

VOMS C API

1.5.0

Generated by Doxygen 1.6.1

Thu Aug 8 12:30:28 2013

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	5
3.1.2.1	name	5
3.1.2.2	qualifier	5
3.1.2.3	value	5
3.2	contactdata Struct Reference	6
3.2.1	Detailed Description	6
3.2.2	Field Documentation	6
3.2.2.1	contact	6
3.2.2.2	host	6
3.2.2.3	nick	6
3.2.2.4	port	6
3.2.2.5	reserved	6
3.2.2.6	version	7
3.2.2.7	vo	7
3.3	data Struct Reference	8
3.3.1	Detailed Description	8
3.3.2	Field Documentation	8
3.3.2.1	cap	8
3.3.2.2	group	8
3.3.2.3	role	8

3.4	voms Struct Reference	9
3.4.1	Detailed Description	9
3.4.2	Field Documentation	9
3.4.2.1	ac	9
3.4.2.2	custom	9
3.4.2.3	datalen	9
3.4.2.4	date1	10
3.4.2.5	date2	10
3.4.2.6	fqan	10
3.4.2.7	holder	10
3.4.2.8	serial	10
3.4.2.9	server	10
3.4.2.10	serverca	10
3.4.2.11	siglen	10
3.4.2.12	signature	10
3.4.2.13	std	11
3.4.2.14	type	11
3.4.2.15	uri	11
3.4.2.16	user	11
3.4.2.17	userca	11
3.4.2.18	version	11
3.4.2.19	voname	11
3.5	vomsdata Struct Reference	12
3.5.1	Detailed Description	12
3.5.2	Field Documentation	12
3.5.2.1	cdir	12
3.5.2.2	data	12
3.5.2.3	extra_data	12
3.5.2.4	extralen	12
3.5.2.5	real	12
3.5.2.6	vdir	13
3.5.2.7	volen	13
3.5.2.8	workvo	13
4	File Documentation	15
4.1	voms_apic.h File Reference	15
4.1.1	Define Documentation	17

4.1.1.1	NOGLOBUS	17
4.1.1.2	RECURSE_CHAIN	17
4.1.1.3	RECURSE_NONE	17
4.1.1.4	TYPE_CUSTOM	18
4.1.1.5	TYPE_NODATA	18
4.1.1.6	TYPE_STD	18
4.1.1.7	VERIFY_CERTLIST	18
4.1.1.8	VERIFY_DATE	18
4.1.1.9	VERIFY_FULL	18
4.1.1.10	VERIFY_ID	18
4.1.1.11	VERIFY_KEY	18
4.1.1.12	VERIFY_NONE	18
4.1.1.13	VERIFY_NOTARGET	18
4.1.1.14	VERIFY_ORDER	19
4.1.1.15	VERIFY_SIGN	19
4.1.1.16	VERR_COMM	19
4.1.1.17	VERR_DIR	19
4.1.1.18	VERR_EXTRAINFO	19
4.1.1.19	VERR_FORMAT	19
4.1.1.20	VERR_IDCHECK	19
4.1.1.21	VERR_MEM	19
4.1.1.22	VERR_NODATA	19
4.1.1.23	VERR_NOEXT	20
4.1.1.24	VERR_NOIDENT	20
4.1.1.25	VERR_NOINIT	20
4.1.1.26	VERR_NONE	20
4.1.1.27	VERR_NOSOCKET	20
4.1.1.28	VERR_NOTAVAIL	20
4.1.1.29	VERR_ORDER	20
4.1.1.30	VERR_PARAM	20
4.1.1.31	VERR_PARSE	20
4.1.1.32	VERR_SERVER	21
4.1.1.33	VERR_SERVERCODE	21
4.1.1.34	VERR_SIGN	21
4.1.1.35	VERR_TIME	21
4.1.1.36	VERR_TYPE	21

4.1.1.37	VERR_VERIFY	21
4.1.2	Typedef Documentation	21
4.1.2.1	gss_cred_id_t	21
4.1.2.2	gss_ctx_id_t	21
4.1.3	Function Documentation	22
4.1.3.1	getMajorVersionNumber	22
4.1.3.2	getMinorVersionNumber	22
4.1.3.3	getPatchVersionNumber	22
4.1.3.4	VOMS_AddTarget	22
4.1.3.5	VOMS_Contact	22
4.1.3.6	VOMS_ContactRaw	22
4.1.3.7	VOMS_Copy	23
4.1.3.8	VOMS_CopyAll	23
4.1.3.9	VOMS_DefaultData	23
4.1.3.10	VOMS_Delete	24
4.1.3.11	VOMS_DeleteContacts	24
4.1.3.12	VOMS_Destroy	24
4.1.3.13	VOMS_Duplicate	24
4.1.3.14	VOMS_ErrorMessage	24
4.1.3.15	VOMS_Export	24
4.1.3.16	VOMS_FindByAlias	25
4.1.3.17	VOMS_FindByVO	25
4.1.3.18	VOMS_FreeTargets	26
4.1.3.19	VOMS_FreeTargetsList	26
4.1.3.20	VOMS_GetAC	26
4.1.3.21	VOMS_GetAttribute	26
4.1.3.22	VOMS_GetAttributeGrantor	26
4.1.3.23	VOMS_GetAttributesNumber	26
4.1.3.24	VOMS_GetAttributeSourceHandle	26
4.1.3.25	VOMS_GetAttributeSourcesNumber	26
4.1.3.26	VOMS_GetTargetsList	26
4.1.3.27	VOMS_Import	26
4.1.3.28	VOMS_Init	26
4.1.3.29	VOMS_ListTargets	27
4.1.3.30	VOMS_LoadCredentials	27
4.1.3.31	VOMS_Ordering	27

4.1.3.32	VOMS_ResetOrder	27
4.1.3.33	VOMS_Retrieve	27
4.1.3.34	VOMS_RetrieveEXT	28
4.1.3.35	VOMS_RetrieveFromAC	28
4.1.3.36	VOMS_RetrieveFromCred	28
4.1.3.37	VOMS_RetrieveFromCtx	29
4.1.3.38	VOMS_RetrieveFromFile	29
4.1.3.39	VOMS_RetrieveFromProxy	29
4.1.3.40	VOMS_SetLifetime	30
4.1.3.41	VOMS_SetTimeout	30
4.1.3.42	VOMS_SetVerificationTime	30
4.1.3.43	VOMS_SetVerificationType	30

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

attribute	5
contactdata	6
data (User's characteristics: can be repeated)	8
voms	9
vomsdata	12

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

voms_apic.h	15
-----------------------------	-------	----

Chapter 3

Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- const char * [name](#)
- const char * [value](#)
- const char * [qualifier](#)

3.1.1 Detailed Description

Definition at line 62 of file voms_apic.h.

3.1.2 Field Documentation

3.1.2.1 const char* attribute::name

Definition at line 63 of file voms_apic.h.

3.1.2.2 const char* attribute::qualifier

Definition at line 65 of file voms_apic.h.

3.1.2.3 const char* attribute::value

Definition at line 64 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.2 contactdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- char * [nick](#)
- char * [host](#)
- char * [contact](#)
- char * [vo](#)
- int [port](#)
- char * [reserved](#)
- int [version](#)

3.2.1 Detailed Description

Definition at line 68 of file voms_apic.h.

3.2.2 Field Documentation

3.2.2.1 char* contactdata::contact

The subject of the server's certificate

Definition at line 73 of file voms_apic.h.

3.2.2.2 char* contactdata::host

The hostname of the server

Definition at line 72 of file voms_apic.h.

3.2.2.3 char* contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the VOMS_FindBy* functions. The alias of the server

Definition at line 71 of file voms_apic.h.

3.2.2.4 int contactdata::port

The port on which the server is listening

Definition at line 75 of file voms_apic.h.

3.2.2.5 char* contactdata::reserved

HANDS OFF!

Definition at line 76 of file voms_apic.h.

3.2.2.6 int contactdata::version

The version of Globus on which this server runs.

Definition at line 77 of file voms_apic.h.

3.2.2.7 char* contactdata::vo

The VO served by this server

Definition at line 74 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.3 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_apic.h>
```

Data Fields

- char * [group](#)
- char * [role](#)
- char * [cap](#)

3.3.1 Detailed Description

User's characteristics: can be repeated. <

Definition at line 56 of file voms_apic.h.

3.3.2 Field Documentation

3.3.2.1 char* data::cap

user's capability

Definition at line 59 of file voms_apic.h.

3.3.2.2 char* data::group

user's group

Definition at line 57 of file voms_apic.h.

3.3.2.3 char* data::role

user's role

Definition at line 58 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.4 voms Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- int [siglen](#)
- char * [signature](#)
- char * [user](#)
- char * [userca](#)
- char * [server](#)
- char * [serverca](#)
- char * [voname](#)
- char * [uri](#)
- char * [date1](#)
- char * [date2](#)
- int [type](#)
- struct [data](#) ** [std](#)
- char * [custom](#)
- int [datalen](#)
- int [version](#)
- char ** [fqan](#)
- char * [serial](#)
- AC * [ac](#)
- X509 * [holder](#)

3.4.1 Detailed Description

Definition at line 88 of file `voms_apic.h`.

3.4.2 Field Documentation

3.4.2.1 AC* voms::ac

Definition at line 108 of file `voms_apic.h`.

3.4.2.2 char* voms::custom

The [data](#) returned by an S command

Definition at line 101 of file `voms_apic.h`.

3.4.2.3 int voms::datalen

Definition at line 102 of file `voms_apic.h`.

3.4.2.4 char* voms::date1

Beginning of validity of the user info

Definition at line 97 of file voms_apic.h.

3.4.2.5 char* voms::date2

End of validity of the user info

Definition at line 98 of file voms_apic.h.

3.4.2.6 char voms::fqan**

User's attributes in compact format

Definition at line 104 of file voms_apic.h.

3.4.2.7 X509* voms::holder

Definition at line 109 of file voms_apic.h.

3.4.2.8 char* voms::serial

Serial number. Only significant if coming from AC. Null otherwise

Definition at line 105 of file voms_apic.h.

3.4.2.9 char* voms::server

The VOMS server DN, as from its certificate

Definition at line 93 of file voms_apic.h.

3.4.2.10 char* voms::serverca

The CA which signed the VOMS certificate

Definition at line 94 of file voms_apic.h.

3.4.2.11 int voms::siglen

The length of the VOMS server signature

Definition at line 89 of file voms_apic.h.

3.4.2.12 char* voms::signature

The VOMS server signature

Definition at line 90 of file voms_apic.h.

3.4.2.13 struct data voms::std [read]**

User's characteristics

Definition at line 100 of file voms_apic.h.

3.4.2.14 int voms::type

The type of [data](#) returned

Definition at line 99 of file voms_apic.h.

3.4.2.15 char* voms::uri

The URI of the VOMS server

Definition at line 96 of file voms_apic.h.

3.4.2.16 char* voms::user

The user's DN, as from his certificate

Definition at line 91 of file voms_apic.h.

3.4.2.17 char* voms::userca

The CA which signed the user's certificate

Definition at line 92 of file voms_apic.h.

3.4.2.18 int voms::version

Definition at line 103 of file voms_apic.h.

3.4.2.19 char* voms::vname

The name of the VO to which the VOMS belongs

Definition at line 95 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.5 vomsdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- char * [cdir](#)
- char * [vdir](#)
- struct [voms](#) ** [data](#)
- char * [workvo](#)
- char * [extra_data](#)
- int [volen](#)
- int [extralen](#)
- struct [vomsdata](#) * [real](#)

3.5.1 Detailed Description

Definition at line 152 of file voms_apic.h.

3.5.2 Field Documentation

3.5.2.1 char* vomsdata::cdir

Definition at line 153 of file voms_apic.h.

3.5.2.2 struct voms** vomsdata::data [read]

User's info, as in the certificate extension. It may contain [data](#) gathered from more than one VOMS server, Definition at line 155 of file voms_apic.h.

3.5.2.3 char* vomsdata::extra_data

The [data](#) specified by the user with the --include switch. Note that this field doesn't contain the result of a request to the VOMS server, but instead [data](#) specified by the user. The reason for the introduction of this extension is to let a user include important [data](#) into his proxy certificate, like, for example, a kerberos ticket

Definition at line 160 of file voms_apic.h.

3.5.2.4 int vomsdata::extralen

Definition at line 170 of file voms_apic.h.

3.5.2.5 struct vomsdata* vomsdata::real [read]

Definition at line 172 of file voms_apic.h.

3.5.2.6 char* vomsdata::vdir

Definition at line 154 of file voms_apic.h.

3.5.2.7 int vomsdata::volen

Definition at line 169 of file voms_apic.h.

3.5.2.8 char* vomsdata::workvo

The value of the -vo option of the voms-proxy-init command

Definition at line 158 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

Chapter 4

File Documentation

4.1 voms_apic.h File Reference

```
#include <openssl/x509.h>
#include <time.h>
#include "newformat.h"
```

Data Structures

- struct [data](#)
User's characteristics: can be repeated.
- struct [attribute](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)

Defines

- #define [NOGLOBUS](#)
- #define [TYPE_NODATA](#) 0
- #define [TYPE_STD](#) 1
- #define [TYPE_CUSTOM](#) 2
- #define [RECURSE_CHAIN](#) 0
- #define [RECURSE_NONE](#) 1
- #define [VERIFY_FULL](#) 0xffffffff
- #define [VERIFY_NONE](#) 0x00000000
- #define [VERIFY_DATE](#) 0x00000001
- #define [VERIFY_NOTARGET](#) 0x00000002
- #define [VERIFY_KEY](#) 0x00000004
- #define [VERIFY_SIGN](#) 0x00000008
- #define [VERIFY_ORDER](#) 0x00000010
- #define [VERIFY_ID](#) 0x00000020
- #define [VERIFY_CERTLIST](#) 0x00000040

- #define [VERR_NONE](#) 0
Error codes.
- #define [VERR_NOSOCKET](#) 1
- #define [VERR_NOIDENT](#) 2
- #define [VERR_COMM](#) 3
- #define [VERR_PARAM](#) 4
- #define [VERR_NOEXT](#) 5
- #define [VERR_NOINIT](#) 6
- #define [VERR_TIME](#) 7
- #define [VERR_IDCHECK](#) 8
- #define [VERR_EXTRAINFO](#) 9
- #define [VERR_FORMAT](#) 10
- #define [VERR_NODATA](#) 11
- #define [VERR_PARSE](#) 12
- #define [VERR_DIR](#) 13
- #define [VERR_SIGN](#) 14
- #define [VERR_SERVER](#) 15
- #define [VERR_MEM](#) 16
- #define [VERR_VERIFY](#) 17
- #define [VERR_TYPE](#) 18
- #define [VERR_ORDER](#) 19
- #define [VERR_SERVERCODE](#) 20
- #define [VERR_NOTAVAIL](#) 21

Typedefs

- typedef void * [gss_cred_id_t](#)
- typedef void * [gss_ctx_id_t](#)

Functions

- struct [contactdata](#) ** [VOMS_FindByAlias](#) (struct [vomsdata](#) *vd, char *alias, char *system, char *user, int *error)
- struct [contactdata](#) ** [VOMS_FindByVO](#) (struct [vomsdata](#) *vd, char *vo, char *system, char *user, int *error)
- void [VOMS_DeleteContacts](#) (struct [contactdata](#) **list)
- struct [vomsdata](#) * [VOMS_Init](#) (char *voms, char *cert)
- struct [voms](#) * [VOMS_Copy](#) (struct [voms](#) *v, int *error)
- struct [vomsdata](#) * [VOMS_CopyAll](#) (struct [vomsdata](#) *vd, int *error)
- void [VOMS_Delete](#) (struct [voms](#) *v)
- int [VOMS_AddTarget](#) (struct [vomsdata](#) *vd, char *target, int *error)
- void [VOMS_FreeTargets](#) (struct [vomsdata](#) *vd, int *error)
- char * [VOMS_ListTargets](#) (struct [vomsdata](#) *vd, int *error)
- int [VOMS_SetVerificationType](#) (int type, struct [vomsdata](#) *vd, int *error)
- int [VOMS_SetLifetime](#) (int length, struct [vomsdata](#) *vd, int *error)
- void [VOMS_Destroy](#) (struct [vomsdata](#) *vd)
- int [VOMS_ResetOrder](#) (struct [vomsdata](#) *vd, int *error)
- int [VOMS_Ordering](#) (char *order, struct [vomsdata](#) *vd, int *error)

- int [VOMS_Contact](#) (char *hostname, int port, char *servsubject, char *command, struct [vomsdata](#) *vd, int *error)
- int [VOMS_ContactRaw](#) (char *hostname, int port, char *servsubject, char *command, void **data, int *datalen, int *version, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Retrieve](#) (X509 *cert, STACK_OF(X509)*chain, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Import](#) (char *buffer, int buflen, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Export](#) (char **buffer, int *buflen, struct [vomsdata](#) *vd, int *error)
- struct [voms](#) * [VOMS_DefaultData](#) (struct [vomsdata](#) *vd, int *error)
- char * [VOMS_ErrorMessage](#) (struct [vomsdata](#) *vd, int error, char *buffer, int len)
- int [VOMS_RetrieveEXT](#) (X509_EXTENSION *ext, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromCred](#) (gss_cred_id_t cred, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromFile](#) (FILE *file, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromCtx](#) (gss_ctx_id_t ctx, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromProxy](#) (int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromAC](#) (AC *ac, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributeSourcesNumber](#) (struct [voms](#) *v, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributeSourceHandle](#) (struct [voms](#) *v, int num, struct [vomsdata](#) *vd, int *error)
- const char * [VOMS_GetAttributeGrantor](#) (struct [voms](#) *v, int handle, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributesNumber](#) (struct [voms](#) *v, int handle, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttribute](#) (struct [voms](#) *v, int handle, int num, struct [attribute](#) *at, struct [vomsdata](#) *vd, int *error)
- struct [vomsdata](#) * [VOMS_Duplicate](#) (struct [vomsdata](#) *vd)
- AC * [VOMS_GetAC](#) (struct [voms](#) *v)
- int [getMajorVersionNumber](#) (void)
- int [getMinorVersionNumber](#) (void)
- int [getPatchVersionNumber](#) (void)
- int [VOMS_SetVerificationTime](#) (time_t verificationtime, struct [vomsdata](#) *vd, int *error)
- char ** [VOMS_GetTargetsList](#) (struct [voms](#) *v, struct [vomsdata](#) *vd, int *error)
- void [VOMS_FreeTargetsList](#) (char **)
- int [VOMS_SetTimeout](#) (int t, struct [vomsdata](#) *vd, int *error)
- int [VOMS_LoadCredentials](#) (X509 *cert, EVP_PKEY *pkey, STACK_OF(X509)*chain, struct [vomsdata](#) *vd, int *error)

4.1.1 Define Documentation

4.1.1.1 #define NOGLOBUS

Definition at line 33 of file voms_apic.h.

4.1.1.2 #define RECURSE_CHAIN 0

Definition at line 113 of file voms_apic.h.

4.1.1.3 #define RECURSE_NONE 1

Definition at line 114 of file voms_apic.h.

4.1.1.4 #define TYPE_CUSTOM 2

result of an S command

Definition at line 85 of file voms_apic.h.

4.1.1.5 #define TYPE_NODATA 0

no [data](#)

Definition at line 83 of file voms_apic.h.

4.1.1.6 #define TYPE_STD 1

group, role, capability triplet

Definition at line 84 of file voms_apic.h.

4.1.1.7 #define VERIFY_CERTLIST 0x00000040

Definition at line 124 of file voms_apic.h.

4.1.1.8 #define VERIFY_DATE 0x00000001

Definition at line 118 of file voms_apic.h.

4.1.1.9 #define VERIFY_FULL 0xffffffff

Definition at line 116 of file voms_apic.h.

4.1.1.10 #define VERIFY_ID 0x00000020

Definition at line 123 of file voms_apic.h.

4.1.1.11 #define VERIFY_KEY 0x00000004

Definition at line 120 of file voms_apic.h.

4.1.1.12 #define VERIFY_NONE 0x00000000

Definition at line 117 of file voms_apic.h.

4.1.1.13 #define VERIFY_NOTARGET 0x00000002

Definition at line 119 of file voms_apic.h.

4.1.1.14 #define VERIFY_ORDER 0x00000010

Definition at line 122 of file voms_apic.h.

4.1.1.15 #define VERIFY_SIGN 0x00000008

Definition at line 121 of file voms_apic.h.

4.1.1.16 #define VERR_COMM 3

Server problem

Definition at line 131 of file voms_apic.h.

4.1.1.17 #define VERR_DIR 13

Directory error

Definition at line 142 of file voms_apic.h.

4.1.1.18 #define VERR_EXTRAINFO 9

VO name and URI missing

Definition at line 138 of file voms_apic.h.

4.1.1.19 #define VERR_FORMAT 10

Wrong [data](#) format

Definition at line 139 of file voms_apic.h.

4.1.1.20 #define VERR_IDCHECK 8

User [data](#) in extension different from the real ones

Definition at line 136 of file voms_apic.h.

4.1.1.21 #define VERR_MEM 16

Memory problems

Definition at line 145 of file voms_apic.h.

4.1.1.22 #define VERR_NODATA 11

Empty extension

Definition at line 140 of file voms_apic.h.

4.1.1.23 #define VERR_NOEXT 5

VOMS extension missing

Definition at line 133 of file voms_apic.h.

4.1.1.24 #define VERR_NOIDENT 2

Cannot identify itself (certificate problem)

Definition at line 130 of file voms_apic.h.

4.1.1.25 #define VERR_NOINIT 6

Initialization error

Definition at line 134 of file voms_apic.h.

4.1.1.26 #define VERR_NONE 0

Error codes.

Definition at line 128 of file voms_apic.h.

4.1.1.27 #define VERR_NOSOCKET 1

Socket problem

Definition at line 129 of file voms_apic.h.

4.1.1.28 #define VERR_NOTAVAIL 21

Method not available

Definition at line 150 of file voms_apic.h.

4.1.1.29 #define VERR_ORDER 19

Ordering different than required

Definition at line 148 of file voms_apic.h.

4.1.1.30 #define VERR_PARAM 4

Wrong parameters

Definition at line 132 of file voms_apic.h.

4.1.1.31 #define VERR_PARSE 12

Parse error

Definition at line 141 of file voms_apic.h.

4.1.1.32 #define VERR_SERVER 15

Unidentifiable VOMS server

Definition at line 144 of file voms_apic.h.

4.1.1.33 #define VERR_SERVERCODE 20

Error from the server

Definition at line 149 of file voms_apic.h.

4.1.1.34 #define VERR_SIGN 14

Signature error

Definition at line 143 of file voms_apic.h.

4.1.1.35 #define VERR_TIME 7

Error in time checking

Definition at line 135 of file voms_apic.h.

4.1.1.36 #define VERR_TYPE 18

Returned [data](#) of unknown type

Definition at line 147 of file voms_apic.h.

4.1.1.37 #define VERR_VERIFY 17

Generic verification error

Definition at line 146 of file voms_apic.h.

4.1.2 Typedef Documentation**4.1.2.1 typedef void* gss_cred_id_t**

Definition at line 42 of file voms_apic.h.

4.1.2.2 typedef void* gss_ctx_id_t

Definition at line 43 of file voms_apic.h.

4.1.3 Function Documentation

4.1.3.1 `int getMajorVersionNumber (void)`

4.1.3.2 `int getMinorVersionNumber (void)`

4.1.3.3 `int getPatchVersionNumber (void)`

4.1.3.4 `int VOMS_AddTarget (struct vomsdata * vd, char * target, int * error)`

Adds a target to the AC.

Parameters:

vd The [vomsdata](#) structure.

target The target to add. It should be a FQDN.

error RETURN PARAMETER: qualifies the error message.

Returns:

failure (0) or success (<>0)

4.1.3.5 `int VOMS_Contact (char * hostname, int port, char * servsubject, char * command, struct vomsdata * vd, int * error)`

Contacts a VOMS server to get a certificate

It is the equivalent of the `voms_proxy_init` command, but without the `--include` functionality.

Parameters:

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command Command

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.6 `int VOMS_ContactRaw (char * hostname, int port, char * servsubject, char * command, void ** data, int * datalen, int * version, struct vomsdata * vd, int * error)`

The same as `VOMS_Contact`, except that instead of starting the verification process, the [data](#) is returned as is in the

Parameters:

[data](#) and

datalen fields.

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command the command sent to the server

version is the version number of the [data](#).

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.7 struct voms* VOMS_Copy (struct voms * *v*, int * *error*) [read]

Copies a [voms](#) structure. N.B: This is the ONLY way to correctly initialize a [voms](#) structure as a copy of another [voms](#) structure.

Parameters:

v The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL (error) or the new [voms](#) structure.

4.1.3.8 struct vomsdata* VOMS_CopyAll (struct vomsdata * *vd*, int * *error*) [read]

Copies a [vomsdata](#) structure. N.B: This is the ONLY way to correctly initialize a [vomsdata](#) structure as a copy of another [vomsdata](#) structure.

Parameters:

vd The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL (error) or the new [vomsdata](#) structure.

4.1.3.9 struct voms* VOMS_DefaultData (struct vomsdata * *vd*, int * *error*) [read]

Gets the default attributes from a [vomsdata](#) structure.

Parameters:

vd the [vomsdata](#) structure to analyze

error RETURN PARAMETER: Qualifies the error message

Returns:

a pointer to the relevant [voms](#) structure. DO NOT modify the fields.

4.1.3.10 void VOMS_Delete (struct voms * *v*)

Deletes a [voms](#) structure

Parameters:

v Pointer to the structure to delete.

4.1.3.11 void VOMS_DeleteContacts (struct contactdata ** *list*)

Frees a [contactdata](#) vector.

Parameters:

list The vector to free.

Returns:

NONE

4.1.3.12 void VOMS_Destroy (struct vomsdata * *vd*)

Destroys a proper [vomsdata](#) structure /param *vd* The structure to deallocate.

4.1.3.13 struct vomsdata* VOMS_Duplicate (struct vomsdata * *vd*) [**read**]

4.1.3.14 char* VOMS_ErrorMessage (struct vomsdata * *vd*, int *error*, char * *buffer*, int *len*)

Gets a textual description of the error.

Parameters:

vd The [vomsdata](#) structure to analyze

error The error returned by the last function

buffer A pointer to a buffer where the error message will be written. If NULL, then memory is allocated by the function, and will have to be free()ed by the caller.

len The length of the memory pointed to by the buffer parameter.

Returns:

A pointer to the error message.

4.1.3.15 int VOMS_Export (char ** *buffer*, int * *buflen*, struct vomsdata * *vd*, int * *error*)

Converts [data](#) into a test format

Parameters:

buffer OUTPUT PARAMETER contains the converted [data](#)

buflen OUTPUT PARAMETER contains the length of buffer

vd contains the [data](#) to convert

error RETURN PARAMETER Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.16 struct contactdata VOMS_FindByAlias (struct vomsdata * *vd*, char * *alias*, char * *system*, char * *user*, int * *error*) [read]**

Gets a list of VOMS servers which share an alias.

Parameters:

vd The correctly initialized [vomsdata](#) structured.

alias The alias to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/edc/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL, or a NULL-terminated vector of [contactdata](#) structures. The only supported way to free this array is via the VOMS_DeleteContacts function. Note also that the order in which the servers are returned is unspecified.

4.1.3.17 struct contactdata VOMS_FindByVO (struct vomsdata * *vd*, char * *vo*, char * *system*, char * *user*, int * *error*) [read]**

Gets a list of VOMS servers which serve the same VO.

Parameters:

vd The correctly initialized [vomsdata](#) structured.

vo The VO to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/edc/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL, or a NULL-terminated vector of [contactdata](#) structures. The only supported way to free this array is via the VOMS_DeleteContacts function. Note also that the order in which the servers are returned is unspecified.

4.1.3.18 void VOMS_FreeTargets (struct vomsdata * *vd*, int * *error*)

Delete the targets from the AC.

Parameters:

vd The [vomsdata](#) structure.

error RETURN PARAMETER: qualifies the error message.

4.1.3.19 void VOMS_FreeTargetsList (char **)**4.1.3.20 AC* VOMS_GetAC (struct voms * *v*)****4.1.3.21 int VOMS_GetAttribute (struct voms * *v*, int *handle*, int *num*, struct attribute * *at*, struct vomsdata * *vd*, int * *error*)****4.1.3.22 const char* VOMS_GetAttributeGrantor (struct voms * *v*, int *handle*, struct vomsdata * *vd*, int * *error*)****4.1.3.23 int VOMS_GetAttributesNumber (struct voms * *v*, int *handle*, struct vomsdata * *vd*, int * *error*)****4.1.3.24 int VOMS_GetAttributeSourceHandle (struct voms * *v*, int *num*, struct vomsdata * *vd*, int * *error*)****4.1.3.25 int VOMS_GetAttributeSourcesNumber (struct voms * *v*, struct vomsdata * *vd*, int * *error*)****4.1.3.26 char** VOMS_GetTargetsList (struct voms * *v*, struct vomsdata * *vd*, int * *error*)****4.1.3.27 int VOMS_Import (char * *buffer*, int *buflen*, struct vomsdata * *vd*, int * *error*)**

Converts [data](#) from the format used for inclusion into a certificate to the internal format

The function does verify the [data](#).

Parameters:

buffer contains the [data](#) to be converted

buflen contains the length of buffer

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.28 struct vomsdata* VOMS_Init (char * *voms*, char * *cert*) [read]

Initializes a [vomsdata](#) structure for use by the other functions. N.B: This is the ONLY way to correctly initialize a [vomsdata](#) structure. It is also forbidden to directly take the sizeof() of this structure.

Parameters:

voms The directory which contains the certificates of the VOMS servers

cert The directory which contains the CA certificates

If voms_dir is empty, the value of the environment variable X509_VOMS_DIR is taken

If cert_dir is empty, the value of the environment variable X509_CERT_DIR is taken

Returns:

NULL for failure, or a pointer to a properly initialized structure.

4.1.3.29 `char* VOMS_ListTargets (struct vomsdata * vd, int * error)`

4.1.3.30 `int VOMS_LoadCredentials (X509 * cert, EVP_PKEY * pkey, STACK_OF(X509)* chain, struct vomsdata * vd, int * error)`

4.1.3.31 `int VOMS_Ordering (char * order, struct vomsdata * vd, int * error)`

Further specified the order of the returned attributes. Please do note that calls are cumulative unless `VOMS_ResetOrder()` is called.

Parameters:

order the group:role [attribute](#).

vd RETURN PARAMETER: contains the modified [data](#).

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.32 `int VOMS_ResetOrder (struct vomsdata * vd, int * error)`

Unsets the return order of the attributes.

Parameters:

vd RETURN PARAMETER: contains the modified [data](#).

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.33 `int VOMS_Retrieve (X509 * cert, STACK_OF(X509)* chain, int how, struct vomsdata * vd, int * error)`

Extracts the VOMS extension from an X.509 certificate.

The function doesn't check the validity of the certificates, but it does check the content of the user [data](#).

Parameters:

cert The certificate with the VOMS extensions
chain The chain of the validation certificates (only the intermediate ones)
how Recursion type
vd RETURN PARAMETER: contains the [data](#) returned by the connection
error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.34 int VOMS_RetrieveEXT (X509_EXTENSION * *ext*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given extension

Parameters:

ext The extension to parse.
vd RETURN PARAMETER: contains the [data](#) returned by the connection
error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.35 int VOMS_RetrieveFromAC (AC * *ac*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from an existing globus proxy

Parameters:

ac AC from which to get the credentials
vd RETURN PARAMETER: contains the [data](#) returned by the connection
error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.36 int VOMS_RetrieveFromCred (gss_cred_id_t *cred*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus credential

Parameters:

cred The credential from which to retrieve the certificate.
how Recursion type
vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.37 int VOMS_RetrieveFromCtx (gss_ctx_id_t *ctx*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus context

Parameters:

ctx The context from which to retrieve the certificate.

how Recursion type

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.38 int VOMS_RetrieveFromFile (FILE * *file*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus credential

Parameters:

file The file from which to retrieve the certificate.

how Recursion type

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.39 int VOMS_RetrieveFromProxy (int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from an existing globus proxy

Parameters:

how Recursion type

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.40 int VOMS_SetLifetime (int *length*, struct vomsdata * *vd*, int * *error*)

Set requested lifetime for [VOMS_Contact\(\)](#) calls.

Parameters:

length Lifetime requested.

vd RETURN PARAMETER: contains the modified [data](#).

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.3.41 int VOMS_SetTimeout (int *t*, struct vomsdata * *vd*, int * *error*)**4.1.3.42 int VOMS_SetVerificationTime (time_t *verificationtime*, struct vomsdata * *vd*, int * *error*)****4.1.3.43 int VOMS_SetVerificationType (int *type*, struct vomsdata * *vd*, int * *error*)**

Index

- ac
 - voms, [9](#)
- attribute, [5](#)
 - name, [5](#)
 - qualifier, [5](#)
 - value, [5](#)
- cap
 - data, [8](#)
- cdir
 - vomsdata, [12](#)
- contact
 - contactdata, [6](#)
- contactdata, [6](#)
 - contact, [6](#)
 - host, [6](#)
 - nick, [6](#)
 - port, [6](#)
 - reserved, [6](#)
 - version, [6](#)
 - vo, [7](#)
- custom
 - voms, [9](#)
- data, [8](#)
 - cap, [8](#)
 - group, [8](#)
 - role, [8](#)
 - vomsdata, [12](#)
- datalen
 - voms, [9](#)
- date1
 - voms, [9](#)
- date2
 - voms, [10](#)
- extra_data
 - vomsdata, [12](#)
- extralen
 - vomsdata, [12](#)
- fqan
 - voms, [10](#)
- getMajorVersionNumber
 - voms_apic.h, [22](#)
- getMinorVersionNumber
 - voms_apic.h, [22](#)
- getPatchVersionNumber
 - voms_apic.h, [22](#)
- group
 - data, [8](#)
- gss_cred_id_t
 - voms_apic.h, [21](#)
- gss_ctx_id_t
 - voms_apic.h, [21](#)
- holder
 - voms, [10](#)
- host
 - contactdata, [6](#)
- name
 - attribute, [5](#)
- nick
 - contactdata, [6](#)
- NOGLOBUS
 - voms_apic.h, [17](#)
- port
 - contactdata, [6](#)
- qualifier
 - attribute, [5](#)
- real
 - vomsdata, [12](#)
- RECURSE_CHAIN
 - voms_apic.h, [17](#)
- RECURSE_NONE
 - voms_apic.h, [17](#)
- reserved
 - contactdata, [6](#)
- role
 - data, [8](#)
- serial
 - voms, [10](#)
- server
 - voms, [10](#)
- serverca
 - voms, [10](#)

- siglen
 - voms, 10
- signature
 - voms, 10
- std
 - voms, 10
- type
 - voms, 11
- TYPE_CUSTOM
 - voms_apic.h, 17
- TYPE_NODATA
 - voms_apic.h, 18
- TYPE_STD
 - voms_apic.h, 18
- uri
 - voms, 11
- user
 - voms, 11
- userca
 - voms, 11
- value
 - attribute, 5
- vdir
 - vomsdata, 12
- VERIFY_CERTLIST
 - voms_apic.h, 18
- VERIFY_DATE
 - voms_apic.h, 18
- VERIFY_FULL
 - voms_apic.h, 18
- VERIFY_ID
 - voms_apic.h, 18
- VERIFY_KEY
 - voms_apic.h, 18
- VERIFY_NONE
 - voms_apic.h, 18
- VERIFY_NOTARGET
 - voms_apic.h, 18
- VERIFY_ORDER
 - voms_apic.h, 18
- VERIFY_SIGN
 - voms_apic.h, 19
- VERR_COMM
 - voms_apic.h, 19
- VERR_DIR
 - voms_apic.h, 19
- VERR_EXTRINFO
 - voms_apic.h, 19
- VERR_FORMAT
 - voms_apic.h, 19
- VERR_IDCHECK
 - voms_apic.h, 19
- VERR_MEM
 - voms_apic.h, 19
- VERR_NODATA
 - voms_apic.h, 19
- VERR_NOEXT
 - voms_apic.h, 19
- VERR_NOIDENT
 - voms_apic.h, 20
- VERR_NOINIT
 - voms_apic.h, 20
- VERR_NONE
 - voms_apic.h, 20
- VERR_NOSOCKET
 - voms_apic.h, 20
- VERR_NOTAVAIL
 - voms_apic.h, 20
- VERR_ORDER
 - voms_apic.h, 20
- VERR_PARAM
 - voms_apic.h, 20
- VERR_PARSE
 - voms_apic.h, 20
- VERR_SERVER
 - voms_apic.h, 20
- VERR_SERVERCODE
 - voms_apic.h, 21
- VERR_SIGN
 - voms_apic.h, 21
- VERR_TIME
 - voms_apic.h, 21
- VERR_TYPE
 - voms_apic.h, 21
- VERR_VERIFY
 - voms_apic.h, 21
- version
 - contactdata, 6
 - voms, 11
- vo
 - contactdata, 7
- volen
 - vomsdata, 13
- voms, 9
 - ac, 9
 - custom, 9
 - datalen, 9
 - date1, 9
 - date2, 10
 - fqan, 10
 - holder, 10
 - serial, 10
 - server, 10
 - serverca, 10
 - siglen, 10

- signature, [10](#)
- std, [10](#)
- type, [11](#)
- uri, [11](#)
- user, [11](#)
- userca, [11](#)
- version, [11](#)
- voname, [11](#)
- VOMS_AddTarget
 - voms_apic.h, [22](#)
- voms_apic.h, [15](#)
 - getMajorVersionNumber, [22](#)
 - getMinorVersionNumber, [22](#)
 - getPatchVersionNumber, [22](#)
 - gss_cred_id_t, [21](#)
 - gss_ctx_id_t, [21](#)
 - NOGLOBUS, [17](#)
 - RECURSE_CHAIN, [17](#)
 - RECURSE_NONE, [17](#)
 - TYPE_CUSTOM, [17](#)
 - TYPE_NODATA, [18](#)
 - TYPE_STD, [18](#)
 - VERIFY_CERTLIST, [18](#)
 - VERIFY_DATE, [18](#)
 - VERIFY_FULL, [18](#)
 - VERIFY_ID, [18](#)
 - VERIFY_KEY, [18](#)
 - VERIFY_NONE, [18](#)
 - VERIFY_NOTARGET, [18](#)
 - VERIFY_ORDER, [18](#)
 - VERIFY_SIGN, [19](#)
 - VERR_COMM, [19](#)
 - VERR_DIR, [19](#)
 - VERR_EXTRINFO, [19](#)
 - VERR_FORMAT, [19](#)
 - VERR_IDCHECK, [19](#)
 - VERR_MEM, [19](#)
 - VERR_NODATA, [19](#)
 - VERR_NOEXT, [19](#)
 - VERR_NOIDENT, [20](#)
 - VERR_NOINIT, [20](#)
 - VERR_NONE, [20](#)
 - VERR_NOSOCKET, [20](#)
 - VERR_NOTAVAIL, [20](#)
 - VERR_ORDER, [20](#)
 - VERR_PARAM, [20](#)
 - VERR_PARSE, [20](#)
 - VERR_SERVER, [20](#)
 - VERR_SERVERCODE, [21](#)
 - VERR_SIGN, [21](#)
 - VERR_TIME, [21](#)
 - VERR_TYPE, [21](#)
 - VERR_VERIFY, [21](#)
 - VOMS_AddTarget, [22](#)
 - VOMS_Contact, [22](#)
 - VOMS_ContactRaw, [22](#)
 - VOMS_Copy, [23](#)
 - VOMS_CopyAll, [23](#)
 - VOMS_DefaultData, [23](#)
 - VOMS_Delete, [23](#)
 - VOMS_DeleteContacts, [24](#)
 - VOMS_Destroy, [24](#)
 - VOMS_Duplicate, [24](#)
 - VOMS_ErrorMessage, [24](#)
 - VOMS_Export, [24](#)
 - VOMS_FindByAlias, [25](#)
 - VOMS_FindByVO, [25](#)
 - VOMS_FreeTargets, [25](#)
 - VOMS_FreeTargetsList, [26](#)
 - VOMS_GetAC, [26](#)
 - VOMS_GetAttribute, [26](#)
 - VOMS_GetAttributeGrantor, [26](#)
 - VOMS_GetAttributesNumber, [26](#)
 - VOMS_GetAttributeSourceHandle, [26](#)
 - VOMS_GetAttributeSourcesNumber, [26](#)
 - VOMS_GetTargetsList, [26](#)
 - VOMS_Import, [26](#)
 - VOMS_Init, [26](#)
 - VOMS_ListTargets, [27](#)
 - VOMS_LoadCredentials, [27](#)
 - VOMS_Ordering, [27](#)
 - VOMS_ResetOrder, [27](#)
 - VOMS_Retrieve, [27](#)
 - VOMS_RetrieveEXT, [28](#)
 - VOMS_RetrieveFromAC, [28](#)
 - VOMS_RetrieveFromCred, [28](#)
 - VOMS_RetrieveFromCtx, [29](#)
 - VOMS_RetrieveFromFile, [29](#)
 - VOMS_RetrieveFromProxy, [29](#)
 - VOMS_SetLifetime, [29](#)
 - VOMS_SetTimeout, [30](#)
 - VOMS_SetVerificationTime, [30](#)
 - VOMS_SetVerificationType, [30](#)
 - VOMS_Contact
 - voms_apic.h, [22](#)
 - VOMS_ContactRaw
 - voms_apic.h, [22](#)
 - VOMS_Copy
 - voms_apic.h, [23](#)
 - VOMS_CopyAll
 - voms_apic.h, [23](#)
 - VOMS_DefaultData
 - voms_apic.h, [23](#)
 - VOMS_Delete
 - voms_apic.h, [23](#)
 - VOMS_DeleteContacts
 - voms_apic.h, [24](#)
 - VOMS_Destroy

- voms_apic.h, [24](#)
- VOMS_Duplicate
 - voms_apic.h, [24](#)
- VOMS_ErrorMessage
 - voms_apic.h, [24](#)
- VOMS_Export
 - voms_apic.h, [24](#)
- VOMS_FindByAlias
 - voms_apic.h, [25](#)
- VOMS_FindByVO
 - voms_apic.h, [25](#)
- VOMS_FreeTargets
 - voms_apic.h, [25](#)
- VOMS_FreeTargetsList
 - voms_apic.h, [26](#)
- VOMS_GetAC
 - voms_apic.h, [26](#)
- VOMS_GetAttribute
 - voms_apic.h, [26](#)
- VOMS_GetAttributeGrantor
 - voms_apic.h, [26](#)
- VOMS_GetAttributesNumber
 - voms_apic.h, [26](#)
- VOMS_GetAttributeSourceHandle
 - voms_apic.h, [26](#)
- VOMS_GetAttributeSourcesNumber
 - voms_apic.h, [26](#)
- VOMS_GetTargetsList
 - voms_apic.h, [26](#)
- VOMS_Import
 - voms_apic.h, [26](#)
- VOMS_Init
 - voms_apic.h, [26](#)
- VOMS_ListTargets
 - voms_apic.h, [27](#)
- VOMS_LoadCredentials
 - voms_apic.h, [27](#)
- VOMS_Ordering
 - voms_apic.h, [27](#)
- VOMS_ResetOrder
 - voms_apic.h, [27](#)
- VOMS_Retrieve
 - voms_apic.h, [27](#)
- VOMS_RetrieveEXT
 - voms_apic.h, [28](#)
- VOMS_RetrieveFromAC
 - voms_apic.h, [28](#)
- VOMS_RetrieveFromCred
 - voms_apic.h, [28](#)
- VOMS_RetrieveFromCtx
 - voms_apic.h, [29](#)
- VOMS_RetrieveFromFile
 - voms_apic.h, [29](#)
- VOMS_RetrieveFromProxy
 - voms_apic.h, [29](#)
- VOMS_SetLifetime
 - voms_apic.h, [29](#)
- VOMS_SetTimeout
 - voms_apic.h, [30](#)
- VOMS_SetVerificationTime
 - voms_apic.h, [30](#)
- VOMS_SetVerificationType
 - voms_apic.h, [30](#)
- vomsdata, [12](#)
 - cdir, [12](#)
 - data, [12](#)
 - extra_data, [12](#)
 - extralen, [12](#)
 - real, [12](#)
 - vdir, [12](#)
 - volen, [13](#)
 - workvo, [13](#)
- voname
 - voms, [11](#)
- workvo
 - vomsdata, [13](#)