

globus gsi cert utils

8.3

Generated by Doxygen 1.6.1

Tue May 1 16:43:26 2012

Contents

1	Globus GSI Certificate Handling Utilities	1
2	Module Index	1
2.1	Modules	1
3	Module Documentation	1
3.1	Activation	1
3.1.1	Detailed Description	2
3.1.2	Define Documentation	2
3.2	Cert Utils Functions	2
3.2.1	Detailed Description	2
3.2.2	Function Documentation	2
3.3	Cert Utils Constants	3
3.3.1	Typedef Documentation	4
3.3.2	Enumeration Type Documentation	4

1 Globus GSI Certificate Handling Utilities

The Globus GSI Certificate Handling Utilities library. This library contains helper functions for dealing with certificates.

- **Activation** (p. 1)
- **Cert Utils Functions** (p. 2)
- **Cert Utils Constants** (p. 3)

2 Module Index

2.1 Modules

Here is a list of all modules:

Activation	1
Cert Utils Functions	2
Cert Utils Constants	3

3 Module Documentation

3.1 Activation

Globus GSI Cert Utils uses standard Globus module activation and deactivation.

Defines

- `#define GLOBUS_GSI_CERT_UTILS_MODULE`

3.1.1 Detailed Description

Globus GSI Cert Utils uses standard Globus module activation and deactivation. Before any Globus GSI Cert Utils functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus GSI Credential was successfully initialized, and you are therefore allowed to subsequently call Globus GSI Cert Utils functions. Otherwise, an error code is returned, and Globus GSI Cert Utils functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI Cert Utils, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function should be called once for each time Globus GSI Cert Utils was activated.

3.1.2 Define Documentation

3.1.2.1 `#define GLOBUS_GSI_CERT_UTILS_MODULE`

Module descriptor.

3.2 Cert Utils Functions

A generic set of utility functions for manipulating OpenSSL objects, such as X509 certificates.

Functions

- `globus_result_t globus_gsi_cert_utils_get_eec (STACK_OF(X509)*cert_chain, X509 **eec)`
- `globus_result_t globus_gsi_cert_utils_get_identity_cert (STACK_OF(X509)*cert_chain, X509 **identity_cert)`

3.2.1 Detailed Description

A generic set of utility functions for manipulating OpenSSL objects, such as X509 certificates.

3.2.2 Function Documentation

3.2.2.1 `globus_result_t globus_gsi_cert_utils_get_eec (STACK_OF(X509)* cert_chain, X509 ** eec)`

Get the end-entity certificate associated with a certificate chain.

Parameters:

cert_chain Certificate chain to inspect.

eec Pointer to be set to the EEC value from within the cert chain. Must freed by the caller.

3.2.2.2 `globus_result_t globus_gsi_cert_utils_get_identity_cert (STACK_OF(X509)* cert_chain, X509** identity_cert)`

Get the identity-providing certificate associated with a certificate chain. This may be an independent proxy or a end-entity certificate.

Parameters:

cert_chain Certificate chain to inspect.

eec Pointer to be set to the certificate value from within the cert chain. Must freed by the caller.

3.3 Cert Utils Constants

Typedefs

- typedef enum `globus_gsi_cert_utils_cert_type_e` `globus_gsi_cert_utils_cert_type_t`

Enumerations

- enum `globus_gsi_cert_utils_error_t` {
 `GLOBUS_GSI_CERT_UTILS_ERROR_SUCCESS` = 0,
 `GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_NAME_ENTRY_OF_SUBJECT` = 1,
 `GLOBUS_GSI_CERT_UTILS_ERROR_COPYING_SUBJECT` = 2,
 `GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_CN_ENTRY` = 3,
 `GLOBUS_GSI_CERT_UTILS_ERROR_ADDING_CN_TO_SUBJECT` = 4,
 `GLOBUS_GSI_CERT_UTILS_ERROR_OUT_OF_MEMORY` = 5,
 `GLOBUS_GSI_CERT_UTILS_ERROR_UNEXPECTED_FORMAT` = 6,
 `GLOBUS_GSI_CERT_UTILS_ERROR_NON_COMPLIANT_PROXY` = 7,
 `GLOBUS_GSI_CERT_UTILS_ERROR_DETERMINING_CERT_TYPE` = 8,
 `GLOBUS_GSI_CERT_UTILS_ERROR_LAST` = 9 }
• enum `globus_gsi_cert_utils_cert_type_e` {
 `GLOBUS_GSI_CERT_UTILS_TYPE_DEFAULT` = 0,
 `GLOBUS_GSI_CERT_UTILS_TYPE_EEC` = (1 << 0),
 `GLOBUS_GSI_CERT_UTILS_TYPE_CA` = (1 << 1),
 `GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2` = (1 << 2),
 `GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3` = (1 << 3),
 `GLOBUS_GSI_CERT_UTILS_TYPE_RFC` = (1 << 4),
 `GLOBUS_GSI_CERT_UTILS_TYPE_FORMAT_MASK`,
 `GLOBUS_GSI_CERT_UTILS_TYPE_IMPERSONATION_PROXY` = (1 << 5),
 `GLOBUS_GSI_CERT_UTILS_TYPE_LIMITED_PROXY` = (1 << 6),
 `GLOBUS_GSI_CERT_UTILS_TYPE_RESTRICTED_PROXY` = (1 << 7),
 `GLOBUS_GSI_CERT_UTILS_TYPE_INDEPENDENT_PROXY` = (1 << 8),

```

GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_MASK,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_IMPERSONATION_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_INDEPENDENT_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_RESTRICTED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_IMPERSONATION_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_INDEPENDENT_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_RESTRICTED_PROXY }

```

3.3.1 Typedef Documentation

3.3.1.1 typedef enum globus_gsi_cert_utils_cert_type_e globus_gsi_cert_utils_cert_type_t

Certificate Types. These certificate types are used to describe some properties of a certificate and to specify what type of proxy should be generated in the proxy core code. There are two non-proxy types of certificates understood by Globus: EEC (End-Entity Certificate) and CA (Certificate Authority Certificates), three proxy formats (GSI 2 "legacy" proxies, GSI 3 "Draft" proxies, and RFC 3820-compliant proxies), and four types of proxy (limited, impersonation "full", restricted, and independent). The latter two types are not expressible in the GSI 2 format.

In addition to enumerations for the concrete renderings of certificate format and type combined, there are default, formats-without-types and types-without-formats so that application logic which uses the proxy library can request default proxy formats which are compatible with the issuing certificate.

3.3.2 Enumeration Type Documentation

3.3.2.1 enum globus_gsi_cert_utils_error_t

Cert Utils Error Codes.

Enumerator:

```

GLOBUS_GSI_CERT_UTILS_ERROR_SUCCESS Success - never used.
GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_NAME_ENTRY_OF_SUBJECT Failed to retrieve a
    subcomponent of the subject.
GLOBUS_GSI_CERT_UTILS_ERROR_COPYING_SUBJECT A error ocured while trying to copy a
    X.509 subject.
GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_CN_ENTRY Failed to retrieve a CN subcomponent
    of the subject.
GLOBUS_GSI_CERT_UTILS_ERROR_ADDING_CN_TO_SUBJECT Failed to add a CN component to
    a X.509 subject name.
GLOBUS_GSI_CERT_UTILS_ERROR_OUT_OF_MEMORY Out of memory.
GLOBUS_GSI_CERT_UTILS_ERROR_UNEXPECTED_FORMAT Something unexpected happen
    while converting a string subject to a X509_NAME structure.
GLOBUS_GSI_CERT_UTILS_ERROR_NON_COMPLIANT_PROXY Proxy does not comply with the
    expected format.

```

GLOBUS_GSI_CERT_UTILS_ERROR_DETERMINING_CERT_TYPE Couldn't determine the certificate type.

GLOBUS_GSI_CERT_UTILS_ERROR_LAST Last marker - never used.

3.3.2.2 enum globus_gsi_cert_utils_cert_type_e

Certificate Types. These certificate types are used to describe some properties of a certificate and to specify what type of proxy should be generated in the proxy core code. There are two non-proxy types of certificates understood by Globus: EEC (End-Entity Certificate) and CA (Certificate Authority Certificates), three proxy formats (GSI 2 "legacy" proxies, GSI 3 "Draft" proxies, and RFC 3820-compliant proxies), and four types of proxy (limited, impersonation "full", restricted, and independent). The latter two types are not expressible in the GSI 2 format.

In addition to enumerations for the concrete renderings of certificate format and type combined, there are default, formats-without-types and types-without-formats so that application logic which uses the proxy library can request default proxy formats which are compatible with the issuing certificate.

Enumerator:

GLOBUS_GSI_CERT_UTILS_TYPE_DEFAULT Default proxy type.

GLOBUS_GSI_CERT_UTILS_TYPE_EEC A end entity certificate.

GLOBUS_GSI_CERT_UTILS_TYPE_CA A CA certificate.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2 Legacy Proxy Format.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3 X.509 Proxy Certificate Profile (draft) Proxy Format.

GLOBUS_GSI_CERT_UTILS_TYPE_RFC X.509 Proxy Certificate Profile Compliant Proxy Format.

GLOBUS_GSI_CERT_UTILS_TYPE_FORMAT_MASK Proxy certificate formats mask.

GLOBUS_GSI_CERT_UTILS_TYPE_IMPERSONATION_PROXY Impersonation proxy type.

GLOBUS_GSI_CERT_UTILS_TYPE_LIMITED_PROXY Limited proxy type.

GLOBUS_GSI_CERT_UTILS_TYPE_RESTRICTED_PROXY Restricted proxy type.

GLOBUS_GSI_CERT_UTILS_TYPE_INDEPENDENT_PROXY Independent proxy type.

GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_MASK Proxy types mask.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_IMPERSONATION_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant impersonation proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_INDEPENDENT_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant independent proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_LIMITED_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant limited proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_RESTRICTED_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant restricted proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_PROXY A legacy Globus impersonation proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_LIMITED_PROXY A legacy Globus limited impersonation proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_RFC_IMPERSONATION_PROXY A X.509 Proxy Certificate Profile RFC compliant impersonation proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_RFC_INDEPENDENT_PROXY A X.509 Proxy Certificate Profile RFC compliant independent proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_RFC_LIMITED_PROXY A X.509 Proxy Certificate Profile RFC compliant limited proxy.

GLOBUS_GSI_CERT_UTILS_TYPE_RFC_RESTRICTED_PROXY A X.509 Proxy Certificate Profile RFC compliant restricted proxy.

Index

Activation, 1

Cert Utils Constants, 2

Cert Utils Functions, 2

globus_gsi_cert_utils

 globus_gsi_cert_utils_get_eec, 2

 globus_gsi_cert_utils_get_identity_cert, 2

globus_gsi_cert_utils_activation

 GLOBUS_GSI_CERT_UTILS_MODULE, 2

globus_gsi_cert_utils_cert_type_e

 globus_gsi_cert_utils_constants, 4

globus_gsi_cert_utils_cert_type_t

 globus_gsi_cert_utils_constants, 3

globus_gsi_cert_utils_constants

 globus_gsi_cert_utils_cert_type_e, 4

 globus_gsi_cert_utils_cert_type_t, 3

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 ADDING_CN_TO_SUBJECT, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 COPYING_SUBJECT, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 DETERMINING_CERT_TYPE, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 GETTING_CN_ENTRY, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 GETTING_NAME_ENTRY_OF_-
 SUBJECT, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_LAST,
 4

 GLOBUS_GSI_CERT_UTILS_ERROR_NON_-
 COMPLIANT_PROXY, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_OUT_-
 OF_MEMORY, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 SUCCESS, 4

 globus_gsi_cert_utils_error_t, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 UNEXPECTED_FORMAT, 4

 GLOBUS_GSI_CERT_UTILS_TYPE_CA, 4

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 DEFAULT, 4

 GLOBUS_GSI_CERT_UTILS_TYPE_EEC, 4

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 FORMAT_MASK, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_-
 LIMITED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_-
 PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
 IMPERSONATION_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
 INDEPENDENT_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
 LIMITED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
 RESTRICTED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 IMPERSONATION_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 INDEPENDENT_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 LIMITED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_-
 MASK, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_-
 RESTRICTED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_RFC, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
 IMPERSONATION_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
 INDEPENDENT_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
 LIMITED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
 RESTRICTED_PROXY, 5

 GLOBUS_GSI_CERT_UTILS_ERROR_ADDING_-
 CN_TO_SUBJECT

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_COPYING_-
 SUBJECT

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_-
 DETERMINING_CERT_TYPE

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_-
 CN_ENTRY

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_-
 NAME_ENTRY_OF_SUBJECT

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_LAST

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_NON_-
 COMPLIANT_PROXY

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_OUT_OF_-
 MEMORY

 globus_gsi_cert_utils_constants, 4

 GLOBUS_GSI_CERT_UTILS_ERROR_SUCCESS

 globus_gsi_cert_utils_constants, 4

 globus_gsi_cert_utils_error_t

 globus_gsi_cert_utils_constants, 4

GLOBUS_GSI_CERT_UTILS_ERROR_-
UNEXPECTED_FORMAT
globus_gsi_cert_utils_constants, 4
globus_gsi_cert_utils_get_eec
globus_gsi_cert_utils, 2
globus_gsi_cert_utils_get_identity_cert
globus_gsi_cert_utils, 2
GLOBUS_GSI_CERT_UTILS_MODULE
globus_gsi_cert_utils_activation, 2
GLOBUS_GSI_CERT_UTILS_TYPE_CA
globus_gsi_cert_utils_constants, 4
GLOBUS_GSI_CERT_UTILS_TYPE_DEFAULT
globus_gsi_cert_utils_constants, 4
GLOBUS_GSI_CERT_UTILS_TYPE_EEC
globus_gsi_cert_utils_constants, 4
GLOBUS_GSI_CERT_UTILS_TYPE_FORMAT_-
MASK
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_-
LIMITED_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_-
PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
IMPERSONATION_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
INDEPENDENT_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
LIMITED_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_-
RESTRICTED_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_-
IMPERSONATION_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_-
INDEPENDENT_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_LIMITED_-
PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_-
MASK
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_-
RESTRICTED_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_RFC

globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
IMPERSONATION_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
INDEPENDENT_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
LIMITED_PROXY
globus_gsi_cert_utils_constants, 5
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_-
RESTRICTED_PROXY
globus_gsi_cert_utils_constants, 5