

VOMS CC API Reference Manual

1.5.0

Generated by Doxygen 1.4.7

Thu Aug 8 12:31:03 2013

Contents

1	VOMS CC API Data Structure Index	1
1.1	VOMS CC API Data Structures	1
2	VOMS CC API File Index	3
2.1	VOMS CC API File List	3
3	VOMS CC API Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.2	attributelist Struct Reference	7
3.3	contactdata Struct Reference	8
3.4	data Struct Reference	10
3.5	voms Struct Reference	11
3.6	vomsdata Struct Reference	15
4	VOMS CC API File Documentation	25
4.1	voms_api.h File Reference	25

Chapter 1

VOMS CC API Data Structure Index

1.1 VOMS CC API Data Structures

Here are the data structures with brief descriptions:

<code>attribute</code>	5
<code>attributelist</code>	7
<code>contactdata</code>	8
<code>data</code> (User's characteristics: can be repeated)	10
<code>voms</code>	11
<code>vomsdata</code>	15

Chapter 2

VOMS CC API File Index

2.1 VOMS CC API File List

Here is a list of all files with brief descriptions:

voms_api.h	25
----------------------------	-------	----

Chapter 3

VOMS CC API Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [name](#)
- std::string [qualifier](#)
- std::string [value](#)

3.1.1 Detailed Description

Definition at line 63 of file voms_api.h.

3.1.2 Field Documentation

3.1.2.1 std::string [attribute::name](#)

attribute's group

Definition at line 64 of file voms_api.h.

3.1.2.2 std::string [attribute::qualifier](#)

attribute's qualifier

Definition at line 65 of file voms_api.h.

3.1.2.3 std::string [attribute::value](#)

attribute's value

Definition at line 66 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [grantor](#)
- std::vector<[attribute](#)> [attributes](#)

3.2.1 Detailed Description

Definition at line 69 of file voms_api.h.

3.2.2 Field Documentation

3.2.2.1 std::vector<[attribute](#)> [attributelist::attributes](#)

The attributes themselves.

Definition at line 71 of file voms_api.h.

3.2.2.2 std::string [attributelist::grantor](#)

Who granted these attributes.

Definition at line 70 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string **nick**
- std::string **host**
- std::string **contact**
- std::string **vo**
- int **port**
- int **version**

3.3.1 Detailed Description

Definition at line 83 of file voms_api.h.

3.3.2 Field Documentation

3.3.2.1 std::string **contactdata::contact**

The subject of the server's certificate

Definition at line 89 of file voms_api.h.

3.3.2.2 std::string **contactdata::host**

The hostname of the server

Definition at line 88 of file voms_api.h.

3.3.2.3 std::string **contactdata::nick**

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy* functions. The alias of the server

Definition at line 87 of file voms_api.h.

3.3.2.4 int **contactdata::port**

The port on which the server is listening

Definition at line 91 of file voms_api.h.

3.3.2.5 int **contactdata::version**

The version of globus under which the server is running

Definition at line 93 of file voms_api.h.

3.3.2.6 std::string contactdata::vo

The VO served by this server

Definition at line 90 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.4 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_api.h>
```

Data Fields

- std::string [group](#)
- std::string [role](#)
- std::string [cap](#)

3.4.1 Detailed Description

User's characteristics: can be repeated.

Definition at line 55 of file voms_api.h.

3.4.2 Field Documentation

3.4.2.1 std::string [data::cap](#)

user's capability

Definition at line 58 of file voms_api.h.

3.4.2.2 std::string [data::group](#)

user's group

Definition at line 56 of file voms_api.h.

3.4.2.3 std::string [data::role](#)

user's role

Definition at line 57 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.5 voms Struct Reference

```
#include <voms_api.h>
```

Public Member Functions

- `voms` (const `voms` &)
- `voms` ()
- `voms` & `operator=` (const `voms` &)
- `~voms` ()
- `AC * GetAC` ()
- `std::vector< attributelist > & GetAttributes` ()
- `std::vector< std::string > GefTargets` ()

Data Fields

- `int version`
- `int siglen`
- `std::string signature`
- `std::string user`
- `std::string userca`
- `std::string server`
- `std::string serverca`
- `std::string voname`
- `std::string uri`
- `std::string date1`
- `std::string date2`
- `data_type type`
- `std::vector< data > std`
- `std::string custom`
- `std::vector< std::string > fqan`
- `std::string serial`

Friends

- class `vomsdata`
- `int TranslateVOMS` (struct vomsdata *vd, `std::vector< voms > &v, int *error)`

3.5.1 Detailed Description

Definition at line 98 of file voms_api.h.

3.5.2 Constructor & Destructor Documentation

3.5.2.1 `voms::voms (const voms &)`

3.5.2.2 `voms::voms ()`

3.5.2.3 `voms::~voms ()`

3.5.3 Member Function Documentation

3.5.3.1 `AC* voms::GetAC ()`

3.5.3.2 `std::vector<attributelist>& voms::GetAttributes ()`

Generic attributes

3.5.3.3 `std::vector<std::string> voms::GetTargets ()`

3.5.3.4 `voms& voms::operator= (const voms &)`

3.5.4 Friends And Related Function Documentation

3.5.4.1 `int TranslateVOMS (struct vomsdata * vd, std::vector< voms > & v, int * error)`
[friend]

3.5.4.2 `friend class vomsdata` [friend]

Definition at line 99 of file voms_api.h.

3.5.5 Field Documentation

3.5.5.1 `std::string voms::custom`

The data returned by an S command

Definition at line 113 of file voms_api.h.

3.5.5.2 `std::string voms::date1`

Beginning of validity of the user info

Definition at line 109 of file voms_api.h.

3.5.5.3 `std::string voms::date2`

End of validity of the user info

Definition at line 110 of file voms_api.h.

3.5.5.4 std::vector<std::string> voms::fqan

Keeps the data in the compact format

Definition at line 115 of file voms_api.h.

3.5.5.5 std::string voms::serial

Serial number. "0" if coming from non-ac

Definition at line 116 of file voms_api.h.

3.5.5.6 std::string voms::server

The VOMS server DN, as from its certificate

Definition at line 105 of file voms_api.h.

3.5.5.7 std::string voms::serverca

The CA which signed the VOMS certificate

Definition at line 106 of file voms_api.h.

3.5.5.8 int voms::siglen

The length of the VOMS server signature

Definition at line 101 of file voms_api.h.

3.5.5.9 std::string voms::signature

The VOMS server signature

Definition at line 102 of file voms_api.h.

3.5.5.10 std::vector<data> voms::std

User's characteristics

Definition at line 112 of file voms_api.h.

3.5.5.11 data_type voms::type

The type of data returned

Definition at line 111 of file voms_api.h.

3.5.5.12 std::string voms::uri

The URI of the VOMS server

Definition at line 108 of file voms_api.h.

3.5.5.13 std::string voms::user

The user's DN, as from his certificate

Definition at line 103 of file voms_api.h.

3.5.5.14 std::string voms::userca

The CA which signed the user's certificate

Definition at line 104 of file voms_api.h.

3.5.5.15 int voms::version

0 means data didn't originate from an AC

Definition at line 100 of file voms_api.h.

3.5.5.16 std::string voms::vuname

The name of the VO to which the VOMS belongs

Definition at line 107 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

Public Member Functions

- `vomsdata` (std::string voms_dir="", std::string cert_dir "")
- bool `LoadSystemContacts` (std::string dir "")
- bool `LoadUserContacts` (std::string dir "")
- std::vector< contactdata > `FindByAlias` (std::string alias)
- std::vector< contactdata > `FindByVO` (std::string vo)
- void `Order` (std::string att)
- void `ResetOrder` (void)
- void `AddTarget` (std::string target)
- std::vector< std::string > `ListTargets` (void)
- void `ResetTargets` (void)
- std::string `ServerErrors` (void)
- bool `Retrieve` (X509 *cert, STACK_OF(X509)*chain, recurse_type how=RECURSE_CHAIN)
- bool `Contact` (std::string hostname, int port, std::string servsubject, std::string command)
- bool `Contact` (std::string hostname, int port, std::string servsubject, std::string command, int timeout)
- bool `ContactRaw` (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)
- bool `ContactRaw` (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version, int timeout)
- void `SetVerificationType` (verify_type how)
- void `SetLifetime` (int lifetime)
- bool `Import` (std::string buffer)
- bool `Export` (std::string &data)
- bool `DefaultData` (voms &)
- std::string `ErrorMessage` (void)
- bool `RetrieveFromCtx` (gss_ctx_id_t context, recurse_type how)
- bool `RetrieveFromCred` (gss_cred_id_t credential, recurse_type how)
- bool `Retrieve` (X509_EXTENSION *ext)
- bool `RetrieveFromProxy` (recurse_type how)
- bool `Retrieve` (FILE *file, recurse_type how)
- bool `Retrieve` (AC *ac)
- `~vomsdata` ()
- `vomsdata` (const vomsdata &)
- void `SetRetryCount` (int retryCount)
- void `SetVerificationTime` (time_t)
- bool `LoadCredentials` (X509 *, EVP_PKEY *, STACK_OF(X509)*)
- bool `ContactRESTRaw` (const std::string &, int, const std::string &, std::string &, int, int)

Data Fields

- `verror_type` error
- std::vector< voms > `data`
- std::string `workvo`
- std::string `extra_data`

Data Structures

- class **Initializer**

3.6.1 Detailed Description

Definition at line 194 of file voms_api.h.

3.6.2 Constructor & Destructor Documentation

3.6.2.1 `vomsdata::vomsdata (std::string voms_dir = "", std::string cert_dir = "")`

Parameters:

voms_dir The directory which contains the certificate of the VOMS server

cert_dir The directory which contains the certificate of the CA

If *voms_dir* is empty, the value of the environment variable X509_VOMS_DIR is taken.

If *cert_dir* is empty, the value of the environment variable X509_CERT_DIR is taken.

3.6.2.2 `vomsdata::~vomsdata ()`

3.6.2.3 `vomsdata::vomsdata (const vomsdata &)`

3.6.3 Member Function Documentation

3.6.3.1 `void vomsdata::AddTarget (std::string target)`

Adds a target to the AC.

Parameters:

target The target to be added. it should be a FQDN.

3.6.3.2 `bool vomsdata::Contact (std::string hostname, int port, std::string servsubject, std::string command, int timeout)`

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the –include functionality.

Parameters:

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command the command sent to the server

Returns:

failure (F) or success (T)

3.6.3.3 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the –include functionality.

Parameters:

hostname FQDN of the VOMS server
port the port on which the VOMS server is listening
servsubject the subject of the server's certificate
command the command sent to the server

Returns:

failure (F) or success (T)

3.6.3.4 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*, int *timeout*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters:

hostname FQDN of the VOMS server
port the port on which the VOMS server is listening
servsubject the subject of the server's certificate
command the command sent to the server
raw OUTPUT PARAMETER the answer from the server
version OUTPUT PARAMETER the version of the answer

Returns:

failure (F) or success (T)

3.6.3.5 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters:

hostname FQDN of the VOMS server
port the port on which the VOMS server is listening
servsubject the subject of the server's certificate
command the command sent to the server
raw OUTPUT PARAMETER the answer from the server

version OUTPUT PARAMETER the version of the answer

Returns:

failure (F) or success (T)

3.6.3.6 bool vomsdata::ContactRESTRaw (const std::string &, int, const std::string &, std::string &, int, int)

3.6.3.7 bool vomsdata::DefaultData ([voms](#) &)

Get the default data extension from those present in the pseudo certificate

3.6.3.8 std::string vomsdata::ErrorMessage (void)

Gets a textual description of the error.

Returns:

A string containg the error message.

3.6.3.9 bool vomsdata::Export (std::string & *data*)

Exports data from [vomsdata::data](#) to the format used for inclusion into a certificate.

The function doesn't verify the data

Parameters:

data The certificate extension

Returns:

Failure (F) or Success (T)

3.6.3.10 std::vector<[contactdata](#)> vomsdata::FindByAlias (std::string *alias*)

Finds servers which share a common alias.

Parameters:

alias The alias to look for.

Returns:

The servers found. The order in which they are returned is unspecified.

3.6.3.11 std::vector<contactdata> vomsdata::FindByVO (std::string *vo*)

Finds servers which serve a common VO

Parameters:

vo The VO name to look for.

Returns:

The servers found. The order in which they are returned is unspecified.

3.6.3.12 bool vomsdata::Import (std::string *buffer*)

Converts data from the format used for inclusion into a certificate to the internal format

The function does verify the data.

Parameters:

buffer contains the data to be converted

Returns:

Failure (F) or Success (T)

3.6.3.13 std::vector<std::string> vomsdata::ListTargets (void)

Returns the list of targets.

3.6.3.14 bool vomsdata::LoadCredentials (X509 *, EVP_PKEY *, STACK_OF(X509)*)**3.6.3.15 bool vomsdata::LoadSystemContacts (std::string *dir* = "")**

Loads the system wide configuration files.

Parameters:

dir The directory in which the files are stored.

If *dir* is empty, defaults to /opt/edg/etc/vomses.

Returns:

True if all went OK, false otherwise.

3.6.3.16 bool vomsdata::LoadUserContacts (std::string *dir* = "")

Loads the user-specific configuration files.

Parameters:

dir The directory in which the files are stored.

If dir is empty, defaults to \$VOMS_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to `~/.edg/vomses` as a last resort.

Returns:

True if all went OK, false otherwise.

3.6.3.17 void vomsdata::Order (std::string *att*)

Sets up the ordering of the results.

Defines the ordering of the data returned by [Contact\(\)](#). Results are ordered in the same order as the calls to this function.

Parameters:

att The attribute to be ordered.

3.6.3.18 void vomsdata::ResetOrder (void)

Resets the ordering.

3.6.3.19 void vomsdata::ResetTargets (void)

Resets the target list.

3.6.3.20 bool vomsdata::Retrieve (AC * *ac*)

Gets VOMS information from the AC

Parameters:

ext The extension to parse.

Returns:

failure (F) or success (T)

3.6.3.21 bool vomsdata::Retrieve (FILE * *file*, recurse_type *how*)

Gets VOMS information from a proxy saved as a file.

Parameters:

file the file name

how Recursion type

Returns:

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

3.6.3.22 bool vomsdata::Retrieve (X509_EXTENSION * *ext*)

Gets VOMS information from the given extension

Parameters:

ext The extension to parse.

Returns:

failure (F) or success (T)

3.6.3.23 bool vomsdata::Retrieve (X509 * *cert*, STACK_OF(X509)* *chain*, recurse_type *how* = RECURSE_CHAIN)

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user data.

Parameters:

cert The certificate with the VOMS extensions

chain The chain of the validation certificates (only the intermediate ones)

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.24 bool vomsdata::RetrieveFromCred (gss_cred_id_t *credential*, recurse_type *how*)

Gets VOMS information from the given globus credential

Parameters:

credential The credential from which to retrieve the certificate.

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.25 bool vomsdata::RetrieveFromCtx (gss_ctx_id_t *context*, recurse_type *how*)

Gets VOMS information from the given globus context

Parameters:

context The context from which to retrieve the certificate.

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.26 bool vomsdata::RetrieveFromProxy (*recurse_type how*)

Gets VOMS information from an existing globus proxy

Parameters:

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.27 std::string vomsdata::ServerErrors (void)

Gets the error message returned by the server

3.6.3.28 void vomsdata::SetLifetime (int *lifetime*)

Set requested lifetime for the [Contact\(\)](#) call.

Parameters:

lifetime Requested lifetime, in seconds

3.6.3.29 void vomsdata::SetRetryCount (int *retryCount*)**3.6.3.30 void vomsdata::SetVerificationTime (time_t)****3.6.3.31 void vomsdata::SetVerificationType (*verify_type how*)**

Sets the type of verification done on the data.

Parameters:

how The type of verification.

3.6.4 Field Documentation**3.6.4.1 std::vector<[voms](#)> vomsdata::data**

User's info, as in the certificate extension. It may contain data gathered from more than one VOMS server,
Definition at line 368 of file voms_api.h.

3.6.4.2 *verror_type* vomsdata::error

Error code

Definition at line 213 of file voms_api.h.

3.6.4.3 std::string vomsdata::extra_data

The data specified by the user with the –include switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead data specified by the user.

The reason for the introduction of this extension is to let a user include important data into his proxy certificate, like, for example, a kerberos ticket

Definition at line 372 of file voms_api.h.

3.6.4.4 std::string vomsdata::workvo

The value of the -vo option of the voms-proxy-init command

Definition at line 371 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

Chapter 4

VOMS CC API File Documentation

4.1 voms_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

Data Structures

- struct [data](#)
User's characteristics: can be repeated.
- struct [attribute](#)
- struct [attributelist](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)
- class [vomsdata::Initializer](#)

Defines

- #define [NOGLOBUS](#)

Typedefs

- typedef void * [gss_cred_id_t](#)
- typedef void * [gss_ctx_id_t](#)
- typedef bool(*) [check_sig](#) (X509 *, void *, [verror_type](#) &)

Enumerations

- enum `data_type` { `TYPE_NODATA`, `TYPE_STD`, `TYPE_CUSTOM` }

The type of data returned.

 - enum `recurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }
 - enum `verify_type` {

`VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001,
 `VERIFY_TARGET` = 0x00000002,

`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER` = 0x00000010,
 `VERIFY_ID` = 0x00000020,

`VERIFY_CERTLIST` = 0x00000040 }
 - enum `verror_type` {

`VERR_NONE`, `VERR_NOSOCKET`, `VERR_NOIDENT`, `VERR_COMM`,
 `VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,
 `VERR_IDCHECK`, `VERR_EXTRAINFO`, `VERR_FORMAT`, `VERR_NODATA`,
 `VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,
 `VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,
 `VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }
- Error codes.*

Functions

- int `getVOMSMajorVersionNumber` (void)
- int `getVOMSMinorVersionNumber` (void)
- int `getVOMSPatchVersionNumber` (void)

4.1.1 Define Documentation

4.1.1.1 #define NOGLOBUS

Definition at line 33 of file voms_api.h.

4.1.2 Typedef Documentation

4.1.2.1 `typedef bool(*) check_sig(X509 *, void *, verror_type &)`

Definition at line 190 of file voms_api.h.

4.1.2.2 `typedef void* gss_cred_id_t`

Definition at line 42 of file voms_api.h.

4.1.2.3 `typedef void* gss_ctx_id_t`

Definition at line 43 of file voms_api.h.

4.1.3 Enumeration Type Documentation

4.1.3.1 enum `data_type`

The type of data returned.

Enumerator:

`TYPE_NODATA` no data
`TYPE_STD` group, role, capability triplet
`TYPE_CUSTOM` result of an S command

Definition at line 77 of file voms_api.h.

4.1.3.2 enum `recurse_type`

Enumerator:

`RECURSE_CHAIN`
`RECURSE_NONE`
`RECURSE_DEEP`

Definition at line 143 of file voms_api.h.

4.1.3.3 enum `verify_type`

Enumerator:

`VERIFY_FULL`
`VERIFY_NONE`
`VERIFY_DATE`
`VERIFY_TARGET`
`VERIFY_KEY`
`VERIFY_SIGN`
`VERIFY_ORDER`
`VERIFY_ID`
`VERIFY_CERTLIST`

Definition at line 149 of file voms_api.h.

4.1.3.4 enum `verror_type`

Error codes.

Enumerator:

`VERR_NONE`
`VERR_NOSOCKET` Socket problem
`VERR_NOIDENT` Cannot identify itself (certificate problem)

VERR_COMM Server problem
VERR_PARAM Wrong parameters
VERR_NOEXT VOMS extension missing
VERR_NOINIT Initialization error
VERR_TIME Error in time checking
VERR_IDCHECK User data in extension different from the real ones
VERR_EXTRAINFO VO name and URI missing
VERR_FORMAT Wrong data format
VERR_NODATA Empty extension
VERR_PARSE Parse error
VERR_DIR Directory error
VERR_SIGN Signature error
VERR_SERVER Unidentifiable VOMS server
VERR_MEM Memory problems
VERR_VERIFY Generic verification error
VERR_TYPE Returned data of unknown type
VERR_ORDER Ordering different than required
VERR_SERVERCODE Error message from the server
VERR_NOTAVAIL Method not available
VERR_FILE Error reading data from file

Definition at line 163 of file voms_api.h.

4.1.4 Function Documentation

- 4.1.4.1 **int getVOMSMajorVersionNumber (void)**
- 4.1.4.2 **int getVOMSMinorVersionNumber (void)**
- 4.1.4.3 **int getVOMSPatchVersionNumber (void)**

Index

~voms
 voms, 12
~vomsdata
 vomsdata, 16

AddTarget
 vomsdata, 16
attribute, 5
 name, 5
 qualifier, 5
 value, 5
attributelist, 7
 attributes, 7
 grantor, 7
attributes
 attributelist, 7

cap
 data, 10
check_sig
 voms_api.h, 26
Contact
 vomsdata, 16
contact
 contactdata, 8
contactdata, 8
 contact, 8
 host, 8
 nick, 8
 port, 8
 version, 8
 vo, 8
ContactRaw
 vomsdata, 17
ContactRESTRaw
 vomsdata, 18
custom
 voms, 12

data, 10
 cap, 10
 group, 10
 role, 10
 vomsdata, 22
data_type
 voms_api.h, 27
date1
 voms, 12
date2
 voms, 12
DefaultData
 vomsdata, 18

error
 vomsdata, 22
ErrorMessage
 vomsdata, 18
Export
 vomsdata, 18
extra_data
 vomsdata, 22

FindByAlias
 vomsdata, 18
FindByVO
 vomsdata, 18
fqan
 voms, 12

GetAC
 voms, 12
GetAttributes
 voms, 12
GetTargets
 voms, 12
getVOMSMajorVersionNumber
 voms_api.h, 28
getVOMSMinorVersionNumber
 voms_api.h, 28
getVOMSPatchVersionNumber
 voms_api.h, 28
grantor
 attributelist, 7
group
 data, 10
 gss_cred_id_t
 voms_api.h, 26
 gss_ctx_id_t
 voms_api.h, 26
host

contactdata, 8
 Import
 vomsdata, 19
 ListTargets
 vomsdata, 19
 LoadCredentials
 vomsdata, 19
 LoadSystemContacts
 vomsdata, 19
 LoadUserContacts
 vomsdata, 19
 name
 attribute, 5
 nick
 contactdata, 8
 NOGLOBUS
 voms_api.h, 26
 operator=
 voms, 12
 Order
 vomsdata, 20
 port
 contactdata, 8
 qualifier
 attribute, 5
 RECURSE_CHAIN
 voms_api.h, 27
 RECURSE_DEEP
 voms_api.h, 27
 RECURSE_NONE
 voms_api.h, 27
 recurse_type
 voms_api.h, 27
 ResetOrder
 vomsdata, 20
 ResetTargets
 vomsdata, 20
 Retrieve
 vomsdata, 20, 21
 RetrieveFromCred
 vomsdata, 21
 RetrieveFromCtx
 vomsdata, 21
 RetrieveFromProxy
 vomsdata, 21
 role
 data, 10
 serial
 voms, 13
 server
 voms, 13
 serverca
 voms, 13
 ServerErrors
 vomsdata, 22
 SetLifetime
 vomsdata, 22
 SetRetryCount
 vomsdata, 22
 SetVerificationTime
 vomsdata, 22
 SetVerificationType
 vomsdata, 22
 siglen
 voms, 13
 signature
 voms, 13
 std
 voms, 13
 TranslateVOMS
 voms, 12
 type
 voms, 13
 TYPE_CUSTOM
 voms_api.h, 27
 TYPE_NODATA
 voms_api.h, 27
 TYPE_STD
 voms_api.h, 27
 uri
 voms, 13
 user
 voms, 13
 userca
 voms, 14
 value
 attribute, 5
 VERIFY_CERTLIST
 voms_api.h, 27
 VERIFY_DATE
 voms_api.h, 27
 VERIFY_FULL
 voms_api.h, 27
 VERIFY_ID
 voms_api.h, 27
 VERIFY_KEY
 voms_api.h, 27
 VERIFY_NONE

voms_api.h, 27
VERIFY_ORDER
 voms_api.h, 27
VERIFY_SIGN
 voms_api.h, 27
VERIFY_TARGET
 voms_api.h, 27
verify_type
 voms_api.h, 27
VERR_COMM
 voms_api.h, 27
VERR_DIR
 voms_api.h, 28
VERR_EXTRAINFO
 voms_api.h, 28
VERR_FILE
 voms_api.h, 28
VERR_FORMAT
 voms_api.h, 28
VERR_IDCHECK
 voms_api.h, 28
VERR_MEM
 voms_api.h, 28
VERR_NODATA
 voms_api.h, 28
VERR_NOEXT
 voms_api.h, 28
VERR_NOIDENT
 voms_api.h, 27
VERR_NOINIT
 voms_api.h, 28
VERR_NONE
 voms_api.h, 27
VERR_NOSOCKET
 voms_api.h, 27
VERR_NOTAVAIL
 voms_api.h, 28
VERR_ORDER
 voms_api.h, 28
VERR_PARAM
 voms_api.h, 28
VERR_PARSE
 voms_api.h, 28
VERR_SERVER
 voms_api.h, 28
VERR_SERVERCODE
 voms_api.h, 28
VERR_SIGN
 voms_api.h, 28
VERR_TIME
 voms_api.h, 28
VERR_TYPE
 voms_api.h, 28
VERR_VERIFY
 voms_api.h, 28
 voms_api.h, 28
verror_type
 voms_api.h, 27
version
 contactdata, 8
 voms, 14
vo
 contactdata, 8
voms, 11
 ~voms, 12
 custom, 12
 date1, 12
 date2, 12
 fqan, 12
 GetAC, 12
 GetAttributes, 12
 GetTargets, 12
 operator=, 12
 serial, 13
 server, 13
 serverca, 13
 siglen, 13
 signature, 13
 std, 13
 TranslateVOMS, 12
 type, 13
 uri, 13
 user, 13
 userca, 14
 version, 14
 voms, 12
 vomsdata, 12
 voname, 14
voms_api.h
 RECURSE_CHAIN, 27
 RECURSE_DEEP, 27
 RECURSE_NONE, 27
 TYPE_CUSTOM, 27
 TYPE_NODATA, 27
 TYPE_STD, 27
 VERIFY_CERTLIST, 27
 VERIFY_DATE, 27
 VERIFY_FULL, 27
 VERIFY_ID, 27
 VERIFY_KEY, 27
 VERIFY_NONE, 27
 VERIFY_ORDER, 27
 VERIFY_SIGN, 27
 VERIFY_TARGET, 27
 VERR_COMM, 27
 VERR_DIR, 28
 VERR_EXTRAINFO, 28
 VERR_FILE, 28
 VERR_FORMAT, 28

VERR_IDCHECK, 28
 VERR_MEM, 28
 VERR_NODATA, 28
 VERR_NOEXT, 28
 VERR_NOIDENT, 27
 VERR_NOINIT, 28
 VERR_NONE, 27
 VERR_NOSOCKET, 27
 VERR_NOTAVAIL, 28
 VERR_ORDER, 28
 VERR_PARAM, 28
 VERR_PARSE, 28
 VERR_SERVER, 28
 VERR_SERVERCODE, 28
 VERR_SIGN, 28
 VERR_TIME, 28
 VERR_TYPE, 28
 VERR_VERIFY, 28

 voms_api.h, 25
 check_sig, 26
 data_type, 27
 getVOMSMajorVersionNumber, 28
 getVOMSMinorVersionNumber, 28
 getVOMSPatchVersionNumber, 28
 gss_cred_id_t, 26
 gss_ctx_id_t, 26
 NOGLOBUS, 26
 reurse_type, 27
 verify_type, 27
 verror_type, 27

 vomsdata, 15
 ~vomsdata, 16
 AddTarget, 16
 Contact, 16
 ContactRaw, 17
 ContactRESTRaw, 18
 data, 22
 DefaultData, 18
 error, 22
 ErrorMessage, 18
 Export, 18
 extra_data, 22
 FindByAlias, 18
 FindByVO, 18
 Import, 19
 ListTargets, 19
 LoadCredentials, 19
 LoadSystemContacts, 19
 LoadUserContacts, 19
 Order, 20
 ResetOrder, 20
 ResetTargets, 20
 Retrieve, 20, 21
 RetrieveFromCred, 21

 RetrieveFromCtx, 21
 RetrieveFromProxy, 21
 ServerErrors, 22
 SetLifetime, 22
 SetRetryCount, 22
 SetVerificationTime, 22
 SetVerificationType, 22
 voms, 12
 vomsdata, 16
 workvo, 23

 voname
 voms, 14

 workvo
 vomsdata, 23