

activemq-cpp-3.2.3

Generated by Doxygen 1.6.1

Wed Nov 10 22:25:45 2010

Contents

1	Namespace Index	1
1.1	Namespace List	1
2	Data Structure Index	3
2.1	Class Hierarchy	3
3	Data Structure Index	25
3.1	Data Structures	25
4	File Index	63
4.1	File List	63
5	Namespace Documentation	85
5.1	activemq Namespace Reference	85
5.1.1	Detailed Description	85
5.2	activemq::cmsutil Namespace Reference	86
5.3	activemq::commands Namespace Reference	87
5.4	activemq::core Namespace Reference	89
5.5	activemq::core::policies Namespace Reference	91
5.6	activemq::exceptions Namespace Reference	92
5.7	activemq::io Namespace Reference	93
5.8	activemq::library Namespace Reference	94
5.9	activemq::state Namespace Reference	95
5.10	activemq::threads Namespace Reference	96
5.11	activemq::transport Namespace Reference	97
5.12	activemq::transport::correlator Namespace Reference	98
5.13	activemq::transport::failover Namespace Reference	99
5.14	activemq::transport::inactivity Namespace Reference	100
5.15	activemq::transport::logging Namespace Reference	101
5.16	activemq::transport::mock Namespace Reference	102

5.17	activemq::transport::tcp Namespace Reference	103
5.18	activemq::util Namespace Reference	104
5.19	activemq::wireformat Namespace Reference	105
5.20	activemq::wireformat::openwire Namespace Reference	106
5.21	activemq::wireformat::openwire::marshal Namespace Reference	107
5.22	activemq::wireformat::openwire::marshal::v1 Namespace Reference	108
5.23	activemq::wireformat::openwire::marshal::v2 Namespace Reference	113
5.24	activemq::wireformat::openwire::marshal::v3 Namespace Reference	118
5.25	activemq::wireformat::openwire::marshal::v4 Namespace Reference	123
5.26	activemq::wireformat::openwire::marshal::v5 Namespace Reference	128
5.27	activemq::wireformat::openwire::marshal::v6 Namespace Reference	133
5.28	activemq::wireformat::openwire::utils Namespace Reference	138
5.29	activemq::wireformat::stomp Namespace Reference	139
5.30	cms Namespace Reference	140
5.30.1	Detailed Description	142
5.31	decaf Namespace Reference	143
5.31.1	Detailed Description	143
5.32	decaf::internal Namespace Reference	144
5.33	decaf::internal::io Namespace Reference	145
5.34	decaf::internal::net Namespace Reference	146
5.35	decaf::internal::net::ssl Namespace Reference	147
5.36	decaf::internal::net::ssl::openssl Namespace Reference	148
5.37	decaf::internal::net::tcp Namespace Reference	149
5.38	decaf::internal::nio Namespace Reference	150
5.39	decaf::internal::security Namespace Reference	151
5.40	decaf::internal::util Namespace Reference	152
5.41	decaf::internal::util::concurrent Namespace Reference	153
5.42	decaf::io Namespace Reference	154
5.43	decaf::lang Namespace Reference	156
5.43.1	Function Documentation	158
5.43.1.1	operator!=	158
5.43.1.2	operator!=	158
5.43.1.3	operator!=	158
5.43.1.4	operator!=	158
5.43.1.5	operator==	158
5.43.1.6	operator==	158

5.43.1.7	operator==	158
5.43.1.8	operator==	158
5.44	decaf::lang::exceptions Namespace Reference	159
5.45	decaf::net Namespace Reference	160
5.46	decaf::net::ssl Namespace Reference	162
5.47	decaf::nio Namespace Reference	163
5.48	decaf::security Namespace Reference	164
5.49	decaf::security::auth Namespace Reference	165
5.50	decaf::security::auth::x500 Namespace Reference	166
5.51	decaf::security::cert Namespace Reference	167
5.52	decaf::util Namespace Reference	168
5.53	decaf::util::comparators Namespace Reference	170
5.54	decaf::util::concurrent Namespace Reference	171
5.55	decaf::util::concurrent::atomic Namespace Reference	173
5.56	decaf::util::concurrent::locks Namespace Reference	174
5.57	decaf::util::logging Namespace Reference	175
5.57.1	Enumeration Type Documentation	176
5.57.1.1	Levels	176
5.58	decaf::util::zip Namespace Reference	177
5.59	std Namespace Reference	178
6	Data Structure Documentation	179
6.1	decaf::util::AbstractCollection< E > Class Template Reference	179
6.1.1	Detailed Description	181
6.1.2	Constructor & Destructor Documentation	182
6.1.2.1	AbstractCollection	182
6.1.2.2	~AbstractCollection	182
6.1.3	Member Function Documentation	182
6.1.3.1	add	182
6.1.3.2	addAll	183
6.1.3.3	clear	183
6.1.3.4	contains	184
6.1.3.5	containsAll	185
6.1.3.6	copy	185
6.1.3.7	equals	185
6.1.3.8	isEmpty	186
6.1.3.9	lock	186

6.1.3.10	notify	186
6.1.3.11	notifyAll	187
6.1.3.12	operator=	187
6.1.3.13	remove	187
6.1.3.14	removeAll	188
6.1.3.15	retainAll	189
6.1.3.16	toArray	189
6.1.3.17	tryLock	189
6.1.3.18	unlock	190
6.1.3.19	wait	190
6.1.3.20	wait	191
6.1.3.21	wait	191
6.1.4	Field Documentation	191
6.1.4.1	mutex	191
6.2	decaf::util::AbstractList< E > Class Template Reference	192
6.2.1	Detailed Description	192
6.2.2	Constructor & Destructor Documentation	192
6.2.2.1	~AbstractList	192
6.3	decaf::util::AbstractMap< K, V, COMPARATOR > Class Template Reference	193
6.3.1	Detailed Description	193
6.3.2	Constructor & Destructor Documentation	193
6.3.2.1	~AbstractMap	193
6.4	decaf::util::AbstractQueue< E > Class Template Reference	194
6.4.1	Detailed Description	194
6.4.2	Constructor & Destructor Documentation	195
6.4.2.1	AbstractQueue	195
6.4.2.2	~AbstractQueue	195
6.4.3	Member Function Documentation	195
6.4.3.1	add	195
6.4.3.2	addAll	195
6.4.3.3	clear	196
6.4.3.4	element	196
6.4.3.5	remove	196
6.5	decaf::util::AbstractSequentialList< E > Class Template Reference	198
6.5.1	Detailed Description	198
6.5.2	Constructor & Destructor Documentation	198

6.5.2.1	~AbstractSequentialList	198
6.6	decaf::util::AbstractSet< E > Class Template Reference	199
6.6.1	Detailed Description	199
6.6.2	Constructor & Destructor Documentation	199
6.6.2.1	~AbstractSet	199
6.6.3	Member Function Documentation	199
6.6.3.1	removeAll	199
6.7	activemq::transport::AbstractTransportFactory Class Reference	201
6.7.1	Detailed Description	201
6.7.2	Constructor & Destructor Documentation	201
6.7.2.1	~AbstractTransportFactory	201
6.7.3	Member Function Documentation	201
6.7.3.1	createWireFormat	201
6.8	activemq::core::ActiveMQAckHandler Class Reference	203
6.8.1	Detailed Description	203
6.8.2	Constructor & Destructor Documentation	203
6.8.2.1	~ActiveMQAckHandler	203
6.8.3	Member Function Documentation	203
6.8.3.1	acknowledgeMessage	203
6.9	activemq::commands::ActiveMQBlobMessage Class Reference	204
6.9.1	Constructor & Destructor Documentation	205
6.9.1.1	ActiveMQBlobMessage	205
6.9.1.2	~ActiveMQBlobMessage	205
6.9.2	Member Function Documentation	205
6.9.2.1	clone	205
6.9.2.2	cloneDataStructure	205
6.9.2.3	copyDataStructure	205
6.9.2.4	equals	206
6.9.2.5	getDataStructureType	206
6.9.2.6	getMimeType	206
6.9.2.7	getName	206
6.9.2.8	getRemoteBlobUrl	207
6.9.2.9	isDeletedByBroker	207
6.9.2.10	setDeletedByBroker	207
6.9.2.11	setMimeType	207
6.9.2.12	setName	207

6.9.2.13	setRemoteBlobUrl	207
6.9.2.14	toString	208
6.9.3	Field Documentation	208
6.9.3.1	BINARY_MIME_TYPE	208
6.9.3.2	ID_ACTIVEMQBLOBMESSAGE	208
6.10	activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller	
	Class Reference	209
6.10.1	Detailed Description	209
6.10.2	Constructor & Destructor Documentation	210
6.10.2.1	ActiveMQBlobMessageMarshaller	210
6.10.2.2	~ActiveMQBlobMessageMarshaller	210
6.10.3	Member Function Documentation	210
6.10.3.1	createObject	210
6.10.3.2	getDataStructureType	210
6.10.3.3	looseMarshal	210
6.10.3.4	looseUnmarshal	211
6.10.3.5	tightMarshal1	211
6.10.3.6	tightMarshal2	211
6.10.3.7	tightUnmarshal	212
6.11	activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller	
	Class Reference	213
6.11.1	Detailed Description	213
6.11.2	Constructor & Destructor Documentation	214
6.11.2.1	ActiveMQBlobMessageMarshaller	214
6.11.2.2	~ActiveMQBlobMessageMarshaller	214
6.11.3	Member Function Documentation	214
6.11.3.1	createObject	214
6.11.3.2	getDataStructureType	214
6.11.3.3	looseMarshal	214
6.11.3.4	looseUnmarshal	215
6.11.3.5	tightMarshal1	215
6.11.3.6	tightMarshal2	215
6.11.3.7	tightUnmarshal	216
6.12	activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller	
	Class Reference	217
6.12.1	Detailed Description	217
6.12.2	Constructor & Destructor Documentation	218

6.12.2.1	ActiveMQBlobMessageMarshaller	218
6.12.2.2	~ActiveMQBlobMessageMarshaller	218
6.12.3	Member Function Documentation	218
6.12.3.1	createObject	218
6.12.3.2	getDataStructureType	218
6.12.3.3	looseMarshal	218
6.12.3.4	looseUnmarshal	219
6.12.3.5	tightMarshal1	219
6.12.3.6	tightMarshal2	219
6.12.3.7	tightUnmarshal	220
6.13	activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller	
	Class Reference	221
6.13.1	Detailed Description	221
6.13.2	Constructor & Destructor Documentation	222
6.13.2.1	ActiveMQBlobMessageMarshaller	222
6.13.2.2	~ActiveMQBlobMessageMarshaller	222
6.13.3	Member Function Documentation	222
6.13.3.1	createObject	222
6.13.3.2	getDataStructureType	222
6.13.3.3	looseMarshal	222
6.13.3.4	looseUnmarshal	223
6.13.3.5	tightMarshal1	223
6.13.3.6	tightMarshal2	223
6.13.3.7	tightUnmarshal	224
6.14	activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller	
	Class Reference	225
6.14.1	Detailed Description	225
6.14.2	Constructor & Destructor Documentation	226
6.14.2.1	ActiveMQBlobMessageMarshaller	226
6.14.2.2	~ActiveMQBlobMessageMarshaller	226
6.14.3	Member Function Documentation	226
6.14.3.1	createObject	226
6.14.3.2	getDataStructureType	226
6.14.3.3	looseMarshal	226
6.14.3.4	looseUnmarshal	227
6.14.3.5	tightMarshal1	227
6.14.3.6	tightMarshal2	227

6.14.3.7	tightUnmarshal	228
6.15	activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller	
	Class Reference	229
6.15.1	Detailed Description	229
6.15.2	Constructor & Destructor Documentation	230
6.15.2.1	ActiveMQBlobMessageMarshaller	230
6.15.2.2	~ActiveMQBlobMessageMarshaller	230
6.15.3	Member Function Documentation	230
6.15.3.1	createObject	230
6.15.3.2	getDataStructureType	230
6.15.3.3	looseMarshal	230
6.15.3.4	looseUnmarshal	231
6.15.3.5	tightMarshal1	231
6.15.3.6	tightMarshal2	231
6.15.3.7	tightUnmarshal	232
6.16	activemq::commands::ActiveMQBytesMessage Class Reference	233
6.16.1	Constructor & Destructor Documentation	236
6.16.1.1	ActiveMQBytesMessage	236
6.16.1.2	~ActiveMQBytesMessage	236
6.16.2	Member Function Documentation	236
6.16.2.1	clearBody	236
6.16.2.2	clone	236
6.16.2.3	cloneDataStructure	236
6.16.2.4	copyDataStructure	237
6.16.2.5	equals	237
6.16.2.6	getBodyBytes	237
6.16.2.7	getBodyLength	238
6.16.2.8	getDataStructureType	238
6.16.2.9	onSend	238
6.16.2.10	readBoolean	238
6.16.2.11	readByte	239
6.16.2.12	readBytes	239
6.16.2.13	readBytes	240
6.16.2.14	readChar	240
6.16.2.15	readDouble	240
6.16.2.16	readFloat	241
6.16.2.17	readInt	241

6.16.2.18 readLong	241
6.16.2.19 readShort	242
6.16.2.20 readString	242
6.16.2.21 readUnsignedShort	243
6.16.2.22 readUTF	243
6.16.2.23 reset	243
6.16.2.24 setBodyBytes	244
6.16.2.25 toString	244
6.16.2.26 writeBoolean	244
6.16.2.27 writeByte	244
6.16.2.28 writeBytes	245
6.16.2.29 writeBytes	245
6.16.2.30 writeChar	245
6.16.2.31 writeDouble	246
6.16.2.32 writeFloat	246
6.16.2.33 writeInt	246
6.16.2.34 writeLong	247
6.16.2.35 writeShort	247
6.16.2.36 writeString	247
6.16.2.37 writeUnsignedShort	248
6.16.2.38 writeUTF	248
6.16.3 Field Documentation	248
6.16.3.1 ID_ACTIVEMQBYTESMESSAGE	248
6.17 activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller	
Class Reference	249
6.17.1 Detailed Description	249
6.17.2 Constructor & Destructor Documentation	250
6.17.2.1 ActiveMQBytesMessageMarshaller	250
6.17.2.2 ~ActiveMQBytesMessageMarshaller	250
6.17.3 Member Function Documentation	250
6.17.3.1 createObject	250
6.17.3.2 getDataStructureType	250
6.17.3.3 looseMarshal	250
6.17.3.4 looseUnmarshal	251
6.17.3.5 tightMarshal1	251
6.17.3.6 tightMarshal2	251
6.17.3.7 tightUnmarshal	252

6.18	activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller	
	Class Reference	253
6.18.1	Detailed Description	253
6.18.2	Constructor & Destructor Documentation	254
	6.18.2.1 ActiveMQBytesMessageMarshaller	254
	6.18.2.2 ~ActiveMQBytesMessageMarshaller	254
6.18.3	Member Function Documentation	254
	6.18.3.1 createObject	254
	6.18.3.2 getDataStructureType	254
	6.18.3.3 looseMarshal	254
	6.18.3.4 looseUnmarshal	255
	6.18.3.5 tightMarshal1	255
	6.18.3.6 tightMarshal2	255
	6.18.3.7 tightUnmarshal	256
6.19	activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller	
	Class Reference	257
6.19.1	Detailed Description	257
6.19.2	Constructor & Destructor Documentation	258
	6.19.2.1 ActiveMQBytesMessageMarshaller	258
	6.19.2.2 ~ActiveMQBytesMessageMarshaller	258
6.19.3	Member Function Documentation	258
	6.19.3.1 createObject	258
	6.19.3.2 getDataStructureType	258
	6.19.3.3 looseMarshal	258
	6.19.3.4 looseUnmarshal	259
	6.19.3.5 tightMarshal1	259
	6.19.3.6 tightMarshal2	259
	6.19.3.7 tightUnmarshal	260
6.20	activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller	
	Class Reference	261
6.20.1	Detailed Description	261
6.20.2	Constructor & Destructor Documentation	262
	6.20.2.1 ActiveMQBytesMessageMarshaller	262
	6.20.2.2 ~ActiveMQBytesMessageMarshaller	262
6.20.3	Member Function Documentation	262
	6.20.3.1 createObject	262
	6.20.3.2 getDataStructureType	262

6.20.3.3	looseMarshal	262
6.20.3.4	looseUnmarshal	263
6.20.3.5	tightMarshal1	263
6.20.3.6	tightMarshal2	263
6.20.3.7	tightUnmarshal	264
6.21	activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller	
	Class Reference	265
6.21.1	Detailed Description	265
6.21.2	Constructor & Destructor Documentation	266
6.21.2.1	ActiveMQBytesMessageMarshaller	266
6.21.2.2	~ActiveMQBytesMessageMarshaller	266
6.21.3	Member Function Documentation	266
6.21.3.1	createObject	266
6.21.3.2	getDataStructureType	266
6.21.3.3	looseMarshal	266
6.21.3.4	looseUnmarshal	267
6.21.3.5	tightMarshal1	267
6.21.3.6	tightMarshal2	267
6.21.3.7	tightUnmarshal	268
6.22	activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller	
	Class Reference	269
6.22.1	Detailed Description	269
6.22.2	Constructor & Destructor Documentation	270
6.22.2.1	ActiveMQBytesMessageMarshaller	270
6.22.2.2	~ActiveMQBytesMessageMarshaller	270
6.22.3	Member Function Documentation	270
6.22.3.1	createObject	270
6.22.3.2	getDataStructureType	270
6.22.3.3	looseMarshal	270
6.22.3.4	looseUnmarshal	271
6.22.3.5	tightMarshal1	271
6.22.3.6	tightMarshal2	271
6.22.3.7	tightUnmarshal	272
6.23	activemq::core::ActiveMQConnection Class Reference	273
6.23.1	Detailed Description	278
6.23.2	Constructor & Destructor Documentation	278
6.23.2.1	ActiveMQConnection	278

6.23.2.2	~ActiveMQConnection	278
6.23.3	Member Function Documentation	278
6.23.3.1	addDispatcher	278
6.23.3.2	addProducer	278
6.23.3.3	addTransportListener	278
6.23.3.4	close	279
6.23.3.5	createSession	279
6.23.3.6	createSession	279
6.23.3.7	destroyDestination	279
6.23.3.8	destroyDestination	280
6.23.3.9	fire	280
6.23.3.10	getBrokerURL	280
6.23.3.11	getClientID	281
6.23.3.12	getCloseTimeout	281
6.23.3.13	getConnectionId	281
6.23.3.14	getConnectionInfo	281
6.23.3.15	getExceptionListener	281
6.23.3.16	getMetaData	282
6.23.3.17	getNextLocalTransactionId	282
6.23.3.18	getNextSessionId	282
6.23.3.19	getNextTempDestinationId	282
6.23.3.20	getPassword	283
6.23.3.21	getPrefetchPolicy	283
6.23.3.22	getProducerWindowSize	283
6.23.3.23	getRedeliveryPolicy	283
6.23.3.24	getSendTimeout	283
6.23.3.25	getTransport	284
6.23.3.26	getUsername	284
6.23.3.27	isAlwaysSyncSend	284
6.23.3.28	isClosed	284
6.23.3.29	isDispatchAsync	284
6.23.3.30	isStarted	284
6.23.3.31	isTransportFailed	285
6.23.3.32	isUseAsyncSend	285
6.23.3.33	isUseCompression	285
6.23.3.34	onCommand	285

6.23.3.35 oneway	285
6.23.3.36 onException	286
6.23.3.37 removeDispatcher	286
6.23.3.38 removeProducer	286
6.23.3.39 removeSession	286
6.23.3.40 removeTransportListener	286
6.23.3.41 sendPullRequest	287
6.23.3.42 setAlwaysSyncSend	287
6.23.3.43 setBrokerURL	287
6.23.3.44 setClientID	287
6.23.3.45 setCloseTimeout	288
6.23.3.46 setDefaultClientId	288
6.23.3.47 setDispatchAsync	288
6.23.3.48 setExceptionListener	288
6.23.3.49 setPassword	288
6.23.3.50 setPrefetchPolicy	289
6.23.3.51 setProducerWindowSize	289
6.23.3.52 setRedeliveryPolicy	289
6.23.3.53 setSendTimeout	289
6.23.3.54 setTransportInterruptionProcessingComplete	289
6.23.3.55 setUseAsyncSend	290
6.23.3.56 setUseCompression	290
6.23.3.57 setUsername	290
6.23.3.58 start	290
6.23.3.59 stop	290
6.23.3.60 syncRequest	291
6.23.3.61 transportInterrupted	291
6.23.3.62 transportResumed	291
6.24 activemq::core::ActiveMQConnectionFactory Class Reference	292
6.24.1 Constructor & Destructor Documentation	294
6.24.1.1 ActiveMQConnectionFactory	294
6.24.1.2 ActiveMQConnectionFactory	294
6.24.1.3 ~ActiveMQConnectionFactory	295
6.24.2 Member Function Documentation	295
6.24.2.1 createConnection	295
6.24.2.2 createConnection	295

6.24.2.3	createConnection	296
6.24.2.4	createConnection	296
6.24.2.5	getBrokerURL	296
6.24.2.6	getClientId	297
6.24.2.7	getCloseTimeout	297
6.24.2.8	getExceptionListener	297
6.24.2.9	getPassword	297
6.24.2.10	getPrefetchPolicy	297
6.24.2.11	getProducerWindowSize	298
6.24.2.12	getRedeliveryPolicy	298
6.24.2.13	getSendTimeout	298
6.24.2.14	getUsername	298
6.24.2.15	isAlwaysSyncSend	298
6.24.2.16	isDispatchAsync	299
6.24.2.17	isUseAsyncSend	299
6.24.2.18	isUseCompression	299
6.24.2.19	setAlwaysSyncSend	299
6.24.2.20	setBrokerURL	299
6.24.2.21	setClientId	299
6.24.2.22	setCloseTimeout	300
6.24.2.23	setDispatchAsync	300
6.24.2.24	setExceptionListener	300
6.24.2.25	setPassword	300
6.24.2.26	setPrefetchPolicy	300
6.24.2.27	setProducerWindowSize	301
6.24.2.28	setRedeliveryPolicy	301
6.24.2.29	setSendTimeout	301
6.24.2.30	setUseAsyncSend	301
6.24.2.31	setUseCompression	301
6.24.2.32	setUsername	302
6.24.3	Field Documentation	302
6.24.3.1	DEFAULT_URI	302
6.25	activemq::core::ActiveMQConnectionMetaData Class Reference	303
6.25.1	Detailed Description	303
6.25.2	Constructor & Destructor Documentation	304
6.25.2.1	ActiveMQConnectionMetaData	304

6.25.2.2	<code>~ActiveMQConnectionMetaData</code>	304
6.25.3	Member Function Documentation	304
6.25.3.1	<code>getCMSMajorVersion</code>	304
6.25.3.2	<code>getCMSMinorVersion</code>	304
6.25.3.3	<code>getCMSProviderName</code>	304
6.25.3.4	<code>getCMSVersion</code>	305
6.25.3.5	<code>getCMSXPropertyNames</code>	305
6.25.3.6	<code>getProviderMajorVersion</code>	305
6.25.3.7	<code>getProviderMinorVersion</code>	306
6.25.3.8	<code>getProviderVersion</code>	306
6.26	<code>activemq::core::ActiveMQConstants</code> Class Reference	307
6.26.1	Detailed Description	308
6.26.2	Member Enumeration Documentation	308
6.26.2.1	<code>AckType</code>	308
6.26.2.2	<code>DestinationActions</code>	308
6.26.2.3	<code>DestinationOption</code>	308
6.26.2.4	<code>TransactionState</code>	309
6.26.2.5	<code>URIParam</code>	309
6.26.3	Member Function Documentation	309
6.26.3.1	<code>toDestinationOption</code>	309
6.26.3.2	<code>toString</code>	309
6.26.3.3	<code>toString</code>	309
6.26.3.4	<code>toURIOption</code>	309
6.27	<code>activemq::core::ActiveMQConsumer</code> Class Reference	310
6.27.1	Constructor & Destructor Documentation	312
6.27.1.1	<code>ActiveMQConsumer</code>	312
6.27.1.2	<code>~ActiveMQConsumer</code>	312
6.27.2	Member Function Documentation	312
6.27.2.1	<code>acknowledge</code>	312
6.27.2.2	<code>acknowledge</code>	313
6.27.2.3	<code>afterMessageIsConsumed</code>	313
6.27.2.4	<code>beforeMessageIsConsumed</code>	313
6.27.2.5	<code>clearMessagesInProgress</code>	313
6.27.2.6	<code>close</code>	313
6.27.2.7	<code>commit</code>	314
6.27.2.8	<code>deliverAcks</code>	314

6.27.2.9	dequeue	314
6.27.2.10	dispatch	314
6.27.2.11	doClose	314
6.27.2.12	getConsumerId	315
6.27.2.13	getConsumerInfo	315
6.27.2.14	getLastDeliveredSequenceId	315
6.27.2.15	getMessageAvailableCount	315
6.27.2.16	getMessageListener	315
6.27.2.17	getMessageSelector	316
6.27.2.18	getRedeliveryPolicy	316
6.27.2.19	inProgressClearRequired	316
6.27.2.20	isClosed	316
6.27.2.21	isSynchronizationRegistered	316
6.27.2.22	iterate	316
6.27.2.23	receive	317
6.27.2.24	receive	317
6.27.2.25	receiveNoWait	317
6.27.2.26	rollback	317
6.27.2.27	setLastDeliveredSequenceId	318
6.27.2.28	setMessageListener	318
6.27.2.29	setRedeliveryPolicy	318
6.27.2.30	setSynchronizationRegistered	318
6.27.2.31	start	318
6.27.2.32	stop	319
6.28	activemq::library::ActiveMQCPP Class Reference	320
6.28.1	Constructor & Destructor Documentation	320
6.28.1.1	ActiveMQCPP	320
6.28.1.2	ActiveMQCPP	320
6.28.1.3	~ActiveMQCPP	320
6.28.2	Member Function Documentation	320
6.28.2.1	initializeLibrary	320
6.28.2.2	initializeLibrary	321
6.28.2.3	operator=	321
6.28.2.4	shutdownLibrary	321
6.29	activemq::commands::ActiveMQDestination Class Reference	322
6.29.1	Constructor & Destructor Documentation	324

6.29.1.1	ActiveMQDestination	324
6.29.1.2	ActiveMQDestination	324
6.29.1.3	~ActiveMQDestination	324
6.29.2	Member Function Documentation	324
6.29.2.1	cloneDataStructure	324
6.29.2.2	copyDataStructure	325
6.29.2.3	createDestination	325
6.29.2.4	createTemporaryName	325
6.29.2.5	equals	326
6.29.2.6	getClientId	326
6.29.2.7	getCMSDestination	326
6.29.2.8	getDataStructureType	326
6.29.2.9	getDestinationType	327
6.29.2.10	getOptions	327
6.29.2.11	getOrderedTarget	327
6.29.2.12	getPhysicalName	327
6.29.2.13	getPhysicalName	327
6.29.2.14	isAdvisory	328
6.29.2.15	isComposite	328
6.29.2.16	isConnectionAdvisory	328
6.29.2.17	isConsumerAdvisory	328
6.29.2.18	isExclusive	328
6.29.2.19	isOrdered	328
6.29.2.20	isProducerAdvisory	329
6.29.2.21	isQueue	329
6.29.2.22	isTemporary	329
6.29.2.23	isTopic	329
6.29.2.24	isWildcard	329
6.29.2.25	setAdvisory	329
6.29.2.26	setExclusive	330
6.29.2.27	setOrdered	330
6.29.2.28	setOrderedTarget	330
6.29.2.29	setPhysicalName	330
6.29.2.30	toString	330
6.29.3	Field Documentation	331
6.29.3.1	advisory	331

6.29.3.2	ADVISORY_PREFIX	331
6.29.3.3	COMPOSITE_SEPARATOR	331
6.29.3.4	CONNECTION_ADVISORY_PREFIX	331
6.29.3.5	CONSUMER_ADVISORY_PREFIX	331
6.29.3.6	DEFAULT_ORDERED_TARGET	331
6.29.3.7	exclusive	332
6.29.3.8	ID_ACTIVEMQDESTINATION	332
6.29.3.9	options	332
6.29.3.10	ordered	332
6.29.3.11	orderedTarget	332
6.29.3.12	physicalName	332
6.29.3.13	PRODUCER_ADVISORY_PREFIX	332
6.29.3.14	QUEUE_QUALIFIED_PREFIX	332
6.29.3.15	TEMP_POSTFIX	332
6.29.3.16	TEMP_PREFIX	332
6.29.3.17	TEMP_QUEUE_QUALIFIED_PREFIX	332
6.29.3.18	TEMP_TOPIC_QUALIFIED_PREFIX	332
6.29.3.19	TOPIC_QUALIFIED_PREFIX	332
6.30	activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller	
	Class Reference	333
6.30.1	Detailed Description	333
6.30.2	Constructor & Destructor Documentation	334
6.30.2.1	ActiveMQDestinationMarshaller	334
6.30.2.2	~ActiveMQDestinationMarshaller	334
6.30.3	Member Function Documentation	334
6.30.3.1	looseMarshal	334
6.30.3.2	looseUnmarshal	334
6.30.3.3	tightMarshal1	335
6.30.3.4	tightMarshal2	335
6.30.3.5	tightUnmarshal	336
6.31	activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller	
	Class Reference	337
6.31.1	Detailed Description	337
6.31.2	Constructor & Destructor Documentation	338
6.31.2.1	ActiveMQDestinationMarshaller	338
6.31.2.2	~ActiveMQDestinationMarshaller	338
6.31.3	Member Function Documentation	338

6.31.3.1	looseMarshal	338
6.31.3.2	looseUnmarshal	338
6.31.3.3	tightMarshal1	339
6.31.3.4	tightMarshal2	339
6.31.3.5	tightUnmarshal	340
6.32	activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	
	Class Reference	341
6.32.1	Detailed Description	341
6.32.2	Constructor & Destructor Documentation	342
	6.32.2.1 ActiveMQDestinationMarshaller	342
	6.32.2.2 ~ActiveMQDestinationMarshaller	342
6.32.3	Member Function Documentation	342
	6.32.3.1 looseMarshal	342
	6.32.3.2 looseUnmarshal	342
	6.32.3.3 tightMarshal1	343
	6.32.3.4 tightMarshal2	343
	6.32.3.5 tightUnmarshal	344
6.33	activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	
	Class Reference	345
6.33.1	Detailed Description	345
6.33.2	Constructor & Destructor Documentation	346
	6.33.2.1 ActiveMQDestinationMarshaller	346
	6.33.2.2 ~ActiveMQDestinationMarshaller	346
6.33.3	Member Function Documentation	346
	6.33.3.1 looseMarshal	346
	6.33.3.2 looseUnmarshal	346
	6.33.3.3 tightMarshal1	347
	6.33.3.4 tightMarshal2	347
	6.33.3.5 tightUnmarshal	348
6.34	activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller	
	Class Reference	349
6.34.1	Detailed Description	349
6.34.2	Constructor & Destructor Documentation	350
	6.34.2.1 ActiveMQDestinationMarshaller	350
	6.34.2.2 ~ActiveMQDestinationMarshaller	350
6.34.3	Member Function Documentation	350
	6.34.3.1 looseMarshal	350

6.34.3.2	looseUnmarshal	350
6.34.3.3	tightMarshal1	351
6.34.3.4	tightMarshal2	351
6.34.3.5	tightUnmarshal	352
6.35	activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller	
	Class Reference	353
6.35.1	Detailed Description	353
6.35.2	Constructor & Destructor Documentation	354
6.35.2.1	ActiveMQDestinationMarshaller	354
6.35.2.2	~ActiveMQDestinationMarshaller	354
6.35.3	Member Function Documentation	354
6.35.3.1	looseMarshal	354
6.35.3.2	looseUnmarshal	354
6.35.3.3	tightMarshal1	355
6.35.3.4	tightMarshal2	355
6.35.3.5	tightUnmarshal	356
6.36	activemq::exceptions::ActiveMQException Class Reference	357
6.36.1	Constructor & Destructor Documentation	357
6.36.1.1	ActiveMQException	357
6.36.1.2	ActiveMQException	357
6.36.1.3	ActiveMQException	358
6.36.1.4	ActiveMQException	358
6.36.1.5	~ActiveMQException	358
6.36.2	Member Function Documentation	358
6.36.2.1	clone	358
6.36.2.2	convertToCMSException	358
6.37	activemq::commands::ActiveMQMapMessage Class Reference	360
6.37.1	Constructor & Destructor Documentation	363
6.37.1.1	ActiveMQMapMessage	363
6.37.1.2	~ActiveMQMapMessage	363
6.37.2	Member Function Documentation	363
6.37.2.1	beforeMarshal	363
6.37.2.2	checkMapIsUnmarshalled	363
6.37.2.3	clearBody	363
6.37.2.4	clone	363
6.37.2.5	cloneDataStructure	364
6.37.2.6	copyDataStructure	364

6.37.2.7	equals	364
6.37.2.8	getBoolean	364
6.37.2.9	getByte	365
6.37.2.10	getBytes	365
6.37.2.11	getChar	365
6.37.2.12	getDataStructureType	366
6.37.2.13	getDouble	366
6.37.2.14	getFloat	366
6.37.2.15	getInt	366
6.37.2.16	getLong	367
6.37.2.17	getMap	367
6.37.2.18	getMap	367
6.37.2.19	getMapNames	367
6.37.2.20	getShort	368
6.37.2.21	getString	368
6.37.2.22	isMarshalAware	368
6.37.2.23	itemExists	368
6.37.2.24	setBoolean	369
6.37.2.25	setByte	369
6.37.2.26	setBytes	370
6.37.2.27	setChar	370
6.37.2.28	setDouble	370
6.37.2.29	setFloat	371
6.37.2.30	setInt	371
6.37.2.31	setLong	371
6.37.2.32	setShort	372
6.37.2.33	setString	372
6.37.2.34	toString	372
6.37.3	Field Documentation	372
6.37.3.1	ID_ACTIVEMQMAPMESSAGE	372
6.38	activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller	
	Class Reference	374
6.38.1	Detailed Description	374
6.38.2	Constructor & Destructor Documentation	375
6.38.2.1	ActiveMQMapMessageMarshaller	375
6.38.2.2	~ActiveMQMapMessageMarshaller	375
6.38.3	Member Function Documentation	375

6.38.3.1	createObject	375
6.38.3.2	getDataStructureType	375
6.38.3.3	looseMarshal	375
6.38.3.4	looseUnmarshal	376
6.38.3.5	tightMarshal1	376
6.38.3.6	tightMarshal2	376
6.38.3.7	tightUnmarshal	377
6.39	activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller	
	Class Reference	378
6.39.1	Detailed Description	378
6.39.2	Constructor & Destructor Documentation	379
6.39.2.1	ActiveMQMapMessageMarshaller	379
6.39.2.2	~ActiveMQMapMessageMarshaller	379
6.39.3	Member Function Documentation	379
6.39.3.1	createObject	379
6.39.3.2	getDataStructureType	379
6.39.3.3	looseMarshal	379
6.39.3.4	looseUnmarshal	380
6.39.3.5	tightMarshal1	380
6.39.3.6	tightMarshal2	380
6.39.3.7	tightUnmarshal	381
6.40	activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller	
	Class Reference	382
6.40.1	Detailed Description	382
6.40.2	Constructor & Destructor Documentation	383
6.40.2.1	ActiveMQMapMessageMarshaller	383
6.40.2.2	~ActiveMQMapMessageMarshaller	383
6.40.3	Member Function Documentation	383
6.40.3.1	createObject	383
6.40.3.2	getDataStructureType	383
6.40.3.3	looseMarshal	383
6.40.3.4	looseUnmarshal	384
6.40.3.5	tightMarshal1	384
6.40.3.6	tightMarshal2	384
6.40.3.7	tightUnmarshal	385
6.41	activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	
	Class Reference	386

6.41.1	Detailed Description	386
6.41.2	Constructor & Destructor Documentation	387
6.41.2.1	ActiveMQMapMessageMarshaller	387
6.41.2.2	~ActiveMQMapMessageMarshaller	387
6.41.3	Member Function Documentation	387
6.41.3.1	createObject	387
6.41.3.2	getDataStructureType	387
6.41.3.3	looseMarshal	387
6.41.3.4	looseUnmarshal	388
6.41.3.5	tightMarshal1	388
6.41.3.6	tightMarshal2	388
6.41.3.7	tightUnmarshal	389
6.42	activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller	
	Class Reference	390
6.42.1	Detailed Description	390
6.42.2	Constructor & Destructor Documentation	391
6.42.2.1	ActiveMQMapMessageMarshaller	391
6.42.2.2	~ActiveMQMapMessageMarshaller	391
6.42.3	Member Function Documentation	391
6.42.3.1	createObject	391
6.42.3.2	getDataStructureType	391
6.42.3.3	looseMarshal	391
6.42.3.4	looseUnmarshal	392
6.42.3.5	tightMarshal1	392
6.42.3.6	tightMarshal2	392
6.42.3.7	tightUnmarshal	393
6.43	activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller	
	Class Reference	394
6.43.1	Detailed Description	394
6.43.2	Constructor & Destructor Documentation	395
6.43.2.1	ActiveMQMapMessageMarshaller	395
6.43.2.2	~ActiveMQMapMessageMarshaller	395
6.43.3	Member Function Documentation	395
6.43.3.1	createObject	395
6.43.3.2	getDataStructureType	395
6.43.3.3	looseMarshal	395
6.43.3.4	looseUnmarshal	396

6.43.3.5	tightMarshal1	396
6.43.3.6	tightMarshal2	396
6.43.3.7	tightUnmarshal	397
6.44	activemq::commands::ActiveMQMessage Class Reference	398
6.44.1	Constructor & Destructor Documentation	398
6.44.1.1	ActiveMQMessage	398
6.44.1.2	~ActiveMQMessage	398
6.44.2	Member Function Documentation	398
6.44.2.1	clone	398
6.44.2.2	cloneDataStructure	399
6.44.2.3	copyDataStructure	399
6.44.2.4	equals	399
6.44.2.5	getDataStructureType	399
6.44.2.6	toString	400
6.44.3	Field Documentation	400
6.44.3.1	ID_ACTIVEMQMESSAGE	400
6.45	activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller Class Reference	401
6.45.1	Detailed Description	401
6.45.2	Constructor & Destructor Documentation	402
6.45.2.1	ActiveMQMessageMarshaller	402
6.45.2.2	~ActiveMQMessageMarshaller	402
6.45.3	Member Function Documentation	402
6.45.3.1	createObject	402
6.45.3.2	getDataStructureType	402
6.45.3.3	looseMarshal	402
6.45.3.4	looseUnmarshal	403
6.45.3.5	tightMarshal1	403
6.45.3.6	tightMarshal2	403
6.45.3.7	tightUnmarshal	404
6.46	activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller Class Reference	405
6.46.1	Detailed Description	405
6.46.2	Constructor & Destructor Documentation	406
6.46.2.1	ActiveMQMessageMarshaller	406
6.46.2.2	~ActiveMQMessageMarshaller	406
6.46.3	Member Function Documentation	406

6.46.3.1	createObject	406
6.46.3.2	getDataStructureType	406
6.46.3.3	looseMarshal	406
6.46.3.4	looseUnmarshal	407
6.46.3.5	tightMarshal1	407
6.46.3.6	tightMarshal2	407
6.46.3.7	tightUnmarshal	408
6.47	activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller Class	
	Reference	409
6.47.1	Detailed Description	409
6.47.2	Constructor & Destructor Documentation	410
6.47.2.1	ActiveMQMessageMarshaller	410
6.47.2.2	~ActiveMQMessageMarshaller	410
6.47.3	Member Function Documentation	410
6.47.3.1	createObject	410
6.47.3.2	getDataStructureType	410
6.47.3.3	looseMarshal	410
6.47.3.4	looseUnmarshal	411
6.47.3.5	tightMarshal1	411
6.47.3.6	tightMarshal2	411
6.47.3.7	tightUnmarshal	412
6.48	activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller Class	
	Reference	413
6.48.1	Detailed Description	413
6.48.2	Constructor & Destructor Documentation	414
6.48.2.1	ActiveMQMessageMarshaller	414
6.48.2.2	~ActiveMQMessageMarshaller	414
6.48.3	Member Function Documentation	414
6.48.3.1	createObject	414
6.48.3.2	getDataStructureType	414
6.48.3.3	looseMarshal	414
6.48.3.4	looseUnmarshal	415
6.48.3.5	tightMarshal1	415
6.48.3.6	tightMarshal2	415
6.48.3.7	tightUnmarshal	416
6.49	activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller Class	
	Reference	417

6.49.1	Detailed Description	417
6.49.2	Constructor & Destructor Documentation	418
6.49.2.1	ActiveMQMessageMarshaller	418
6.49.2.2	~ActiveMQMessageMarshaller	418
6.49.3	Member Function Documentation	418
6.49.3.1	createObject	418
6.49.3.2	getDataStructureType	418
6.49.3.3	looseMarshal	418
6.49.3.4	looseUnmarshal	419
6.49.3.5	tightMarshal1	419
6.49.3.6	tightMarshal2	419
6.49.3.7	tightUnmarshal	420
6.50	activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller Class Reference	421
6.50.1	Detailed Description	421
6.50.2	Constructor & Destructor Documentation	422
6.50.2.1	ActiveMQMessageMarshaller	422
6.50.2.2	~ActiveMQMessageMarshaller	422
6.50.3	Member Function Documentation	422
6.50.3.1	createObject	422
6.50.3.2	getDataStructureType	422
6.50.3.3	looseMarshal	422
6.50.3.4	looseUnmarshal	423
6.50.3.5	tightMarshal1	423
6.50.3.6	tightMarshal2	423
6.50.3.7	tightUnmarshal	424
6.51	activemq::commands::ActiveMQMessageTemplate< T > Class Template Reference	425
6.51.1	Constructor & Destructor Documentation	428
6.51.1.1	ActiveMQMessageTemplate	428
6.51.1.2	~ActiveMQMessageTemplate	428
6.51.2	Member Function Documentation	428
6.51.2.1	acknowledge	428
6.51.2.2	clearBody	428
6.51.2.3	clearProperties	429
6.51.2.4	equals	429
6.51.2.5	failIfReadOnlyBody	429
6.51.2.6	failIfReadOnlyProperties	429

6.51.2.7 failIfWriteOnlyBody	429
6.51.2.8 getBooleanProperty	429
6.51.2.9 getByteProperty	430
6.51.2.10 getCMSCorrelationID	430
6.51.2.11 getCMSDeliveryMode	430
6.51.2.12 getCMSDestination	431
6.51.2.13 getCMSExpiration	431
6.51.2.14 getCMSMessageID	431
6.51.2.15 getCMSPriority	432
6.51.2.16 getCMSRedelivered	432
6.51.2.17 getCMSReplyTo	432
6.51.2.18 getCMSTimestamp	432
6.51.2.19 getCMSType	433
6.51.2.20 getDoubleProperty	433
6.51.2.21 getFloatProperty	433
6.51.2.22 getIntProperty	434
6.51.2.23 getLongProperty	434
6.51.2.24 getPropertyNames	435
6.51.2.25 getShortProperty	435
6.51.2.26 getStringProperty	435
6.51.2.27 onSend	436
6.51.2.28 propertyExists	436
6.51.2.29 setBooleanProperty	436
6.51.2.30 setByteProperty	436
6.51.2.31 setCMSCorrelationID	437
6.51.2.32 setCMSDeliveryMode	437
6.51.2.33 setCMSDestination	437
6.51.2.34 setCMSExpiration	438
6.51.2.35 setCMSMessageID	438
6.51.2.36 setCMSPriority	438
6.51.2.37 setCMSRedelivered	438
6.51.2.38 setCMSReplyTo	439
6.51.2.39 setCMSTimestamp	439
6.51.2.40 setCMSType	439
6.51.2.41 setDoubleProperty	440
6.51.2.42 setFloatProperty	440

6.51.2.43	setIntProperty	440
6.51.2.44	setLongProperty	441
6.51.2.45	setShortProperty	441
6.51.2.46	setStringProperty	441
6.52	activemq::commands::ActiveMQObjectMessage Class Reference	443
6.52.1	Constructor & Destructor Documentation	444
6.52.1.1	ActiveMQObjectMessage	444
6.52.1.2	~ActiveMQObjectMessage	444
6.52.2	Member Function Documentation	444
6.52.2.1	clone	444
6.52.2.2	cloneDataStructure	444
6.52.2.3	copyDataStructure	444
6.52.2.4	equals	444
6.52.2.5	getDataStructureType	445
6.52.2.6	toString	445
6.52.3	Field Documentation	445
6.52.3.1	ID_ACTIVEMQOBJECTMESSAGE	445
6.53	activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller Class Reference	446
6.53.1	Detailed Description	446
6.53.2	Constructor & Destructor Documentation	447
6.53.2.1	ActiveMQObjectMessageMarshaller	447
6.53.2.2	~ActiveMQObjectMessageMarshaller	447
6.53.3	Member Function Documentation	447
6.53.3.1	createObject	447
6.53.3.2	getDataStructureType	447
6.53.3.3	looseMarshal	447
6.53.3.4	looseUnmarshal	448
6.53.3.5	tightMarshal1	448
6.53.3.6	tightMarshal2	448
6.53.3.7	tightUnmarshal	449
6.54	activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller Class Reference	450
6.54.1	Detailed Description	450
6.54.2	Constructor & Destructor Documentation	451
6.54.2.1	ActiveMQObjectMessageMarshaller	451
6.54.2.2	~ActiveMQObjectMessageMarshaller	451

6.54.3	Member Function Documentation	451
6.54.3.1	createObject	451
6.54.3.2	getDataStructureType	451
6.54.3.3	looseMarshal	451
6.54.3.4	looseUnmarshal	452
6.54.3.5	tightMarshal1	452
6.54.3.6	tightMarshal2	452
6.54.3.7	tightUnmarshal	453
6.55	activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller Class Reference	454
6.55.1	Detailed Description	454
6.55.2	Constructor & Destructor Documentation	455
6.55.2.1	ActiveMQObjectMessageMarshaller	455
6.55.2.2	~ActiveMQObjectMessageMarshaller	455
6.55.3	Member Function Documentation	455
6.55.3.1	createObject	455
6.55.3.2	getDataStructureType	455
6.55.3.3	looseMarshal	455
6.55.3.4	looseUnmarshal	456
6.55.3.5	tightMarshal1	456
6.55.3.6	tightMarshal2	456
6.55.3.7	tightUnmarshal	457
6.56	activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller Class Reference	458
6.56.1	Detailed Description	458
6.56.2	Constructor & Destructor Documentation	459
6.56.2.1	ActiveMQObjectMessageMarshaller	459
6.56.2.2	~ActiveMQObjectMessageMarshaller	459
6.56.3	Member Function Documentation	459
6.56.3.1	createObject	459
6.56.3.2	getDataStructureType	459
6.56.3.3	looseMarshal	459
6.56.3.4	looseUnmarshal	460
6.56.3.5	tightMarshal1	460
6.56.3.6	tightMarshal2	460
6.56.3.7	tightUnmarshal	461

6.57	activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller	
	Class Reference	462
6.57.1	Detailed Description	462
6.57.2	Constructor & Destructor Documentation	463
	6.57.2.1 ActiveMQObjectMessageMarshaller	463
	6.57.2.2 ~ActiveMQObjectMessageMarshaller	463
6.57.3	Member Function Documentation	463
	6.57.3.1 createObject	463
	6.57.3.2 getDataStructureType	463
	6.57.3.3 looseMarshal	463
	6.57.3.4 looseUnmarshal	464
	6.57.3.5 tightMarshal1	464
	6.57.3.6 tightMarshal2	464
	6.57.3.7 tightUnmarshal	465
6.58	activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller	
	Class Reference	466
6.58.1	Detailed Description	466
6.58.2	Constructor & Destructor Documentation	467
	6.58.2.1 ActiveMQObjectMessageMarshaller	467
	6.58.2.2 ~ActiveMQObjectMessageMarshaller	467
6.58.3	Member Function Documentation	467
	6.58.3.1 createObject	467
	6.58.3.2 getDataStructureType	467
	6.58.3.3 looseMarshal	467
	6.58.3.4 looseUnmarshal	468
	6.58.3.5 tightMarshal1	468
	6.58.3.6 tightMarshal2	468
	6.58.3.7 tightUnmarshal	469
6.59	activemq::core::ActiveMQProducer Class Reference	470
6.59.1	Constructor & Destructor Documentation	471
	6.59.1.1 ActiveMQProducer	471
	6.59.1.2 ~ActiveMQProducer	472
6.59.2	Member Function Documentation	472
	6.59.2.1 close	472
	6.59.2.2 getDeliveryMode	472
	6.59.2.3 getDisableMessageID	472
	6.59.2.4 getDisableMessageTimeStamp	472

6.59.2.5	getPriority	473
6.59.2.6	getProducerId	473
6.59.2.7	getProducerInfo	473
6.59.2.8	getSendTimeout	473
6.59.2.9	getTimeToLive	473
6.59.2.10	isClosed	474
6.59.2.11	onProducerAck	474
6.59.2.12	send	474
6.59.2.13	send	475
6.59.2.14	send	475
6.59.2.15	send	476
6.59.2.16	setDeliveryMode	476
6.59.2.17	setDisableMessageID	476
6.59.2.18	setDisableMessageTimeStamp	476
6.59.2.19	setPriority	477
6.59.2.20	setSendTimeout	477
6.59.2.21	setTimeToLive	477
6.60	activemq::util::ActiveMQProperties Class Reference	478
6.60.1	Detailed Description	479
6.60.2	Constructor & Destructor Documentation	479
6.60.2.1	ActiveMQProperties	479
6.60.2.2	~ActiveMQProperties	479
6.60.3	Member Function Documentation	479
6.60.3.1	clear	479
6.60.3.2	clone	479
6.60.3.3	copy	479
6.60.3.4	getProperties	480
6.60.3.5	getProperties	480
6.60.3.6	getProperty	480
6.60.3.7	getProperty	480
6.60.3.8	hasProperty	480
6.60.3.9	isEmpty	481
6.60.3.10	remove	481
6.60.3.11	setProperties	481
6.60.3.12	setProperty	481
6.60.3.13	toArray	481

6.60.3.14	toString	481
6.61	activemq::commands::ActiveMQQueue Class Reference	483
6.61.1	Constructor & Destructor Documentation	484
6.61.1.1	ActiveMQQueue	484
6.61.1.2	ActiveMQQueue	484
6.61.1.3	~ActiveMQQueue	484
6.61.2	Member Function Documentation	484
6.61.2.1	clone	484
6.61.2.2	cloneDataStructure	484
6.61.2.3	copy	484
6.61.2.4	copyDataStructure	484
6.61.2.5	equals	485
6.61.2.6	getCMSDestination	485
6.61.2.7	getCMSProperties	485
6.61.2.8	getDataStructureType	485
6.61.2.9	getDestinationType	485
6.61.2.10	getQueueName	486
6.61.2.11	toString	486
6.61.3	Field Documentation	486
6.61.3.1	ID_ACTIVEMQQUEUE	486
6.62	activemq::core::ActiveMQQueueBrowser Class Reference	487
6.62.1	Constructor & Destructor Documentation	488
6.62.1.1	ActiveMQQueueBrowser	488
6.62.1.2	~ActiveMQQueueBrowser	488
6.62.2	Member Function Documentation	488
6.62.2.1	close	488
6.62.2.2	getEnumeration	488
6.62.2.3	getMessageSelector	488
6.62.2.4	getQueue	489
6.62.2.5	hasMoreMessages	489
6.62.2.6	nextMessage	489
6.62.3	Friends And Related Function Documentation	490
6.62.3.1	Browser	490
6.63	activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller Class Reference	491
6.63.1	Detailed Description	491
6.63.2	Constructor & Destructor Documentation	492

6.63.2.1	ActiveMQQueueMarshaller	492
6.63.2.2	~ActiveMQQueueMarshaller	492
6.63.3	Member Function Documentation	492
6.63.3.1	createObject	492
6.63.3.2	getDataStructureType	492
6.63.3.3	looseMarshal	492
6.63.3.4	looseUnmarshal	493
6.63.3.5	tightMarshal1	493
6.63.3.6	tightMarshal2	493
6.63.3.7	tightUnmarshal	494
6.64	activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller Class	
	Reference	495
6.64.1	Detailed Description	495
6.64.2	Constructor & Destructor Documentation	496
6.64.2.1	ActiveMQQueueMarshaller	496
6.64.2.2	~ActiveMQQueueMarshaller	496
6.64.3	Member Function Documentation	496
6.64.3.1	createObject	496
6.64.3.2	getDataStructureType	496
6.64.3.3	looseMarshal	496
6.64.3.4	looseUnmarshal	497
6.64.3.5	tightMarshal1	497
6.64.3.6	tightMarshal2	497
6.64.3.7	tightUnmarshal	498
6.65	activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller Class	
	Reference	499
6.65.1	Detailed Description	499
6.65.2	Constructor & Destructor Documentation	500
6.65.2.1	ActiveMQQueueMarshaller	500
6.65.2.2	~ActiveMQQueueMarshaller	500
6.65.3	Member Function Documentation	500
6.65.3.1	createObject	500
6.65.3.2	getDataStructureType	500
6.65.3.3	looseMarshal	500
6.65.3.4	looseUnmarshal	501
6.65.3.5	tightMarshal1	501
6.65.3.6	tightMarshal2	501

6.65.3.7	tightUnmarshal	502
6.66	activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	Class
	Reference	503
6.66.1	Detailed Description	503
6.66.2	Constructor & Destructor Documentation	504
6.66.2.1	ActiveMQQueueMarshaller	504
6.66.2.2	~ActiveMQQueueMarshaller	504
6.66.3	Member Function Documentation	504
6.66.3.1	createObject	504
6.66.3.2	getDataStructureType	504
6.66.3.3	looseMarshal	504
6.66.3.4	looseUnmarshal	505
6.66.3.5	tightMarshal1	505
6.66.3.6	tightMarshal2	505
6.66.3.7	tightUnmarshal	506
6.67	activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller	Class
	Reference	507
6.67.1	Detailed Description	507
6.67.2	Constructor & Destructor Documentation	508
6.67.2.1	ActiveMQQueueMarshaller	508
6.67.2.2	~ActiveMQQueueMarshaller	508
6.67.3	Member Function Documentation	508
6.67.3.1	createObject	508
6.67.3.2	getDataStructureType	508
6.67.3.3	looseMarshal	508
6.67.3.4	looseUnmarshal	509
6.67.3.5	tightMarshal1	509
6.67.3.6	tightMarshal2	509
6.67.3.7	tightUnmarshal	510
6.68	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller	Class
	Reference	511
6.68.1	Detailed Description	511
6.68.2	Constructor & Destructor Documentation	512
6.68.2.1	ActiveMQQueueMarshaller	512
6.68.2.2	~ActiveMQQueueMarshaller	512
6.68.3	Member Function Documentation	512
6.68.3.1	createObject	512

6.68.3.2	getDataStructureType	512
6.68.3.3	looseMarshal	512
6.68.3.4	looseUnmarshal	513
6.68.3.5	tightMarshal1	513
6.68.3.6	tightMarshal2	513
6.68.3.7	tightUnmarshal	514
6.69	activemq::core::ActiveMQSession Class Reference	515
6.69.1	Constructor & Destructor Documentation	519
6.69.1.1	ActiveMQSession	519
6.69.1.2	~ActiveMQSession	519
6.69.2	Member Function Documentation	519
6.69.2.1	acknowledge	519
6.69.2.2	addConsumer	519
6.69.2.3	addProducer	519
6.69.2.4	clearMessagesInProgress	520
6.69.2.5	close	520
6.69.2.6	commit	520
6.69.2.7	createBrowser	520
6.69.2.8	createBrowser	521
6.69.2.9	createBytesMessage	521
6.69.2.10	createBytesMessage	521
6.69.2.11	createConsumer	522
6.69.2.12	createConsumer	522
6.69.2.13	createConsumer	522
6.69.2.14	createDurableConsumer	523
6.69.2.15	createMapMessage	523
6.69.2.16	createMessage	523
6.69.2.17	createProducer	524
6.69.2.18	createQueue	524
6.69.2.19	createStreamMessage	524
6.69.2.20	createTemporaryQueue	524
6.69.2.21	createTemporaryTopic	525
6.69.2.22	createTextMessage	525
6.69.2.23	createTextMessage	525
6.69.2.24	createTopic	526
6.69.2.25	deliverAcks	526

6.69.2.26	dispatch	526
6.69.2.27	doStartTransaction	526
6.69.2.28	fire	526
6.69.2.29	getAcknowledgeMode	526
6.69.2.30	getConnection	527
6.69.2.31	getExceptionListener	527
6.69.2.32	getLastDeliveredSequenceId	527
6.69.2.33	getNextConsumerId	527
6.69.2.34	getNextProducerId	527
6.69.2.35	getSessionId	528
6.69.2.36	getSessionInfo	528
6.69.2.37	getTransactionContext	528
6.69.2.38	isAutoAcknowledge	528
6.69.2.39	isClientAcknowledge	528
6.69.2.40	isDupsOkAcknowledge	528
6.69.2.41	isIndividualAcknowledge	528
6.69.2.42	isStarted	529
6.69.2.43	isTransacted	529
6.69.2.44	oneway	529
6.69.2.45	recover	529
6.69.2.46	redispatch	530
6.69.2.47	removeConsumer	530
6.69.2.48	removeProducer	530
6.69.2.49	rollback	530
6.69.2.50	send	531
6.69.2.51	setLastDeliveredSequenceId	531
6.69.2.52	start	531
6.69.2.53	stop	531
6.69.2.54	syncRequest	531
6.69.2.55	unsubscribe	532
6.69.2.56	wakeup	532
6.69.3	Friends And Related Function Documentation	532
6.69.3.1	ActiveMQSessionExecutor	532
6.70	activemq::core::ActiveMQSessionExecutor Class Reference	533
6.70.1	Detailed Description	534
6.70.2	Constructor & Destructor Documentation	534

6.70.2.1	ActiveMQSessionExecutor	534
6.70.2.2	~ActiveMQSessionExecutor	534
6.70.3	Member Function Documentation	534
6.70.3.1	clear	534
6.70.3.2	clearMessagesInProgress	534
6.70.3.3	close	534
6.70.3.4	execute	534
6.70.3.5	executeFirst	534
6.70.3.6	getUnconsumedMessages	535
6.70.3.7	hasUnconsumedMessages	535
6.70.3.8	isEmpty	535
6.70.3.9	isRunning	535
6.70.3.10	iterate	535
6.70.3.11	start	535
6.70.3.12	stop	536
6.70.3.13	wakeup	536
6.71	activemq::commands::ActiveMQStreamMessage Class Reference	537
6.71.1	Constructor & Destructor Documentation	540
6.71.1.1	ActiveMQStreamMessage	540
6.71.1.2	~ActiveMQStreamMessage	540
6.71.2	Member Function Documentation	540
6.71.2.1	clearBody	540
6.71.2.2	clone	540
6.71.2.3	cloneDataStructure	540
6.71.2.4	copyDataStructure	540
6.71.2.5	equals	541
6.71.2.6	getDataStructureType	541
6.71.2.7	onSend	541
6.71.2.8	readBoolean	541
6.71.2.9	readByte	542
6.71.2.10	readBytes	542
6.71.2.11	readBytes	543
6.71.2.12	readChar	543
6.71.2.13	readDouble	544
6.71.2.14	readFloat	544
6.71.2.15	readInt	545

6.71.2.16	readLong	545
6.71.2.17	readShort	545
6.71.2.18	readString	546
6.71.2.19	readUnsignedShort	546
6.71.2.20	reset	547
6.71.2.21	toString	547
6.71.2.22	writeBoolean	547
6.71.2.23	writeByte	547
6.71.2.24	writeBytes	548
6.71.2.25	writeBytes	548
6.71.2.26	writeChar	548
6.71.2.27	writeDouble	549
6.71.2.28	writeFloat	549
6.71.2.29	writeInt	549
6.71.2.30	writeLong	550
6.71.2.31	writeShort	550
6.71.2.32	writeString	550
6.71.2.33	writeUnsignedShort	551
6.71.3	Field Documentation	551
6.71.3.1	ID_ACTIVEMQSTREAMMESSAGE	551
6.72	activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller	
	Class Reference	552
6.72.1	Detailed Description	552
6.72.2	Constructor & Destructor Documentation	553
6.72.2.1	ActiveMQStreamMessageMarshaller	553
6.72.2.2	~ActiveMQStreamMessageMarshaller	553
6.72.3	Member Function Documentation	553
6.72.3.1	createObject	553
6.72.3.2	getDataStructureType	553
6.72.3.3	looseMarshal	553
6.72.3.4	looseUnmarshal	554
6.72.3.5	tightMarshal1	554
6.72.3.6	tightMarshal2	554
6.72.3.7	tightUnmarshal	555
6.73	activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller	
	Class Reference	556
6.73.1	Detailed Description	556

6.73.2	Constructor & Destructor Documentation	557
6.73.2.1	ActiveMQStreamMessageMarshaller	557
6.73.2.2	~ActiveMQStreamMessageMarshaller	557
6.73.3	Member Function Documentation	557
6.73.3.1	createObject	557
6.73.3.2	getDataStructureType	557
6.73.3.3	looseMarshal	557
6.73.3.4	looseUnmarshal	558
6.73.3.5	tightMarshal1	558
6.73.3.6	tightMarshal2	558
6.73.3.7	tightUnmarshal	559
6.74	activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller	
	Class Reference	560
6.74.1	Detailed Description	560
6.74.2	Constructor & Destructor Documentation	561
6.74.2.1	ActiveMQStreamMessageMarshaller	561
6.74.2.2	~ActiveMQStreamMessageMarshaller	561
6.74.3	Member Function Documentation	561
6.74.3.1	createObject	561
6.74.3.2	getDataStructureType	561
6.74.3.3	looseMarshal	561
6.74.3.4	looseUnmarshal	562
6.74.3.5	tightMarshal1	562
6.74.3.6	tightMarshal2	562
6.74.3.7	tightUnmarshal	563
6.75	activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller	
	Class Reference	564
6.75.1	Detailed Description	564
6.75.2	Constructor & Destructor Documentation	565
6.75.2.1	ActiveMQStreamMessageMarshaller	565
6.75.2.2	~ActiveMQStreamMessageMarshaller	565
6.75.3	Member Function Documentation	565
6.75.3.1	createObject	565
6.75.3.2	getDataStructureType	565
6.75.3.3	looseMarshal	565
6.75.3.4	looseUnmarshal	566
6.75.3.5	tightMarshal1	566

6.75.3.6	tightMarshal2	566
6.75.3.7	tightUnmarshal	567
6.76	activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller	
	Class Reference	568
6.76.1	Detailed Description	568
6.76.2	Constructor & Destructor Documentation	569
6.76.2.1	ActiveMQStreamMessageMarshaller	569
6.76.2.2	~ActiveMQStreamMessageMarshaller	569
6.76.3	Member Function Documentation	569
6.76.3.1	createObject	569
6.76.3.2	getDataStructureType	569
6.76.3.3	looseMarshal	569
6.76.3.4	looseUnmarshal	570
6.76.3.5	tightMarshal1	570
6.76.3.6	tightMarshal2	570
6.76.3.7	tightUnmarshal	571
6.77	activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller	
	Class Reference	572
6.77.1	Detailed Description	572
6.77.2	Constructor & Destructor Documentation	573
6.77.2.1	ActiveMQStreamMessageMarshaller	573
6.77.2.2	~ActiveMQStreamMessageMarshaller	573
6.77.3	Member Function Documentation	573
6.77.3.1	createObject	573
6.77.3.2	getDataStructureType	573
6.77.3.3	looseMarshal	573
6.77.3.4	looseUnmarshal	574
6.77.3.5	tightMarshal1	574
6.77.3.6	tightMarshal2	574
6.77.3.7	tightUnmarshal	575
6.78	activemq::commands::ActiveMQTempDestination Class Reference	576
6.78.1	Constructor & Destructor Documentation	577
6.78.1.1	ActiveMQTempDestination	577
6.78.1.2	ActiveMQTempDestination	577
6.78.1.3	~ActiveMQTempDestination	577
6.78.2	Member Function Documentation	577
6.78.2.1	cloneDataStructure	577

6.78.2.2	close	577
6.78.2.3	copyDataStructure	577
6.78.2.4	equals	578
6.78.2.5	getDataStructureType	578
6.78.2.6	setConnection	578
6.78.2.7	toString	578
6.78.3	Field Documentation	579
6.78.3.1	connection	579
6.78.3.2	ID_ACTIVEMQTEMPDESTINATION	579
6.79	activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller	
	Class Reference	580
6.79.1	Detailed Description	580
6.79.2	Constructor & Destructor Documentation	581
6.79.2.1	ActiveMQTempDestinationMarshaller	581
6.79.2.2	~ActiveMQTempDestinationMarshaller	581
6.79.3	Member Function Documentation	581
6.79.3.1	looseMarshal	581
6.79.3.2	looseUnmarshal	581
6.79.3.3	tightMarshal1	582
6.79.3.4	tightMarshal2	582
6.79.3.5	tightUnmarshal	583
6.80	activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller	
	Class Reference	584
6.80.1	Detailed Description	584
6.80.2	Constructor & Destructor Documentation	585
6.80.2.1	ActiveMQTempDestinationMarshaller	585
6.80.2.2	~ActiveMQTempDestinationMarshaller	585
6.80.3	Member Function Documentation	585
6.80.3.1	looseMarshal	585
6.80.3.2	looseUnmarshal	585
6.80.3.3	tightMarshal1	586
6.80.3.4	tightMarshal2	586
6.80.3.5	tightUnmarshal	587
6.81	activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller	
	Class Reference	588
6.81.1	Detailed Description	588
6.81.2	Constructor & Destructor Documentation	589

6.81.2.1	ActiveMQTempDestinationMarshaller	589
6.81.2.2	~ActiveMQTempDestinationMarshaller	589
6.81.3	Member Function Documentation	589
6.81.3.1	looseMarshal	589
6.81.3.2	looseUnmarshal	589
6.81.3.3	tightMarshal1	590
6.81.3.4	tightMarshal2	590
6.81.3.5	tightUnmarshal	591
6.82	activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller Class Reference	592
6.82.1	Detailed Description	592
6.82.2	Constructor & Destructor Documentation	593
6.82.2.1	ActiveMQTempDestinationMarshaller	593
6.82.2.2	~ActiveMQTempDestinationMarshaller	593
6.82.3	Member Function Documentation	593
6.82.3.1	looseMarshal	593
6.82.3.2	looseUnmarshal	593
6.82.3.3	tightMarshal1	594
6.82.3.4	tightMarshal2	594
6.82.3.5	tightUnmarshal	595
6.83	activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller Class Reference	596
6.83.1	Detailed Description	596
6.83.2	Constructor & Destructor Documentation	597
6.83.2.1	ActiveMQTempDestinationMarshaller	597
6.83.2.2	~ActiveMQTempDestinationMarshaller	597
6.83.3	Member Function Documentation	597
6.83.3.1	looseMarshal	597
6.83.3.2	looseUnmarshal	597
6.83.3.3	tightMarshal1	598
6.83.3.4	tightMarshal2	598
6.83.3.5	tightUnmarshal	599
6.84	activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller Class Reference	600
6.84.1	Detailed Description	600
6.84.2	Constructor & Destructor Documentation	601
6.84.2.1	ActiveMQTempDestinationMarshaller	601

6.84.2.2	<code>~ActiveMQTempDestinationMarshaller</code>	601
6.84.3	Member Function Documentation	601
6.84.3.1	<code>looseMarshal</code>	601
6.84.3.2	<code>looseUnmarshal</code>	601
6.84.3.3	<code>tightMarshal1</code>	602
6.84.3.4	<code>tightMarshal2</code>	602
6.84.3.5	<code>tightUnmarshal</code>	603
6.85	<code>activemq::commands::ActiveMQTempQueue</code> Class Reference	604
6.85.1	Constructor & Destructor Documentation	605
6.85.1.1	<code>ActiveMQTempQueue</code>	605
6.85.1.2	<code>ActiveMQTempQueue</code>	605
6.85.1.3	<code>~ActiveMQTempQueue</code>	605
6.85.2	Member Function Documentation	605
6.85.2.1	<code>clone</code>	605
6.85.2.2	<code>cloneDataStructure</code>	605
6.85.2.3	<code>copy</code>	605
6.85.2.4	<code>copyDataStructure</code>	606
6.85.2.5	<code>destroy</code>	606
6.85.2.6	<code>equals</code>	606
6.85.2.7	<code>getCMSDestination</code>	606
6.85.2.8	<code>getCMSProperties</code>	606
6.85.2.9	<code>getDataStructureType</code>	607
6.85.2.10	<code>getDestinationType</code>	607
6.85.2.11	<code>getQueueName</code>	607
6.85.2.12	<code>toString</code>	607
6.85.3	Field Documentation	608
6.85.3.1	<code>ID_ACTIVEMQTEMPQUEUE</code>	608
6.86	<code>activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller</code> Class Reference	609
6.86.1	Detailed Description	609
6.86.2	Constructor & Destructor Documentation	610
6.86.2.1	<code>ActiveMQTempQueueMarshaller</code>	610
6.86.2.2	<code>~ActiveMQTempQueueMarshaller</code>	610
6.86.3	Member Function Documentation	610
6.86.3.1	<code>createObject</code>	610
6.86.3.2	<code>getDataStructureType</code>	610
6.86.3.3	<code>looseMarshal</code>	610

6.86.3.4	looseUnmarshal	611
6.86.3.5	tightMarshal1	611
6.86.3.6	tightMarshal2	611
6.86.3.7	tightUnmarshal	612
6.87	activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller	
	Class Reference	613
6.87.1	Detailed Description	613
6.87.2	Constructor & Destructor Documentation	614
6.87.2.1	ActiveMQTempQueueMarshaller	614
6.87.2.2	~ActiveMQTempQueueMarshaller	614
6.87.3	Member Function Documentation	614
6.87.3.1	createObject	614
6.87.3.2	getDataStructureType	614
6.87.3.3	looseMarshal	614
6.87.3.4	looseUnmarshal	615
6.87.3.5	tightMarshal1	615
6.87.3.6	tightMarshal2	615
6.87.3.7	tightUnmarshal	616
6.88	activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	
	Class Reference	617
6.88.1	Detailed Description	617
6.88.2	Constructor & Destructor Documentation	618
6.88.2.1	ActiveMQTempQueueMarshaller	618
6.88.2.2	~ActiveMQTempQueueMarshaller	618
6.88.3	Member Function Documentation	618
6.88.3.1	createObject	618
6.88.3.2	getDataStructureType	618
6.88.3.3	looseMarshal	618
6.88.3.4	looseUnmarshal	619
6.88.3.5	tightMarshal1	619
6.88.3.6	tightMarshal2	619
6.88.3.7	tightUnmarshal	620
6.89	activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	
	Class Reference	621
6.89.1	Detailed Description	621
6.89.2	Constructor & Destructor Documentation	622
6.89.2.1	ActiveMQTempQueueMarshaller	622

6.89.2.2	~ActiveMQTempQueueMarshaller	622
6.89.3	Member Function Documentation	622
6.89.3.1	createObject	622
6.89.3.2	getDataStructureType	622
6.89.3.3	looseMarshal	622
6.89.3.4	looseUnmarshal	623
6.89.3.5	tightMarshal1	623
6.89.3.6	tightMarshal2	623
6.89.3.7	tightUnmarshal	624
6.90	activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller	
	Class Reference	625
6.90.1	Detailed Description	625
6.90.2	Constructor & Destructor Documentation	626
6.90.2.1	ActiveMQTempQueueMarshaller	626
6.90.2.2	~ActiveMQTempQueueMarshaller	626
6.90.3	Member Function Documentation	626
6.90.3.1	createObject	626
6.90.3.2	getDataStructureType	626
6.90.3.3	looseMarshal	626
6.90.3.4	looseUnmarshal	627
6.90.3.5	tightMarshal1	627
6.90.3.6	tightMarshal2	627
6.90.3.7	tightUnmarshal	628
6.91	activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	
	Class Reference	629
6.91.1	Detailed Description	629
6.91.2	Constructor & Destructor Documentation	630
6.91.2.1	ActiveMQTempQueueMarshaller	630
6.91.2.2	~ActiveMQTempQueueMarshaller	630
6.91.3	Member Function Documentation	630
6.91.3.1	createObject	630
6.91.3.2	getDataStructureType	630
6.91.3.3	looseMarshal	630
6.91.3.4	looseUnmarshal	631
6.91.3.5	tightMarshal1	631
6.91.3.6	tightMarshal2	631
6.91.3.7	tightUnmarshal	632

6.92	activemq::commands::ActiveMQTempTopic Class Reference	633
6.92.1	Constructor & Destructor Documentation	634
6.92.1.1	ActiveMQTempTopic	634
6.92.1.2	ActiveMQTempTopic	634
6.92.1.3	~ActiveMQTempTopic	634
6.92.2	Member Function Documentation	634
6.92.2.1	clone	634
6.92.2.2	cloneDataStructure	634
6.92.2.3	copy	634
6.92.2.4	copyDataStructure	635
6.92.2.5	destroy	635
6.92.2.6	equals	635
6.92.2.7	getCMSDestination	635
6.92.2.8	getCMSProperties	635
6.92.2.9	getDataStructureType	636
6.92.2.10	getDestinationType	636
6.92.2.11	getTopicName	636
6.92.2.12	toString	636
6.92.3	Field Documentation	637
6.92.3.1	ID_ACTIVEMQTEMPTOPIC	637
6.93	activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller Class Reference	638
6.93.1	Detailed Description	638
6.93.2	Constructor & Destructor Documentation	639
6.93.2.1	ActiveMQTempTopicMarshaller	639
6.93.2.2	~ActiveMQTempTopicMarshaller	639
6.93.3	Member Function Documentation	639
6.93.3.1	createObject	639
6.93.3.2	getDataStructureType	639
6.93.3.3	looseMarshal	639
6.93.3.4	looseUnmarshal	640
6.93.3.5	tightMarshal1	640
6.93.3.6	tightMarshal2	640
6.93.3.7	tightUnmarshal	641
6.94	activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller Class Reference	642
6.94.1	Detailed Description	642

6.94.2	Constructor & Destructor Documentation	643
6.94.2.1	ActiveMQTempTopicMarshaller	643
6.94.2.2	~ActiveMQTempTopicMarshaller	643
6.94.3	Member Function Documentation	643
6.94.3.1	createObject	643
6.94.3.2	getDataStructureType	643
6.94.3.3	looseMarshal	643
6.94.3.4	looseUnmarshal	644
6.94.3.5	tightMarshal1	644
6.94.3.6	tightMarshal2	644
6.94.3.7	tightUnmarshal	645
6.95	activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller Class Reference	646
6.95.1	Detailed Description	646
6.95.2	Constructor & Destructor Documentation	647
6.95.2.1	ActiveMQTempTopicMarshaller	647
6.95.2.2	~ActiveMQTempTopicMarshaller	647
6.95.3	Member Function Documentation	647
6.95.3.1	createObject	647
6.95.3.2	getDataStructureType	647
6.95.3.3	looseMarshal	647
6.95.3.4	looseUnmarshal	648
6.95.3.5	tightMarshal1	648
6.95.3.6	tightMarshal2	648
6.95.3.7	tightUnmarshal	649
6.96	activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller Class Reference	650
6.96.1	Detailed Description	650
6.96.2	Constructor & Destructor Documentation	651
6.96.2.1	ActiveMQTempTopicMarshaller	651
6.96.2.2	~ActiveMQTempTopicMarshaller	651
6.96.3	Member Function Documentation	651
6.96.3.1	createObject	651
6.96.3.2	getDataStructureType	651
6.96.3.3	looseMarshal	651
6.96.3.4	looseUnmarshal	652
6.96.3.5	tightMarshal1	652

6.96.3.6	tightMarshal2	652
6.96.3.7	tightUnmarshal	653
6.97	activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller	
	Class Reference	654
6.97.1	Detailed Description	654
6.97.2	Constructor & Destructor Documentation	655
6.97.2.1	ActiveMQTempTopicMarshaller	655
6.97.2.2	~ActiveMQTempTopicMarshaller	655
6.97.3	Member Function Documentation	655
6.97.3.1	createObject	655
6.97.3.2	getDataStructureType	655
6.97.3.3	looseMarshal	655
6.97.3.4	looseUnmarshal	656
6.97.3.5	tightMarshal1	656
6.97.3.6	tightMarshal2	656
6.97.3.7	tightUnmarshal	657
6.98	activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	
	Class Reference	658
6.98.1	Detailed Description	658
6.98.2	Constructor & Destructor Documentation	659
6.98.2.1	ActiveMQTempTopicMarshaller	659
6.98.2.2	~ActiveMQTempTopicMarshaller	659
6.98.3	Member Function Documentation	659
6.98.3.1	createObject	659
6.98.3.2	getDataStructureType	659
6.98.3.3	looseMarshal	659
6.98.3.4	looseUnmarshal	660
6.98.3.5	tightMarshal1	660
6.98.3.6	tightMarshal2	660
6.98.3.7	tightUnmarshal	661
6.99	activemq::commands::ActiveMQTextMessage Class Reference	662
6.99.1	Constructor & Destructor Documentation	663
6.99.1.1	ActiveMQTextMessage	663
6.99.1.2	~ActiveMQTextMessage	663
6.99.2	Member Function Documentation	663
6.99.2.1	beforeMarshal	663
6.99.2.2	clearBody	663

6.99.2.3	clone	663
6.99.2.4	cloneDataStructure	664
6.99.2.5	copyDataStructure	664
6.99.2.6	equals	664
6.99.2.7	getDataStructureType	664
6.99.2.8	getSize	665
6.99.2.9	getText	665
6.99.2.10	setText	665
6.99.2.11	setText	665
6.99.2.12	toString	666
6.99.3	Field Documentation	666
6.99.3.1	ID_ACTIVEMQTEXTMESSAGE	666
6.99.3.2	text	666
6.100	activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	
	Class Reference	667
6.100.1	Detailed Description	667
6.100.2	Constructor & Destructor Documentation	668
6.100.2.1	ActiveMQTextMessageMarshaller	668
6.100.2.2	~ActiveMQTextMessageMarshaller	668
6.100.3	Member Function Documentation	668
6.100.3.1	createObject	668
6.100.3.2	getDataStructureType	668
6.100.3.3	looseMarshal	668
6.100.3.4	looseUnmarshal	669
6.100.3.5	tightMarshal1	669
6.100.3.6	tightMarshal2	669
6.100.3.7	tightUnmarshal	670
6.101	activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	
	Class Reference	671
6.101.1	Detailed Description	671
6.101.2	Constructor & Destructor Documentation	672
6.101.2.1	ActiveMQTextMessageMarshaller	672
6.101.2.2	~ActiveMQTextMessageMarshaller	672
6.101.3	Member Function Documentation	672
6.101.3.1	createObject	672
6.101.3.2	getDataStructureType	672
6.101.3.3	looseMarshal	672

6.101.3.4 looseUnmarshal	673
6.101.3.5 tightMarshal1	673
6.101.3.6 tightMarshal2	673
6.101.3.7 tightUnmarshal	674
6.102activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller	
Class Reference	675
6.102.1 Detailed Description	675
6.102.2 Constructor & Destructor Documentation	676
6.102.2.1 ActiveMQTextMessageMarshaller	676
6.102.2.2 ~ActiveMQTextMessageMarshaller	676
6.102.3 Member Function Documentation	676
6.102.3.1 createObject	676
6.102.3.2 getDataStructureType	676
6.102.3.3 looseMarshal	676
6.102.3.4 looseUnmarshal	677
6.102.3.5 tightMarshal1	677
6.102.3.6 tightMarshal2	677
6.102.3.7 tightUnmarshal	678
6.103activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	
Class Reference	679
6.103.1 Detailed Description	679
6.103.2 Constructor & Destructor Documentation	680
6.103.2.1 ActiveMQTextMessageMarshaller	680
6.103.2.2 ~ActiveMQTextMessageMarshaller	680
6.103.3 Member Function Documentation	680
6.103.3.1 createObject	680
6.103.3.2 getDataStructureType	680
6.103.3.3 looseMarshal	680
6.103.3.4 looseUnmarshal	681
6.103.3.5 tightMarshal1	681
6.103.3.6 tightMarshal2	681
6.103.3.7 tightUnmarshal	682
6.104activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller	
Class Reference	683
6.104.1 Detailed Description	683
6.104.2 Constructor & Destructor Documentation	684
6.104.2.1 ActiveMQTextMessageMarshaller	684

6.104.2.2 ~ActiveMQTextMessageMarshaller	684
6.104.3 Member Function Documentation	684
6.104.3.1 createObject	684
6.104.3.2 getDataStructureType	684
6.104.3.3 looseMarshal	684
6.104.3.4 looseUnmarshal	685
6.104.3.5 tightMarshal1	685
6.104.3.6 tightMarshal2	685
6.104.3.7 tightUnmarshal	686
6.105activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller	
Class Reference	687
6.105.1 Detailed Description	687
6.105.2 Constructor & Destructor Documentation	688
6.105.2.1 ActiveMQTextMessageMarshaller	688
6.105.2.2 ~ActiveMQTextMessageMarshaller	688
6.105.3 Member Function Documentation	688
6.105.3.1 createObject	688
6.105.3.2 getDataStructureType	688
6.105.3.3 looseMarshal	688
6.105.3.4 looseUnmarshal	689
6.105.3.5 tightMarshal1	689
6.105.3.6 tightMarshal2	689
6.105.3.7 tightUnmarshal	690
6.106activemq::commands::ActiveMQTopic Class Reference	691
6.106.1 Constructor & Destructor Documentation	692
6.106.1.1 ActiveMQTopic	692
6.106.1.2 ActiveMQTopic	692
6.106.1.3 ~ActiveMQTopic	692
6.106.2 Member Function Documentation	692
6.106.2.1 clone	692
6.106.2.2 cloneDataStructure	692
6.106.2.3 copy	692
6.106.2.4 copyDataStructure	692
6.106.2.5 equals	693
6.106.2.6 getCMSDestination	693
6.106.2.7 getCMSProperties	693
6.106.2.8 getDataStructureType	693

6.106.2.9	getDestinationType	693
6.106.2.10	getTopicName	694
6.106.2.11	toString	694
6.106.3	Field Documentation	694
6.106.3.1	ID_ACTIVEMQTOPIC	694
6.107	activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller Class Reference	695
6.107.1	Detailed Description	695
6.107.2	Constructor & Destructor Documentation	696
6.107.2.1	ActiveMQTopicMarshaller	696
6.107.2.2	~ActiveMQTopicMarshaller	696
6.107.3	Member Function Documentation	696
6.107.3.1	createObject	696
6.107.3.2	getDataStructureType	696
6.107.3.3	looseMarshal	696
6.107.3.4	looseUnmarshal	697
6.107.3.5	tightMarshal1	697
6.107.3.6	tightMarshal2	697
6.107.3.7	tightUnmarshal	698
6.108	activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller Class Reference	699
6.108.1	Detailed Description	699
6.108.2	Constructor & Destructor Documentation	700
6.108.2.1	ActiveMQTopicMarshaller	700
6.108.2.2	~ActiveMQTopicMarshaller	700
6.108.3	Member Function Documentation	700
6.108.3.1	createObject	700
6.108.3.2	getDataStructureType	700
6.108.3.3	looseMarshal	700
6.108.3.4	looseUnmarshal	701
6.108.3.5	tightMarshal1	701
6.108.3.6	tightMarshal2	701
6.108.3.7	tightUnmarshal	702
6.109	activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller Class Reference	703
6.109.1	Detailed Description	703
6.109.2	Constructor & Destructor Documentation	704

6.109.2.1 ActiveMQTopicMarshaller	704
6.109.2.2 ~ActiveMQTopicMarshaller	704
6.109.3 Member Function Documentation	704
6.109.3.1 createObject	704
6.109.3.2 getDataStructureType	704
6.109.3.3 looseMarshal	704
6.109.3.4 looseUnmarshal	705
6.109.3.5 tightMarshal1	705
6.109.3.6 tightMarshal2	705
6.109.3.7 tightUnmarshal	706
6.110activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller Class Reference	707
6.110.1 Detailed Description	707
6.110.2 Constructor & Destructor Documentation	708
6.110.2.1 ActiveMQTopicMarshaller	708
6.110.2.2 ~ActiveMQTopicMarshaller	708
6.110.3 Member Function Documentation	708
6.110.3.1 createObject	708
6.110.3.2 getDataStructureType	708
6.110.3.3 looseMarshal	708
6.110.3.4 looseUnmarshal	709
6.110.3.5 tightMarshal1	709
6.110.3.6 tightMarshal2	709
6.110.3.7 tightUnmarshal	710
6.111activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller Class Reference	711
6.111.1 Detailed Description	711
6.111.2 Constructor & Destructor Documentation	712
6.111.2.1 ActiveMQTopicMarshaller	712
6.111.2.2 ~ActiveMQTopicMarshaller	712
6.111.3 Member Function Documentation	712
6.111.3.1 createObject	712
6.111.3.2 getDataStructureType	712
6.111.3.3 looseMarshal	712
6.111.3.4 looseUnmarshal	713
6.111.3.5 tightMarshal1	713
6.111.3.6 tightMarshal2	713

6.111.3.7 tightUnmarshal	714
6.112activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller Class Reference	715
6.112.1 Detailed Description	715
6.112.2 Constructor & Destructor Documentation	716
6.112.2.1 ActiveMQTopicMarshaller	716
6.112.2.2 ~ActiveMQTopicMarshaller	716
6.112.3 Member Function Documentation	716
6.112.3.1 createObject	716
6.112.3.2 getDataStructureType	716
6.112.3.3 looseMarshal	716
6.112.3.4 looseUnmarshal	717
6.112.3.5 tightMarshal1	717
6.112.3.6 tightMarshal2	717
6.112.3.7 tightUnmarshal	718
6.113activemq::core::ActiveMQTransactionContext Class Reference	719
6.113.1 Detailed Description	719
6.113.2 Constructor & Destructor Documentation	720
6.113.2.1 ActiveMQTransactionContext	720
6.113.2.2 ~ActiveMQTransactionContext	720
6.113.3 Member Function Documentation	720
6.113.3.1 addSynchronization	720
6.113.3.2 begin	720
6.113.3.3 commit	720
6.113.3.4 getTransactionId	720
6.113.3.5 isInTransaction	721
6.113.3.6 removeSynchronization	721
6.113.3.7 rollback	721
6.114decaf::util::zip::Adler32 Class Reference	722
6.114.1 Detailed Description	722
6.114.2 Constructor & Destructor Documentation	723
6.114.2.1 Adler32	723
6.114.2.2 ~Adler32	723
6.114.3 Member Function Documentation	723
6.114.3.1 getValue	723
6.114.3.2 reset	723
6.114.3.3 update	723

6.114.3.4 update	723
6.114.3.5 update	724
6.114.3.6 update	724
6.115decaf::lang::Appendable Class Reference	725
6.115.1 Detailed Description	725
6.115.2 Constructor & Destructor Documentation	726
6.115.2.1 ~Appendable	726
6.115.3 Member Function Documentation	726
6.115.3.1 append	726
6.115.3.2 append	726
6.115.3.3 append	726
6.116decaf::internal::AprPool Class Reference	728
6.116.1 Detailed Description	728
6.116.2 Constructor & Destructor Documentation	728
6.116.2.1 AprPool	728
6.116.2.2 ~AprPool	728
6.116.3 Member Function Documentation	728
6.116.3.1 cleanup	728
6.116.3.2 getAprPool	728
6.116.3.3 getGlobalPool	729
6.117decaf::lang::ArrayPointer< T, REFCOUNTER > Class Template Reference	730
6.117.1 Detailed Description	731
6.117.2 Member Typedef Documentation	732
6.117.2.1 ConstReferenceType	732
6.117.2.2 CounterType	732
6.117.2.3 PointerType	732
6.117.2.4 ReferenceType	732
6.117.3 Constructor & Destructor Documentation	732
6.117.3.1 ArrayPointer	732
6.117.3.2 ArrayPointer	732
6.117.3.3 ArrayPointer	732
6.117.3.4 ArrayPointer	733
6.117.3.5 ~ArrayPointer	733
6.117.4 Member Function Documentation	733
6.117.4.1 clone	733
6.117.4.2 get	733

6.117.4.3 length	734
6.117.4.4 operator!	734
6.117.4.5 operator!=	734
6.117.4.6 operator=	734
6.117.4.7 operator=	734
6.117.4.8 operator==	735
6.117.4.9 operator[]	735
6.117.4.10operator[]	735
6.117.4.11release	735
6.117.4.12reset	735
6.117.4.13wap	736
6.117.5 Friends And Related Function Documentation	736
6.117.5.1 operator!=	736
6.117.5.2 operator!=	736
6.117.5.3 operator==	736
6.117.5.4 operator==	736
6.118decaf::lang::ArrayPointerComparator< T, R > Class Template Reference	737
6.118.1 Detailed Description	737
6.118.2 Member Function Documentation	737
6.118.2.1 compare	737
6.118.2.2 operator()	737
6.119decaf::util::concurrent::atomic::AtomicBoolean Class Reference	738
6.119.1 Detailed Description	738
6.119.2 Constructor & Destructor Documentation	738
6.119.2.1 AtomicBoolean	738
6.119.2.2 AtomicBoolean	738
6.119.2.3 ~AtomicBoolean	739
6.119.3 Member Function Documentation	739
6.119.3.1 compareAndSet	739
6.119.3.2 get	739
6.119.3.3 getAndSet	739
6.119.3.4 set	739
6.119.3.5 toString	740
6.120decaf::util::concurrent::atomic::AtomicInteger Class Reference	741
6.120.1 Detailed Description	742
6.120.2 Constructor & Destructor Documentation	742

6.120.2.1 AtomicInteger	742
6.120.2.2 AtomicInteger	742
6.120.2.3 ~AtomicInteger	742
6.120.3 Member Function Documentation	742
6.120.3.1 addAndGet	742
6.120.3.2 compareAndSet	743
6.120.3.3 decrementAndGet	743
6.120.3.4 doubleValue	743
6.120.3.5 floatValue	743
6.120.3.6 get	744
6.120.3.7 getAndAdd	744
6.120.3.8 getAndDecrement	744
6.120.3.9 getAndIncrement	744
6.120.3.10 getAndSet	744
6.120.3.11 incrementAndGet	745
6.120.3.12 intValue	745
6.120.3.13 longValue	745
6.120.3.14 set	745
6.120.3.15 toString	745
6.121 decaf::util::concurrent::atomic::AtomicRefCounter Class Reference	746
6.121.1 Constructor & Destructor Documentation	747
6.121.1.1 AtomicRefCounter	747
6.121.1.2 AtomicRefCounter	747
6.121.1.3 ~AtomicRefCounter	747
6.121.2 Member Function Documentation	747
6.121.2.1 release	747
6.121.2.2 swap	748
6.122 decaf::util::concurrent::atomic::AtomicReference< T > Class Template Reference	749
6.122.1 Detailed Description	749
6.122.2 Constructor & Destructor Documentation	750
6.122.2.1 AtomicReference	750
6.122.2.2 AtomicReference	750
6.122.2.3 ~AtomicReference	750
6.122.3 Member Function Documentation	750
6.122.3.1 compareAndSet	750
6.122.3.2 get	750

6.122.3.3	getAndSet	750
6.122.3.4	set	751
6.122.3.5	toString	751
6.123	activemq::transport::failover::BackupTransport Class Reference	752
6.123.1	Constructor & Destructor Documentation	752
6.123.1.1	BackupTransport	752
6.123.1.2	~BackupTransport	752
6.123.2	Member Function Documentation	752
6.123.2.1	getTransport	752
6.123.2.2	getUri	753
6.123.2.3	isClosed	753
6.123.2.4	onException	753
6.123.2.5	setClosed	753
6.123.2.6	setTransport	753
6.123.2.7	setUri	754
6.124	activemq::transport::failover::BackupTransportPool Class Reference	755
6.124.1	Constructor & Destructor Documentation	756
6.124.1.1	BackupTransportPool	756
6.124.1.2	BackupTransportPool	756
6.124.1.3	~BackupTransportPool	756
6.124.2	Member Function Documentation	756
6.124.2.1	getBackup	756
6.124.2.2	getBackupPoolSize	756
6.124.2.3	isEnabled	756
6.124.2.4	isPending	757
6.124.2.5	iterate	757
6.124.2.6	setBackupPoolSize	757
6.124.2.7	setEnabled	757
6.124.3	Friends And Related Function Documentation	757
6.124.3.1	BackupTransport	757
6.125	activemq::commands::BaseCommand Class Reference	758
6.125.1	Constructor & Destructor Documentation	759
6.125.1.1	BaseCommand	759
6.125.1.2	~BaseCommand	759
6.125.2	Member Function Documentation	759
6.125.2.1	copyDataStructure	759

6.125.2.2 equals	759
6.125.2.3 getCommandId	760
6.125.2.4 isBrokerInfo	760
6.125.2.5 isConnectionInfo	761
6.125.2.6 isConsumerInfo	761
6.125.2.7 isKeepAliveInfo	761
6.125.2.8 isMessage	761
6.125.2.9 isMessageAck	761
6.125.2.10sMessageDispatch	761
6.125.2.11sMessageDispatchNotification	761
6.125.2.12sProducerAck	762
6.125.2.13sProducerInfo	762
6.125.2.14sRemoveInfo	762
6.125.2.15sRemoveSubscriptionInfo	762
6.125.2.16sResponse	762
6.125.2.17sResponseRequired	762
6.125.2.18sShutdownInfo	762
6.125.2.19sTransactionInfo	763
6.125.2.20sWireFormatInfo	763
6.125.2.21setCommandId	763
6.125.2.22setResponseRequired	763
6.125.2.23oString	763
6.126activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller Class Reference	765
6.126.1 Detailed Description	765
6.126.2 Constructor & Destructor Documentation	766
6.126.2.1 BaseCommandMarshaller	766
6.126.2.2 ~BaseCommandMarshaller	766
6.126.3 Member Function Documentation	766
6.126.3.1 looseMarshal	766
6.126.3.2 looseUnmarshal	767
6.126.3.3 tightMarshal1	768
6.126.3.4 tightMarshal2	769
6.126.3.5 tightUnmarshal	770
6.127activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller Class Reference	772
6.127.1 Detailed Description	772

6.127.2 Constructor & Destructor Documentation	773
6.127.2.1 BaseCommandMarshaller	773
6.127.2.2 ~BaseCommandMarshaller	773
6.127.3 Member Function Documentation	773
6.127.3.1 looseMarshal	773
6.127.3.2 looseUnmarshal	774
6.127.3.3 tightMarshal1	775
6.127.3.4 tightMarshal2	776
6.127.3.5 tightUnmarshal	777
6.128activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller Class Reference	779
6.128.1 Detailed Description	779
6.128.2 Constructor & Destructor Documentation	780
6.128.2.1 BaseCommandMarshaller	780
6.128.2.2 ~BaseCommandMarshaller	780
6.128.3 Member Function Documentation	780
6.128.3.1 looseMarshal	780
6.128.3.2 looseUnmarshal	781
6.128.3.3 tightMarshal1	782
6.128.3.4 tightMarshal2	783
6.128.3.5 tightUnmarshal	784
6.129activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller Class Reference	786
6.129.1 Detailed Description	786
6.129.2 Constructor & Destructor Documentation	787
6.129.2.1 BaseCommandMarshaller	787
6.129.2.2 ~BaseCommandMarshaller	787
6.129.3 Member Function Documentation	787
6.129.3.1 looseMarshal	787
6.129.3.2 looseUnmarshal	788
6.129.3.3 tightMarshal1	789
6.129.3.4 tightMarshal2	790
6.129.3.5 tightUnmarshal	791
6.130activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller Class Reference	793
6.130.1 Detailed Description	793
6.130.2 Constructor & Destructor Documentation	794

6.130.2.1 BaseCommandMarshaller	794
6.130.2.2 ~BaseCommandMarshaller	794
6.130.3 Member Function Documentation	794
6.130.3.1 looseMarshal	794
6.130.3.2 looseUnmarshal	795
6.130.3.3 tightMarshal1	796
6.130.3.4 tightMarshal2	797
6.130.3.5 tightUnmarshal	798
6.131activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller Class Reference	800
6.131.1 Detailed Description	800
6.131.2 Constructor & Destructor Documentation	801
6.131.2.1 BaseCommandMarshaller	801
6.131.2.2 ~BaseCommandMarshaller	801
6.131.3 Member Function Documentation	801
6.131.3.1 looseMarshal	801
6.131.3.2 looseUnmarshal	802
6.131.3.3 tightMarshal1	803
6.131.3.4 tightMarshal2	804
6.131.3.5 tightUnmarshal	805
6.132activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller Class Reference	807
6.132.1 Detailed Description	813
6.132.2 Constructor & Destructor Documentation	813
6.132.2.1 ~BaseDataStreamMarshaller	813
6.132.3 Member Function Documentation	813
6.132.3.1 looseMarshal	813
6.132.3.2 looseMarshalBrokerError	814
6.132.3.3 looseMarshalCachedObject	814
6.132.3.4 looseMarshalLong	814
6.132.3.5 looseMarshalNestedObject	815
6.132.3.6 looseMarshalObjectArray	815
6.132.3.7 looseMarshalString	816
6.132.3.8 looseUnmarshal	816
6.132.3.9 looseUnmarshalBrokerError	816
6.132.3.10looseUnmarshalByteArray	817
6.132.3.11looseUnmarshalCachedObject	817

6.132.3.12	ooseUnmarshalConstByteArray	817
6.132.3.13	ooseUnmarshalLong	818
6.132.3.14	ooseUnmarshalNestedObject	818
6.132.3.15	ooseUnmarshalString	818
6.132.3.16	readAsciiString	819
6.132.3.17	ightMarshal1	819
6.132.3.18	ightMarshal2	819
6.132.3.19	ightMarshalBrokerError1	820
6.132.3.20	ightMarshalBrokerError2	820
6.132.3.21	ightMarshalCachedObject1	821
6.132.3.22	ightMarshalCachedObject2	821
6.132.3.23	ightMarshalLong1	821
6.132.3.24	ightMarshalLong2	822
6.132.3.25	ightMarshalNestedObject1	822
6.132.3.26	ightMarshalNestedObject2	823
6.132.3.27	ightMarshalObjectArray1	823
6.132.3.28	ightMarshalObjectArray2	823
6.132.3.29	ightMarshalString1	824
6.132.3.30	ightMarshalString2	824
6.132.3.31	ightUnmarshal	825
6.132.3.32	ightUnmarshalBrokerError	825
6.132.3.33	ightUnmarshalByteArray	825
6.132.3.34	ightUnmarshalCachedObject	826
6.132.3.35	ightUnmarshalConstByteArray	826
6.132.3.36	ightUnmarshalLong	827
6.132.3.37	ightUnmarshalNestedObject	827
6.132.3.38	ightUnmarshalString	827
6.132.3.39	oHexFromBytes	828
6.132.3.40	oString	828
6.132.3.41	toString	828
6.132.3.42	oString	829
6.133	activemq::commands::BaseDataStructure Class Reference	830
6.133.1	Constructor & Destructor Documentation	831
6.133.1.1	~BaseDataStructure	831
6.133.2	Member Function Documentation	831
6.133.2.1	afterMarshal	831

6.133.2.2 afterUnmarshal	831
6.133.2.3 beforeMarshal	831
6.133.2.4 beforeUnmarshal	831
6.133.2.5 copyDataStructure	832
6.133.2.6 equals	832
6.133.2.7 getMarshaledForm	832
6.133.2.8 isMarshalAware	832
6.133.2.9 setMarshaledForm	833
6.133.2.10 toString	833
6.134binary_function Class Reference	835
6.135decaf::net::BindException Class Reference	836
6.135.1 Constructor & Destructor Documentation	836
6.135.1.1 BindException	836
6.135.1.2 BindException	836
6.135.1.3 BindException	837
6.135.1.4 BindException	837
6.135.1.5 BindException	837
6.135.1.6 BindException	837
6.135.1.7 ~BindException	838
6.135.2 Member Function Documentation	838
6.135.2.1 clone	838
6.136decaf::io::BlockingByteArrayInputStream Class Reference	839
6.136.1 Detailed Description	840
6.136.2 Constructor & Destructor Documentation	840
6.136.2.1 BlockingByteArrayInputStream	840
6.136.2.2 BlockingByteArrayInputStream	840
6.136.2.3 ~BlockingByteArrayInputStream	840
6.136.3 Member Function Documentation	840
6.136.3.1 available	840
6.136.3.2 close	841
6.136.3.3 doReadArrayBounded	841
6.136.3.4 doReadByte	841
6.136.3.5 setByteArray	841
6.136.3.6 skip	841
6.137decaf::util::concurrent::BlockingQueue< E > Class Template Reference	843
6.137.1 Detailed Description	844

6.137.2 Constructor & Destructor Documentation	846
6.137.2.1 ~BlockingQueue	846
6.137.3 Member Function Documentation	846
6.137.3.1 drainTo	846
6.137.3.2 drainTo	846
6.137.3.3 offer	847
6.137.3.4 poll	847
6.137.3.5 put	848
6.137.3.6 remainingCapacity	848
6.137.3.7 take	849
6.138 decaf::lang::Boolean Class Reference	850
6.138.1 Constructor & Destructor Documentation	851
6.138.1.1 Boolean	851
6.138.1.2 Boolean	851
6.138.1.3 ~Boolean	851
6.138.2 Member Function Documentation	851
6.138.2.1 booleanValue	851
6.138.2.2 compareTo	851
6.138.2.3 compareTo	852
6.138.2.4 equals	852
6.138.2.5 equals	852
6.138.2.6 operator<	852
6.138.2.7 operator<	852
6.138.2.8 operator==	853
6.138.2.9 operator==	853
6.138.2.10 parseBoolean	853
6.138.2.11 toString	854
6.138.2.12 toString	854
6.138.2.13 valueOf	854
6.138.2.14 valueOf	854
6.138.3 Field Documentation	854
6.138.3.1 _FALSE	854
6.138.3.2 _TRUE	854
6.139 activemq::commands::BooleanExpression Class Reference	855
6.139.1 Constructor & Destructor Documentation	855
6.139.1.1 BooleanExpression	855

6.139.1.2 <code>~BooleanExpression</code>	855
6.139.2 Member Function Documentation	855
6.139.2.1 <code>cloneDataStructure</code>	855
6.139.2.2 <code>copyDataStructure</code>	856
6.139.2.3 <code>equals</code>	856
6.139.2.4 <code>toString</code>	856
6.140 <code>activemq::wireformat::openwire::utils::BooleanStream</code> Class Reference	857
6.140.1 Detailed Description	857
6.140.2 Constructor & Destructor Documentation	858
6.140.2.1 <code>BooleanStream</code>	858
6.140.2.2 <code>~BooleanStream</code>	858
6.140.3 Member Function Documentation	858
6.140.3.1 <code>clear</code>	858
6.140.3.2 <code>marshal</code>	858
6.140.3.3 <code>marshal</code>	858
6.140.3.4 <code>marshalledSize</code>	858
6.140.3.5 <code>readBoolean</code>	858
6.140.3.6 <code>unmarshal</code>	859
6.140.3.7 <code>writeBoolean</code>	859
6.141 <code>decaf::util::concurrent::BrokenBarrierException</code> Class Reference	860
6.141.1 Constructor & Destructor Documentation	860
6.141.1.1 <code>BrokenBarrierException</code>	860
6.141.1.2 <code>BrokenBarrierException</code>	860
6.141.1.3 <code>BrokenBarrierException</code>	861
6.141.1.4 <code>BrokenBarrierException</code>	861
6.141.1.5 <code>BrokenBarrierException</code>	861
6.141.1.6 <code>BrokenBarrierException</code>	861
6.141.1.7 <code>~BrokenBarrierException</code>	862
6.141.2 Member Function Documentation	862
6.141.2.1 <code>clone</code>	862
6.142 <code>activemq::commands::BrokerError</code> Class Reference	863
6.142.1 Detailed Description	864
6.142.2 Constructor & Destructor Documentation	864
6.142.2.1 <code>BrokerError</code>	864
6.142.2.2 <code>~BrokerError</code>	864
6.142.3 Member Function Documentation	864

6.142.3.1 cloneDataStructure	864
6.142.3.2 copyDataStructure	864
6.142.3.3 getCause	865
6.142.3.4 getDataStructureType	865
6.142.3.5 getExceptionClass	865
6.142.3.6 getMessage	865
6.142.3.7 getStackTraceElements	865
6.142.3.8 setCause	866
6.142.3.9 setExceptionClass	866
6.142.3.10 setMessage	866
6.142.3.11 setStackTraceElements	866
6.142.3.12 visit	866
6.143activemq::exceptions::BrokerException Class Reference	867
6.143.1 Constructor & Destructor Documentation	867
6.143.1.1 BrokerException	867
6.143.1.2 BrokerException	867
6.143.1.3 BrokerException	867
6.143.1.4 BrokerException	867
6.143.1.5 BrokerException	867
6.143.1.6 ~BrokerException	867
6.143.2 Member Function Documentation	867
6.143.2.1 clone	867
6.144activemq::commands::BrokerId Class Reference	869
6.144.1 Member Typedef Documentation	870
6.144.1.1 COMPARATOR	870
6.144.2 Constructor & Destructor Documentation	870
6.144.2.1 BrokerId	870
6.144.2.2 BrokerId	870
6.144.2.3 ~BrokerId	870
6.144.3 Member Function Documentation	870
6.144.3.1 cloneDataStructure	870
6.144.3.2 compareTo	870
6.144.3.3 copyDataStructure	870
6.144.3.4 equals	870
6.144.3.5 equals	870
6.144.3.6 getDataStructureType	871

6.144.3.7	getValue	871
6.144.3.8	getValue	871
6.144.3.9	operator<	871
6.144.3.10	operator=	871
6.144.3.11	operator==	871
6.144.3.12	setValue	871
6.144.3.13	toString	871
6.144.4	Field Documentation	871
6.144.4.1	ID_BROKERID	871
6.144.4.2	value	871
6.145	activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller Class Reference	872
6.145.1	Detailed Description	872
6.145.2	Constructor & Destructor Documentation	873
6.145.2.1	BrokerIdMarshaller	873
6.145.2.2	~BrokerIdMarshaller	873
6.145.3	Member Function Documentation	873
6.145.3.1	createObject	873
6.145.3.2	getDataStructureType	873
6.145.3.3	looseMarshal	873
6.145.3.4	looseUnmarshal	874
6.145.3.5	tightMarshal1	874
6.145.3.6	tightMarshal2	874
6.145.3.7	tightUnmarshal	875
6.146	activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller Class Reference	876
6.146.1	Detailed Description	876
6.146.2	Constructor & Destructor Documentation	877
6.146.2.1	BrokerIdMarshaller	877
6.146.2.2	~BrokerIdMarshaller	877
6.146.3	Member Function Documentation	877
6.146.3.1	createObject	877
6.146.3.2	getDataStructureType	877
6.146.3.3	looseMarshal	877
6.146.3.4	looseUnmarshal	878
6.146.3.5	tightMarshal1	878
6.146.3.6	tightMarshal2	878
6.146.3.7	tightUnmarshal	879

6.147	activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller Class Reference	880
6.147.1	Detailed Description	880
6.147.2	Constructor & Destructor Documentation	881
6.147.2.1	BrokerIdMarshaller	881
6.147.2.2	~BrokerIdMarshaller	881
6.147.3	Member Function Documentation	881
6.147.3.1	createObject	881
6.147.3.2	getDataStructureType	881
6.147.3.3	looseMarshal	881
6.147.3.4	looseUnmarshal	882
6.147.3.5	tightMarshal1	882
6.147.3.6	tightMarshal2	882
6.147.3.7	tightUnmarshal	883
6.148	activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller Class Reference	884
6.148.1	Detailed Description	884
6.148.2	Constructor & Destructor Documentation	885
6.148.2.1	BrokerIdMarshaller	885
6.148.2.2	~BrokerIdMarshaller	885
6.148.3	Member Function Documentation	885
6.148.3.1	createObject	885
6.148.3.2	getDataStructureType	885
6.148.3.3	looseMarshal	885
6.148.3.4	looseUnmarshal	886
6.148.3.5	tightMarshal1	886
6.148.3.6	tightMarshal2	886
6.148.3.7	tightUnmarshal	887
6.149	activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller Class Reference	888
6.149.1	Detailed Description	888
6.149.2	Constructor & Destructor Documentation	889
6.149.2.1	BrokerIdMarshaller	889
6.149.2.2	~BrokerIdMarshaller	889
6.149.3	Member Function Documentation	889
6.149.3.1	createObject	889
6.149.3.2	getDataStructureType	889
6.149.3.3	looseMarshal	889
6.149.3.4	looseUnmarshal	890

6.149.3.5 tightMarshal1	890
6.149.3.6 tightMarshal2	890
6.149.3.7 tightUnmarshal	891
6.150activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller Class Reference	892
6.150.1 Detailed Description	892
6.150.2 Constructor & Destructor Documentation	893
6.150.2.1 BrokerIdMarshaller	893
6.150.2.2 ~BrokerIdMarshaller	893
6.150.3 Member Function Documentation	893
6.150.3.1 createObject	893
6.150.3.2 getDataStructureType	893
6.150.3.3 looseMarshal	893
6.150.3.4 looseUnmarshal	894
6.150.3.5 tightMarshal1	894
6.150.3.6 tightMarshal2	894
6.150.3.7 tightUnmarshal	895
6.151activemq::commands::BrokerInfo Class Reference	896
6.151.1 Constructor & Destructor Documentation	897
6.151.1.1 BrokerInfo	897
6.151.1.2 ~BrokerInfo	897
6.151.2 Member Function Documentation	897
6.151.2.1 cloneDataStructure	897
6.151.2.2 copyDataStructure	898
6.151.2.3 equals	898
6.151.2.4 getBrokerId	899
6.151.2.5 getBrokerId	899
6.151.2.6 getBrokerName	899
6.151.2.7 getBrokerName	899
6.151.2.8 getBrokerUploadUrl	899
6.151.2.9 getBrokerUploadUrl	899
6.151.2.10getBrokerURL	899
6.151.2.11getBrokerURL	899
6.151.2.12getConnectionId	899
6.151.2.13getDataStructureType	899
6.151.2.14getNetworkProperties	900
6.151.2.15getNetworkProperties	900

6.151.2.16	getPeerBrokerInfos	900
6.151.2.17	getPeerBrokerInfos	900
6.151.2.18	sBrokerInfo	900
6.151.2.19	sDuplexConnection	901
6.151.2.20	sFaultTolerantConfiguration	901
6.151.2.21	isMasterBroker	901
6.151.2.22	sNetworkConnection	901
6.151.2.23	sSlaveBroker	901
6.151.2.24	setBrokerId	901
6.151.2.25	setBrokerName	901
6.151.2.26	setBrokerUploadUrl	901
6.151.2.27	setBrokerURL	901
6.151.2.28	setConnectionId	901
6.151.2.29	setDuplexConnection	901
6.151.2.30	setFaultTolerantConfiguration	901
6.151.2.31	setMasterBroker	901
6.151.2.32	setNetworkConnection	901
6.151.2.33	setNetworkProperties	901
6.151.2.34	setPeerBrokerInfos	901
6.151.2.35	setSlaveBroker	901
6.151.2.36	toString	901
6.151.2.37	visit	902
6.151.3	Field Documentation	903
6.151.3.1	brokerId	903
6.151.3.2	brokerName	903
6.151.3.3	brokerUploadUrl	903
6.151.3.4	brokerURL	903
6.151.3.5	connectionId	903
6.151.3.6	duplexConnection	903
6.151.3.7	faultTolerantConfiguration	903
6.151.3.8	ID_BROKERINFO	903
6.151.3.9	masterBroker	903
6.151.3.10	networkConnection	903
6.151.3.11	networkProperties	903
6.151.3.12	peerBrokerInfos	903
6.151.3.13	slaveBroker	903

6.152activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller Class Reference	904
6.152.1 Detailed Description	904
6.152.2 Constructor & Destructor Documentation	905
6.152.2.1 BrokerInfoMarshaller	905
6.152.2.2 ~BrokerInfoMarshaller	905
6.152.3 Member Function Documentation	905
6.152.3.1 createObject	905
6.152.3.2 getDataStructureType	905
6.152.3.3 looseMarshal	905
6.152.3.4 looseUnmarshal	906
6.152.3.5 tightMarshal1	906
6.152.3.6 tightMarshal2	906
6.152.3.7 tightUnmarshal	907
6.153activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller Class Reference	908
6.153.1 Detailed Description	908
6.153.2 Constructor & Destructor Documentation	909
6.153.2.1 BrokerInfoMarshaller	909
6.153.2.2 ~BrokerInfoMarshaller	909
6.153.3 Member Function Documentation	909
6.153.3.1 createObject	909
6.153.3.2 getDataStructureType	909
6.153.3.3 looseMarshal	909
6.153.3.4 looseUnmarshal	910
6.153.3.5 tightMarshal1	910
6.153.3.6 tightMarshal2	910
6.153.3.7 tightUnmarshal	911
6.154activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller Class Reference	912
6.154.1 Detailed Description	912
6.154.2 Constructor & Destructor Documentation	913
6.154.2.1 BrokerInfoMarshaller	913
6.154.2.2 ~BrokerInfoMarshaller	913
6.154.3 Member Function Documentation	913
6.154.3.1 createObject	913
6.154.3.2 getDataStructureType	913
6.154.3.3 looseMarshal	913
6.154.3.4 looseUnmarshal	914

6.154.3.5 tightMarshal1	914
6.154.3.6 tightMarshal2	914
6.154.3.7 tightUnmarshal	915
6.155activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller Class Reference	916
6.155.1 Detailed Description	916
6.155.2 Constructor & Destructor Documentation	917
6.155.2.1 BrokerInfoMarshaller	917
6.155.2.2 ~BrokerInfoMarshaller	917
6.155.3 Member Function Documentation	917
6.155.3.1 createObject	917
6.155.3.2 getDataStructureType	917
6.155.3.3 looseMarshal	917
6.155.3.4 looseUnmarshal	918
6.155.3.5 tightMarshal1	918
6.155.3.6 tightMarshal2	918
6.155.3.7 tightUnmarshal	919
6.156activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller Class Reference	920
6.156.1 Detailed Description	920
6.156.2 Constructor & Destructor Documentation	921
6.156.2.1 BrokerInfoMarshaller	921
6.156.2.2 ~BrokerInfoMarshaller	921
6.156.3 Member Function Documentation	921
6.156.3.1 createObject	921
6.156.3.2 getDataStructureType	921
6.156.3.3 looseMarshal	921
6.156.3.4 looseUnmarshal	922
6.156.3.5 tightMarshal1	922
6.156.3.6 tightMarshal2	922
6.156.3.7 tightUnmarshal	923
6.157activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller Class Reference	924
6.157.1 Detailed Description	924
6.157.2 Constructor & Destructor Documentation	925
6.157.2.1 BrokerInfoMarshaller	925
6.157.2.2 ~BrokerInfoMarshaller	925
6.157.3 Member Function Documentation	925
6.157.3.1 createObject	925

6.157.3.2	getDataStructureType	925
6.157.3.3	looseMarshal	925
6.157.3.4	looseUnmarshal	926
6.157.3.5	tightMarshal1	926
6.157.3.6	tightMarshal2	926
6.157.3.7	tightUnmarshal	927
6.158	decaf::nio::Buffer Class Reference	928
6.158.1	Detailed Description	929
6.158.2	Constructor & Destructor Documentation	930
6.158.2.1	Buffer	930
6.158.2.2	Buffer	930
6.158.2.3	~Buffer	930
6.158.3	Member Function Documentation	930
6.158.3.1	capacity	930
6.158.3.2	clear	930
6.158.3.3	flip	931
6.158.3.4	hasRemaining	931
6.158.3.5	isReadOnly	931
6.158.3.6	limit	931
6.158.3.7	limit	932
6.158.3.8	mark	932
6.158.3.9	position	932
6.158.3.10	position	932
6.158.3.11	remaining	933
6.158.3.12	reset	933
6.158.3.13	rewind	933
6.158.4	Field Documentation	933
6.158.4.1	_capacity	933
6.158.4.2	_limit	933
6.158.4.3	_mark	933
6.158.4.4	_markSet	933
6.158.4.5	_position	933
6.159	decaf::io::BufferedInputStream Class Reference	934
6.159.1	Detailed Description	936
6.159.2	Constructor & Destructor Documentation	936
6.159.2.1	BufferedInputStream	936

6.159.2.2 <code>BufferedInputStream</code>	936
6.159.2.3 <code>~BufferedInputStream</code>	936
6.159.3 Member Function Documentation	936
6.159.3.1 <code>available</code>	936
6.159.3.2 <code>close</code>	937
6.159.3.3 <code>doReadArrayBounded</code>	937
6.159.3.4 <code>doReadByte</code>	937
6.159.3.5 <code>mark</code>	937
6.159.3.6 <code>markSupported</code>	937
6.159.3.7 <code>reset</code>	938
6.159.3.8 <code>skip</code>	938
6.160 <code>decaf::io::BufferedOutputStream</code> Class Reference	940
6.160.1 Detailed Description	940
6.160.2 Constructor & Destructor Documentation	940
6.160.2.1 <code>BufferedOutputStream</code>	940
6.160.2.2 <code>BufferedOutputStream</code>	941
6.160.2.3 <code>~BufferedOutputStream</code>	941
6.160.3 Member Function Documentation	941
6.160.3.1 <code>doWriteArray</code>	941
6.160.3.2 <code>doWriteArrayBounded</code>	941
6.160.3.3 <code>doWriteByte</code>	941
6.160.3.4 <code>flush</code>	941
6.161 <code>decaf::internal::nio::BufferFactory</code> Class Reference	942
6.161.1 Detailed Description	944
6.161.2 Constructor & Destructor Documentation	944
6.161.2.1 <code>~BufferFactory</code>	944
6.161.3 Member Function Documentation	944
6.161.3.1 <code>createByteBuffer</code>	944
6.161.3.2 <code>createByteBuffer</code>	944
6.161.3.3 <code>createByteBuffer</code>	945
6.161.3.4 <code>createCharBuffer</code>	945
6.161.3.5 <code>createCharBuffer</code>	946
6.161.3.6 <code>createCharBuffer</code>	946
6.161.3.7 <code>createDoubleBuffer</code>	946
6.161.3.8 <code>createDoubleBuffer</code>	947
6.161.3.9 <code>createDoubleBuffer</code>	947

6.161.3.10	createFloatBuffer	948
6.161.3.11	createFloatBuffer	948
6.161.3.12	createFloatBuffer	949
6.161.3.13	createIntBuffer	949
6.161.3.14	createIntBuffer	949
6.161.3.15	createIntBuffer	950
6.161.3.16	createLongBuffer	950
6.161.3.17	createLongBuffer	951
6.161.3.18	createLongBuffer	951
6.161.3.19	createShortBuffer	951
6.161.3.20	createShortBuffer	952
6.161.3.21	createShortBuffer	952
6.162	decaf::nio::BufferOverflowException Class Reference	954
6.162.1	Constructor & Destructor Documentation	954
6.162.1.1	BufferOverflowException	954
6.162.1.2	BufferOverflowException	954
6.162.1.3	BufferOverflowException	955
6.162.1.4	BufferOverflowException	955
6.162.1.5	BufferOverflowException	955
6.162.1.6	BufferOverflowException	955
6.162.1.7	~BufferOverflowException	956
6.162.2	Member Function Documentation	956
6.162.2.1	clone	956
6.163	decaf::nio::BufferUnderflowException Class Reference	957
6.163.1	Constructor & Destructor Documentation	957
6.163.1.1	BufferUnderflowException	957
6.163.1.2	BufferUnderflowException	957
6.163.1.3	BufferUnderflowException	958
6.163.1.4	BufferUnderflowException	958
6.163.1.5	BufferUnderflowException	958
6.163.1.6	BufferUnderflowException	958
6.163.1.7	~BufferUnderflowException	959
6.163.2	Member Function Documentation	959
6.163.2.1	clone	959
6.164	decaf::lang::Byte Class Reference	960
6.164.1	Constructor & Destructor Documentation	961

6.164.1.1 Byte	961
6.164.1.2 Byte	962
6.164.1.3 ~Byte	962
6.164.2 Member Function Documentation	962
6.164.2.1 byteValue	962
6.164.2.2 compareTo	962
6.164.2.3 compareTo	962
6.164.2.4 decode	963
6.164.2.5 doubleValue	963
6.164.2.6 equals	963
6.164.2.7 equals	963
6.164.2.8 float Value	964
6.164.2.9 int Value	964
6.164.2.10 long Value	964
6.164.2.11 operator<	964
6.164.2.12 operator<	964
6.164.2.13 operator==	965
6.164.2.14 operator==	965
6.164.2.15 parseByte	965
6.164.2.16 parseByte	966
6.164.2.17 short Value	966
6.164.2.18 toString	966
6.164.2.19 toString	966
6.164.2.20 valueOf	967
6.164.2.21 valueOf	967
6.164.2.22 valueOf	967
6.164.3 Field Documentation	968
6.164.3.1 MAX_VALUE	968
6.164.3.2 MIN_VALUE	968
6.164.3.3 SIZE	968
6.165 decaf::internal::util::ByteArrayAdapter Class Reference	969
6.165.1 Detailed Description	973
6.165.2 Constructor & Destructor Documentation	973
6.165.2.1 ByteArrayAdapter	973
6.165.2.2 ByteArrayAdapter	973
6.165.2.3 ByteArrayAdapter	974

6.165.2.4 ByteArrayAdapter	974
6.165.2.5 ByteArrayAdapter	975
6.165.2.6 ByteArrayAdapter	975
6.165.2.7 ByteArrayAdapter	975
6.165.2.8 ByteArrayAdapter	976
6.165.2.9 ~ByteArrayAdapter	976
6.165.3 Member Function Documentation	976
6.165.3.1 clear	976
6.165.3.2 get	976
6.165.3.3 getByteArray	977
6.165.3.4 getCapacity	977
6.165.3.5 getChar	977
6.165.3.6 getCharArray	977
6.165.3.7 getCharCapacity	977
6.165.3.8 getDouble	978
6.165.3.9 getDoubleArray	978
6.165.3.10 getDoubleAt	978
6.165.3.11 getDoubleCapacity	979
6.165.3.12 getFloat	979
6.165.3.13 getFloatArray	979
6.165.3.14 getFloatAt	979
6.165.3.15 getFloatCapacity	980
6.165.3.16 getInt	980
6.165.3.17 getIntArray	980
6.165.3.18 getIntAt	980
6.165.3.19 getIntCapacity	981
6.165.3.20 getLong	981
6.165.3.21 getLongArray	981
6.165.3.22 getLongAt	982
6.165.3.23 getLongCapacity	982
6.165.3.24 getShort	982
6.165.3.25 getShortArray	983
6.165.3.26 getShortAt	983
6.165.3.27 getShortCapacity	983
6.165.3.28 operator[]	983
6.165.3.29 operator[]	983

6.165.3.30	put	984
6.165.3.31	putChar	984
6.165.3.32	putDouble	985
6.165.3.33	putDoubleAt	985
6.165.3.34	putFloat	985
6.165.3.35	putFloatAt	986
6.165.3.36	putInt	986
6.165.3.37	putIntAt	987
6.165.3.38	putLong	987
6.165.3.39	putLongAt	987
6.165.3.40	putShort	988
6.165.3.41	putShortAt	988
6.165.3.42	read	989
6.165.3.43	resize	989
6.165.3.44	write	989
6.166	decaf::internal::nio::ByteBuffer Class Reference	991
6.166.1	Detailed Description	1001
6.166.2	Constructor & Destructor Documentation	1002
6.166.2.1	ByteBuffer	1002
6.166.2.2	ByteBuffer	1002
6.166.2.3	ByteBuffer	1003
6.166.2.4	ByteBuffer	1003
6.166.2.5	~ByteBuffer	1003
6.166.3	Member Function Documentation	1003
6.166.3.1	array	1003
6.166.3.2	arrayOffset	1004
6.166.3.3	asCharBuffer	1004
6.166.3.4	asDoubleBuffer	1004
6.166.3.5	asFloatBuffer	1005
6.166.3.6	asIntBuffer	1005
6.166.3.7	asLongBuffer	1006
6.166.3.8	asReadOnlyBuffer	1006
6.166.3.9	asShortBuffer	1006
6.166.3.10	compact	1007
6.166.3.11	duplicate	1007
6.166.3.12	get	1007

6.166.3.13	get	1008
6.166.3.14	getChar	1008
6.166.3.15	getChar	1009
6.166.3.16	getDouble	1009
6.166.3.17	getDouble	1009
6.166.3.18	getFloat	1010
6.166.3.19	getFloat	1010
6.166.3.20	getInt	1010
6.166.3.21	getInt	1011
6.166.3.22	getLong	1011
6.166.3.23	getLong	1011
6.166.3.24	getShort	1012
6.166.3.25	getShort	1012
6.166.3.26	hasArray	1012
6.166.3.27	isReadOnly	1013
6.166.3.28	put	1013
6.166.3.29	put	1013
6.166.3.30	putChar	1014
6.166.3.31	putChar	1014
6.166.3.32	putDouble	1014
6.166.3.33	putDouble	1015
6.166.3.34	putFloat	1015
6.166.3.35	putFloat	1016
6.166.3.36	putInt	1016
6.166.3.37	putInt	1017
6.166.3.38	putLong	1017
6.166.3.39	putLong	1017
6.166.3.40	putShort	1018
6.166.3.41	putShort	1018
6.166.3.42	setReadOnly	1019
6.166.3.43	lice	1019
6.167	decaf::io::ByteArrayInputStream Class Reference	1020
6.167.1	Detailed Description	1022
6.167.2	Constructor & Destructor Documentation	1022
6.167.2.1	ByteArrayInputStream	1022
6.167.2.2	ByteArrayInputStream	1022

6.167.2.3	ByteArrayInputStream	1023
6.167.2.4	ByteArrayInputStream	1023
6.167.2.5	~ByteArrayInputStream	1023
6.167.3	Member Function Documentation	1023
6.167.3.1	available	1023
6.167.3.2	doReadArrayBounded	1024
6.167.3.3	doReadByte	1024
6.167.3.4	mark	1024
6.167.3.5	markSupported	1024
6.167.3.6	reset	1025
6.167.3.7	setByteArray	1025
6.167.3.8	setByteArray	1026
6.167.3.9	setByteArray	1026
6.167.3.10	skip	1026
6.168	decaf::io::ByteArrayOutputStream Class Reference	1028
6.168.1	Constructor & Destructor Documentation	1028
6.168.1.1	ByteArrayOutputStream	1028
6.168.1.2	ByteArrayOutputStream	1029
6.168.1.3	~ByteArrayOutputStream	1029
6.168.2	Member Function Documentation	1029
6.168.2.1	doWriteArrayBounded	1029
6.168.2.2	doWriteByte	1029
6.168.2.3	reset	1029
6.168.2.4	size	1029
6.168.2.5	toArray	1030
6.168.2.6	toString	1030
6.168.2.7	writeTo	1030
6.169	decaf::nio::ByteBuffer Class Reference	1031
6.169.1	Detailed Description	1035
6.169.2	Constructor & Destructor Documentation	1036
6.169.2.1	ByteBuffer	1036
6.169.2.2	~ByteBuffer	1036
6.169.3	Member Function Documentation	1036
6.169.3.1	allocate	1036
6.169.3.2	array	1037
6.169.3.3	arrayOffset	1037

6.169.3.4 asCharBuffer	1037
6.169.3.5 asDoubleBuffer	1038
6.169.3.6 asFloatBuffer	1038
6.169.3.7 asIntBuffer	1038
6.169.3.8 asLongBuffer	1039
6.169.3.9 asReadOnlyBuffer	1039
6.169.3.10 asShortBuffer	1039
6.169.3.11 compact	1040
6.169.3.12 compareTo	1040
6.169.3.13 duplicate	1040
6.169.3.14 equals	1040
6.169.3.15 get	1040
6.169.3.16 get	1041
6.169.3.17 get	1041
6.169.3.18 get	1042
6.169.3.19 getChar	1042
6.169.3.20 getChar	1042
6.169.3.21 getDouble	1043
6.169.3.22 getDouble	1043
6.169.3.23 getFloat	1043
6.169.3.24 getFloat	1044
6.169.3.25 getInt	1044
6.169.3.26 getInt	1044
6.169.3.27 getLong	1045
6.169.3.28 getLong	1045
6.169.3.29 getShort	1045
6.169.3.30 getShort	1046
6.169.3.31 hasArray	1046
6.169.3.32 isReadOnly	1046
6.169.3.33 operator<	1046
6.169.3.34 operator==	1046
6.169.3.35 put	1046
6.169.3.36 put	1047
6.169.3.37 put	1047
6.169.3.38 put	1048
6.169.3.39 put	1048

6.169.3.40	putChar	1049
6.169.3.41	putChar	1049
6.169.3.42	putDouble	1050
6.169.3.43	putDouble	1050
6.169.3.44	putFloat	1050
6.169.3.45	putFloat	1051
6.169.3.46	putInt	1051
6.169.3.47	putInt	1052
6.169.3.48	putLong	1052
6.169.3.49	putLong	1052
6.169.3.50	putShort	1053
6.169.3.51	putShort	1053
6.169.3.52	slice	1054
6.169.3.53	toString	1054
6.169.3.54	wrap	1054
6.169.3.55	wrap	1054
6.170	cms::BytesMessage Class Reference	1056
6.170.1	Detailed Description	1058
6.170.2	Constructor & Destructor Documentation	1059
6.170.2.1	~BytesMessage	1059
6.170.3	Member Function Documentation	1059
6.170.3.1	clone	1059
6.170.3.2	getBodyBytes	1059
6.170.3.3	getBodyLength	1060
6.170.3.4	readBoolean	1060
6.170.3.5	readByte	1060
6.170.3.6	readBytes	1061
6.170.3.7	readBytes	1061
6.170.3.8	readChar	1062
6.170.3.9	readDouble	1062
6.170.3.10	readFloat	1063
6.170.3.11	readInt	1063
6.170.3.12	readLong	1063
6.170.3.13	readShort	1064
6.170.3.14	readString	1064
6.170.3.15	readUnsignedShort	1064

6.170.3.16	readUTF	1065
6.170.3.17	reset	1065
6.170.3.18	setBodyBytes	1065
6.170.3.19	writeBoolean	1066
6.170.3.20	writeByte	1066
6.170.3.21	writeBytes	1066
6.170.3.22	writeBytes	1067
6.170.3.23	writeChar	1067
6.170.3.24	writeDouble	1067
6.170.3.25	writeFloat	1068
6.170.3.26	writeInt	1068
6.170.3.27	writeLong	1068
6.170.3.28	writeShort	1069
6.170.3.29	writeString	1069
6.170.3.30	writeUnsignedShort	1069
6.170.3.31	writeUTF	1070
6.171	activemq::cmsutil::CachedConsumer Class Reference	1071
6.171.1	Detailed Description	1071
6.171.2	Constructor & Destructor Documentation	1072
6.171.2.1	CachedConsumer	1072
6.171.2.2	CachedConsumer	1072
6.171.2.3	~CachedConsumer	1072
6.171.3	Member Function Documentation	1072
6.171.3.1	close	1072
6.171.3.2	getMessageListener	1072
6.171.3.3	getMessageSelector	1072
6.171.3.4	operator=	1073
6.171.3.5	receive	1073
6.171.3.6	receive	1073
6.171.3.7	receiveNoWait	1073
6.171.3.8	setMessageListener	1073
6.172	activemq::cmsutil::CachedProducer Class Reference	1075
6.172.1	Detailed Description	1076
6.172.2	Constructor & Destructor Documentation	1076
6.172.2.1	CachedProducer	1076
6.172.2.2	CachedProducer	1076

6.172.2.3 ~CachedProducer	1076
6.172.3 Member Function Documentation	1076
6.172.3.1 close	1076
6.172.3.2 getDeliveryMode	1076
6.172.3.3 getDisableMessageID	1077
6.172.3.4 getDisableMessageTimeStamp	1077
6.172.3.5 getPriority	1077
6.172.3.6 getTimeToLive	1078
6.172.3.7 operator=	1078
6.172.3.8 send	1078
6.172.3.9 send	1078
6.172.3.10 send	1079
6.172.3.11 send	1079
6.172.3.12 setDeliveryMode	1080
6.172.3.13 setDisableMessageID	1080
6.172.3.14 setDisableMessageTimeStamp	1080
6.172.3.15 setPriority	1081
6.172.3.16 setTimeToLive	1081
6.173 decaf::util::concurrent::Callable< V > Class Template Reference	1082
6.173.1 Detailed Description	1082
6.173.2 Constructor & Destructor Documentation	1082
6.173.2.1 ~Callable	1082
6.173.3 Member Function Documentation	1082
6.173.3.1 call	1082
6.174 decaf::util::concurrent::CancellationException Class Reference	1083
6.174.1 Constructor & Destructor Documentation	1083
6.174.1.1 CancellationException	1083
6.174.1.2 CancellationException	1083
6.174.1.3 CancellationException	1084
6.174.1.4 CancellationException	1084
6.174.1.5 CancellationException	1084
6.174.1.6 CancellationException	1084
6.174.1.7 ~CancellationException	1085
6.174.2 Member Function Documentation	1085
6.174.2.1 clone	1085
6.175 decaf::security::cert::Certificate Class Reference	1086

6.175.1 Detailed Description	1086
6.175.2 Constructor & Destructor Documentation	1087
6.175.2.1 ~Certificate	1087
6.175.3 Member Function Documentation	1087
6.175.3.1 equals	1087
6.175.3.2 getEncoded	1087
6.175.3.3 getPublicKey	1087
6.175.3.4 getPublicKey	1087
6.175.3.5 getType	1088
6.175.3.6 toString	1088
6.175.3.7 verify	1088
6.175.3.8 verify	1088
6.176decaf::security::cert::CertificateEncodingException Class Reference	1090
6.176.1 Constructor & Destructor Documentation	1090
6.176.1.1 CertificateEncodingException	1090
6.176.1.2 CertificateEncodingException	1090
6.176.1.3 CertificateEncodingException	1090
6.176.1.4 CertificateEncodingException	1091
6.176.1.5 ~CertificateEncodingException	1091
6.176.2 Member Function Documentation	1091
6.176.2.1 clone	1091
6.177decaf::security::cert::CertificateException Class Reference	1092
6.177.1 Constructor & Destructor Documentation	1092
6.177.1.1 CertificateException	1092
6.177.1.2 CertificateException	1092
6.177.1.3 CertificateException	1092
6.177.1.4 CertificateException	1093
6.177.1.5 ~CertificateException	1093
6.177.2 Member Function Documentation	1093
6.177.2.1 clone	1093
6.178decaf::security::cert::CertificateExpiredException Class Reference	1094
6.178.1 Constructor & Destructor Documentation	1094
6.178.1.1 CertificateExpiredException	1094
6.178.1.2 CertificateExpiredException	1094
6.178.1.3 CertificateExpiredException	1094
6.178.1.4 CertificateExpiredException	1095

6.178.1.5 ~CertificateExpiredException	1095
6.178.2 Member Function Documentation	1095
6.178.2.1 clone	1095
6.179decaf::security::cert::CertificateNotYetValidException Class Reference	1096
6.179.1 Constructor & Destructor Documentation	1096
6.179.1.1 CertificateNotYetValidException	1096
6.179.1.2 CertificateNotYetValidException	1096
6.179.1.3 CertificateNotYetValidException	1096
6.179.1.4 CertificateNotYetValidException	1097
6.179.1.5 ~CertificateNotYetValidException	1097
6.179.2 Member Function Documentation	1097
6.179.2.1 clone	1097
6.180decaf::security::cert::CertificateParsingException Class Reference	1098
6.180.1 Constructor & Destructor Documentation	1098
6.180.1.1 CertificateParsingException	1098
6.180.1.2 CertificateParsingException	1098
6.180.1.3 CertificateParsingException	1098
6.180.1.4 CertificateParsingException	1099
6.180.1.5 ~CertificateParsingException	1099
6.180.2 Member Function Documentation	1099
6.180.2.1 clone	1099
6.181decaf::lang::Character Class Reference	1100
6.181.1 Constructor & Destructor Documentation	1102
6.181.1.1 Character	1102
6.181.2 Member Function Documentation	1102
6.181.2.1 byteValue	1102
6.181.2.2 compareTo	1102
6.181.2.3 compareTo	1102
6.181.2.4 digit	1103
6.181.2.5 doubleValue	1103
6.181.2.6 equals	1103
6.181.2.7 equals	1103
6.181.2.8 floatValue	1103
6.181.2.9 intValue	1104
6.181.2.10sDigit	1104
6.181.2.11sISOControl	1104

6.181.2.12sLetter	1104
6.181.2.13sLetterOrDigit	1104
6.181.2.14sLowerCase	1104
6.181.2.15sUpperCase	1104
6.181.2.16sWhitespace	1104
6.181.2.17ongValue	1105
6.181.2.18operator<	1105
6.181.2.19operator<	1105
6.181.2.20operator==	1105
6.181.2.21operator==	1106
6.181.2.22hortValue	1106
6.181.2.23oString	1106
6.181.2.24valueOf	1106
6.181.3 Field Documentation	1106
6.181.3.1 MAX_RADIX	1106
6.181.3.2 MAX_VALUE	1106
6.181.3.3 MIN_RADIX	1107
6.181.3.4 MIN_VALUE	1107
6.181.3.5 SIZE	1107
6.182decaf::nio::CharArrayBuffer Class Reference	1108
6.182.1 Constructor & Destructor Documentation	1111
6.182.1.1 CharArrayBuffer	1111
6.182.1.2 CharArrayBuffer	1112
6.182.1.3 CharArrayBuffer	1112
6.182.1.4 CharArrayBuffer	1113
6.182.1.5 ~CharArrayBuffer	1113
6.182.2 Member Function Documentation	1113
6.182.2.1 array	1113
6.182.2.2 arrayOffset	1113
6.182.2.3 asReadOnlyBuffer	1114
6.182.2.4 compact	1114
6.182.2.5 duplicate	1114
6.182.2.6 get	1115
6.182.2.7 get	1115
6.182.2.8 hasArray	1115
6.182.2.9 isReadOnly	1116

6.182.2.10	put	1116
6.182.2.11	put	1116
6.182.2.12	setReadOnly	1117
6.182.2.13	slice	1117
6.182.2.14	subSequence	1117
6.182.3	Field Documentation	1118
6.182.3.1	_array	1118
6.182.3.2	length	1118
6.182.3.3	offset	1118
6.182.3.4	readOnly	1118
6.183	decaf::nio::CharBuffer Class Reference	1119
6.183.1	Detailed Description	1122
6.183.2	Constructor & Destructor Documentation	1122
6.183.2.1	CharBuffer	1122
6.183.2.2	~CharBuffer	1122
6.183.3	Member Function Documentation	1122
6.183.3.1	allocate	1122
6.183.3.2	append	1123
6.183.3.3	append	1123
6.183.3.4	append	1124
6.183.3.5	array	1124
6.183.3.6	arrayOffset	1124
6.183.3.7	asReadOnlyBuffer	1125
6.183.3.8	charAt	1125
6.183.3.9	compact	1125
6.183.3.10	compareTo	1126
6.183.3.11	duplicate	1126
6.183.3.12	equals	1126
6.183.3.13	get	1126
6.183.3.14	get	1127
6.183.3.15	get	1127
6.183.3.16	get	1127
6.183.3.17	hasArray	1128
6.183.3.18	length	1128
6.183.3.19	operator<	1128
6.183.3.20	operator==	1128

6.183.3.21put	1128
6.183.3.22put	1129
6.183.3.23put	1129
6.183.3.24put	1130
6.183.3.25put	1130
6.183.3.26put	1130
6.183.3.27put	1131
6.183.3.28read	1131
6.183.3.29lice	1132
6.183.3.30ubSequence	1132
6.183.3.31toString	1133
6.183.3.32wrap	1133
6.183.3.33wrap	1133
6.184decaf::lang::CharSequence Class Reference	1135
6.184.1 Detailed Description	1135
6.184.2 Constructor & Destructor Documentation	1135
6.184.2.1 ~CharSequence	1135
6.184.3 Member Function Documentation	1135
6.184.3.1 charAt	1135
6.184.3.2 length	1136
6.184.3.3 subSequence	1136
6.184.3.4 toString	1136
6.185decaf::util::zip::CheckedInputStream Class Reference	1137
6.185.1 Detailed Description	1137
6.185.2 Constructor & Destructor Documentation	1138
6.185.2.1 CheckedInputStream	1138
6.185.2.2 ~CheckedInputStream	1138
6.185.3 Member Function Documentation	1138
6.185.3.1 doReadArrayBounded	1138
6.185.3.2 doReadByte	1138
6.185.3.3 getChecksum	1138
6.185.3.4 skip	1139
6.186decaf::util::zip::CheckedOutputStream Class Reference	1140
6.186.1 Detailed Description	1140
6.186.2 Constructor & Destructor Documentation	1140
6.186.2.1 CheckedOutputStream	1140

6.186.2.2 ~CheckedOutputStream	1141
6.186.3 Member Function Documentation	1141
6.186.3.1 doWriteArrayBounded	1141
6.186.3.2 doWriteByte	1141
6.186.3.3 getChecksum	1141
6.187decaf::util::zip::Checksum Class Reference	1142
6.187.1 Detailed Description	1142
6.187.2 Constructor & Destructor Documentation	1142
6.187.2.1 ~Checksum	1142
6.187.3 Member Function Documentation	1142
6.187.3.1 getValue	1142
6.187.3.2 reset	1143
6.187.3.3 update	1143
6.187.3.4 update	1143
6.187.3.5 update	1143
6.187.3.6 update	1144
6.188decaf::lang::exceptions::ClassCastException Class Reference	1145
6.188.1 Constructor & Destructor Documentation	1145
6.188.1.1 ClassCastException	1145
6.188.1.2 ClassCastException	1145
6.188.1.3 ClassCastException	1146
6.188.1.4 ClassCastException	1146
6.188.1.5 ClassCastException	1146
6.188.1.6 ClassCastException	1146
6.188.1.7 ~ClassCastException	1147
6.188.2 Member Function Documentation	1147
6.188.2.1 clone	1147
6.189cms::Closeable Class Reference	1148
6.189.1 Detailed Description	1148
6.189.2 Constructor & Destructor Documentation	1148
6.189.2.1 ~Closeable	1148
6.189.3 Member Function Documentation	1148
6.189.3.1 close	1148
6.190decaf::io::Closeable Class Reference	1149
6.190.1 Detailed Description	1149
6.190.2 Constructor & Destructor Documentation	1149

6.190.2.1 ~Closeable	1149
6.190.3 Member Function Documentation	1149
6.190.3.1 close	1149
6.191activemq::transport::failover::CloseTransportsTask Class Reference	1151
6.191.1 Constructor & Destructor Documentation	1151
6.191.1.1 CloseTransportsTask	1151
6.191.1.2 ~CloseTransportsTask	1151
6.191.2 Member Function Documentation	1151
6.191.2.1 add	1151
6.191.2.2 isPending	1151
6.191.2.3 iterate	1152
6.192activemq::cmsutil::CmsAccessor Class Reference	1153
6.192.1 Detailed Description	1154
6.192.2 Constructor & Destructor Documentation	1154
6.192.2.1 CmsAccessor	1154
6.192.2.2 CmsAccessor	1154
6.192.2.3 ~CmsAccessor	1154
6.192.3 Member Function Documentation	1154
6.192.3.1 checkConnectionFactory	1154
6.192.3.2 createConnection	1154
6.192.3.3 createSession	1155
6.192.3.4 destroy	1155
6.192.3.5 getConnectionFactory	1155
6.192.3.6 getConnectionFactory	1155
6.192.3.7 getResourceLifecycleManager	1155
6.192.3.8 getResourceLifecycleManager	1155
6.192.3.9 getSessionAcknowledgeMode	1155
6.192.3.10init	1156
6.192.3.11operator=	1156
6.192.3.12setConnectionFactory	1156
6.192.3.13setSessionAcknowledgeMode	1156
6.193activemq::cmsutil::CmsDestinationAccessor Class Reference	1157
6.193.1 Detailed Description	1157
6.193.2 Constructor & Destructor Documentation	1158
6.193.2.1 CmsDestinationAccessor	1158
6.193.2.2 CmsDestinationAccessor	1158

6.193.2.3 ~CmsDestinationAccessor	1158
6.193.3 Member Function Documentation	1158
6.193.3.1 checkDestinationResolver	1158
6.193.3.2 destroy	1158
6.193.3.3 getDestinationResolver	1158
6.193.3.4 getDestinationResolver	1158
6.193.3.5 init	1158
6.193.3.6 isPubSubDomain	1159
6.193.3.7 operator=	1159
6.193.3.8 resolveDestinationName	1159
6.193.3.9 setDestinationResolver	1159
6.193.3.10 setPubSubDomain	1159
6.194 cms::CMSException Class Reference	1160
6.194.1 Detailed Description	1160
6.194.2 Constructor & Destructor Documentation	1161
6.194.2.1 CMSException	1161
6.194.2.2 CMSException	1161
6.194.2.3 CMSException	1161
6.194.2.4 CMSException	1161
6.194.2.5 ~CMSException	1161
6.194.3 Member Function Documentation	1161
6.194.3.1 getCause	1161
6.194.3.2 getMessage	1161
6.194.3.3 getStackTrace	1161
6.194.3.4 getStackTraceString	1162
6.194.3.5 printStackTrace	1162
6.194.3.6 printStackTrace	1162
6.194.3.7 setMark	1162
6.194.3.8 what	1162
6.195 activemq::util::CMSExceptionSupport Class Reference	1163
6.195.1 Constructor & Destructor Documentation	1163
6.195.1.1 ~CMSExceptionSupport	1163
6.195.2 Member Function Documentation	1163
6.195.2.1 create	1163
6.195.2.2 create	1163
6.195.2.3 createMessageEOFException	1163

6.195.2.4 createMessageFormatException	1163
6.196cms::CMSProperties Class Reference	1165
6.196.1 Detailed Description	1166
6.196.2 Constructor & Destructor Documentation	1166
6.196.2.1 ~CMSProperties	1166
6.196.3 Member Function Documentation	1166
6.196.3.1 clear	1166
6.196.3.2 clone	1166
6.196.3.3 copy	1166
6.196.3.4 getProperty	1166
6.196.3.5 getProperty	1167
6.196.3.6 hasProperty	1167
6.196.3.7 isEmpty	1167
6.196.3.8 remove	1167
6.196.3.9 setProperty	1168
6.196.3.10oArray	1168
6.196.3.11toString	1168
6.197cms::CMSSecurityException Class Reference	1169
6.197.1 Detailed Description	1169
6.197.2 Constructor & Destructor Documentation	1169
6.197.2.1 CMSSecurityException	1169
6.197.2.2 CMSSecurityException	1169
6.197.2.3 CMSSecurityException	1169
6.197.2.4 CMSSecurityException	1169
6.197.2.5 ~CMSSecurityException	1169
6.198activemq::cmsutil::CmsTemplate Class Reference	1170
6.198.1 Detailed Description	1173
6.198.2 Constructor & Destructor Documentation	1173
6.198.2.1 CmsTemplate	1173
6.198.2.2 CmsTemplate	1173
6.198.2.3 CmsTemplate	1173
6.198.2.4 ~CmsTemplate	1173
6.198.3 Member Function Documentation	1173
6.198.3.1 destroy	1173
6.198.3.2 execute	1174
6.198.3.3 execute	1174

6.198.3.4	execute	1174
6.198.3.5	execute	1174
6.198.3.6	getDefaultDestination	1175
6.198.3.7	getDefaultDestination	1175
6.198.3.8	getDefaultDestinationName	1175
6.198.3.9	getDeliveryMode	1175
6.198.3.10	getPriority	1175
6.198.3.11	getReceiveTimeout	1176
6.198.3.12	getTimeToLive	1176
6.198.3.13	init	1176
6.198.3.14	isExplicitQosEnabled	1176
6.198.3.15	isMessageIdEnabled	1176
6.198.3.16	isMessageTimestampEnabled	1176
6.198.3.17	isNoLocal	1176
6.198.3.18	operator=	1176
6.198.3.19	receive	1176
6.198.3.20	receive	1177
6.198.3.21	receive	1177
6.198.3.22	receiveSelected	1177
6.198.3.23	receiveSelected	1178
6.198.3.24	receiveSelected	1178
6.198.3.25	send	1178
6.198.3.26	send	1179
6.198.3.27	send	1179
6.198.3.28	setDefaultDestination	1179
6.198.3.29	setDefaultDestinationName	1180
6.198.3.30	setDeliveryMode	1180
6.198.3.31	setDeliveryPersistent	1180
6.198.3.32	setExplicitQosEnabled	1180
6.198.3.33	setMessageIdEnabled	1181
6.198.3.34	setMessageTimestampEnabled	1181
6.198.3.35	setNoLocal	1181
6.198.3.36	setPriority	1181
6.198.3.37	setPubSubDomain	1181
6.198.3.38	setReceiveTimeout	1181
6.198.3.39	setTimeToLive	1181

6.198.4 Friends And Related Function Documentation	1182
6.198.4.1 ProducerExecutor	1182
6.198.4.2 ReceiveExecutor	1182
6.198.4.3 ResolveProducerExecutor	1182
6.198.4.4 ResolveReceiveExecutor	1182
6.198.4.5 SendExecutor	1182
6.198.5 Field Documentation	1182
6.198.5.1 DEFAULT_PRIORITY	1182
6.198.5.2 DEFAULT_TIME_TO_LIVE	1182
6.198.5.3 RECEIVE_TIMEOUT_INDEFINITE_WAIT	1182
6.198.5.4 RECEIVE_TIMEOUT_NO_WAIT	1182
6.199 code Struct Reference	1183
6.199.1 Field Documentation	1183
6.199.1.1 bits	1183
6.199.1.2 op	1183
6.199.1.3 val	1183
6.200 decaf::util::Collection< E > Class Template Reference	1184
6.200.1 Detailed Description	1185
6.200.2 Constructor & Destructor Documentation	1186
6.200.2.1 ~Collection	1186
6.200.3 Member Function Documentation	1186
6.200.3.1 add	1186
6.200.3.2 addAll	1187
6.200.3.3 clear	1187
6.200.3.4 contains	1188
6.200.3.5 containsAll	1189
6.200.3.6 equals	1189
6.200.3.7 isEmpty	1189
6.200.3.8 remove	1190
6.200.3.9 removeAll	1191
6.200.3.10 retainAll	1191
6.200.3.11 size	1192
6.200.3.12 toArray	1192
6.201 activemq::commands::Command Class Reference	1194
6.201.1 Constructor & Destructor Documentation	1195
6.201.1.1 ~Command	1195

6.201.2 Member Function Documentation	1195
6.201.2.1 getCommandId	1195
6.201.2.2 isBrokerInfo	1195
6.201.2.3 isConnectionInfo	1195
6.201.2.4 isConsumerInfo	1195
6.201.2.5 isKeepAliveInfo	1195
6.201.2.6 isMessage	1195
6.201.2.7 isMessageAck	1196
6.201.2.8 isMessageDispatch	1196
6.201.2.9 isMessageDispatchNotification	1196
6.201.2.10sProducerAck	1196
6.201.2.11sProducerInfo	1196
6.201.2.12sRemoveInfo	1196
6.201.2.13sRemoveSubscriptionInfo	1196
6.201.2.14sResponse	1196
6.201.2.15sResponseRequired	1197
6.201.2.16sShutdownInfo	1197
6.201.2.17sTransactionInfo	1197
6.201.2.18sWireFormatInfo	1197
6.201.2.19setCommandId	1197
6.201.2.20setResponseRequired	1197
6.201.2.21toString	1198
6.201.2.22visit	1198
6.202activemq::state::CommandVisitor Class Reference	1200
6.202.1 Detailed Description	1201
6.202.2 Constructor & Destructor Documentation	1202
6.202.2.1 ~CommandVisitor	1202
6.202.3 Member Function Documentation	1202
6.202.3.1 processBeginTransaction	1202
6.202.3.2 processBrokerError	1202
6.202.3.3 processBrokerInfo	1202
6.202.3.4 processCommitTransactionOnePhase	1202
6.202.3.5 processCommitTransactionTwoPhase	1202
6.202.3.6 processConnectionControl	1203
6.202.3.7 processConnectionError	1203
6.202.3.8 processConnectionInfo	1203

6.202.3.9 processConsumerControl	1203
6.202.3.10 processConsumerInfo	1203
6.202.3.11 processControlCommand	1203
6.202.3.12 processDestinationInfo	1203
6.202.3.13 processEndTransaction	1203
6.202.3.14 processFlushCommand	1204
6.202.3.15 processForgetTransaction	1204
6.202.3.16 processKeepAliveInfo	1204
6.202.3.17 processMessage	1204
6.202.3.18 processMessageAck	1204
6.202.3.19 processMessageDispatch	1204
6.202.3.20 processMessageDispatchNotification	1204
6.202.3.21 processMessagePull	1204
6.202.3.22 processPrepareTransaction	1204
6.202.3.23 processProducerAck	1205
6.202.3.24 processProducerInfo	1205
6.202.3.25 processRecoverTransactions	1205
6.202.3.26 processRemoveConnection	1205
6.202.3.27 processRemoveConsumer	1205
6.202.3.28 processRemoveDestination	1205
6.202.3.29 processRemoveInfo	1205
6.202.3.30 processRemoveProducer	1205
6.202.3.31 processRemoveSession	1206
6.202.3.32 processRemoveSubscriptionInfo	1206
6.202.3.33 processReplayCommand	1206
6.202.3.34 processResponse	1206
6.202.3.35 processRollbackTransaction	1206
6.202.3.36 processSessionInfo	1206
6.202.3.37 processShutdownInfo	1206
6.202.3.38 processTransactionInfo	1206
6.202.3.39 processWireFormat	1207
6.203 activemq::state::CommandVisitorAdapter Class Reference	1208
6.203.1 Detailed Description	1210
6.203.2 Constructor & Destructor Documentation	1211
6.203.2.1 ~CommandVisitorAdapter	1211
6.203.3 Member Function Documentation	1211

6.203.3.1	processBeginTransaction	1211
6.203.3.2	processBrokerError	1211
6.203.3.3	processBrokerInfo	1211
6.203.3.4	processCommitTransactionOnePhase	1211
6.203.3.5	processCommitTransactionTwoPhase	1211
6.203.3.6	processConnectionControl	1211
6.203.3.7	processConnectionError	1211
6.203.3.8	processConnectionInfo	1211
6.203.3.9	processConsumerControl	1211
6.203.3.10	processConsumerInfo	1211
6.203.3.11	processControlCommand	1211
6.203.3.12	processDestinationInfo	1211
6.203.3.13	processEndTransaction	1211
6.203.3.14	processFlushCommand	1211
6.203.3.15	processForgetTransaction	1211
6.203.3.16	processKeepAliveInfo	1211
6.203.3.17	processMessage	1211
6.203.3.18	processMessageAck	1211
6.203.3.19	processMessageDispatch	1211
6.203.3.20	processMessageDispatchNotification	1211
6.203.3.21	processMessagePull	1211
6.203.3.22	processPrepareTransaction	1211
6.203.3.23	processProducerAck	1211
6.203.3.24	processProducerInfo	1211
6.203.3.25	processRecoverTransactions	1211
6.203.3.26	processRemoveConnection	1211
6.203.3.27	processRemoveConsumer	1211
6.203.3.28	processRemoveDestination	1211
6.203.3.29	processRemoveInfo	1211
6.203.3.30	processRemoveProducer	1212
6.203.3.31	processRemoveSession	1212
6.203.3.32	processRemoveSubscriptionInfo	1212
6.203.3.33	processReplayCommand	1212
6.203.3.34	processResponse	1212
6.203.3.35	processRollbackTransaction	1212
6.203.3.36	processSessionInfo	1212

6.203.3.37	processShutdownInfo	1212
6.203.3.38	processTransactionInfo	1212
6.203.3.39	processWireFormat	1213
6.204	decaf::lang::Comparable< T > Class Template Reference	1214
6.204.1	Detailed Description	1214
6.204.2	Constructor & Destructor Documentation	1214
6.204.2.1	~Comparable	1214
6.204.3	Member Function Documentation	1214
6.204.3.1	compareTo	1214
6.204.3.2	equals	1215
6.204.3.3	operator<	1215
6.204.3.4	operator==	1215
6.205	decaf::util::Comparator< T > Class Template Reference	1217
6.205.1	Detailed Description	1217
6.205.2	Constructor & Destructor Documentation	1217
6.205.2.1	~Comparator	1217
6.205.3	Member Function Documentation	1217
6.205.3.1	compare	1217
6.205.3.2	operator()	1218
6.206	activemq::util::CompositeData Class Reference	1219
6.206.1	Detailed Description	1219
6.206.2	Constructor & Destructor Documentation	1220
6.206.2.1	CompositeData	1220
6.206.2.2	~CompositeData	1220
6.206.3	Member Function Documentation	1220
6.206.3.1	getComponents	1220
6.206.3.2	getComponents	1220
6.206.3.3	getFragment	1220
6.206.3.4	getHost	1220
6.206.3.5	getParameters	1220
6.206.3.6	getPath	1220
6.206.3.7	getScheme	1220
6.206.3.8	setComponents	1220
6.206.3.9	setFragment	1220
6.206.3.10	setHost	1220
6.206.3.11	setParameters	1220

6.206.3.12	setPath	1220
6.206.3.13	setScheme	1220
6.206.3.14	oURI	1220
6.207	activemq::threads::CompositeTask Class Reference	1221
6.207.1	Detailed Description	1221
6.207.2	Constructor & Destructor Documentation	1221
6.207.2.1	~CompositeTask	1221
6.207.3	Member Function Documentation	1221
6.207.3.1	isPending	1221
6.208	activemq::threads::CompositeTaskRunner Class Reference	1223
6.208.1	Detailed Description	1223
6.208.2	Constructor & Destructor Documentation	1224
6.208.2.1	CompositeTaskRunner	1224
6.208.2.2	~CompositeTaskRunner	1224
6.208.3	Member Function Documentation	1224
6.208.3.1	addTask	1224
6.208.3.2	iterate	1224
6.208.3.3	removeTask	1224
6.208.3.4	run	1224
6.208.3.5	shutdown	1224
6.208.3.6	shutdown	1225
6.208.3.7	wakeup	1225
6.209	activemq::transport::CompositeTransport Class Reference	1226
6.209.1	Detailed Description	1226
6.209.2	Constructor & Destructor Documentation	1226
6.209.2.1	~CompositeTransport	1226
6.209.3	Member Function Documentation	1226
6.209.3.1	addURI	1226
6.209.3.2	removeURI	1227
6.210	decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR > Class Template Reference	1228
6.210.1	Detailed Description	1228
6.210.2	Constructor & Destructor Documentation	1229
6.210.2.1	~ConcurrentMap	1229
6.210.3	Member Function Documentation	1229
6.210.3.1	putIfAbsent	1229
6.210.3.2	remove	1230

6.210.3.3 replace	1230
6.210.3.4 replace	1231
6.211decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > Class Template Reference	1233
6.211.1 Detailed Description	1236
6.211.2 Constructor & Destructor Documentation	1237
6.211.2.1 ConcurrentStlMap	1237
6.211.2.2 ConcurrentStlMap	1237
6.211.2.3 ConcurrentStlMap	1237
6.211.2.4 ~ConcurrentStlMap	1237
6.211.3 Member Function Documentation	1237
6.211.3.1 clear	1237
6.211.3.2 containsKey	1238
6.211.3.3 containsValue	1238
6.211.3.4 copy	1239
6.211.3.5 copy	1239
6.211.3.6 equals	1239
6.211.3.7 equals	1239
6.211.3.8 get	1239
6.211.3.9 get	1240
6.211.3.10isEmpty	1240
6.211.3.11keySet	1240
6.211.3.12lock	1241
6.211.3.13notify	1241
6.211.3.14notifyAll	1241
6.211.3.15put	1242
6.211.3.16putAll	1242
6.211.3.17putAll	1242
6.211.3.18putIfAbsent	1243
6.211.3.19remove	1243
6.211.3.20remove	1244
6.211.3.21replace	1244
6.211.3.22replace	1245
6.211.3.23size	1246
6.211.3.24tryLock	1246
6.211.3.25unlock	1246
6.211.3.26values	1246

6.211.3.27wait	1247
6.211.3.28wait	1247
6.211.3.29wait	1248
6.212decaf::util::concurrent::locks::Condition Class Reference	1249
6.212.1 Detailed Description	1249
6.212.2 Constructor & Destructor Documentation	1251
6.212.2.1 ~Condition	1251
6.212.3 Member Function Documentation	1251
6.212.3.1 await	1251
6.212.3.2 await	1251
6.212.3.3 awaitNanos	1252
6.212.3.4 awaitUninterruptibly	1253
6.212.3.5 awaitUntil	1254
6.212.3.6 signal	1254
6.212.3.7 signalAll	1254
6.213decaf::util::concurrent::ConditionHandle Class Reference	1255
6.213.1 Constructor & Destructor Documentation	1255
6.213.1.1 ConditionHandle	1255
6.213.1.2 ~ConditionHandle	1255
6.213.1.3 ConditionHandle	1255
6.213.1.4 ~ConditionHandle	1255
6.213.2 Field Documentation	1255
6.213.2.1 condition	1255
6.213.2.2 criticalSection	1255
6.213.2.3 generation	1255
6.213.2.4 mutex	1255
6.213.2.5 numWaiting	1255
6.213.2.6 numWake	1255
6.213.2.7 semaphore	1255
6.214decaf::internal::util::concurrent::ConditionImpl Class Reference	1257
6.214.1 Member Function Documentation	1257
6.214.1.1 create	1257
6.214.1.2 destroy	1257
6.214.1.3 notify	1258
6.214.1.4 notifyAll	1258
6.214.1.5 wait	1258

6.214.1.6 wait	1258
6.215decaf::net::ConnectException Class Reference	1259
6.215.1 Constructor & Destructor Documentation	1259
6.215.1.1 ConnectException	1259
6.215.1.2 ConnectException	1259
6.215.1.3 ConnectException	1260
6.215.1.4 ConnectException	1260
6.215.1.5 ConnectException	1260
6.215.1.6 ConnectException	1260
6.215.1.7 ~ConnectException	1261
6.215.2 Member Function Documentation	1261
6.215.2.1 clone	1261
6.216cms::Connection Class Reference	1262
6.216.1 Detailed Description	1262
6.216.2 Constructor & Destructor Documentation	1263
6.216.2.1 ~Connection	1263
6.216.3 Member Function Documentation	1263
6.216.3.1 close	1263
6.216.3.2 createSession	1264
6.216.3.3 createSession	1264
6.216.3.4 getClientID	1264
6.216.3.5 getExceptionListener	1264
6.216.3.6 getMetaData	1265
6.216.3.7 setClientID	1265
6.216.3.8 setExceptionListener	1265
6.217activemq::commands::ConnectionControl Class Reference	1267
6.217.1 Constructor & Destructor Documentation	1268
6.217.1.1 ConnectionControl	1268
6.217.1.2 ~ConnectionControl	1268
6.217.2 Member Function Documentation	1268
6.217.2.1 cloneDataStructure	1268
6.217.2.2 copyDataStructure	1268
6.217.2.3 equals	1269
6.217.2.4 getConnectedBrokers	1269
6.217.2.5 getConnectedBrokers	1269
6.217.2.6 getDataStructureType	1269

6.217.2.7	getReconnectTo	1270
6.217.2.8	getReconnectTo	1270
6.217.2.9	isClose	1270
6.217.2.10	isExit	1270
6.217.2.11	isFaultTolerant	1270
6.217.2.12	isRebalanceConnection	1270
6.217.2.13	isResume	1270
6.217.2.14	isSuspend	1270
6.217.2.15	setClose	1270
6.217.2.16	setConnectedBrokers	1270
6.217.2.17	setExit	1270
6.217.2.18	setFaultTolerant	1270
6.217.2.19	setRebalanceConnection	1270
6.217.2.20	setReconnectTo	1270
6.217.2.21	setResume	1270
6.217.2.22	setSuspend	1270
6.217.2.23	toString	1270
6.217.2.24	visit	1271
6.217.3	Field Documentation	1271
6.217.3.1	close	1271
6.217.3.2	connectedBrokers	1271
6.217.3.3	exit	1271
6.217.3.4	faultTolerant	1271
6.217.3.5	ID_CONNECTIONCONTROL	1271
6.217.3.6	rebalanceConnection	1271
6.217.3.7	reconnectTo	1271
6.217.3.8	resume	1271
6.217.3.9	suspend	1271
6.218	activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller Class	
	Reference	1272
6.218.1	Detailed Description	1272
6.218.2	Constructor & Destructor Documentation	1273
6.218.2.1	ConnectionControlMarshaller	1273
6.218.2.2	~ConnectionControlMarshaller	1273
6.218.3	Member Function Documentation	1273
6.218.3.1	createObject	1273
6.218.3.2	getDataStructureType	1273

6.218.3.3 looseMarshal	1273
6.218.3.4 looseUnmarshal	1274
6.218.3.5 tightMarshal1	1274
6.218.3.6 tightMarshal2	1274
6.218.3.7 tightUnmarshal	1275
6.219activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller Class	
Reference	1276
6.219.1 Detailed Description	1276
6.219.2 Constructor & Destructor Documentation	1277
6.219.2.1 ConnectionControlMarshaller	1277
6.219.2.2 ~ConnectionControlMarshaller	1277
6.219.3 Member Function Documentation	1277
6.219.3.1 createObject	1277
6.219.3.2 getDataStructureType	1277
6.219.3.3 looseMarshal	1277
6.219.3.4 looseUnmarshal	1278
6.219.3.5 tightMarshal1	1278
6.219.3.6 tightMarshal2	1278
6.219.3.7 tightUnmarshal	1279
6.220activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller Class	
Reference	1280
6.220.1 Detailed Description	1280
6.220.2 Constructor & Destructor Documentation	1281
6.220.2.1 ConnectionControlMarshaller	1281
6.220.2.2 ~ConnectionControlMarshaller	1281
6.220.3 Member Function Documentation	1281
6.220.3.1 createObject	1281
6.220.3.2 getDataStructureType	1281
6.220.3.3 looseMarshal	1281
6.220.3.4 looseUnmarshal	1282
6.220.3.5 tightMarshal1	1282
6.220.3.6 tightMarshal2	1282
6.220.3.7 tightUnmarshal	1283
6.221activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller Class	
Reference	1284
6.221.1 Detailed Description	1284
6.221.2 Constructor & Destructor Documentation	1285

6.221.2.1	ConnectionControlMarshaller	1285
6.221.2.2	~ConnectionControlMarshaller	1285
6.221.3	Member Function Documentation	1285
6.221.3.1	createObject	1285
6.221.3.2	getDataStructureType	1285
6.221.3.3	looseMarshal	1285
6.221.3.4	looseUnmarshal	1286
6.221.3.5	tightMarshal1	1286
6.221.3.6	tightMarshal2	1286
6.221.3.7	tightUnmarshal	1287
6.222	activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller Class	
	Reference	1288
6.222.1	Detailed Description	1288
6.222.2	Constructor & Destructor Documentation	1289
6.222.2.1	ConnectionControlMarshaller	1289
6.222.2.2	~ConnectionControlMarshaller	1289
6.222.3	Member Function Documentation	1289
6.222.3.1	createObject	1289
6.222.3.2	getDataStructureType	1289
6.222.3.3	looseMarshal	1289
6.222.3.4	looseUnmarshal	1290
6.222.3.5	tightMarshal1	1290
6.222.3.6	tightMarshal2	1290
6.222.3.7	tightUnmarshal	1291
6.223	activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller Class	
	Reference	1292
6.223.1	Detailed Description	1292
6.223.2	Constructor & Destructor Documentation	1293
6.223.2.1	ConnectionControlMarshaller	1293
6.223.2.2	~ConnectionControlMarshaller	1293
6.223.3	Member Function Documentation	1293
6.223.3.1	createObject	1293
6.223.3.2	getDataStructureType	1293
6.223.3.3	looseMarshal	1293
6.223.3.4	looseUnmarshal	1294
6.223.3.5	tightMarshal1	1294
6.223.3.6	tightMarshal2	1294

6.223.3.7 tightUnmarshal	1295
6.224activemq::commands::ConnectionError Class Reference	1296
6.224.1 Constructor & Destructor Documentation	1297
6.224.1.1 ConnectionError	1297
6.224.1.2 ~ConnectionError	1297
6.224.2 Member Function Documentation	1297
6.224.2.1 cloneDataStructure	1297
6.224.2.2 copyDataStructure	1297
6.224.2.3 equals	1297
6.224.2.4 getConnectionId	1298
6.224.2.5 getConnectionId	1298
6.224.2.6 getDataStructureType	1298
6.224.2.7 getException	1298
6.224.2.8 getException	1298
6.224.2.9 setConnectionId	1298
6.224.2.10setException	1298
6.224.2.11toString	1298
6.224.2.12visit	1298
6.224.3 Field Documentation	1299
6.224.3.1 connectionId	1299
6.224.3.2 exception	1299
6.224.3.3 ID_CONNECTIONERROR	1299
6.225activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller Class Reference	1300
6.225.1 Detailed Description	1300
6.225.2 Constructor & Destructor Documentation	1301
6.225.2.1 ConnectionErrorMarshaller	1301
6.225.2.2 ~ConnectionErrorMarshaller	1301
6.225.3 Member Function Documentation	1301
6.225.3.1 createObject	1301
6.225.3.2 getDataStructureType	1301
6.225.3.3 looseMarshal	1301
6.225.3.4 looseUnmarshal	1302
6.225.3.5 tightMarshal1	1302
6.225.3.6 tightMarshal2	1302
6.225.3.7 tightUnmarshal	1303

6.226	activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	Class	
	Reference		1304
6.226.1	Detailed Description		1304
6.226.2	Constructor & Destructor Documentation		1305
6.226.2.1	ConnectionErrorMarshaller		1305
6.226.2.2	~ConnectionErrorMarshaller		1305
6.226.3	Member Function Documentation		1305
6.226.3.1	createObject		1305
6.226.3.2	getDataStructureType		1305
6.226.3.3	looseMarshal		1305
6.226.3.4	looseUnmarshal		1306
6.226.3.5	tightMarshal1		1306
6.226.3.6	tightMarshal2		1306
6.226.3.7	tightUnmarshal		1307
6.227	activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller	Class	
	Reference		1308
6.227.1	Detailed Description		1308
6.227.2	Constructor & Destructor Documentation		1309
6.227.2.1	ConnectionErrorMarshaller		1309
6.227.2.2	~ConnectionErrorMarshaller		1309
6.227.3	Member Function Documentation		1309
6.227.3.1	createObject		1309
6.227.3.2	getDataStructureType		1309
6.227.3.3	looseMarshal		1309
6.227.3.4	looseUnmarshal		1310
6.227.3.5	tightMarshal1		1310
6.227.3.6	tightMarshal2		1310
6.227.3.7	tightUnmarshal		1311
6.228	activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller	Class	
	Reference		1312
6.228.1	Detailed Description		1312
6.228.2	Constructor & Destructor Documentation		1313
6.228.2.1	ConnectionErrorMarshaller		1313
6.228.2.2	~ConnectionErrorMarshaller		1313
6.228.3	Member Function Documentation		1313
6.228.3.1	createObject		1313
6.228.3.2	getDataStructureType		1313

6.228.3.3 looseMarshal	1313
6.228.3.4 looseUnmarshal	1314
6.228.3.5 tightMarshal1	1314
6.228.3.6 tightMarshal2	1314
6.228.3.7 tightUnmarshal	1315
6.229activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller Class	
Reference	1316
6.229.1 Detailed Description	1316
6.229.2 Constructor & Destructor Documentation	1317
6.229.2.1 ConnectionErrorMarshaller	1317
6.229.2.2 ~ConnectionErrorMarshaller	1317
6.229.3 Member Function Documentation	1317
6.229.3.1 createObject	1317
6.229.3.2 getDataStructureType	1317
6.229.3.3 looseMarshal	1317
6.229.3.4 looseUnmarshal	1318
6.229.3.5 tightMarshal1	1318
6.229.3.6 tightMarshal2	1318
6.229.3.7 tightUnmarshal	1319
6.230activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller Class	
Reference	1320
6.230.1 Detailed Description	1320
6.230.2 Constructor & Destructor Documentation	1321
6.230.2.1 ConnectionErrorMarshaller	1321
6.230.2.2 ~ConnectionErrorMarshaller	1321
6.230.3 Member Function Documentation	1321
6.230.3.1 createObject	1321
6.230.3.2 getDataStructureType	1321
6.230.3.3 looseMarshal	1321
6.230.3.4 looseUnmarshal	1322
6.230.3.5 tightMarshal1	1322
6.230.3.6 tightMarshal2	1322
6.230.3.7 tightUnmarshal	1323
6.231cms::ConnectionFactory Class Reference	1324
6.231.1 Detailed Description	1324
6.231.2 Constructor & Destructor Documentation	1325
6.231.2.1 ~ConnectionFactory	1325

6.231.3 Member Function Documentation	1325
6.231.3.1 createCMSConnectionFactory	1325
6.231.3.2 createConnection	1325
6.231.3.3 createConnection	1326
6.231.3.4 createConnection	1326
6.232activemq::commands::ConnectionId Class Reference	1327
6.232.1 Member Typedef Documentation	1328
6.232.1.1 COMPARATOR	1328
6.232.2 Constructor & Destructor Documentation	1328
6.232.2.1 ConnectionId	1328
6.232.2.2 ConnectionId	1328
6.232.2.3 ConnectionId	1328
6.232.2.4 ConnectionId	1328
6.232.2.5 ConnectionId	1328
6.232.2.6 ~ConnectionId	1328
6.232.3 Member Function Documentation	1328
6.232.3.1 cloneDataStructure	1328
6.232.3.2 compareTo	1328
6.232.3.3 copyDataStructure	1328
6.232.3.4 equals	1329
6.232.3.5 equals	1329
6.232.3.6 getDataStructureType	1329
6.232.3.7 getValue	1329
6.232.3.8 getValue	1329
6.232.3.9 operator<	1329
6.232.3.10operator=	1329
6.232.3.11operator==	1329
6.232.3.12setValue	1329
6.232.3.13toString	1329
6.232.4 Field Documentation	1330
6.232.4.1 ID_CONNECTIONID	1330
6.232.4.2 value	1330
6.233activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller Class Refer- ence	1331
6.233.1 Detailed Description	1331
6.233.2 Constructor & Destructor Documentation	1332
6.233.2.1 ConnectionIdMarshaller	1332

6.233.2.2 <code>~ConnectionIdMarshaller</code>	1332
6.233.3 Member Function Documentation	1332
6.233.3.1 <code>createObject</code>	1332
6.233.3.2 <code>getDataStructureType</code>	1332
6.233.3.3 <code>looseMarshal</code>	1332
6.233.3.4 <code>looseUnmarshal</code>	1333
6.233.3.5 <code>tightMarshal1</code>	1333
6.233.3.6 <code>tightMarshal2</code>	1333
6.233.3.7 <code>tightUnmarshal</code>	1334
6.234 <code>activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller</code> Class Reference	1335
6.234.1 Detailed Description	1335
6.234.2 Constructor & Destructor Documentation	1336
6.234.2.1 <code>ConnectionIdMarshaller</code>	1336
6.234.2.2 <code>~ConnectionIdMarshaller</code>	1336
6.234.3 Member Function Documentation	1336
6.234.3.1 <code>createObject</code>	1336
6.234.3.2 <code>getDataStructureType</code>	1336
6.234.3.3 <code>looseMarshal</code>	1336
6.234.3.4 <code>looseUnmarshal</code>	1337
6.234.3.5 <code>tightMarshal1</code>	1337
6.234.3.6 <code>tightMarshal2</code>	1337
6.234.3.7 <code>tightUnmarshal</code>	1338
6.235 <code>activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller</code> Class Reference	1339
6.235.1 Detailed Description	1339
6.235.2 Constructor & Destructor Documentation	1340
6.235.2.1 <code>ConnectionIdMarshaller</code>	1340
6.235.2.2 <code>~ConnectionIdMarshaller</code>	1340
6.235.3 Member Function Documentation	1340
6.235.3.1 <code>createObject</code>	1340
6.235.3.2 <code>getDataStructureType</code>	1340
6.235.3.3 <code>looseMarshal</code>	1340
6.235.3.4 <code>looseUnmarshal</code>	1341
6.235.3.5 <code>tightMarshal1</code>	1341
6.235.3.6 <code>tightMarshal2</code>	1341
6.235.3.7 <code>tightUnmarshal</code>	1342

6.236activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller Class Reference	1343
6.236.1 Detailed Description	1343
6.236.2 Constructor & Destructor Documentation	1344
6.236.2.1 ConnectionIdMarshaller	1344
6.236.2.2 ~ConnectionIdMarshaller	1344
6.236.3 Member Function Documentation	1344
6.236.3.1 createObject	1344
6.236.3.2 getDataStructureType	1344
6.236.3.3 looseMarshal	1344
6.236.3.4 looseUnmarshal	1345
6.236.3.5 tightMarshal1	1345
6.236.3.6 tightMarshal2	1345
6.236.3.7 tightUnmarshal	1346
6.237activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller Class Reference	1347
6.237.1 Detailed Description	1347
6.237.2 Constructor & Destructor Documentation	1348
6.237.2.1 ConnectionIdMarshaller	1348
6.237.2.2 ~ConnectionIdMarshaller	1348
6.237.3 Member Function Documentation	1348
6.237.3.1 createObject	1348
6.237.3.2 getDataStructureType	1348
6.237.3.3 looseMarshal	1348
6.237.3.4 looseUnmarshal	1349
6.237.3.5 tightMarshal1	1349
6.237.3.6 tightMarshal2	1349
6.237.3.7 tightUnmarshal	1350
6.238activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller Class Reference	1351
6.238.1 Detailed Description	1351
6.238.2 Constructor & Destructor Documentation	1352
6.238.2.1 ConnectionIdMarshaller	1352
6.238.2.2 ~ConnectionIdMarshaller	1352
6.238.3 Member Function Documentation	1352
6.238.3.1 createObject	1352
6.238.3.2 getDataStructureType	1352

6.238.3.3 looseMarshal	1352
6.238.3.4 looseUnmarshal	1353
6.238.3.5 tightMarshal1	1353
6.238.3.6 tightMarshal2	1353
6.238.3.7 tightUnmarshal	1354
6.239activemq::commands::ConnectionInfo Class Reference	1355
6.239.1 Constructor & Destructor Documentation	1356
6.239.1.1 ConnectionInfo	1356
6.239.1.2 ~ConnectionInfo	1356
6.239.2 Member Function Documentation	1356
6.239.2.1 cloneDataStructure	1356
6.239.2.2 copyDataStructure	1357
6.239.2.3 createRemoveCommand	1357
6.239.2.4 equals	1357
6.239.2.5 getBrokerPath	1357
6.239.2.6 getBrokerPath	1357
6.239.2.7 getClientId	1357
6.239.2.8 getClientId	1357
6.239.2.9 getConnectionId	1357
6.239.2.10getConnectionId	1357
6.239.2.11getDataStructureType	1357
6.239.2.12getPassword	1358
6.239.2.13getPassword	1358
6.239.2.14getUserName	1358
6.239.2.15getUserName	1358
6.239.2.16sBrokerMasterConnector	1358
6.239.2.17sClientMaster	1358
6.239.2.18sConnectionInfo	1358
6.239.2.19sFaultTolerant	1359
6.239.2.20sManageable	1359
6.239.2.21setBrokerMasterConnector	1359
6.239.2.22setBrokerPath	1359
6.239.2.23setClientId	1359
6.239.2.24setClientMaster	1359
6.239.2.25setConnectionId	1359
6.239.2.26setFaultTolerant	1359

6.239.2.27	setManageable	1359
6.239.2.28	setPassword	1359
6.239.2.29	setUserName	1359
6.239.2.30	toString	1359
6.239.2.31	visit	1359
6.239.3	Field Documentation	1360
6.239.3.1	brokerMasterConnector	1360
6.239.3.2	brokerPath	1360
6.239.3.3	clientId	1360
6.239.3.4	clientMaster	1360
6.239.3.5	connectionId	1360
6.239.3.6	faultTolerant	1360
6.239.3.7	ID_CONNECTIONINFO	1360
6.239.3.8	manageable	1360
6.239.3.9	password	1360
6.239.3.10	userName	1360
6.240	activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller Class Reference	1361
6.240.1	Detailed Description	1361
6.240.2	Constructor & Destructor Documentation	1362
6.240.2.1	ConnectionInfoMarshaller	1362
6.240.2.2	~ConnectionInfoMarshaller	1362
6.240.3	Member Function Documentation	1362
6.240.3.1	createObject	1362
6.240.3.2	getDataStructureType	1362
6.240.3.3	looseMarshal	1362
6.240.3.4	looseUnmarshal	1363
6.240.3.5	tightMarshal1	1363
6.240.3.6	tightMarshal2	1363
6.240.3.7	tightUnmarshal	1364
6.241	activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller Class Reference	1365
6.241.1	Detailed Description	1365
6.241.2	Constructor & Destructor Documentation	1366
6.241.2.1	ConnectionInfoMarshaller	1366
6.241.2.2	~ConnectionInfoMarshaller	1366
6.241.3	Member Function Documentation	1366

6.241.3.1 createObject	1366
6.241.3.2 getDataStructureType	1366
6.241.3.3 looseMarshal	1366
6.241.3.4 looseUnmarshal	1367
6.241.3.5 tightMarshal1	1367
6.241.3.6 tightMarshal2	1367
6.241.3.7 tightUnmarshal	1368
6.242activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller Class Reference	1369
6.242.1 Detailed Description	1369
6.242.2 Constructor & Destructor Documentation	1370
6.242.2.1 ConnectionInfoMarshaller	1370
6.242.2.2 ~ConnectionInfoMarshaller	1370
6.242.3 Member Function Documentation	1370
6.242.3.1 createObject	1370
6.242.3.2 getDataStructureType	1370
6.242.3.3 looseMarshal	1370
6.242.3.4 looseUnmarshal	1371
6.242.3.5 tightMarshal1	1371
6.242.3.6 tightMarshal2	1371
6.242.3.7 tightUnmarshal	1372
6.243activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller Class Reference	1373
6.243.1 Detailed Description	1373
6.243.2 Constructor & Destructor Documentation	1374
6.243.2.1 ConnectionInfoMarshaller	1374
6.243.2.2 ~ConnectionInfoMarshaller	1374
6.243.3 Member Function Documentation	1374
6.243.3.1 createObject	1374
6.243.3.2 getDataStructureType	1374
6.243.3.3 looseMarshal	1374
6.243.3.4 looseUnmarshal	1375
6.243.3.5 tightMarshal1	1375
6.243.3.6 tightMarshal2	1375
6.243.3.7 tightUnmarshal	1376
6.244activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller Class Reference	1377

6.244.1 Detailed Description	1377
6.244.2 Constructor & Destructor Documentation	1378
6.244.2.1 ConnectionInfoMarshaller	1378
6.244.2.2 ~ConnectionInfoMarshaller	1378
6.244.3 Member Function Documentation	1378
6.244.3.1 createObject	1378
6.244.3.2 getDataStructureType	1378
6.244.3.3 looseMarshal	1378
6.244.3.4 looseUnmarshal	1379
6.244.3.5 tightMarshal1	1379
6.244.3.6 tightMarshal2	1379
6.244.3.7 tightUnmarshal	1380
6.245activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller Class Reference	1381
6.245.1 Detailed Description	1381
6.245.2 Constructor & Destructor Documentation	1382
6.245.2.1 ConnectionInfoMarshaller	1382
6.245.2.2 ~ConnectionInfoMarshaller	1382
6.245.3 Member Function Documentation	1382
6.245.3.1 createObject	1382
6.245.3.2 getDataStructureType	1382
6.245.3.3 looseMarshal	1382
6.245.3.4 looseUnmarshal	1383
6.245.3.5 tightMarshal1	1383
6.245.3.6 tightMarshal2	1383
6.245.3.7 tightUnmarshal	1384
6.246cms::ConnectionMetaData Class Reference	1385
6.246.1 Detailed Description	1385
6.246.2 Constructor & Destructor Documentation	1386
6.246.2.1 ~ConnectionMetaData	1386
6.246.3 Member Function Documentation	1386
6.246.3.1 getCMSMajorVersion	1386
6.246.3.2 getCMSMinorVersion	1386
6.246.3.3 getCMSProviderName	1386
6.246.3.4 getCMSVersion	1387
6.246.3.5 getCMSXPropertyNames	1387
6.246.3.6 getProviderMajorVersion	1387

6.246.3.7	getProviderMinorVersion	1387
6.246.3.8	getProviderVersion	1388
6.247	activemq::state::ConnectionState Class Reference	1389
6.247.1	Constructor & Destructor Documentation	1390
6.247.1.1	ConnectionState	1390
6.247.1.2	~ConnectionState	1390
6.247.2	Member Function Documentation	1390
6.247.2.1	addSession	1390
6.247.2.2	addTempDestination	1390
6.247.2.3	addTransactionState	1390
6.247.2.4	checkShutdown	1390
6.247.2.5	getInfo	1390
6.247.2.6	getRecoveringPullConsumers	1390
6.247.2.7	getSessionState	1390
6.247.2.8	getSessionStates	1390
6.247.2.9	getTempDesinations	1390
6.247.2.10	getTransactionState	1390
6.247.2.11	getTransactionStates	1391
6.247.2.12	sConnectionInterruptProcessingComplete	1391
6.247.2.13	removeSession	1391
6.247.2.14	removeTempDestination	1391
6.247.2.15	removeTransactionState	1391
6.247.2.16	reset	1391
6.247.2.17	setConnectionInterruptProcessingComplete	1391
6.247.2.18	shutdown	1391
6.247.2.19	oString	1391
6.248	activemq::state::ConnectionStateTracker Class Reference	1392
6.248.1	Constructor & Destructor Documentation	1394
6.248.1.1	ConnectionStateTracker	1394
6.248.1.2	~ConnectionStateTracker	1394
6.248.2	Member Function Documentation	1394
6.248.2.1	connectionInterruptProcessingComplete	1394
6.248.2.2	getMaxCacheSize	1394
6.248.2.3	isRestoreConsumers	1394
6.248.2.4	isRestoreProducers	1394
6.248.2.5	isRestoreSessions	1394

6.248.2.6	isRestoreTransaction	1394
6.248.2.7	isTrackMessages	1394
6.248.2.8	isTrackTransactionProducers	1394
6.248.2.9	isTrackTransactions	1394
6.248.2.10	processBeginTransaction	1394
6.248.2.11	processCommitTransactionOnePhase	1394
6.248.2.12	processCommitTransactionTwoPhase	1395
6.248.2.13	processConnectionInfo	1395
6.248.2.14	processConsumerInfo	1395
6.248.2.15	processDestinationInfo	1395
6.248.2.16	processEndTransaction	1395
6.248.2.17	processMessage	1395
6.248.2.18	processMessageAck	1395
6.248.2.19	processPrepareTransaction	1396
6.248.2.20	processProducerInfo	1396
6.248.2.21	processRemoveConnection	1396
6.248.2.22	processRemoveConsumer	1396
6.248.2.23	processRemoveDestination	1396
6.248.2.24	processRemoveProducer	1396
6.248.2.25	processRemoveSession	1396
6.248.2.26	processRollbackTransaction	1397
6.248.2.27	processSessionInfo	1397
6.248.2.28	restore	1398
6.248.2.29	setMaxCacheSize	1398
6.248.2.30	setRestoreConsumers	1398
6.248.2.31	setRestoreProducers	1398
6.248.2.32	setRestoreSessions	1398
6.248.2.33	setRestoreTransaction	1398
6.248.2.34	setTrackMessages	1398
6.248.2.35	setTrackTransactionProducers	1398
6.248.2.36	setTrackTransactions	1398
6.248.2.37	track	1398
6.248.2.38	rackBack	1398
6.248.2.39	ransportInterrupted	1398
6.248.3	Friends And Related Function Documentation	1398
6.248.3.1	RemoveTransactionAction	1398

6.249	decaf::util::logging::ConsoleHandler Class Reference	1399
6.249.1	Detailed Description	1399
6.249.2	Constructor & Destructor Documentation	1399
6.249.2.1	ConsoleHandler	1399
6.249.2.2	~ConsoleHandler	1399
6.249.3	Member Function Documentation	1399
6.249.3.1	close	1399
6.249.3.2	publish	1400
6.250	activemq::commands::ConsumerControl Class Reference	1401
6.250.1	Constructor & Destructor Documentation	1402
6.250.1.1	ConsumerControl	1402
6.250.1.2	~ConsumerControl	1402
6.250.2	Member Function Documentation	1402
6.250.2.1	cloneDataStructure	1402
6.250.2.2	copyDataStructure	1402
6.250.2.3	equals	1402
6.250.2.4	getConsumerId	1403
6.250.2.5	getConsumerId	1403
6.250.2.6	getDataStructureType	1403
6.250.2.7	getDestination	1404
6.250.2.8	getDestination	1404
6.250.2.9	getPrefetch	1404
6.250.2.10	isClose	1404
6.250.2.11	isFlush	1404
6.250.2.12	isStart	1404
6.250.2.13	isStop	1404
6.250.2.14	setClose	1404
6.250.2.15	setConsumerId	1404
6.250.2.16	setDestination	1404
6.250.2.17	setFlush	1404
6.250.2.18	setPrefetch	1404
6.250.2.19	setStart	1404
6.250.2.20	setStop	1404
6.250.2.21	toString	1404
6.250.2.22	visit	1405
6.250.3	Field Documentation	1405

6.250.3.1 close	1405
6.250.3.2 consumerId	1405
6.250.3.3 destination	1405
6.250.3.4 flush	1405
6.250.3.5 ID_CONSUMERCONTROL	1405
6.250.3.6 prefetch	1405
6.250.3.7 start	1405
6.250.3.8 stop	1405
6.251activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller Class	
Reference	1406
6.251.1 Detailed Description	1406
6.251.2 Constructor & Destructor Documentation	1407
6.251.2.1 ConsumerControlMarshaller	1407
6.251.2.2 ~ConsumerControlMarshaller	1407
6.251.3 Member Function Documentation	1407
6.251.3.1 createObject	1407
6.251.3.2 getDataStructureType	1407
6.251.3.3 looseMarshal	1407
6.251.3.4 looseUnmarshal	1408
6.251.3.5 tightMarshal1	1408
6.251.3.6 tightMarshal2	1408
6.251.3.7 tightUnmarshal	1409
6.252activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller Class	
Reference	1410
6.252.1 Detailed Description	1410
6.252.2 Constructor & Destructor Documentation	1411
6.252.2.1 ConsumerControlMarshaller	1411
6.252.2.2 ~ConsumerControlMarshaller	1411
6.252.3 Member Function Documentation	1411
6.252.3.1 createObject	1411
6.252.3.2 getDataStructureType	1411
6.252.3.3 looseMarshal	1411
6.252.3.4 looseUnmarshal	1412
6.252.3.5 tightMarshal1	1412
6.252.3.6 tightMarshal2	1412
6.252.3.7 tightUnmarshal	1413

6.253	activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller	Class	
	Reference		1414
6.253.1	Detailed Description		1414
6.253.2	Constructor & Destructor Documentation		1415
6.253.2.1	ConsumerControlMarshaller		1415
6.253.2.2	~ConsumerControlMarshaller		1415
6.253.3	Member Function Documentation		1415
6.253.3.1	createObject		1415
6.253.3.2	getDataStructureType		1415
6.253.3.3	looseMarshal		1415
6.253.3.4	looseUnmarshal		1416
6.253.3.5	tightMarshal1		1416
6.253.3.6	tightMarshal2		1416
6.253.3.7	tightUnmarshal		1417
6.254	activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller	Class	
	Reference		1418
6.254.1	Detailed Description		1418
6.254.2	Constructor & Destructor Documentation		1419
6.254.2.1	ConsumerControlMarshaller		1419
6.254.2.2	~ConsumerControlMarshaller		1419
6.254.3	Member Function Documentation		1419
6.254.3.1	createObject		1419
6.254.3.2	getDataStructureType		1419
6.254.3.3	looseMarshal		1419
6.254.3.4	looseUnmarshal		1420
6.254.3.5	tightMarshal1		1420
6.254.3.6	tightMarshal2		1420
6.254.3.7	tightUnmarshal		1421
6.255	activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller	Class	
	Reference		1422
6.255.1	Detailed Description		1422
6.255.2	Constructor & Destructor Documentation		1423
6.255.2.1	ConsumerControlMarshaller		1423
6.255.2.2	~ConsumerControlMarshaller		1423
6.255.3	Member Function Documentation		1423
6.255.3.1	createObject		1423
6.255.3.2	getDataStructureType		1423

6.255.3.3	looseMarshal	1423
6.255.3.4	looseUnmarshal	1424
6.255.3.5	tightMarshal1	1424
6.255.3.6	tightMarshal2	1424
6.255.3.7	tightUnmarshal	1425
6.256	activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller	Class
	Reference	1426
6.256.1	Detailed Description	1426
6.256.2	Constructor & Destructor Documentation	1427
6.256.2.1	ConsumerControlMarshaller	1427
6.256.2.2	~ConsumerControlMarshaller	1427
6.256.3	Member Function Documentation	1427
6.256.3.1	createObject	1427
6.256.3.2	getDataStructureType	1427
6.256.3.3	looseMarshal	1427
6.256.3.4	looseUnmarshal	1428
6.256.3.5	tightMarshal1	1428
6.256.3.6	tightMarshal2	1428
6.256.3.7	tightUnmarshal	1429
6.257	activemq::commands::ConsumerId	Class Reference
6.257.1	Member Typedef Documentation	1431
6.257.1.1	COMPARATOR	1431
6.257.2	Constructor & Destructor Documentation	1431
6.257.2.1	ConsumerId	1431
6.257.2.2	ConsumerId	1431
6.257.2.3	ConsumerId	1431
6.257.2.4	~ConsumerId	1431
6.257.3	Member Function Documentation	1431
6.257.3.1	cloneDataStructure	1431
6.257.3.2	compareTo	1431
6.257.3.3	copyDataStructure	1431
6.257.3.4	equals	1432
6.257.3.5	equals	1432
6.257.3.6	getConnectionId	1432
6.257.3.7	getConnectionId	1432
6.257.3.8	getDataStructureType	1432
6.257.3.9	getParentId	1433

6.257.3.10	getSessionId	1433
6.257.3.11	getValue	1433
6.257.3.12	operator<	1433
6.257.3.13	operator=	1433
6.257.3.14	operator==	1433
6.257.3.15	setConnectionId	1433
6.257.3.16	setSessionId	1433
6.257.3.17	setValue	1433
6.257.3.18	toString	1433
6.257.4	Field Documentation	1433
6.257.4.1	connectionId	1433
6.257.4.2	ID_CONSUMERID	1433
6.257.4.3	sessionId	1434
6.257.4.4	value	1434
6.258	activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller Class Reference	1435
6.258.1	Detailed Description	1435
6.258.2	Constructor & Destructor Documentation	1436
6.258.2.1	ConsumerIdMarshaller	1436
6.258.2.2	~ConsumerIdMarshaller	1436
6.258.3	Member Function Documentation	1436
6.258.3.1	createObject	1436
6.258.3.2	getDataStructureType	1436
6.258.3.3	looseMarshal	1436
6.258.3.4	looseUnmarshal	1437
6.258.3.5	tightMarshal1	1437
6.258.3.6	tightMarshal2	1437
6.258.3.7	tightUnmarshal	1438
6.259	activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller Class Reference	1439
6.259.1	Detailed Description	1439
6.259.2	Constructor & Destructor Documentation	1440
6.259.2.1	ConsumerIdMarshaller	1440
6.259.2.2	~ConsumerIdMarshaller	1440
6.259.3	Member Function Documentation	1440
6.259.3.1	createObject	1440
6.259.3.2	getDataStructureType	1440
6.259.3.3	looseMarshal	1440

6.259.3.4 looseUnmarshal	1441
6.259.3.5 tightMarshal1	1441
6.259.3.6 tightMarshal2	1441
6.259.3.7 tightUnmarshal	1442
6.260activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller Class Reference	1443
6.260.1 Detailed Description	1443
6.260.2 Constructor & Destructor Documentation	1444
6.260.2.1 ConsumerIdMarshaller	1444
6.260.2.2 ~ConsumerIdMarshaller	1444
6.260.3 Member Function Documentation	1444
6.260.3.1 createObject	1444
6.260.3.2 getDataStructureType	1444
6.260.3.3 looseMarshal	1444
6.260.3.4 looseUnmarshal	1445
6.260.3.5 tightMarshal1	1445
6.260.3.6 tightMarshal2	1445
6.260.3.7 tightUnmarshal	1446
6.261activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller Class Reference	1447
6.261.1 Detailed Description	1447
6.261.2 Constructor & Destructor Documentation	1448
6.261.2.1 ConsumerIdMarshaller	1448
6.261.2.2 ~ConsumerIdMarshaller	1448
6.261.3 Member Function Documentation	1448
6.261.3.1 createObject	1448
6.261.3.2 getDataStructureType	1448
6.261.3.3 looseMarshal	1448
6.261.3.4 looseUnmarshal	1449
6.261.3.5 tightMarshal1	1449
6.261.3.6 tightMarshal2	1449
6.261.3.7 tightUnmarshal	1450
6.262activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller Class Reference	1451
6.262.1 Detailed Description	1451
6.262.2 Constructor & Destructor Documentation	1452
6.262.2.1 ConsumerIdMarshaller	1452
6.262.2.2 ~ConsumerIdMarshaller	1452
6.262.3 Member Function Documentation	1452

6.262.3.1 createObject	1452
6.262.3.2 getDataStructureType	1452
6.262.3.3 looseMarshal	1452
6.262.3.4 looseUnmarshal	1453
6.262.3.5 tightMarshal1	1453
6.262.3.6 tightMarshal2	1453
6.262.3.7 tightUnmarshal	1454
6.263activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller Class Reference	1455
6.263.1 Detailed Description	1455
6.263.2 Constructor & Destructor Documentation	1456
6.263.2.1 ConsumerIdMarshaller	1456
6.263.2.2 ~ConsumerIdMarshaller	1456
6.263.3 Member Function Documentation	1456
6.263.3.1 createObject	1456
6.263.3.2 getDataStructureType	1456
6.263.3.3 looseMarshal	1456
6.263.3.4 looseUnmarshal	1457
6.263.3.5 tightMarshal1	1457
6.263.3.6 tightMarshal2	1457
6.263.3.7 tightUnmarshal	1458
6.264activemq::commands::ConsumerInfo Class Reference	1459
6.264.1 Constructor & Destructor Documentation	1461
6.264.1.1 ConsumerInfo	1461
6.264.1.2 ~ConsumerInfo	1461
6.264.2 Member Function Documentation	1461
6.264.2.1 cloneDataStructure	1461
6.264.2.2 copyDataStructure	1461
6.264.2.3 createRemoveCommand	1461
6.264.2.4 equals	1461
6.264.2.5 getAdditionalPredicate	1462
6.264.2.6 getAdditionalPredicate	1462
6.264.2.7 getBrokerPath	1462
6.264.2.8 getBrokerPath	1462
6.264.2.9 getConsumerId	1462
6.264.2.10getConsumerId	1462
6.264.2.11getDataStructureType	1462

6.264.2.12	getDestination	1463
6.264.2.13	getDestination	1463
6.264.2.14	getMaximumPendingMessageLimit	1463
6.264.2.15	getNetworkConsumerPath	1463
6.264.2.16	getNetworkConsumerPath	1463
6.264.2.17	getPrefetchSize	1463
6.264.2.18	getPriority	1463
6.264.2.19	getSelector	1463
6.264.2.20	getSelector	1463
6.264.2.21	getSubscriptionName	1463
6.264.2.22	getSubscriptionName	1463
6.264.2.23	sBrowser	1463
6.264.2.24	sConsumerInfo	1463
6.264.2.25	sDispatchAsync	1464
6.264.2.26	sExclusive	1464
6.264.2.27	sNetworkSubscription	1464
6.264.2.28	sNoLocal	1464
6.264.2.29	sNoRangeAcks	1464
6.264.2.30	sOptimizedAcknowledge	1464
6.264.2.31	isRetroactive	1464
6.264.2.32	setAdditionalPredicate	1464
6.264.2.33	setBrokerPath	1464
6.264.2.34	setBrowser	1464
6.264.2.35	setConsumerId	1464
6.264.2.36	setDestination	1464
6.264.2.37	setDispatchAsync	1464
6.264.2.38	setExclusive	1464
6.264.2.39	setMaximumPendingMessageLimit	1464
6.264.2.40	setNetworkConsumerPath	1464
6.264.2.41	setNetworkSubscription	1464
6.264.2.42	setNoLocal	1464
6.264.2.43	setNoRangeAcks	1464
6.264.2.44	setOptimizedAcknowledge	1464
6.264.2.45	setPrefetchSize	1464
6.264.2.46	setPriority	1464
6.264.2.47	setRetroactive	1464

6.264.2.4	setSelector	1464
6.264.2.4	setSubscriptionName	1464
6.264.2.5	toString	1464
6.264.2.5	visit	1465
6.264.3	Field Documentation	1466
6.264.3.1	additionalPredicate	1466
6.264.3.2	brokerPath	1466
6.264.3.3	browser	1466
6.264.3.4	consumerId	1466
6.264.3.5	destination	1466
6.264.3.6	dispatchAsync	1466
6.264.3.7	exclusive	1466
6.264.3.8	ID_CONSUMERINFO	1466
6.264.3.9	maximumPendingMessageLimit	1466
6.264.3.10	networkConsumerPath	1466
6.264.3.11	networkSubscription	1466
6.264.3.12	noLocal	1466
6.264.3.13	noRangeAcks	1466
6.264.3.14	optimizedAcknowledge	1466
6.264.3.15	prefetchSize	1466
6.264.3.16	priority	1466
6.264.3.17	retroactive	1466
6.264.3.18	selector	1466
6.264.3.19	subscriptionName	1466
6.265	activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller Class Reference	1468
6.265.1	Detailed Description	1468
6.265.2	Constructor & Destructor Documentation	1469
6.265.2.1	ConsumerInfoMarshaller	1469
6.265.2.2	~ConsumerInfoMarshaller	1469
6.265.3	Member Function Documentation	1469
6.265.3.1	createObject	1469
6.265.3.2	getDataStructureType	1469
6.265.3.3	looseMarshal	1469
6.265.3.4	looseUnmarshal	1470
6.265.3.5	tightMarshal1	1470
6.265.3.6	tightMarshal2	1470

6.265.3.7 tightUnmarshal	1471
6.266activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller Class Reference	1472
6.266.1 Detailed Description	1472
6.266.2 Constructor & Destructor Documentation	1473
6.266.2.1 ConsumerInfoMarshaller	1473
6.266.2.2 ~ConsumerInfoMarshaller	1473
6.266.3 Member Function Documentation	1473
6.266.3.1 createObject	1473
6.266.3.2 getDataStructureType	1473
6.266.3.3 looseMarshal	1473
6.266.3.4 looseUnmarshal	1474
6.266.3.5 tightMarshal1	1474
6.266.3.6 tightMarshal2	1474
6.266.3.7 tightUnmarshal	1475
6.267activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller Class Reference	1476
6.267.1 Detailed Description	1476
6.267.2 Constructor & Destructor Documentation	1477
6.267.2.1 ConsumerInfoMarshaller	1477
6.267.2.2 ~ConsumerInfoMarshaller	1477
6.267.3 Member Function Documentation	1477
6.267.3.1 createObject	1477
6.267.3.2 getDataStructureType	1477
6.267.3.3 looseMarshal	1477
6.267.3.4 looseUnmarshal	1478
6.267.3.5 tightMarshal1	1478
6.267.3.6 tightMarshal2	1478
6.267.3.7 tightUnmarshal	1479
6.268activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller Class Reference	1480
6.268.1 Detailed Description	1480
6.268.2 Constructor & Destructor Documentation	1481
6.268.2.1 ConsumerInfoMarshaller	1481
6.268.2.2 ~ConsumerInfoMarshaller	1481
6.268.3 Member Function Documentation	1481
6.268.3.1 createObject	1481

6.268.3.2	getDataStructureType	1481
6.268.3.3	looseMarshal	1481
6.268.3.4	looseUnmarshal	1482
6.268.3.5	tightMarshal1	1482
6.268.3.6	tightMarshal2	1482
6.268.3.7	tightUnmarshal	1483
6.269	activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller Class Reference	1484
6.269.1	Detailed Description	1484
6.269.2	Constructor & Destructor Documentation	1485
6.269.2.1	ConsumerInfoMarshaller	1485
6.269.2.2	~ConsumerInfoMarshaller	1485
6.269.3	Member Function Documentation	1485
6.269.3.1	createObject	1485
6.269.3.2	getDataStructureType	1485
6.269.3.3	looseMarshal	1485
6.269.3.4	looseUnmarshal	1486
6.269.3.5	tightMarshal1	1486
6.269.3.6	tightMarshal2	1486
6.269.3.7	tightUnmarshal	1487
6.270	activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller Class Reference	1488
6.270.1	Detailed Description	1488
6.270.2	Constructor & Destructor Documentation	1489
6.270.2.1	ConsumerInfoMarshaller	1489
6.270.2.2	~ConsumerInfoMarshaller	1489
6.270.3	Member Function Documentation	1489
6.270.3.1	createObject	1489
6.270.3.2	getDataStructureType	1489
6.270.3.3	looseMarshal	1489
6.270.3.4	looseUnmarshal	1490
6.270.3.5	tightMarshal1	1490
6.270.3.6	tightMarshal2	1490
6.270.3.7	tightUnmarshal	1491
6.271	activemq::state::ConsumerState Class Reference	1492
6.271.1	Constructor & Destructor Documentation	1492
6.271.1.1	ConsumerState	1492

6.271.1.2 <code>~ConsumerState</code>	1492
6.271.2 Member Function Documentation	1492
6.271.2.1 <code>getInfo</code>	1492
6.271.2.2 <code>toString</code>	1492
6.272 <code>activemq::commands::ControlCommand</code> Class Reference	1493
6.272.1 Constructor & Destructor Documentation	1494
6.272.1.1 <code>ControlCommand</code>	1494
6.272.1.2 <code>~ControlCommand</code>	1494
6.272.2 Member Function Documentation	1494
6.272.2.1 <code>cloneDataStructure</code>	1494
6.272.2.2 <code>copyDataStructure</code>	1494
6.272.2.3 <code>equals</code>	1494
6.272.2.4 <code>getCommand</code>	1495
6.272.2.5 <code>getCommand</code>	1495
6.272.2.6 <code>getDataStructureType</code>	1495
6.272.2.7 <code>setCommand</code>	1495
6.272.2.8 <code>toString</code>	1495
6.272.2.9 <code>visit</code>	1495
6.272.3 Field Documentation	1496
6.272.3.1 <code>command</code>	1496
6.272.3.2 <code>ID_CONTROLCOMMAND</code>	1496
6.273 <code>activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller</code> Class Reference	1497
6.273.1 Detailed Description	1497
6.273.2 Constructor & Destructor Documentation	1498
6.273.2.1 <code>ControlCommandMarshaller</code>	1498
6.273.2.2 <code>~ControlCommandMarshaller</code>	1498
6.273.3 Member Function Documentation	1498
6.273.3.1 <code>createObject</code>	1498
6.273.3.2 <code>getDataStructureType</code>	1498
6.273.3.3 <code>looseMarshal</code>	1498
6.273.3.4 <code>looseUnmarshal</code>	1499
6.273.3.5 <code>tightMarshal1</code>	1499
6.273.3.6 <code>tightMarshal2</code>	1499
6.273.3.7 <code>tightUnmarshal</code>	1500
6.274 <code>activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller</code> Class Reference	1501

6.274.1 Detailed Description	1501
6.274.2 Constructor & Destructor Documentation	1502
6.274.2.1 ControlCommandMarshaller	1502
6.274.2.2 ~ControlCommandMarshaller	1502
6.274.3 Member Function Documentation	1502
6.274.3.1 createObject	1502
6.274.3.2 getDataStructureType	1502
6.274.3.3 looseMarshal	1502
6.274.3.4 looseUnmarshal	1503
6.274.3.5 tightMarshal1	1503
6.274.3.6 tightMarshal2	1503
6.274.3.7 tightUnmarshal	1504
6.275activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller Class	
Reference	1505
6.275.1 Detailed Description	1505
6.275.2 Constructor & Destructor Documentation	1506
6.275.2.1 ControlCommandMarshaller	1506
6.275.2.2 ~ControlCommandMarshaller	1506
6.275.3 Member Function Documentation	1506
6.275.3.1 createObject	1506
6.275.3.2 getDataStructureType	1506
6.275.3.3 looseMarshal	1506
6.275.3.4 looseUnmarshal	1507
6.275.3.5 tightMarshal1	1507
6.275.3.6 tightMarshal2	1507
6.275.3.7 tightUnmarshal	1508
6.276activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller Class	
Reference	1509
6.276.1 Detailed Description	1509
6.276.2 Constructor & Destructor Documentation	1510
6.276.2.1 ControlCommandMarshaller	1510
6.276.2.2 ~ControlCommandMarshaller	1510
6.276.3 Member Function Documentation	1510
6.276.3.1 createObject	1510
6.276.3.2 getDataStructureType	1510
6.276.3.3 looseMarshal	1510
6.276.3.4 looseUnmarshal	1511

6.276.3.5	tightMarshal1	1511
6.276.3.6	tightMarshal2	1511
6.276.3.7	tightUnmarshal	1512
6.277	activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller	Class
	Reference	1513
6.277.1	Detailed Description	1513
6.277.2	Constructor & Destructor Documentation	1514
6.277.2.1	ControlCommandMarshaller	1514
6.277.2.2	~ControlCommandMarshaller	1514
6.277.3	Member Function Documentation	1514
6.277.3.1	createObject	1514
6.277.3.2	getDataStructureType	1514
6.277.3.3	looseMarshal	1514
6.277.3.4	looseUnmarshal	1515
6.277.3.5	tightMarshal1	1515
6.277.3.6	tightMarshal2	1515
6.277.3.7	tightUnmarshal	1516
6.278	activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller	Class
	Reference	1517
6.278.1	Detailed Description	1517
6.278.2	Constructor & Destructor Documentation	1518
6.278.2.1	ControlCommandMarshaller	1518
6.278.2.2	~ControlCommandMarshaller	1518
6.278.3	Member Function Documentation	1518
6.278.3.1	createObject	1518
6.278.3.2	getDataStructureType	1518
6.278.3.3	looseMarshal	1518
6.278.3.4	looseUnmarshal	1519
6.278.3.5	tightMarshal1	1519
6.278.3.6	tightMarshal2	1519
6.278.3.7	tightUnmarshal	1520
6.279	decaf::util::concurrent::CountDownLatch	Class Reference
6.279.1	Constructor & Destructor Documentation	1521
6.279.1.1	CountDownLatch	1521
6.279.1.2	~CountDownLatch	1522
6.279.2	Member Function Documentation	1522
6.279.2.1	await	1522

6.279.2.2 await	1522
6.279.2.3 await	1523
6.279.2.4 countDown	1523
6.279.2.5 getCount	1523
6.280decaf::util::zip::CRC32 Class Reference	1524
6.280.1 Detailed Description	1524
6.280.2 Constructor & Destructor Documentation	1525
6.280.2.1 CRC32	1525
6.280.2.2 ~CRC32	1525
6.280.3 Member Function Documentation	1525
6.280.3.1 getValue	1525
6.280.3.2 reset	1525
6.280.3.3 update	1525
6.280.3.4 update	1525
6.280.3.5 update	1526
6.280.3.6 update	1526
6.281ct_data_s Struct Reference	1527
6.281.1 Field Documentation	1527
6.281.1.1 code	1527
6.281.1.2 dad	1527
6.281.1.3 dl	1527
6.281.1.4 fc	1527
6.281.1.5 freq	1527
6.281.1.6 len	1527
6.282activemq::commands::DataArrayResponse Class Reference	1528
6.282.1 Constructor & Destructor Documentation	1529
6.282.1.1 DataArrayResponse	1529
6.282.1.2 ~DataArrayResponse	1529
6.282.2 Member Function Documentation	1529
6.282.2.1 cloneDataStructure	1529
6.282.2.2 copyDataStructure	1529
6.282.2.3 equals	1529
6.282.2.4 getData	1530
6.282.2.5 getData	1530
6.282.2.6 getDataStructureType	1530
6.282.2.7 setData	1530

6.282.2.8 toString	1530
6.282.3 Field Documentation	1530
6.282.3.1 data	1530
6.282.3.2 ID_DATAARRAYRESPONSE	1530
6.283activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller Class	
Reference	1531
6.283.1 Detailed Description	1531
6.283.2 Constructor & Destructor Documentation	1532
6.283.2.1 DataArrayResponseMarshaller	1532
6.283.2.2 ~DataArrayResponseMarshaller	1532
6.283.3 Member Function Documentation	1532
6.283.3.1 createObject	1532
6.283.3.2 getDataStructureType	1532
6.283.3.3 looseMarshal	1532
6.283.3.4 looseUnmarshal	1533
6.283.3.5 tightMarshal1	1533
6.283.3.6 tightMarshal2	1534
6.283.3.7 tightUnmarshal	1534
6.284activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller Class	
Reference	1535
6.284.1 Detailed Description	1535
6.284.2 Constructor & Destructor Documentation	1536
6.284.2.1 DataArrayResponseMarshaller	1536
6.284.2.2 ~DataArrayResponseMarshaller	1536
6.284.3 Member Function Documentation	1536
6.284.3.1 createObject	1536
6.284.3.2 getDataStructureType	1536
6.284.3.3 looseMarshal	1536
6.284.3.4 looseUnmarshal	1537
6.284.3.5 tightMarshal1	1537
6.284.3.6 tightMarshal2	1538
6.284.3.7 tightUnmarshal	1538
6.285activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller Class	
Reference	1539
6.285.1 Detailed Description	1539
6.285.2 Constructor & Destructor Documentation	1540
6.285.2.1 DataArrayResponseMarshaller	1540

6.285.2.2	~DataArrayResponseMarshaller	1540
6.285.3	Member Function Documentation	1540
6.285.3.1	createObject	1540
6.285.3.2	getDataStructureType	1540
6.285.3.3	looseMarshal	1540
6.285.3.4	looseUnmarshal	1541
6.285.3.5	tightMarshal1	1541
6.285.3.6	tightMarshal2	1542
6.285.3.7	tightUnmarshal	1542
6.286	activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller Class	
	Reference	1543
6.286.1	Detailed Description	1543
6.286.2	Constructor & Destructor Documentation	1544
6.286.2.1	DataArrayResponseMarshaller	1544
6.286.2.2	~DataArrayResponseMarshaller	1544
6.286.3	Member Function Documentation	1544
6.286.3.1	createObject	1544
6.286.3.2	getDataStructureType	1544
6.286.3.3	looseMarshal	1544
6.286.3.4	looseUnmarshal	1545
6.286.3.5	tightMarshal1	1545
6.286.3.6	tightMarshal2	1546
6.286.3.7	tightUnmarshal	1546
6.287	activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller Class	
	Reference	1547
6.287.1	Detailed Description	1547
6.287.2	Constructor & Destructor Documentation	1548
6.287.2.1	DataArrayResponseMarshaller	1548
6.287.2.2	~DataArrayResponseMarshaller	1548
6.287.3	Member Function Documentation	1548
6.287.3.1	createObject	1548
6.287.3.2	getDataStructureType	1548
6.287.3.3	looseMarshal	1548
6.287.3.4	looseUnmarshal	1549
6.287.3.5	tightMarshal1	1549
6.287.3.6	tightMarshal2	1550
6.287.3.7	tightUnmarshal	1550

6.288	activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller Class Reference	1551
6.288.1	Detailed Description	1551
6.288.2	Constructor & Destructor Documentation	1552
6.288.2.1	DataArrayResponseMarshaller	1552
6.288.2.2	~DataArrayResponseMarshaller	1552
6.288.3	Member Function Documentation	1552
6.288.3.1	createObject	1552
6.288.3.2	getDataStructureType	1552
6.288.3.3	looseMarshal	1552
6.288.3.4	looseUnmarshal	1553
6.288.3.5	tightMarshal1	1553
6.288.3.6	tightMarshal2	1554
6.288.3.7	tightUnmarshal	1554
6.289	decaf::util::zip::DataFormatException Class Reference	1555
6.289.1	Constructor & Destructor Documentation	1555
6.289.1.1	DataFormatException	1555
6.289.1.2	DataFormatException	1555
6.289.1.3	DataFormatException	1556
6.289.1.4	DataFormatException	1556
6.289.1.5	DataFormatException	1556
6.289.1.6	DataFormatException	1556
6.289.1.7	~DataFormatException	1557
6.289.2	Member Function Documentation	1557
6.289.2.1	clone	1557
6.290	decaf::io::DataInput Class Reference	1558
6.290.1	Detailed Description	1559
6.290.2	Constructor & Destructor Documentation	1559
6.290.2.1	~DataInput	1559
6.290.3	Member Function Documentation	1559
6.290.3.1	readBoolean	1559
6.290.3.2	readByte	1560
6.290.3.3	readChar	1560
6.290.3.4	readDouble	1560
6.290.3.5	readFloat	1561
6.290.3.6	readFully	1561
6.290.3.7	readFully	1561

6.290.3.8 readInt	1562
6.290.3.9 readLine	1562
6.290.3.10 readLong	1563
6.290.3.11 readShort	1563
6.290.3.12 readString	1563
6.290.3.13 readUnsignedByte	1564
6.290.3.14 readUnsignedShort	1564
6.290.3.15 readUTF	1564
6.290.3.16 skipBytes	1565
6.291 decaf::io::DataInputStream Class Reference	1566
6.291.1 Detailed Description	1567
6.291.2 Constructor & Destructor Documentation	1567
6.291.2.1 DataInputStream	1567
6.291.2.2 ~DataInputStream	1568
6.291.3 Member Function Documentation	1568
6.291.3.1 readBoolean	1568
6.291.3.2 readByte	1568
6.291.3.3 readChar	1568
6.291.3.4 readDouble	1569
6.291.3.5 readFloat	1569
6.291.3.6 readFully	1569
6.291.3.7 readFully	1570
6.291.3.8 readInt	1570
6.291.3.9 readLine	1571
6.291.3.10 readLong	1571
6.291.3.11 readShort	1571
6.291.3.12 readString	1572
6.291.3.13 readUnsignedByte	1572
6.291.3.14 readUnsignedShort	1572
6.291.3.15 readUTF	1573
6.291.3.16 skipBytes	1573
6.292 decaf::io::DataOutput Class Reference	1574
6.292.1 Detailed Description	1575
6.292.2 Constructor & Destructor Documentation	1575
6.292.2.1 ~DataOutput	1575
6.292.3 Member Function Documentation	1575

6.292.3.1 writeBoolean	1575
6.292.3.2 writeByte	1575
6.292.3.3 writeBytes	1576
6.292.3.4 writeChar	1576
6.292.3.5 writeChars	1576
6.292.3.6 writeDouble	1576
6.292.3.7 writeFloat	1577
6.292.3.8 writeInt	1577
6.292.3.9 writeLong	1577
6.292.3.10 writeShort	1578
6.292.3.11 writeUnsignedShort	1578
6.292.3.12 writeUTF	1578
6.293 decaf::io::DataOutputStream Class Reference	1579
6.293.1 Detailed Description	1580
6.293.2 Constructor & Destructor Documentation	1580
6.293.2.1 DataOutputStream	1580
6.293.2.2 ~DataOutputStream	1580
6.293.3 Member Function Documentation	1580
6.293.3.1 doWriteArrayBounded	1580
6.293.3.2 doWriteByte	1581
6.293.3.3 size	1581
6.293.3.4 writeBoolean	1582
6.293.3.5 writeByte	1582
6.293.3.6 writeBytes	1582
6.293.3.7 writeChar	1582
6.293.3.8 writeChars	1582
6.293.3.9 writeDouble	1582
6.293.3.10 writeFloat	1582
6.293.3.11 writeInt	1582
6.293.3.12 writeLong	1582
6.293.3.13 writeShort	1582
6.293.3.14 writeUnsignedShort	1582
6.293.3.15 writeUTF	1582
6.293.4 Field Documentation	1582
6.293.4.1 buffer	1582
6.293.4.2 written	1582

6.294activemq::commands::DataResponse Class Reference	1583
6.294.1 Constructor & Destructor Documentation	1584
6.294.1.1 DataResponse	1584
6.294.1.2 ~DataResponse	1584
6.294.2 Member Function Documentation	1584
6.294.2.1 cloneDataStructure	1584
6.294.2.2 copyDataStructure	1584
6.294.2.3 equals	1584
6.294.2.4 getData	1585
6.294.2.5 getData	1585
6.294.2.6 getDataStructureType	1585
6.294.2.7 setData	1585
6.294.2.8 toString	1585
6.294.3 Field Documentation	1585
6.294.3.1 data	1585
6.294.3.2 ID_DATARESPONSE	1585
6.295activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller Class Refer- ence	1586
6.295.1 Detailed Description	1586
6.295.2 Constructor & Destructor Documentation	1587
6.295.2.1 DataResponseMarshaller	1587
6.295.2.2 ~DataResponseMarshaller	1587
6.295.3 Member Function Documentation	1587
6.295.3.1 createObject	1587
6.295.3.2 getDataStructureType	1587
6.295.3.3 looseMarshal	1587
6.295.3.4 looseUnmarshal	1588
6.295.3.5 tightMarshal1	1588
6.295.3.6 tightMarshal2	1589
6.295.3.7 tightUnmarshal	1589
6.296activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller Class Refer- ence	1590
6.296.1 Detailed Description	1590
6.296.2 Constructor & Destructor Documentation	1591
6.296.2.1 DataResponseMarshaller	1591
6.296.2.2 ~DataResponseMarshaller	1591
6.296.3 Member Function Documentation	1591

6.296.3.1 createObject	1591
6.296.3.2 getDataStructureType	1591
6.296.3.3 looseMarshal	1591
6.296.3.4 looseUnmarshal	1592
6.296.3.5 tightMarshal1	1592
6.296.3.6 tightMarshal2	1593
6.296.3.7 tightUnmarshal	1593
6.297activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller Class Reference	1594
6.297.1 Detailed Description	1594
6.297.2 Constructor & Destructor Documentation	1595
6.297.2.1 DataResponseMarshaller	1595
6.297.2.2 ~DataResponseMarshaller	1595
6.297.3 Member Function Documentation	1595
6.297.3.1 createObject	1595
6.297.3.2 getDataStructureType	1595
6.297.3.3 looseMarshal	1595
6.297.3.4 looseUnmarshal	1596
6.297.3.5 tightMarshal1	1596
6.297.3.6 tightMarshal2	1597
6.297.3.7 tightUnmarshal	1597
6.298activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller Class Reference	1598
6.298.1 Detailed Description	1598
6.298.2 Constructor & Destructor Documentation	1599
6.298.2.1 DataResponseMarshaller	1599
6.298.2.2 ~DataResponseMarshaller	1599
6.298.3 Member Function Documentation	1599
6.298.3.1 createObject	1599
6.298.3.2 getDataStructureType	1599
6.298.3.3 looseMarshal	1599
6.298.3.4 looseUnmarshal	1600
6.298.3.5 tightMarshal1	1600
6.298.3.6 tightMarshal2	1601
6.298.3.7 tightUnmarshal	1601
6.299activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller Class Reference	1602

6.299.1 Detailed Description	1602
6.299.2 Constructor & Destructor Documentation	1603
6.299.2.1 DataResponseMarshaller	1603
6.299.2.2 ~DataResponseMarshaller	1603
6.299.3 Member Function Documentation	1603
6.299.3.1 createObject	1603
6.299.3.2 getDataStructureType	1603
6.299.3.3 looseMarshal	1603
6.299.3.4 looseUnmarshal	1604
6.299.3.5 tightMarshal1	1604
6.299.3.6 tightMarshal2	1605
6.299.3.7 tightUnmarshal	1605
6.300activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller Class Reference	1606
6.300.1 Detailed Description	1606
6.300.2 Constructor & Destructor Documentation	1607
6.300.2.1 DataResponseMarshaller	1607
6.300.2.2 ~DataResponseMarshaller	1607
6.300.3 Member Function Documentation	1607
6.300.3.1 createObject	1607
6.300.3.2 getDataStructureType	1607
6.300.3.3 looseMarshal	1607
6.300.3.4 looseUnmarshal	1608
6.300.3.5 tightMarshal1	1608
6.300.3.6 tightMarshal2	1609
6.300.3.7 tightUnmarshal	1609
6.301activemq::wireformat::openwire::marshal::DataStreamMarshaller Class Reference	1610
6.301.1 Detailed Description	1610
6.301.2 Constructor & Destructor Documentation	1611
6.301.2.1 ~DataStreamMarshaller	1611
6.301.3 Member Function Documentation	1611
6.301.3.1 createObject	1611
6.301.3.2 getDataStructureType	1617
6.301.3.3 looseMarshal	1624
6.301.3.4 looseUnmarshal	1631
6.301.3.5 tightMarshal1	1638
6.301.3.6 tightMarshal2	1645

6.301.3.7 tightUnmarshal	1652
6.302activemq::commands::DataStructure Class Reference	1660
6.302.1 Constructor & Destructor Documentation	1660
6.302.1.1 ~DataStructure	1660
6.302.2 Member Function Documentation	1660
6.302.2.1 cloneDataStructure	1660
6.302.2.2 copyDataStructure	1661
6.302.2.3 equals	1661
6.302.2.4 getDataStructureType	1662
6.302.2.5 toString	1663
6.303decaf::util::Date Class Reference	1665
6.303.1 Detailed Description	1666
6.303.2 Constructor & Destructor Documentation	1666
6.303.2.1 Date	1666
6.303.2.2 Date	1666
6.303.2.3 Date	1666
6.303.2.4 ~Date	1666
6.303.3 Member Function Documentation	1666
6.303.3.1 after	1666
6.303.3.2 before	1666
6.303.3.3 compareTo	1667
6.303.3.4 equals	1667
6.303.3.5 getTime	1667
6.303.3.6 operator<	1667
6.303.3.7 operator=	1668
6.303.3.8 operator==	1668
6.303.3.9 setTime	1668
6.303.3.10 toString	1668
6.304decaf::internal::DecafRuntime Class Reference	1670
6.304.1 Detailed Description	1670
6.304.2 Constructor & Destructor Documentation	1670
6.304.2.1 DecafRuntime	1670
6.304.2.2 ~DecafRuntime	1670
6.304.3 Member Function Documentation	1670
6.304.3.1 getGlobalPool	1670
6.305activemq::threads::DedicatedTaskRunner Class Reference	1671

6.305.1 Constructor & Destructor Documentation	1671
6.305.1.1 DedicatedTaskRunner	1671
6.305.1.2 ~DedicatedTaskRunner	1671
6.305.2 Member Function Documentation	1671
6.305.2.1 run	1671
6.305.2.2 shutdown	1672
6.305.2.3 shutdown	1672
6.305.2.4 wakeup	1672
6.306activemq::core::policies::DefaultPrefetchPolicy Class Reference	1673
6.306.1 Constructor & Destructor Documentation	1674
6.306.1.1 DefaultPrefetchPolicy	1674
6.306.1.2 ~DefaultPrefetchPolicy	1674
6.306.2 Member Function Documentation	1674
6.306.2.1 clone	1674
6.306.2.2 getDurableTopicPrefetch	1674
6.306.2.3 getMaxPrefetchLimit	1674
6.306.2.4 getQueueBrowserPrefetch	1674
6.306.2.5 getQueuePrefetch	1675
6.306.2.6 getTopicPrefetch	1675
6.306.2.7 setDurableTopicPrefetch	1675
6.306.2.8 setQueueBrowserPrefetch	1675
6.306.2.9 setQueuePrefetch	1676
6.306.2.10setTopicPrefetch	1676
6.306.3 Field Documentation	1676
6.306.3.1 DEFAULT_DURABLE_TOPIC_PREFETCH	1676
6.306.3.2 DEFAULT_QUEUE_BROWSER_PREFETCH	1676
6.306.3.3 DEFAULT_QUEUE_PREFETCH	1676
6.306.3.4 DEFAULT_TOPIC_PREFETCH	1676
6.306.3.5 MAX_PREFETCH_SIZE	1676
6.307activemq::core::policies::DefaultRedeliveryPolicy Class Reference	1677
6.307.1 Constructor & Destructor Documentation	1678
6.307.1.1 DefaultRedeliveryPolicy	1678
6.307.1.2 ~DefaultRedeliveryPolicy	1678
6.307.2 Member Function Documentation	1678
6.307.2.1 clone	1678
6.307.2.2 getBackOffMultiplier	1678

6.307.2.3	getCollisionAvoidancePercent	1678
6.307.2.4	getInitialRedeliveryDelay	1678
6.307.2.5	getMaximumRedeliveries	1679
6.307.2.6	getRedeliveryDelay	1679
6.307.2.7	isUseCollisionAvoidance	1679
6.307.2.8	isUseExponentialBackOff	1679
6.307.2.9	setBackOffMultiplier	1679
6.307.2.10	setCollisionAvoidancePercent	1680
6.307.2.11	setInitialRedeliveryDelay	1680
6.307.2.12	setMaximumRedeliveries	1680
6.307.2.13	setUseCollisionAvoidance	1680
6.307.2.14	setUseExponentialBackOff	1681
6.308	decaf::internal::net::DefaultServerSocketFactory Class Reference	1682
6.308.1	Detailed Description	1683
6.308.2	Constructor & Destructor Documentation	1683
6.308.2.1	DefaultServerSocketFactory	1683
6.308.2.2	~DefaultServerSocketFactory	1683
6.308.3	Member Function Documentation	1683
6.308.3.1	createServerSocket	1683
6.308.3.2	createServerSocket	1684
6.308.3.3	createServerSocket	1684
6.308.3.4	createServerSocket	1685
6.309	decaf::internal::net::DefaultSocketFactory Class Reference	1686
6.309.1	Detailed Description	1687
6.309.2	Constructor & Destructor Documentation	1688
6.309.2.1	DefaultSocketFactory	1688
6.309.2.2	~DefaultSocketFactory	1688
6.309.3	Member Function Documentation	1688
6.309.3.1	createSocket	1688
6.309.3.2	createSocket	1688
6.309.3.3	createSocket	1689
6.309.3.4	createSocket	1689
6.309.3.5	createSocket	1690
6.310	decaf::internal::net::ssl::DefaultSSLContext Class Reference	1691
6.310.1	Detailed Description	1691
6.310.2	Constructor & Destructor Documentation	1691

6.310.2.1 DefaultSSLContext	1691
6.310.2.2 ~DefaultSSLContext	1691
6.310.3 Member Function Documentation	1691
6.310.3.1 getContext	1691
6.311decaf::internal::net::ssl::DefaultSSLServerSocketFactory Class Reference	1692
6.311.1 Detailed Description	1693
6.311.2 Constructor & Destructor Documentation	1694
6.311.2.1 DefaultSSLServerSocketFactory	1694
6.311.2.2 ~DefaultSSLServerSocketFactory	1694
6.311.3 Member Function Documentation	1694
6.311.3.1 createServerSocket	1694
6.311.3.2 createServerSocket	1694
6.311.3.3 createServerSocket	1695
6.311.3.4 createServerSocket	1695
6.311.3.5 getDefaultCipherSuites	1695
6.311.3.6 getSupportedCipherSuites	1696
6.312decaf::internal::net::ssl::DefaultSSLSocketFactory Class Reference	1697
6.312.1 Detailed Description	1699
6.312.2 Constructor & Destructor Documentation	1699
6.312.2.1 DefaultSSLSocketFactory	1699
6.312.2.2 ~DefaultSSLSocketFactory	1699
6.312.3 Member Function Documentation	1699
6.312.3.1 createSocket	1699
6.312.3.2 createSocket	1700
6.312.3.3 createSocket	1700
6.312.3.4 createSocket	1701
6.312.3.5 createSocket	1701
6.312.3.6 createSocket	1702
6.312.3.7 getDefaultCipherSuites	1702
6.312.3.8 getSupportedCipherSuites	1703
6.313activemq::transport::DefaultTransportListener Class Reference	1704
6.313.1 Constructor & Destructor Documentation	1704
6.313.1.1 ~DefaultTransportListener	1704
6.313.2 Member Function Documentation	1704
6.313.2.1 onCommand	1704
6.313.2.2 onException	1704

6.313.2.3 transportInterrupted	1705
6.313.2.4 transportResumed	1705
6.314decaf::util::zip::Deflater Class Reference	1706
6.314.1 Detailed Description	1708
6.314.2 Constructor & Destructor Documentation	1708
6.314.2.1 Deflater	1708
6.314.2.2 Deflater	1708
6.314.2.3 ~Deflater	1709
6.314.3 Member Function Documentation	1709
6.314.3.1 deflate	1709
6.314.3.2 deflate	1709
6.314.3.3 deflate	1709
6.314.3.4 end	1710
6.314.3.5 finish	1710
6.314.3.6 finished	1710
6.314.3.7 getAdler	1710
6.314.3.8 getBytesRead	1710
6.314.3.9 getBytesWritten	1711
6.314.3.10needsInput	1711
6.314.3.11reset	1711
6.314.3.12setDictionary	1711
6.314.3.13setDictionary	1712
6.314.3.14setDictionary	1712
6.314.3.15setInput	1712
6.314.3.16setInput	1713
6.314.3.17setInput	1713
6.314.3.18setLevel	1714
6.314.3.19setStrategy	1714
6.314.4 Field Documentation	1714
6.314.4.1 BEST_COMPRESSION	1714
6.314.4.2 BEST_SPEED	1714
6.314.4.3 DEFAULT_COMPRESSION	1714
6.314.4.4 DEFAULT_STRATEGY	1714
6.314.4.5 DEFLATED	1715
6.314.4.6 FILTERED	1715
6.314.4.7 HUFFMAN_ONLY	1715

6.314.4.8 NO_COMPRESSION	1715
6.315decaf::util::zip::DeflaterOutputStream Class Reference	1716
6.315.1 Detailed Description	1717
6.315.2 Constructor & Destructor Documentation	1717
6.315.2.1 DeflaterOutputStream	1717
6.315.2.2 DeflaterOutputStream	1717
6.315.2.3 DeflaterOutputStream	1718
6.315.2.4 ~DeflaterOutputStream	1718
6.315.3 Member Function Documentation	1718
6.315.3.1 close	1718
6.315.3.2 deflate	1718
6.315.3.3 doWriteArrayBounded	1719
6.315.3.4 doWriteByte	1719
6.315.3.5 finish	1719
6.315.4 Field Documentation	1719
6.315.4.1 buf	1719
6.315.4.2 DEFAULT_BUFFER_SIZE	1719
6.315.4.3 deflater	1719
6.315.4.4 isDone	1719
6.315.4.5 ownDeflater	1719
6.316decaf::util::concurrent::Delayed Class Reference	1720
6.316.1 Detailed Description	1720
6.316.2 Constructor & Destructor Documentation	1720
6.316.2.1 ~Delayed	1720
6.316.3 Member Function Documentation	1720
6.316.3.1 getDelay	1720
6.317cms::DeliveryMode Class Reference	1721
6.317.1 Detailed Description	1721
6.317.2 Member Enumeration Documentation	1721
6.317.2.1 DELIVERY_MODE	1721
6.317.3 Constructor & Destructor Documentation	1722
6.317.3.1 ~DeliveryMode	1722
6.318cms::Destination Class Reference	1723
6.318.1 Detailed Description	1723
6.318.2 Member Enumeration Documentation	1723
6.318.2.1 DestinationType	1723

6.318.3 Constructor & Destructor Documentation	1724
6.318.3.1 ~Destination	1724
6.318.4 Member Function Documentation	1724
6.318.4.1 clone	1724
6.318.4.2 copy	1724
6.318.4.3 getCMSProperties	1724
6.318.4.4 getDestinationType	1724
6.319activemq::commands::ActiveMQDestination::DestinationFilter Struct Reference . .	1726
6.319.1 Field Documentation	1726
6.319.1.1 ANY_CHILD	1726
6.319.1.2 ANY_DESCENDENT	1726
6.320activemq::commands::DestinationInfo Class Reference	1727
6.320.1 Constructor & Destructor Documentation	1728
6.320.1.1 DestinationInfo	1728
6.320.1.2 ~DestinationInfo	1728
6.320.2 Member Function Documentation	1728
6.320.2.1 cloneDataStructure	1728
6.320.2.2 copyDataStructure	1728
6.320.2.3 equals	1728
6.320.2.4 getBrokerPath	1729
6.320.2.5 getBrokerPath	1729
6.320.2.6 getConnectionId	1729
6.320.2.7 getConnectionId	1729
6.320.2.8 getDataStructureType	1729
6.320.2.9 getDestination	1730
6.320.2.10getDestination	1730
6.320.2.11getOperationType	1730
6.320.2.12getTimeout	1730
6.320.2.13setBrokerPath	1730
6.320.2.14setConnectionId	1730
6.320.2.15setDestination	1730
6.320.2.16setOperationType	1730
6.320.2.17setTimeout	1730
6.320.2.18oString	1730
6.320.2.19visit	1730
6.320.3 Field Documentation	1731

6.320.3.1 brokerPath	1731
6.320.3.2 connectionId	1731
6.320.3.3 destination	1731
6.320.3.4 ID_DESTINATIONINFO	1731
6.320.3.5 operationType	1731
6.320.3.6 timeout	1731
6.321activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller Class Reference	1732
6.321.1 Detailed Description	1732
6.321.2 Constructor & Destructor Documentation	1733
6.321.2.1 DestinationInfoMarshaller	1733
6.321.2.2 ~DestinationInfoMarshaller	1733
6.321.3 Member Function Documentation	1733
6.321.3.1 createObject	1733
6.321.3.2 getDataStructureType	1733
6.321.3.3 looseMarshal	1733
6.321.3.4 looseUnmarshal	1734
6.321.3.5 tightMarshal1	1734
6.321.3.6 tightMarshal2	1734
6.321.3.7 tightUnmarshal	1735
6.322activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller Class Reference	1736
6.322.1 Detailed Description	1736
6.322.2 Constructor & Destructor Documentation	1737
6.322.2.1 DestinationInfoMarshaller	1737
6.322.2.2 ~DestinationInfoMarshaller	1737
6.322.3 Member Function Documentation	1737
6.322.3.1 createObject	1737
6.322.3.2 getDataStructureType	1737
6.322.3.3 looseMarshal	1737
6.322.3.4 looseUnmarshal	1738
6.322.3.5 tightMarshal1	1738
6.322.3.6 tightMarshal2	1738
6.322.3.7 tightUnmarshal	1739
6.323activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller Class Reference	1740
6.323.1 Detailed Description	1740

6.323.2 Constructor & Destructor Documentation	1741
6.323.2.1 DestinationInfoMarshaller	1741
6.323.2.2 ~DestinationInfoMarshaller	1741
6.323.3 Member Function Documentation	1741
6.323.3.1 createObject	1741
6.323.3.2 getDataStructureType	1741
6.323.3.3 looseMarshal	1741
6.323.3.4 looseUnmarshal	1742
6.323.3.5 tightMarshal1	1742
6.323.3.6 tightMarshal2	1742
6.323.3.7 tightUnmarshal	1743
6.324activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller Class Reference	1744
6.324.1 Detailed Description	1744
6.324.2 Constructor & Destructor Documentation	1745
6.324.2.1 DestinationInfoMarshaller	1745
6.324.2.2 ~DestinationInfoMarshaller	1745
6.324.3 Member Function Documentation	1745
6.324.3.1 createObject	1745
6.324.3.2 getDataStructureType	1745
6.324.3.3 looseMarshal	1745
6.324.3.4 looseUnmarshal	1746
6.324.3.5 tightMarshal1	1746
6.324.3.6 tightMarshal2	1746
6.324.3.7 tightUnmarshal	1747
6.325activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller Class Reference	1748
6.325.1 Detailed Description	1748
6.325.2 Constructor & Destructor Documentation	1749
6.325.2.1 DestinationInfoMarshaller	1749
6.325.2.2 ~DestinationInfoMarshaller	1749
6.325.3 Member Function Documentation	1749
6.325.3.1 createObject	1749
6.325.3.2 getDataStructureType	1749
6.325.3.3 looseMarshal	1749
6.325.3.4 looseUnmarshal	1750
6.325.3.5 tightMarshal1	1750

6.325.3.6 tightMarshal2	1750
6.325.3.7 tightUnmarshal	1751
6.326activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller Class Reference	1752
6.326.1 Detailed Description	1752
6.326.2 Constructor & Destructor Documentation	1753
6.326.2.1 DestinationInfoMarshaller	1753
6.326.2.2 ~DestinationInfoMarshaller	1753
6.326.3 Member Function Documentation	1753
6.326.3.1 createObject	1753
6.326.3.2 getDataStructureType	1753
6.326.3.3 looseMarshal	1753
6.326.3.4 looseUnmarshal	1754
6.326.3.5 tightMarshal1	1754
6.326.3.6 tightMarshal2	1754
6.326.3.7 tightUnmarshal	1755
6.327activemq::cmsutil::DestinationResolver Class Reference	1756
6.327.1 Detailed Description	1756
6.327.2 Constructor & Destructor Documentation	1756
6.327.2.1 ~DestinationResolver	1756
6.327.3 Member Function Documentation	1756
6.327.3.1 destroy	1756
6.327.3.2 init	1756
6.327.3.3 resolveDestinationName	1757
6.328activemq::commands::DiscoveryEvent Class Reference	1758
6.328.1 Constructor & Destructor Documentation	1759
6.328.1.1 DiscoveryEvent	1759
6.328.1.2 ~DiscoveryEvent	1759
6.328.2 Member Function Documentation	1759
6.328.2.1 cloneDataStructure	1759
6.328.2.2 copyDataStructure	1759
6.328.2.3 equals	1759
6.328.2.4 getBrokerName	1760
6.328.2.5 getBrokerName	1760
6.328.2.6 getDataStructureType	1760
6.328.2.7 getServiceName	1760
6.328.2.8 getServiceName	1760

6.328.2.9	setBrokerName	1760
6.328.2.10	getServiceName	1760
6.328.2.11	toString	1760
6.328.3	Field Documentation	1761
6.328.3.1	brokerName	1761
6.328.3.2	ID_DISCOVERYEVENT	1761
6.328.3.3	serviceName	1761
6.329	activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller Class Reference	1762
6.329.1	Detailed Description	1762
6.329.2	Constructor & Destructor Documentation	1763
6.329.2.1	DiscoveryEventMarshaller	1763
6.329.2.2	~DiscoveryEventMarshaller	1763
6.329.3	Member Function Documentation	1763
6.329.3.1	createObject	1763
6.329.3.2	getDataStructureType	1763
6.329.3.3	looseMarshal	1763
6.329.3.4	looseUnmarshal	1764
6.329.3.5	tightMarshal1	1764
6.329.3.6	tightMarshal2	1764
6.329.3.7	tightUnmarshal	1765
6.330	activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller Class Reference	1766
6.330.1	Detailed Description	1766
6.330.2	Constructor & Destructor Documentation	1767
6.330.2.1	DiscoveryEventMarshaller	1767
6.330.2.2	~DiscoveryEventMarshaller	1767
6.330.3	Member Function Documentation	1767
6.330.3.1	createObject	1767
6.330.3.2	getDataStructureType	1767
6.330.3.3	looseMarshal	1767
6.330.3.4	looseUnmarshal	1768
6.330.3.5	tightMarshal1	1768
6.330.3.6	tightMarshal2	1768
6.330.3.7	tightUnmarshal	1769
6.331	activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller Class Reference	1770

6.331.1 Detailed Description	1770
6.331.2 Constructor & Destructor Documentation	1771
6.331.2.1 DiscoveryEventMarshaller	1771
6.331.2.2 ~DiscoveryEventMarshaller	1771
6.331.3 Member Function Documentation	1771
6.331.3.1 createObject	1771
6.331.3.2 getDataStructureType	1771
6.331.3.3 looseMarshal	1771
6.331.3.4 looseUnmarshal	1772
6.331.3.5 tightMarshal1	1772
6.331.3.6 tightMarshal2	1772
6.331.3.7 tightUnmarshal	1773
6.332activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller Class Reference	1774
6.332.1 Detailed Description	1774
6.332.2 Constructor & Destructor Documentation	1775
6.332.2.1 DiscoveryEventMarshaller	1775
6.332.2.2 ~DiscoveryEventMarshaller	1775
6.332.3 Member Function Documentation	1775
6.332.3.1 createObject	1775
6.332.3.2 getDataStructureType	1775
6.332.3.3 looseMarshal	1775
6.332.3.4 looseUnmarshal	1776
6.332.3.5 tightMarshal1	1776
6.332.3.6 tightMarshal2	1776
6.332.3.7 tightUnmarshal	1777
6.333activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller Class Reference	1778
6.333.1 Detailed Description	1778
6.333.2 Constructor & Destructor Documentation	1779
6.333.2.1 DiscoveryEventMarshaller	1779
6.333.2.2 ~DiscoveryEventMarshaller	1779
6.333.3 Member Function Documentation	1779
6.333.3.1 createObject	1779
6.333.3.2 getDataStructureType	1779
6.333.3.3 looseMarshal	1779
6.333.3.4 looseUnmarshal	1780

6.333.3.5 tightMarshal1	1780
6.333.3.6 tightMarshal2	1780
6.333.3.7 tightUnmarshal	1781
6.334activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller Class Reference	1782
6.334.1 Detailed Description	1782
6.334.2 Constructor & Destructor Documentation	1783
6.334.2.1 DiscoveryEventMarshaller	1783
6.334.2.2 ~DiscoveryEventMarshaller	1783
6.334.3 Member Function Documentation	1783
6.334.3.1 createObject	1783
6.334.3.2 getDataStructureType	1783
6.334.3.3 looseMarshal	1783
6.334.3.4 looseUnmarshal	1784
6.334.3.5 tightMarshal1	1784
6.334.3.6 tightMarshal2	1784
6.334.3.7 tightUnmarshal	1785
6.335activemq::core::DispatchData Class Reference	1786
6.335.1 Detailed Description	1786
6.335.2 Constructor & Destructor Documentation	1786
6.335.2.1 DispatchData	1786
6.335.2.2 DispatchData	1786
6.335.3 Member Function Documentation	1786
6.335.3.1 getConsumerId	1786
6.335.3.2 getMessage	1786
6.336activemq::core::Dispatcher Class Reference	1787
6.336.1 Detailed Description	1787
6.336.2 Constructor & Destructor Documentation	1787
6.336.2.1 ~Dispatcher	1787
6.336.3 Member Function Documentation	1787
6.336.3.1 dispatch	1787
6.337decaf::lang::Double Class Reference	1788
6.337.1 Constructor & Destructor Documentation	1790
6.337.1.1 Double	1790
6.337.1.2 Double	1790
6.337.1.3 ~Double	1790
6.337.2 Member Function Documentation	1790

6.337.2.1	byteValue	1790
6.337.2.2	compare	1790
6.337.2.3	compareTo	1791
6.337.2.4	compareTo	1791
6.337.2.5	doubleToLongBits	1791
6.337.2.6	doubleToRawLongBits	1792
6.337.2.7	doubleValue	1792
6.337.2.8	equals	1793
6.337.2.9	equals	1793
6.337.2.10	float Value	1793
6.337.2.11	int Value	1793
6.337.2.12	isInfinite	1793
6.337.2.13	isInfinite	1794
6.337.2.14	isNaN	1794
6.337.2.15	isNaN	1794
6.337.2.16	longBitsToDouble	1794
6.337.2.17	long Value	1794
6.337.2.18	operator<	1795
6.337.2.19	operator<	1795
6.337.2.20	operator==	1795
6.337.2.21	operator==	1795
6.337.2.22	parseDouble	1796
6.337.2.23	short Value	1796
6.337.2.24	toHexString	1796
6.337.2.25	toString	1797
6.337.2.26	toString	1797
6.337.2.27	valueOf	1797
6.337.2.28	valueOf	1798
6.337.3	Field Documentation	1798
6.337.3.1	MAX_VALUE	1798
6.337.3.2	MIN_VALUE	1798
6.337.3.3	NaN	1798
6.337.3.4	NEGATIVE_INFINITY	1798
6.337.3.5	POSITIVE_INFINITY	1798
6.337.3.6	SIZE	1798
6.338	decaf::internal::nio::DoubleArrayBuffer Class Reference	1799

6.338.1 Constructor & Destructor Documentation	1802
6.338.1.1 DoubleArrayBuffer	1802
6.338.1.2 DoubleArrayBuffer	1802
6.338.1.3 DoubleArrayBuffer	1803
6.338.1.4 DoubleArrayBuffer	1803
6.338.1.5 ~DoubleArrayBuffer	1803
6.338.2 Member Function Documentation	1803
6.338.2.1 array	1803
6.338.2.2 arrayOffset	1804
6.338.2.3 asReadOnlyBuffer	1804
6.338.2.4 compact	1805
6.338.2.5 duplicate	1805
6.338.2.6 get	1805
6.338.2.7 get	1806
6.338.2.8 hasArray	1806
6.338.2.9 isReadOnly	1806
6.338.2.10put	1806
6.338.2.11put	1807
6.338.2.12setReadOnly	1807
6.338.2.13lice	1807
6.339decaf::nio::DoubleBuffer Class Reference	1809
6.339.1 Detailed Description	1811
6.339.2 Constructor & Destructor Documentation	1811
6.339.2.1 DoubleBuffer	1811
6.339.2.2 ~DoubleBuffer	1811
6.339.3 Member Function Documentation	1811
6.339.3.1 allocate	1811
6.339.3.2 array	1812
6.339.3.3 arrayOffset	1812
6.339.3.4 asReadOnlyBuffer	1813
6.339.3.5 compact	1813
6.339.3.6 compareTo	1813
6.339.3.7 duplicate	1813
6.339.3.8 equals	1814
6.339.3.9 get	1814
6.339.3.10get	1814

6.339.3.11	get	1815
6.339.3.12	get	1815
6.339.3.13	hasArray	1815
6.339.3.14	operator<	1816
6.339.3.15	operator==	1816
6.339.3.16	put	1816
6.339.3.17	put	1816
6.339.3.18	put	1816
6.339.3.19	put	1817
6.339.3.20	put	1817
6.339.3.21	slice	1818
6.339.3.22	toString	1818
6.339.3.23	wrap	1818
6.339.3.24	wrap	1819
6.340	decaf::lang::DYNAMIC_CAST_TOKEN Struct Reference	1820
6.341	activemq::cmsutil::DynamicDestinationResolver Class Reference	1821
6.341.1	Detailed Description	1821
6.341.2	Constructor & Destructor Documentation	1822
6.341.2.1	DynamicDestinationResolver	1822
6.341.2.2	DynamicDestinationResolver	1822
6.341.2.3	~DynamicDestinationResolver	1822
6.341.3	Member Function Documentation	1822
6.341.3.1	destroy	1822
6.341.3.2	init	1822
6.341.3.3	operator=	1822
6.341.3.4	resolveDestinationName	1822
6.342	decaf::util::Map< K, V, COMPARATOR >::Entry Class Reference	1824
6.342.1	Constructor & Destructor Documentation	1824
6.342.1.1	Entry	1824
6.342.1.2	~Entry	1824
6.342.2	Member Function Documentation	1824
6.342.2.1	getKey	1824
6.342.2.2	getValue	1824
6.342.2.3	setValue	1824
6.343	decaf::io::EOFException Class Reference	1825
6.343.1	Constructor & Destructor Documentation	1825

6.343.1.1 EOFException	1825
6.343.1.2 EOFException	1825
6.343.1.3 EOFException	1826
6.343.1.4 EOFException	1826
6.343.1.5 EOFException	1826
6.343.1.6 EOFException	1826
6.343.1.7 ~EOFException	1827
6.343.2 Member Function Documentation	1827
6.343.2.1 clone	1827
6.344decaf::util::logging::ErrorManager Class Reference	1828
6.344.1 Detailed Description	1828
6.344.2 Constructor & Destructor Documentation	1829
6.344.2.1 ErrorManager	1829
6.344.2.2 ~ErrorManager	1829
6.344.3 Member Function Documentation	1829
6.344.3.1 error	1829
6.344.4 Field Documentation	1829
6.344.4.1 CLOSE_FAILURE	1829
6.344.4.2 FLUSH_FAILURE	1829
6.344.4.3 FORMAT_FAILURE	1829
6.344.4.4 GENERIC_FAILURE	1829
6.344.4.5 OPEN_FAILURE	1829
6.344.4.6 WRITE_FAILURE	1830
6.345decaf::lang::Exception Class Reference	1831
6.345.1 Constructor & Destructor Documentation	1832
6.345.1.1 Exception	1832
6.345.1.2 Exception	1833
6.345.1.3 Exception	1833
6.345.1.4 Exception	1833
6.345.1.5 Exception	1833
6.345.1.6 ~Exception	1834
6.345.2 Member Function Documentation	1834
6.345.2.1 buildMessage	1834
6.345.2.2 clone	1834
6.345.2.3 getCause	1835
6.345.2.4 getMessage	1835

6.345.2.5	getStackTrace	1835
6.345.2.6	getStackTraceString	1835
6.345.2.7	initCause	1836
6.345.2.8	operator=	1836
6.345.2.9	printStackTrace	1836
6.345.2.10	printStackTrace	1836
6.345.2.11	setMark	1836
6.345.2.12	setMessage	1837
6.345.2.13	setStackTrace	1837
6.345.2.14	what	1837
6.345.3	Field Documentation	1837
6.345.3.1	cause	1837
6.345.3.2	message	1837
6.345.3.3	stackTrace	1837
6.346	cms::ExceptionListener Class Reference	1838
6.346.1	Detailed Description	1838
6.346.2	Constructor & Destructor Documentation	1838
6.346.2.1	~ExceptionListener	1838
6.346.3	Member Function Documentation	1838
6.346.3.1	onException	1838
6.347	activemq::commands::ExceptionResponse Class Reference	1839
6.347.1	Constructor & Destructor Documentation	1840
6.347.1.1	ExceptionResponse	1840
6.347.1.2	~ExceptionResponse	1840
6.347.2	Member Function Documentation	1840
6.347.2.1	cloneDataStructure	1840
6.347.2.2	copyDataStructure	1840
6.347.2.3	equals	1840
6.347.2.4	getDataStructureType	1840
6.347.2.5	getException	1841
6.347.2.6	getException	1841
6.347.2.7	setException	1841
6.347.2.8	toString	1841
6.347.3	Field Documentation	1841
6.347.3.1	exception	1841
6.347.3.2	ID_EXCEPTIONRESPONSE	1841

6.348	activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller	Class	
	Reference		1842
6.348.1	Detailed Description		1842
6.348.2	Constructor & Destructor Documentation		1843
	6.348.2.1 ExceptionResponseMarshaller		1843
	6.348.2.2 ~ExceptionResponseMarshaller		1843
6.348.3	Member Function Documentation		1843
	6.348.3.1 createObject		1843
	6.348.3.2 getDataStructureType		1843
	6.348.3.3 looseMarshal		1843
	6.348.3.4 looseUnmarshal		1844
	6.348.3.5 tightMarshal1		1844
	6.348.3.6 tightMarshal2		1845
	6.348.3.7 tightUnmarshal		1845
6.349	activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	Class	
	Reference		1846
6.349.1	Detailed Description		1846
6.349.2	Constructor & Destructor Documentation		1847
	6.349.2.1 ExceptionResponseMarshaller		1847
	6.349.2.2 ~ExceptionResponseMarshaller		1847
6.349.3	Member Function Documentation		1847
	6.349.3.1 createObject		1847
	6.349.3.2 getDataStructureType		1847
	6.349.3.3 looseMarshal		1847
	6.349.3.4 looseUnmarshal		1848
	6.349.3.5 tightMarshal1		1848
	6.349.3.6 tightMarshal2		1849
	6.349.3.7 tightUnmarshal		1849
6.350	activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	Class	
	Reference		1850
6.350.1	Detailed Description		1850
6.350.2	Constructor & Destructor Documentation		1851
	6.350.2.1 ExceptionResponseMarshaller		1851
	6.350.2.2 ~ExceptionResponseMarshaller		1851
6.350.3	Member Function Documentation		1851
	6.350.3.1 createObject		1851
	6.350.3.2 getDataStructureType		1851

6.350.3.3 looseMarshal	1851
6.350.3.4 looseUnmarshal	1852
6.350.3.5 tightMarshal1	1852
6.350.3.6 tightMarshal2	1853
6.350.3.7 tightUnmarshal	1853
6.351activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller Class	
Reference	1854
6.351.1 Detailed Description	1854
6.351.2 Constructor & Destructor Documentation	1855
6.351.2.1 ExceptionResponseMarshaller	1855
6.351.2.2 ~ExceptionResponseMarshaller	1855
6.351.3 Member Function Documentation	1855
6.351.3.1 createObject	1855
6.351.3.2 getDataStructureType	1855
6.351.3.3 looseMarshal	1855
6.351.3.4 looseUnmarshal	1856
6.351.3.5 tightMarshal1	1856
6.351.3.6 tightMarshal2	1857
6.351.3.7 tightUnmarshal	1857
6.352activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller Class	
Reference	1858
6.352.1 Detailed Description	1858
6.352.2 Constructor & Destructor Documentation	1859
6.352.2.1 ExceptionResponseMarshaller	1859
6.352.2.2 ~ExceptionResponseMarshaller	1859
6.352.3 Member Function Documentation	1859
6.352.3.1 createObject	1859
6.352.3.2 getDataStructureType	1859
6.352.3.3 looseMarshal	1859
6.352.3.4 looseUnmarshal	1860
6.352.3.5 tightMarshal1	1860
6.352.3.6 tightMarshal2	1861
6.352.3.7 tightUnmarshal	1861
6.353activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller Class	
Reference	1862
6.353.1 Detailed Description	1862
6.353.2 Constructor & Destructor Documentation	1863

6.353.2.1	ExceptionResponseMarshaller	1863
6.353.2.2	~ExceptionResponseMarshaller	1863
6.353.3	Member Function Documentation	1863
6.353.3.1	createObject	1863
6.353.3.2	getDataStructureType	1863
6.353.3.3	looseMarshal	1863
6.353.3.4	looseUnmarshal	1864
6.353.3.5	tightMarshal1	1864
6.353.3.6	tightMarshal2	1865
6.353.3.7	tightUnmarshal	1865
6.354	decaf::util::concurrent::ExecutionException Class Reference	1866
6.354.1	Constructor & Destructor Documentation	1866
6.354.1.1	ExecutionException	1866
6.354.1.2	ExecutionException	1866
6.354.1.3	ExecutionException	1867
6.354.1.4	ExecutionException	1867
6.354.1.5	ExecutionException	1867
6.354.1.6	ExecutionException	1867
6.354.1.7	~ExecutionException	1868
6.354.2	Member Function Documentation	1868
6.354.2.1	clone	1868
6.355	decaf::util::concurrent::Executor Class Reference	1869
6.355.1	Detailed Description	1869
6.355.2	Constructor & Destructor Documentation	1870
6.355.2.1	~Executor	1870
6.355.3	Member Function Documentation	1870
6.355.3.1	execute	1870
6.356	decaf::util::concurrent::ExecutorService Class Reference	1871
6.356.1	Detailed Description	1871
6.356.2	Constructor & Destructor Documentation	1872
6.356.2.1	~ExecutorService	1872
6.356.3	Member Function Documentation	1872
6.356.3.1	awaitTermination	1872
6.357	activemq::transport::failover::FailoverTransport Class Reference	1873
6.357.1	Constructor & Destructor Documentation	1875
6.357.1.1	FailoverTransport	1875

6.357.1.2 ~FailoverTransport	1875
6.357.2 Member Function Documentation	1875
6.357.2.1 add	1875
6.357.2.2 addURI	1876
6.357.2.3 close	1876
6.357.2.4 getBackOffMultiplier	1877
6.357.2.5 getBackupPoolSize	1877
6.357.2.6 getInitialReconnectDelay	1877
6.357.2.7 getMaxCacheSize	1877
6.357.2.8 getMaxReconnectAttempts	1877
6.357.2.9 getMaxReconnectDelay	1877
6.357.2.10getReconnectDelay	1877
6.357.2.11getRemoteAddress	1877
6.357.2.12getStartupMaxReconnectAttempts	1877
6.357.2.13getTimeout	1877
6.357.2.14getTransportListener	1877
6.357.2.15handleTransportFailure	1878
6.357.2.16sBackup	1878
6.357.2.17sClosed	1878
6.357.2.18sConnected	1878
6.357.2.19sFaultTolerant	1878
6.357.2.20sInitialized	1879
6.357.2.21sPending	1879
6.357.2.22sRandomize	1879
6.357.2.23sTrackMessages	1879
6.357.2.24sTrackTransactionProducers	1879
6.357.2.25sUseExponentialBackOff	1879
6.357.2.26terate	1879
6.357.2.27narrow	1879
6.357.2.28neway	1880
6.357.2.29reconnect	1880
6.357.2.30reconnect	1880
6.357.2.31removeURI	1881
6.357.2.32request	1881
6.357.2.33request	1881
6.357.2.34estoreTransport	1882

6.357.2.35	setBackOffMultiplier	1882
6.357.2.36	setBackup	1882
6.357.2.37	setBackupPoolSize	1882
6.357.2.38	setConnectionInterruptProcessingComplete	1882
6.357.2.39	setInitialized	1882
6.357.2.40	setInitialReconnectDelay	1883
6.357.2.41	setMaxCacheSize	1883
6.357.2.42	setMaxReconnectAttempts	1883
6.357.2.43	setMaxReconnectDelay	1883
6.357.2.44	setRandomize	1883
6.357.2.45	setReconnectDelay	1883
6.357.2.46	setStartupMaxReconnectAttempts	1883
6.357.2.47	setTimeout	1883
6.357.2.48	setTrackMessages	1883
6.357.2.49	setTrackTransactionProducers	1883
6.357.2.50	setTransportListener	1883
6.357.2.51	setUseExponentialBackOff	1884
6.357.2.52	setWireFormat	1884
6.357.2.53	start	1884
6.357.2.54	stop	1884
6.357.3	Friends And Related Function Documentation	1884
6.357.3.1	FailoverTransportListener	1884
6.358	activemq::transport::failover::FailoverTransportFactory Class Reference	1885
6.358.1	Detailed Description	1885
6.358.2	Constructor & Destructor Documentation	1886
6.358.2.1	~FailoverTransportFactory	1886
6.358.3	Member Function Documentation	1886
6.358.3.1	create	1886
6.358.3.2	createComposite	1886
6.358.3.3	doCreateComposite	1886
6.359	activemq::transport::failover::FailoverTransportListener Class Reference	1888
6.359.1	Detailed Description	1888
6.359.2	Constructor & Destructor Documentation	1889
6.359.2.1	FailoverTransportListener	1889
6.359.2.2	~FailoverTransportListener	1889
6.359.3	Member Function Documentation	1889

6.359.3.1 onCommand	1889
6.359.3.2 onException	1889
6.359.3.3 transportInterrupted	1889
6.359.3.4 transportResumed	1889
6.360decaf::io::FileDescriptor Class Reference	1891
6.360.1 Detailed Description	1891
6.360.2 Constructor & Destructor Documentation	1892
6.360.2.1 FileDescriptor	1892
6.360.2.2 FileDescriptor	1892
6.360.2.3 ~FileDescriptor	1892
6.360.3 Member Function Documentation	1892
6.360.3.1 sync	1892
6.360.3.2 valid	1892
6.360.4 Field Documentation	1892
6.360.4.1 descriptor	1892
6.360.4.2 err	1892
6.360.4.3 in	1892
6.360.4.4 out	1892
6.360.4.5 readonly	1892
6.361decaf::util::logging::Filter Class Reference	1893
6.361.1 Detailed Description	1893
6.361.2 Constructor & Destructor Documentation	1893
6.361.2.1 ~Filter	1893
6.361.3 Member Function Documentation	1893
6.361.3.1 isLoggable	1893
6.362decaf::io::FilterInputStream Class Reference	1894
6.362.1 Detailed Description	1896
6.362.2 Constructor & Destructor Documentation	1896
6.362.2.1 FilterInputStream	1896
6.362.2.2 ~FilterInputStream	1896
6.362.3 Member Function Documentation	1896
6.362.3.1 available	1896
6.362.3.2 close	1897
6.362.3.3 doReadArray	1897
6.362.3.4 doReadArrayBounded	1897
6.362.3.5 doReadByte	1897

6.362.3.6	isClosed	1897
6.362.3.7	mark	1897
6.362.3.8	markSupported	1898
6.362.3.9	reset	1898
6.362.3.10	skip	1899
6.362.4	Field Documentation	1899
6.362.4.1	closed	1899
6.362.4.2	inputStream	1899
6.362.4.3	own	1899
6.363	decaf::io::FilterOutputStream Class Reference	1900
6.363.1	Detailed Description	1901
6.363.2	Constructor & Destructor Documentation	1901
6.363.2.1	FilterOutputStream	1901
6.363.2.2	~FilterOutputStream	1901
6.363.3	Member Function Documentation	1901
6.363.3.1	close	1901
6.363.3.2	doWriteArray	1902
6.363.3.3	doWriteArrayBounded	1902
6.363.3.4	doWriteByte	1902
6.363.3.5	flush	1902
6.363.3.6	isClosed	1902
6.363.3.7	toString	1903
6.363.4	Field Documentation	1903
6.363.4.1	closed	1903
6.363.4.2	outputStream	1903
6.363.4.3	own	1903
6.364	decaf::lang::Float Class Reference	1904
6.364.1	Constructor & Destructor Documentation	1906
6.364.1.1	Float	1906
6.364.1.2	Float	1906
6.364.1.3	Float	1906
6.364.1.4	~Float	1906
6.364.2	Member Function Documentation	1906
6.364.2.1	byteValue	1906
6.364.2.2	compare	1907
6.364.2.3	compareTo	1907

6.364.2.4	compareTo	1907
6.364.2.5	doubleValue	1907
6.364.2.6	equals	1908
6.364.2.7	equals	1908
6.364.2.8	floatToIntBits	1908
6.364.2.9	floatToRawIntBits	1908
6.364.2.10	floatValue	1909
6.364.2.11	intBitsToFloat	1909
6.364.2.12	intValue	1909
6.364.2.13	isInfinite	1910
6.364.2.14	isInfinite	1910
6.364.2.15	isNaN	1910
6.364.2.16	isNaN	1910
6.364.2.17	longValue	1910
6.364.2.18	operator<	1910
6.364.2.19	operator<	1911
6.364.2.20	operator==	1911
6.364.2.21	operator==	1911
6.364.2.22	parseFloat	1911
6.364.2.23	shortValue	1912
6.364.2.24	toHexString	1912
6.364.2.25	toString	1913
6.364.2.26	toString	1913
6.364.2.27	valueOf	1913
6.364.2.28	valueOf	1914
6.364.3	Field Documentation	1914
6.364.3.1	MAX_VALUE	1914
6.364.3.2	MIN_VALUE	1914
6.364.3.3	NaN	1914
6.364.3.4	NEGATIVE_INFINITY	1914
6.364.3.5	POSITIVE_INFINITY	1914
6.364.3.6	SIZE	1914
6.365	decaf::internal::nio::FloatArrayBuffer Class Reference	1915
6.365.1	Constructor & Destructor Documentation	1918
6.365.1.1	FloatArrayBuffer	1918
6.365.1.2	FloatArrayBuffer	1918

6.365.1.3 FloatArrayBuffer	1919
6.365.1.4 FloatArrayBuffer	1919
6.365.1.5 ~FloatArrayBuffer	1919
6.365.2 Member Function Documentation	1919
6.365.2.1 array	1919
6.365.2.2 arrayOffset	1920
6.365.2.3 asReadOnlyBuffer	1920
6.365.2.4 compact	1921
6.365.2.5 duplicate	1921
6.365.2.6 get	1921
6.365.2.7 get	1922
6.365.2.8 hasArray	1922
6.365.2.9 isReadOnly	1922
6.365.2.10put	1922
6.365.2.11put	1923
6.365.2.12setReadOnly	1923
6.365.2.13slice	1923
6.366decaf::nio::FloatBuffer Class Reference	1925
6.366.1 Detailed Description	1927
6.366.2 Constructor & Destructor Documentation	1927
6.366.2.1 FloatBuffer	1927
6.366.2.2 ~FloatBuffer	1927
6.366.3 Member Function Documentation	1927
6.366.3.1 allocate	1927
6.366.3.2 array	1928
6.366.3.3 arrayOffset	1928
6.366.3.4 asReadOnlyBuffer	1928
6.366.3.5 compact	1929
6.366.3.6 compareTo	1929
6.366.3.7 duplicate	1929
6.366.3.8 equals	1929
6.366.3.9 get	1929
6.366.3.10get	1930
6.366.3.11get	1930
6.366.3.12get	1931
6.366.3.13hasArray	1931

6.366.3.14	operator<	1931
6.366.3.15	operator==	1931
6.366.3.16	put	1931
6.366.3.17	put	1932
6.366.3.18	put	1932
6.366.3.19	put	1932
6.366.3.20	put	1933
6.366.3.21	slice	1934
6.366.3.22	toString	1934
6.366.3.23	wrap	1934
6.366.3.24	wrap	1934
6.367	decaf::io::Flushable Class Reference	1936
6.367.1	Detailed Description	1936
6.367.2	Constructor & Destructor Documentation	1936
6.367.2.1	~Flushable	1936
6.367.3	Member Function Documentation	1936
6.367.3.1	flush	1936
6.368	activemq::commands::FlushCommand Class Reference	1937
6.368.1	Constructor & Destructor Documentation	1938
6.368.1.1	FlushCommand	1938
6.368.1.2	~FlushCommand	1938
6.368.2	Member Function Documentation	1938
6.368.2.1	cloneDataStructure	1938
6.368.2.2	copyDataStructure	1938
6.368.2.3	equals	1938
6.368.2.4	getDataStructureType	1938
6.368.2.5	toString	1939
6.368.2.6	visit	1939
6.368.3	Field Documentation	1939
6.368.3.1	ID_FLUSHCOMMAND	1939
6.369	activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller Class Reference	1940
6.369.1	Detailed Description	1940
6.369.2	Constructor & Destructor Documentation	1941
6.369.2.1	FlushCommandMarshaller	1941
6.369.2.2	~FlushCommandMarshaller	1941
6.369.3	Member Function Documentation	1941

6.369.3.1 createObject	1941
6.369.3.2 getDataStructureType	1941
6.369.3.3 looseMarshal	1941
6.369.3.4 looseUnmarshal	1942
6.369.3.5 tightMarshal1	1942
6.369.3.6 tightMarshal2	1942
6.369.3.7 tightUnmarshal	1943
6.370activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller Class Reference	1944
6.370.1 Detailed Description	1944
6.370.2 Constructor & Destructor Documentation	1945
6.370.2.1 FlushCommandMarshaller	1945
6.370.2.2 ~FlushCommandMarshaller	1945
6.370.3 Member Function Documentation	1945
6.370.3.1 createObject	1945
6.370.3.2 getDataStructureType	1945
6.370.3.3 looseMarshal	1945
6.370.3.4 looseUnmarshal	1946
6.370.3.5 tightMarshal1	1946
6.370.3.6 tightMarshal2	1946
6.370.3.7 tightUnmarshal	1947
6.371activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller Class Reference	1948
6.371.1 Detailed Description	1948
6.371.2 Constructor & Destructor Documentation	1949
6.371.2.1 FlushCommandMarshaller	1949
6.371.2.2 ~FlushCommandMarshaller	1949
6.371.3 Member Function Documentation	1949
6.371.3.1 createObject	1949
6.371.3.2 getDataStructureType	1949
6.371.3.3 looseMarshal	1949
6.371.3.4 looseUnmarshal	1950
6.371.3.5 tightMarshal1	1950
6.371.3.6 tightMarshal2	1950
6.371.3.7 tightUnmarshal	1951
6.372activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller Class Reference	1952

6.372.1 Detailed Description	1952
6.372.2 Constructor & Destructor Documentation	1953
6.372.2.1 FlushCommandMarshaller	1953
6.372.2.2 ~FlushCommandMarshaller	1953
6.372.3 Member Function Documentation	1953
6.372.3.1 createObject	1953
6.372.3.2 getDataStructureType	1953
6.372.3.3 looseMarshal	1953
6.372.3.4 looseUnmarshal	1954
6.372.3.5 tightMarshal1	1954
6.372.3.6 tightMarshal2	1954
6.372.3.7 tightUnmarshal	1955
6.373activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller Class Reference	1956
6.373.1 Detailed Description	1956
6.373.2 Constructor & Destructor Documentation	1957
6.373.2.1 FlushCommandMarshaller	1957
6.373.2.2 ~FlushCommandMarshaller	1957
6.373.3 Member Function Documentation	1957
6.373.3.1 createObject	1957
6.373.3.2 getDataStructureType	1957
6.373.3.3 looseMarshal	1957
6.373.3.4 looseUnmarshal	1958
6.373.3.5 tightMarshal1	1958
6.373.3.6 tightMarshal2	1958
6.373.3.7 tightUnmarshal	1959
6.374activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller Class Reference	1960
6.374.1 Detailed Description	1960
6.374.2 Constructor & Destructor Documentation	1961
6.374.2.1 FlushCommandMarshaller	1961
6.374.2.2 ~FlushCommandMarshaller	1961
6.374.3 Member Function Documentation	1961
6.374.3.1 createObject	1961
6.374.3.2 getDataStructureType	1961
6.374.3.3 looseMarshal	1961
6.374.3.4 looseUnmarshal	1962

6.374.3.5 tightMarshal1	1962
6.374.3.6 tightMarshal2	1962
6.374.3.7 tightUnmarshal	1963
6.375decaf::util::logging::Formatter Class Reference	1964
6.375.1 Detailed Description	1964
6.375.2 Constructor & Destructor Documentation	1964
6.375.2.1 ~Formatter	1964
6.375.3 Member Function Documentation	1964
6.375.3.1 format	1964
6.375.3.2 formatMessage	1965
6.375.3.3 getHead	1965
6.375.3.4 getTail	1965
6.376decaf::util::concurrent::Future< V > Class Template Reference	1966
6.376.1 Detailed Description	1966
6.376.2 Constructor & Destructor Documentation	1967
6.376.2.1 ~Future	1967
6.376.3 Member Function Documentation	1967
6.376.3.1 cancel	1967
6.376.3.2 get	1967
6.376.3.3 get	1968
6.376.3.4 isCancelled	1968
6.376.3.5 isDone	1968
6.377activemq::transport::correlator::FutureResponse Class Reference	1969
6.377.1 Detailed Description	1969
6.377.2 Constructor & Destructor Documentation	1969
6.377.2.1 FutureResponse	1969
6.377.2.2 ~FutureResponse	1969
6.377.3 Member Function Documentation	1969
6.377.3.1 getResponse	1969
6.377.3.2 getResponse	1969
6.377.3.3 getResponse	1970
6.377.3.4 getResponse	1970
6.377.3.5 setResponse	1970
6.378decaf::security::GeneralSecurityException Class Reference	1971
6.378.1 Constructor & Destructor Documentation	1971
6.378.1.1 GeneralSecurityException	1971

6.378.1.2 GeneralSecurityException	1971
6.378.1.3 GeneralSecurityException	1972
6.378.1.4 GeneralSecurityException	1972
6.378.1.5 GeneralSecurityException	1972
6.378.1.6 GeneralSecurityException	1972
6.378.1.7 ~GeneralSecurityException	1973
6.378.2 Member Function Documentation	1973
6.378.2.1 clone	1973
6.379decaf::internal::util::GenericResource< T > Class Template Reference	1974
6.379.1 Detailed Description	1974
6.379.2 Constructor & Destructor Documentation	1974
6.379.2.1 GenericResource	1974
6.379.2.2 ~GenericResource	1974
6.379.3 Member Function Documentation	1974
6.379.3.1 getManaged	1974
6.379.3.2 setManaged	1974
6.380gz_header_s Struct Reference	1975
6.380.1 Field Documentation	1975
6.380.1.1 comm_max	1975
6.380.1.2 comment	1975
6.380.1.3 done	1975
6.380.1.4 extra	1975
6.380.1.5 extra_len	1975
6.380.1.6 extra_max	1975
6.380.1.7 hcrc	1975
6.380.1.8 name	1975
6.380.1.9 name_max	1975
6.380.1.10bs	1975
6.380.1.11text	1975
6.380.1.12ime	1975
6.380.1.13flags	1975
6.381gz_state Struct Reference	1976
6.381.1 Field Documentation	1977
6.381.1.1 direct	1977
6.381.1.2 eof	1977
6.381.1.3 err	1977

6.381.1.4	fd	1977
6.381.1.5	have	1977
6.381.1.6	how	1977
6.381.1.7	in	1977
6.381.1.8	level	1977
6.381.1.9	mode	1977
6.381.1.10	msg	1977
6.381.1.11	next	1977
6.381.1.12	out	1977
6.381.1.13	path	1977
6.381.1.14	pos	1977
6.381.1.15	raw	1977
6.381.1.16	seek	1977
6.381.1.17	size	1977
6.381.1.18	skip	1977
6.381.1.19	start	1977
6.381.1.20	strategy	1977
6.381.1.21	strm	1977
6.381.1.22	want	1977
6.382	decaf::util::logging::Handler Class Reference	1978
6.382.1	Detailed Description	1979
6.382.2	Constructor & Destructor Documentation	1979
6.382.2.1	Handler	1979
6.382.2.2	~Handler	1979
6.382.3	Member Function Documentation	1979
6.382.3.1	flush	1979
6.382.3.2	getErrorManager	1979
6.382.3.3	getFilter	1979
6.382.3.4	getFormatter	1979
6.382.3.5	getLevel	1980
6.382.3.6	isLoggable	1980
6.382.3.7	publish	1980
6.382.3.8	reportError	1980
6.382.3.9	setErrorManager	1980
6.382.3.10	setFilter	1981
6.382.3.11	setFormatter	1981

6.382.3.12	setLevel	1981
6.383	decaf::internal::util::HexStringParser Class Reference	1982
6.383.1	Constructor & Destructor Documentation	1982
6.383.1.1	HexStringParser	1982
6.383.1.2	~HexStringParser	1982
6.383.2	Member Function Documentation	1982
6.383.2.1	parse	1982
6.383.2.2	parseDouble	1983
6.383.2.3	parseFloat	1983
6.384	activemq::wireformat::openwire::utils::HexTable Class Reference	1984
6.384.1	Detailed Description	1984
6.384.2	Constructor & Destructor Documentation	1984
6.384.2.1	HexTable	1984
6.384.2.2	~HexTable	1984
6.384.3	Member Function Documentation	1984
6.384.3.1	operator[]	1984
6.384.3.2	operator[]	1984
6.384.3.3	size	1985
6.385	decaf::net::HttpRetryException Class Reference	1986
6.385.1	Constructor & Destructor Documentation	1986
6.385.1.1	HttpRetryException	1986
6.385.1.2	HttpRetryException	1986
6.385.1.3	HttpRetryException	1987
6.385.1.4	HttpRetryException	1987
6.385.1.5	HttpRetryException	1987
6.385.1.6	HttpRetryException	1987
6.385.1.7	~HttpRetryException	1988
6.385.2	Member Function Documentation	1988
6.385.2.1	clone	1988
6.386	activemq::util::IdGenerator Class Reference	1989
6.386.1	Constructor & Destructor Documentation	1989
6.386.1.1	IdGenerator	1989
6.386.1.2	IdGenerator	1989
6.386.1.3	~IdGenerator	1989
6.386.2	Member Function Documentation	1989
6.386.2.1	compare	1989

6.386.2.2 generateId	1990
6.386.2.3 getHostname	1990
6.386.2.4 getSeedFromId	1990
6.386.2.5 getSequenceFromId	1990
6.387decaf::lang::exceptions::IllegalArgumentException Class Reference	1991
6.387.1 Constructor & Destructor Documentation	1991
6.387.1.1 IllegalArgumentException	1991
6.387.1.2 IllegalArgumentException	1991
6.387.1.3 IllegalArgumentException	1992
6.387.1.4 IllegalArgumentException	1992
6.387.1.5 IllegalArgumentException	1992
6.387.1.6 IllegalArgumentException	1992
6.387.1.7 ~IllegalArgumentException	1993
6.387.2 Member Function Documentation	1993
6.387.2.1 clone	1993
6.388decaf::lang::exceptions::IllegalMonitorStateException Class Reference	1994
6.388.1 Constructor & Destructor Documentation	1994
6.388.1.1 IllegalMonitorStateException	1994
6.388.1.2 IllegalMonitorStateException	1994
6.388.1.3 IllegalMonitorStateException	1995
6.388.1.4 IllegalMonitorStateException	1995
6.388.1.5 IllegalMonitorStateException	1995
6.388.1.6 IllegalMonitorStateException	1995
6.388.1.7 ~IllegalMonitorStateException	1996
6.388.2 Member Function Documentation	1996
6.388.2.1 clone	1996
6.389cms::IllegalStateException Class Reference	1997
6.389.1 Detailed Description	1997
6.389.2 Constructor & Destructor Documentation	1997
6.389.2.1 IllegalStateException	1997
6.389.2.2 IllegalStateException	1997
6.389.2.3 IllegalStateException	1997
6.389.2.4 IllegalStateException	1997
6.389.2.5 ~IllegalStateException	1997
6.390decaf::lang::exceptions::IllegalStateException Class Reference	1998
6.390.1 Constructor & Destructor Documentation	1998

6.390.1.1	IllegalStateException	1998
6.390.1.2	IllegalStateException	1998
6.390.1.3	IllegalStateException	1999
6.390.1.4	IllegalStateException	1999
6.390.1.5	IllegalStateException	1999
6.390.1.6	IllegalStateException	1999
6.390.1.7	~IllegalStateException	2000
6.390.2	Member Function Documentation	2000
6.390.2.1	clone	2000
6.391	decaf::lang::exceptions::IllegalThreadStateException Class Reference	2001
6.391.1	Constructor & Destructor Documentation	2001
6.391.1.1	IllegalThreadStateException	2001
6.391.1.2	IllegalThreadStateException	2001
6.391.1.3	IllegalThreadStateException	2002
6.391.1.4	IllegalThreadStateException	2002
6.391.1.5	IllegalThreadStateException	2002
6.391.1.6	IllegalThreadStateException	2002
6.391.1.7	~IllegalThreadStateException	2003
6.391.2	Member Function Documentation	2003
6.391.2.1	clone	2003
6.392	activemq::transport::inactivity::InactivityMonitor Class Reference	2004
6.392.1	Constructor & Destructor Documentation	2005
6.392.1.1	InactivityMonitor	2005
6.392.1.2	InactivityMonitor	2005
6.392.1.3	~InactivityMonitor	2005
6.392.2	Member Function Documentation	2005
6.392.2.1	close	2005
6.392.2.2	getInitialDelayTime	2005
6.392.2.3	getReadCheckTime	2005
6.392.2.4	getWriteCheckTime	2005
6.392.2.5	isKeepAliveResponseRequired	2005
6.392.2.6	onCommand	2005
6.392.2.7	oneway	2006
6.392.2.8	onException	2006
6.392.2.9	setInitialDelayTime	2007
6.392.2.10	setKeepAliveResponseRequired	2007

6.392.2.1	setReadCheckTime	2007
6.392.2.2	setWriteCheckTime	2007
6.392.3	Friends And Related Function Documentation	2007
6.392.3.1	AsyncSignalReadErrorTask	2007
6.392.3.2	AsyncWriteTask	2007
6.392.3.3	ReadChecker	2007
6.392.3.4	WriteChecker	2007
6.393	decaf::lang::exceptions::IndexOutOfBoundsException Class Reference	2008
6.393.1	Constructor & Destructor Documentation	2008
6.393.1.1	IndexOutOfBoundsException	2008
6.393.1.2	IndexOutOfBoundsException	2008
6.393.1.3	IndexOutOfBoundsException	2009
6.393.1.4	IndexOutOfBoundsException	2009
6.393.1.5	IndexOutOfBoundsException	2009
6.393.1.6	IndexOutOfBoundsException	2009
6.393.1.7	~IndexOutOfBoundsException	2010
6.393.2	Member Function Documentation	2010
6.393.2.1	clone	2010
6.394	decaf::net::Inet4Address Class Reference	2011
6.394.1	Constructor & Destructor Documentation	2012
6.394.1.1	Inet4Address	2012
6.394.1.2	Inet4Address	2012
6.394.1.3	Inet4Address	2012
6.394.1.4	~Inet4Address	2012
6.394.2	Member Function Documentation	2012
6.394.2.1	isAnyLocalAddress	2012
6.394.2.2	isLinkLocalAddress	2012
6.394.2.3	isLoopbackAddress	2012
6.394.2.4	isMCGlobal	2013
6.394.2.5	isMCLinkLocal	2013
6.394.2.6	isMCNodeLocal	2013
6.394.2.7	isMCOrgLocal	2013
6.394.2.8	isMCSiteLocal	2013
6.394.2.9	isMulticastAddress	2014
6.394.2.10	sSiteLocalAddress	2014
6.394.3	Friends And Related Function Documentation	2014

6.394.3.1 InetAddress	2014
6.395decaf::net::Inet6Address Class Reference	2015
6.395.1 Constructor & Destructor Documentation	2015
6.395.1.1 Inet6Address	2015
6.395.1.2 Inet6Address	2015
6.395.1.3 Inet6Address	2015
6.395.1.4 ~Inet6Address	2015
6.395.2 Friends And Related Function Documentation	2015
6.395.2.1 InetAddress	2015
6.396decaf::net::InetAddress Class Reference	2016
6.396.1 Detailed Description	2018
6.396.2 Constructor & Destructor Documentation	2018
6.396.2.1 InetAddress	2018
6.396.2.2 InetAddress	2018
6.396.2.3 InetAddress	2018
6.396.2.4 ~InetAddress	2018
6.396.3 Member Function Documentation	2018
6.396.3.1 bytesToInt	2018
6.396.3.2 getAddress	2018
6.396.3.3 getAnyAddress	2019
6.396.3.4 getByAddress	2019
6.396.3.5 getByAddress	2019
6.396.3.6 getHostAddress	2019
6.396.3.7 getHostName	2019
6.396.3.8 getLocalHost	2020
6.396.3.9 getLoopbackAddress	2020
6.396.3.10sAnyLocalAddress	2020
6.396.3.11sLinkLocalAddress	2020
6.396.3.12sLoopbackAddress	2020
6.396.3.13sMCGlobal	2021
6.396.3.14sMCLinkLocal	2021
6.396.3.15sMCNodeLocal	2021
6.396.3.16sMCOrgLocal	2021
6.396.3.17sMCSiteLocal	2021
6.396.3.18sMulticastAddress	2022
6.396.3.19sSiteLocalAddress	2022

6.396.3.20oString	2022
6.396.4Field Documentation	2022
6.396.4.1 addressBytes	2022
6.396.4.2 anyBytes	2022
6.396.4.3 hostname	2022
6.396.4.4 loopbackBytes	2022
6.396.4.5 reached	2022
6.397decaf::net::InetSocketAddress Class Reference	2023
6.397.1 Constructor & Destructor Documentation	2023
6.397.1.1 InetSocketAddress	2023
6.397.1.2 ~InetSocketAddress	2023
6.398inflate_state Struct Reference	2024
6.398.1 Field Documentation	2025
6.398.1.1 back	2025
6.398.1.2 bits	2025
6.398.1.3 check	2025
6.398.1.4 codes	2025
6.398.1.5 distbits	2025
6.398.1.6 distcode	2025
6.398.1.7 dmax	2025
6.398.1.8 extra	2025
6.398.1.9 flags	2025
6.398.1.10have	2025
6.398.1.11havedict	2025
6.398.1.12head	2025
6.398.1.13hold	2025
6.398.1.14last	2025
6.398.1.15lenbits	2025
6.398.1.16encode	2025
6.398.1.17length	2025
6.398.1.18ens	2025
6.398.1.19mode	2025
6.398.1.20hcode	2025
6.398.1.21ndist	2025
6.398.1.22next	2025
6.398.1.23hlen	2025

6.398.1.24	offset	2025
6.398.1.25	same	2025
6.398.1.26	total	2025
6.398.1.27	was	2025
6.398.1.28	vbits	2025
6.398.1.29	whave	2025
6.398.1.30	window	2025
6.398.1.31	wnext	2025
6.398.1.32	work	2025
6.398.1.33	wrap	2025
6.398.1.34	wsize	2025
6.399	decaf::util::zip::Inflater Class Reference	2027
6.399.1	Detailed Description	2028
6.399.2	Constructor & Destructor Documentation	2029
6.399.2.1	Inflater	2029
6.399.2.2	Inflater	2029
6.399.2.3	~Inflater	2029
6.399.3	Member Function Documentation	2029
6.399.3.1	end	2029
6.399.3.2	finish	2029
6.399.3.3	finished	2029
6.399.3.4	getAdler	2029
6.399.3.5	getBytesRead	2030
6.399.3.6	getBytesWritten	2030
6.399.3.7	getRemaining	2030
6.399.3.8	inflate	2030
6.399.3.9	inflate	2031
6.399.3.10	inflate	2031
6.399.3.11	needsDictionary	2032
6.399.3.12	needsInput	2032
6.399.3.13	reset	2032
6.399.3.14	setDictionary	2032
6.399.3.15	setDictionary	2032
6.399.3.16	setDictionary	2033
6.399.3.17	setInput	2033
6.399.3.18	setInput	2034

6.399.3.19	setInput	2034
6.400	decaf::util::zip::InflaterInputStream Class Reference	2035
6.400.1	Detailed Description	2037
6.400.2	Constructor & Destructor Documentation	2037
6.400.2.1	InflaterInputStream	2037
6.400.2.2	InflaterInputStream	2037
6.400.2.3	InflaterInputStream	2038
6.400.2.4	~InflaterInputStream	2038
6.400.3	Member Function Documentation	2038
6.400.3.1	available	2038
6.400.3.2	close	2039
6.400.3.3	doReadArrayBounded	2039
6.400.3.4	doReadByte	2039
6.400.3.5	fill	2039
6.400.3.6	mark	2039
6.400.3.7	markSupported	2040
6.400.3.8	reset	2040
6.400.3.9	skip	2041
6.400.4	Field Documentation	2041
6.400.4.1	atEOF	2041
6.400.4.2	buff	2041
6.400.4.3	DEFAULT_BUFFER_SIZE	2041
6.400.4.4	inflater	2041
6.400.4.5	length	2041
6.400.4.6	ownInflater	2042
6.401	decaf::io::InputStream Class Reference	2043
6.401.1	Detailed Description	2044
6.401.2	Constructor & Destructor Documentation	2045
6.401.2.1	InputStream	2045
6.401.2.2	~InputStream	2045
6.401.3	Member Function Documentation	2045
6.401.3.1	available	2045
6.401.3.2	close	2045
6.401.3.3	doReadArray	2045
6.401.3.4	doReadArrayBounded	2046
6.401.3.5	doReadByte	2046

6.401.3.6 lock	2046
6.401.3.7 mark	2046
6.401.3.8 markSupported	2047
6.401.3.9 notify	2047
6.401.3.10 notifyAll	2047
6.401.3.11 read	2048
6.401.3.12 read	2048
6.401.3.13 read	2049
6.401.3.14 reset	2049
6.401.3.15 skip	2050
6.401.3.16 toString	2050
6.401.3.17 tryLock	2051
6.401.3.18 unlock	2051
6.401.3.19 wait	2051
6.401.3.20 wait	2052
6.401.3.21 wait	2052
6.402 decaf::io::InputStreamReader Class Reference	2053
6.402.1 Detailed Description	2053
6.402.2 Constructor & Destructor Documentation	2054
6.402.2.1 InputStreamReader	2054
6.402.2.2 ~InputStreamReader	2054
6.402.3 Member Function Documentation	2054
6.402.3.1 checkClosed	2054
6.402.3.2 close	2054
6.402.3.3 doReadArrayBounded	2054
6.402.3.4 ready	2054
6.403 decaf::internal::nio::IntArrayBuffer Class Reference	2056
6.403.1 Constructor & Destructor Documentation	2059
6.403.1.1 IntArrayBuffer	2059
6.403.1.2 IntArrayBuffer	2059
6.403.1.3 IntArrayBuffer	2060
6.403.1.4 IntArrayBuffer	2060
6.403.1.5 ~IntArrayBuffer	2060
6.403.2 Member Function Documentation	2060
6.403.2.1 array	2060
6.403.2.2 arrayOffset	2061

6.403.2.3 asReadOnlyBuffer	2061
6.403.2.4 compact	2062
6.403.2.5 duplicate	2062
6.403.2.6 get	2062
6.403.2.7 get	2063
6.403.2.8 hasArray	2063
6.403.2.9 isReadOnly	2063
6.403.2.10put	2063
6.403.2.11put	2064
6.403.2.12setReadOnly	2064
6.403.2.13lice	2064
6.404decaf::nio::IntBuffer Class Reference	2066
6.404.1 Detailed Description	2068
6.404.2 Constructor & Destructor Documentation	2068
6.404.2.1 IntBuffer	2068
6.404.2.2 ~IntBuffer	2068
6.404.3 Member Function Documentation	2068
6.404.3.1 allocate	2068
6.404.3.2 array	2069
6.404.3.3 arrayOffset	2069
6.404.3.4 asReadOnlyBuffer	2069
6.404.3.5 compact	2070
6.404.3.6 compareTo	2070
6.404.3.7 duplicate	2070
6.404.3.8 equals	2070
6.404.3.9 get	2070
6.404.3.10get	2071
6.404.3.11get	2071
6.404.3.12get	2072
6.404.3.13hasArray	2072
6.404.3.14operator<	2072
6.404.3.15operator==	2072
6.404.3.16put	2072
6.404.3.17put	2073
6.404.3.18put	2073
6.404.3.19put	2074

6.404.3.20put	2074
6.404.3.21slice	2075
6.404.3.22toString	2075
6.404.3.23wrap	2075
6.404.3.24wrap	2075
6.405decaf::lang::Integer Class Reference	2077
6.405.1 Constructor & Destructor Documentation	2079
6.405.1.1 Integer	2079
6.405.1.2 Integer	2080
6.405.1.3 ~Integer	2080
6.405.2 Member Function Documentation	2080
6.405.2.1 bitCount	2080
6.405.2.2 byteValue	2080
6.405.2.3 compareTo	2080
6.405.2.4 compareTo	2081
6.405.2.5 decode	2081
6.405.2.6 doubleValue	2081
6.405.2.7 equals	2081
6.405.2.8 equals	2082
6.405.2.9 floatValue	2082
6.405.2.10highestOneBit	2082
6.405.2.11int Value	2082
6.405.2.12long Value	2083
6.405.2.13lowestOneBit	2083
6.405.2.14numberOfLeadingZeros	2083
6.405.2.15numberOfTrailingZeros	2083
6.405.2.16operator<	2084
6.405.2.17operator<	2084
6.405.2.18operator==	2084
6.405.2.19operator==	2085
6.405.2.20parseInt	2085
6.405.2.21parseInt	2085
6.405.2.22reverse	2086
6.405.2.23reverseBytes	2086
6.405.2.24rotateLeft	2086
6.405.2.25rotateRight	2087

6.405.2.26	shortValue	2087
6.405.2.27	signum	2087
6.405.2.28	toBinaryString	2087
6.405.2.29	toHexString	2088
6.405.2.30	toOctalString	2088
6.405.2.31	toString	2088
6.405.2.32	toString	2089
6.405.2.33	toString	2089
6.405.2.34	valueOf	2089
6.405.2.35	valueOf	2090
6.405.2.36	valueOf	2090
6.405.3	Field Documentation	2090
6.405.3.1	MAX_VALUE	2090
6.405.3.2	MIN_VALUE	2090
6.405.3.3	SIZE	2090
6.406	activemq::commands::IntegerResponse Class Reference	2091
6.406.1	Constructor & Destructor Documentation	2092
6.406.1.1	IntegerResponse	2092
6.406.1.2	~IntegerResponse	2092
6.406.2	Member Function Documentation	2092
6.406.2.1	cloneDataStructure	2092
6.406.2.2	copyDataStructure	2092
6.406.2.3	equals	2092
6.406.2.4	getDataStructureType	2092
6.406.2.5	getResult	2093
6.406.2.6	setResult	2093
6.406.2.7	toString	2093
6.406.3	Field Documentation	2093
6.406.3.1	ID_INTEGERRESPONSE	2093
6.406.3.2	result	2093
6.407	activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller Class Reference	2094
6.407.1	Detailed Description	2094
6.407.2	Constructor & Destructor Documentation	2095
6.407.2.1	IntegerResponseMarshaller	2095
6.407.2.2	~IntegerResponseMarshaller	2095
6.407.3	Member Function Documentation	2095

6.407.3.1 createObject	2095
6.407.3.2 getDataStructureType	2095
6.407.3.3 looseMarshal	2095
6.407.3.4 looseUnmarshal	2096
6.407.3.5 tightMarshal1	2096
6.407.3.6 tightMarshal2	2097
6.407.3.7 tightUnmarshal	2097
6.408activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller	Class
Reference	2098
6.408.1 Detailed Description	2098
6.408.2 Constructor & Destructor Documentation	2099
6.408.2.1 IntegerResponseMarshaller	2099
6.408.2.2 ~IntegerResponseMarshaller	2099
6.408.3 Member Function Documentation	2099
6.408.3.1 createObject	2099
6.408.3.2 getDataStructureType	2099
6.408.3.3 looseMarshal	2099
6.408.3.4 looseUnmarshal	2100
6.408.3.5 tightMarshal1	2100
6.408.3.6 tightMarshal2	2101
6.408.3.7 tightUnmarshal	2101
6.409activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller	Class
Reference	2102
6.409.1 Detailed Description	2102
6.409.2 Constructor & Destructor Documentation	2103
6.409.2.1 IntegerResponseMarshaller	2103
6.409.2.2 ~IntegerResponseMarshaller	2103
6.409.3 Member Function Documentation	2103
6.409.3.1 createObject	2103
6.409.3.2 getDataStructureType	2103
6.409.3.3 looseMarshal	2103
6.409.3.4 looseUnmarshal	2104
6.409.3.5 tightMarshal1	2104
6.409.3.6 tightMarshal2	2105
6.409.3.7 tightUnmarshal	2105
6.410activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller	Class
Reference	2106

6.410.1 Detailed Description	2106
6.410.2 Constructor & Destructor Documentation	2107
6.410.2.1 IntegerResponseMarshaller	2107
6.410.2.2 ~IntegerResponseMarshaller	2107
6.410.3 Member Function Documentation	2107
6.410.3.1 createObject	2107
6.410.3.2 getDataStructureType	2107
6.410.3.3 looseMarshal	2107
6.410.3.4 looseUnmarshal	2108
6.410.3.5 tightMarshal1	2108
6.410.3.6 tightMarshal2	2109
6.410.3.7 tightUnmarshal	2109
6.411activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller Class	
Reference	2110
6.411.1 Detailed Description	2110
6.411.2 Constructor & Destructor Documentation	2111
6.411.2.1 IntegerResponseMarshaller	2111
6.411.2.2 ~IntegerResponseMarshaller	2111
6.411.3 Member Function Documentation	2111
6.411.3.1 createObject	2111
6.411.3.2 getDataStructureType	2111
6.411.3.3 looseMarshal	2111
6.411.3.4 looseUnmarshal	2112
6.411.3.5 tightMarshal1	2112
6.411.3.6 tightMarshal2	2113
6.411.3.7 tightUnmarshal	2113
6.412activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller Class	
Reference	2114
6.412.1 Detailed Description	2114
6.412.2 Constructor & Destructor Documentation	2115
6.412.2.1 IntegerResponseMarshaller	2115
6.412.2.2 ~IntegerResponseMarshaller	2115
6.412.3 Member Function Documentation	2115
6.412.3.1 createObject	2115
6.412.3.2 getDataStructureType	2115
6.412.3.3 looseMarshal	2115
6.412.3.4 looseUnmarshal	2116

6.412.3.5 tightMarshal1	2116
6.412.3.6 tightMarshal2	2117
6.412.3.7 tightUnmarshal	2117
6.413internal_state Struct Reference	2118
6.413.1 Field Documentation	2120
6.413.1.1 bi_buf	2120
6.413.1.2 bi_valid	2120
6.413.1.3 bl_count	2120
6.413.1.4 bl_desc	2120
6.413.1.5 bl_tree	2120
6.413.1.6 block_start	2120
6.413.1.7 d_buf	2120
6.413.1.8 d_desc	2120
6.413.1.9 depth	2120
6.413.1.10 dummy	2120
6.413.1.11 dyn_dtree	2120
6.413.1.12 dyn_ltree	2120
6.413.1.13 good_match	2120
6.413.1.14 gzhead	2120
6.413.1.15 gzindex	2120
6.413.1.16 hash_bits	2120
6.413.1.17 hash_mask	2120
6.413.1.18 hash_shift	2120
6.413.1.19 hash_size	2120
6.413.1.20 head	2120
6.413.1.21 heap	2120
6.413.1.22 heap_len	2120
6.413.1.23 heap_max	2120
6.413.1.24 high_water	2120
6.413.1.25 ins_h	2120
6.413.1.26 _buf	2120
6.413.1.27 _desc	2120
6.413.1.28 ast_eob_len	2120
6.413.1.29 ast_flush	2120
6.413.1.30 ast_lit	2120
6.413.1.31 level	2120

6.413.1.32	lit_bufsize	2120
6.413.1.33	lookahead	2120
6.413.1.34	match_available	2120
6.413.1.35	match_length	2120
6.413.1.36	match_start	2120
6.413.1.37	matches	2120
6.413.1.38	max_chain_length	2120
6.413.1.39	max_lazy_match	2120
6.413.1.40	method	2120
6.413.1.41	nice_match	2120
6.413.1.42	opt_len	2120
6.413.1.43	pending	2120
6.413.1.44	pending_buf	2120
6.413.1.45	pending_buf_size	2120
6.413.1.46	pending_out	2120
6.413.1.47	prev	2120
6.413.1.48	prev_length	2120
6.413.1.49	prev_match	2120
6.413.1.50	static_len	2120
6.413.1.51	status	2120
6.413.1.52	strategy	2120
6.413.1.53	strm	2120
6.413.1.54	strstart	2120
6.413.1.55	w_bits	2120
6.413.1.56	w_mask	2120
6.413.1.57	w_size	2120
6.413.1.58	window	2120
6.413.1.59	window_size	2120
6.413.1.60	wrap	2120
6.414	activemq::transport::mock::InternalCommandListener Class Reference	2122
6.414.1	Detailed Description	2122
6.414.2	Constructor & Destructor Documentation	2122
6.414.2.1	InternalCommandListener	2122
6.414.2.2	~InternalCommandListener	2122
6.414.3	Member Function Documentation	2122
6.414.3.1	onCommand	2122

6.414.3.2 run	2123
6.414.3.3 setResponseBuilder	2123
6.414.3.4 setTransport	2123
6.415decaf::lang::exceptions::InterruptedException Class Reference	2124
6.415.1 Constructor & Destructor Documentation	2124
6.415.1.1 InterruptedException	2124
6.415.1.2 InterruptedException	2124
6.415.1.3 InterruptedException	2125
6.415.1.4 InterruptedException	2125
6.415.1.5 InterruptedException	2125
6.415.1.6 InterruptedException	2125
6.415.1.7 ~InterruptedException	2126
6.415.2 Member Function Documentation	2126
6.415.2.1 clone	2126
6.416decaf::io::InterruptedException Class Reference	2127
6.416.1 Constructor & Destructor Documentation	2127
6.416.1.1 InterruptedException	2127
6.416.1.2 InterruptedException	2127
6.416.1.3 InterruptedException	2128
6.416.1.4 InterruptedException	2128
6.416.1.5 InterruptedException	2128
6.416.1.6 InterruptedException	2128
6.416.1.7 ~InterruptedException	2129
6.416.2 Member Function Documentation	2129
6.416.2.1 clone	2129
6.417cms::InvalidClientIdException Class Reference	2130
6.417.1 Detailed Description	2130
6.417.2 Constructor & Destructor Documentation	2130
6.417.2.1 InvalidClientIdException	2130
6.417.2.2 InvalidClientIdException	2130
6.417.2.3 InvalidClientIdException	2130
6.417.2.4 InvalidClientIdException	2130
6.417.2.5 ~InvalidClientIdException	2130
6.418cms::InvalidDestinationException Class Reference	2131
6.418.1 Detailed Description	2131
6.418.2 Constructor & Destructor Documentation	2131

6.418.2.1 InvalidDestinationException	2131
6.418.2.2 InvalidDestinationException	2131
6.418.2.3 InvalidDestinationException	2131
6.418.2.4 InvalidDestinationException	2131
6.418.2.5 ~InvalidDestinationException	2131
6.419decaf::security::InvalidKeyException Class Reference	2132
6.419.1 Constructor & Destructor Documentation	2132
6.419.1.1 InvalidKeyException	2132
6.419.1.2 InvalidKeyException	2132
6.419.1.3 InvalidKeyException	2133
6.419.1.4 InvalidKeyException	2133
6.419.1.5 InvalidKeyException	2133
6.419.1.6 InvalidKeyException	2133
6.419.1.7 ~InvalidKeyException	2134
6.419.2 Member Function Documentation	2134
6.419.2.1 clone	2134
6.420decaf::nio::InvalidMarkException Class Reference	2135
6.420.1 Constructor & Destructor Documentation	2135
6.420.1.1 InvalidMarkException	2135
6.420.1.2 InvalidMarkException	2135
6.420.1.3 InvalidMarkException	2136
6.420.1.4 InvalidMarkException	2136
6.420.1.5 InvalidMarkException	2136
6.420.1.6 InvalidMarkException	2136
6.420.1.7 ~InvalidMarkException	2137
6.420.2 Member Function Documentation	2137
6.420.2.1 clone	2137
6.421cms::InvalidSelectorException Class Reference	2138
6.421.1 Detailed Description	2138
6.421.2 Constructor & Destructor Documentation	2138
6.421.2.1 InvalidSelectorException	2138
6.421.2.2 InvalidSelectorException	2138
6.421.2.3 InvalidSelectorException	2138
6.421.2.4 InvalidSelectorException	2138
6.421.2.5 ~InvalidSelectorException	2138
6.422decaf::lang::exceptions::InvalidStateException Class Reference	2139

6.422.1 Constructor & Destructor Documentation	2139
6.422.1.1 InvalidStateException	2139
6.422.1.2 InvalidStateException	2139
6.422.1.3 InvalidStateException	2140
6.422.1.4 InvalidStateException	2140
6.422.1.5 InvalidStateException	2140
6.422.1.6 InvalidStateException	2140
6.422.1.7 ~InvalidStateException	2141
6.422.2 Member Function Documentation	2141
6.422.2.1 clone	2141
6.423decaf::io::IOException Class Reference	2142
6.423.1 Constructor & Destructor Documentation	2142
6.423.1.1 IOException	2142
6.423.1.2 IOException	2142
6.423.1.3 IOException	2143
6.423.1.4 IOException	2143
6.423.1.5 IOException	2143
6.423.1.6 IOException	2143
6.423.1.7 ~IOException	2144
6.423.2 Member Function Documentation	2144
6.423.2.1 clone	2144
6.424activemq::transport::IOTransport Class Reference	2145
6.424.1 Detailed Description	2146
6.424.2 Constructor & Destructor Documentation	2146
6.424.2.1 IOTransport	2146
6.424.2.2 IOTransport	2147
6.424.2.3 ~IOTransport	2147
6.424.3 Member Function Documentation	2147
6.424.3.1 close	2147
6.424.3.2 getRemoteAddress	2147
6.424.3.3 getTransportListener	2147
6.424.3.4 isClosed	2147
6.424.3.5 isConnected	2148
6.424.3.6 isFaultTolerant	2148
6.424.3.7 narrow	2148
6.424.3.8 oneway	2148

6.424.3.9 reconnect	2149
6.424.3.10 request	2149
6.424.3.11 request	2149
6.424.3.12 run	2150
6.424.3.13 setInputStream	2150
6.424.3.14 setOutputStream	2150
6.424.3.15 setTransportListener	2150
6.424.3.16 setWireFormat	2150
6.424.3.17 start	2150
6.424.3.18 stop	2151
6.425 decaf::lang::Iterable< E > Class Template Reference	2152
6.425.1 Detailed Description	2152
6.425.2 Constructor & Destructor Documentation	2152
6.425.2.1 ~Iterable	2152
6.425.3 Member Function Documentation	2152
6.425.3.1 iterator	2152
6.425.3.2 iterator	2152
6.426 decaf::util::Iterator< T > Class Template Reference	2154
6.426.1 Detailed Description	2154
6.426.2 Constructor & Destructor Documentation	2154
6.426.2.1 ~Iterator	2154
6.426.3 Member Function Documentation	2154
6.426.3.1 hasNext	2154
6.426.3.2 next	2154
6.426.3.3 remove	2155
6.427 activemq::commands::JournalQueueAck Class Reference	2156
6.427.1 Constructor & Destructor Documentation	2157
6.427.1.1 JournalQueueAck	2157
6.427.1.2 ~JournalQueueAck	2157
6.427.2 Member Function Documentation	2157
6.427.2.1 cloneDataStructure	2157
6.427.2.2 copyDataStructure	2157
6.427.2.3 equals	2157
6.427.2.4 getDataStructureType	2157
6.427.2.5 getDestination	2158
6.427.2.6 getDestination	2158

6.427.2.7	getMessageAck	2158
6.427.2.8	getMessageAck	2158
6.427.2.9	setDestination	2158
6.427.2.10	setMessageAck	2158
6.427.2.11	toString	2158
6.427.3	Field Documentation	2158
6.427.3.1	destination	2158
6.427.3.2	ID_JOURNALQUEUEACK	2158
6.427.3.3	messageAck	2158
6.428	activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller Class	
	Reference	2159
6.428.1	Detailed Description	2159
6.428.2	Constructor & Destructor Documentation	2160
6.428.2.1	JournalQueueAckMarshaller	2160
6.428.2.2	~JournalQueueAckMarshaller	2160
6.428.3	Member Function Documentation	2160
6.428.3.1	createObject	2160
6.428.3.2	getDataStructureType	2160
6.428.3.3	looseMarshal	2160
6.428.3.4	looseUnmarshal	2161
6.428.3.5	tightMarshal1	2161
6.428.3.6	tightMarshal2	2161
6.428.3.7	tightUnmarshal	2162
6.429	activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller Class	
	Reference	2163
6.429.1	Detailed Description	2163
6.429.2	Constructor & Destructor Documentation	2164
6.429.2.1	JournalQueueAckMarshaller	2164
6.429.2.2	~JournalQueueAckMarshaller	2164
6.429.3	Member Function Documentation	2164
6.429.3.1	createObject	2164
6.429.3.2	getDataStructureType	2164
6.429.3.3	looseMarshal	2164
6.429.3.4	looseUnmarshal	2165
6.429.3.5	tightMarshal1	2165
6.429.3.6	tightMarshal2	2165
6.429.3.7	tightUnmarshal	2166

6.430	activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller	Class	
	Reference		2167
6.430.1	Detailed Description		2167
6.430.2	Constructor & Destructor Documentation		2168
6.430.2.1	JournalQueueAckMarshaller		2168
6.430.2.2	~JournalQueueAckMarshaller		2168
6.430.3	Member Function Documentation		2168
6.430.3.1	createObject		2168
6.430.3.2	getDataStructureType		2168
6.430.3.3	looseMarshal		2168
6.430.3.4	looseUnmarshal		2169
6.430.3.5	tightMarshal1		2169
6.430.3.6	tightMarshal2		2169
6.430.3.7	tightUnmarshal		2170
6.431	activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	Class	
	Reference		2171
6.431.1	Detailed Description		2171
6.431.2	Constructor & Destructor Documentation		2172
6.431.2.1	JournalQueueAckMarshaller		2172
6.431.2.2	~JournalQueueAckMarshaller		2172
6.431.3	Member Function Documentation		2172
6.431.3.1	createObject		2172
6.431.3.2	getDataStructureType		2172
6.431.3.3	looseMarshal		2172
6.431.3.4	looseUnmarshal		2173
6.431.3.5	tightMarshal1		2173
6.431.3.6	tightMarshal2		2173
6.431.3.7	tightUnmarshal		2174
6.432	activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller	Class	
	Reference		2175
6.432.1	Detailed Description		2175
6.432.2	Constructor & Destructor Documentation		2176
6.432.2.1	JournalQueueAckMarshaller		2176
6.432.2.2	~JournalQueueAckMarshaller		2176
6.432.3	Member Function Documentation		2176
6.432.3.1	createObject		2176
6.432.3.2	getDataStructureType		2176

6.432.3.3 looseMarshal	2176
6.432.3.4 looseUnmarshal	2177
6.432.3.5 tightMarshal1	2177
6.432.3.6 tightMarshal2	2177
6.432.3.7 tightUnmarshal	2178
6.433activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller Class Reference	2179
6.433.1 Detailed Description	2179
6.433.2 Constructor & Destructor Documentation	2180
6.433.2.1 JournalQueueAckMarshaller	2180
6.433.2.2 ~JournalQueueAckMarshaller	2180
6.433.3 Member Function Documentation	2180
6.433.3.1 createObject	2180
6.433.3.2 getDataStructureType	2180
6.433.3.3 looseMarshal	2180
6.433.3.4 looseUnmarshal	2181
6.433.3.5 tightMarshal1	2181
6.433.3.6 tightMarshal2	2181
6.433.3.7 tightUnmarshal	2182
6.434activemq::commands::JournalTopicAck Class Reference	2183
6.434.1 Constructor & Destructor Documentation	2184
6.434.1.1 JournalTopicAck	2184
6.434.1.2 ~JournalTopicAck	2184
6.434.2 Member Function Documentation	2184
6.434.2.1 cloneDataStructure	2184
6.434.2.2 copyDataStructure	2184
6.434.2.3 equals	2184
6.434.2.4 getClientId	2185
6.434.2.5 getClientId	2185
6.434.2.6 getDataStructureType	2185
6.434.2.7 getDestination	2186
6.434.2.8 getDestination	2186
6.434.2.9 getMessageId	2186
6.434.2.10getMessageId	2186
6.434.2.11getMessageSequenceId	2186
6.434.2.12getSubscriptionName	2186
6.434.2.13getSubscriptionName	2186

6.434.2.14	getTransactionId	2186
6.434.2.15	getTransactionId	2186
6.434.2.16	setClientId	2186
6.434.2.17	setDestination	2186
6.434.2.18	setMessageId	2186
6.434.2.19	setMessageSequenceId	2186
6.434.2.20	setSubscriptionName	2186
6.434.2.21	setTransactionId	2186
6.434.2.22	toString	2186
6.434.3	Field Documentation	2187
6.434.3.1	clientId	2187
6.434.3.2	destination	2187
6.434.3.3	ID_ JOURNALTOPICACK	2187
6.434.3.4	messageId	2187
6.434.3.5	messageSequenceId	2187
6.434.3.6	subscriptionName	2187
6.434.3.7	transactionId	2187
6.435	activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller Class	
	Reference	2188
6.435.1	Detailed Description	2188
6.435.2	Constructor & Destructor Documentation	2189
6.435.2.1	JournalTopicAckMarshaller	2189
6.435.2.2	~JournalTopicAckMarshaller	2189
6.435.3	Member Function Documentation	2189
6.435.3.1	createObject	2189
6.435.3.2	getDataStructureType	2189
6.435.3.3	looseMarshal	2189
6.435.3.4	looseUnmarshal	2190
6.435.3.5	tightMarshal1	2190
6.435.3.6	tightMarshal2	2190
6.435.3.7	tightUnmarshal	2191
6.436	activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller Class	
	Reference	2192
6.436.1	Detailed Description	2192
6.436.2	Constructor & Destructor Documentation	2193
6.436.2.1	JournalTopicAckMarshaller	2193
6.436.2.2	~JournalTopicAckMarshaller	2193

6.436.3 Member Function Documentation	2193
6.436.3.1 createObject	2193
6.436.3.2 getDataStructureType	2193
6.436.3.3 looseMarshal	2193
6.436.3.4 looseUnmarshal	2194
6.436.3.5 tightMarshal1	2194
6.436.3.6 tightMarshal2	2194
6.436.3.7 tightUnmarshal	2195
6.437activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller Class	
Reference	2196
6.437.1 Detailed Description	2196
6.437.2 Constructor & Destructor Documentation	2197
6.437.2.1 JournalTopicAckMarshaller	2197
6.437.2.2 ~JournalTopicAckMarshaller	2197
6.437.3 Member Function Documentation	2197
6.437.3.1 createObject	2197
6.437.3.2 getDataStructureType	2197
6.437.3.3 looseMarshal	2197
6.437.3.4 looseUnmarshal	2198
6.437.3.5 tightMarshal1	2198
6.437.3.6 tightMarshal2	2198
6.437.3.7 tightUnmarshal	2199
6.438activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller Class	
Reference	2200
6.438.1 Detailed Description	2200
6.438.2 Constructor & Destructor Documentation	2201
6.438.2.1 JournalTopicAckMarshaller	2201
6.438.2.2 ~JournalTopicAckMarshaller	2201
6.438.3 Member Function Documentation	2201
6.438.3.1 createObject	2201
6.438.3.2 getDataStructureType	2201
6.438.3.3 looseMarshal	2201
6.438.3.4 looseUnmarshal	2202
6.438.3.5 tightMarshal1	2202
6.438.3.6 tightMarshal2	2202
6.438.3.7 tightUnmarshal	2203

6.439	activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller	Class	
	Reference		2204
6.439.1	Detailed Description		2204
6.439.2	Constructor & Destructor Documentation		2205
6.439.2.1	JournalTopicAckMarshaller		2205
6.439.2.2	~JournalTopicAckMarshaller		2205
6.439.3	Member Function Documentation		2205
6.439.3.1	createObject		2205
6.439.3.2	getDataStructureType		2205
6.439.3.3	looseMarshal		2205
6.439.3.4	looseUnmarshal		2206
6.439.3.5	tightMarshal1		2206
6.439.3.6	tightMarshal2		2206
6.439.3.7	tightUnmarshal		2207
6.440	activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller	Class	
	Reference		2208
6.440.1	Detailed Description		2208
6.440.2	Constructor & Destructor Documentation		2209
6.440.2.1	JournalTopicAckMarshaller		2209
6.440.2.2	~JournalTopicAckMarshaller		2209
6.440.3	Member Function Documentation		2209
6.440.3.1	createObject		2209
6.440.3.2	getDataStructureType		2209
6.440.3.3	looseMarshal		2209
6.440.3.4	looseUnmarshal		2210
6.440.3.5	tightMarshal1		2210
6.440.3.6	tightMarshal2		2210
6.440.3.7	tightUnmarshal		2211
6.441	activemq::commands::JournalTrace	Class Reference	2212
6.441.1	Constructor & Destructor Documentation		2213
6.441.1.1	JournalTrace		2213
6.441.1.2	~JournalTrace		2213
6.441.2	Member Function Documentation		2213
6.441.2.1	cloneDataStructure		2213
6.441.2.2	copyDataStructure		2213
6.441.2.3	equals		2213
6.441.2.4	getDataStructureType		2213

6.441.2.5	getMessage	2214
6.441.2.6	getMessage	2214
6.441.2.7	setMessage	2214
6.441.2.8	toString	2214
6.441.3	Field Documentation	2214
6.441.3.1	ID_JOURNALTRACE	2214
6.441.3.2	message	2214
6.442	activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller Class Reference	2215
6.442.1	Detailed Description	2215
6.442.2	Constructor & Destructor Documentation	2216
6.442.2.1	JournalTraceMarshaller	2216
6.442.2.2	~JournalTraceMarshaller	2216
6.442.3	Member Function Documentation	2216
6.442.3.1	createObject	2216
6.442.3.2	getDataStructureType	2216
6.442.3.3	looseMarshal	2216
6.442.3.4	looseUnmarshal	2217
6.442.3.5	tightMarshal1	2217
6.442.3.6	tightMarshal2	2217
6.442.3.7	tightUnmarshal	2218
6.443	activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller Class Reference	2219
6.443.1	Detailed Description	2219
6.443.2	Constructor & Destructor Documentation	2220
6.443.2.1	JournalTraceMarshaller	2220
6.443.2.2	~JournalTraceMarshaller	2220
6.443.3	Member Function Documentation	2220
6.443.3.1	createObject	2220
6.443.3.2	getDataStructureType	2220
6.443.3.3	looseMarshal	2220
6.443.3.4	looseUnmarshal	2221
6.443.3.5	tightMarshal1	2221
6.443.3.6	tightMarshal2	2221
6.443.3.7	tightUnmarshal	2222
6.444	activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller Class Reference	2223

6.444.1 Detailed Description	2223
6.444.2 Constructor & Destructor Documentation	2224
6.444.2.1 JournalTraceMarshaller	2224
6.444.2.2 ~JournalTraceMarshaller	2224
6.444.3 Member Function Documentation	2224
6.444.3.1 createObject	2224
6.444.3.2 getDataStructureType	2224
6.444.3.3 looseMarshal	2224
6.444.3.4 looseUnmarshal	2225
6.444.3.5 tightMarshal1	2225
6.444.3.6 tightMarshal2	2225
6.444.3.7 tightUnmarshal	2226
6.445activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller Class Reference	2227
6.445.1 Detailed Description	2227
6.445.2 Constructor & Destructor Documentation	2228
6.445.2.1 JournalTraceMarshaller	2228
6.445.2.2 ~JournalTraceMarshaller	2228
6.445.3 Member Function Documentation	2228
6.445.3.1 createObject	2228
6.445.3.2 getDataStructureType	2228
6.445.3.3 looseMarshal	2228
6.445.3.4 looseUnmarshal	2229
6.445.3.5 tightMarshal1	2229
6.445.3.6 tightMarshal2	2229
6.445.3.7 tightUnmarshal	2230
6.446activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller Class Reference	2231
6.446.1 Detailed Description	2231
6.446.2 Constructor & Destructor Documentation	2232
6.446.2.1 JournalTraceMarshaller	2232
6.446.2.2 ~JournalTraceMarshaller	2232
6.446.3 Member Function Documentation	2232
6.446.3.1 createObject	2232
6.446.3.2 getDataStructureType	2232
6.446.3.3 looseMarshal	2232
6.446.3.4 looseUnmarshal	2233

6.446.3.5 tightMarshal1	2233
6.446.3.6 tightMarshal2	2233
6.446.3.7 tightUnmarshal	2234
6.447activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller Class Reference	2235
6.447.1 Detailed Description	2235
6.447.2 Constructor & Destructor Documentation	2236
6.447.2.1 JournalTraceMarshaller	2236
6.447.2.2 ~JournalTraceMarshaller	2236
6.447.3 Member Function Documentation	2236
6.447.3.1 createObject	2236
6.447.3.2 getDataStructureType	2236
6.447.3.3 looseMarshal	2236
6.447.3.4 looseUnmarshal	2237
6.447.3.5 tightMarshal1	2237
6.447.3.6 tightMarshal2	2237
6.447.3.7 tightUnmarshal	2238
6.448activemq::commands::JournalTransaction Class Reference	2239
6.448.1 Constructor & Destructor Documentation	2240
6.448.1.1 JournalTransaction	2240
6.448.1.2 ~JournalTransaction	2240
6.448.2 Member Function Documentation	2240
6.448.2.1 cloneDataStructure	2240
6.448.2.2 copyDataStructure	2240
6.448.2.3 equals	2240
6.448.2.4 getDataStructureType	2240
6.448.2.5 getTransactionId	2241
6.448.2.6 getTransactionId	2241
6.448.2.7 getType	2241
6.448.2.8 getWasPrepared	2241
6.448.2.9 setTransactionId	2241
6.448.2.10 setType	2241
6.448.2.11 setWasPrepared	2241
6.448.2.12 toString	2241
6.448.3 Field Documentation	2241
6.448.3.1 ID_JOURNALTRANSACTION	2241
6.448.3.2 transactionId	2241

6.448.3.3 type	2241
6.448.3.4 wasPrepared	2241
6.449activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller Class	
Reference	2242
6.449.1 Detailed Description	2242
6.449.2 Constructor & Destructor Documentation	2243
6.449.2.1 JournalTransactionMarshaller	2243
6.449.2.2 ~JournalTransactionMarshaller	2243
6.449.3 Member Function Documentation	2243
6.449.3.1 createObject	2243
6.449.3.2 getDataStructureType	2243
6.449.3.3 looseMarshal	2243
6.449.3.4 looseUnmarshal	2244
6.449.3.5 tightMarshal1	2244
6.449.3.6 tightMarshal2	2244
6.449.3.7 tightUnmarshal	2245
6.450activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller Class	
Reference	2246
6.450.1 Detailed Description	2246
6.450.2 Constructor & Destructor Documentation	2247
6.450.2.1 JournalTransactionMarshaller	2247
6.450.2.2 ~JournalTransactionMarshaller	2247
6.450.3 Member Function Documentation	2247
6.450.3.1 createObject	2247
6.450.3.2 getDataStructureType	2247
6.450.3.3 looseMarshal	2247
6.450.3.4 looseUnmarshal	2248
6.450.3.5 tightMarshal1	2248
6.450.3.6 tightMarshal2	2248
6.450.3.7 tightUnmarshal	2249
6.451activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller Class	
Reference	2250
6.451.1 Detailed Description	2250
6.451.2 Constructor & Destructor Documentation	2251
6.451.2.1 JournalTransactionMarshaller	2251
6.451.2.2 ~JournalTransactionMarshaller	2251
6.451.3 Member Function Documentation	2251

6.451.3.1 createObject	2251
6.451.3.2 getDataStructureType	2251
6.451.3.3 looseMarshal	2251
6.451.3.4 looseUnmarshal	2252
6.451.3.5 tightMarshal1	2252
6.451.3.6 tightMarshal2	2252
6.451.3.7 tightUnmarshal	2253
6.452activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller Class	
Reference	2254
6.452.1 Detailed Description	2254
6.452.2 Constructor & Destructor Documentation	2255
6.452.2.1 JournalTransactionMarshaller	2255
6.452.2.2 ~JournalTransactionMarshaller	2255
6.452.3 Member Function Documentation	2255
6.452.3.1 createObject	2255
6.452.3.2 getDataStructureType	2255
6.452.3.3 looseMarshal	2255
6.452.3.4 looseUnmarshal	2256
6.452.3.5 tightMarshal1	2256
6.452.3.6 tightMarshal2	2256
6.452.3.7 tightUnmarshal	2257
6.453activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller Class	
Reference	2258
6.453.1 Detailed Description	2258
6.453.2 Constructor & Destructor Documentation	2259
6.453.2.1 JournalTransactionMarshaller	2259
6.453.2.2 ~JournalTransactionMarshaller	2259
6.453.3 Member Function Documentation	2259
6.453.3.1 createObject	2259
6.453.3.2 getDataStructureType	2259
6.453.3.3 looseMarshal	2259
6.453.3.4 looseUnmarshal	2260
6.453.3.5 tightMarshal1	2260
6.453.3.6 tightMarshal2	2260
6.453.3.7 tightUnmarshal	2261
6.454activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller Class	
Reference	2262

6.454.1 Detailed Description	2262
6.454.2 Constructor & Destructor Documentation	2263
6.454.2.1 JournalTransactionMarshaller	2263
6.454.2.2 ~JournalTransactionMarshaller	2263
6.454.3 Member Function Documentation	2263
6.454.3.1 createObject	2263
6.454.3.2 getDataStructureType	2263
6.454.3.3 looseMarshal	2263
6.454.3.4 looseUnmarshal	2264
6.454.3.5 tightMarshal1	2264
6.454.3.6 tightMarshal2	2264
6.454.3.7 tightUnmarshal	2265
6.455activemq::commands::KeepAliveInfo Class Reference	2266
6.455.1 Constructor & Destructor Documentation	2267
6.455.1.1 KeepAliveInfo	2267
6.455.1.2 ~KeepAliveInfo	2267
6.455.2 Member Function Documentation	2267
6.455.2.1 cloneDataStructure	2267
6.455.2.2 copyDataStructure	2267
6.455.2.3 equals	2267
6.455.2.4 getDataStructureType	2267
6.455.2.5 isKeepAliveInfo	2268
6.455.2.6 toString	2268
6.455.2.7 visit	2268
6.455.3 Field Documentation	2268
6.455.3.1 ID_KEEPLIVEINFO	2268
6.456activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller Class Refer- ence	2269
6.456.1 Detailed Description	2269
6.456.2 Constructor & Destructor Documentation	2270
6.456.2.1 KeepAliveInfoMarshaller	2270
6.456.2.2 ~KeepAliveInfoMarshaller	2270
6.456.3 Member Function Documentation	2270
6.456.3.1 createObject	2270
6.456.3.2 getDataStructureType	2270
6.456.3.3 looseMarshal	2270
6.456.3.4 looseUnmarshal	2271

6.456.3.5 tightMarshal1	2271
6.456.3.6 tightMarshal2	2271
6.456.3.7 tightUnmarshal	2272
6.457activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller Class Reference	2273
6.457.1 Detailed Description	2273
6.457.2 Constructor & Destructor Documentation	2274
6.457.2.1 KeepAliveInfoMarshaller	2274
6.457.2.2 ~KeepAliveInfoMarshaller	2274
6.457.3 Member Function Documentation	2274
6.457.3.1 createObject	2274
6.457.3.2 getDataStructureType	2274
6.457.3.3 looseMarshal	2274
6.457.3.4 looseUnmarshal	2275
6.457.3.5 tightMarshal1	2275
6.457.3.6 tightMarshal2	2275
6.457.3.7 tightUnmarshal	2276
6.458activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller Class Reference	2277
6.458.1 Detailed Description	2277
6.458.2 Constructor & Destructor Documentation	2278
6.458.2.1 KeepAliveInfoMarshaller	2278
6.458.2.2 ~KeepAliveInfoMarshaller	2278
6.458.3 Member Function Documentation	2278
6.458.3.1 createObject	2278
6.458.3.2 getDataStructureType	2278
6.458.3.3 looseMarshal	2278
6.458.3.4 looseUnmarshal	2279
6.458.3.5 tightMarshal1	2279
6.458.3.6 tightMarshal2	2279
6.458.3.7 tightUnmarshal	2280
6.459activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller Class Reference	2281
6.459.1 Detailed Description	2281
6.459.2 Constructor & Destructor Documentation	2282
6.459.2.1 KeepAliveInfoMarshaller	2282
6.459.2.2 ~KeepAliveInfoMarshaller	2282

6.459.3 Member Function Documentation	2282
6.459.3.1 createObject	2282
6.459.3.2 getDataStructureType	2282
6.459.3.3 looseMarshal	2282
6.459.3.4 looseUnmarshal	2283
6.459.3.5 tightMarshal1	2283
6.459.3.6 tightMarshal2	2283
6.459.3.7 tightUnmarshal	2284
6.460activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller Class Reference	2285
6.460.1 Detailed Description	2285
6.460.2 Constructor & Destructor Documentation	2286
6.460.2.1 KeepAliveInfoMarshaller	2286
6.460.2.2 ~KeepAliveInfoMarshaller	2286
6.460.3 Member Function Documentation	2286
6.460.3.1 createObject	2286
6.460.3.2 getDataStructureType	2286
6.460.3.3 looseMarshal	2286
6.460.3.4 looseUnmarshal	2287
6.460.3.5 tightMarshal1	2287
6.460.3.6 tightMarshal2	2287
6.460.3.7 tightUnmarshal	2288
6.461activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller Class Reference	2289
6.461.1 Detailed Description	2289
6.461.2 Constructor & Destructor Documentation	2290
6.461.2.1 KeepAliveInfoMarshaller	2290
6.461.2.2 ~KeepAliveInfoMarshaller	2290
6.461.3 Member Function Documentation	2290
6.461.3.1 createObject	2290
6.461.3.2 getDataStructureType	2290
6.461.3.3 looseMarshal	2290
6.461.3.4 looseUnmarshal	2291
6.461.3.5 tightMarshal1	2291
6.461.3.6 tightMarshal2	2291
6.461.3.7 tightUnmarshal	2292
6.462decaf::security::Key Class Reference	2293

6.462.1 Detailed Description	2293
6.462.2 Constructor & Destructor Documentation	2294
6.462.2.1 ~Key	2294
6.462.3 Member Function Documentation	2294
6.462.3.1 getAlgorithm	2294
6.462.3.2 getEncoded	2294
6.462.3.3 getFormat	2294
6.463decaf::security::KeyException Class Reference	2295
6.463.1 Constructor & Destructor Documentation	2295
6.463.1.1 KeyException	2295
6.463.1.2 KeyException	2295
6.463.1.3 KeyException	2296
6.463.1.4 KeyException	2296
6.463.1.5 KeyException	2296
6.463.1.6 KeyException	2296
6.463.1.7 ~KeyException	2297
6.463.2 Member Function Documentation	2297
6.463.2.1 clone	2297
6.464decaf::security::KeyManagementException Class Reference	2298
6.464.1 Constructor & Destructor Documentation	2298
6.464.1.1 KeyManagementException	2298
6.464.1.2 KeyManagementException	2298
6.464.1.3 KeyManagementException	2299
6.464.1.4 KeyManagementException	2299
6.464.1.5 KeyManagementException	2299
6.464.1.6 KeyManagementException	2299
6.464.1.7 ~KeyManagementException	2300
6.464.2 Member Function Documentation	2300
6.464.2.1 clone	2300
6.465activemq::commands::LastPartialCommand Class Reference	2301
6.465.1 Constructor & Destructor Documentation	2301
6.465.1.1 LastPartialCommand	2301
6.465.1.2 ~LastPartialCommand	2301
6.465.2 Member Function Documentation	2301
6.465.2.1 cloneDataStructure	2301
6.465.2.2 copyDataStructure	2302

6.465.2.3 equals	2302
6.465.2.4 getDataStructureType	2302
6.465.2.5 toString	2302
6.465.3 Field Documentation	2303
6.465.3.1 ID_LASTPARTIALCOMMAND	2303
6.466activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller	
Class Reference	2304
6.466.1 Detailed Description	2304
6.466.2 Constructor & Destructor Documentation	2305
6.466.2.1 LastPartialCommandMarshaller	2305
6.466.2.2 ~LastPartialCommandMarshaller	2305
6.466.3 Member Function Documentation	2305
6.466.3.1 createObject	2305
6.466.3.2 getDataStructureType	2305
6.466.3.3 looseMarshal	2305
6.466.3.4 looseUnmarshal	2306
6.466.3.5 tightMarshal1	2306
6.466.3.6 tightMarshal2	2307
6.466.3.7 tightUnmarshal	2307
6.467activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	
Class Reference	2308
6.467.1 Detailed Description	2308
6.467.2 Constructor & Destructor Documentation	2309
6.467.2.1 LastPartialCommandMarshaller	2309
6.467.2.2 ~LastPartialCommandMarshaller	2309
6.467.3 Member Function Documentation	2309
6.467.3.1 createObject	2309
6.467.3.2 getDataStructureType	2309
6.467.3.3 looseMarshal	2309
6.467.3.4 looseUnmarshal	2310
6.467.3.5 tightMarshal1	2310
6.467.3.6 tightMarshal2	2311
6.467.3.7 tightUnmarshal	2311
6.468activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller	
Class Reference	2312
6.468.1 Detailed Description	2312
6.468.2 Constructor & Destructor Documentation	2313

6.468.2.1 LastPartialCommandMarshaller	2313
6.468.2.2 ~LastPartialCommandMarshaller	2313
6.468.3 Member Function Documentation	2313
6.468.3.1 createObject	2313
6.468.3.2 getDataStructureType	2313
6.468.3.3 looseMarshal	2313
6.468.3.4 looseUnmarshal	2314
6.468.3.5 tightMarshal1	2314
6.468.3.6 tightMarshal2	2315
6.468.3.7 tightUnmarshal	2315
6.469activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller	
Class Reference	2316
6.469.1 Detailed Description	2316
6.469.2 Constructor & Destructor Documentation	2317
6.469.2.1 LastPartialCommandMarshaller	2317
6.469.2.2 ~LastPartialCommandMarshaller	2317
6.469.3 Member Function Documentation	2317
6.469.3.1 createObject	2317
6.469.3.2 getDataStructureType	2317
6.469.3.3 looseMarshal	2317
6.469.3.4 looseUnmarshal	2318
6.469.3.5 tightMarshal1	2318
6.469.3.6 tightMarshal2	2319
6.469.3.7 tightUnmarshal	2319
6.470activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller	
Class Reference	2320
6.470.1 Detailed Description	2320
6.470.2 Constructor & Destructor Documentation	2321
6.470.2.1 LastPartialCommandMarshaller	2321
6.470.2.2 ~LastPartialCommandMarshaller	2321
6.470.3 Member Function Documentation	2321
6.470.3.1 createObject	2321
6.470.3.2 getDataStructureType	2321
6.470.3.3 looseMarshal	2321
6.470.3.4 looseUnmarshal	2322
6.470.3.5 tightMarshal1	2322
6.470.3.6 tightMarshal2	2323

6.470.3.7 tightUnmarshal	2323
6.471activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller	
Class Reference	2324
6.471.1 Detailed Description	2324
6.471.2 Constructor & Destructor Documentation	2325
6.471.2.1 LastPartialCommandMarshaller	2325
6.471.2.2 ~LastPartialCommandMarshaller	2325
6.471.3 Member Function Documentation	2325
6.471.3.1 createObject	2325
6.471.3.2 getDataStructureType	2325
6.471.3.3 looseMarshal	2325
6.471.3.4 looseUnmarshal	2326
6.471.3.5 tightMarshal1	2326
6.471.3.6 tightMarshal2	2327
6.471.3.7 tightUnmarshal	2327
6.472decaf::util::comparators::Less< E > Class Template Reference	2328
6.472.1 Detailed Description	2328
6.472.2 Constructor & Destructor Documentation	2328
6.472.2.1 Less	2328
6.472.2.2 ~Less	2328
6.472.3 Member Function Documentation	2328
6.472.3.1 compare	2328
6.472.3.2 operator()	2329
6.473std::less< decaf::lang::ArrayPointer< T > > Struct Template Reference	2330
6.473.1 Detailed Description	2330
6.473.2 Member Function Documentation	2330
6.473.2.1 operator()	2330
6.474std::less< decaf::lang::Pointer< T > > Struct Template Reference	2331
6.474.1 Detailed Description	2331
6.474.2 Member Function Documentation	2331
6.474.2.1 operator()	2331
6.475decaf::util::logging::Level Class Reference	2332
6.475.1 Detailed Description	2333
6.475.2 Constructor & Destructor Documentation	2333
6.475.2.1 Level	2333
6.475.2.2 ~Level	2334
6.475.3 Member Function Documentation	2334

6.475.3.1 compareTo	2334
6.475.3.2 equals	2334
6.475.3.3 getName	2334
6.475.3.4 intValue	2334
6.475.3.5 operator<	2334
6.475.3.6 operator==	2334
6.475.3.7 parse	2334
6.475.3.8 toString	2335
6.475.4 Field Documentation	2335
6.475.4.1 ALL	2335
6.475.4.2 CONFIG	2335
6.475.4.3 DEBUG	2335
6.475.4.4 FINE	2335
6.475.4.5 FINER	2335
6.475.4.6 FINEST	2336
6.475.4.7 INFO	2336
6.475.4.8 INHERIT	2336
6.475.4.9 OFF	2336
6.475.4.10 SEVERE	2336
6.475.4.11 WARNING	2336
6.476 decaf::util::List< E > Class Template Reference	2337
6.476.1 Detailed Description	2338
6.476.2 Constructor & Destructor Documentation	2338
6.476.2.1 List	2338
6.476.2.2 ~List	2338
6.476.3 Member Function Documentation	2338
6.476.3.1 add	2338
6.476.3.2 addAll	2339
6.476.3.3 get	2339
6.476.3.4 indexOf	2340
6.476.3.5 lastIndexOf	2340
6.476.3.6 listIterator	2341
6.476.3.7 listIterator	2341
6.476.3.8 listIterator	2341
6.476.3.9 listIterator	2342
6.476.3.10 remove	2342

6.476.3.1	set	2342
6.477	decaf::util::ListIterator< E > Class Template Reference	2344
6.477.1	Detailed Description	2344
6.477.2	Constructor & Destructor Documentation	2345
6.477.2.1	~ListIterator	2345
6.477.3	Member Function Documentation	2345
6.477.3.1	add	2345
6.477.3.2	hasPrevious	2345
6.477.3.3	nextIndex	2345
6.477.3.4	previous	2346
6.477.3.5	previousIndex	2346
6.477.3.6	set	2346
6.478	activemq::commands::LocalTransactionId Class Reference	2347
6.478.1	Member Typedef Documentation	2348
6.478.1.1	COMPARATOR	2348
6.478.2	Constructor & Destructor Documentation	2348
6.478.2.1	LocalTransactionId	2348
6.478.2.2	LocalTransactionId	2348
6.478.2.3	~LocalTransactionId	2348
6.478.3	Member Function Documentation	2348
6.478.3.1	cloneDataStructure	2348
6.478.3.2	compareTo	2348
6.478.3.3	copyDataStructure	2348
6.478.3.4	equals	2349
6.478.3.5	equals	2349
6.478.3.6	getConnectionId	2349
6.478.3.7	getConnectionId	2349
6.478.3.8	getDataStructureType	2349
6.478.3.9	getValue	2349
6.478.3.10	operator<	2349
6.478.3.11	operator=	2349
6.478.3.12	operator==	2350
6.478.3.13	setConnectionId	2350
6.478.3.14	setValue	2350
6.478.3.15	toString	2350
6.478.4	Field Documentation	2350

6.478.4.1	connectionId	2350
6.478.4.2	ID_LOCALTRANSACTIONID	2350
6.478.4.3	value	2350
6.479	activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller Class	
	Reference	2351
6.479.1	Detailed Description	2351
6.479.2	Constructor & Destructor Documentation	2352
6.479.2.1	LocalTransactionIdMarshaller	2352
6.479.2.2	~LocalTransactionIdMarshaller	2352
6.479.3	Member Function Documentation	2352
6.479.3.1	createObject	2352
6.479.3.2	getDataStructureType	2352
6.479.3.3	looseMarshal	2352
6.479.3.4	looseUnmarshal	2353
6.479.3.5	tightMarshal1	2353
6.479.3.6	tightMarshal2	2353
6.479.3.7	tightUnmarshal	2354
6.480	activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller Class	
	Reference	2355
6.480.1	Detailed Description	2355
6.480.2	Constructor & Destructor Documentation	2356
6.480.2.1	LocalTransactionIdMarshaller	2356
6.480.2.2	~LocalTransactionIdMarshaller	2356
6.480.3	Member Function Documentation	2356
6.480.3.1	createObject	2356
6.480.3.2	getDataStructureType	2356
6.480.3.3	looseMarshal	2356
6.480.3.4	looseUnmarshal	2357
6.480.3.5	tightMarshal1	2357
6.480.3.6	tightMarshal2	2357
6.480.3.7	tightUnmarshal	2358
6.481	activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller Class	
	Reference	2359
6.481.1	Detailed Description	2359
6.481.2	Constructor & Destructor Documentation	2360
6.481.2.1	LocalTransactionIdMarshaller	2360
6.481.2.2	~LocalTransactionIdMarshaller	2360

6.481.3 Member Function Documentation	2360
6.481.3.1 createObject	2360
6.481.3.2 getDataStructureType	2360
6.481.3.3 looseMarshal	2360
6.481.3.4 looseUnmarshal	2361
6.481.3.5 tightMarshal1	2361
6.481.3.6 tightMarshal2	2361
6.481.3.7 tightUnmarshal	2362
6.482activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller Class	
Reference	2363
6.482.1 Detailed Description	2363
6.482.2 Constructor & Destructor Documentation	2364
6.482.2.1 LocalTransactionIdMarshaller	2364
6.482.2.2 ~LocalTransactionIdMarshaller	2364
6.482.3 Member Function Documentation	2364
6.482.3.1 createObject	2364
6.482.3.2 getDataStructureType	2364
6.482.3.3 looseMarshal	2364
6.482.3.4 looseUnmarshal	2365
6.482.3.5 tightMarshal1	2365
6.482.3.6 tightMarshal2	2365
6.482.3.7 tightUnmarshal	2366
6.483activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller Class	
Reference	2367
6.483.1 Detailed Description	2367
6.483.2 Constructor & Destructor Documentation	2368
6.483.2.1 LocalTransactionIdMarshaller	2368
6.483.2.2 ~LocalTransactionIdMarshaller	2368
6.483.3 Member Function Documentation	2368
6.483.3.1 createObject	2368
6.483.3.2 getDataStructureType	2368
6.483.3.3 looseMarshal	2368
6.483.3.4 looseUnmarshal	2369
6.483.3.5 tightMarshal1	2369
6.483.3.6 tightMarshal2	2369
6.483.3.7 tightUnmarshal	2370

6.484activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller	Class	
Reference		2371
6.484.1 Detailed Description		2371
6.484.2 Constructor & Destructor Documentation		2372
6.484.2.1 LocalTransactionIdMarshaller		2372
6.484.2.2 ~LocalTransactionIdMarshaller		2372
6.484.3 Member Function Documentation		2372
6.484.3.1 createObject		2372
6.484.3.2 getDataStructureType		2372
6.484.3.3 looseMarshal		2372
6.484.3.4 looseUnmarshal		2373
6.484.3.5 tightMarshal1		2373
6.484.3.6 tightMarshal2		2373
6.484.3.7 tightUnmarshal		2374
6.485decaf::util::concurrent::Lock	Class Reference	2375
6.485.1 Detailed Description		2375
6.485.2 Constructor & Destructor Documentation		2375
6.485.2.1 Lock		2375
6.485.2.2 ~Lock		2375
6.485.3 Member Function Documentation		2376
6.485.3.1 isLocked		2376
6.485.3.2 lock		2376
6.485.3.3 unlock		2376
6.486decaf::util::concurrent::locks::Lock	Class Reference	2377
6.486.1 Detailed Description		2377
6.486.2 Constructor & Destructor Documentation		2378
6.486.2.1 ~Lock		2378
6.486.3 Member Function Documentation		2378
6.486.3.1 lock		2378
6.486.3.2 lockInterruptibly		2379
6.486.3.3 newCondition		2379
6.486.3.4 tryLock		2380
6.486.3.5 tryLock		2381
6.486.3.6 unlock		2381
6.487decaf::util::concurrent::locks::LockSupport	Class Reference	2383
6.487.1 Detailed Description		2383
6.487.2 Constructor & Destructor Documentation		2384

6.487.2.1 ~LockSupport	2384
6.487.3 Member Function Documentation	2384
6.487.3.1 park	2384
6.487.3.2 parkNanos	2384
6.487.3.3 parkUntil	2385
6.487.3.4 unpark	2385
6.488decaf::util::logging::Logger Class Reference	2386
6.488.1 Detailed Description	2388
6.488.2 Constructor & Destructor Documentation	2389
6.488.2.1 Logger	2389
6.488.2.2 ~Logger	2389
6.488.3 Member Function Documentation	2389
6.488.3.1 addHandler	2389
6.488.3.2 config	2390
6.488.3.3 debug	2390
6.488.3.4 entering	2390
6.488.3.5 exiting	2390
6.488.3.6 fine	2391
6.488.3.7 finer	2391
6.488.3.8 finest	2391
6.488.3.9 getAnonymousLogger	2391
6.488.3.10getFilter	2392
6.488.3.11getHandlers	2392
6.488.3.12getLevel	2392
6.488.3.13getLogger	2392
6.488.3.14getName	2393
6.488.3.15getParent	2393
6.488.3.16getUseParentHandlers	2393
6.488.3.17info	2393
6.488.3.18sLoggable	2393
6.488.3.19log	2394
6.488.3.20log	2394
6.488.3.21log	2394
6.488.3.22log	2395
6.488.3.23removeHandler	2395
6.488.3.24setFilter	2395

6.488.3.25	setLevel	2395
6.488.3.26	setParent	2395
6.488.3.27	setUseParentHandlers	2396
6.488.3.28	severe	2396
6.488.3.29	throwing	2396
6.488.3.30	warning	2396
6.489	decaf::util::logging::LoggerHierarchy Class Reference	2398
6.489.1	Constructor & Destructor Documentation	2398
6.489.1.1	LoggerHierarchy	2398
6.489.1.2	~LoggerHierarchy	2398
6.490	activemq::io::LoggingInputStream Class Reference	2399
6.490.1	Constructor & Destructor Documentation	2399
6.490.1.1	LoggingInputStream	2399
6.490.1.2	~LoggingInputStream	2399
6.490.2	Member Function Documentation	2399
6.490.2.1	doReadArrayBounded	2399
6.490.2.2	doReadByte	2400
6.491	activemq::io::LoggingOutputStream Class Reference	2401
6.491.1	Detailed Description	2401
6.491.2	Constructor & Destructor Documentation	2401
6.491.2.1	LoggingOutputStream	2401
6.491.2.2	~LoggingOutputStream	2401
6.491.3	Member Function Documentation	2401
6.491.3.1	doWriteArrayBounded	2401
6.491.3.2	doWriteByte	2402
6.492	activemq::transport::logging::LoggingTransport Class Reference	2403
6.492.1	Detailed Description	2403
6.492.2	Constructor & Destructor Documentation	2403
6.492.2.1	LoggingTransport	2403
6.492.2.2	~LoggingTransport	2404
6.492.3	Member Function Documentation	2404
6.492.3.1	onCommand	2404
6.492.3.2	oneway	2404
6.492.3.3	request	2404
6.492.3.4	request	2405
6.493	decaf::util::logging::LogManager Class Reference	2406

6.493.1 Detailed Description	2407
6.493.2 Constructor & Destructor Documentation	2408
6.493.2.1 ~LogManager	2408
6.493.2.2 LogManager	2408
6.493.2.3 LogManager	2408
6.493.3 Member Function Documentation	2409
6.493.3.1 addLogger	2409
6.493.3.2 addPropertyChangeListener	2409
6.493.3.3 getLogger	2409
6.493.3.4 getLoggerNames	2409
6.493.3.5 getLoggerManager	2410
6.493.3.6 getProperties	2410
6.493.3.7 getProperty	2410
6.493.3.8 operator=	2410
6.493.3.9 readConfiguration	2410
6.493.3.10 readConfiguration	2411
6.493.3.11 removePropertyChangeListener	2411
6.493.3.12 reset	2411
6.493.3.13 setProperties	2411
6.493.4 Friends And Related Function Documentation	2412
6.493.4.1 decaf::lang::Runtime	2412
6.494 decaf::util::logging::LogRecord Class Reference	2413
6.494.1 Detailed Description	2414
6.494.2 Constructor & Destructor Documentation	2414
6.494.2.1 LogRecord	2414
6.494.2.2 ~LogRecord	2414
6.494.3 Member Function Documentation	2414
6.494.3.1 getLevel	2414
6.494.3.2 getLoggerName	2414
6.494.3.3 getMessage	2415
6.494.3.4 getSourceFile	2415
6.494.3.5 getSourceFunction	2415
6.494.3.6 getSourceLine	2415
6.494.3.7 getThrown	2415
6.494.3.8 getTimestamp	2415
6.494.3.9 getTreadId	2416

6.494.3.10	setLevel	2416
6.494.3.11	setLoggerName	2416
6.494.3.12	setMessage	2416
6.494.3.13	setSourceFile	2416
6.494.3.14	setSourceFunction	2416
6.494.3.15	setSourceLine	2417
6.494.3.16	setThrown	2417
6.494.3.17	setTimestamp	2417
6.494.3.18	setTreadId	2417
6.495	decaf::util::logging::LogWriter Class Reference	2418
6.495.1	Constructor & Destructor Documentation	2418
6.495.1.1	LogWriter	2418
6.495.1.2	~LogWriter	2418
6.495.2	Member Function Documentation	2418
6.495.2.1	destroy	2418
6.495.2.2	getInstance	2418
6.495.2.3	log	2419
6.495.2.4	log	2419
6.495.2.5	returnInstance	2419
6.496	decaf::lang::Long Class Reference	2420
6.496.1	Constructor & Destructor Documentation	2422
6.496.1.1	Long	2422
6.496.1.2	Long	2423
6.496.1.3	~Long	2423
6.496.2	Member Function Documentation	2423
6.496.2.1	bitCount	2423
6.496.2.2	byteValue	2423
6.496.2.3	compareTo	2423
6.496.2.4	compareTo	2424
6.496.2.5	decode	2424
6.496.2.6	doubleValue	2424
6.496.2.7	equals	2424
6.496.2.8	equals	2425
6.496.2.9	float Value	2425
6.496.2.10	highestOneBit	2425
6.496.2.11	int Value	2425

6.496.2.12	longValue	2426
6.496.2.13	lowestOneBit	2426
6.496.2.14	numberOfLeadingZeros	2426
6.496.2.15	numberOfTrailingZeros	2426
6.496.2.16	operator<	2427
6.496.2.17	operator<	2427
6.496.2.18	operator==	2427
6.496.2.19	operator==	2428
6.496.2.20	parseLong	2428
6.496.2.21	parseLong	2428
6.496.2.22	reverse	2429
6.496.2.23	reverseBytes	2429
6.496.2.24	rotateLeft	2429
6.496.2.25	rotateRight	2429
6.496.2.26	shortValue	2430
6.496.2.27	signum	2430
6.496.2.28	toBinaryString	2430
6.496.2.29	toHexString	2431
6.496.2.30	toOctalString	2431
6.496.2.31	toString	2431
6.496.2.32	toString	2431
6.496.2.33	toString	2432
6.496.2.34	valueOf	2432
6.496.2.35	valueOf	2432
6.496.2.36	valueOf	2432
6.496.3	Field Documentation	2433
6.496.3.1	MAX_VALUE	2433
6.496.3.2	MIN_VALUE	2433
6.496.3.3	SIZE	2433
6.497	decaf::internal::nio::LongArrayBuffer Class Reference	2434
6.497.1	Constructor & Destructor Documentation	2437
6.497.1.1	LongArrayBuffer	2437
6.497.1.2	LongArrayBuffer	2437
6.497.1.3	LongArrayBuffer	2438
6.497.1.4	LongArrayBuffer	2438
6.497.1.5	~LongArrayBuffer	2438

6.497.2 Member Function Documentation	2438
6.497.2.1 array	2438
6.497.2.2 arrayOffset	2439
6.497.2.3 asReadOnlyBuffer	2439
6.497.2.4 compact	2440
6.497.2.5 duplicate	2440
6.497.2.6 get	2440
6.497.2.7 get	2441
6.497.2.8 hasArray	2441
6.497.2.9 isReadOnly	2441
6.497.2.10put	2441
6.497.2.11put	2442
6.497.2.12setReadOnly	2442
6.497.2.13lice	2442
6.498decaf::nio::LongBuffer Class Reference	2444
6.498.1 Detailed Description	2446
6.498.2 Constructor & Destructor Documentation	2446
6.498.2.1 LongBuffer	2446
6.498.2.2 ~LongBuffer	2446
6.498.3 Member Function Documentation	2446
6.498.3.1 allocate	2446
6.498.3.2 array	2447
6.498.3.3 arrayOffset	2447
6.498.3.4 asReadOnlyBuffer	2447
6.498.3.5 compact	2448
6.498.3.6 compareTo	2448
6.498.3.7 duplicate	2448
6.498.3.8 equals	2448
6.498.3.9 get	2448
6.498.3.10get	2449
6.498.3.11get	2449
6.498.3.12get	2450
6.498.3.13hasArray	2450
6.498.3.14operator<	2450
6.498.3.15operator==	2450
6.498.3.16put	2450

6.498.3.17put	2451
6.498.3.18put	2451
6.498.3.19put	2452
6.498.3.20put	2452
6.498.3.21slice	2453
6.498.3.22toString	2453
6.498.3.23wrap	2453
6.498.3.24wrap	2454
6.499activemq::util::LongSequenceGenerator Class Reference	2455
6.499.1 Detailed Description	2455
6.499.2 Constructor & Destructor Documentation	2455
6.499.2.1 LongSequenceGenerator	2455
6.499.2.2 ~LongSequenceGenerator	2455
6.499.3 Member Function Documentation	2455
6.499.3.1 getLastSequenceId	2455
6.499.3.2 getNextSequenceId	2455
6.500decaf::net::MalformedURLException Class Reference	2456
6.500.1 Constructor & Destructor Documentation	2456
6.500.1.1 MalformedURLException	2456
6.500.1.2 MalformedURLException	2456
6.500.1.3 MalformedURLException	2457
6.500.1.4 MalformedURLException	2457
6.500.1.5 MalformedURLException	2457
6.500.1.6 MalformedURLException	2457
6.500.1.7 ~MalformedURLException	2458
6.500.2 Member Function Documentation	2458
6.500.2.1 clone	2458
6.501decaf::util::Map< K, V, COMPARATOR > Class Template Reference	2459
6.501.1 Detailed Description	2460
6.501.2 Constructor & Destructor Documentation	2460
6.501.2.1 Map	2460
6.501.2.2 ~Map	2460
6.501.3 Member Function Documentation	2460
6.501.3.1 clear	2460
6.501.3.2 containsKey	2461
6.501.3.3 containsValue	2462

6.501.3.4 copy	2463
6.501.3.5 equals	2463
6.501.3.6 get	2463
6.501.3.7 get	2464
6.501.3.8 isEmpty	2465
6.501.3.9 keySet	2466
6.501.3.10put	2467
6.501.3.11putAll	2468
6.501.3.12remove	2468
6.501.3.13size	2469
6.501.3.14values	2470
6.502cms::MapMessage Class Reference	2472
6.502.1 Detailed Description	2473
6.502.2 Constructor & Destructor Documentation	2474
6.502.2.1 ~MapMessage	2474
6.502.3 Member Function Documentation	2474
6.502.3.1 getBoolean	2474
6.502.3.2 getByte	2475
6.502.3.3 getBytes	2475
6.502.3.4 getChar	2475
6.502.3.5 getDouble	2476
6.502.3.6 getFloat	2476
6.502.3.7 getInt	2476
6.502.3.8 getLong	2477
6.502.3.9 getMapNames	2477
6.502.3.10getShort	2477
6.502.3.11getString	2477
6.502.3.12temExists	2478
6.502.3.13setBoolean	2478
6.502.3.14setByte	2478
6.502.3.15setBytes	2479
6.502.3.16setChar	2479
6.502.3.17setDouble	2480
6.502.3.18setFloat	2480
6.502.3.19setInt	2480
6.502.3.20setLong	2481

6.502.3.2	setShort	2481
6.502.3.2	setString	2481
6.503	decaf::util::logging::MarkBlockLogger Class Reference	2483
6.503.1	Detailed Description	2483
6.503.2	Constructor & Destructor Documentation	2483
6.503.2.1	MarkBlockLogger	2483
6.503.2.2	~MarkBlockLogger	2483
6.504	activemq::wireformat::MarshalAware Class Reference	2484
6.504.1	Constructor & Destructor Documentation	2484
6.504.1.1	~MarshalAware	2484
6.504.2	Member Function Documentation	2484
6.504.2.1	afterMarshal	2484
6.504.2.2	afterUnmarshal	2485
6.504.2.3	beforeMarshal	2485
6.504.2.4	beforeUnmarshal	2485
6.504.2.5	getMarshaledForm	2485
6.504.2.6	isMarshalAware	2486
6.504.2.7	setMarshaledForm	2486
6.505	activemq::wireformat::openwire::marshal::v6::MarshallerFactory Class Reference	2487
6.505.1	Detailed Description	2487
6.505.2	Constructor & Destructor Documentation	2487
6.505.2.1	~MarshallerFactory	2487
6.505.3	Member Function Documentation	2487
6.505.3.1	configure	2487
6.506	activemq::wireformat::openwire::marshal::v3::MarshallerFactory Class Reference	2488
6.506.1	Detailed Description	2488
6.506.2	Constructor & Destructor Documentation	2488
6.506.2.1	~MarshallerFactory	2488
6.506.3	Member Function Documentation	2488
6.506.3.1	configure	2488
6.507	activemq::wireformat::openwire::marshal::v4::MarshallerFactory Class Reference	2489
6.507.1	Detailed Description	2489
6.507.2	Constructor & Destructor Documentation	2489
6.507.2.1	~MarshallerFactory	2489
6.507.3	Member Function Documentation	2489
6.507.3.1	configure	2489

6.508	activemq::wireformat::openwire::marshal::v5::MarshallerFactory Class Reference . .	2490
6.508.1	Detailed Description	2490
6.508.2	Constructor & Destructor Documentation	2490
6.508.2.1	~MarshallerFactory	2490
6.508.3	Member Function Documentation	2490
6.508.3.1	configure	2490
6.509	activemq::wireformat::openwire::marshal::v1::MarshallerFactory Class Reference . .	2491
6.509.1	Detailed Description	2491
6.509.2	Constructor & Destructor Documentation	2491
6.509.2.1	~MarshallerFactory	2491
6.509.3	Member Function Documentation	2491
6.509.3.1	configure	2491
6.510	activemq::wireformat::openwire::marshal::v2::MarshallerFactory Class Reference . .	2492
6.510.1	Detailed Description	2492
6.510.2	Constructor & Destructor Documentation	2492
6.510.2.1	~MarshallerFactory	2492
6.510.3	Member Function Documentation	2492
6.510.3.1	configure	2492
6.511	activemq::util::MarshallingSupport Class Reference	2493
6.511.1	Constructor & Destructor Documentation	2494
6.511.1.1	MarshallingSupport	2494
6.511.1.2	~MarshallingSupport	2494
6.511.2	Member Function Documentation	2494
6.511.2.1	asciiToModifiedUtf8	2494
6.511.2.2	modifiedUtf8ToAscii	2494
6.511.2.3	readString16	2495
6.511.2.4	readString32	2495
6.511.2.5	writeString	2495
6.511.2.6	writeString16	2496
6.511.2.7	writeString32	2496
6.512	decaf::lang::Math Class Reference	2497
6.512.1	Detailed Description	2499
6.512.2	Constructor & Destructor Documentation	2499
6.512.2.1	Math	2499
6.512.2.2	~Math	2499
6.512.3	Member Function Documentation	2499

6.512.3.1 abs	2499
6.512.3.2 abs	2499
6.512.3.3 abs	2499
6.512.3.4 abs	2500
6.512.3.5 ceil	2500
6.512.3.6 floor	2501
6.512.3.7 max	2501
6.512.3.8 max	2502
6.512.3.9 max	2502
6.512.3.10max	2502
6.512.3.11max	2503
6.512.3.12min	2503
6.512.3.13min	2503
6.512.3.14min	2503
6.512.3.15min	2504
6.512.3.16min	2504
6.512.3.17min	2504
6.512.3.18pow	2505
6.512.3.19random	2505
6.512.3.20round	2506
6.512.3.21round	2506
6.512.3.22signum	2507
6.512.3.23signum	2507
6.512.3.24qrt	2508
6.512.3.25toDegrees	2511
6.512.3.26toRadians	2511
6.512.4 Field Documentation	2511
6.512.4.1 E	2511
6.512.4.2 PI	2511
6.513activemq::util::MemoryUsage Class Reference	2512
6.513.1 Constructor & Destructor Documentation	2513
6.513.1.1 MemoryUsage	2513
6.513.1.2 MemoryUsage	2513
6.513.1.3 ~MemoryUsage	2513
6.513.2 Member Function Documentation	2513
6.513.2.1 decreaseUsage	2513

6.513.2.2 enqueueUsage	2513
6.513.2.3 getLimit	2513
6.513.2.4 getUsage	2514
6.513.2.5 increaseUsage	2514
6.513.2.6 isFull	2514
6.513.2.7 setLimit	2514
6.513.2.8 setUsage	2514
6.513.2.9 waitForSpace	2514
6.513.2.10waitForSpace	2515
6.514activemq::commands::Message Class Reference	2516
6.514.1 Constructor & Destructor Documentation	2520
6.514.1.1 Message	2520
6.514.1.2 ~Message	2520
6.514.2 Member Function Documentation	2520
6.514.2.1 afterUnmarshal	2520
6.514.2.2 beforeMarshal	2520
6.514.2.3 cloneDataStructure	2520
6.514.2.4 copyDataStructure	2521
6.514.2.5 equals	2521
6.514.2.6 getAckHandler	2522
6.514.2.7 getArrival	2522
6.514.2.8 getBrokerInTime	2522
6.514.2.9 getBrokerOutTime	2522
6.514.2.10getBrokerPath	2522
6.514.2.11getBrokerPath	2522
6.514.2.12getCluster	2522
6.514.2.13getCluster	2522
6.514.2.14getConnection	2522
6.514.2.15getContent	2523
6.514.2.16getContent	2523
6.514.2.17getCorrelationId	2523
6.514.2.18getCorrelationId	2523
6.514.2.19getDataStructure	2523
6.514.2.20getDataStructure	2523
6.514.2.21getDataStructureType	2523
6.514.2.22getDestination	2524

6.514.2.23	getDestination	2524
6.514.2.24	getExpiration	2524
6.514.2.25	getGroupID	2524
6.514.2.26	getGroupID	2524
6.514.2.27	getGroupSequence	2524
6.514.2.28	getMarshaledProperties	2524
6.514.2.29	getMarshaledProperties	2524
6.514.2.30	getMessageId	2524
6.514.2.31	getMessageId	2524
6.514.2.32	getMessageProperties	2524
6.514.2.33	getMessageProperties	2524
6.514.2.34	getOriginalDestination	2525
6.514.2.35	getOriginalDestination	2525
6.514.2.36	getOriginalTransactionId	2525
6.514.2.37	getOriginalTransactionId	2525
6.514.2.38	getPriority	2525
6.514.2.39	getProducerId	2525
6.514.2.40	getProducerId	2525
6.514.2.41	getRedeliveryCounter	2525
6.514.2.42	getReplyTo	2525
6.514.2.43	getReplyTo	2525
6.514.2.44	getSize	2525
6.514.2.45	getTargetConsumerId	2526
6.514.2.46	getTargetConsumerId	2526
6.514.2.47	getTimestamp	2526
6.514.2.48	getTransactionId	2526
6.514.2.49	getTransactionId	2526
6.514.2.50	getType	2526
6.514.2.51	getType	2526
6.514.2.52	getUserID	2526
6.514.2.53	getUserID	2526
6.514.2.54	isCompressed	2526
6.514.2.55	isDroppable	2526
6.514.2.56	isExpired	2526
6.514.2.57	isMarshalAware	2526
6.514.2.58	isMessage	2527

6.514.2.59	isPersistent	2527
6.514.2.60	isReadOnlyBody	2527
6.514.2.61	isReadOnlyProperties	2527
6.514.2.62	isRecievedByDFBridge	2527
6.514.2.63	isSend	2527
6.514.2.64	setAckHandler	2528
6.514.2.65	setArrival	2528
6.514.2.66	setBrokerInTime	2528
6.514.2.67	setBrokerOutTime	2528
6.514.2.68	setBrokerPath	2528
6.514.2.69	setCluster	2528
6.514.2.70	setCompressed	2528
6.514.2.71	setConnection	2528
6.514.2.72	setContent	2529
6.514.2.73	setCorrelationId	2529
6.514.2.74	setDataStructure	2529
6.514.2.75	setDestination	2529
6.514.2.76	setDroppable	2529
6.514.2.77	setExpiration	2529
6.514.2.78	setGroupID	2529
6.514.2.79	setGroupSequence	2529
6.514.2.80	setMarshallledProperties	2529
6.514.2.81	setMessageId	2529
6.514.2.82	setOriginalDestination	2529
6.514.2.83	setOriginalTransactionId	2529
6.514.2.84	setPersistent	2529
6.514.2.85	setPriority	2529
6.514.2.86	setProducerId	2529
6.514.2.87	setReadOnlyBody	2529
6.514.2.88	setReadOnlyProperties	2530
6.514.2.89	setRecievedByDFBridge	2530
6.514.2.90	setRedeliveryCounter	2530
6.514.2.91	setReplyTo	2530
6.514.2.92	setTargetConsumerId	2530
6.514.2.93	setTimestamp	2530
6.514.2.94	setTransactionId	2530

6.514.2.95	set Type	2530
6.514.2.96	set UserID	2530
6.514.2.97	toString	2530
6.514.2.98	visit	2531
6.514.3	Field Documentation	2532
6.514.3.1	arrival	2532
6.514.3.2	brokerInTime	2532
6.514.3.3	brokerOutTime	2532
6.514.3.4	brokerPath	2532
6.514.3.5	cluster	2532
6.514.3.6	compressed	2532
6.514.3.7	connection	2532
6.514.3.8	content	2532
6.514.3.9	correlationId	2532
6.514.3.10	dataStructure	2532
6.514.3.11	DEFAULT_MESSAGE_SIZE	2532
6.514.3.12	destination	2532
6.514.3.13	droppable	2532
6.514.3.14	expiration	2532
6.514.3.15	groupId	2532
6.514.3.16	groupSequence	2532
6.514.3.17	ID_MESSAGE	2532
6.514.3.18	marshalledProperties	2532
6.514.3.19	messageId	2532
6.514.3.20	originalDestination	2532
6.514.3.21	originalTransactionId	2532
6.514.3.22	persistent	2532
6.514.3.23	priority	2532
6.514.3.24	producerId	2532
6.514.3.25	recievedByDFBridge	2532
6.514.3.26	redeliveryCounter	2532
6.514.3.27	replyTo	2532
6.514.3.28	targetConsumerId	2532
6.514.3.29	timestamp	2532
6.514.3.30	transactionId	2532
6.514.3.31	type	2532

6.514.3.32	userID	2532
6.515	cms::Message Class Reference	2534
6.515.1	Detailed Description	2537
6.515.2	Constructor & Destructor Documentation	2538
6.515.2.1	~Message	2538
6.515.3	Member Function Documentation	2538
6.515.3.1	acknowledge	2538
6.515.3.2	clearBody	2539
6.515.3.3	clearProperties	2539
6.515.3.4	clone	2539
6.515.3.5	getBooleanProperty	2540
6.515.3.6	getByteProperty	2540
6.515.3.7	getCMSCorrelationID	2541
6.515.3.8	getCMSDeliveryMode	2541
6.515.3.9	getCMSDestination	2541
6.515.3.10	getCMSExpiration	2542
6.515.3.11	getCMSMessageID	2542
6.515.3.12	getCMSPriority	2543
6.515.3.13	getCMSRedelivered	2544
6.515.3.14	getCMSReplyTo	2544
6.515.3.15	getCMSTimestamp	2544
6.515.3.16	getCMSType	2545
6.515.3.17	getDoubleProperty	2545
6.515.3.18	getFloatProperty	2546
6.515.3.19	getIntProperty	2546
6.515.3.20	getLongProperty	2547
6.515.3.21	getPropertyNames	2547
6.515.3.22	getShortProperty	2548
6.515.3.23	getStringProperty	2548
6.515.3.24	propertyExists	2549
6.515.3.25	setBooleanProperty	2549
6.515.3.26	setByteProperty	2550
6.515.3.27	setCMSCorrelationID	2550
6.515.3.28	setCMSDeliveryMode	2551
6.515.3.29	setCMSDestination	2551
6.515.3.30	setCMSExpiration	2552

6.515.3.31	setCMSMessageID	2552
6.515.3.32	setCMSPriority	2552
6.515.3.33	setCMSRedelivered	2553
6.515.3.34	setCMSReplyTo	2553
6.515.3.35	setCMSTimestamp	2554
6.515.3.36	setCMSType	2554
6.515.3.37	setDoubleProperty	2555
6.515.3.38	setFloatProperty	2555
6.515.3.39	setIntProperty	2556
6.515.3.40	setLongProperty	2556
6.515.3.41	setShortProperty	2557
6.515.3.42	setStringProperty	2557
6.516	activemq::commands::MessageAck Class Reference	2559
6.516.1	Constructor & Destructor Documentation	2560
6.516.1.1	MessageAck	2560
6.516.1.2	~MessageAck	2560
6.516.2	Member Function Documentation	2560
6.516.2.1	cloneDataStructure	2560
6.516.2.2	copyDataStructure	2560
6.516.2.3	equals	2560
6.516.2.4	getAckType	2561
6.516.2.5	getConsumerId	2561
6.516.2.6	getConsumerId	2561
6.516.2.7	getDataStructureType	2561
6.516.2.8	getDestination	2562
6.516.2.9	getDestination	2562
6.516.2.10	getFirstMessageId	2562
6.516.2.11	getFirstMessageId	2562
6.516.2.12	getLastMessageId	2562
6.516.2.13	getLastMessageId	2562
6.516.2.14	getMessageCount	2562
6.516.2.15	getTransactionId	2562
6.516.2.16	getTransactionId	2562
6.516.2.17	isMessageAck	2562
6.516.2.18	setAckType	2563
6.516.2.19	setConsumerId	2563

6.516.2.20	setDestination	2563
6.516.2.21	setFirstMessageId	2563
6.516.2.22	setLastMessageId	2563
6.516.2.23	setMessageCount	2563
6.516.2.24	setTransactionId	2563
6.516.2.25	toString	2563
6.516.2.26	visit	2563
6.516.3	Field Documentation	2564
6.516.3.1	ackType	2564
6.516.3.2	consumerId	2564
6.516.3.3	destination	2564
6.516.3.4	firstMessageId	2564
6.516.3.5	ID_MESSAGEACK	2564
6.516.3.6	lastMessageId	2564
6.516.3.7	messageCount	2564
6.516.3.8	transactionId	2564
6.517	activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller Class Reference	2565
6.517.1	Detailed Description	2565
6.517.2	Constructor & Destructor Documentation	2566
6.517.2.1	MessageAckMarshaller	2566
6.517.2.2	~MessageAckMarshaller	2566
6.517.3	Member Function Documentation	2566
6.517.3.1	createObject	2566
6.517.3.2	getDataStructureType	2566
6.517.3.3	looseMarshal	2566
6.517.3.4	looseUnmarshal	2567
6.517.3.5	tightMarshal1	2567
6.517.3.6	tightMarshal2	2567
6.517.3.7	tightUnmarshal	2568
6.518	activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller Class Reference	2569
6.518.1	Detailed Description	2569
6.518.2	Constructor & Destructor Documentation	2570
6.518.2.1	MessageAckMarshaller	2570
6.518.2.2	~MessageAckMarshaller	2570
6.518.3	Member Function Documentation	2570
6.518.3.1	createObject	2570

6.518.3.2	getDataStructureType	2570
6.518.3.3	looseMarshal	2570
6.518.3.4	looseUnmarshal	2571
6.518.3.5	tightMarshal1	2571
6.518.3.6	tightMarshal2	2571
6.518.3.7	tightUnmarshal	2572
6.519	activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller Class Reference	2573
6.519.1	Detailed Description	2573
6.519.2	Constructor & Destructor Documentation	2574
6.519.2.1	MessageAckMarshaller	2574
6.519.2.2	~MessageAckMarshaller	2574
6.519.3	Member Function Documentation	2574
6.519.3.1	createObject	2574
6.519.3.2	getDataStructureType	2574
6.519.3.3	looseMarshal	2574
6.519.3.4	looseUnmarshal	2575
6.519.3.5	tightMarshal1	2575
6.519.3.6	tightMarshal2	2575
6.519.3.7	tightUnmarshal	2576
6.520	activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller Class Reference	2577
6.520.1	Detailed Description	2577
6.520.2	Constructor & Destructor Documentation	2578
6.520.2.1	MessageAckMarshaller	2578
6.520.2.2	~MessageAckMarshaller	2578
6.520.3	Member Function Documentation	2578
6.520.3.1	createObject	2578
6.520.3.2	getDataStructureType	2578
6.520.3.3	looseMarshal	2578
6.520.3.4	looseUnmarshal	2579
6.520.3.5	tightMarshal1	2579
6.520.3.6	tightMarshal2	2579
6.520.3.7	tightUnmarshal	2580
6.521	activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller Class Reference	2581
6.521.1	Detailed Description	2581
6.521.2	Constructor & Destructor Documentation	2582
6.521.2.1	MessageAckMarshaller	2582

6.521.2.2 ~MessageAckMarshaller	2582
6.521.3 Member Function Documentation	2582
6.521.3.1 createObject	2582
6.521.3.2 getDataStructureType	2582
6.521.3.3 looseMarshal	2582
6.521.3.4 looseUnmarshal	2583
6.521.3.5 tightMarshal1	2583
6.521.3.6 tightMarshal2	2583
6.521.3.7 tightUnmarshal	2584
6.522activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller Class Reference	2585
6.522.1 Detailed Description	2585
6.522.2 Constructor & Destructor Documentation	2586
6.522.2.1 MessageAckMarshaller	2586
6.522.2.2 ~MessageAckMarshaller	2586
6.522.3 Member Function Documentation	2586
6.522.3.1 createObject	2586
6.522.3.2 getDataStructureType	2586
6.522.3.3 looseMarshal	2586
6.522.3.4 looseUnmarshal	2587
6.522.3.5 tightMarshal1	2587
6.522.3.6 tightMarshal2	2587
6.522.3.7 tightUnmarshal	2588
6.523cms::MessageConsumer Class Reference	2589
6.523.1 Detailed Description	2589
6.523.2 Constructor & Destructor Documentation	2590
6.523.2.1 ~MessageConsumer	2590
6.523.3 Member Function Documentation	2590
6.523.3.1 getMessageListener	2590
6.523.3.2 getMessageSelector	2590
6.523.3.3 receive	2590
6.523.3.4 receive	2591
6.523.3.5 receiveNoWait	2591
6.523.3.6 setMessageListener	2591
6.524activemq::cmsutil::MessageCreator Class Reference	2593
6.524.1 Detailed Description	2593
6.524.2 Constructor & Destructor Documentation	2593

6.524.2.1	~MessageCreator	2593
6.524.3	Member Function Documentation	2593
6.524.3.1	createMessage	2593
6.525	activemq::commands::MessageDispatch Class Reference	2594
6.525.1	Constructor & Destructor Documentation	2595
6.525.1.1	MessageDispatch	2595
6.525.1.2	~MessageDispatch	2595
6.525.2	Member Function Documentation	2595
6.525.2.1	cloneDataStructure	2595
6.525.2.2	copyDataStructure	2595
6.525.2.3	equals	2595
6.525.2.4	getConsumerId	2596
6.525.2.5	getConsumerId	2596
6.525.2.6	getDataStructureType	2596
6.525.2.7	getDestination	2596
6.525.2.8	getDestination	2596
6.525.2.9	getMessage	2596
6.525.2.10	getMessage	2596
6.525.2.11	getRedeliveryCounter	2596
6.525.2.12	isMessageDispatch	2596
6.525.2.13	setConsumerId	2597
6.525.2.14	setDestination	2597
6.525.2.15	setMessage	2597
6.525.2.16	setRedeliveryCounter	2597
6.525.2.17	toString	2597
6.525.2.18	visit	2597
6.525.3	Field Documentation	2598
6.525.3.1	consumerId	2598
6.525.3.2	destination	2598
6.525.3.3	ID_MESSAGE_DISPATCH	2598
6.525.3.4	message	2598
6.525.3.5	redeliveryCounter	2598
6.526	activemq::core::MessageDispatchChannel Class Reference	2599
6.526.1	Constructor & Destructor Documentation	2600
6.526.1.1	MessageDispatchChannel	2600
6.526.1.2	~MessageDispatchChannel	2600

6.526.2 Member Function Documentation	2600
6.526.2.1 clear	2600
6.526.2.2 close	2600
6.526.2.3 dequeue	2601
6.526.2.4 dequeueNoWait	2601
6.526.2.5 enqueue	2601
6.526.2.6 enqueueFirst	2601
6.526.2.7 isClosed	2601
6.526.2.8 isEmpty	2602
6.526.2.9 isRunning	2602
6.526.2.10 lock	2602
6.526.2.11 notify	2602
6.526.2.12 notifyAll	2602
6.526.2.13 peek	2603
6.526.2.14 removeAll	2603
6.526.2.15 size	2603
6.526.2.16 start	2603
6.526.2.17 stop	2603
6.526.2.18 tryLock	2603
6.526.2.19 unlock	2604
6.526.2.20 wait	2604
6.526.2.21 lwait	2604
6.526.2.22 wait	2605
6.527 activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller Class	
Reference	2606
6.527.1 Detailed Description	2606
6.527.2 Constructor & Destructor Documentation	2607
6.527.2.1 MessageDispatchMarshaller	2607
6.527.2.2 ~MessageDispatchMarshaller	2607
6.527.3 Member Function Documentation	2607
6.527.3.1 createObject	2607
6.527.3.2 getDataStructureType	2607
6.527.3.3 looseMarshal	2607
6.527.3.4 looseUnmarshal	2608
6.527.3.5 tightMarshal1	2608
6.527.3.6 tightMarshal2	2608
6.527.3.7 tightUnmarshal	2609

6.528	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	Class	
	Reference		2610
6.528.1	Detailed Description		2610
6.528.2	Constructor & Destructor Documentation		2611
	6.528.2.1 MessageDispatchMarshaller		2611
	6.528.2.2 ~MessageDispatchMarshaller		2611
6.528.3	Member Function Documentation		2611
	6.528.3.1 createObject		2611
	6.528.3.2 getDataStructureType		2611
	6.528.3.3 looseMarshal		2611
	6.528.3.4 looseUnmarshal		2612
	6.528.3.5 tightMarshal1		2612
	6.528.3.6 tightMarshal2		2612
	6.528.3.7 tightUnmarshal		2613
6.529	activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller	Class	
	Reference		2614
6.529.1	Detailed Description		2614
6.529.2	Constructor & Destructor Documentation		2615
	6.529.2.1 MessageDispatchMarshaller		2615
	6.529.2.2 ~MessageDispatchMarshaller		2615
6.529.3	Member Function Documentation		2615
	6.529.3.1 createObject		2615
	6.529.3.2 getDataStructureType		2615
	6.529.3.3 looseMarshal		2615
	6.529.3.4 looseUnmarshal		2616
	6.529.3.5 tightMarshal1		2616
	6.529.3.6 tightMarshal2		2616
	6.529.3.7 tightUnmarshal		2617
6.530	activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller	Class	
	Reference		2618
6.530.1	Detailed Description		2618
6.530.2	Constructor & Destructor Documentation		2619
	6.530.2.1 MessageDispatchMarshaller		2619
	6.530.2.2 ~MessageDispatchMarshaller		2619
6.530.3	Member Function Documentation		2619
	6.530.3.1 createObject		2619
	6.530.3.2 getDataStructureType		2619

6.530.3.3 looseMarshal	2619
6.530.3.4 looseUnmarshal	2620
6.530.3.5 tightMarshal1	2620
6.530.3.6 tightMarshal2	2620
6.530.3.7 tightUnmarshal	2621
6.531activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller Class	
Reference	2622
6.531.1 Detailed Description	2622
6.531.2 Constructor & Destructor Documentation	2623
6.531.2.1 MessageDispatchMarshaller	2623
6.531.2.2 ~MessageDispatchMarshaller	2623
6.531.3 Member Function Documentation	2623
6.531.3.1 createObject	2623
6.531.3.2 getDataStructureType	2623
6.531.3.3 looseMarshal	2623
6.531.3.4 looseUnmarshal	2624
6.531.3.5 tightMarshal1	2624
6.531.3.6 tightMarshal2	2624
6.531.3.7 tightUnmarshal	2625
6.532activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller Class	
Reference	2626
6.532.1 Detailed Description	2626
6.532.2 Constructor & Destructor Documentation	2627
6.532.2.1 MessageDispatchMarshaller	2627
6.532.2.2 ~MessageDispatchMarshaller	2627
6.532.3 Member Function Documentation	2627
6.532.3.1 createObject	2627
6.532.3.2 getDataStructureType	2627
6.532.3.3 looseMarshal	2627
6.532.3.4 looseUnmarshal	2628
6.532.3.5 tightMarshal1	2628
6.532.3.6 tightMarshal2	2628
6.532.3.7 tightUnmarshal	2629
6.533activemq::commands::MessageDispatchNotification Class Reference	2630
6.533.1 Constructor & Destructor Documentation	2631
6.533.1.1 MessageDispatchNotification	2631
6.533.1.2 ~MessageDispatchNotification	2631

6.533.2 Member Function Documentation	2631
6.533.2.1 cloneDataStructure	2631
6.533.2.2 copyDataStructure	2631
6.533.2.3 equals	2631
6.533.2.4 getConsumerId	2632
6.533.2.5 getConsumerId	2632
6.533.2.6 getDataStructureType	2632
6.533.2.7 getDeliverySequenceId	2632
6.533.2.8 getDestination	2632
6.533.2.9 getDestination	2632
6.533.2.10 getMessageId	2632
6.533.2.11 getMessageId	2632
6.533.2.12 sMessageDispatchNotification	2632
6.533.2.13 setConsumerId	2633
6.533.2.14 setDeliverySequenceId	2633
6.533.2.15 setDestination	2633
6.533.2.16 setMessageId	2633
6.533.2.17 toString	2633
6.533.2.18 visit	2633
6.533.3 Field Documentation	2634
6.533.3.1 consumerId	2634
6.533.3.2 deliverySequenceId	2634
6.533.3.3 destination	2634
6.533.3.4 ID_MESSAGE_DISPATCH_NOTIFICATION	2634
6.533.3.5 messageId	2634
6.534 activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller	
Class Reference	2635
6.534.1 Detailed Description	2635
6.534.2 Constructor & Destructor Documentation	2636
6.534.2.1 MessageDispatchNotificationMarshaller	2636
6.534.2.2 ~MessageDispatchNotificationMarshaller	2636
6.534.3 Member Function Documentation	2636
6.534.3.1 createObject	2636
6.534.3.2 getDataStructureType	2636
6.534.3.3 looseMarshal	2636
6.534.3.4 looseUnmarshal	2637
6.534.3.5 tightMarshal1	2637

6.534.3.6 tightMarshal2	2637
6.534.3.7 tightUnmarshal	2638
6.535activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller	
Class Reference	2639
6.535.1 Detailed Description	2639
6.535.2 Constructor & Destructor Documentation	2640
6.535.2.1 MessageDispatchNotificationMarshaller	2640
6.535.2.2 ~MessageDispatchNotificationMarshaller	2640
6.535.3 Member Function Documentation	2640
6.535.3.1 createObject	2640
6.535.3.2 getDataStructureType	2640
6.535.3.3 looseMarshal	2640
6.535.3.4 looseUnmarshal	2641
6.535.3.5 tightMarshal1	2641
6.535.3.6 tightMarshal2	2641
6.535.3.7 tightUnmarshal	2642
6.536activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller	
Class Reference	2643
6.536.1 Detailed Description	2643
6.536.2 Constructor & Destructor Documentation	2644
6.536.2.1 MessageDispatchNotificationMarshaller	2644
6.536.2.2 ~MessageDispatchNotificationMarshaller	2644
6.536.3 Member Function Documentation	2644
6.536.3.1 createObject	2644
6.536.3.2 getDataStructureType	2644
6.536.3.3 looseMarshal	2644
6.536.3.4 looseUnmarshal	2645
6.536.3.5 tightMarshal1	2645
6.536.3.6 tightMarshal2	2645
6.536.3.7 tightUnmarshal	2646
6.537activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller	
Class Reference	2647
6.537.1 Detailed Description	2647
6.537.2 Constructor & Destructor Documentation	2648
6.537.2.1 MessageDispatchNotificationMarshaller	2648
6.537.2.2 ~MessageDispatchNotificationMarshaller	2648
6.537.3 Member Function Documentation	2648

6.537.3.1 createObject	2648
6.537.3.2 getDataStructureType	2648
6.537.3.3 looseMarshal	2648
6.537.3.4 looseUnmarshal	2649
6.537.3.5 tightMarshal1	2649
6.537.3.6 tightMarshal2	2649
6.537.3.7 tightUnmarshal	2650
6.538activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller	
Class Reference	2651
6.538.1 Detailed Description	2651
6.538.2 Constructor & Destructor Documentation	2652
6.538.2.1 MessageDispatchNotificationMarshaller	2652
6.538.2.2 ~MessageDispatchNotificationMarshaller	2652
6.538.3 Member Function Documentation	2652
6.538.3.1 createObject	2652
6.538.3.2 getDataStructureType	2652
6.538.3.3 looseMarshal	2652
6.538.3.4 looseUnmarshal	2653
6.538.3.5 tightMarshal1	2653
6.538.3.6 tightMarshal2	2653
6.538.3.7 tightUnmarshal	2654
6.539activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller	
Class Reference	2655
6.539.1 Detailed Description	2655
6.539.2 Constructor & Destructor Documentation	2656
6.539.2.1 MessageDispatchNotificationMarshaller	2656
6.539.2.2 ~MessageDispatchNotificationMarshaller	2656
6.539.3 Member Function Documentation	2656
6.539.3.1 createObject	2656
6.539.3.2 getDataStructureType	2656
6.539.3.3 looseMarshal	2656
6.539.3.4 looseUnmarshal	2657
6.539.3.5 tightMarshal1	2657
6.539.3.6 tightMarshal2	2657
6.539.3.7 tightUnmarshal	2658
6.540cms::MessageEnumeration Class Reference	2659
6.540.1 Detailed Description	2659

6.540.2 Constructor & Destructor Documentation	2659
6.540.2.1 ~MessageEnumeration	2659
6.540.3 Member Function Documentation	2659
6.540.3.1 hasMoreMessages	2659
6.540.3.2 nextMessage	2660
6.541cms::MessageEOFException Class Reference	2661
6.541.1 Detailed Description	2661
6.541.2 Constructor & Destructor Documentation	2661
6.541.2.1 MessageEOFException	2661
6.541.2.2 MessageEOFException	2661
6.541.2.3 MessageEOFException	2661
6.541.2.4 MessageEOFException	2661
6.541.2.5 ~MessageEOFException	2661
6.542cms::MessageFormatException Class Reference	2662
6.542.1 Detailed Description	2662
6.542.2 Constructor & Destructor Documentation	2662
6.542.2.1 MessageFormatException	2662
6.542.2.2 MessageFormatException	2662
6.542.2.3 MessageFormatException	2662
6.542.2.4 MessageFormatException	2662
6.542.2.5 ~MessageFormatException	2662
6.543activemq::commands::MessageId Class Reference	2663
6.543.1 Member Typedef Documentation	2664
6.543.1.1 COMPARATOR	2664
6.543.2 Constructor & Destructor Documentation	2664
6.543.2.1 MessageId	2664
6.543.2.2 MessageId	2664
6.543.2.3 MessageId	2664
6.543.2.4 MessageId	2664
6.543.2.5 MessageId	2664
6.543.2.6 MessageId	2664
6.543.2.7 ~MessageId	2664
6.543.3 Member Function Documentation	2664
6.543.3.1 cloneDataStructure	2664
6.543.3.2 compareTo	2665
6.543.3.3 copyDataStructure	2665

6.543.3.4 equals	2665
6.543.3.5 equals	2665
6.543.3.6 getBrokerSequenceId	2665
6.543.3.7 getDataStructureType	2665
6.543.3.8 getProducerId	2666
6.543.3.9 getProducerId	2666
6.543.3.10getProducerSequenceId	2666
6.543.3.11operator<	2666
6.543.3.12operator=	2666
6.543.3.13operator==	2666
6.543.3.14setBrokerSequenceId	2666
6.543.3.15setProducerId	2666
6.543.3.16setProducerSequenceId	2666
6.543.3.17set TextView	2666
6.543.3.18set Value	2666
6.543.3.19oString	2666
6.543.4 Field Documentation	2667
6.543.4.1 brokerSequenceId	2667
6.543.4.2 ID_MESSAGEID	2667
6.543.4.3 producerId	2667
6.543.4.4 producerSequenceId	2667
6.544activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller Class Reference	2668
6.544.1 Detailed Description	2668
6.544.2 Constructor & Destructor Documentation	2669
6.544.2.1 MessageIdMarshaller	2669
6.544.2.2 ~MessageIdMarshaller	2669
6.544.3 Member Function Documentation	2669
6.544.3.1 createObject	2669
6.544.3.2 getDataStructureType	2669
6.544.3.3 looseMarshal	2669
6.544.3.4 looseUnmarshal	2670
6.544.3.5 tightMarshal1	2670
6.544.3.6 tightMarshal2	2670
6.544.3.7 tightUnmarshal	2671
6.545activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller Class Reference	2672
6.545.1 Detailed Description	2672

6.545.2 Constructor & Destructor Documentation	2673
6.545.2.1 MessageIdMarshaller	2673
6.545.2.2 ~MessageIdMarshaller	2673
6.545.3 Member Function Documentation	2673
6.545.3.1 createObject	2673
6.545.3.2 getDataStructureType	2673
6.545.3.3 looseMarshal	2673
6.545.3.4 looseUnmarshal	2674
6.545.3.5 tightMarshal1	2674
6.545.3.6 tightMarshal2	2674
6.545.3.7 tightUnmarshal	2675
6.546activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller Class Reference	2676
6.546.1 Detailed Description	2676
6.546.2 Constructor & Destructor Documentation	2677
6.546.2.1 MessageIdMarshaller	2677
6.546.2.2 ~MessageIdMarshaller	2677
6.546.3 Member Function Documentation	2677
6.546.3.1 createObject	2677
6.546.3.2 getDataStructureType	2677
6.546.3.3 looseMarshal	2677
6.546.3.4 looseUnmarshal	2678
6.546.3.5 tightMarshal1	2678
6.546.3.6 tightMarshal2	2678
6.546.3.7 tightUnmarshal	2679
6.547activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller Class Reference	2680
6.547.1 Detailed Description	2680
6.547.2 Constructor & Destructor Documentation	2681
6.547.2.1 MessageIdMarshaller	2681
6.547.2.2 ~MessageIdMarshaller	2681
6.547.3 Member Function Documentation	2681
6.547.3.1 createObject	2681
6.547.3.2 getDataStructureType	2681
6.547.3.3 looseMarshal	2681
6.547.3.4 looseUnmarshal	2682
6.547.3.5 tightMarshal1	2682
6.547.3.6 tightMarshal2	2682

6.547.3.7 tightUnmarshal	2683
6.548activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller Class Reference	2684
6.548.1 Detailed Description	2684
6.548.2 Constructor & Destructor Documentation	2685
6.548.2.1 MessageIdMarshaller	2685
6.548.2.2 ~MessageIdMarshaller	2685
6.548.3 Member Function Documentation	2685
6.548.3.1 createObject	2685
6.548.3.2 getDataStructureType	2685
6.548.3.3 looseMarshal	2685
6.548.3.4 looseUnmarshal	2686
6.548.3.5 tightMarshal1	2686
6.548.3.6 tightMarshal2	2686
6.548.3.7 tightUnmarshal	2687
6.549activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller Class Reference	2688
6.549.1 Detailed Description	2688
6.549.2 Constructor & Destructor Documentation	2689
6.549.2.1 MessageIdMarshaller	2689
6.549.2.2 ~MessageIdMarshaller	2689
6.549.3 Member Function Documentation	2689
6.549.3.1 createObject	2689
6.549.3.2 getDataStructureType	2689
6.549.3.3 looseMarshal	2689
6.549.3.4 looseUnmarshal	2690
6.549.3.5 tightMarshal1	2690
6.549.3.6 tightMarshal2	2690
6.549.3.7 tightUnmarshal	2691
6.550cms::MessageListener Class Reference	2692
6.550.1 Detailed Description	2692
6.550.2 Constructor & Destructor Documentation	2692
6.550.2.1 ~MessageListener	2692
6.550.3 Member Function Documentation	2692
6.550.3.1 onMessage	2692
6.551activemq::wireformat::openwire::marshal::v5::MessageMarshaller Class Reference	2693
6.551.1 Detailed Description	2693
6.551.2 Constructor & Destructor Documentation	2694

6.551.2.1 MessageMarshaller	2694
6.551.2.2 ~MessageMarshaller	2694
6.551.3 Member Function Documentation	2694
6.551.3.1 looseMarshal	2694
6.551.3.2 looseUnmarshal	2694
6.551.3.3 tightMarshal1	2695
6.551.3.4 tightMarshal2	2696
6.551.3.5 tightUnmarshal	2696
6.552activemq::wireformat::openwire::marshal::v3::MessageMarshaller Class Reference	2698
6.552.1 Detailed Description	2698
6.552.2 Constructor & Destructor Documentation	2699
6.552.2.1 MessageMarshaller	2699
6.552.2.2 ~MessageMarshaller	2699
6.552.3 Member Function Documentation	2699
6.552.3.1 looseMarshal	2699
6.552.3.2 looseUnmarshal	2699
6.552.3.3 tightMarshal1	2700
6.552.3.4 tightMarshal2	2701
6.552.3.5 tightUnmarshal	2701
6.553activemq::wireformat::openwire::marshal::v2::MessageMarshaller Class Reference	2703
6.553.1 Detailed Description	2703
6.553.2 Constructor & Destructor Documentation	2704
6.553.2.1 MessageMarshaller	2704
6.553.2.2 ~MessageMarshaller	2704
6.553.3 Member Function Documentation	2704
6.553.3.1 looseMarshal	2704
6.553.3.2 looseUnmarshal	2704
6.553.3.3 tightMarshal1	2705
6.553.3.4 tightMarshal2	2706
6.553.3.5 tightUnmarshal	2706
6.554activemq::wireformat::openwire::marshal::v4::MessageMarshaller Class Reference	2708
6.554.1 Detailed Description	2708
6.554.2 Constructor & Destructor Documentation	2709
6.554.2.1 MessageMarshaller	2709
6.554.2.2 ~MessageMarshaller	2709
6.554.3 Member Function Documentation	2709

6.554.3.1 looseMarshal	2709
6.554.3.2 looseUnmarshal	2709
6.554.3.3 tightMarshal1	2710
6.554.3.4 tightMarshal2	2711
6.554.3.5 tightUnmarshal	2711
6.555activemq::wireformat::openwire::marshal::v1::MessageMarshaller Class Reference	2713
6.555.1 Detailed Description	2713
6.555.2 Constructor & Destructor Documentation	2714
6.555.2.1 MessageMarshaller	2714
6.555.2.2 ~MessageMarshaller	2714
6.555.3 Member Function Documentation	2714
6.555.3.1 looseMarshal	2714
6.555.3.2 looseUnmarshal	2714
6.555.3.3 tightMarshal1	2715
6.555.3.4 tightMarshal2	2716
6.555.3.5 tightUnmarshal	2716
6.556activemq::wireformat::openwire::marshal::v6::MessageMarshaller Class Reference	2718
6.556.1 Detailed Description	2718
6.556.2 Constructor & Destructor Documentation	2719
6.556.2.1 MessageMarshaller	2719
6.556.2.2 ~MessageMarshaller	2719
6.556.3 Member Function Documentation	2719
6.556.3.1 looseMarshal	2719
6.556.3.2 looseUnmarshal	2719
6.556.3.3 tightMarshal1	2720
6.556.3.4 tightMarshal2	2721
6.556.3.5 tightUnmarshal	2721
6.557cms::MessageNotReadableException Class Reference	2723
6.557.1 Detailed Description	2723
6.557.2 Constructor & Destructor Documentation	2723
6.557.2.1 MessageNotReadableException	2723
6.557.2.2 MessageNotReadableException	2723
6.557.2.3 MessageNotReadableException	2723
6.557.2.4 MessageNotReadableException	2723
6.557.2.5 ~MessageNotReadableException	2723
6.558cms::MessageNotWriteableException Class Reference	2724

6.558.1 Detailed Description	2724
6.558.2 Constructor & Destructor Documentation	2724
6.558.2.1 MessageNotWriteableException	2724
6.558.2.2 MessageNotWriteableException	2724
6.558.2.3 MessageNotWriteableException	2724
6.558.2.4 MessageNotWriteableException	2724
6.558.2.5 ~MessageNotWriteableException	2724
6.559cms::MessageProducer Class Reference	2725
6.559.1 Detailed Description	2726
6.559.2 Constructor & Destructor Documentation	2726
6.559.2.1 ~MessageProducer	2726
6.559.3 Member Function Documentation	2726
6.559.3.1 getDeliveryMode	2726
6.559.3.2 getDisableMessageID	2727
6.559.3.3 getDisableMessageTimeStamp	2727
6.559.3.4 getPriority	2727
6.559.3.5 getTimeToLive	2728
6.559.3.6 send	2728
6.559.3.7 send	2728
6.559.3.8 send	2729
6.559.3.9 send	2729
6.559.3.10setDeliveryMode	2730
6.559.3.11setDisableMessageID	2730
6.559.3.12setDisableMessageTimeStamp	2730
6.559.3.13setPriority	2731
6.559.3.14setTimeToLive	2731
6.560activemq::wireformat::openwire::utils::MessagePropertyInterceptor Class Reference	2732
6.560.1 Detailed Description	2733
6.560.2 Constructor & Destructor Documentation	2733
6.560.2.1 MessagePropertyInterceptor	2733
6.560.2.2 ~MessagePropertyInterceptor	2734
6.560.3 Member Function Documentation	2734
6.560.3.1 getBooleanProperty	2734
6.560.3.2 getByteProperty	2734
6.560.3.3 getDoubleProperty	2734
6.560.3.4 getFloatProperty	2734

6.560.3.5	getIntProperty	2735
6.560.3.6	getLongProperty	2735
6.560.3.7	getShortProperty	2735
6.560.3.8	getStringProperty	2736
6.560.3.9	setBooleanProperty	2736
6.560.3.10	setByteProperty	2736
6.560.3.11	setDoubleProperty	2736
6.560.3.12	setFloatProperty	2737
6.560.3.13	setIntProperty	2737
6.560.3.14	setLongProperty	2737
6.560.3.15	setShortProperty	2737
6.560.3.16	setStringProperty	2737
6.561	activemq::commands::MessagePull Class Reference	2739
6.561.1	Constructor & Destructor Documentation	2740
6.561.1.1	MessagePull	2740
6.561.1.2	~MessagePull	2740
6.561.2	Member Function Documentation	2740
6.561.2.1	cloneDataStructure	2740
6.561.2.2	copyDataStructure	2740
6.561.2.3	equals	2740
6.561.2.4	getConsumerId	2741
6.561.2.5	getConsumerId	2741
6.561.2.6	getCorrelationId	2741
6.561.2.7	getCorrelationId	2741
6.561.2.8	getDataStructureType	2741
6.561.2.9	getDestination	2742
6.561.2.10	getDestination	2742
6.561.2.11	getMessageId	2742
6.561.2.12	getMessageId	2742
6.561.2.13	getTimeout	2742
6.561.2.14	setConsumerId	2742
6.561.2.15	setCorrelationId	2742
6.561.2.16	setDestination	2742
6.561.2.17	setMessageId	2742
6.561.2.18	setTimeout	2742
6.561.2.19	toString	2742

6.561.2.20visit	2742
6.561.3Field Documentation	2743
6.561.3.1 consumerId	2743
6.561.3.2 correlationId	2743
6.561.3.3 destination	2743
6.561.3.4 ID_MESSAGEPULL	2743
6.561.3.5 messageId	2743
6.561.3.6 timeout	2743
6.562activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller Class Reference	2744
6.562.1 Detailed Description	2744
6.562.2 Constructor & Destructor Documentation	2745
6.562.2.1 MessagePullMarshaller	2745
6.562.2.2 ~MessagePullMarshaller	2745
6.562.3 Member Function Documentation	2745
6.562.3.1 createObject	2745
6.562.3.2 getDataStructureType	2745
6.562.3.3 looseMarshal	2745
6.562.3.4 looseUnmarshal	2746
6.562.3.5 tightMarshal1	2746
6.562.3.6 tightMarshal2	2746
6.562.3.7 tightUnmarshal	2747
6.563activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller Class Reference	2748
6.563.1 Detailed Description	2748
6.563.2 Constructor & Destructor Documentation	2749
6.563.2.1 MessagePullMarshaller	2749
6.563.2.2 ~MessagePullMarshaller	2749
6.563.3 Member Function Documentation	2749
6.563.3.1 createObject	2749
6.563.3.2 getDataStructureType	2749
6.563.3.3 looseMarshal	2749
6.563.3.4 looseUnmarshal	2750
6.563.3.5 tightMarshal1	2750
6.563.3.6 tightMarshal2	2750
6.563.3.7 tightUnmarshal	2751
6.564activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller Class Reference	2752
6.564.1 Detailed Description	2752

6.564.2 Constructor & Destructor Documentation	2753
6.564.2.1 MessagePullMarshaller	2753
6.564.2.2 ~MessagePullMarshaller	2753
6.564.3 Member Function Documentation	2753
6.564.3.1 createObject	2753
6.564.3.2 getDataStructureType	2753
6.564.3.3 looseMarshal	2753
6.564.3.4 looseUnmarshal	2754
6.564.3.5 tightMarshal1	2754
6.564.3.6 tightMarshal2	2754
6.564.3.7 tightUnmarshal	2755
6.565activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller Class Reference	2756
6.565.1 Detailed Description	2756
6.565.2 Constructor & Destructor Documentation	2757
6.565.2.1 MessagePullMarshaller	2757
6.565.2.2 ~MessagePullMarshaller	2757
6.565.3 Member Function Documentation	2757
6.565.3.1 createObject	2757
6.565.3.2 getDataStructureType	2757
6.565.3.3 looseMarshal	2757
6.565.3.4 looseUnmarshal	2758
6.565.3.5 tightMarshal1	2758
6.565.3.6 tightMarshal2	2758
6.565.3.7 tightUnmarshal	2759
6.566activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller Class Reference	2760
6.566.1 Detailed Description	2760
6.566.2 Constructor & Destructor Documentation	2761
6.566.2.1 MessagePullMarshaller	2761
6.566.2.2 ~MessagePullMarshaller	2761
6.566.3 Member Function Documentation	2761
6.566.3.1 createObject	2761
6.566.3.2 getDataStructureType	2761
6.566.3.3 looseMarshal	2761
6.566.3.4 looseUnmarshal	2762
6.566.3.5 tightMarshal1	2762
6.566.3.6 tightMarshal2	2762

6.566.3.7 tightUnmarshal	2763
6.567activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller Class Reference	2764
6.567.1 Detailed Description	2764
6.567.2 Constructor & Destructor Documentation	2765
6.567.2.1 MessagePullMarshaller	2765
6.567.2.2 ~MessagePullMarshaller	2765
6.567.3 Member Function Documentation	2765
6.567.3.1 createObject	2765
6.567.3.2 getDataStructureType	2765
6.567.3.3 looseMarshal	2765
6.567.3.4 looseUnmarshal	2766
6.567.3.5 tightMarshal1	2766
6.567.3.6 tightMarshal2	2766
6.567.3.7 tightUnmarshal	2767
6.568activemq::transport::mock::MockTransport Class Reference	2768
6.568.1 Detailed Description	2770
6.568.2 Constructor & Destructor Documentation	2770
6.568.2.1 MockTransport	2770
6.568.2.2 ~MockTransport	2770
6.568.3 Member Function Documentation	2770
6.568.3.1 close	2770
6.568.3.2 fireCommand	2771
6.568.3.3 fireException	2771
6.568.3.4 getInstance	2771
6.568.3.5 getNumReceivedMessageBeforeFail	2771
6.568.3.6 getNumReceivedMessages	2771
6.568.3.7 getNumSentKeepAlives	2771
6.568.3.8 getNumSentKeepAlivesBeforeFail	2771
6.568.3.9 getNumSentMessageBeforeFail	2771
6.568.3.10getNumSentMessages	2771
6.568.3.11getRemoteAddress	2771
6.568.3.12getTransportListener	2772
6.568.3.13getWireFormat	2772
6.568.3.14sClosed	2772
6.568.3.15sConnected	2772
6.568.3.16sFailOnClose	2773

6.568.3.17sFailOnKeepAliveSends	2773
6.568.3.18sFailOnReceiveMessage	2773
6.568.3.19sFailOnSendMessage	2773
6.568.3.20sFailOnStart	2773
6.568.3.21sFailOnStop	2773
6.568.3.22sFault Tolerant	2773
6.568.3.23narrow	2773
6.568.3.24neway	2773
6.568.3.25reconnect	2774
6.568.3.26request	2774
6.568.3.27request	2775
6.568.3.28set FailOnClose	2776
6.568.3.29set FailOnKeepAliveSends	2776
6.568.3.30set FailOnReceiveMessage	2776
6.568.3.31set FailOnSendMessage	2776
6.568.3.32set FailOnStart	2776
6.568.3.33set FailOnStop	2776
6.568.3.34set NumReceivedMessageBeforeFail	2776
6.568.3.35set NumReceivedMessages	2776
6.568.3.36set NumSentKeepAlives	2776
6.568.3.37set NumSentKeepAlivesBeforeFail	2776
6.568.3.38set NumSentMessageBeforeFail	2776
6.568.3.39set NumSentMessages	2776
6.568.3.40set OutgoingListener	2776
6.568.3.41set ResponseBuilder	2777
6.568.3.42set TransportListener	2777
6.568.3.43set WireFormat	2777
6.568.3.44start	2777
6.568.3.45stop	2777
6.569activemq::transport::mock::MockTransportFactory Class Reference	2779
6.569.1 Detailed Description	2779
6.569.2 Constructor & Destructor Documentation	2780
6.569.2.1 ~MockTransportFactory	2780
6.569.3 Member Function Documentation	2780
6.569.3.1 create	2780
6.569.3.2 createComposite	2780

6.569.3.3 doCreateComposite	2780
6.570decaf::util::concurrent::Mutex Class Reference	2782
6.570.1 Detailed Description	2783
6.570.2 Constructor & Destructor Documentation	2783
6.570.2.1 Mutex	2783
6.570.2.2 ~Mutex	2783
6.570.3 Member Function Documentation	2783
6.570.3.1 lock	2783
6.570.3.2 notify	2783
6.570.3.3 notifyAll	2784
6.570.3.4 tryLock	2784
6.570.3.5 unlock	2784
6.570.3.6 wait	2785
6.570.3.7 wait	2785
6.570.3.8 wait	2786
6.571decaf::util::concurrent::MutexHandle Class Reference	2787
6.571.1 Constructor & Destructor Documentation	2787
6.571.1.1 MutexHandle	2787
6.571.1.2 ~MutexHandle	2787
6.571.1.3 MutexHandle	2787
6.571.1.4 ~MutexHandle	2787
6.571.2 Field Documentation	2787
6.571.2.1 lock_count	2787
6.571.2.2 lock_owner	2787
6.571.2.3 mutex	2787
6.571.2.4 mutex	2787
6.572decaf::internal::util::concurrent::MutexImpl Class Reference	2788
6.572.1 Member Function Documentation	2788
6.572.1.1 create	2788
6.572.1.2 destroy	2788
6.572.1.3 lock	2789
6.572.1.4 trylock	2789
6.572.1.5 unlock	2789
6.573decaf::internal::net::Network Class Reference	2790
6.573.1 Detailed Description	2790
6.573.2 Constructor & Destructor Documentation	2791

6.573.2.1 Network	2791
6.573.2.2 ~Network	2791
6.573.3 Member Function Documentation	2791
6.573.3.1 addAsResource	2791
6.573.3.2 addNetworkResource	2791
6.573.3.3 getNetworkRuntime	2791
6.573.3.4 getRuntimeLock	2791
6.573.3.5 initializeNetworking	2791
6.573.3.6 shutdownNetworking	2792
6.574activemq::commands::NetworkBridgeFilter Class Reference	2793
6.574.1 Constructor & Destructor Documentation	2794
6.574.1.1 NetworkBridgeFilter	2794
6.574.1.2 ~NetworkBridgeFilter	2794
6.574.2 Member Function Documentation	2794
6.574.2.1 cloneDataStructure	2794
6.574.2.2 copyDataStructure	2794
6.574.2.3 equals	2794
6.574.2.4 getDataStructureType	2794
6.574.2.5 getNetworkBrokerId	2795
6.574.2.6 getNetworkBrokerId	2795
6.574.2.7 getNetworkTTL	2795
6.574.2.8 setNetworkBrokerId	2795
6.574.2.9 setNetworkTTL	2795
6.574.2.10toString	2795
6.574.3 Field Documentation	2795
6.574.3.1 ID_NETWORKBRIDGEFILTER	2795
6.574.3.2 networkBrokerId	2795
6.574.3.3 networkTTL	2795
6.575activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller Class Reference	2796
6.575.1 Detailed Description	2796
6.575.2 Constructor & Destructor Documentation	2797
6.575.2.1 NetworkBridgeFilterMarshaller	2797
6.575.2.2 ~NetworkBridgeFilterMarshaller	2797
6.575.3 Member Function Documentation	2797
6.575.3.1 createObject	2797
6.575.3.2 getDataStructureType	2797

6.575.3.3 looseMarshal	2797
6.575.3.4 looseUnmarshal	2798
6.575.3.5 tightMarshal1	2798
6.575.3.6 tightMarshal2	2798
6.575.3.7 tightUnmarshal	2799
6.576activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller Class	
Reference	2800
6.576.1 Detailed Description	2800
6.576.2 Constructor & Destructor Documentation	2801
6.576.2.1 NetworkBridgeFilterMarshaller	2801
6.576.2.2 ~NetworkBridgeFilterMarshaller	2801
6.576.3 Member Function Documentation	2801
6.576.3.1 createObject	2801
6.576.3.2 getDataStructureType	2801
6.576.3.3 looseMarshal	2801
6.576.3.4 looseUnmarshal	2802
6.576.3.5 tightMarshal1	2802
6.576.3.6 tightMarshal2	2802
6.576.3.7 tightUnmarshal	2803
6.577activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller Class	
Reference	2804
6.577.1 Detailed Description	2804
6.577.2 Constructor & Destructor Documentation	2805
6.577.2.1 NetworkBridgeFilterMarshaller	2805
6.577.2.2 ~NetworkBridgeFilterMarshaller	2805
6.577.3 Member Function Documentation	2805
6.577.3.1 createObject	2805
6.577.3.2 getDataStructureType	2805
6.577.3.3 looseMarshal	2805
6.577.3.4 looseUnmarshal	2806
6.577.3.5 tightMarshal1	2806
6.577.3.6 tightMarshal2	2806
6.577.3.7 tightUnmarshal	2807
6.578activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller Class	
Reference	2808
6.578.1 Detailed Description	2808
6.578.2 Constructor & Destructor Documentation	2809

6.578.2.1 NetworkBridgeFilterMarshaller	2809
6.578.2.2 ~NetworkBridgeFilterMarshaller	2809
6.578.3 Member Function Documentation	2809
6.578.3.1 createObject	2809
6.578.3.2 getDataStructureType	2809
6.578.3.3 looseMarshal	2809
6.578.3.4 looseUnmarshal	2810
6.578.3.5 tightMarshal1	2810
6.578.3.6 tightMarshal2	2810
6.578.3.7 tightUnmarshal	2811
6.579activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller Class	
Reference	2812
6.579.1 Detailed Description	2812
6.579.2 Constructor & Destructor Documentation	2813
6.579.2.1 NetworkBridgeFilterMarshaller	2813
6.579.2.2 ~NetworkBridgeFilterMarshaller	2813
6.579.3 Member Function Documentation	2813
6.579.3.1 createObject	2813
6.579.3.2 getDataStructureType	2813
6.579.3.3 looseMarshal	2813
6.579.3.4 looseUnmarshal	2814
6.579.3.5 tightMarshal1	2814
6.579.3.6 tightMarshal2	2814
6.579.3.7 tightUnmarshal	2815
6.580activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller Class	
Reference	2816
6.580.1 Detailed Description	2816
6.580.2 Constructor & Destructor Documentation	2817
6.580.2.1 NetworkBridgeFilterMarshaller	2817
6.580.2.2 ~NetworkBridgeFilterMarshaller	2817
6.580.3 Member Function Documentation	2817
6.580.3.1 createObject	2817
6.580.3.2 getDataStructureType	2817
6.580.3.3 looseMarshal	2817
6.580.3.4 looseUnmarshal	2818
6.580.3.5 tightMarshal1	2818
6.580.3.6 tightMarshal2	2818

6.580.3.7 tightUnmarshal	2819
6.581decaf::net::NoRouteToHostException Class Reference	2820
6.581.1 Constructor & Destructor Documentation	2820
6.581.1.1 NoRouteToHostException	2820
6.581.1.2 NoRouteToHostException	2820
6.581.1.3 NoRouteToHostException	2821
6.581.1.4 NoRouteToHostException	2821
6.581.1.5 NoRouteToHostException	2821
6.581.1.6 NoRouteToHostException	2821
6.581.1.7 ~NoRouteToHostException	2822
6.581.2 Member Function Documentation	2822
6.581.2.1 clone	2822
6.582decaf::security::NoSuchAlgorithmException Class Reference	2823
6.582.1 Constructor & Destructor Documentation	2823
6.582.1.1 NoSuchAlgorithmException	2823
6.582.1.2 NoSuchAlgorithmException	2823
6.582.1.3 NoSuchAlgorithmException	2824
6.582.1.4 NoSuchAlgorithmException	2824
6.582.1.5 NoSuchAlgorithmException	2824
6.582.1.6 NoSuchAlgorithmException	2824
6.582.1.7 ~NoSuchAlgorithmException	2825
6.582.2 Member Function Documentation	2825
6.582.2.1 clone	2825
6.583decaf::lang::exceptions::NoSuchElementException Class Reference	2826
6.583.1 Constructor & Destructor Documentation	2826
6.583.1.1 NoSuchElementException	2826
6.583.1.2 NoSuchElementException	2826
6.583.1.3 NoSuchElementException	2827
6.583.1.4 NoSuchElementException	2827
6.583.1.5 NoSuchElementException	2827
6.583.1.6 NoSuchElementException	2827
6.583.1.7 ~NoSuchElementException	2828
6.583.2 Member Function Documentation	2828
6.583.2.1 clone	2828
6.584decaf::security::NoSuchProviderException Class Reference	2829
6.584.1 Constructor & Destructor Documentation	2829

6.584.1.1 NoSuchProviderException	2829
6.584.1.2 NoSuchProviderException	2829
6.584.1.3 NoSuchProviderException	2830
6.584.1.4 NoSuchProviderException	2830
6.584.1.5 NoSuchProviderException	2830
6.584.1.6 NoSuchProviderException	2830
6.584.1.7 ~NoSuchProviderException	2831
6.584.2 Member Function Documentation	2831
6.584.2.1 clone	2831
6.585decaf::lang::exceptions::NullPointerException Class Reference	2832
6.585.1 Constructor & Destructor Documentation	2832
6.585.1.1 NullPointerException	2832
6.585.1.2 NullPointerException	2832
6.585.1.3 NullPointerException	2833
6.585.1.4 NullPointerException	2833
6.585.1.5 NullPointerException	2833
6.585.1.6 NullPointerException	2833
6.585.1.7 ~NullPointerException	2834
6.585.2 Member Function Documentation	2834
6.585.2.1 clone	2834
6.586decaf::lang::Number Class Reference	2835
6.586.1 Detailed Description	2835
6.586.2 Constructor & Destructor Documentation	2835
6.586.2.1 ~Number	2835
6.586.3 Member Function Documentation	2835
6.586.3.1 byteValue	2835
6.586.3.2 doubleValue	2836
6.586.3.3 floatValue	2836
6.586.3.4 intValue	2836
6.586.3.5 longValue	2836
6.586.3.6 shortValue	2837
6.587decaf::lang::exceptions::NumberFormatException Class Reference	2838
6.587.1 Constructor & Destructor Documentation	2838
6.587.1.1 NumberFormatException	2838
6.587.1.2 NumberFormatException	2838
6.587.1.3 NumberFormatException	2839

6.587.1.4 NumberFormatException	2839
6.587.1.5 NumberFormatException	2839
6.587.1.6 NumberFormatException	2839
6.587.1.7 ~NumberFormatException	2840
6.587.2 Member Function Documentation	2840
6.587.2.1 clone	2840
6.588cms::ObjectMessage Class Reference	2841
6.588.1 Detailed Description	2841
6.588.2 Constructor & Destructor Documentation	2841
6.588.2.1 ~ObjectMessage	2841
6.589decaf::internal::net::ssl::openssl::OpenSSLContextSpi Class Reference	2842
6.589.1 Detailed Description	2843
6.589.2 Constructor & Destructor Documentation	2843
6.589.2.1 OpenSSLContextSpi	2843
6.589.2.2 ~OpenSSLContextSpi	2843
6.589.3 Member Function Documentation	2843
6.589.3.1 providerGetServerSocketFactory	2843
6.589.3.2 providerGetSocketFactory	2843
6.589.3.3 providerInit	2844
6.589.4 Friends And Related Function Documentation	2844
6.589.4.1 OpenSSLSocket	2844
6.589.4.2 OpenSSLSocketFactory	2844
6.590decaf::internal::net::ssl::openssl::OpenSSLParameters Class Reference	2845
6.590.1 Detailed Description	2845
6.590.2 Constructor & Destructor Documentation	2845
6.590.2.1 ~OpenSSLParameters	2845
6.590.3 Member Function Documentation	2845
6.590.3.1 clone	2845
6.590.3.2 getEnabledCipherSuites	2846
6.590.3.3 getEnabledProtocols	2846
6.590.3.4 getNeedClientAuth	2846
6.590.3.5 getSupportedCipherSuites	2846
6.590.3.6 getSupportedProtocols	2846
6.590.3.7 getUseClientMode	2846
6.590.3.8 getWantClientAuth	2846
6.590.3.9 setEnabledCipherSuites	2846

6.590.3.10	setEnabledProtocols	2846
6.590.3.11	setNeedClientAuth	2846
6.590.3.12	setUseClientMode	2846
6.590.3.13	setWantClientAuth	2846
6.591	decaf::internal::net::ssl::openssl::OpenSSLServerSocket Class Reference	2847
6.591.1	Detailed Description	2848
6.591.2	Constructor & Destructor Documentation	2849
6.591.2.1	OpenSSLServerSocket	2849
6.591.2.2	~OpenSSLServerSocket	2849
6.591.3	Member Function Documentation	2849
6.591.3.1	accept	2849
6.591.3.2	setEnabledCipherSuites	2849
6.591.3.3	setEnabledProtocols	2850
6.591.3.4	getNeedClientAuth	2850
6.591.3.5	getSupportedCipherSuites	2850
6.591.3.6	getSupportedProtocols	2850
6.591.3.7	getWantClientAuth	2851
6.591.3.8	setEnabledCipherSuites	2851
6.591.3.9	setEnabledProtocols	2851
6.591.3.10	setNeedClientAuth	2851
6.591.3.11	setWantClientAuth	2852
6.592	decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory Class Reference	2853
6.592.1	Detailed Description	2854
6.592.2	Constructor & Destructor Documentation	2855
6.592.2.1	OpenSSLServerSocketFactory	2855
6.592.2.2	~OpenSSLServerSocketFactory	2855
6.592.3	Member Function Documentation	2855
6.592.3.1	createServerSocket	2855
6.592.3.2	createServerSocket	2855
6.592.3.3	createServerSocket	2856
6.592.3.4	createServerSocket	2856
6.592.3.5	getDefaultCipherSuites	2856
6.592.3.6	getSupportedCipherSuites	2857
6.593	decaf::internal::net::ssl::openssl::OpenSSLSocket Class Reference	2858
6.593.1	Detailed Description	2862
6.593.2	Constructor & Destructor Documentation	2862

6.593.2.1 OpenSSLSocket	2862
6.593.2.2 OpenSSLSocket	2862
6.593.2.3 OpenSSLSocket	2862
6.593.2.4 OpenSSLSocket	2862
6.593.2.5 OpenSSLSocket	2862
6.593.2.6 ~OpenSSLSocket	2862
6.593.3 Member Function Documentation	2862
6.593.3.1 available	2862
6.593.3.2 close	2863
6.593.3.3 connect	2863
6.593.3.4 getEnabledCipherSuites	2863
6.593.3.5 getEnabledProtocols	2864
6.593.3.6 getInputStream	2864
6.593.3.7 getNeedClientAuth	2864
6.593.3.8 getOutputStream	2865
6.593.3.9 getSupportedCipherSuites	2865
6.593.3.10getSupportedProtocols	2865
6.593.3.11getUseClientMode	2865
6.593.3.12getWantClientAuth	2866
6.593.3.13read	2866
6.593.3.14endUrgentData	2866
6.593.3.15setEnabledCipherSuites	2867
6.593.3.16setEnabledProtocols	2867
6.593.3.17setNeedClientAuth	2867
6.593.3.18setOOBInline	2868
6.593.3.19setUseClientMode	2868
6.593.3.20setWantClientAuth	2868
6.593.3.21shutdownInput	2869
6.593.3.22shutdownOutput	2869
6.593.3.23startHandshake	2869
6.593.3.24write	2869
6.594decaf::internal::net::ssl::openssl::OpenSSLSocketException Class Reference	2871
6.594.1 Detailed Description	2872
6.594.2 Constructor & Destructor Documentation	2872
6.594.2.1 OpenSSLSocketException	2872
6.594.2.2 OpenSSLSocketException	2872

6.594.2.3 OpenSSLSocketException	2872
6.594.2.4 OpenSSLSocketException	2872
6.594.2.5 OpenSSLSocketException	2873
6.594.2.6 OpenSSLSocketException	2873
6.594.2.7 OpenSSLSocketException	2873
6.594.2.8 ~OpenSSLSocketException	2873
6.594.3 Member Function Documentation	2873
6.594.3.1 clone	2873
6.594.3.2 getErrorString	2874
6.595decaf::internal::net::ssl::openssl::OpenSSLSocketFactory Class Reference	2875
6.595.1 Detailed Description	2877
6.595.2 Constructor & Destructor Documentation	2877
6.595.2.1 OpenSSLSocketFactory	2877
6.595.2.2 ~OpenSSLSocketFactory	2877
6.595.3 Member Function Documentation	2877
6.595.3.1 createSocket	2877
6.595.3.2 createSocket	2878
6.595.3.3 createSocket	2878
6.595.3.4 createSocket	2879
6.595.3.5 createSocket	2879
6.595.3.6 createSocket	2880
6.595.3.7 getDefaultCipherSuites	2880
6.595.3.8 getSupportedCipherSuites	2880
6.596decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream Class Reference	2882
6.596.1 Detailed Description	2882
6.596.2 Constructor & Destructor Documentation	2883
6.596.2.1 OpenSSLSocketInputStream	2883
6.596.2.2 ~OpenSSLSocketInputStream	2883
6.596.3 Member Function Documentation	2883
6.596.3.1 available	2883
6.596.3.2 close	2883
6.596.3.3 doReadArrayBounded	2883
6.596.3.4 doReadByte	2884
6.596.3.5 skip	2884
6.597decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream Class Reference	2885
6.597.1 Detailed Description	2885

6.597.2 Constructor & Destructor Documentation	2886
6.597.2.1 OpenSSLSocketOutputStream	2886
6.597.2.2 ~OpenSSLSocketOutputStream	2886
6.597.3 Member Function Documentation	2886
6.597.3.1 close	2886
6.597.3.2 doWriteArrayBounded	2886
6.597.3.3 doWriteByte	2886
6.598activemq::wireformat::openwire::OpenWireFormat Class Reference	2887
6.598.1 Constructor & Destructor Documentation	2890
6.598.1.1 OpenWireFormat	2890
6.598.1.2 ~OpenWireFormat	2890
6.598.2 Member Function Documentation	2890
6.598.2.1 addMarshaller	2890
6.598.2.2 createNegotiator	2890
6.598.2.3 destroyMarshalers	2890
6.598.2.4 doUnmarshal	2891
6.598.2.5 getCacheSize	2891
6.598.2.6 getMaxInactivityDuration	2891
6.598.2.7 getMaxInactivityDurationInitialDelay	2891
6.598.2.8 getPreferredWireFormatInfo	2892
6.598.2.9 getVersion	2892
6.598.2.10hasNegotiator	2892
6.598.2.11inReceive	2892
6.598.2.12sCacheEnabled	2892
6.598.2.13sSizePrefixDisabled	2893
6.598.2.14sStackTraceEnabled	2893
6.598.2.15sTcpNoDelayEnabled	2893
6.598.2.16sTightEncodingEnabled	2893
6.598.2.17ooseMarshalNestedObject	2893
6.598.2.18ooseUnmarshalNestedObject	2894
6.598.2.19marshal	2894
6.598.2.20renegotiateWireFormat	2894
6.598.2.21setCacheEnabled	2895
6.598.2.22setCacheSize	2895
6.598.2.23setMaxInactivityDuration	2895
6.598.2.24setMaxInactivityDurationInitialDelay	2895

6.598.2.25	setPreferedWireFormatInfo	2895
6.598.2.26	setSizePrefixDisabled	2896
6.598.2.27	setStackTraceEnabled	2896
6.598.2.28	setTcpNoDelayEnabled	2896
6.598.2.29	setTightEncodingEnabled	2896
6.598.2.30	setVersion	2896
6.598.2.31	tightMarshalNestedObject1	2897
6.598.2.32	tightMarshalNestedObject2	2897
6.598.2.33	tightUnmarshalNestedObject	2897
6.598.2.34	unmarshal	2898
6.598.3	Field Documentation	2898
6.598.3.1	DEFAULT_VERSION	2898
6.598.3.2	NULL_TYPE	2898
6.599	activemq::wireformat::openwire::OpenWireFormatFactory Class Reference	2899
6.599.1	Constructor & Destructor Documentation	2899
6.599.1.1	OpenWireFormatFactory	2899
6.599.1.2	~OpenWireFormatFactory	2899
6.599.2	Member Function Documentation	2899
6.599.2.1	createWireFormat	2899
6.600	activemq::wireformat::openwire::OpenWireFormatNegotiator Class Reference	2901
6.600.1	Constructor & Destructor Documentation	2901
6.600.1.1	OpenWireFormatNegotiator	2901
6.600.1.2	~OpenWireFormatNegotiator	2902
6.600.2	Member Function Documentation	2902
6.600.2.1	close	2902
6.600.2.2	onCommand	2902
6.600.2.3	oneway	2902
6.600.2.4	onTransportException	2903
6.600.2.5	request	2903
6.600.2.6	request	2903
6.600.2.7	start	2904
6.601	activemq::wireformat::openwire::OpenWireResponseBuilder Class Reference	2905
6.601.1	Constructor & Destructor Documentation	2905
6.601.1.1	OpenWireResponseBuilder	2905
6.601.1.2	~OpenWireResponseBuilder	2905
6.601.2	Member Function Documentation	2905

6.601.2.1 buildIncomingCommands	2905
6.601.2.2 buildResponse	2906
6.602decaf::io::OutputStream Class Reference	2907
6.602.1 Detailed Description	2908
6.602.2 Constructor & Destructor Documentation	2909
6.602.2.1 OutputStream	2909
6.602.2.2 ~OutputStream	2909
6.602.3 Member Function Documentation	2909
6.602.3.1 close	2909
6.602.3.2 doWriteArray	2909
6.602.3.3 doWriteArrayBounded	2909
6.602.3.4 doWriteByte	2910
6.602.3.5 flush	2910
6.602.3.6 lock	2910
6.602.3.7 notify	2910
6.602.3.8 notifyAll	2911
6.602.3.9 toString	2911
6.602.3.10tryLock	2911
6.602.3.11unlock	2911
6.602.3.12wait	2912
6.602.3.13wait	2912
6.602.3.14wait	2913
6.602.3.15write	2913
6.602.3.16write	2913
6.602.3.17write	2914
6.603decaf::io::OutputStreamWriter Class Reference	2915
6.603.1 Detailed Description	2915
6.603.2 Constructor & Destructor Documentation	2915
6.603.2.1 OutputStreamWriter	2915
6.603.2.2 ~OutputStreamWriter	2916
6.603.3 Member Function Documentation	2916
6.603.3.1 checkClosed	2916
6.603.3.2 close	2916
6.603.3.3 doWriteArrayBounded	2916
6.603.3.4 flush	2916
6.604activemq::commands::PartialCommand Class Reference	2918

6.604.1 Constructor & Destructor Documentation	2919
6.604.1.1 PartialCommand	2919
6.604.1.2 ~PartialCommand	2919
6.604.2 Member Function Documentation	2919
6.604.2.1 cloneDataStructure	2919
6.604.2.2 copyDataStructure	2919
6.604.2.3 equals	2919
6.604.2.4 getCommandId	2920
6.604.2.5 getData	2920
6.604.2.6 getData	2920
6.604.2.7 getDataStructureType	2920
6.604.2.8 setCommandId	2920
6.604.2.9 setData	2920
6.604.2.10 toString	2920
6.604.3 Field Documentation	2921
6.604.3.1 commandId	2921
6.604.3.2 data	2921
6.604.3.3 ID_PARTIALCOMMAND	2921
6.605activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller Class	
Reference	2922
6.605.1 Detailed Description	2922
6.605.2 Constructor & Destructor Documentation	2923
6.605.2.1 PartialCommandMarshaller	2923
6.605.2.2 ~PartialCommandMarshaller	2923
6.605.3 Member Function Documentation	2923
6.605.3.1 createObject	2923
6.605.3.2 getDataStructureType	2923
6.605.3.3 looseMarshal	2923
6.605.3.4 looseUnmarshal	2924
6.605.3.5 tightMarshal1	2924
6.605.3.6 tightMarshal2	2925
6.605.3.7 tightUnmarshal	2925
6.606activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller Class	
Reference	2926
6.606.1 Detailed Description	2926
6.606.2 Constructor & Destructor Documentation	2927
6.606.2.1 PartialCommandMarshaller	2927

6.606.2.2 ~PartialCommandMarshaller	2927
6.606.3 Member Function Documentation	2927
6.606.3.1 createObject	2927
6.606.3.2 getDataStructureType	2927
6.606.3.3 looseMarshal	2927
6.606.3.4 looseUnmarshal	2928
6.606.3.5 tightMarshal1	2928
6.606.3.6 tightMarshal2	2929
6.606.3.7 tightUnmarshal	2929
6.607activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller Class	
Reference	2930
6.607.1 Detailed Description	2930
6.607.2 Constructor & Destructor Documentation	2931
6.607.2.1 PartialCommandMarshaller	2931
6.607.2.2 ~PartialCommandMarshaller	2931
6.607.3 Member Function Documentation	2931
6.607.3.1 createObject	2931
6.607.3.2 getDataStructureType	2931
6.607.3.3 looseMarshal	2931
6.607.3.4 looseUnmarshal	2932
6.607.3.5 tightMarshal1	2932
6.607.3.6 tightMarshal2	2933
6.607.3.7 tightUnmarshal	2933
6.608activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller Class	
Reference	2934
6.608.1 Detailed Description	2934
6.608.2 Constructor & Destructor Documentation	2935
6.608.2.1 PartialCommandMarshaller	2935
6.608.2.2 ~PartialCommandMarshaller	2935
6.608.3 Member Function Documentation	2935
6.608.3.1 createObject	2935
6.608.3.2 getDataStructureType	2935
6.608.3.3 looseMarshal	2935
6.608.3.4 looseUnmarshal	2936
6.608.3.5 tightMarshal1	2936
6.608.3.6 tightMarshal2	2937
6.608.3.7 tightUnmarshal	2937

6.609	activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller	Class	
	Reference		2938
6.609.1	Detailed Description		2938
6.609.2	Constructor & Destructor Documentation		2939
	6.609.2.1 PartialCommandMarshaller		2939
	6.609.2.2 ~PartialCommandMarshaller		2939
6.609.3	Member Function Documentation		2939
	6.609.3.1 createObject		2939
	6.609.3.2 getDataStructureType		2939
	6.609.3.3 looseMarshal		2939
	6.609.3.4 looseUnmarshal		2940
	6.609.3.5 tightMarshal1		2940
	6.609.3.6 tightMarshal2		2941
	6.609.3.7 tightUnmarshal		2941
6.610	activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller	Class	
	Reference		2942
6.610.1	Detailed Description		2942
6.610.2	Constructor & Destructor Documentation		2943
	6.610.2.1 PartialCommandMarshaller		2943
	6.610.2.2 ~PartialCommandMarshaller		2943
6.610.3	Member Function Documentation		2943
	6.610.3.1 createObject		2943
	6.610.3.2 getDataStructureType		2943
	6.610.3.3 looseMarshal		2943
	6.610.3.4 looseUnmarshal		2944
	6.610.3.5 tightMarshal1		2944
	6.610.3.6 tightMarshal2		2945
	6.610.3.7 tightUnmarshal		2945
6.611	decaf::lang::Pointer< T, REFCOUNTER > Class Template Reference		2946
	6.611.1 Detailed Description		2947
	6.611.2 Member Typedef Documentation		2948
	6.611.2.1 CounterType		2948
	6.611.2.2 PointerType		2948
	6.611.2.3 ReferenceType		2948
	6.611.3 Constructor & Destructor Documentation		2948
	6.611.3.1 Pointer		2948
	6.611.3.2 Pointer		2948

6.611.3.3 Pointer	2948
6.611.3.4 Pointer	2949
6.611.3.5 Pointer	2949
6.611.3.6 Pointer	2949
6.611.3.7 ~Pointer	2950
6.611.4 Member Function Documentation	2950
6.611.4.1 dynamicCast	2950
6.611.4.2 get	2950
6.611.4.3 operator!	2950
6.611.4.4 operator!=	2950
6.611.4.5 operator*	2950
6.611.4.6 operator*	2950
6.611.4.7 operator->	2951
6.611.4.8 operator->	2951
6.611.4.9 operator=	2951
6.611.4.10operator=	2951
6.611.4.11operator==	2951
6.611.4.12release	2951
6.611.4.13reset	2952
6.611.4.14staticCast	2952
6.611.4.15swap	2952
6.611.5 Friends And Related Function Documentation	2953
6.611.5.1 operator!=	2953
6.611.5.2 operator!=	2953
6.611.5.3 operator==	2953
6.611.5.4 operator==	2953
6.612decaf::lang::PointerComparator< T, R > Class Template Reference	2954
6.612.1 Detailed Description	2954
6.612.2 Member Function Documentation	2954
6.612.2.1 compare	2954
6.612.2.2 operator()	2954
6.613activemq::cmsutil::PooledSession Class Reference	2955
6.613.1 Detailed Description	2957
6.613.2 Constructor & Destructor Documentation	2957
6.613.2.1 PooledSession	2957
6.613.2.2 PooledSession	2957

6.613.2.3 ~PooledSession	2957
6.613.3 Member Function Documentation	2957
6.613.3.1 close	2957
6.613.3.2 commit	2958
6.613.3.3 createBrowser	2958
6.613.3.4 createBrowser	2958
6.613.3.5 createBytesMessage	2959
6.613.3.6 createBytesMessage	2959
6.613.3.7 createCachedConsumer	2959
6.613.3.8 createCachedProducer	2960
6.613.3.9 createConsumer	2960
6.613.3.10 createConsumer	2961
6.613.3.11 createConsumer	2961
6.613.3.12 createDurableConsumer	2961
6.613.3.13 createMapMessage	2962
6.613.3.14 createMessage	2962
6.613.3.15 createProducer	2962
6.613.3.16 createQueue	2963
6.613.3.17 createStreamMessage	2963
6.613.3.18 createTemporaryQueue	2963
6.613.3.19 createTemporaryTopic	2964
6.613.3.20 createTextMessage	2964
6.613.3.21 createTextMessage	2964
6.613.3.22 createTopic	2964
6.613.3.23 getAcknowledgeMode	2965
6.613.3.24 getSession	2965
6.613.3.25 getSession	2965
6.613.3.26 isTransacted	2965
6.613.3.27 operator=	2966
6.613.3.28 recover	2966
6.613.3.29 rollback	2966
6.613.3.30 unsubscribe	2966
6.614 decaf::util::concurrent::PooledThread Class Reference	2968
6.614.1 Constructor & Destructor Documentation	2968
6.614.1.1 PooledThread	2968
6.614.1.2 ~PooledThread	2969

6.614.2 Member Function Documentation	2969
6.614.2.1 getPooledThreadListener	2969
6.614.2.2 isBusy	2969
6.614.2.3 run	2969
6.614.2.4 setPooledThreadListener	2969
6.614.2.5 stop	2969
6.615decaf::util::concurrent::PooledThreadListener Class Reference	2971
6.615.1 Detailed Description	2971
6.615.2 Constructor & Destructor Documentation	2971
6.615.2.1 ~PooledThreadListener	2971
6.615.3 Member Function Documentation	2971
6.615.3.1 onTaskCompleted	2971
6.615.3.2 onTaskException	2972
6.615.3.3 onTaskStarted	2972
6.616decaf::net::PortUnreachableException Class Reference	2973
6.616.1 Constructor & Destructor Documentation	2973
6.616.1.1 PortUnreachableException	2973
6.616.1.2 PortUnreachableException	2973
6.616.1.3 PortUnreachableException	2974
6.616.1.4 PortUnreachableException	2974
6.616.1.5 PortUnreachableException	2974
6.616.1.6 PortUnreachableException	2974
6.616.1.7 ~PortUnreachableException	2975
6.616.2 Member Function Documentation	2975
6.616.2.1 clone	2975
6.617activemq::core::PrefetchPolicy Class Reference	2976
6.617.1 Detailed Description	2977
6.617.2 Constructor & Destructor Documentation	2977
6.617.2.1 PrefetchPolicy	2977
6.617.2.2 ~PrefetchPolicy	2977
6.617.3 Member Function Documentation	2977
6.617.3.1 clone	2977
6.617.3.2 configure	2977
6.617.3.3 getDurableTopicPrefetch	2978
6.617.3.4 getMaxPrefetchLimit	2978
6.617.3.5 getQueueBrowserPrefetch	2978

6.617.3.6	getQueuePrefetch	2978
6.617.3.7	getTopicPrefetch	2978
6.617.3.8	setDurableTopicPrefetch	2979
6.617.3.9	setQueueBrowserPrefetch	2979
6.617.3.10	setQueuePrefetch	2979
6.617.3.11	setTopicPrefetch	2979
6.618	activemq::util::PrimitiveList Class Reference	2980
6.618.1	Detailed Description	2982
6.618.2	Constructor & Destructor Documentation	2982
6.618.2.1	PrimitiveList	2982
6.618.2.2	~PrimitiveList	2982
6.618.2.3	PrimitiveList	2982
6.618.2.4	PrimitiveList	2983
6.618.3	Member Function Documentation	2983
6.618.3.1	getBool	2983
6.618.3.2	getByte	2983
6.618.3.3	getByteArray	2984
6.618.3.4	getChar	2984
6.618.3.5	getDouble	2984
6.618.3.6	getFloat	2985
6.618.3.7	getInt	2985
6.618.3.8	getLong	2985
6.618.3.9	getShort	2986
6.618.3.10	getString	2986
6.618.3.11	setBool	2987
6.618.3.12	setByte	2987
6.618.3.13	setByteArray	2987
6.618.3.14	setChar	2988
6.618.3.15	setDouble	2988
6.618.3.16	setFloat	2988
6.618.3.17	setInt	2989
6.618.3.18	setLong	2989
6.618.3.19	setShort	2989
6.618.3.20	setString	2990
6.618.3.21	toString	2990
6.619	activemq::util::PrimitiveMap Class Reference	2991

6.619.1 Detailed Description	2993
6.619.2 Constructor & Destructor Documentation	2993
6.619.2.1 PrimitiveMap	2993
6.619.2.2 ~PrimitiveMap	2993
6.619.2.3 PrimitiveMap	2993
6.619.2.4 PrimitiveMap	2993
6.619.3 Member Function Documentation	2994
6.619.3.1 getBool	2994
6.619.3.2 getByte	2994
6.619.3.3 getByteArray	2994
6.619.3.4 getChar	2995
6.619.3.5 getDouble	2995
6.619.3.6 getFloat	2996
6.619.3.7 getInt	2996
6.619.3.8 getLong	2996
6.619.3.9 getShort	2997
6.619.3.10 getString	2997
6.619.3.11 setBool	2998
6.619.3.12 setByte	2998
6.619.3.13 setByteArray	2998
6.619.3.14 setChar	2998
6.619.3.15 setDouble	2998
6.619.3.16 setFloat	2999
6.619.3.17 setInt	2999
6.619.3.18 setLong	2999
6.619.3.19 setShort	2999
6.619.3.20 setString	3000
6.619.3.21 toString	3000
6.620 activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller Class Reference	3001
6.620.1 Detailed Description	3002
6.620.2 Constructor & Destructor Documentation	3003
6.620.2.1 PrimitiveTypesMarshaller	3003
6.620.2.2 ~PrimitiveTypesMarshaller	3003
6.620.3 Member Function Documentation	3003
6.620.3.1 marshal	3003
6.620.3.2 marshal	3003

6.620.3.3 marshalList	3003
6.620.3.4 marshalMap	3004
6.620.3.5 marshalPrimitive	3004
6.620.3.6 marshalPrimitiveList	3004
6.620.3.7 marshalPrimitiveMap	3005
6.620.3.8 unmarshal	3005
6.620.3.9 unmarshal	3005
6.620.3.10 unmarshalList	3006
6.620.3.11 unmarshalMap	3006
6.620.3.12 unmarshalPrimitive	3006
6.620.3.13 unmarshalPrimitiveList	3007
6.620.3.14 unmarshalPrimitiveMap	3007
6.621 activemq::util::PrimitiveValueNode::PrimitiveValue Union Reference	3008
6.621.1 Detailed Description	3008
6.621.2 Field Documentation	3009
6.621.2.1 boolValue	3009
6.621.2.2 byteArrayValue	3009
6.621.2.3 byteValue	3009
6.621.2.4 charValue	3009
6.621.2.5 doubleValue	3009
6.621.2.6 floatValue	3009
6.621.2.7 intValue	3009
6.621.2.8 listValue	3009
6.621.2.9 longValue	3009
6.621.2.10 mapValue	3009
6.621.2.11 shortValue	3009
6.621.2.12 stringValue	3009
6.622 activemq::util::PrimitiveValueConverter Class Reference	3010
6.622.1 Detailed Description	3010
6.622.2 Constructor & Destructor Documentation	3010
6.622.2.1 PrimitiveValueConverter	3010
6.622.2.2 ~PrimitiveValueConverter	3010
6.622.3 Member Function Documentation	3010
6.622.3.1 convert	3010
6.623 activemq::util::PrimitiveValueNode Class Reference	3012
6.623.1 Detailed Description	3015

6.623.2 Member Enumeration Documentation	3015
6.623.2.1 PrimitiveType	3015
6.623.3 Constructor & Destructor Documentation	3016
6.623.3.1 PrimitiveValueNode	3016
6.623.3.2 PrimitiveValueNode	3016
6.623.3.3 PrimitiveValueNode	3016
6.623.3.4 PrimitiveValueNode	3016
6.623.3.5 PrimitiveValueNode	3017
6.623.3.6 PrimitiveValueNode	3017
6.623.3.7 PrimitiveValueNode	3017
6.623.3.8 PrimitiveValueNode	3017
6.623.3.9 PrimitiveValueNode	3017
6.623.3.10 PrimitiveValueNode	3017
6.623.3.11 PrimitiveValueNode	3018
6.623.3.12 PrimitiveValueNode	3018
6.623.3.13 PrimitiveValueNode	3018
6.623.3.14 PrimitiveValueNode	3018
6.623.3.15 PrimitiveValueNode	3018
6.623.3.16 ~PrimitiveValueNode	3018
6.623.4 Member Function Documentation	3018
6.623.4.1 clear	3018
6.623.4.2 getBool	3019
6.623.4.3 getByte	3019
6.623.4.4 getByteArray	3019
6.623.4.5 getChar	3019
6.623.4.6 getDouble	3020
6.623.4.7 getFloat	3020
6.623.4.8 getInt	3020
6.623.4.9 getList	3020
6.623.4.10 getLong	3021
6.623.4.11 getMap	3021
6.623.4.12 getShort	3021
6.623.4.13 getString	3021
6.623.4.14 getType	3022
6.623.4.15 getValue	3022
6.623.4.16 operator=	3022

6.623.4.17	operator==	3022
6.623.4.18	setBool	3022
6.623.4.19	setByte	3022
6.623.4.20	setByteArray	3023
6.623.4.21	setChar	3023
6.623.4.22	setDouble	3023
6.623.4.23	setFloat	3023
6.623.4.24	setInt	3023
6.623.4.25	setList	3023
6.623.4.26	setLong	3024
6.623.4.27	setMap	3024
6.623.4.28	setShort	3024
6.623.4.29	setString	3024
6.623.4.30	setValue	3024
6.623.4.31	toString	3025
6.624	decaf::security::Principal Class Reference	3026
6.624.1	Detailed Description	3026
6.624.2	Constructor & Destructor Documentation	3026
6.624.2.1	~Principal	3026
6.624.3	Member Function Documentation	3026
6.624.3.1	equals	3026
6.624.3.2	getName	3026
6.625	decaf::util::PriorityQueue< E > Class Template Reference	3028
6.625.1	Detailed Description	3029
6.625.2	Constructor & Destructor Documentation	3030
6.625.2.1	PriorityQueue	3030
6.625.2.2	PriorityQueue	3030
6.625.2.3	PriorityQueue	3030
6.625.2.4	PriorityQueue	3030
6.625.2.5	PriorityQueue	3031
6.625.2.6	~PriorityQueue	3031
6.625.3	Member Function Documentation	3031
6.625.3.1	add	3031
6.625.3.2	clear	3031
6.625.3.3	comparator	3032
6.625.3.4	iterator	3032

6.625.3.5 iterator	3032
6.625.3.6 offer	3032
6.625.3.7 operator=	3033
6.625.3.8 operator=	3033
6.625.3.9 peek	3033
6.625.3.10 poll	3033
6.625.3.11 remove	3034
6.625.3.12 remove	3034
6.625.3.13 size	3034
6.625.4 Friends And Related Function Documentation	3035
6.625.4.1 PriorityQueueIterator	3035
6.626 activemq::commands::ProducerAck Class Reference	3036
6.626.1 Constructor & Destructor Documentation	3037
6.626.1.1 ProducerAck	3037
6.626.1.2 ~ProducerAck	3037
6.626.2 Member Function Documentation	3037
6.626.2.1 cloneDataStructure	3037
6.626.2.2 copyDataStructure	3037
6.626.2.3 equals	3037
6.626.2.4 getDataStructureType	3037
6.626.2.5 getProducerId	3038
6.626.2.6 getProducerId	3038
6.626.2.7 getSize	3038
6.626.2.8 isProducerAck	3038
6.626.2.9 setProducerId	3038
6.626.2.10 setSize	3038
6.626.2.11 toString	3038
6.626.2.12 visit	3038
6.626.3 Field Documentation	3039
6.626.3.1 ID_PRODUCERACK	3039
6.626.3.2 producerId	3039
6.626.3.3 size	3039
6.627 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller Class Reference	3040
6.627.1 Detailed Description	3040
6.627.2 Constructor & Destructor Documentation	3041
6.627.2.1 ProducerAckMarshaller	3041

6.627.2.2	~ProducerAckMarshaller	3041
6.627.3	Member Function Documentation	3041
6.627.3.1	createObject	3041
6.627.3.2	getDataStructureType	3041
6.627.3.3	looseMarshal	3041
6.627.3.4	looseUnmarshal	3042
6.627.3.5	tightMarshal1	3042
6.627.3.6	tightMarshal2	3042
6.627.3.7	tightUnmarshal	3043
6.628	activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller Class Reference	3044
6.628.1	Detailed Description	3044
6.628.2	Constructor & Destructor Documentation	3045
6.628.2.1	ProducerAckMarshaller	3045
6.628.2.2	~ProducerAckMarshaller	3045
6.628.3	Member Function Documentation	3045
6.628.3.1	createObject	3045
6.628.3.2	getDataStructureType	3045
6.628.3.3	looseMarshal	3045
6.628.3.4	looseUnmarshal	3046
6.628.3.5	tightMarshal1	3046
6.628.3.6	tightMarshal2	3046
6.628.3.7	tightUnmarshal	3047
6.629	activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller Class Reference	3048
6.629.1	Detailed Description	3048
6.629.2	Constructor & Destructor Documentation	3049
6.629.2.1	ProducerAckMarshaller	3049
6.629.2.2	~ProducerAckMarshaller	3049
6.629.3	Member Function Documentation	3049
6.629.3.1	createObject	3049
6.629.3.2	getDataStructureType	3049
6.629.3.3	looseMarshal	3049
6.629.3.4	looseUnmarshal	3050
6.629.3.5	tightMarshal1	3050
6.629.3.6	tightMarshal2	3050
6.629.3.7	tightUnmarshal	3051
6.630	activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller Class Reference	3052

6.630.1 Detailed Description	3052
6.630.2 Constructor & Destructor Documentation	3053
6.630.2.1 ProducerAckMarshaller	3053
6.630.2.2 ~ProducerAckMarshaller	3053
6.630.3 Member Function Documentation	3053
6.630.3.1 createObject	3053
6.630.3.2 getDataStructureType	3053
6.630.3.3 looseMarshal	3053
6.630.3.4 looseUnmarshal	3054
6.630.3.5 tightMarshal1	3054
6.630.3.6 tightMarshal2	3054
6.630.3.7 tightUnmarshal	3055
6.631activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller Class Reference	3056
6.631.1 Detailed Description	3056
6.631.2 Constructor & Destructor Documentation	3057
6.631.2.1 ProducerAckMarshaller	3057
6.631.2.2 ~ProducerAckMarshaller	3057
6.631.3 Member Function Documentation	3057
6.631.3.1 createObject	3057
6.631.3.2 getDataStructureType	3057
6.631.3.3 looseMarshal	3057
6.631.3.4 looseUnmarshal	3058
6.631.3.5 tightMarshal1	3058
6.631.3.6 tightMarshal2	3058
6.631.3.7 tightUnmarshal	3059
6.632activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller Class Reference	3060
6.632.1 Detailed Description	3060
6.632.2 Constructor & Destructor Documentation	3061
6.632.2.1 ProducerAckMarshaller	3061
6.632.2.2 ~ProducerAckMarshaller	3061
6.632.3 Member Function Documentation	3061
6.632.3.1 createObject	3061
6.632.3.2 getDataStructureType	3061
6.632.3.3 looseMarshal	3061
6.632.3.4 looseUnmarshal	3062
6.632.3.5 tightMarshal1	3062

6.632.3.6 tightMarshal2	3062
6.632.3.7 tightUnmarshal	3063
6.633activemq::cmsutil::ProducerCallback Class Reference	3064
6.633.1 Detailed Description	3064
6.633.2 Constructor & Destructor Documentation	3064
6.633.2.1 ~ProducerCallback	3064
6.633.3 Member Function Documentation	3064
6.633.3.1 doInCms	3064
6.634activemq::cmsutil::CmsTemplate::ProducerExecutor Class Reference	3065
6.634.1 Constructor & Destructor Documentation	3065
6.634.1.1 ProducerExecutor	3065
6.634.1.2 ProducerExecutor	3065
6.634.1.3 ~ProducerExecutor	3065
6.634.2 Member Function Documentation	3065
6.634.2.1 doInCms	3065
6.634.2.2 getDestination	3066
6.634.2.3 operator=	3066
6.634.3 Field Documentation	3066
6.634.3.1 action	3066
6.634.3.2 destination	3066
6.634.3.3 parent	3066
6.635activemq::commands::ProducerId Class Reference	3067
6.635.1 Member Typedef Documentation	3068
6.635.1.1 COMPARATOR	3068
6.635.2 Constructor & Destructor Documentation	3068
6.635.2.1 ProducerId	3068
6.635.2.2 ProducerId	3068
6.635.2.3 ProducerId	3068
6.635.2.4 ProducerId	3068
6.635.2.5 ~ProducerId	3068
6.635.3 Member Function Documentation	3068
6.635.3.1 cloneDataStructure	3068
6.635.3.2 compareTo	3068
6.635.3.3 copyDataStructure	3068
6.635.3.4 equals	3069
6.635.3.5 equals	3069

6.635.3.6	getConnectionId	3069
6.635.3.7	getConnectionId	3069
6.635.3.8	getDataStructureType	3069
6.635.3.9	getParentId	3070
6.635.3.10	getSessionId	3070
6.635.3.11	getValue	3070
6.635.3.12	operator<	3070
6.635.3.13	operator=	3070
6.635.3.14	operator==	3070
6.635.3.15	setConnectionId	3070
6.635.3.16	setProducerSessionKey	3070
6.635.3.17	setSessionId	3070
6.635.3.18	setValue	3070
6.635.3.19	toString	3070
6.635.4	Field Documentation	3070
6.635.4.1	connectionId	3070
6.635.4.2	ID_PRODUCERID	3070
6.635.4.3	sessionId	3071
6.635.4.4	value	3071
6.636	activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller Class Reference	3072
6.636.1	Detailed Description	3072
6.636.2	Constructor & Destructor Documentation	3073
6.636.2.1	ProducerIdMarshaller	3073
6.636.2.2	~ProducerIdMarshaller	3073
6.636.3	Member Function Documentation	3073
6.636.3.1	createObject	3073
6.636.3.2	getDataStructureType	3073
6.636.3.3	looseMarshal	3073
6.636.3.4	looseUnmarshal	3074
6.636.3.5	tightMarshal1	3074
6.636.3.6	tightMarshal2	3074
6.636.3.7	tightUnmarshal	3075
6.637	activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller Class Reference	3076
6.637.1	Detailed Description	3076
6.637.2	Constructor & Destructor Documentation	3077
6.637.2.1	ProducerIdMarshaller	3077

6.637.2.2	~ProducerIdMarshaller	3077
6.637.3	Member Function Documentation	3077
6.637.3.1	createObject	3077
6.637.3.2	getDataStructureType	3077
6.637.3.3	looseMarshal	3077
6.637.3.4	looseUnmarshal	3078
6.637.3.5	tightMarshal1	3078
6.637.3.6	tightMarshal2	3078
6.637.3.7	tightUnmarshal	3079
6.638	activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller Class Reference	3080
6.638.1	Detailed Description	3080
6.638.2	Constructor & Destructor Documentation	3081
6.638.2.1	ProducerIdMarshaller	3081
6.638.2.2	~ProducerIdMarshaller	3081
6.638.3	Member Function Documentation	3081
6.638.3.1	createObject	3081
6.638.3.2	getDataStructureType	3081
6.638.3.3	looseMarshal	3081
6.638.3.4	looseUnmarshal	3082
6.638.3.5	tightMarshal1	3082
6.638.3.6	tightMarshal2	3082
6.638.3.7	tightUnmarshal	3083
6.639	activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller Class Reference	3084
6.639.1	Detailed Description	3084
6.639.2	Constructor & Destructor Documentation	3085
6.639.2.1	ProducerIdMarshaller	3085
6.639.2.2	~ProducerIdMarshaller	3085
6.639.3	Member Function Documentation	3085
6.639.3.1	createObject	3085
6.639.3.2	getDataStructureType	3085
6.639.3.3	looseMarshal	3085
6.639.3.4	looseUnmarshal	3086
6.639.3.5	tightMarshal1	3086
6.639.3.6	tightMarshal2	3086
6.639.3.7	tightUnmarshal	3087
6.640	activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller Class Reference	3088

6.640.1 Detailed Description	3088
6.640.2 Constructor & Destructor Documentation	3089
6.640.2.1 ProducerIdMarshaller	3089
6.640.2.2 ~ProducerIdMarshaller	3089
6.640.3 Member Function Documentation	3089
6.640.3.1 createObject	3089
6.640.3.2 getDataStructureType	3089
6.640.3.3 looseMarshal	3089
6.640.3.4 looseUnmarshal	3090
6.640.3.5 tightMarshal1	3090
6.640.3.6 tightMarshal2	3090
6.640.3.7 tightUnmarshal	3091
6.641activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller Class Reference	3092
6.641.1 Detailed Description	3092
6.641.2 Constructor & Destructor Documentation	3093
6.641.2.1 ProducerIdMarshaller	3093
6.641.2.2 ~ProducerIdMarshaller	3093
6.641.3 Member Function Documentation	3093
6.641.3.1 createObject	3093
6.641.3.2 getDataStructureType	3093
6.641.3.3 looseMarshal	3093
6.641.3.4 looseUnmarshal	3094
6.641.3.5 tightMarshal1	3094
6.641.3.6 tightMarshal2	3094
6.641.3.7 tightUnmarshal	3095
6.642activemq::commands::ProducerInfo Class Reference	3096
6.642.1 Constructor & Destructor Documentation	3097
6.642.1.1 ProducerInfo	3097
6.642.1.2 ~ProducerInfo	3097
6.642.2 Member Function Documentation	3097
6.642.2.1 cloneDataStructure	3097
6.642.2.2 copyDataStructure	3097
6.642.2.3 createRemoveCommand	3097
6.642.2.4 equals	3097
6.642.2.5 getBrokerPath	3098
6.642.2.6 getBrokerPath	3098

6.642.2.7	getDataStructureType	3098
6.642.2.8	getDestination	3098
6.642.2.9	getDestination	3098
6.642.2.10	getProducerId	3098
6.642.2.11	getProducerId	3098
6.642.2.12	getWindowSize	3098
6.642.2.13	sDispatchAsync	3098
6.642.2.14	sProducerInfo	3098
6.642.2.15	setBrokerPath	3099
6.642.2.16	setDestination	3099
6.642.2.17	setDispatchAsync	3099
6.642.2.18	setProducerId	3099
6.642.2.19	setWindowSize	3099
6.642.2.20	toString	3099
6.642.2.21	visit	3099
6.642.3	Field Documentation	3100
6.642.3.1	brokerPath	3100
6.642.3.2	destination	3100
6.642.3.3	dispatchAsync	3100
6.642.3.4	ID_PRODUCERINFO	3100
6.642.3.5	producerId	3100
6.642.3.6	windowSize	3100
6.643	activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller Class Reference	3101
6.643.1	Detailed Description	3101
6.643.2	Constructor & Destructor Documentation	3102
6.643.2.1	ProducerInfoMarshaller	3102
6.643.2.2	~ProducerInfoMarshaller	3102
6.643.3	Member Function Documentation	3102
6.643.3.1	createObject	3102
6.643.3.2	getDataStructureType	3102
6.643.3.3	looseMarshal	3102
6.643.3.4	looseUnmarshal	3103
6.643.3.5	tightMarshal1	3103
6.643.3.6	tightMarshal2	3103
6.643.3.7	tightUnmarshal	3104

6.644activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller Class Reference	3105
6.644.1 Detailed Description	3105
6.644.2 Constructor & Destructor Documentation	3106
6.644.2.1 ProducerInfoMarshaller	3106
6.644.2.2 ~ProducerInfoMarshaller	3106
6.644.3 Member Function Documentation	3106
6.644.3.1 createObject	3106
6.644.3.2 getDataStructureType	3106
6.644.3.3 looseMarshal	3106
6.644.3.4 looseUnmarshal	3107
6.644.3.5 tightMarshal1	3107
6.644.3.6 tightMarshal2	3107
6.644.3.7 tightUnmarshal	3108
6.645activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller Class Reference	3109
6.645.1 Detailed Description	3109
6.645.2 Constructor & Destructor Documentation	3110
6.645.2.1 ProducerInfoMarshaller	3110
6.645.2.2 ~ProducerInfoMarshaller	3110
6.645.3 Member Function Documentation	3110
6.645.3.1 createObject	3110
6.645.3.2 getDataStructureType	3110
6.645.3.3 looseMarshal	3110
6.645.3.4 looseUnmarshal	3111
6.645.3.5 tightMarshal1	3111
6.645.3.6 tightMarshal2	3111
6.645.3.7 tightUnmarshal	3112
6.646activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller Class Reference	3113
6.646.1 Detailed Description	3113
6.646.2 Constructor & Destructor Documentation	3114
6.646.2.1 ProducerInfoMarshaller	3114
6.646.2.2 ~ProducerInfoMarshaller	3114
6.646.3 Member Function Documentation	3114
6.646.3.1 createObject	3114
6.646.3.2 getDataStructureType	3114

6.646.3.3 looseMarshal	3114
6.646.3.4 looseUnmarshal	3115
6.646.3.5 tightMarshal1	3115
6.646.3.6 tightMarshal2	3115
6.646.3.7 tightUnmarshal	3116
6.647activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller Class Reference	3117
6.647.1 Detailed Description	3117
6.647.2 Constructor & Destructor Documentation	3118
6.647.2.1 ProducerInfoMarshaller	3118
6.647.2.2 ~ProducerInfoMarshaller	3118
6.647.3 Member Function Documentation	3118
6.647.3.1 createObject	3118
6.647.3.2 getDataStructureType	3118
6.647.3.3 looseMarshal	3118
6.647.3.4 looseUnmarshal	3119
6.647.3.5 tightMarshal1	3119
6.647.3.6 tightMarshal2	3119
6.647.3.7 tightUnmarshal	3120
6.648activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller Class Reference	3121
6.648.1 Detailed Description	3121
6.648.2 Constructor & Destructor Documentation	3122
6.648.2.1 ProducerInfoMarshaller	3122
6.648.2.2 ~ProducerInfoMarshaller	3122
6.648.3 Member Function Documentation	3122
6.648.3.1 createObject	3122
6.648.3.2 getDataStructureType	3122
6.648.3.3 looseMarshal	3122
6.648.3.4 looseUnmarshal	3123
6.648.3.5 tightMarshal1	3123
6.648.3.6 tightMarshal2	3123
6.648.3.7 tightUnmarshal	3124
6.649activemq::state::ProducerState Class Reference	3125
6.649.1 Constructor & Destructor Documentation	3125
6.649.1.1 ProducerState	3125
6.649.1.2 ~ProducerState	3125

6.649.2 Member Function Documentation	3125
6.649.2.1 getInfo	3125
6.649.2.2 getTransactionState	3125
6.649.2.3 setTransactionState	3125
6.649.2.4 toString	3125
6.650decaf::util::Properties Class Reference	3126
6.650.1 Detailed Description	3127
6.650.2 Constructor & Destructor Documentation	3128
6.650.2.1 Properties	3128
6.650.2.2 Properties	3128
6.650.2.3 ~Properties	3128
6.650.3 Member Function Documentation	3128
6.650.3.1 clear	3128
6.650.3.2 clone	3128
6.650.3.3 copy	3128
6.650.3.4 equals	3128
6.650.3.5 getProperty	3128
6.650.3.6 getProperty	3129
6.650.3.7 hasProperty	3129
6.650.3.8 isEmpty	3129
6.650.3.9 load	3129
6.650.3.10load	3131
6.650.3.11operator=	3132
6.650.3.12propertyName	3132
6.650.3.13remove	3132
6.650.3.14setProperty	3132
6.650.3.15size	3132
6.650.3.16store	3133
6.650.3.17store	3133
6.650.3.18oArray	3134
6.650.3.19oString	3134
6.650.4 Field Documentation	3134
6.650.4.1 defaults	3134
6.651decaf::util::logging::PropertiesChangeListener Class Reference	3135
6.651.1 Detailed Description	3135
6.651.2 Constructor & Destructor Documentation	3135

6.651.2.1 ~PropertiesChangeListener	3135
6.651.3 Member Function Documentation	3135
6.651.3.1 onPropertiesReset	3135
6.651.3.2 onPropertyChanged	3135
6.652decaf::net::ProtocolException Class Reference	3137
6.652.1 Constructor & Destructor Documentation	3137
6.652.1.1 ProtocolException	3137
6.652.1.2 ProtocolException	3137
6.652.1.3 ProtocolException	3138
6.652.1.4 ProtocolException	3138
6.652.1.5 ProtocolException	3138
6.652.1.6 ProtocolException	3138
6.652.1.7 ~ProtocolException	3139
6.652.2 Member Function Documentation	3139
6.652.2.1 clone	3139
6.653decaf::security::PublicKey Class Reference	3140
6.653.1 Detailed Description	3140
6.653.2 Constructor & Destructor Documentation	3140
6.653.2.1 ~PublicKey	3140
6.654decaf::io::PushbackInputStream Class Reference	3141
6.654.1 Detailed Description	3142
6.654.2 Constructor & Destructor Documentation	3143
6.654.2.1 PushbackInputStream	3143
6.654.2.2 PushbackInputStream	3143
6.654.2.3 ~PushbackInputStream	3143
6.654.3 Member Function Documentation	3143
6.654.3.1 available	3143
6.654.3.2 doReadArrayBounded	3144
6.654.3.3 doReadByte	3144
6.654.3.4 mark	3144
6.654.3.5 markSupported	3144
6.654.3.6 reset	3145
6.654.3.7 skip	3145
6.654.3.8 unread	3146
6.654.3.9 unread	3146
6.654.3.10unread	3147

6.655	cms::Queue Class Reference	3148
6.655.1	Detailed Description	3148
6.655.2	Constructor & Destructor Documentation	3148
6.655.2.1	~Queue	3148
6.655.3	Member Function Documentation	3148
6.655.3.1	getQueueName	3148
6.656	decaf::util::Queue< E > Class Template Reference	3149
6.656.1	Detailed Description	3149
6.656.2	Constructor & Destructor Documentation	3150
6.656.2.1	~Queue	3150
6.656.3	Member Function Documentation	3150
6.656.3.1	element	3150
6.656.3.2	offer	3150
6.656.3.3	peek	3151
6.656.3.4	poll	3151
6.656.3.5	remove	3151
6.657	cms::QueueBrowser Class Reference	3153
6.657.1	Detailed Description	3153
6.657.2	Constructor & Destructor Documentation	3153
6.657.2.1	~QueueBrowser	3153
6.657.3	Member Function Documentation	3153
6.657.3.1	getEnumeration	3153
6.657.3.2	getMessageSelector	3154
6.657.3.3	getQueue	3154
6.658	decaf::util::Random Class Reference	3155
6.658.1	Detailed Description	3156
6.658.2	Constructor & Destructor Documentation	3156
6.658.2.1	Random	3156
6.658.2.2	Random	3156
6.658.3	Member Function Documentation	3156
6.658.3.1	next	3156
6.658.3.2	nextBoolean	3157
6.658.3.3	nextBytes	3157
6.658.3.4	nextBytes	3157
6.658.3.5	nextDouble	3158
6.658.3.6	nextFloat	3158

6.658.3.7	nextGaussian	3158
6.658.3.8	nextInt	3158
6.658.3.9	nextInt	3159
6.658.3.10	nextLong	3159
6.658.3.11	setSeed	3159
6.659	decaf::lang::Readable Class Reference	3160
6.659.1	Detailed Description	3160
6.659.2	Constructor & Destructor Documentation	3160
6.659.2.1	~Readable	3160
6.659.3	Member Function Documentation	3160
6.659.3.1	read	3160
6.660	activemq::transport::inactivity::ReadChecker Class Reference	3162
6.660.1	Detailed Description	3162
6.660.2	Constructor & Destructor Documentation	3162
6.660.2.1	ReadChecker	3162
6.660.2.2	~ReadChecker	3162
6.660.3	Member Function Documentation	3162
6.660.3.1	run	3162
6.661	decaf::io::Reader Class Reference	3163
6.661.1	Constructor & Destructor Documentation	3164
6.661.1.1	Reader	3164
6.661.1.2	~Reader	3164
6.661.2	Member Function Documentation	3164
6.661.2.1	doReadArray	3164
6.661.2.2	doReadArrayBounded	3164
6.661.2.3	doReadChar	3165
6.661.2.4	doReadCharBuffer	3165
6.661.2.5	doReadVector	3165
6.661.2.6	mark	3165
6.661.2.7	markSupported	3165
6.661.2.8	read	3165
6.661.2.9	read	3166
6.661.2.10	read	3166
6.661.2.11	read	3167
6.661.2.12	read	3167
6.661.2.13	ready	3167

6.661.2.14	reset	3168
6.661.2.15	skip	3168
6.662	decaf::nio::ReadOnlyBufferException Class Reference	3169
6.662.1	Constructor & Destructor Documentation	3169
6.662.1.1	ReadOnlyBufferException	3169
6.662.1.2	ReadOnlyBufferException	3169
6.662.1.3	ReadOnlyBufferException	3170
6.662.1.4	ReadOnlyBufferException	3170
6.662.1.5	ReadOnlyBufferException	3170
6.662.1.6	ReadOnlyBufferException	3170
6.662.1.7	~ReadOnlyBufferException	3171
6.662.2	Member Function Documentation	3171
6.662.2.1	clone	3171
6.663	decaf::util::concurrent::locks::ReadWriteLock Class Reference	3172
6.663.1	Detailed Description	3172
6.663.2	Constructor & Destructor Documentation	3173
6.663.2.1	~ReadWriteLock	3173
6.663.3	Member Function Documentation	3173
6.663.3.1	readLock	3173
6.663.3.2	writeLock	3173
6.664	activemq::cmsutil::CmsTemplate::ReceiveExecutor Class Reference	3174
6.664.1	Constructor & Destructor Documentation	3175
6.664.1.1	ReceiveExecutor	3175
6.664.1.2	ReceiveExecutor	3175
6.664.1.3	~ReceiveExecutor	3175
6.664.2	Member Function Documentation	3175
6.664.2.1	doInCms	3175
6.664.2.2	getDestination	3175
6.664.2.3	getMessage	3175
6.664.2.4	operator=	3175
6.664.3	Field Documentation	3176
6.664.3.1	destination	3176
6.664.3.2	message	3176
6.664.3.3	noLocal	3176
6.664.3.4	parent	3176
6.664.3.5	selector	3176

6.665	activemq::core::RedeliveryPolicy Class Reference	3177
6.665.1	Detailed Description	3178
6.665.2	Constructor & Destructor Documentation	3178
6.665.2.1	RedeliveryPolicy	3178
6.665.2.2	~RedeliveryPolicy	3178
6.665.3	Member Function Documentation	3178
6.665.3.1	clone	3178
6.665.3.2	configure	3178
6.665.3.3	getBackOffMultiplier	3179
6.665.3.4	getCollisionAvoidancePercent	3179
6.665.3.5	getInitialRedeliveryDelay	3179
6.665.3.6	getMaximumRedeliveries	3179
6.665.3.7	getRedeliveryDelay	3179
6.665.3.8	isUseCollisionAvoidance	3180
6.665.3.9	isUseExponentialBackOff	3180
6.665.3.10	setBackOffMultiplier	3180
6.665.3.11	setCollisionAvoidancePercent	3180
6.665.3.12	setInitialRedeliveryDelay	3180
6.665.3.13	setMaximumRedeliveries	3181
6.665.3.14	setUseCollisionAvoidance	3181
6.665.3.15	setUseExponentialBackOff	3181
6.665.4	Field Documentation	3181
6.665.4.1	NO_MAXIMUM_REDELIVERIES	3181
6.666	decaf::util::concurrent::locks::ReentrantLock Class Reference	3182
6.666.1	Detailed Description	3183
6.666.2	Constructor & Destructor Documentation	3183
6.666.2.1	ReentrantLock	3183
6.666.2.2	~ReentrantLock	3183
6.666.3	Member Function Documentation	3183
6.666.3.1	getHoldCount	3183
6.666.3.2	isFair	3184
6.666.3.3	isHeldByCurrentThread	3184
6.666.3.4	isLocked	3184
6.666.3.5	lock	3185
6.666.3.6	lockInterruptibly	3185
6.666.3.7	newCondition	3186

6.666.3.8 toString	3186
6.666.3.9 tryLock	3186
6.666.3.10 tryLock	3187
6.666.3.11 unlock	3188
6.667 decaf::util::concurrent::RejectedExecutionException Class Reference	3189
6.667.1 Constructor & Destructor Documentation	3189
6.667.1.1 RejectedExecutionException	3189
6.667.1.2 RejectedExecutionException	3189
6.667.1.3 RejectedExecutionException	3190
6.667.1.4 RejectedExecutionException	3190
6.667.1.5 RejectedExecutionException	3190
6.667.1.6 RejectedExecutionException	3190
6.667.1.7 ~RejectedExecutionException	3191
6.667.2 Member Function Documentation	3191
6.667.2.1 clone	3191
6.668 decaf::util::concurrent::RejectedExecutionHandler Class Reference	3192
6.668.1 Detailed Description	3192
6.668.2 Constructor & Destructor Documentation	3192
6.668.2.1 ~RejectedExecutionHandler	3192
6.668.3 Member Function Documentation	3192
6.668.3.1 rejectedExecution	3192
6.669 activemq::commands::RemoveInfo Class Reference	3194
6.669.1 Constructor & Destructor Documentation	3195
6.669.1.1 RemoveInfo	3195
6.669.1.2 ~RemoveInfo	3195
6.669.2 Member Function Documentation	3195
6.669.2.1 cloneDataStructure	3195
6.669.2.2 copyDataStructure	3195
6.669.2.3 equals	3195
6.669.2.4 getDataStructureType	3195
6.669.2.5 getLastDeliveredSequenceId	3196
6.669.2.6 getObjectId	3196
6.669.2.7 getObjectId	3196
6.669.2.8 isRemoveInfo	3196
6.669.2.9 setLastDeliveredSequenceId	3196
6.669.2.10 setObjectId	3196

6.669.2.1	toString	3196
6.669.2.2	visit	3196
6.669.3	Field Documentation	3197
6.669.3.1	ID_REMOVEINFO	3197
6.669.3.2	lastDeliveredSequenceId	3197
6.669.3.3	objectId	3197
6.670	activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller Class Reference	3198
6.670.1	Detailed Description	3198
6.670.2	Constructor & Destructor Documentation	3199
6.670.2.1	RemoveInfoMarshaller	3199
6.670.2.2	~RemoveInfoMarshaller	3199
6.670.3	Member Function Documentation	3199
6.670.3.1	createObject	3199
6.670.3.2	getDataStructureType	3199
6.670.3.3	looseMarshal	3199
6.670.3.4	looseUnmarshal	3200
6.670.3.5	tightMarshal1	3200
6.670.3.6	tightMarshal2	3200
6.670.3.7	tightUnmarshal	3201
6.671	activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller Class Reference	3202
6.671.1	Detailed Description	3202
6.671.2	Constructor & Destructor Documentation	3203
6.671.2.1	RemoveInfoMarshaller	3203
6.671.2.2	~RemoveInfoMarshaller	3203
6.671.3	Member Function Documentation	3203
6.671.3.1	createObject	3203
6.671.3.2	getDataStructureType	3203
6.671.3.3	looseMarshal	3203
6.671.3.4	looseUnmarshal	3204
6.671.3.5	tightMarshal1	3204
6.671.3.6	tightMarshal2	3204
6.671.3.7	tightUnmarshal	3205
6.672	activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller Class Reference	3206
6.672.1	Detailed Description	3206
6.672.2	Constructor & Destructor Documentation	3207
6.672.2.1	RemoveInfoMarshaller	3207

6.672.2.2 ~RemoveInfoMarshaller	3207
6.672.3 Member Function Documentation	3207
6.672.3.1 createObject	3207
6.672.3.2 getDataStructureType	3207
6.672.3.3 looseMarshal	3207
6.672.3.4 looseUnmarshal	3208
6.672.3.5 tightMarshal1	3208
6.672.3.6 tightMarshal2	3208
6.672.3.7 tightUnmarshal	3209
6.673activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller Class Reference	3210
6.673.1 Detailed Description	3210
6.673.2 Constructor & Destructor Documentation	3211
6.673.2.1 RemoveInfoMarshaller	3211
6.673.2.2 ~RemoveInfoMarshaller	3211
6.673.3 Member Function Documentation	3211
6.673.3.1 createObject	3211
6.673.3.2 getDataStructureType	3211
6.673.3.3 looseMarshal	3211
6.673.3.4 looseUnmarshal	3212
6.673.3.5 tightMarshal1	3212
6.673.3.6 tightMarshal2	3212
6.673.3.7 tightUnmarshal	3213
6.674activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller Class Reference	3214
6.674.1 Detailed Description	3214
6.674.2 Constructor & Destructor Documentation	3215
6.674.2.1 RemoveInfoMarshaller	3215
6.674.2.2 ~RemoveInfoMarshaller	3215
6.674.3 Member Function Documentation	3215
6.674.3.1 createObject	3215
6.674.3.2 getDataStructureType	3215
6.674.3.3 looseMarshal	3215
6.674.3.4 looseUnmarshal	3216
6.674.3.5 tightMarshal1	3216
6.674.3.6 tightMarshal2	3216
6.674.3.7 tightUnmarshal	3217
6.675activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller Class Reference	3218

6.675.1 Detailed Description	3218
6.675.2 Constructor & Destructor Documentation	3219
6.675.2.1 RemoveInfoMarshaller	3219
6.675.2.2 ~RemoveInfoMarshaller	3219
6.675.3 Member Function Documentation	3219
6.675.3.1 createObject	3219
6.675.3.2 getDataStructureType	3219
6.675.3.3 looseMarshal	3219
6.675.3.4 looseUnmarshal	3220
6.675.3.5 tightMarshal1	3220
6.675.3.6 tightMarshal2	3220
6.675.3.7 tightUnmarshal	3221
6.676activemq::commands::RemoveSubscriptionInfo Class Reference	3222
6.676.1 Constructor & Destructor Documentation	3223
6.676.1.1 RemoveSubscriptionInfo	3223
6.676.1.2 ~RemoveSubscriptionInfo	3223
6.676.2 Member Function Documentation	3223
6.676.2.1 cloneDataStructure	3223
6.676.2.2 copyDataStructure	3223
6.676.2.3 equals	3223
6.676.2.4 getClientId	3224
6.676.2.5 getClientId	3224
6.676.2.6 getConnectionId	3224
6.676.2.7 getConnectionId	3224
6.676.2.8 getDataStructureType	3224
6.676.2.9 getSubscriptionName	3224
6.676.2.10getSubscriptionName	3224
6.676.2.11isRemoveSubscriptionInfo	3224
6.676.2.12setClientId	3225
6.676.2.13setConnectionId	3225
6.676.2.14setSubscriptionName	3225
6.676.2.15toString	3225
6.676.2.16visit	3225
6.676.3 Field Documentation	3226
6.676.3.1 clientId	3226
6.676.3.2 connectionId	3226

6.676.3.3 ID_REMOVESUBSCRIPTIONINFO	3226
6.676.3.4 subscriptionName	3226
6.677activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller	
Class Reference	3227
6.677.1 Detailed Description	3227
6.677.2 Constructor & Destructor Documentation	3228
6.677.2.1 RemoveSubscriptionInfoMarshaller	3228
6.677.2.2 ~RemoveSubscriptionInfoMarshaller	3228
6.677.3 Member Function Documentation	3228
6.677.3.1 createObject	3228
6.677.3.2 getDataStructureType	3228
6.677.3.3 looseMarshal	3228
6.677.3.4 looseUnmarshal	3229
6.677.3.5 tightMarshal1	3229
6.677.3.6 tightMarshal2	3229
6.677.3.7 tightUnmarshal	3230
6.678activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller	
Class Reference	3231
6.678.1 Detailed Description	3231
6.678.2 Constructor & Destructor Documentation	3232
6.678.2.1 RemoveSubscriptionInfoMarshaller	3232
6.678.2.2 ~RemoveSubscriptionInfoMarshaller	3232
6.678.3 Member Function Documentation	3232
6.678.3.1 createObject	3232
6.678.3.2 getDataStructureType	3232
6.678.3.3 looseMarshal	3232
6.678.3.4 looseUnmarshal	3233
6.678.3.5 tightMarshal1	3233
6.678.3.6 tightMarshal2	3233
6.678.3.7 tightUnmarshal	3234
6.679activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller	
Class Reference	3235
6.679.1 Detailed Description	3235
6.679.2 Constructor & Destructor Documentation	3236
6.679.2.1 RemoveSubscriptionInfoMarshaller	3236
6.679.2.2 ~RemoveSubscriptionInfoMarshaller	3236
6.679.3 Member Function Documentation	3236

6.679.3.1	createObject	3236
6.679.3.2	getDataStructureType	3236
6.679.3.3	looseMarshal	3236
6.679.3.4	looseUnmarshal	3237
6.679.3.5	tightMarshal1	3237
6.679.3.6	tightMarshal2	3237
6.679.3.7	tightUnmarshal	3238
6.680	activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller	
	Class Reference	3239
6.680.1	Detailed Description	3239
6.680.2	Constructor & Destructor Documentation	3240
	6.680.2.1 RemoveSubscriptionInfoMarshaller	3240
	6.680.2.2 ~RemoveSubscriptionInfoMarshaller	3240
6.680.3	Member Function Documentation	3240
	6.680.3.1 createObject	3240
	6.680.3.2 getDataStructureType	3240
	6.680.3.3 looseMarshal	3240
	6.680.3.4 looseUnmarshal	3241
	6.680.3.5 tightMarshal1	3241
	6.680.3.6 tightMarshal2	3241
	6.680.3.7 tightUnmarshal	3242
6.681	activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller	
	Class Reference	3243
6.681.1	Detailed Description	3243
6.681.2	Constructor & Destructor Documentation	3244
	6.681.2.1 RemoveSubscriptionInfoMarshaller	3244
	6.681.2.2 ~RemoveSubscriptionInfoMarshaller	3244
6.681.3	Member Function Documentation	3244
	6.681.3.1 createObject	3244
	6.681.3.2 getDataStructureType	3244
	6.681.3.3 looseMarshal	3244
	6.681.3.4 looseUnmarshal	3245
	6.681.3.5 tightMarshal1	3245
	6.681.3.6 tightMarshal2	3245
	6.681.3.7 tightUnmarshal	3246
6.682	activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller	
	Class Reference	3247

6.682.1 Detailed Description	3247
6.682.2 Constructor & Destructor Documentation	3248
6.682.2.1 RemoveSubscriptionInfoMarshaller	3248
6.682.2.2 ~RemoveSubscriptionInfoMarshaller	3248
6.682.3 Member Function Documentation	3248
6.682.3.1 createObject	3248
6.682.3.2 getDataStructureType	3248
6.682.3.3 looseMarshal	3248
6.682.3.4 looseUnmarshal	3249
6.682.3.5 tightMarshal1	3249
6.682.3.6 tightMarshal2	3249
6.682.3.7 tightUnmarshal	3250
6.683activemq::commands::ReplayCommand Class Reference	3251
6.683.1 Constructor & Destructor Documentation	3252
6.683.1.1 ReplayCommand	3252
6.683.1.2 ~ReplayCommand	3252
6.683.2 Member Function Documentation	3252
6.683.2.1 cloneDataStructure	3252
6.683.2.2 copyDataStructure	3252
6.683.2.3 equals	3252
6.683.2.4 getDataStructureType	3252
6.683.2.5 getFirstNakNumber	3253
6.683.2.6 getLastNakNumber	3253
6.683.2.7 setFirstNakNumber	3253
6.683.2.8 setLastNakNumber	3253
6.683.2.9 toString	3253
6.683.2.10visit	3253
6.683.3 Field Documentation	3253
6.683.3.1 firstNakNumber	3253
6.683.3.2 ID_REPLAYCOMMAND	3253
6.683.3.3 lastNakNumber	3253
6.684activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller Class Reference	3254
6.684.1 Detailed Description	3254
6.684.2 Constructor & Destructor Documentation	3255
6.684.2.1 ReplayCommandMarshaller	3255
6.684.2.2 ~ReplayCommandMarshaller	3255

6.684.3 Member Function Documentation	3255
6.684.3.1 createObject	3255
6.684.3.2 getDataStructureType	3255
6.684.3.3 looseMarshal	3255
6.684.3.4 looseUnmarshal	3256
6.684.3.5 tightMarshal1	3256
6.684.3.6 tightMarshal2	3256
6.684.3.7 tightUnmarshal	3257
6.685activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller Class	
Reference	3258
6.685.1 Detailed Description	3258
6.685.2 Constructor & Destructor Documentation	3259
6.685.2.1 ReplayCommandMarshaller	3259
6.685.2.2 ~ReplayCommandMarshaller	3259
6.685.3 Member Function Documentation	3259
6.685.3.1 createObject	3259
6.685.3.2 getDataStructureType	3259
6.685.3.3 looseMarshal	3259
6.685.3.4 looseUnmarshal	3260
6.685.3.5 tightMarshal1	3260
6.685.3.6 tightMarshal2	3260
6.685.3.7 tightUnmarshal	3261
6.686activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller Class	
Reference	3262
6.686.1 Detailed Description	3262
6.686.2 Constructor & Destructor Documentation	3263
6.686.2.1 ReplayCommandMarshaller	3263
6.686.2.2 ~ReplayCommandMarshaller	3263
6.686.3 Member Function Documentation	3263
6.686.3.1 createObject	3263
6.686.3.2 getDataStructureType	3263
6.686.3.3 looseMarshal	3263
6.686.3.4 looseUnmarshal	3264
6.686.3.5 tightMarshal1	3264
6.686.3.6 tightMarshal2	3264
6.686.3.7 tightUnmarshal	3265

6.687	activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	Class	
	Reference		3266
6.687.1	Detailed Description		3266
6.687.2	Constructor & Destructor Documentation		3267
	6.687.2.1 ReplayCommandMarshaller		3267
	6.687.2.2 ~ReplayCommandMarshaller		3267
6.687.3	Member Function Documentation		3267
	6.687.3.1 createObject		3267
	6.687.3.2 getDataStructureType		3267
	6.687.3.3 looseMarshal		3267
	6.687.3.4 looseUnmarshal		3268
	6.687.3.5 tightMarshal1		3268
	6.687.3.6 tightMarshal2		3268
	6.687.3.7 tightUnmarshal		3269
6.688	activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller	Class	
	Reference		3270
6.688.1	Detailed Description		3270
6.688.2	Constructor & Destructor Documentation		3271
	6.688.2.1 ReplayCommandMarshaller		3271
	6.688.2.2 ~ReplayCommandMarshaller		3271
6.688.3	Member Function Documentation		3271
	6.688.3.1 createObject		3271
	6.688.3.2 getDataStructureType		3271
	6.688.3.3 looseMarshal		3271
	6.688.3.4 looseUnmarshal		3272
	6.688.3.5 tightMarshal1		3272
	6.688.3.6 tightMarshal2		3272
	6.688.3.7 tightUnmarshal		3273
6.689	activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller	Class	
	Reference		3274
6.689.1	Detailed Description		3274
6.689.2	Constructor & Destructor Documentation		3275
	6.689.2.1 ReplayCommandMarshaller		3275
	6.689.2.2 ~ReplayCommandMarshaller		3275
6.689.3	Member Function Documentation		3275
	6.689.3.1 createObject		3275
	6.689.3.2 getDataStructureType		3275

6.689.3.3 looseMarshal	3275
6.689.3.4 looseUnmarshal	3276
6.689.3.5 tightMarshal1	3276
6.689.3.6 tightMarshal2	3276
6.689.3.7 tightUnmarshal	3277
6.690activemq::cmsutil::CmsTemplate::ResolveProducerExecutor Class Reference	3278
6.690.1 Constructor & Destructor Documentation	3278
6.690.1.1 ResolveProducerExecutor	3278
6.690.1.2 ~ResolveProducerExecutor	3278
6.690.2 Member Function Documentation	3278
6.690.2.1 getDestination	3278
6.690.2.2 operator=	3278
6.691activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor Class Reference	3279
6.691.1 Constructor & Destructor Documentation	3279
6.691.1.1 ResolveReceiveExecutor	3279
6.691.1.2 ~ResolveReceiveExecutor	3279
6.691.2 Member Function Documentation	3279
6.691.2.1 getDestination	3279
6.691.2.2 operator=	3279
6.692decaf::internal::util::Resource Class Reference	3280
6.692.1 Detailed Description	3280
6.692.2 Constructor & Destructor Documentation	3280
6.692.2.1 ~Resource	3280
6.693decaf::internal::util::ResourceLifecycleManager Class Reference	3281
6.693.1 Detailed Description	3281
6.693.2 Constructor & Destructor Documentation	3281
6.693.2.1 ResourceLifecycleManager	3281
6.693.2.2 ~ResourceLifecycleManager	3281
6.693.3 Member Function Documentation	3281
6.693.3.1 addResource	3281
6.693.3.2 destroyResources	3281
6.694activemq::cmsutil::ResourceLifecycleManager Class Reference	3282
6.694.1 Detailed Description	3282
6.694.2 Constructor & Destructor Documentation	3283
6.694.2.1 ResourceLifecycleManager	3283
6.694.2.2 ResourceLifecycleManager	3283

6.694.2.3 ~ResourceLifecycleManager	3283
6.694.3 Member Function Documentation	3283
6.694.3.1 addConnection	3283
6.694.3.2 addDestination	3283
6.694.3.3 addMessageConsumer	3283
6.694.3.4 addMessageProducer	3283
6.694.3.5 addSession	3284
6.694.3.6 destroy	3284
6.694.3.7 operator=	3284
6.694.3.8 releaseAll	3284
6.695activemq::commands::Response Class Reference	3285
6.695.1 Constructor & Destructor Documentation	3286
6.695.1.1 Response	3286
6.695.1.2 ~Response	3286
6.695.2 Member Function Documentation	3286
6.695.2.1 cloneDataStructure	3286
6.695.2.2 copyDataStructure	3286
6.695.2.3 equals	3286
6.695.2.4 getCorrelationId	3287
6.695.2.5 getDataStructureType	3287
6.695.2.6 isResponse	3287
6.695.2.7 setCorrelationId	3287
6.695.2.8 toString	3287
6.695.2.9 visit	3287
6.695.3 Field Documentation	3288
6.695.3.1 correlationId	3288
6.695.3.2 ID_RESPONSE	3288
6.696activemq::transport::mock::ResponseBuilder Class Reference	3289
6.696.1 Detailed Description	3289
6.696.2 Constructor & Destructor Documentation	3289
6.696.2.1 ~ResponseBuilder	3289
6.696.3 Member Function Documentation	3289
6.696.3.1 buildIncomingCommands	3289
6.696.3.2 buildResponse	3290
6.697activemq::transport::correlator::ResponseCorrelator Class Reference	3291
6.697.1 Detailed Description	3291

6.697.2 Constructor & Destructor Documentation	3292
6.697.2.1 ResponseCorrelator	3292
6.697.2.2 ~ResponseCorrelator	3292
6.697.3 Member Function Documentation	3292
6.697.3.1 close	3292
6.697.3.2 onCommand	3292
6.697.3.3 oneway	3292
6.697.3.4 onTransportException	3293
6.697.3.5 request	3293
6.697.3.6 request	3293
6.697.3.7 start	3294
6.698activemq::wireformat::openwire::marshal::v4::ResponseMarshaller Class Reference .	3295
6.698.1 Detailed Description	3295
6.698.2 Constructor & Destructor Documentation	3296
6.698.2.1 ResponseMarshaller	3296
6.698.2.2 ~ResponseMarshaller	3296
6.698.3 Member Function Documentation	3296
6.698.3.1 createObject	3296
6.698.3.2 getDataStructureType	3296
6.698.3.3 looseMarshal	3296
6.698.3.4 looseUnmarshal	3297
6.698.3.5 tightMarshal1	3297
6.698.3.6 tightMarshal2	3298
6.698.3.7 tightUnmarshal	3299
6.699activemq::wireformat::openwire::marshal::v2::ResponseMarshaller Class Reference .	3300
6.699.1 Detailed Description	3300
6.699.2 Constructor & Destructor Documentation	3301
6.699.2.1 ResponseMarshaller	3301
6.699.2.2 ~ResponseMarshaller	3301
6.699.3 Member Function Documentation	3301
6.699.3.1 createObject	3301
6.699.3.2 getDataStructureType	3301
6.699.3.3 looseMarshal	3301
6.699.3.4 looseUnmarshal	3302
6.699.3.5 tightMarshal1	3302
6.699.3.6 tightMarshal2	3303

6.699.3.7 tightUnmarshal	3304
6.700activemq::wireformat::openwire::marshal::v5::ResponseMarshaller Class Reference	3305
6.700.1 Detailed Description	3305
6.700.2 Constructor & Destructor Documentation	3306
6.700.2.1 ResponseMarshaller	3306
6.700.2.2 ~ResponseMarshaller	3306
6.700.3 Member Function Documentation	3306
6.700.3.1 createObject	3306
6.700.3.2 getDataStructureType	3306
6.700.3.3 looseMarshal	3306
6.700.3.4 looseUnmarshal	3307
6.700.3.5 tightMarshal1	3307
6.700.3.6 tightMarshal2	3308
6.700.3.7 tightUnmarshal	3309
6.701activemq::wireformat::openwire::marshal::v3::ResponseMarshaller Class Reference	3310
6.701.1 Detailed Description	3310
6.701.2 Constructor & Destructor Documentation	3311
6.701.2.1 ResponseMarshaller	3311
6.701.2.2 ~ResponseMarshaller	3311
6.701.3 Member Function Documentation	3311
6.701.3.1 createObject	3311
6.701.3.2 getDataStructureType	3311
6.701.3.3 looseMarshal	3311
6.701.3.4 looseUnmarshal	3312
6.701.3.5 tightMarshal1	3312
6.701.3.6 tightMarshal2	3313
6.701.3.7 tightUnmarshal	3314
6.702activemq::wireformat::openwire::marshal::v1::ResponseMarshaller Class Reference	3315
6.702.1 Detailed Description	3315
6.702.2 Constructor & Destructor Documentation	3316
6.702.2.1 ResponseMarshaller	3316
6.702.2.2 ~ResponseMarshaller	3316
6.702.3 Member Function Documentation	3316
6.702.3.1 createObject	3316
6.702.3.2 getDataStructureType	3316
6.702.3.3 looseMarshal	3316

6.702.3.4 looseUnmarshal	3317
6.702.3.5 tightMarshal1	3317
6.702.3.6 tightMarshal2	3318
6.702.3.7 tightUnmarshal	3319
6.703activemq::wireformat::openwire::marshal::v6::ResponseMarshaller Class Reference	3320
6.703.1 Detailed Description	3320
6.703.2 Constructor & Destructor Documentation	3321
6.703.2.1 ResponseMarshaller	3321
6.703.2.2 ~ResponseMarshaller	3321
6.703.3 Member Function Documentation	3321
6.703.3.1 createObject	3321
6.703.3.2 getDataStructureType	3321
6.703.3.3 looseMarshal	3321
6.703.3.4 looseUnmarshal	3322
6.703.3.5 tightMarshal1	3322
6.703.3.6 tightMarshal2	3323
6.703.3.7 tightUnmarshal	3324
6.704decaf::lang::Runnable Class Reference	3325
6.704.1 Detailed Description	3325
6.704.2 Constructor & Destructor Documentation	3325
6.704.2.1 ~Runnable	3325
6.704.3 Member Function Documentation	3325
6.704.3.1 run	3325
6.705decaf::lang::Runtime Class Reference	3326
6.705.1 Constructor & Destructor Documentation	3326
6.705.1.1 ~Runtime	3326
6.705.2 Member Function Documentation	3326
6.705.2.1 getRuntime	3326
6.705.2.2 initializeRuntime	3326
6.705.2.3 initializeRuntime	3327
6.705.2.4 shutdownRuntime	3327
6.706decaf::lang::exceptions::RuntimeException Class Reference	3328
6.706.1 Constructor & Destructor Documentation	3328
6.706.1.1 RuntimeException	3328
6.706.1.2 RuntimeException	3328
6.706.1.3 RuntimeException	3329

6.706.1.4 RuntimeException	3329
6.706.1.5 RuntimeException	3329
6.706.1.6 RuntimeException	3329
6.706.1.7 ~RuntimeException	3330
6.706.2 Member Function Documentation	3330
6.706.2.1 clone	3330
6.707decaf::security::SecureRandom Class Reference	3331
6.707.1 Detailed Description	3332
6.707.2 Constructor & Destructor Documentation	3332
6.707.2.1 SecureRandom	3332
6.707.2.2 SecureRandom	3332
6.707.2.3 SecureRandom	3333
6.707.2.4 ~SecureRandom	3333
6.707.3 Member Function Documentation	3333
6.707.3.1 next	3333
6.707.3.2 nextBytes	3334
6.707.3.3 nextBytes	3334
6.707.3.4 setSeed	3334
6.707.3.5 setSeed	3335
6.707.3.6 setSeed	3335
6.708decaf::internal::security::SecureRandomImpl Class Reference	3336
6.708.1 Detailed Description	3336
6.708.2 Constructor & Destructor Documentation	3337
6.708.2.1 SecureRandomImpl	3337
6.708.2.2 ~SecureRandomImpl	3337
6.708.2.3 SecureRandomImpl	3337
6.708.2.4 ~SecureRandomImpl	3337
6.708.3 Member Function Documentation	3337
6.708.3.1 providerGenerateSeed	3337
6.708.3.2 providerGenerateSeed	3337
6.708.3.3 providerNextBytes	3337
6.708.3.4 providerNextBytes	3338
6.708.3.5 providerSetSeed	3338
6.708.3.6 providerSetSeed	3338
6.709decaf::security::SecureRandomSpi Class Reference	3339
6.709.1 Detailed Description	3339

6.709.2 Constructor & Destructor Documentation	3339
6.709.2.1 SecureRandomSpi	3339
6.709.2.2 ~SecureRandomSpi	3339
6.709.3 Member Function Documentation	3339
6.709.3.1 providerGenerateSeed	3339
6.709.3.2 providerNextBytes	3340
6.709.3.3 providerSetSeed	3340
6.710decaf::util::concurrent::Semaphore Class Reference	3341
6.710.1 Detailed Description	3342
6.710.2 Constructor & Destructor Documentation	3343
6.710.2.1 Semaphore	3343
6.710.2.2 Semaphore	3343
6.710.2.3 ~Semaphore	3344
6.710.3 Member Function Documentation	3344
6.710.3.1 acquire	3344
6.710.3.2 acquire	3344
6.710.3.3 acquireUninterruptibly	3345
6.710.3.4 acquireUninterruptibly	3345
6.710.3.5 availablePermits	3346
6.710.3.6 drainPermits	3346
6.710.3.7 isFair	3346
6.710.3.8 release	3346
6.710.3.9 release	3347
6.710.3.10 toString	3347
6.710.3.11 tryAcquire	3347
6.710.3.12 tryAcquire	3348
6.710.3.13 tryAcquire	3348
6.710.3.14 tryAcquire	3349
6.711activemq::cmsutil::CmsTemplate::SendExecutor Class Reference	3350
6.711.1 Constructor & Destructor Documentation	3350
6.711.1.1 SendExecutor	3350
6.711.1.2 SendExecutor	3350
6.711.1.3 ~SendExecutor	3350
6.711.2 Member Function Documentation	3350
6.711.2.1 doInCms	3350
6.711.2.2 operator=	3351

6.712	decaf::net::ServerSocket Class Reference	3352
6.712.1	Detailed Description	3354
6.712.2	Constructor & Destructor Documentation	3354
6.712.2.1	ServerSocket	3354
6.712.2.2	ServerSocket	3354
6.712.2.3	ServerSocket	3354
6.712.2.4	ServerSocket	3355
6.712.2.5	~ServerSocket	3355
6.712.2.6	ServerSocket	3355
6.712.3	Member Function Documentation	3356
6.712.3.1	accept	3356
6.712.3.2	bind	3356
6.712.3.3	bind	3356
6.712.3.4	checkClosed	3357
6.712.3.5	close	3357
6.712.3.6	ensureCreated	3357
6.712.3.7	getDefaultBacklog	3357
6.712.3.8	getLocalPort	3357
6.712.3.9	getReceiveBufferSize	3357
6.712.3.10	getReuseAddress	3358
6.712.3.11	getSoTimeout	3358
6.712.3.12	implAccept	3358
6.712.3.13	sBound	3358
6.712.3.14	sClosed	3358
6.712.3.15	setReceiveBufferSize	3359
6.712.3.16	setReuseAddress	3359
6.712.3.17	setSocketImplFactory	3359
6.712.3.18	setSoTimeout	3359
6.712.3.19	setUpSocketImpl	3360
6.712.3.20	toString	3360
6.713	decaf::net::ServerSocketFactory Class Reference	3361
6.713.1	Detailed Description	3361
6.713.2	Constructor & Destructor Documentation	3362
6.713.2.1	ServerSocketFactory	3362
6.713.2.2	~ServerSocketFactory	3362
6.713.3	Member Function Documentation	3362

6.713.3.1 createServerSocket	3362
6.713.3.2 createServerSocket	3362
6.713.3.3 createServerSocket	3363
6.713.3.4 createServerSocket	3363
6.713.3.5 getDefault	3363
6.714cms::Session Class Reference	3365
6.714.1 Detailed Description	3367
6.714.2 Member Enumeration Documentation	3368
6.714.2.1 AcknowledgeMode	3368
6.714.3 Constructor & Destructor Documentation	3368
6.714.3.1 ~Session	3368
6.714.4 Member Function Documentation	3368
6.714.4.1 close	3368
6.714.4.2 commit	3369
6.714.4.3 createBrowser	3369
6.714.4.4 createBrowser	3369
6.714.4.5 createBytesMessage	3370
6.714.4.6 createBytesMessage	3370
6.714.4.7 createConsumer	3370
6.714.4.8 createConsumer	3371
6.714.4.9 createConsumer	3371
6.714.4.10 createDurableConsumer	3372
6.714.4.11 createMapMessage	3372
6.714.4.12 createMessage	3372
6.714.4.13 createProducer	3373
6.714.4.14 createQueue	3373
6.714.4.15 createStreamMessage	3373
6.714.4.16 createTemporaryQueue	3374
6.714.4.17 createTemporaryTopic	3374
6.714.4.18 createTextMessage	3374
6.714.4.19 createTextMessage	3374
6.714.4.20 createTopic	3375
6.714.4.21 getAcknowledgeMode	3375
6.714.4.22 isTransacted	3375
6.714.4.23 recover	3376
6.714.4.24 rollback	3376

6.714.4.25	unsubscribe	3376
6.715	activemq::cmsutil::SessionCallback Class Reference	3378
6.715.1	Detailed Description	3378
6.715.2	Constructor & Destructor Documentation	3378
6.715.2.1	~SessionCallback	3378
6.715.3	Member Function Documentation	3378
6.715.3.1	doInCms	3378
6.716	activemq::commands::SessionId Class Reference	3379
6.716.1	Member Typedef Documentation	3380
6.716.1.1	COMPARATOR	3380
6.716.2	Constructor & Destructor Documentation	3380
6.716.2.1	SessionId	3380
6.716.2.2	SessionId	3380
6.716.2.3	SessionId	3380
6.716.2.4	SessionId	3380
6.716.2.5	SessionId	3380
6.716.2.6	~SessionId	3380
6.716.3	Member Function Documentation	3380
6.716.3.1	cloneDataStructure	3380
6.716.3.2	compareTo	3380
6.716.3.3	copyDataStructure	3380
6.716.3.4	equals	3381
6.716.3.5	equals	3381
6.716.3.6	getConnectionId	3381
6.716.3.7	getConnectionId	3381
6.716.3.8	getDataStructureType	3381
6.716.3.9	getParentId	3382
6.716.3.10	getValue	3382
6.716.3.11	operator<	3382
6.716.3.12	operator=	3382
6.716.3.13	operator==	3382
6.716.3.14	setConnectionId	3382
6.716.3.15	setValue	3382
6.716.3.16	toString	3382
6.716.4	Field Documentation	3382
6.716.4.1	connectionId	3382

6.716.4.2 ID_SESSIONID	3382
6.716.4.3 value	3382
6.717activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller Class Reference	3383
6.717.1 Detailed Description	3383
6.717.2 Constructor & Destructor Documentation	3384
6.717.2.1 SessionIdMarshaller	3384
6.717.2.2 ~SessionIdMarshaller	3384
6.717.3 Member Function Documentation	3384
6.717.3.1 createObject	3384
6.717.3.2 getDataStructureType	3384
6.717.3.3 looseMarshal	3384
6.717.3.4 looseUnmarshal	3385
6.717.3.5 tightMarshal1	3385
6.717.3.6 tightMarshal2	3385
6.717.3.7 tightUnmarshal	3386
6.718activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller Class Reference	3387
6.718.1 Detailed Description	3387
6.718.2 Constructor & Destructor Documentation	3388
6.718.2.1 SessionIdMarshaller	3388
6.718.2.2 ~SessionIdMarshaller	3388
6.718.3 Member Function Documentation	3388
6.718.3.1 createObject	3388
6.718.3.2 getDataStructureType	3388
6.718.3.3 looseMarshal	3388
6.718.3.4 looseUnmarshal	3389
6.718.3.5 tightMarshal1	3389
6.718.3.6 tightMarshal2	3389
6.718.3.7 tightUnmarshal	3390
6.719activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller Class Reference	3391
6.719.1 Detailed Description	3391
6.719.2 Constructor & Destructor Documentation	3392
6.719.2.1 SessionIdMarshaller	3392
6.719.2.2 ~SessionIdMarshaller	3392
6.719.3 Member Function Documentation	3392
6.719.3.1 createObject	3392
6.719.3.2 getDataStructureType	3392

6.719.3.3 looseMarshal	3392
6.719.3.4 looseUnmarshal	3393
6.719.3.5 tightMarshal1	3393
6.719.3.6 tightMarshal2	3393
6.719.3.7 tightUnmarshal	3394
6.720activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller Class Reference	3395
6.720.1 Detailed Description	3395
6.720.2 Constructor & Destructor Documentation	3396
6.720.2.1 SessionIdMarshaller	3396
6.720.2.2 ~SessionIdMarshaller	3396
6.720.3 Member Function Documentation	3396
6.720.3.1 createObject	3396
6.720.3.2 getDataStructureType	3396
6.720.3.3 looseMarshal	3396
6.720.3.4 looseUnmarshal	3397
6.720.3.5 tightMarshal1	3397
6.720.3.6 tightMarshal2	3397
6.720.3.7 tightUnmarshal	3398
6.721activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller Class Reference	3399
6.721.1 Detailed Description	3399
6.721.2 Constructor & Destructor Documentation	3400
6.721.2.1 SessionIdMarshaller	3400
6.721.2.2 ~SessionIdMarshaller	3400
6.721.3 Member Function Documentation	3400
6.721.3.1 createObject	3400
6.721.3.2 getDataStructureType	3400
6.721.3.3 looseMarshal	3400
6.721.3.4 looseUnmarshal	3401
6.721.3.5 tightMarshal1	3401
6.721.3.6 tightMarshal2	3401
6.721.3.7 tightUnmarshal	3402
6.722activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller Class Reference	3403
6.722.1 Detailed Description	3403
6.722.2 Constructor & Destructor Documentation	3404
6.722.2.1 SessionIdMarshaller	3404
6.722.2.2 ~SessionIdMarshaller	3404

6.722.3 Member Function Documentation	3404
6.722.3.1 createObject	3404
6.722.3.2 getDataStructureType	3404
6.722.3.3 looseMarshal	3404
6.722.3.4 looseUnmarshal	3405
6.722.3.5 tightMarshal1	3405
6.722.3.6 tightMarshal2	3405
6.722.3.7 tightUnmarshal	3406
6.723activemq::commands::SessionInfo Class Reference	3407
6.723.1 Constructor & Destructor Documentation	3408
6.723.1.1 SessionInfo	3408
6.723.1.2 ~SessionInfo	3408
6.723.2 Member Function Documentation	3408
6.723.2.1 cloneDataStructure	3408
6.723.2.2 copyDataStructure	3408
6.723.2.3 createRemoveCommand	3408
6.723.2.4 equals	3408
6.723.2.5 getAckMode	3409
6.723.2.6 getDataStructureType	3409
6.723.2.7 getSessionId	3409
6.723.2.8 getSessionId	3409
6.723.2.9 setAckMode	3409
6.723.2.10setSessionId	3409
6.723.2.11toString	3409
6.723.2.12visit	3409
6.723.3 Field Documentation	3410
6.723.3.1 ID_SESSIONINFO	3410
6.723.3.2 sessionId	3410
6.724activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller Class Reference	3411
6.724.1 Detailed Description	3411
6.724.2 Constructor & Destructor Documentation	3412
6.724.2.1 SessionInfoMarshaller	3412
6.724.2.2 ~SessionInfoMarshaller	3412
6.724.3 Member Function Documentation	3412
6.724.3.1 createObject	3412
6.724.3.2 getDataStructureType	3412

6.724.3.3 looseMarshal	3412
6.724.3.4 looseUnmarshal	3413
6.724.3.5 tightMarshal1	3413
6.724.3.6 tightMarshal2	3413
6.724.3.7 tightUnmarshal	3414
6.725activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller Class Reference	3415
6.725.1 Detailed Description	3415
6.725.2 Constructor & Destructor Documentation	3416
6.725.2.1 SessionInfoMarshaller	3416
6.725.2.2 ~SessionInfoMarshaller	3416
6.725.3 Member Function Documentation	3416
6.725.3.1 createObject	3416
6.725.3.2 getDataStructureType	3416
6.725.3.3 looseMarshal	3416
6.725.3.4 looseUnmarshal	3417
6.725.3.5 tightMarshal1	3417
6.725.3.6 tightMarshal2	3417
6.725.3.7 tightUnmarshal	3418
6.726activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller Class Reference	3419
6.726.1 Detailed Description	3419
6.726.2 Constructor & Destructor Documentation	3420
6.726.2.1 SessionInfoMarshaller	3420
6.726.2.2 ~SessionInfoMarshaller	3420
6.726.3 Member Function Documentation	3420
6.726.3.1 createObject	3420
6.726.3.2 getDataStructureType	3420
6.726.3.3 looseMarshal	3420
6.726.3.4 looseUnmarshal	3421
6.726.3.5 tightMarshal1	3421
6.726.3.6 tightMarshal2	3421
6.726.3.7 tightUnmarshal	3422
6.727activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller Class Reference	3423
6.727.1 Detailed Description	3423
6.727.2 Constructor & Destructor Documentation	3424
6.727.2.1 SessionInfoMarshaller	3424
6.727.2.2 ~SessionInfoMarshaller	3424

6.727.3 Member Function Documentation	3424
6.727.3.1 createObject	3424
6.727.3.2 getDataStructureType	3424
6.727.3.3 looseMarshal	3424
6.727.3.4 looseUnmarshal	3425
6.727.3.5 tightMarshal1	3425
6.727.3.6 tightMarshal2	3425
6.727.3.7 tightUnmarshal	3426
6.728activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller Class Reference	3427
6.728.1 Detailed Description	3427
6.728.2 Constructor & Destructor Documentation	3428
6.728.2.1 SessionInfoMarshaller	3428
6.728.2.2 ~SessionInfoMarshaller	3428
6.728.3 Member Function Documentation	3428
6.728.3.1 createObject	3428
6.728.3.2 getDataStructureType	3428
6.728.3.3 looseMarshal	3428
6.728.3.4 looseUnmarshal	3429
6.728.3.5 tightMarshal1	3429
6.728.3.6 tightMarshal2	3429
6.728.3.7 tightUnmarshal	3430
6.729activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller Class Reference	3431
6.729.1 Detailed Description	3431
6.729.2 Constructor & Destructor Documentation	3432
6.729.2.1 SessionInfoMarshaller	3432
6.729.2.2 ~SessionInfoMarshaller	3432
6.729.3 Member Function Documentation	3432
6.729.3.1 createObject	3432
6.729.3.2 getDataStructureType	3432
6.729.3.3 looseMarshal	3432
6.729.3.4 looseUnmarshal	3433
6.729.3.5 tightMarshal1	3433
6.729.3.6 tightMarshal2	3433
6.729.3.7 tightUnmarshal	3434
6.730activemq::cmsutil::SessionPool Class Reference	3435
6.730.1 Detailed Description	3435

6.730.2 Constructor & Destructor Documentation	3435
6.730.2.1 SessionPool	3435
6.730.2.2 SessionPool	3435
6.730.2.3 ~SessionPool	3436
6.730.3 Member Function Documentation	3436
6.730.3.1 getResourceLifecycleManager	3436
6.730.3.2 operator=	3436
6.730.3.3 returnSession	3436
6.730.3.4 takeSession	3436
6.731activemq::state::SessionState Class Reference	3437
6.731.1 Constructor & Destructor Documentation	3438
6.731.1.1 SessionState	3438
6.731.1.2 ~SessionState	3438
6.731.2 Member Function Documentation	3438
6.731.2.1 addConsumer	3438
6.731.2.2 addProducer	3438
6.731.2.3 checkShutdown	3438
6.731.2.4 getConsumerState	3438
6.731.2.5 getConsumerStates	3438
6.731.2.6 getInfo	3438
6.731.2.7 getProducerState	3438
6.731.2.8 getProducerStates	3438
6.731.2.9 removeConsumer	3438
6.731.2.10removeProducer	3438
6.731.2.11shutdown	3438
6.731.2.12toString	3438
6.732decaf::util::Set< E > Class Template Reference	3439
6.732.1 Detailed Description	3439
6.732.2 Constructor & Destructor Documentation	3439
6.732.2.1 ~Set	3439
6.733decaf::lang::Short Class Reference	3440
6.733.1 Constructor & Destructor Documentation	3441
6.733.1.1 Short	3441
6.733.1.2 Short	3442
6.733.1.3 ~Short	3442
6.733.2 Member Function Documentation	3442

6.733.2.1	byteValue	3442
6.733.2.2	compareTo	3442
6.733.2.3	compareTo	3442
6.733.2.4	decode	3443
6.733.2.5	doubleValue	3443
6.733.2.6	equals	3443
6.733.2.7	equals	3443
6.733.2.8	float Value	3444
6.733.2.9	int Value	3444
6.733.2.10	longValue	3444
6.733.2.11	operator<	3444
6.733.2.12	operator<	3444
6.733.2.13	operator==	3445
6.733.2.14	operator==	3445
6.733.2.15	parseShort	3445
6.733.2.16	parseShort	3446
6.733.2.17	reverseBytes	3446
6.733.2.18	short Value	3446
6.733.2.19	toString	3446
6.733.2.20	toString	3447
6.733.2.21	valueOf	3447
6.733.2.22	valueOf	3447
6.733.2.23	valueOf	3447
6.733.3	Field Documentation	3448
6.733.3.1	MAX_VALUE	3448
6.733.3.2	MIN_VALUE	3448
6.733.3.3	SIZE	3448
6.734	decaf::internal::nio::ShortArrayBuffer Class Reference	3449
6.734.1	Constructor & Destructor Documentation	3452
6.734.1.1	ShortArrayBuffer	3452
6.734.1.2	ShortArrayBuffer	3452
6.734.1.3	ShortArrayBuffer	3453
6.734.1.4	ShortArrayBuffer	3453
6.734.1.5	~ShortArrayBuffer	3453
6.734.2	Member Function Documentation	3453
6.734.2.1	array	3453

6.734.2.2 arrayOffset	3454
6.734.2.3 asReadOnlyBuffer	3454
6.734.2.4 compact	3455
6.734.2.5 duplicate	3455
6.734.2.6 get	3455
6.734.2.7 get	3456
6.734.2.8 hasArray	3456
6.734.2.9 isReadOnly	3456
6.734.2.10put	3456
6.734.2.11put	3457
6.734.2.12setReadOnly	3457
6.734.2.13slice	3457
6.735decaf::nio::ShortBuffer Class Reference	3459
6.735.1 Detailed Description	3461
6.735.2 Constructor & Destructor Documentation	3461
6.735.2.1 ShortBuffer	3461
6.735.2.2 ~ShortBuffer	3461
6.735.3 Member Function Documentation	3461
6.735.3.1 allocate	3461
6.735.3.2 array	3462
6.735.3.3 arrayOffset	3462
6.735.3.4 asReadOnlyBuffer	3462
6.735.3.5 compact	3463
6.735.3.6 compareTo	3463
6.735.3.7 duplicate	3463
6.735.3.8 equals	3463
6.735.3.9 get	3463
6.735.3.10get	3464
6.735.3.11get	3464
6.735.3.12get	3465
6.735.3.13hasArray	3465
6.735.3.14operator<	3465
6.735.3.15operator==	3465
6.735.3.16put	3465
6.735.3.17put	3466
6.735.3.18put	3466

6.735.3.1	put	3466
6.735.3.2	put	3467
6.735.3.2	slice	3468
6.735.3.2	toString	3468
6.735.3.2	wrap	3468
6.735.3.2	wrap	3468
6.736	activemq::commands::ShutdownInfo Class Reference	3470
6.736.1	Constructor & Destructor Documentation	3471
6.736.1.1	ShutdownInfo	3471
6.736.1.2	~ShutdownInfo	3471
6.736.2	Member Function Documentation	3471
6.736.2.1	cloneDataStructure	3471
6.736.2.2	copyDataStructure	3471
6.736.2.3	equals	3471
6.736.2.4	getDataStructureType	3471
6.736.2.5	isShutdownInfo	3472
6.736.2.6	toString	3472
6.736.2.7	visit	3472
6.736.3	Field Documentation	3472
6.736.3.1	ID_SHUTDOWNINFO	3472
6.737	activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller Class Refer- ence	3473
6.737.1	Detailed Description	3473
6.737.2	Constructor & Destructor Documentation	3474
6.737.2.1	ShutdownInfoMarshaller	3474
6.737.2.2	~ShutdownInfoMarshaller	3474
6.737.3	Member Function Documentation	3474
6.737.3.1	createObject	3474
6.737.3.2	getDataStructureType	3474
6.737.3.3	looseMarshal	3474
6.737.3.4	looseUnmarshal	3475
6.737.3.5	tightMarshal1	3475
6.737.3.6	tightMarshal2	3475
6.737.3.7	tightUnmarshal	3476
6.738	activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller Class Refer- ence	3477
6.738.1	Detailed Description	3477

6.738.2 Constructor & Destructor Documentation	3478
6.738.2.1 ShutdownInfoMarshaller	3478
6.738.2.2 ~ShutdownInfoMarshaller	3478
6.738.3 Member Function Documentation	3478
6.738.3.1 createObject	3478
6.738.3.2 getDataStructureType	3478
6.738.3.3 looseMarshal	3478
6.738.3.4 looseUnmarshal	3479
6.738.3.5 tightMarshal1	3479
6.738.3.6 tightMarshal2	3479
6.738.3.7 tightUnmarshal	3480
6.739activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller Class Refer- ence	3481
6.739.1 Detailed Description	3481
6.739.2 Constructor & Destructor Documentation	3482
6.739.2.1 ShutdownInfoMarshaller	3482
6.739.2.2 ~ShutdownInfoMarshaller	3482
6.739.3 Member Function Documentation	3482
6.739.3.1 createObject	3482
6.739.3.2 getDataStructureType	3482
6.739.3.3 looseMarshal	3482
6.739.3.4 looseUnmarshal	3483
6.739.3.5 tightMarshal1	3483
6.739.3.6 tightMarshal2	3483
6.739.3.7 tightUnmarshal	3484
6.740activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller Class Refer- ence	3485
6.740.1 Detailed Description	3485
6.740.2 Constructor & Destructor Documentation	3486
6.740.2.1 ShutdownInfoMarshaller	3486
6.740.2.2 ~ShutdownInfoMarshaller	3486
6.740.3 Member Function Documentation	3486
6.740.3.1 createObject	3486
6.740.3.2 getDataStructureType	3486
6.740.3.3 looseMarshal	3486
6.740.3.4 looseUnmarshal	3487
6.740.3.5 tightMarshal1	3487

6.740.3.6	tightMarshal2	3487
6.740.3.7	tightUnmarshal	3488
6.741	activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller Class Reference	3489
6.741.1	Detailed Description	3489
6.741.2	Constructor & Destructor Documentation	3490
6.741.2.1	ShutdownInfoMarshaller	3490
6.741.2.2	~ShutdownInfoMarshaller	3490
6.741.3	Member Function Documentation	3490
6.741.3.1	createObject	3490
6.741.3.2	getDataStructureType	3490
6.741.3.3	looseMarshal	3490
6.741.3.4	looseUnmarshal	3491
6.741.3.5	tightMarshal1	3491
6.741.3.6	tightMarshal2	3491
6.741.3.7	tightUnmarshal	3492
6.742	activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller Class Reference	3493
6.742.1	Detailed Description	3493
6.742.2	Constructor & Destructor Documentation	3494
6.742.2.1	ShutdownInfoMarshaller	3494
6.742.2.2	~ShutdownInfoMarshaller	3494
6.742.3	Member Function Documentation	3494
6.742.3.1	createObject	3494
6.742.3.2	getDataStructureType	3494
6.742.3.3	looseMarshal	3494
6.742.3.4	looseUnmarshal	3495
6.742.3.5	tightMarshal1	3495
6.742.3.6	tightMarshal2	3495
6.742.3.7	tightUnmarshal	3496
6.743	decaf::security::SignatureException Class Reference	3497
6.743.1	Constructor & Destructor Documentation	3497
6.743.1.1	SignatureException	3497
6.743.1.2	SignatureException	3497
6.743.1.3	SignatureException	3498
6.743.1.4	SignatureException	3498
6.743.1.5	SignatureException	3498

6.743.1.6 SignatureException	3498
6.743.1.7 ~SignatureException	3499
6.743.2 Member Function Documentation	3499
6.743.2.1 clone	3499
6.744decaf::util::logging::SimpleFormatter Class Reference	3500
6.744.1 Detailed Description	3500
6.744.2 Constructor & Destructor Documentation	3500
6.744.2.1 SimpleFormatter	3500
6.744.2.2 ~SimpleFormatter	3500
6.744.3 Member Function Documentation	3500
6.744.3.1 format	3500
6.745decaf::util::logging::SimpleLogger Class Reference	3501
6.745.1 Constructor & Destructor Documentation	3501
6.745.1.1 SimpleLogger	3501
6.745.1.2 ~SimpleLogger	3501
6.745.2 Member Function Documentation	3502
6.745.2.1 debug	3502
6.745.2.2 error	3502
6.745.2.3 fatal	3502
6.745.2.4 info	3502
6.745.2.5 log	3502
6.745.2.6 mark	3502
6.745.2.7 warn	3502
6.746decaf::net::Socket Class Reference	3503
6.746.1 Detailed Description	3506
6.746.2 Constructor & Destructor Documentation	3506
6.746.2.1 Socket	3506
6.746.2.2 Socket	3506
6.746.2.3 Socket	3507
6.746.2.4 Socket	3507
6.746.2.5 Socket	3507
6.746.2.6 Socket	3508
6.746.2.7 ~Socket	3508
6.746.3 Member Function Documentation	3508
6.746.3.1 accepted	3508
6.746.3.2 bind	3508

6.746.3.3	checkClosed	3509
6.746.3.4	close	3509
6.746.3.5	connect	3509
6.746.3.6	connect	3509
6.746.3.7	ensureCreated	3510
6.746.3.8	getInetAddress	3510
6.746.3.9	getInputStream	3510
6.746.3.10	getKeepAlive	3510
6.746.3.11	getLocalAddress	3511
6.746.3.12	getLocalPort	3511
6.746.3.13	getOOBInline	3511
6.746.3.14	getOutputStream	3511
6.746.3.15	getPort	3511
6.746.3.16	getReceiveBufferSize	3512
6.746.3.17	getReuseAddress	3512
6.746.3.18	getSendBufferSize	3512
6.746.3.19	getSoLinger	3512
6.746.3.20	getSoTimeout	3513
6.746.3.21	getTcpNoDelay	3513
6.746.3.22	getTrafficClass	3513
6.746.3.23	initSocketImpl	3513
6.746.3.24	isBound	3513
6.746.3.25	isClosed	3514
6.746.3.26	isConnected	3514
6.746.3.27	isInputShutdown	3514
6.746.3.28	isOutputShutdown	3514
6.746.3.29	isSendUrgentData	3514
6.746.3.30	setKeepAlive	3514
6.746.3.31	setOOBInline	3515
6.746.3.32	setReceiveBufferSize	3515
6.746.3.33	setReuseAddress	3515
6.746.3.34	setSendBufferSize	3515
6.746.3.35	setSocketImplFactory	3516
6.746.3.36	setSoLinger	3516
6.746.3.37	setSoTimeout	3516
6.746.3.38	setTcpNoDelay	3517

6.746.3.39	setTrafficClass	3517
6.746.3.40	shutdownInput	3517
6.746.3.41	shutdownOutput	3518
6.746.3.42	toString	3518
6.746.4	Friends And Related Function Documentation	3518
6.746.4.1	ServerSocket	3518
6.746.5	Field Documentation	3518
6.746.5.1	impl	3518
6.747	decaf::net::SocketAddress Class Reference	3519
6.747.1	Detailed Description	3519
6.747.2	Constructor & Destructor Documentation	3519
6.747.2.1	~SocketAddress	3519
6.748	decaf::net::SocketError Class Reference	3520
6.748.1	Detailed Description	3520
6.748.2	Member Function Documentation	3520
6.748.2.1	getErrorCode	3520
6.748.2.2	getErrorString	3520
6.749	decaf::net::SocketException Class Reference	3521
6.749.1	Detailed Description	3521
6.749.2	Constructor & Destructor Documentation	3521
6.749.2.1	SocketException	3521
6.749.2.2	SocketException	3521
6.749.2.3	SocketException	3521
6.749.2.4	SocketException	3521
6.749.2.5	SocketException	3522
6.749.2.6	SocketException	3522
6.749.2.7	~SocketException	3522
6.749.3	Member Function Documentation	3522
6.749.3.1	clone	3522
6.750	decaf::net::SocketFactory Class Reference	3524
6.750.1	Detailed Description	3525
6.750.2	Constructor & Destructor Documentation	3525
6.750.2.1	SocketFactory	3525
6.750.2.2	~SocketFactory	3525
6.750.3	Member Function Documentation	3525
6.750.3.1	createSocket	3525

6.750.3.2 createSocket	3525
6.750.3.3 createSocket	3526
6.750.3.4 createSocket	3526
6.750.3.5 createSocket	3527
6.750.3.6 getDefault	3527
6.751decaf::internal::net::SocketFileDescriptor Class Reference	3528
6.751.1 Detailed Description	3528
6.751.2 Constructor & Destructor Documentation	3528
6.751.2.1 SocketFileDescriptor	3528
6.751.2.2 ~SocketFileDescriptor	3528
6.751.3 Member Function Documentation	3528
6.751.3.1 getValue	3528
6.752decaf::net::SocketImpl Class Reference	3529
6.752.1 Detailed Description	3531
6.752.2 Constructor & Destructor Documentation	3531
6.752.2.1 SocketImpl	3531
6.752.2.2 ~SocketImpl	3531
6.752.3 Member Function Documentation	3531
6.752.3.1 accept	3531
6.752.3.2 available	3531
6.752.3.3 bind	3531
6.752.3.4 close	3532
6.752.3.5 connect	3532
6.752.3.6 create	3532
6.752.3.7 getFileDescriptor	3533
6.752.3.8 getInetAddress	3533
6.752.3.9 getInputStream	3533
6.752.3.10getLocalAddress	3533
6.752.3.11getLocalPort	3533
6.752.3.12getOption	3534
6.752.3.13getOutputStream	3534
6.752.3.14getPort	3534
6.752.3.15listen	3534
6.752.3.16sendUrgentData	3535
6.752.3.17setOption	3535
6.752.3.18shutdownInput	3535

6.752.3.1	shutdownOutput	3536
6.752.3.2	supportsUrgentData	3536
6.752.3.2.1	toString	3536
6.752.4	Field Documentation	3536
6.752.4.1	address	3536
6.752.4.2	fd	3536
6.752.4.3	localPort	3536
6.752.4.4	port	3536
6.753	decaf::net::SocketImplFactory Class Reference	3537
6.753.1	Detailed Description	3537
6.753.2	Constructor & Destructor Documentation	3537
6.753.2.1	~SocketImplFactory	3537
6.753.3	Member Function Documentation	3537
6.753.3.1	createSocketImpl	3537
6.754	decaf::net::SocketOptions Class Reference	3538
6.754.1	Detailed Description	3539
6.754.2	Constructor & Destructor Documentation	3539
6.754.2.1	~SocketOptions	3539
6.754.3	Field Documentation	3539
6.754.3.1	SOCKET_OPTION_BINDADDR	3539
6.754.3.2	SOCKET_OPTION_BROADCAST	3539
6.754.3.3	SOCKET_OPTION_IP_MULTICAST_IF	3539
6.754.3.4	SOCKET_OPTION_IP_MULTICAST_IF2	3540
6.754.3.5	SOCKET_OPTION_IP_MULTICAST_LOOP	3540
6.754.3.6	SOCKET_OPTION_IP_TOS	3540
6.754.3.7	SOCKET_OPTION_KEEPALIVE	3540
6.754.3.8	SOCKET_OPTION_LINGER	3540
6.754.3.9	SOCKET_OPTION_OOBLINE	3540
6.754.3.10	SOCKET_OPTION_RCVBUF	3541
6.754.3.11	SOCKET_OPTION_REUSEADDR	3541
6.754.3.12	SOCKET_OPTION_SNDBUF	3541
6.754.3.13	SOCKET_OPTION_TCP_NODELAY	3541
6.754.3.14	SOCKET_OPTION_TIMEOUT	3541
6.755	decaf::net::SocketTimeoutException Class Reference	3542
6.755.1	Constructor & Destructor Documentation	3542
6.755.1.1	SocketTimeoutException	3542

6.755.1.2 SocketTimeoutException	3542
6.755.1.3 SocketTimeoutException	3543
6.755.1.4 SocketTimeoutException	3543
6.755.1.5 SocketTimeoutException	3543
6.755.1.6 SocketTimeoutException	3543
6.755.1.7 ~SocketTimeoutException	3544
6.755.2 Member Function Documentation	3544
6.755.2.1 clone	3544
6.756decaf::net::ssl::SSLContext Class Reference	3545
6.756.1 Detailed Description	3545
6.756.2 Constructor & Destructor Documentation	3545
6.756.2.1 SSLContext	3545
6.756.2.2 ~SSLContext	3545
6.756.3 Member Function Documentation	3545
6.756.3.1 getDefault	3545
6.756.3.2 getDefaultSSLParameters	3546
6.756.3.3 getServerSocketFactory	3546
6.756.3.4 getSocketFactory	3546
6.756.3.5 getSupportedSSLParameters	3546
6.756.3.6 setDefault	3547
6.757decaf::net::ssl::SSLContextSpi Class Reference	3548
6.757.1 Detailed Description	3548
6.757.2 Constructor & Destructor Documentation	3548
6.757.2.1 ~SSLContextSpi	3548
6.757.3 Member Function Documentation	3548
6.757.3.1 providerGetDefaultSSLParameters	3548
6.757.3.2 providerGetServerSocketFactory	3549
6.757.3.3 providerGetSocketFactory	3549
6.757.3.4 providerGetSupportedSSLParameters	3549
6.757.3.5 providerInit	3550
6.758decaf::net::ssl::SSLParameters Class Reference	3551
6.758.1 Constructor & Destructor Documentation	3551
6.758.1.1 SSLParameters	3551
6.758.1.2 SSLParameters	3551
6.758.1.3 SSLParameters	3552
6.758.1.4 ~SSLParameters	3552

6.758.2 Member Function Documentation	3552
6.758.2.1 getCipherSuites	3552
6.758.2.2 getNeedClientAuth	3552
6.758.2.3 getProtocols	3552
6.758.2.4 getWantClientAuth	3552
6.758.2.5 setCipherSuites	3553
6.758.2.6 setNeedClientAuth	3553
6.758.2.7 setProtocols	3553
6.758.2.8 setWantClientAuth	3553
6.759decaf::net::ssl::SSLServerSocket Class Reference	3554
6.759.1 Detailed Description	3555
6.759.2 Constructor & Destructor Documentation	3555
6.759.2.1 SSLServerSocket	3555
6.759.2.2 SSLServerSocket	3555
6.759.2.3 SSLServerSocket	3555
6.759.2.4 SSLServerSocket	3556
6.759.2.5 ~SSLServerSocket	3556
6.759.3 Member Function Documentation	3556
6.759.3.1 getEnabledCipherSuites	3556
6.759.3.2 getEnabledProtocols	3557
6.759.3.3 getNeedClientAuth	3557
6.759.3.4 getSupportedCipherSuites	3557
6.759.3.5 getSupportedProtocols	3557
6.759.3.6 getWantClientAuth	3558
6.759.3.7 setEnabledCipherSuites	3558
6.759.3.8 setEnabledProtocols	3558
6.759.3.9 setNeedClientAuth	3558
6.759.3.10set WantClientAuth	3559
6.760decaf::net::ssl::SSLServerSocketFactory Class Reference	3560
6.760.1 Detailed Description	3560
6.760.2 Constructor & Destructor Documentation	3561
6.760.2.1 SSLServerSocketFactory	3561
6.760.2.2 ~SSLServerSocketFactory	3561
6.760.3 Member Function Documentation	3561
6.760.3.1 getDefault	3561
6.760.3.2 getDefaultCipherSuites	3561

6.760.3.3	getSupportedCipherSuites	3561
6.761	decaf::net::ssl::SSLSocket Class Reference	3563
6.761.1	Detailed Description	3564
6.761.2	Constructor & Destructor Documentation	3564
6.761.2.1	SSLSocket	3564
6.761.2.2	SSLSocket	3564
6.761.2.3	SSLSocket	3565
6.761.2.4	SSLSocket	3565
6.761.2.5	SSLSocket	3566
6.761.2.6	~SSLSocket	3566
6.761.3	Member Function Documentation	3566
6.761.3.1	getEnabledCipherSuites	3566
6.761.3.2	getEnabledProtocols	3566
6.761.3.3	getNeedClientAuth	3567
6.761.3.4	getSSLParameters	3567
6.761.3.5	getSupportedCipherSuites	3567
6.761.3.6	getSupportedProtocols	3567
6.761.3.7	getUseClientMode	3568
6.761.3.8	getWantClientAuth	3568
6.761.3.9	setEnabledCipherSuites	3568
6.761.3.10	setEnabledProtocols	3568
6.761.3.11	setNeedClientAuth	3569
6.761.3.12	setSSLParameters	3569
6.761.3.13	setUseClientMode	3569
6.761.3.14	setWantClientAuth	3570
6.761.3.15	startHandshake	3570
6.762	decaf::net::ssl::SSLSocketFactory Class Reference	3571
6.762.1	Detailed Description	3571
6.762.2	Constructor & Destructor Documentation	3572
6.762.2.1	SSLSocketFactory	3572
6.762.2.2	~SSLSocketFactory	3572
6.762.3	Member Function Documentation	3572
6.762.3.1	createSocket	3572
6.762.3.2	getDefault	3572
6.762.3.3	getDefaultCipherSuites	3573
6.762.3.4	getSupportedCipherSuites	3573

6.763activemq::transport::tcp::SslTransport Class Reference	3574
6.763.1 Detailed Description	3574
6.763.2 Constructor & Destructor Documentation	3574
6.763.2.1 SslTransport	3574
6.763.2.2 ~SslTransport	3575
6.763.3 Member Function Documentation	3575
6.763.3.1 configureSocket	3575
6.763.3.2 createSocket	3575
6.764activemq::transport::tcp::SslTransportFactory Class Reference	3576
6.764.1 Constructor & Destructor Documentation	3576
6.764.1.1 ~SslTransportFactory	3576
6.764.2 Member Function Documentation	3576
6.764.2.1 doCreateComposite	3576
6.765activemq::commands::BrokerError::StackTraceElement Struct Reference	3578
6.765.1 Field Documentation	3578
6.765.1.1 className	3578
6.765.1.2 fileName	3578
6.765.1.3 lineNumber	3578
6.765.1.4 methodName	3578
6.766decaf::internal::io::StandardErrorOutputStream Class Reference	3579
6.766.1 Detailed Description	3579
6.766.2 Constructor & Destructor Documentation	3580
6.766.2.1 StandardErrorOutputStream	3580
6.766.2.2 ~StandardErrorOutputStream	3580
6.766.3 Member Function Documentation	3580
6.766.3.1 close	3580
6.766.3.2 doWriteArrayBounded	3580
6.766.3.3 doWriteByte	3580
6.766.3.4 flush	3580
6.767decaf::internal::io::StandardInputStream Class Reference	3582
6.767.1 Constructor & Destructor Documentation	3582
6.767.1.1 StandardInputStream	3582
6.767.1.2 ~StandardInputStream	3582
6.767.2 Member Function Documentation	3582
6.767.2.1 available	3582
6.767.2.2 doReadByte	3583

6.768	decaf::internal::io::StandardOutputStream Class Reference	3584
6.768.1	Constructor & Destructor Documentation	3584
6.768.1.1	StandardOutputStream	3584
6.768.1.2	~StandardOutputStream	3584
6.768.2	Member Function Documentation	3584
6.768.2.1	close	3584
6.768.2.2	doWriteArrayBounded	3585
6.768.2.3	doWriteByte	3585
6.768.2.4	flush	3585
6.769	cms::Startable Class Reference	3586
6.769.1	Detailed Description	3586
6.769.2	Constructor & Destructor Documentation	3586
6.769.2.1	~Startable	3586
6.769.3	Member Function Documentation	3586
6.769.3.1	start	3586
6.770	decaf::lang::STATIC_CAST_TOKEN Struct Reference	3587
6.771	activemq::core::ActiveMQConstants::StaticInitializer Class Reference	3588
6.771.1	Constructor & Destructor Documentation	3588
6.771.1.1	StaticInitializer	3588
6.771.1.2	~StaticInitializer	3588
6.771.2	Field Documentation	3588
6.771.2.1	destOptionMap	3588
6.771.2.2	destOptions	3588
6.771.2.3	uriParams	3588
6.771.2.4	uriParamsMap	3588
6.772	decaf::util::StlList< E > Class Template Reference	3589
6.772.1	Detailed Description	3593
6.772.2	Constructor & Destructor Documentation	3593
6.772.2.1	StlList	3593
6.772.2.2	StlList	3594
6.772.2.3	StlList	3594
6.772.2.4	~StlList	3594
6.772.3	Member Function Documentation	3594
6.772.3.1	add	3594
6.772.3.2	add	3594
6.772.3.3	addAll	3595

6.772.3.4 clear	3596
6.772.3.5 contains	3596
6.772.3.6 copy	3596
6.772.3.7 equals	3597
6.772.3.8 get	3597
6.772.3.9 indexOf	3597
6.772.3.10isEmpty	3598
6.772.3.11iterator	3598
6.772.3.12iterator	3598
6.772.3.13lastIndexOf	3598
6.772.3.14listIterator	3598
6.772.3.15listIterator	3599
6.772.3.16listIterator	3599
6.772.3.17listIterator	3599
6.772.3.18remove	3599
6.772.3.19remove	3600
6.772.3.20set	3600
6.772.3.21size	3601
6.773decaf::util::StlMap< K, V, COMPARATOR > Class Template Reference	3602
6.773.1 Detailed Description	3605
6.773.2 Constructor & Destructor Documentation	3605
6.773.2.1 StlMap	3605
6.773.2.2 StlMap	3606
6.773.2.3 StlMap	3606
6.773.2.4 ~StlMap	3606
6.773.3 Member Function Documentation	3606
6.773.3.1 clear	3606
6.773.3.2 containsKey	3606
6.773.3.3 containsValue	3607
6.773.3.4 copy	3607
6.773.3.5 copy	3607
6.773.3.6 equals	3608
6.773.3.7 equals	3608
6.773.3.8 get	3608
6.773.3.9 get	3608
6.773.3.10isEmpty	3609

6.773.3.1	keySet	3609
6.773.3.12	lock	3609
6.773.3.13	notify	3610
6.773.3.14	notifyAll	3610
6.773.3.15	put	3610
6.773.3.16	putAll	3611
6.773.3.17	putAll	3611
6.773.3.18	remove	3611
6.773.3.19	size	3612
6.773.3.20	tryLock	3612
6.773.3.21	unlock	3612
6.773.3.22	values	3612
6.773.3.23	wait	3613
6.773.3.24	wait	3613
6.773.3.25	wait	3614
6.774	decaf::util::StlQueue< T > Class Template Reference	3615
6.774.1	Detailed Description	3616
6.774.2	Constructor & Destructor Documentation	3617
6.774.2.1	StlQueue	3617
6.774.2.2	~StlQueue	3617
6.774.3	Member Function Documentation	3617
6.774.3.1	back	3617
6.774.3.2	back	3617
6.774.3.3	clear	3617
6.774.3.4	empty	3617
6.774.3.5	enqueueFront	3618
6.774.3.6	front	3618
6.774.3.7	front	3618
6.774.3.8	getSafeValue	3618
6.774.3.9	iterator	3618
6.774.3.10	lock	3619
6.774.3.11	notify	3619
6.774.3.12	notifyAll	3619
6.774.3.13	pop	3619
6.774.3.14	push	3620
6.774.3.15	reverse	3620

6.774.3.16	size	3620
6.774.3.17	toArray	3620
6.774.3.18	tryLock	3620
6.774.3.19	unlock	3621
6.774.3.20	wait	3621
6.774.3.21	lwait	3621
6.774.3.22	wait	3622
6.775	decaf::util::StlSet< E > Class Template Reference	3623
6.775.1	Detailed Description	3625
6.775.2	Constructor & Destructor Documentation	3625
6.775.2.1	StlSet	3625
6.775.2.2	StlSet	3625
6.775.2.3	StlSet	3625
6.775.2.4	~StlSet	3625
6.775.3	Member Function Documentation	3625
6.775.3.1	add	3625
6.775.3.2	clear	3626
6.775.3.3	contains	3627
6.775.3.4	copy	3627
6.775.3.5	equals	3627
6.775.3.6	isEmpty	3627
6.775.3.7	iterator	3627
6.775.3.8	iterator	3628
6.775.3.9	remove	3628
6.775.3.10	size	3628
6.776	activemq::wireformat::stomp::StompCommandConstants Class Reference	3629
6.776.1	Field Documentation	3631
6.776.1.1	ABORT	3631
6.776.1.2	ACK	3631
6.776.1.3	ACK_AUTO	3631
6.776.1.4	ACK_CLIENT	3631
6.776.1.5	ACK_INDIVIDUAL	3631
6.776.1.6	BEGIN	3631
6.776.1.7	BYTES	3631
6.776.1.8	COMMIT	3631
6.776.1.9	CONNECT	3631

6.776.1.10	CONNECTED	3631
6.776.1.11	DISCONNECT	3631
6.776.1.12	ERROR_CMD	3631
6.776.1.13	HEADER_ACK	3631
6.776.1.14	HEADER_CLIENT_ID	3631
6.776.1.15	HEADER_CONSUMERPRIORITY	3631
6.776.1.16	HEADER_CONTENTLENGTH	3631
6.776.1.17	HEADER_CORRELATIONID	3631
6.776.1.18	HEADER_DESTINATION	3631
6.776.1.19	HEADER_DISPATCH_ASYNC	3631
6.776.1.20	HEADER_EXCLUSIVE	3631
6.776.1.21	HEADER_EXPIRES	3631
6.776.1.22	HEADER_ID	3631
6.776.1.23	HEADER_JMSPRIORITY	3631
6.776.1.24	HEADER_LOGIN	3631
6.776.1.25	HEADER_MAXPENDINGMSGLIMIT	3631
6.776.1.26	HEADER_MESSAGE	3631
6.776.1.27	HEADER_MESSAGEID	3631
6.776.1.28	HEADER_NOLOCAL	3631
6.776.1.29	HEADER_OLDSUBSCRIPTIONNAME	3631
6.776.1.30	HEADER_PASSWORD	3631
6.776.1.31	HEADER_PERSISTENT	3631
6.776.1.32	HEADER_PREFETCHSIZE	3631
6.776.1.33	HEADER_RECEIPT_REQUIRED	3631
6.776.1.34	HEADER_RECEIPTID	3631
6.776.1.35	HEADER_REDELIVERED	3631
6.776.1.36	HEADER_REDELIVERYCOUNT	3631
6.776.1.37	HEADER_REPLYTO	3631
6.776.1.38	HEADER_REQUESTID	3631
6.776.1.39	HEADER_RESPONSEID	3631
6.776.1.40	HEADER_RETROACTIVE	3631
6.776.1.41	HEADER_SELECTOR	3631
6.776.1.42	HEADER_SESSIONID	3631
6.776.1.43	HEADER_SUBSCRIPTION	3631
6.776.1.44	HEADER_SUBSCRIPTIONNAME	3631
6.776.1.45	HEADER_TIMESTAMP	3631

6.776.1.46	HEADER_TRANSACTIONID	3631
6.776.1.47	HEADER_TRANSFORMATION	3631
6.776.1.48	HEADER_TRANSFORMATION_ERROR	3631
6.776.1.49	HEADER_TYPE	3631
6.776.1.50	MESSAGE	3631
6.776.1.51	QUEUE_PREFIX	3631
6.776.1.52	RECEIPT	3631
6.776.1.53	SEND	3631
6.776.1.54	SUBSCRIBE	3631
6.776.1.55	TEMPQUEUE_PREFIX	3631
6.776.1.56	TEMPTOPIC_PREFIX	3631
6.776.1.57	TEXT	3631
6.776.1.58	TOPIC_PREFIX	3631
6.776.1.59	UNSUBSCRIBE	3631
6.777	activemq::wireformat::stomp::StompFrame Class Reference	3633
6.777.1	Detailed Description	3634
6.777.2	Constructor & Destructor Documentation	3634
6.777.2.1	StompFrame	3634
6.777.2.2	~StompFrame	3634
6.777.3	Member Function Documentation	3634
6.777.3.1	clone	3634
6.777.3.2	copy	3634
6.777.3.3	fromStream	3635
6.777.3.4	getBody	3635
6.777.3.5	getBody	3635
6.777.3.6	getBodyLength	3635
6.777.3.7	getCommand	3635
6.777.3.8	getProperties	3635
6.777.3.9	getProperties	3635
6.777.3.10	getProperty	3636
6.777.3.11	hasProperty	3636
6.777.3.12	removeProperty	3636
6.777.3.13	setBody	3636
6.777.3.14	setCommand	3637
6.777.3.15	setProperty	3637
6.777.3.16	oStream	3637

6.778activemq::wireformat::stomp::StompHelper Class Reference	3638
6.778.1 Detailed Description	3639
6.778.2 Constructor & Destructor Documentation	3639
6.778.2.1 StompHelper	3639
6.778.2.2 ~StompHelper	3639
6.778.3 Member Function Documentation	3639
6.778.3.1 convertConsumerId	3639
6.778.3.2 convertConsumerId	3639
6.778.3.3 convertDestination	3639
6.778.3.4 convertDestination	3640
6.778.3.5 convertMessageId	3640
6.778.3.6 convertMessageId	3640
6.778.3.7 convertProducerId	3640
6.778.3.8 convertProducerId	3641
6.778.3.9 convertProperties	3641
6.778.3.10convertProperties	3641
6.778.3.11convertTransactionId	3641
6.778.3.12convertTransactionId	3642
6.779activemq::wireformat::stomp::StompWireFormat Class Reference	3643
6.779.1 Constructor & Destructor Documentation	3644
6.779.1.1 StompWireFormat	3644
6.779.1.2 ~StompWireFormat	3644
6.779.2 Member Function Documentation	3644
6.779.2.1 createNegotiator	3644
6.779.2.2 getVersion	3644
6.779.2.3 hasNegotiator	3644
6.779.2.4 inReceive	3645
6.779.2.5 marshal	3645
6.779.2.6 setVersion	3645
6.779.2.7 unmarshal	3645
6.780activemq::wireformat::stomp::StompWireFormatFactory Class Reference	3647
6.780.1 Detailed Description	3647
6.780.2 Constructor & Destructor Documentation	3647
6.780.2.1 StompWireFormatFactory	3647
6.780.2.2 ~StompWireFormatFactory	3647
6.780.3 Member Function Documentation	3647

6.780.3.1 createWireFormat	3647
6.781cms::Stoppable Class Reference	3648
6.781.1 Detailed Description	3648
6.781.2 Constructor & Destructor Documentation	3648
6.781.2.1 ~Stoppable	3648
6.781.3 Member Function Documentation	3648
6.781.3.1 stop	3648
6.782decaf::util::logging::StreamHandler Class Reference	3649
6.782.1 Detailed Description	3649
6.782.2 Constructor & Destructor Documentation	3650
6.782.2.1 StreamHandler	3650
6.782.2.2 StreamHandler	3650
6.782.2.3 ~StreamHandler	3650
6.782.3 Member Function Documentation	3650
6.782.3.1 close	3650
6.782.3.2 close	3650
6.782.3.3 flush	3651
6.782.3.4 isLoggable	3651
6.782.3.5 publish	3651
6.782.3.6 setOutputStream	3651
6.783cms::StreamMessage Class Reference	3652
6.783.1 Detailed Description	3654
6.783.2 Constructor & Destructor Documentation	3655
6.783.2.1 ~StreamMessage	3655
6.783.3 Member Function Documentation	3655
6.783.3.1 readBoolean	3655
6.783.3.2 readByte	3655
6.783.3.3 readBytes	3656
6.783.3.4 readBytes	3656
6.783.3.5 readChar	3657
6.783.3.6 readDouble	3657
6.783.3.7 readFloat	3658
6.783.3.8 readInt	3658
6.783.3.9 readLong	3658
6.783.3.10readShort	3659
6.783.3.11readString	3659

6.783.3.12	readUnsignedShort	3660
6.783.3.13	writeBoolean	3660
6.783.3.14	writeByte	3660
6.783.3.15	writeBytes	3661
6.783.3.16	writeBytes	3661
6.783.3.17	writeChar	3661
6.783.3.18	writeDouble	3662
6.783.3.19	writeFloat	3662
6.783.3.20	writeInt	3662
6.783.3.21	writeLong	3663
6.783.3.22	writeShort	3663
6.783.3.23	writeString	3663
6.783.3.24	writeUnsignedShort	3664
6.784	decaf::lang::String Class Reference	3665
6.784.1	Detailed Description	3666
6.784.2	Constructor & Destructor Documentation	3666
6.784.2.1	String	3666
6.784.2.2	String	3666
6.784.2.3	~String	3666
6.784.3	Member Function Documentation	3666
6.784.3.1	charAt	3666
6.784.3.2	isEmpty	3667
6.784.3.3	length	3667
6.784.3.4	subSequence	3667
6.784.3.5	toString	3667
6.785	decaf::util::StringTokenizer Class Reference	3668
6.785.1	Constructor & Destructor Documentation	3668
6.785.1.1	StringTokenizer	3668
6.785.1.2	~StringTokenizer	3669
6.785.2	Member Function Documentation	3669
6.785.2.1	countTokens	3669
6.785.2.2	hasMoreTokens	3669
6.785.2.3	nextToken	3669
6.785.2.4	nextToken	3669
6.785.2.5	reset	3670
6.785.2.6	toArray	3670

6.786	activemq::commands::SubscriptionInfo Class Reference	3671
6.786.1	Constructor & Destructor Documentation	3672
6.786.1.1	SubscriptionInfo	3672
6.786.1.2	~SubscriptionInfo	3672
6.786.2	Member Function Documentation	3672
6.786.2.1	cloneDataStructure	3672
6.786.2.2	copyDataStructure	3672
6.786.2.3	equals	3672
6.786.2.4	getClientId	3673
6.786.2.5	getClientId	3673
6.786.2.6	getDataStructureType	3673
6.786.2.7	getDestination	3674
6.786.2.8	getDestination	3674
6.786.2.9	getSelector	3674
6.786.2.10	getSelector	3674
6.786.2.11	getSubscriptionName	3674
6.786.2.12	getSubscriptionName	3674
6.786.2.13	getSubscribedDestination	3674
6.786.2.14	getSubscribedDestination	3674
6.786.2.15	setClientId	3674
6.786.2.16	setDestination	3674
6.786.2.17	setSelector	3674
6.786.2.18	setSubscriptionName	3674
6.786.2.19	setSubscribedDestination	3674
6.786.2.20	toString	3674
6.786.3	Field Documentation	3675
6.786.3.1	clientId	3675
6.786.3.2	destination	3675
6.786.3.3	ID_SUBSCRIPTIONINFO	3675
6.786.3.4	selector	3675
6.786.3.5	subscriptionName	3675
6.786.3.6	subscribedDestination	3675
6.787	activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller Class Reference	3676
6.787.1	Detailed Description	3676
6.787.2	Constructor & Destructor Documentation	3677
6.787.2.1	SubscriptionInfoMarshaller	3677

6.787.2.2 ~SubscriptionInfoMarshaller	3677
6.787.3 Member Function Documentation	3677
6.787.3.1 createObject	3677
6.787.3.2 getDataStructureType	3677
6.787.3.3 looseMarshal	3677
6.787.3.4 looseUnmarshal	3678
6.787.3.5 tightMarshal1	3678
6.787.3.6 tightMarshal2	3678
6.787.3.7 tightUnmarshal	3679
6.788activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller Class	
Reference	3680
6.788.1 Detailed Description	3680
6.788.2 Constructor & Destructor Documentation	3681
6.788.2.1 SubscriptionInfoMarshaller	3681
6.788.2.2 ~SubscriptionInfoMarshaller	3681
6.788.3 Member Function Documentation	3681
6.788.3.1 createObject	3681
6.788.3.2 getDataStructureType	3681
6.788.3.3 looseMarshal	3681
6.788.3.4 looseUnmarshal	3682
6.788.3.5 tightMarshal1	3682
6.788.3.6 tightMarshal2	3682
6.788.3.7 tightUnmarshal	3683
6.789activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller Class	
Reference	3684
6.789.1 Detailed Description	3684
6.789.2 Constructor & Destructor Documentation	3685
6.789.2.1 SubscriptionInfoMarshaller	3685
6.789.2.2 ~SubscriptionInfoMarshaller	3685
6.789.3 Member Function Documentation	3685
6.789.3.1 createObject	3685
6.789.3.2 getDataStructureType	3685
6.789.3.3 looseMarshal	3685
6.789.3.4 looseUnmarshal	3686
6.789.3.5 tightMarshal1	3686
6.789.3.6 tightMarshal2	3686
6.789.3.7 tightUnmarshal	3687

6.790	activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	Class	
	Reference		3688
6.790.1	Detailed Description		3688
6.790.2	Constructor & Destructor Documentation		3689
6.790.2.1	SubscriptionInfoMarshaller		3689
6.790.2.2	~SubscriptionInfoMarshaller		3689
6.790.3	Member Function Documentation		3689
6.790.3.1	createObject		3689
6.790.3.2	getDataStructureType		3689
6.790.3.3	looseMarshal		3689
6.790.3.4	looseUnmarshal		3690
6.790.3.5	tightMarshal1		3690
6.790.3.6	tightMarshal2		3690
6.790.3.7	tightUnmarshal		3691
6.791	activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller	Class	
	Reference		3692
6.791.1	Detailed Description		3692
6.791.2	Constructor & Destructor Documentation		3693
6.791.2.1	SubscriptionInfoMarshaller		3693
6.791.2.2	~SubscriptionInfoMarshaller		3693
6.791.3	Member Function Documentation		3693
6.791.3.1	createObject		3693
6.791.3.2	getDataStructureType		3693
6.791.3.3	looseMarshal		3693
6.791.3.4	looseUnmarshal		3694
6.791.3.5	tightMarshal1		3694
6.791.3.6	tightMarshal2		3694
6.791.3.7	tightUnmarshal		3695
6.792	activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	Class	
	Reference		3696
6.792.1	Detailed Description		3696
6.792.2	Constructor & Destructor Documentation		3697
6.792.2.1	SubscriptionInfoMarshaller		3697
6.792.2.2	~SubscriptionInfoMarshaller		3697
6.792.3	Member Function Documentation		3697
6.792.3.1	createObject		3697
6.792.3.2	getDataStructureType		3697

6.792.3.3 looseMarshal	3697
6.792.3.4 looseUnmarshal	3698
6.792.3.5 tightMarshal1	3698
6.792.3.6 tightMarshal2	3698
6.792.3.7 tightUnmarshal	3699
6.793decaf::util::concurrent::Synchronizable Class Reference	3700
6.793.1 Detailed Description	3701
6.793.2 Constructor & Destructor Documentation	3701
6.793.2.1 ~Synchronizable	3701
6.793.3 Member Function Documentation	3701
6.793.3.1 lock	3701
6.793.3.2 notify	3702
6.793.3.3 notifyAll	3703
6.793.3.4 tryLock	3704
6.793.3.5 unlock	3705
6.793.3.6 wait	3707
6.793.3.7 wait	3708
6.793.3.8 wait	3709
6.794decaf::internal::util::concurrent::SynchronizableImpl Class Reference	3711
6.794.1 Detailed Description	3712
6.794.2 Constructor & Destructor Documentation	3712
6.794.2.1 SynchronizableImpl	3712
6.794.2.2 ~SynchronizableImpl	3712
6.794.3 Member Function Documentation	3712
6.794.3.1 lock	3712
6.794.3.2 notify	3712
6.794.3.3 notifyAll	3712
6.794.3.4 tryLock	3713
6.794.3.5 unlock	3713
6.794.3.6 wait	3713
6.794.3.7 wait	3714
6.794.3.8 wait	3714
6.795activemq::core::Synchronization Class Reference	3715
6.795.1 Detailed Description	3715
6.795.2 Constructor & Destructor Documentation	3715
6.795.2.1 ~Synchronization	3715

6.795.3 Member Function Documentation	3715
6.795.3.1 afterCommit	3715
6.795.3.2 afterRollback	3715
6.795.3.3 beforeEnd	3715
6.796decaf::util::concurrent::SynchronousQueue< E > Class Template Reference	3716
6.796.1 Detailed Description	3717
6.796.2 Constructor & Destructor Documentation	3718
6.796.2.1 SynchronousQueue	3718
6.796.2.2 ~SynchronousQueue	3718
6.796.3 Member Function Documentation	3718
6.796.3.1 clear	3718
6.796.3.2 contains	3719
6.796.3.3 containsAll	3719
6.796.3.4 drainTo	3719
6.796.3.5 drainTo	3720
6.796.3.6 equals	3720
6.796.3.7 isEmpty	3721
6.796.3.8 iterator	3721
6.796.3.9 iterator	3721
6.796.3.10offer	3721
6.796.3.11offer	3722
6.796.3.12peek	3722
6.796.3.13poll	3722
6.796.3.14poll	3722
6.796.3.15put	3723
6.796.3.16remainingCapacity	3723
6.796.3.17remove	3724
6.796.3.18removeAll	3724
6.796.3.19retainAll	3724
6.796.3.20size	3724
6.796.3.21take	3724
6.796.3.22toArray	3724
6.797decaf::lang::System Class Reference	3726
6.797.1 Detailed Description	3727
6.797.2 Constructor & Destructor Documentation	3728
6.797.2.1 System	3728

6.797.2.2	~System	3728
6.797.3	Member Function Documentation	3728
6.797.3.1	arraycopy	3728
6.797.3.2	arraycopy	3728
6.797.3.3	arraycopy	3729
6.797.3.4	arraycopy	3729
6.797.3.5	availableProcessors	3729
6.797.3.6	clearProperty	3730
6.797.3.7	currentTimeMillis	3730
6.797.3.8	getenv	3730
6.797.3.9	getenv	3730
6.797.3.10	getProperties	3731
6.797.3.11	getProperty	3731
6.797.3.12	getProperty	3731
6.797.3.13	nanoTime	3732
6.797.3.14	setenv	3732
6.797.3.15	setProperty	3732
6.797.3.16	unsetenv	3733
6.797.4	Friends And Related Function Documentation	3733
6.797.4.1	decaf::lang::Runtime	3733
6.798	activemq::threads::Task Class Reference	3734
6.798.1	Detailed Description	3734
6.798.2	Constructor & Destructor Documentation	3734
6.798.2.1	~Task	3734
6.798.3	Member Function Documentation	3734
6.798.3.1	iterate	3734
6.799	decaf::util::concurrent::TaskListener Class Reference	3735
6.799.1	Constructor & Destructor Documentation	3735
6.799.1.1	~TaskListener	3735
6.799.2	Member Function Documentation	3735
6.799.2.1	onTaskComplete	3735
6.799.2.2	onTaskException	3735
6.800	activemq::threads::TaskRunner Class Reference	3736
6.800.1	Constructor & Destructor Documentation	3736
6.800.1.1	~TaskRunner	3736
6.800.2	Member Function Documentation	3736

6.800.2.1 shutdown	3736
6.800.2.2 shutdown	3736
6.800.2.3 wakeup	3737
6.801decaf::internal::net::tcp::TcpSocket Class Reference	3738
6.801.1 Detailed Description	3740
6.801.2 Constructor & Destructor Documentation	3741
6.801.2.1 TcpSocket	3741
6.801.2.2 ~TcpSocket	3741
6.801.3 Member Function Documentation	3741
6.801.3.1 accept	3741
6.801.3.2 available	3741
6.801.3.3 bind	3741
6.801.3.4 checkResult	3742
6.801.3.5 close	3742
6.801.3.6 connect	3742
6.801.3.7 create	3742
6.801.3.8 getInputStream	3743
6.801.3.9 getLocalAddress	3743
6.801.3.10getOption	3743
6.801.3.11getOutputStream	3743
6.801.3.12getSocketHandle	3744
6.801.3.13sClosed	3744
6.801.3.14sConnected	3744
6.801.3.15listen	3744
6.801.3.16read	3745
6.801.3.17setOption	3745
6.801.3.18shutdownInput	3745
6.801.3.19shutdownOutput	3746
6.801.3.20write	3746
6.802decaf::internal::net::tcp::TcpSocketInputStream Class Reference	3747
6.802.1 Detailed Description	3747
6.802.2 Constructor & Destructor Documentation	3748
6.802.2.1 TcpSocketInputStream	3748
6.802.2.2 ~TcpSocketInputStream	3748
6.802.3 Member Function Documentation	3748
6.802.3.1 available	3748

6.802.3.2 close	3748
6.802.3.3 doReadArrayBounded	3749
6.802.3.4 doReadByte	3749
6.802.3.5 skip	3749
6.803decaf::internal::net::tcp::TcpSocketOutputStream Class Reference	3750
6.803.1 Detailed Description	3750
6.803.2 Constructor & Destructor Documentation	3750
6.803.2.1 TcpSocketOutputStream	3750
6.803.2.2 ~TcpSocketOutputStream	3751
6.803.3 Member Function Documentation	3751
6.803.3.1 close	3751
6.803.3.2 doWriteArrayBounded	3751
6.803.3.3 doWriteByte	3751
6.804activemq::transport::tcp::TcpTransport Class Reference	3752
6.804.1 Detailed Description	3753
6.804.2 Constructor & Destructor Documentation	3753
6.804.2.1 TcpTransport	3753
6.804.2.2 ~TcpTransport	3753
6.804.3 Member Function Documentation	3753
6.804.3.1 close	3753
6.804.3.2 configureSocket	3753
6.804.3.3 connect	3754
6.804.3.4 createSocket	3754
6.804.3.5 isClosed	3754
6.804.3.6 isConnected	3754
6.804.3.7 isFaultTolerant	3755
6.805activemq::transport::tcp::TcpTransportFactory Class Reference	3756
6.805.1 Detailed Description	3756
6.805.2 Constructor & Destructor Documentation	3757
6.805.2.1 ~TcpTransportFactory	3757
6.805.3 Member Function Documentation	3757
6.805.3.1 create	3757
6.805.3.2 createComposite	3757
6.805.3.3 doCreateComposite	3757
6.806cms::TemporaryQueue Class Reference	3759
6.806.1 Detailed Description	3759

6.806.2 Constructor & Destructor Documentation	3759
6.806.2.1 ~TemporaryQueue	3759
6.806.3 Member Function Documentation	3759
6.806.3.1 destroy	3759
6.806.3.2 getQueueName	3760
6.807cms::TemporaryTopic Class Reference	3761
6.807.1 Detailed Description	3761
6.807.2 Constructor & Destructor Documentation	3761
6.807.2.1 ~TemporaryTopic	3761
6.807.3 Member Function Documentation	3761
6.807.3.1 destroy	3761
6.807.3.2 getTopicName	3762
6.808cms::TextMessage Class Reference	3763
6.808.1 Detailed Description	3763
6.808.2 Constructor & Destructor Documentation	3763
6.808.2.1 ~TextMessage	3763
6.808.3 Member Function Documentation	3763
6.808.3.1 getText	3763
6.808.3.2 setText	3764
6.808.3.3 setText	3764
6.809decaf::lang::Thread Class Reference	3765
6.809.1 Detailed Description	3767
6.809.2 Member Enumeration Documentation	3768
6.809.2.1 State	3768
6.809.3 Constructor & Destructor Documentation	3768
6.809.3.1 Thread	3768
6.809.3.2 Thread	3768
6.809.3.3 Thread	3768
6.809.3.4 Thread	3769
6.809.3.5 ~Thread	3769
6.809.4 Member Function Documentation	3769
6.809.4.1 currentThread	3769
6.809.4.2 getId	3769
6.809.4.3 getName	3769
6.809.4.4 getPriority	3769
6.809.4.5 getState	3770

6.809.4.6	getUncaughtExceptionHandler	3770
6.809.4.7	isAlive	3770
6.809.4.8	join	3770
6.809.4.9	join	3770
6.809.4.10	join	3771
6.809.4.11	run	3771
6.809.4.12	setName	3771
6.809.4.13	setPriority	3771
6.809.4.14	setUncaughtExceptionHandler	3772
6.809.4.15	sleep	3772
6.809.4.16	sleep	3772
6.809.4.17	start	3772
6.809.4.18	toString	3773
6.809.4.19	yield	3773
6.809.5	Friends And Related Function Documentation	3773
6.809.5.1	decaf::lang::Runtime	3773
6.809.5.2	decaf::util::concurrent::locks::LockSupport	3773
6.809.6	Field Documentation	3773
6.809.6.1	MAX_PRIORITY	3773
6.809.6.2	MIN_PRIORITY	3773
6.809.6.3	NORM_PRIORITY	3773
6.810	decaf::util::concurrent::ThreadFactory Class Reference	3774
6.810.1	Detailed Description	3774
6.810.2	Constructor & Destructor Documentation	3774
6.810.2.1	~ThreadFactory	3774
6.810.3	Member Function Documentation	3774
6.810.3.1	newThread	3774
6.811	decaf::lang::ThreadGroup Class Reference	3776
6.811.1	Detailed Description	3776
6.811.2	Constructor & Destructor Documentation	3776
6.811.2.1	ThreadGroup	3776
6.811.2.2	~ThreadGroup	3776
6.812	decaf::util::concurrent::ThreadPool Class Reference	3777
6.812.1	Detailed Description	3778
6.812.2	Member Typedef Documentation	3779
6.812.2.1	Task	3779

6.812.3 Constructor & Destructor Documentation	3779
6.812.3.1 ThreadPool	3779
6.812.3.2 ~ThreadPool	3779
6.812.4 Member Function Documentation	3779
6.812.4.1 deQueueTask	3779
6.812.4.2 getBacklog	3779
6.812.4.3 getBlockSize	3779
6.812.4.4 getFreeThreadCount	3779
6.812.4.5 getInstance	3780
6.812.4.6 getMaxThreads	3780
6.812.4.7 getPoolSize	3780
6.812.4.8 onTaskCompleted	3780
6.812.4.9 onTaskException	3780
6.812.4.10 onTaskStarted	3781
6.812.4.11 queueTask	3781
6.812.4.12 reserve	3781
6.812.4.13 setBlockSize	3781
6.812.4.14 setMaxThreads	3782
6.812.5 Field Documentation	3782
6.812.5.1 DEFAULT_MAX_BLOCK_SIZE	3782
6.812.5.2 DEFAULT_MAX_POOL_SIZE	3782
6.813 decaf::lang::Throwable Class Reference	3783
6.813.1 Detailed Description	3783
6.813.2 Constructor & Destructor Documentation	3784
6.813.2.1 Throwable	3784
6.813.2.2 ~Throwable	3784
6.813.3 Member Function Documentation	3784
6.813.3.1 clone	3784
6.813.3.2 getCause	3785
6.813.3.3 getMessage	3785
6.813.3.4 getStackTrace	3785
6.813.3.5 getStackTraceString	3786
6.813.3.6 initCause	3786
6.813.3.7 printStackTrace	3786
6.813.3.8 printStackTrace	3786
6.813.3.9 setMark	3786

6.814decaf::util::concurrent::TimeoutException Class Reference	3787
6.814.1 Constructor & Destructor Documentation	3787
6.814.1.1 TimeoutException	3787
6.814.1.2 TimeoutException	3787
6.814.1.3 TimeoutException	3788
6.814.1.4 TimeoutException	3788
6.814.1.5 TimeoutException	3788
6.814.1.6 TimeoutException	3788
6.814.1.7 ~TimeoutException	3789
6.814.2 Member Function Documentation	3789
6.814.2.1 clone	3789
6.815decaf::util::Timer Class Reference	3790
6.815.1 Detailed Description	3791
6.815.2 Constructor & Destructor Documentation	3792
6.815.2.1 Timer	3792
6.815.2.2 ~Timer	3792
6.815.3 Member Function Documentation	3792
6.815.3.1 cancel	3792
6.815.3.2 purge	3792
6.815.3.3 schedule	3792
6.815.3.4 schedule	3793
6.815.3.5 schedule	3794
6.815.3.6 schedule	3794
6.815.3.7 schedule	3795
6.815.3.8 schedule	3796
6.815.3.9 schedule	3796
6.815.3.10 schedule	3797
6.815.3.11 scheduleAtFixedRate	3797
6.815.3.12 scheduleAtFixedRate	3798
6.815.3.13 scheduleAtFixedRate	3799
6.815.3.14 scheduleAtFixedRate	3799
6.816decaf::util::TimerTask Class Reference	3801
6.816.1 Detailed Description	3801
6.816.2 Constructor & Destructor Documentation	3802
6.816.2.1 TimerTask	3802
6.816.2.2 ~TimerTask	3802

6.816.3 Member Function Documentation	3802
6.816.3.1 cancel	3802
6.816.3.2 getWhen	3802
6.816.3.3 isScheduled	3802
6.816.3.4 scheduledExecutionTime	3802
6.816.3.5 setScheduledTime	3803
6.816.4 Friends And Related Function Documentation	3803
6.816.4.1 decaf::internal::util::TimerTaskHeap	3803
6.816.4.2 Timer	3803
6.816.4.3 TimerImpl	3803
6.817 decaf::internal::util::TimerTaskHeap Class Reference	3804
6.817.1 Detailed Description	3804
6.817.2 Constructor & Destructor Documentation	3805
6.817.2.1 TimerTaskHeap	3805
6.817.2.2 ~TimerTaskHeap	3805
6.817.3 Member Function Documentation	3805
6.817.3.1 adjustMinimum	3805
6.817.3.2 deleteIfCancelled	3805
6.817.3.3 find	3805
6.817.3.4 insert	3805
6.817.3.5 isEmpty	3805
6.817.3.6 peek	3806
6.817.3.7 remove	3806
6.817.3.8 reset	3806
6.817.3.9 size	3806
6.818 decaf::util::concurrent::TimeUnit Class Reference	3807
6.818.1 Detailed Description	3808
6.818.2 Constructor & Destructor Documentation	3809
6.818.2.1 TimeUnit	3809
6.818.2.2 ~TimeUnit	3809
6.818.3 Member Function Documentation	3809
6.818.3.1 compareTo	3809
6.818.3.2 convert	3810
6.818.3.3 equals	3810
6.818.3.4 operator<	3810
6.818.3.5 operator==	3811

6.818.3.6 sleep	3811
6.818.3.7 timedJoin	3811
6.818.3.8 timedWait	3812
6.818.3.9 toDays	3812
6.818.3.10 toHours	3813
6.818.3.11 toMicros	3813
6.818.3.12 toMillis	3813
6.818.3.13 toMinutes	3814
6.818.3.14 toNanos	3814
6.818.3.15 toSeconds	3814
6.818.3.16 toString	3815
6.818.3.17 valueOf	3815
6.818.4 Field Documentation	3815
6.818.4.1 DAYS	3815
6.818.4.2 HOURS	3815
6.818.4.3 MICROSECONDS	3815
6.818.4.4 MILLISECONDS	3815
6.818.4.5 MINUTES	3815
6.818.4.6 NANOSECONDS	3815
6.818.4.7 SECONDS	3816
6.818.4.8 values	3816
6.819 cms::Topic Class Reference	3817
6.819.1 Detailed Description	3817
6.819.2 Constructor & Destructor Documentation	3817
6.819.2.1 ~Topic	3817
6.819.3 Member Function Documentation	3817
6.819.3.1 getTopicName	3817
6.820 activemq::state::Tracked Class Reference	3818
6.820.1 Constructor & Destructor Documentation	3818
6.820.1.1 Tracked	3818
6.820.1.2 Tracked	3818
6.820.1.3 ~Tracked	3818
6.820.2 Member Function Documentation	3818
6.820.2.1 isWaitingForResponse	3818
6.820.2.2 onResponse	3818
6.821 activemq::commands::TransactionId Class Reference	3819

6.821.1 Member Typedef Documentation	3819
6.821.1.1 COMPARATOR	3819
6.821.2 Constructor & Destructor Documentation	3820
6.821.2.1 TransactionId	3820
6.821.2.2 TransactionId	3820
6.821.2.3 ~TransactionId	3820
6.821.3 Member Function Documentation	3820
6.821.3.1 cloneDataStructure	3820
6.821.3.2 compareTo	3820
6.821.3.3 copyDataStructure	3820
6.821.3.4 equals	3820
6.821.3.5 equals	3821
6.821.3.6 getDataStructureType	3821
6.821.3.7 operator<	3821
6.821.3.8 operator=	3821
6.821.3.9 operator==	3821
6.821.3.10 toString	3821
6.821.4 Field Documentation	3822
6.821.4.1 ID_TRANSACTIONID	3822
6.822activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller Class Reference	3823
6.822.1 Detailed Description	3823
6.822.2 Constructor & Destructor Documentation	3824
6.822.2.1 TransactionIdMarshaller	3824
6.822.2.2 ~TransactionIdMarshaller	3824
6.822.3 Member Function Documentation	3824
6.822.3.1 looseMarshal	3824
6.822.3.2 looseUnmarshal	3824
6.822.3.3 tightMarshal1	3825
6.822.3.4 tightMarshal2	3825
6.822.3.5 tightUnmarshal	3826
6.823activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller Class Reference	3827
6.823.1 Detailed Description	3827
6.823.2 Constructor & Destructor Documentation	3828
6.823.2.1 TransactionIdMarshaller	3828
6.823.2.2 ~TransactionIdMarshaller	3828

6.823.3 Member Function Documentation	3828
6.823.3.1 looseMarshal	3828
6.823.3.2 looseUnmarshal	3828
6.823.3.3 tightMarshal1	3829
6.823.3.4 tightMarshal2	3829
6.823.3.5 tightUnmarshal	3830
6.824activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller Class Reference	3831
6.824.1 Detailed Description	3831
6.824.2 Constructor & Destructor Documentation	3832
6.824.2.1 TransactionIdMarshaller	3832
6.824.2.2 ~TransactionIdMarshaller	3832
6.824.3 Member Function Documentation	3832
6.824.3.1 looseMarshal	3832
6.824.3.2 looseUnmarshal	3832
6.824.3.3 tightMarshal1	3833
6.824.3.4 tightMarshal2	3833
6.824.3.5 tightUnmarshal	3834
6.825activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller Class Reference	3835
6.825.1 Detailed Description	3835
6.825.2 Constructor & Destructor Documentation	3836
6.825.2.1 TransactionIdMarshaller	3836
6.825.2.2 ~TransactionIdMarshaller	3836
6.825.3 Member Function Documentation	3836
6.825.3.1 looseMarshal	3836
6.825.3.2 looseUnmarshal	3836
6.825.3.3 tightMarshal1	3837
6.825.3.4 tightMarshal2	3837
6.825.3.5 tightUnmarshal	3838
6.826activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller Class Reference	3839
6.826.1 Detailed Description	3839
6.826.2 Constructor & Destructor Documentation	3840
6.826.2.1 TransactionIdMarshaller	3840
6.826.2.2 ~TransactionIdMarshaller	3840
6.826.3 Member Function Documentation	3840

6.826.3.1 looseMarshal	3840
6.826.3.2 looseUnmarshal	3840
6.826.3.3 tightMarshal1	3841
6.826.3.4 tightMarshal2	3841
6.826.3.5 tightUnmarshal	3842
6.827activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller Class Reference	3843
6.827.1 Detailed Description	3843
6.827.2 Constructor & Destructor Documentation	3844
6.827.2.1 TransactionIdMarshaller	3844
6.827.2.2 ~TransactionIdMarshaller	3844
6.827.3 Member Function Documentation	3844
6.827.3.1 looseMarshal	3844
6.827.3.2 looseUnmarshal	3844
6.827.3.3 tightMarshal1	3845
6.827.3.4 tightMarshal2	3845
6.827.3.5 tightUnmarshal	3846
6.828activemq::commands::TransactionInfo Class Reference	3847
6.828.1 Constructor & Destructor Documentation	3848
6.828.1.1 TransactionInfo	3848
6.828.1.2 ~TransactionInfo	3848
6.828.2 Member Function Documentation	3848
6.828.2.1 cloneDataStructure	3848
6.828.2.2 copyDataStructure	3848
6.828.2.3 equals	3848
6.828.2.4 getConnectionId	3849
6.828.2.5 getConnectionId	3849
6.828.2.6 getDataStructureType	3849
6.828.2.7 getTransactionId	3849
6.828.2.8 getTransactionId	3849
6.828.2.9 getType	3849
6.828.2.10sTransactionInfo	3849
6.828.2.11setConnectionId	3849
6.828.2.12setTransactionId	3849
6.828.2.13setType	3849
6.828.2.14toString	3849
6.828.2.15visit	3850

6.828.3 Field Documentation	3850
6.828.3.1 connectionId	3850
6.828.3.2 ID_TRANSACTIONINFO	3850
6.828.3.3 transactionId	3850
6.828.3.4 type	3850
6.829activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller Class Reference	3851
6.829.1 Detailed Description	3851
6.829.2 Constructor & Destructor Documentation	3852
6.829.2.1 TransactionInfoMarshaller	3852
6.829.2.2 ~TransactionInfoMarshaller	3852
6.829.3 Member Function Documentation	3852
6.829.3.1 createObject	3852
6.829.3.2 getDataStructureType	3852
6.829.3.3 looseMarshal	3852
6.829.3.4 looseUnmarshal	3853
6.829.3.5 tightMarshal1	3853
6.829.3.6 tightMarshal2	3853
6.829.3.7 tightUnmarshal	3854
6.830activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller Class Reference	3855
6.830.1 Detailed Description	3855
6.830.2 Constructor & Destructor Documentation	3856
6.830.2.1 TransactionInfoMarshaller	3856
6.830.2.2 ~TransactionInfoMarshaller	3856
6.830.3 Member Function Documentation	3856
6.830.3.1 createObject	3856
6.830.3.2 getDataStructureType	3856
6.830.3.3 looseMarshal	3856
6.830.3.4 looseUnmarshal	3857
6.830.3.5 tightMarshal1	3857
6.830.3.6 tightMarshal2	3857
6.830.3.7 tightUnmarshal	3858
6.831activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller Class Reference	3859
6.831.1 Detailed Description	3859
6.831.2 Constructor & Destructor Documentation	3860

6.831.2.1 TransactionInfoMarshaller	3860
6.831.2.2 ~TransactionInfoMarshaller	3860
6.831.3 Member Function Documentation	3860
6.831.3.1 createObject	3860
6.831.3.2 getDataStructureType	3860
6.831.3.3 looseMarshal	3860
6.831.3.4 looseUnmarshal	3861
6.831.3.5 tightMarshal1	3861
6.831.3.6 tightMarshal2	3861
6.831.3.7 tightUnmarshal	3862
6.832activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller Class Reference	3863
6.832.1 Detailed Description	3863
6.832.2 Constructor & Destructor Documentation	3864
6.832.2.1 TransactionInfoMarshaller	3864
6.832.2.2 ~TransactionInfoMarshaller	3864
6.832.3 Member Function Documentation	3864
6.832.3.1 createObject	3864
6.832.3.2 getDataStructureType	3864
6.832.3.3 looseMarshal	3864
6.832.3.4 looseUnmarshal	3865
6.832.3.5 tightMarshal1	3865
6.832.3.6 tightMarshal2	3865
6.832.3.7 tightUnmarshal	3866
6.833activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller Class Reference	3867
6.833.1 Detailed Description	3867
6.833.2 Constructor & Destructor Documentation	3868
6.833.2.1 TransactionInfoMarshaller	3868
6.833.2.2 ~TransactionInfoMarshaller	3868
6.833.3 Member Function Documentation	3868
6.833.3.1 createObject	3868
6.833.3.2 getDataStructureType	3868
6.833.3.3 looseMarshal	3868
6.833.3.4 looseUnmarshal	3869
6.833.3.5 tightMarshal1	3869
6.833.3.6 tightMarshal2	3869

6.833.3.7 tightUnmarshal	3870
6.834activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller Class Reference	3871
6.834.1 Detailed Description	3871
6.834.2 Constructor & Destructor Documentation	3872
6.834.2.1 TransactionInfoMarshaller	3872
6.834.2.2 ~TransactionInfoMarshaller	3872
6.834.3 Member Function Documentation	3872
6.834.3.1 createObject	3872
6.834.3.2 getDataStructureType	3872
6.834.3.3 looseMarshal	3872
6.834.3.4 looseUnmarshal	3873
6.834.3.5 tightMarshal1	3873
6.834.3.6 tightMarshal2	3873
6.834.3.7 tightUnmarshal	3874
6.835activemq::state::TransactionState Class Reference	3875
6.835.1 Constructor & Destructor Documentation	3876
6.835.1.1 TransactionState	3876
6.835.1.2 ~TransactionState	3876
6.835.2 Member Function Documentation	3876
6.835.2.1 addCommand	3876
6.835.2.2 addProducerState	3876
6.835.2.3 checkShutdown	3876
6.835.2.4 getCommands	3876
6.835.2.5 getId	3876
6.835.2.6 getPreparedResult	3876
6.835.2.7 getProducerStates	3876
6.835.2.8 isPrepared	3876
6.835.2.9 setPrepared	3876
6.835.2.10setPreparedResult	3876
6.835.2.11shutdown	3876
6.835.2.12toString	3876
6.836decaf::internal::util::concurrent::Transferer< E > Class Template Reference	3877
6.836.1 Detailed Description	3877
6.837decaf::internal::util::concurrent::TransferQueue< E > Class Template Reference	3878
6.837.1 Detailed Description	3878
6.837.2 Constructor & Destructor Documentation	3878

6.837.2.1	TransferQueue	3878
6.837.2.2	~TransferQueue	3879
6.837.3	Member Function Documentation	3879
6.837.3.1	transfer	3879
6.837.3.2	transfer	3879
6.838	decaf::internal::util::concurrent::TransferStack< E > Class Template Reference	3881
6.838.1	Constructor & Destructor Documentation	3881
6.838.1.1	TransferStack	3881
6.838.1.2	~TransferStack	3881
6.838.2	Member Function Documentation	3881
6.838.2.1	transfer	3881
6.838.2.2	transfer	3882
6.839	activemq::transport::Transport Class Reference	3883
6.839.1	Detailed Description	3884
6.839.2	Constructor & Destructor Documentation	3884
6.839.2.1	~Transport	3884
6.839.3	Member Function Documentation	3884
6.839.3.1	getRemoteAddress	3884
6.839.3.2	getTransportListener	3884
6.839.3.3	isClosed	3885
6.839.3.4	isConnected	3885
6.839.3.5	isFaultTolerant	3885
6.839.3.6	narrow	3885
6.839.3.7	oneway	3886
6.839.3.8	reconnect	3886
6.839.3.9	request	3886
6.839.3.10	request	3887
6.839.3.11	setTransportListener	3887
6.839.3.12	setWireFormat	3888
6.839.3.13	start	3888
6.839.3.14	stop	3888
6.840	activemq::transport::TransportFactory Class Reference	3889
6.840.1	Detailed Description	3889
6.840.2	Constructor & Destructor Documentation	3889
6.840.2.1	~TransportFactory	3889
6.840.3	Member Function Documentation	3889

6.840.3.1 create	3889
6.840.3.2 createComposite	3890
6.841activemq::transport::TransportFilter Class Reference	3891
6.841.1 Detailed Description	3893
6.841.2 Constructor & Destructor Documentation	3893
6.841.2.1 TransportFilter	3893
6.841.2.2 ~TransportFilter	3893
6.841.3 Member Function Documentation	3893
6.841.3.1 close	3893
6.841.3.2 fire	3893
6.841.3.3 fire	3894
6.841.3.4 getRemoteAddress	3894
6.841.3.5 getTransportListener	3894
6.841.3.6 isClosed	3894
6.841.3.7 isConnected	3894
6.841.3.8 isFaultTolerant	3895
6.841.3.9 narrow	3895
6.841.3.10onCommand	3895
6.841.3.11oneway	3895
6.841.3.12onException	3896
6.841.3.13reconnect	3896
6.841.3.14request	3896
6.841.3.15request	3897
6.841.3.16setTransportListener	3897
6.841.3.17setWireFormat	3897
6.841.3.18start	3898
6.841.3.19stop	3898
6.841.3.20transportInterrupted	3898
6.841.3.21transportResumed	3898
6.841.4 Field Documentation	3898
6.841.4.1 listener	3898
6.841.4.2 next	3898
6.842activemq::transport::TransportListener Class Reference	3900
6.842.1 Detailed Description	3900
6.842.2 Constructor & Destructor Documentation	3900
6.842.2.1 ~TransportListener	3900

6.842.3 Member Function Documentation	3900
6.842.3.1 onCommand	3900
6.842.3.2 onException	3901
6.842.3.3 transportInterrupted	3901
6.842.3.4 transportResumed	3901
6.843activemq::transport::TransportRegistry Class Reference	3902
6.843.1 Detailed Description	3902
6.843.2 Constructor & Destructor Documentation	3903
6.843.2.1 ~TransportRegistry	3903
6.843.3 Member Function Documentation	3903
6.843.3.1 findFactory	3903
6.843.3.2 getInstance	3903
6.843.3.3 getTransportNames	3903
6.843.3.4 registerFactory	3903
6.843.3.5 unregisterFactory	3904
6.844tree_desc_s Struct Reference	3905
6.844.1 Field Documentation	3905
6.844.1.1 dyn_tree	3905
6.844.1.2 max_code	3905
6.844.1.3 stat_desc	3905
6.845decaf::lang::Thread::UncaughtExceptionHandler Class Reference	3906
6.845.1 Detailed Description	3906
6.845.2 Constructor & Destructor Documentation	3906
6.845.2.1 ~UncaughtExceptionHandler	3906
6.845.3 Member Function Documentation	3906
6.845.3.1 uncaughtException	3906
6.846decaf::net::UnknownHostException Class Reference	3907
6.846.1 Constructor & Destructor Documentation	3907
6.846.1.1 UnknownHostException	3907
6.846.1.2 UnknownHostException	3907
6.846.1.3 UnknownHostException	3908
6.846.1.4 UnknownHostException	3908
6.846.1.5 UnknownHostException	3908
6.846.1.6 UnknownHostException	3908
6.846.1.7 ~UnknownHostException	3909
6.846.2 Member Function Documentation	3909

6.846.2.1 clone	3909
6.847decaf::net::UnknownServiceException Class Reference	3910
6.847.1 Constructor & Destructor Documentation	3910
6.847.1.1 UnknownServiceException	3910
6.847.1.2 UnknownServiceException	3910
6.847.1.3 UnknownServiceException	3911
6.847.1.4 UnknownServiceException	3911
6.847.1.5 UnknownServiceException	3911
6.847.1.6 UnknownServiceException	3911
6.847.1.7 ~UnknownServiceException	3912
6.847.2 Member Function Documentation	3912
6.847.2.1 clone	3912
6.848decaf::io::UnsupportedEncodingException Class Reference	3913
6.848.1 Detailed Description	3913
6.848.2 Constructor & Destructor Documentation	3913
6.848.2.1 UnsupportedEncodingException	3913
6.848.2.2 UnsupportedEncodingException	3914
6.848.2.3 UnsupportedEncodingException	3914
6.848.2.4 UnsupportedEncodingException	3914
6.848.2.5 UnsupportedEncodingException	3914
6.848.2.6 UnsupportedEncodingException	3914
6.848.2.7 ~UnsupportedEncodingException	3915
6.848.3 Member Function Documentation	3915
6.848.3.1 clone	3915
6.849decaf::lang::exceptions::UnsupportedOperationException Class Reference	3916
6.849.1 Constructor & Destructor Documentation	3916
6.849.1.1 UnsupportedOperationException	3916
6.849.1.2 UnsupportedOperationException	3916
6.849.1.3 UnsupportedOperationException	3917
6.849.1.4 UnsupportedOperationException	3917
6.849.1.5 UnsupportedOperationException	3917
6.849.1.6 UnsupportedOperationException	3917
6.849.1.7 ~UnsupportedOperationException	3918
6.849.2 Member Function Documentation	3918
6.849.2.1 clone	3918
6.850cms::UnsupportedOperationException Class Reference	3919

6.850.1 Detailed Description	3919
6.850.2 Constructor & Destructor Documentation	3919
6.850.2.1 UnsupportedOperationException	3919
6.850.2.2 UnsupportedOperationException	3919
6.850.2.3 UnsupportedOperationException	3919
6.850.2.4 UnsupportedOperationException	3919
6.850.2.5 ~UnsupportedOperationException	3919
6.851decaf::net::URI Class Reference	3921
6.851.1 Detailed Description	3923
6.851.2 Constructor & Destructor Documentation	3923
6.851.2.1 URI	3923
6.851.2.2 URI	3923
6.851.2.3 URI	3923
6.851.2.4 URI	3923
6.851.2.5 URI	3924
6.851.2.6 URI	3924
6.851.2.7 URI	3924
6.851.2.8 ~URI	3925
6.851.3 Member Function Documentation	3925
6.851.3.1 compareTo	3925
6.851.3.2 create	3925
6.851.3.3 equals	3925
6.851.3.4 getAuthority	3925
6.851.3.5 getFragment	3925
6.851.3.6 getHost	3926
6.851.3.7 getPath	3926
6.851.3.8 getPort	3926
6.851.3.9 getQuery	3926
6.851.3.10getRawAuthority	3926
6.851.3.11getRawFragment	3926
6.851.3.12getRawPath	3926
6.851.3.13getRawQuery	3927
6.851.3.14getRawSchemeSpecificPart	3927
6.851.3.15getRawUserInfo	3927
6.851.3.16getScheme	3927
6.851.3.17getSchemeSpecificPart	3927

6.851.3.18	getUserInfo	3928
6.851.3.19	sAbsolute	3928
6.851.3.20	sOpaque	3928
6.851.3.21	normalize	3928
6.851.3.22	operator<	3928
6.851.3.23	operator==	3929
6.851.3.24	parseServerAuthority	3929
6.851.3.25	relativize	3929
6.851.3.26	resolve	3930
6.851.3.27	resolve	3930
6.851.3.28	oString	3931
6.851.3.29	oURL	3931
6.852	decaf::internal::net::URIEncoderDecoder Class Reference	3932
6.852.1	Constructor & Destructor Documentation	3932
6.852.1.1	URIEncoderDecoder	3932
6.852.1.2	~URIEncoderDecoder	3932
6.852.2	Member Function Documentation	3932
6.852.2.1	decode	3932
6.852.2.2	encodeOthers	3933
6.852.2.3	quoteIllegal	3933
6.852.2.4	validate	3933
6.852.2.5	validateSimple	3934
6.853	decaf::internal::net::URIHelper Class Reference	3935
6.853.1	Detailed Description	3936
6.853.2	Constructor & Destructor Documentation	3936
6.853.2.1	URIHelper	3936
6.853.2.2	URIHelper	3936
6.853.2.3	~URIHelper	3937
6.853.3	Member Function Documentation	3937
6.853.3.1	isValidDomainName	3937
6.853.3.2	isValidHexChar	3937
6.853.3.3	isValidHost	3937
6.853.3.4	isValidIP4Word	3937
6.853.3.5	isValidIP6Address	3938
6.853.3.6	isValidIPv4Address	3938
6.853.3.7	parseAuthority	3938

6.853.3.8	parseURI	3939
6.853.3.9	validateAuthority	3939
6.853.3.10	validateFragment	3939
6.853.3.11	validatePath	3940
6.853.3.12	validateQuery	3940
6.853.3.13	validateScheme	3940
6.853.3.14	validateSsp	3941
6.853.3.15	validateUserinfo	3941
6.854	activemq::transport::failover::URIPool Class Reference	3942
6.854.1	Constructor & Destructor Documentation	3942
6.854.1.1	URIPool	3942
6.854.1.2	URIPool	3942
6.854.1.3	~URIPool	3943
6.854.2	Member Function Documentation	3943
6.854.2.1	addURI	3943
6.854.2.2	addURIs	3943
6.854.2.3	getURI	3943
6.854.2.4	isRandomize	3943
6.854.2.5	removeURI	3943
6.854.2.6	setRandomize	3944
6.855	activemq::util::URISupport Class Reference	3945
6.855.1	Member Function Documentation	3945
6.855.1.1	createQueryString	3945
6.855.1.2	parseComposite	3946
6.855.1.3	parseQuery	3946
6.855.1.4	parseQuery	3946
6.855.1.5	parseURL	3947
6.856	decaf::net::URISyntaxException Class Reference	3948
6.856.1	Constructor & Destructor Documentation	3948
6.856.1.1	URISyntaxException	3948
6.856.1.2	URISyntaxException	3949
6.856.1.3	URISyntaxException	3949
6.856.1.4	URISyntaxException	3949
6.856.1.5	URISyntaxException	3949
6.856.1.6	URISyntaxException	3949
6.856.1.7	URISyntaxException	3950

6.856.1.8 URISyntaxException	3950
6.856.1.9 ~URISyntaxException	3950
6.856.2 Member Function Documentation	3950
6.856.2.1 clone	3950
6.856.2.2 getIndex	3951
6.856.2.3 getInput	3951
6.856.2.4 getReason	3951
6.857decaf::internal::net::URIType Class Reference	3952
6.857.1 Detailed Description	3954
6.857.2 Constructor & Destructor Documentation	3954
6.857.2.1 URIType	3954
6.857.2.2 URIType	3954
6.857.2.3 ~URIType	3954
6.857.3 Member Function Documentation	3954
6.857.3.1 getAuthority	3954
6.857.3.2 getFragment	3954
6.857.3.3 getHost	3954
6.857.3.4 getPath	3954
6.857.3.5 getPort	3955
6.857.3.6 getQuery	3955
6.857.3.7 getScheme	3955
6.857.3.8 getSchemeSpecificPart	3955
6.857.3.9 getSource	3955
6.857.3.10getUserInfo	3955
6.857.3.11isAbsolute	3956
6.857.3.12sOpaque	3956
6.857.3.13sServerAuthority	3956
6.857.3.14sValid	3956
6.857.3.15setAbsolute	3956
6.857.3.16setAuthority	3956
6.857.3.17setFragment	3957
6.857.3.18setHost	3957
6.857.3.19setOpaque	3957
6.857.3.20setPath	3957
6.857.3.21setPort	3957
6.857.3.22setQuery	3957

6.857.3.23	setScheme	3958
6.857.3.24	setSchemeSpecificPart	3958
6.857.3.25	setServerAuthority	3958
6.857.3.26	setSource	3958
6.857.3.27	setUserInfo	3958
6.857.3.28	setValid	3958
6.858	decaf::net::URL Class Reference	3960
6.858.1	Detailed Description	3960
6.858.2	Constructor & Destructor Documentation	3961
6.858.2.1	URL	3961
6.858.2.2	URL	3961
6.858.2.3	~URL	3961
6.859	decaf::net::URLDecoder Class Reference	3962
6.859.1	Constructor & Destructor Documentation	3962
6.859.1.1	~URLDecoder	3962
6.859.2	Member Function Documentation	3962
6.859.2.1	decode	3962
6.860	decaf::net::URLEncoder Class Reference	3963
6.860.1	Constructor & Destructor Documentation	3963
6.860.1.1	~URLEncoder	3963
6.860.2	Member Function Documentation	3963
6.860.2.1	encode	3963
6.861	activemq::util::Usage Class Reference	3964
6.861.1	Constructor & Destructor Documentation	3964
6.861.1.1	~Usage	3964
6.861.2	Member Function Documentation	3964
6.861.2.1	decreaseUsage	3964
6.861.2.2	enqueueUsage	3964
6.861.2.3	increaseUsage	3965
6.861.2.4	isFull	3965
6.861.2.5	waitForSpace	3965
6.861.2.6	waitForSpace	3965
6.862	decaf::io::UTFDataFormatException Class Reference	3966
6.862.1	Detailed Description	3966
6.862.2	Constructor & Destructor Documentation	3966
6.862.2.1	UTFDataFormatException	3966

6.862.2.2 UTFDataFormatException	3967
6.862.2.3 UTFDataFormatException	3967
6.862.2.4 UTFDataFormatException	3967
6.862.2.5 UTFDataFormatException	3967
6.862.2.6 UTFDataFormatException	3967
6.862.2.7 ~UTFDataFormatException	3968
6.862.3 Member Function Documentation	3968
6.862.3.1 clone	3968
6.863decaf::util::UUID Class Reference	3969
6.863.1 Detailed Description	3970
6.863.2 Constructor & Destructor Documentation	3970
6.863.2.1 UUID	3970
6.863.2.2 ~UUID	3971
6.863.3 Member Function Documentation	3971
6.863.3.1 clockSequence	3971
6.863.3.2 compareTo	3971
6.863.3.3 equals	3971
6.863.3.4 fromString	3972
6.863.3.5 getLeastSignificantBits	3972
6.863.3.6 getMostSignificantBits	3972
6.863.3.7 nameUUIDFromBytes	3972
6.863.3.8 nameUUIDFromBytes	3972
6.863.3.9 node	3973
6.863.3.10 operator<	3973
6.863.3.11 operator==	3973
6.863.3.12 randomUUID	3973
6.863.3.13 timestamp	3974
6.863.3.14 toString	3974
6.863.3.15 variant	3974
6.863.3.16 version	3974
6.864activemq::wireformat::WireFormat Class Reference	3976
6.864.1 Detailed Description	3976
6.864.2 Constructor & Destructor Documentation	3977
6.864.2.1 ~WireFormat	3977
6.864.3 Member Function Documentation	3977
6.864.3.1 createNegotiator	3977

6.864.3.2	getVersion	3977
6.864.3.3	hasNegotiator	3977
6.864.3.4	inReceive	3978
6.864.3.5	marshal	3978
6.864.3.6	setVersion	3978
6.864.3.7	unmarshal	3979
6.865	activemq::wireformat::WireFormatFactory Class Reference	3980
6.865.1	Detailed Description	3980
6.865.2	Constructor & Destructor Documentation	3980
6.865.2.1	~WireFormatFactory	3980
6.865.3	Member Function Documentation	3980
6.865.3.1	createWireFormat	3980
6.866	activemq::commands::WireFormatInfo Class Reference	3982
6.866.1	Constructor & Destructor Documentation	3984
6.866.1.1	WireFormatInfo	3984
6.866.1.2	~WireFormatInfo	3984
6.866.2	Member Function Documentation	3984
6.866.2.1	afterUnmarshal	3984
6.866.2.2	beforeMarshal	3985
6.866.2.3	cloneDataStructure	3985
6.866.2.4	copyDataStructure	3985
6.866.2.5	equals	3985
6.866.2.6	getCacheSize	3986
6.866.2.7	getDataStructureType	3986
6.866.2.8	getMagic	3986
6.866.2.9	getMarshaledProperties	3986
6.866.2.10	getMaxInactivityDuration	3986
6.866.2.11	getMaxInactivityDurationInitialDelay	3987
6.866.2.12	getProperties	3987
6.866.2.13	getProperties	3987
6.866.2.14	getVersion	3987
6.866.2.15	isCacheEnabled	3987
6.866.2.16	isMarshalAware	3987
6.866.2.17	isSizePrefixDisabled	3988
6.866.2.18	isStackTraceEnabled	3988
6.866.2.19	isTcpNoDelayEnabled	3988

6.866.2.20	isTightEncodingEnabled	3988
6.866.2.21	isValid	3988
6.866.2.22	isWireFormatInfo	3989
6.866.2.23	setCacheEnabled	3989
6.866.2.24	setCacheSize	3989
6.866.2.25	setMagic	3989
6.866.2.26	setMarshaledProperties	3989
6.866.2.27	setMaxInactivityDuration	3989
6.866.2.28	setMaxInactivityDurationInitialDelay	3990
6.866.2.29	setProperties	3990
6.866.2.30	setSizePrefixDisabled	3990
6.866.2.31	setStackTraceEnabled	3990
6.866.2.32	setTcpNoDelayEnabled	3990
6.866.2.33	setTightEncodingEnabled	3990
6.866.2.34	setVersion	3991
6.866.2.35	toString	3991
6.866.2.36	visit	3991
6.866.3	Field Documentation	3991
6.866.3.1	ID_WIREFORMATINFO	3991
6.867	activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller Class Reference	3992
6.867.1	Detailed Description	3992
6.867.2	Constructor & Destructor Documentation	3993
6.867.2.1	WireFormatInfoMarshaller	3993
6.867.2.2	~WireFormatInfoMarshaller	3993
6.867.3	Member Function Documentation	3993
6.867.3.1	createObject	3993
6.867.3.2	getDataStructureType	3993
6.867.3.3	looseMarshal	3993
6.867.3.4	looseUnmarshal	3994
6.867.3.5	tightMarshal1	3994
6.867.3.6	tightMarshal2	3994
6.867.3.7	tightUnmarshal	3995
6.868	activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller Class Reference	3996
6.868.1	Detailed Description	3996
6.868.2	Constructor & Destructor Documentation	3997

6.868.2.1 WireFormatInfoMarshaller	3997
6.868.2.2 ~WireFormatInfoMarshaller	3997
6.868.3 Member Function Documentation	3997
6.868.3.1 createObject	3997
6.868.3.2 getDataStructureType	3997
6.868.3.3 looseMarshal	3997
6.868.3.4 looseUnmarshal	3998
6.868.3.5 tightMarshal1	3998
6.868.3.6 tightMarshal2	3998
6.868.3.7 tightUnmarshal	3999
6.869activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller Class Reference	4000
6.869.1 Detailed Description	4000
6.869.2 Constructor & Destructor Documentation	4001
6.869.2.1 WireFormatInfoMarshaller	4001
6.869.2.2 ~WireFormatInfoMarshaller	4001
6.869.3 Member Function Documentation	4001
6.869.3.1 createObject	4001
6.869.3.2 getDataStructureType	4001
6.869.3.3 looseMarshal	4001
6.869.3.4 looseUnmarshal	4002
6.869.3.5 tightMarshal1	4002
6.869.3.6 tightMarshal2	4002
6.869.3.7 tightUnmarshal	4003
6.870activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller Class Reference	4004
6.870.1 Detailed Description	4004
6.870.2 Constructor & Destructor Documentation	4005
6.870.2.1 WireFormatInfoMarshaller	4005
6.870.2.2 ~WireFormatInfoMarshaller	4005
6.870.3 Member Function Documentation	4005
6.870.3.1 createObject	4005
6.870.3.2 getDataStructureType	4005
6.870.3.3 looseMarshal	4005
6.870.3.4 looseUnmarshal	4006
6.870.3.5 tightMarshal1	4006
6.870.3.6 tightMarshal2	4006

6.870.3.7 tightUnmarshal	4007
6.871activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller Class Reference	4008
6.871.1 Detailed Description	4008
6.871.2 Constructor & Destructor Documentation	4009
6.871.2.1 WireFormatInfoMarshaller	4009
6.871.2.2 ~WireFormatInfoMarshaller	4009
6.871.3 Member Function Documentation	4009
6.871.3.1 createObject	4009
6.871.3.2 getDataStructureType	4009
6.871.3.3 looseMarshal	4009
6.871.3.4 looseUnmarshal	4010
6.871.3.5 tightMarshal1	4010
6.871.3.6 tightMarshal2	4010
6.871.3.7 tightUnmarshal	4011
6.872activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller Class Reference	4012
6.872.1 Detailed Description	4012
6.872.2 Constructor & Destructor Documentation	4013
6.872.2.1 WireFormatInfoMarshaller	4013
6.872.2.2 ~WireFormatInfoMarshaller	4013
6.872.3 Member Function Documentation	4013
6.872.3.1 createObject	4013
6.872.3.2 getDataStructureType	4013
6.872.3.3 looseMarshal	4013
6.872.3.4 looseUnmarshal	4014
6.872.3.5 tightMarshal1	4014
6.872.3.6 tightMarshal2	4014
6.872.3.7 tightUnmarshal	4015
6.873activemq::wireformat::WireFormatNegotiator Class Reference	4016
6.873.1 Detailed Description	4016
6.873.2 Constructor & Destructor Documentation	4016
6.873.2.1 WireFormatNegotiator	4016
6.873.2.2 ~WireFormatNegotiator	4016
6.874activemq::wireformat::WireFormatRegistry Class Reference	4017
6.874.1 Detailed Description	4017
6.874.2 Constructor & Destructor Documentation	4018

6.874.2.1 ~WireFormatRegistry	4018
6.874.3 Member Function Documentation	4018
6.874.3.1 findFactory	4018
6.874.3.2 getInstance	4018
6.874.3.3 getWireFormatNames	4018
6.874.3.4 registerFactory	4019
6.874.3.5 unregisterFactory	4019
6.875activemq::transport::inactivity::WriteChecker Class Reference	4020
6.875.1 Detailed Description	4020
6.875.2 Constructor & Destructor Documentation	4020
6.875.2.1 WriteChecker	4020
6.875.2.2 ~WriteChecker	4020
6.875.3 Member Function Documentation	4020
6.875.3.1 run	4020
6.876decaf::io::Writer Class Reference	4021
6.876.1 Constructor & Destructor Documentation	4022
6.876.1.1 Writer	4022
6.876.1.2 ~Writer	4022
6.876.2 Member Function Documentation	4022
6.876.2.1 append	4022
6.876.2.2 append	4023
6.876.2.3 append	4023
6.876.2.4 doAppendChar	4024
6.876.2.5 doAppendCharSequence	4024
6.876.2.6 doAppendCharSequenceStartEnd	4024
6.876.2.7 doWriteArray	4024
6.876.2.8 doWriteArrayBounded	4024
6.876.2.9 doWriteChar	4024
6.876.2.10doWriteString	4024
6.876.2.11doWriteStringBounded	4024
6.876.2.12doWriteVector	4024
6.876.2.13write	4024
6.876.2.14write	4025
6.876.2.15write	4025
6.876.2.16write	4025
6.876.2.17write	4026

6.876.2.18	write	4026
6.877	decaf::security::auth::x500::X500Principal Class Reference	4027
6.877.1	Constructor & Destructor Documentation	4027
6.877.1.1	~X500Principal	4027
6.877.2	Member Function Documentation	4027
6.877.2.1	getEncoded	4027
6.877.2.2	getName	4027
6.877.2.3	hashCode	4027
6.878	decaf::security::cert::X509Certificate Class Reference	4028
6.878.1	Detailed Description	4028
6.878.2	Constructor & Destructor Documentation	4029
6.878.2.1	~X509Certificate	4029
6.878.3	Member Function Documentation	4029
6.878.3.1	checkValidity	4029
6.878.3.2	checkValidity	4029
6.878.3.3	getBasicConstraints	4029
6.878.3.4	getIssuerUniqueID	4029
6.878.3.5	getIssuerX500Principal	4029
6.878.3.6	getKeyUsage	4029
6.878.3.7	getNotAfter	4029
6.878.3.8	getNotBefore	4029
6.878.3.9	getSigAlgName	4029
6.878.3.10	getSigAlgOID	4029
6.878.3.11	getSigAlgParams	4029
6.878.3.12	getSignature	4029
6.878.3.13	getSubjectUniqueID	4029
6.878.3.14	getSubjectX500Principal	4029
6.878.3.15	getTBSCertificate	4029
6.878.3.16	getVersion	4029
6.879	activemq::commands::XATransactionId Class Reference	4031
6.879.1	Member Typedef Documentation	4032
6.879.1.1	COMPARATOR	4032
6.879.2	Constructor & Destructor Documentation	4032
6.879.2.1	XATransactionId	4032
6.879.2.2	XATransactionId	4032
6.879.2.3	~XATransactionId	4032

6.879.3 Member Function Documentation	4032
6.879.3.1 cloneDataStructure	4032
6.879.3.2 compareTo	4032
6.879.3.3 copyDataStructure	4032
6.879.3.4 equals	4033
6.879.3.5 equals	4033
6.879.3.6 getBranchQualifier	4033
6.879.3.7 getBranchQualifier	4033
6.879.3.8 getDataStructureType	4033
6.879.3.9 getFormatId	4034
6.879.3.10 getGlobalTransactionId	4034
6.879.3.11 getGlobalTransactionId	4034
6.879.3.12 operator<	4034
6.879.3.13 operator=	4034
6.879.3.14 operator==	4034
6.879.3.15 setBranchQualifier	4034
6.879.3.16 setFormatId	4034
6.879.3.17 setGlobalTransactionId	4034
6.879.3.18 toString	4034
6.879.4 Field Documentation	4035
6.879.4.1 branchQualifier	4035
6.879.4.2 formatId	4035
6.879.4.3 globalTransactionId	4035
6.879.4.4 ID_XATRANSACTIONID	4035
6.880 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller Class	
Reference	4036
6.880.1 Detailed Description	4036
6.880.2 Constructor & Destructor Documentation	4037
6.880.2.1 XATransactionIdMarshaller	4037
6.880.2.2 ~XATransactionIdMarshaller	4037
6.880.3 Member Function Documentation	4037
6.880.3.1 createObject	4037
6.880.3.2 getDataStructureType	4037
6.880.3.3 looseMarshal	4037
6.880.3.4 looseUnmarshal	4038
6.880.3.5 tightMarshal1	4038
6.880.3.6 tightMarshal2	4038

6.880.3.7 tightUnmarshal	4039
6.881activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller Class	
Reference	4040
6.881.1 Detailed Description	4040
6.881.2 Constructor & Destructor Documentation	4041
6.881.2.1 XATransactionIdMarshaller	4041
6.881.2.2 ~XATransactionIdMarshaller	4041
6.881.3 Member Function Documentation	4041
6.881.3.1 createObject	4041
6.881.3.2 getDataStructureType	4041
6.881.3.3 looseMarshal	4041
6.881.3.4 looseUnmarshal	4042
6.881.3.5 tightMarshal1	4042
6.881.3.6 tightMarshal2	4042
6.881.3.7 tightUnmarshal	4043
6.882activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller Class	
Reference	4044
6.882.1 Detailed Description	4044
6.882.2 Constructor & Destructor Documentation	4045
6.882.2.1 XATransactionIdMarshaller	4045
6.882.2.2 ~XATransactionIdMarshaller	4045
6.882.3 Member Function Documentation	4045
6.882.3.1 createObject	4045
6.882.3.2 getDataStructureType	4045
6.882.3.3 looseMarshal	4045
6.882.3.4 looseUnmarshal	4046
6.882.3.5 tightMarshal1	4046
6.882.3.6 tightMarshal2	4046
6.882.3.7 tightUnmarshal	4047
6.883activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller Class	
Reference	4048
6.883.1 Detailed Description	4048
6.883.2 Constructor & Destructor Documentation	4049
6.883.2.1 XATransactionIdMarshaller	4049
6.883.2.2 ~XATransactionIdMarshaller	4049
6.883.3 Member Function Documentation	4049
6.883.3.1 createObject	4049

6.883.3.2	getDataStructureType	4049
6.883.3.3	looseMarshal	4049
6.883.3.4	looseUnmarshal	4050
6.883.3.5	tightMarshal1	4050
6.883.3.6	tightMarshal2	4050
6.883.3.7	tightUnmarshal	4051
6.884	activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller Class	
	Reference	4052
6.884.1	Detailed Description	4052
6.884.2	Constructor & Destructor Documentation	4053
6.884.2.1	XATransactionIdMarshaller	4053
6.884.2.2	~XATransactionIdMarshaller	4053
6.884.3	Member Function Documentation	4053
6.884.3.1	createObject	4053
6.884.3.2	getDataStructureType	4053
6.884.3.3	looseMarshal	4053
6.884.3.4	looseUnmarshal	4054
6.884.3.5	tightMarshal1	4054
6.884.3.6	tightMarshal2	4054
6.884.3.7	tightUnmarshal	4055
6.885	activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller Class	
	Reference	4056
6.885.1	Detailed Description	4056
6.885.2	Constructor & Destructor Documentation	4057
6.885.2.1	XATransactionIdMarshaller	4057
6.885.2.2	~XATransactionIdMarshaller	4057
6.885.3	Member Function Documentation	4057
6.885.3.1	createObject	4057
6.885.3.2	getDataStructureType	4057
6.885.3.3	looseMarshal	4057
6.885.3.4	looseUnmarshal	4058
6.885.3.5	tightMarshal1	4058
6.885.3.6	tightMarshal2	4058
6.885.3.7	tightUnmarshal	4059
6.886	decaf::util::logging::XMLFormatter Class Reference	4060
6.886.1	Detailed Description	4060
6.886.2	Constructor & Destructor Documentation	4060

6.886.2.1 XMLFormatter	4060
6.886.2.2 ~XMLFormatter	4060
6.886.3 Member Function Documentation	4060
6.886.3.1 format	4060
6.886.3.2 getHead	4061
6.886.3.3 getTail	4061
6.887z_stream_s Struct Reference	4062
6.887.1 Field Documentation	4062
6.887.1.1 Adler	4062
6.887.1.2 avail_in	4062
6.887.1.3 avail_out	4062
6.887.1.4 data_type	4062
6.887.1.5 msg	4062
6.887.1.6 next_in	4062
6.887.1.7 next_out	4062
6.887.1.8 opaque	4062
6.887.1.9 reserved	4062
6.887.1.10 state	4062
6.887.1.11 total_in	4062
6.887.1.12 total_out	4062
6.887.1.13 alloc	4062
6.887.1.14 free	4062
6.888deflate::util::zip::ZipException Class Reference	4064
6.888.1 Constructor & Destructor Documentation	4064
6.888.1.1 ZipException	4064
6.888.1.2 ZipException	4064
6.888.1.3 ZipException	4065
6.888.1.4 ZipException	4065
6.888.1.5 ZipException	4065
6.888.1.6 ZipException	4065
6.888.1.7 ~ZipException	4066
6.888.2 Member Function Documentation	4066
6.888.2.1 clone	4066
7 File Documentation	4067
7.1 src/main/activemq/cmsutil/CachedConsumer.h File Reference	4067
7.2 src/main/activemq/cmsutil/CachedProducer.h File Reference	4068

7.3	src/main/activemq/cmsutil/CmsAccessor.h File Reference	4069
7.4	src/main/activemq/cmsutil/CmsDestinationAccessor.h File Reference	4070
7.5	src/main/activemq/cmsutil/CmsTemplate.h File Reference	4071
7.6	src/main/activemq/cmsutil/DestinationResolver.h File Reference	4072
7.7	src/main/activemq/cmsutil/DynamicDestinationResolver.h File Reference	4073
7.8	src/main/activemq/cmsutil/MessageCreator.h File Reference	4074
7.9	src/main/activemq/cmsutil/PooledSession.h File Reference	4075
7.10	src/main/activemq/cmsutil/ProducerCallback.h File Reference	4076
7.11	src/main/activemq/cmsutil/ResourceLifecycleManager.h File Reference	4077
7.12	src/main/decaf/internal/util/ResourceLifecycleManager.h File Reference	4078
7.13	src/main/activemq/cmsutil/SessionCallback.h File Reference	4079
7.14	src/main/activemq/cmsutil/SessionPool.h File Reference	4080
7.15	src/main/activemq/commands/ActiveMQBlobMessage.h File Reference	4081
7.16	src/main/activemq/commands/ActiveMQBytesMessage.h File Reference	4082
7.17	src/main/activemq/commands/ActiveMQDestination.h File Reference	4083
7.18	src/main/activemq/commands/ActiveMQMapMessage.h File Reference	4084
7.19	src/main/activemq/commands/ActiveMQMessage.h File Reference	4085
7.20	src/main/activemq/commands/ActiveMQMessageTemplate.h File Reference	4086
7.21	src/main/activemq/commands/ActiveMQObjectMessage.h File Reference	4087
7.22	src/main/activemq/commands/ActiveMQQueue.h File Reference	4088
7.23	src/main/activemq/commands/ActiveMQStreamMessage.h File Reference	4089
7.24	src/main/activemq/commands/ActiveMQTempDestination.h File Reference	4090
7.25	src/main/activemq/commands/ActiveMQTempQueue.h File Reference	4091
7.26	src/main/activemq/commands/ActiveMQTempTopic.h File Reference	4092
7.27	src/main/activemq/commands/ActiveMQTextMessage.h File Reference	4093
7.28	src/main/activemq/commands/ActiveMQTopic.h File Reference	4094
7.29	src/main/activemq/commands/BaseCommand.h File Reference	4095
7.30	src/main/activemq/commands/BaseDataStructure.h File Reference	4096
7.31	src/main/activemq/commands/BooleanExpression.h File Reference	4097
7.32	src/main/activemq/commands/BrokerError.h File Reference	4098
7.33	src/main/activemq/commands/BrokerId.h File Reference	4099
7.34	src/main/activemq/commands/BrokerInfo.h File Reference	4100
7.35	src/main/activemq/commands/Command.h File Reference	4101
7.36	src/main/activemq/commands/ConnectionControl.h File Reference	4102
7.37	src/main/activemq/commands/ConnectionError.h File Reference	4103
7.38	src/main/activemq/commands/ConnectionId.h File Reference	4104

7.39	src/main/activemq/commands/ConnectionInfo.h File Reference	4105
7.40	src/main/activemq/commands/ConsumerControl.h File Reference	4106
7.41	src/main/activemq/commands/ConsumerId.h File Reference	4107
7.42	src/main/activemq/commands/ConsumerInfo.h File Reference	4108
7.43	src/main/activemq/commands/ControlCommand.h File Reference	4109
7.44	src/main/activemq/commands/DataArrayResponse.h File Reference	4110
7.45	src/main/activemq/commands/DataResponse.h File Reference	4111
7.46	src/main/activemq/commands/DataStructure.h File Reference	4112
7.47	src/main/activemq/commands/DestinationInfo.h File Reference	4113
7.48	src/main/activemq/commands/DiscoveryEvent.h File Reference	4114
7.49	src/main/activemq/commands/ExceptionResponse.h File Reference	4115
7.50	src/main/activemq/commands/FlushCommand.h File Reference	4116
7.51	src/main/activemq/commands/IntegerResponse.h File Reference	4117
7.52	src/main/activemq/commands/JournalQueueAck.h File Reference	4118
7.53	src/main/activemq/commands/JournalTopicAck.h File Reference	4119
7.54	src/main/activemq/commands/JournalTrace.h File Reference	4120
7.55	src/main/activemq/commands/JournalTransaction.h File Reference	4121
7.56	src/main/activemq/commands/KeepAliveInfo.h File Reference	4122
7.57	src/main/activemq/commands/LastPartialCommand.h File Reference	4123
7.58	src/main/activemq/commands/LocalTransactionId.h File Reference	4124
7.59	src/main/activemq/commands/Message.h File Reference	4125
7.60	src/main/cms/Message.h File Reference	4126
7.61	src/main/activemq/commands/MessageAck.h File Reference	4127
7.62	src/main/activemq/commands/MessageDispatch.h File Reference	4128
7.63	src/main/activemq/commands/MessageDispatchNotification.h File Reference . . .	4129
7.64	src/main/activemq/commands/MessageId.h File Reference	4130
7.65	src/main/activemq/commands/MessagePull.h File Reference	4131
7.66	src/main/activemq/commands/NetworkBridgeFilter.h File Reference	4132
7.67	src/main/activemq/commands/PartialCommand.h File Reference	4133
7.68	src/main/activemq/commands/ProducerAck.h File Reference	4134
7.69	src/main/activemq/commands/ProducerId.h File Reference	4135
7.70	src/main/activemq/commands/ProducerInfo.h File Reference	4136
7.71	src/main/activemq/commands/RemoveInfo.h File Reference	4137
7.72	src/main/activemq/commands/RemoveSubscriptionInfo.h File Reference	4138
7.73	src/main/activemq/commands/ReplayCommand.h File Reference	4139
7.74	src/main/activemq/commands/Response.h File Reference	4140

7.75	src/main/activemq/commands/SessionId.h File Reference	4141
7.76	src/main/activemq/commands/SessionInfo.h File Reference	4142
7.77	src/main/activemq/commands/ShutdownInfo.h File Reference	4143
7.78	src/main/activemq/commands/SubscriptionInfo.h File Reference	4144
7.79	src/main/activemq/commands/TransactionId.h File Reference	4145
7.80	src/main/activemq/commands/TransactionInfo.h File Reference	4146
7.81	src/main/activemq/commands/WireFormatInfo.h File Reference	4147
7.82	src/main/activemq/commands/XATransactionId.h File Reference	4148
7.83	src/main/activemq/core/ActiveMQAckHandler.h File Reference	4149
7.84	src/main/activemq/core/ActiveMQConnection.h File Reference	4150
7.85	src/main/activemq/core/ActiveMQConnectionFactory.h File Reference	4151
7.86	src/main/activemq/core/ActiveMQConnectionMetaData.h File Reference	4152
7.87	src/main/activemq/core/ActiveMQConstants.h File Reference	4153
7.88	src/main/activemq/core/ActiveMQConsumer.h File Reference	4154
7.89	src/main/activemq/core/ActiveMQProducer.h File Reference	4155
7.90	src/main/activemq/core/ActiveMQQueueBrowser.h File Reference	4156
7.91	src/main/activemq/core/ActiveMQSession.h File Reference	4157
7.92	src/main/activemq/core/ActiveMQSessionExecutor.h File Reference	4158
7.93	src/main/activemq/core/ActiveMQTransactionContext.h File Reference	4159
7.94	src/main/activemq/core/DispatchData.h File Reference	4160
7.95	src/main/activemq/core/Dispatcher.h File Reference	4161
7.96	src/main/activemq/core/MessageDispatchChannel.h File Reference	4162
7.97	src/main/activemq/core/policies/DefaultPrefetchPolicy.h File Reference	4163
7.98	src/main/activemq/core/policies/DefaultRedeliveryPolicy.h File Reference	4164
7.99	src/main/activemq/core/PrefetchPolicy.h File Reference	4165
7.100	src/main/activemq/core/RedeliveryPolicy.h File Reference	4166
7.101	src/main/activemq/core/Synchronization.h File Reference	4167
7.102	src/main/activemq/exceptions/ActiveMQException.h File Reference	4168
7.103	src/main/activemq/exceptions/BrokerException.h File Reference	4169
7.104	src/main/activemq/exceptions/ExceptionDefines.h File Reference	4170
7.104.1	Define Documentation	4170
7.104.1.1	AMQ_CATCH_EXCEPTION_CONVERT	4170
7.104.1.2	AMQ_CATCH_NOTHROW	4170
7.104.1.3	AMQ_CATCH_RETHROW	4171
7.104.1.4	AMQ_CATCHALL_NOTHROW	4171
7.104.1.5	AMQ_CATCHALL_THROW	4171

7.105src/main/decaf/lang/exceptions/ExceptionDefines.h File Reference	4173
7.105.1 Define Documentation	4173
7.105.1.1 DECAF_CATCH_EXCEPTION_CONVERT	4173
7.105.1.2 DECAF_CATCH_NOTHROW	4173
7.105.1.3 DECAF_CATCH_RETHROW	4174
7.105.1.4 DECAF_CATCHALL_NOTHROW	4174
7.105.1.5 DECAF_CATCHALL_THROW	4174
7.106src/main/activemq/io/LoggingInputStream.h File Reference	4175
7.107src/main/activemq/io/LoggingOutputStream.h File Reference	4176
7.108src/main/activemq/library/ActiveMQCPP.h File Reference	4177
7.109src/main/activemq/state/CommandVisitor.h File Reference	4178
7.110src/main/activemq/state/CommandVisitorAdapter.h File Reference	4179
7.111src/main/activemq/state/ConnectionState.h File Reference	4181
7.112src/main/activemq/state/ConnectionStateTracker.h File Reference	4182
7.113src/main/activemq/state/ConsumerState.h File Reference	4183
7.114src/main/activemq/state/ProducerState.h File Reference	4184
7.115src/main/activemq/state/SessionState.h File Reference	4185
7.116src/main/activemq/state/Tracked.h File Reference	4186
7.117src/main/activemq/state/TransactionState.h File Reference	4187
7.118src/main/activemq/threads/CompositeTask.h File Reference	4188
7.119src/main/activemq/threads/CompositeTaskRunner.h File Reference	4189
7.120src/main/activemq/threads/DedicatedTaskRunner.h File Reference	4190
7.121src/main/activemq/threads/Task.h File Reference	4191
7.122src/main/activemq/threads/TaskRunner.h File Reference	4192
7.123src/main/activemq/transport/AbstractTransportFactory.h File Reference	4193
7.124src/main/activemq/transport/CompositeTransport.h File Reference	4194
7.125src/main/activemq/transport/correlator/FutureResponse.h File Reference	4195
7.126src/main/activemq/transport/correlator/ResponseCorrelator.h File Reference	4196
7.127src/main/activemq/transport/DefaultTransportListener.h File Reference	4197
7.128src/main/activemq/transport/failover/BackupTransport.h File Reference	4198
7.129src/main/activemq/transport/failover/BackupTransportPool.h File Reference	4199
7.130src/main/activemq/transport/failover/CloseTransportsTask.h File Reference	4200
7.131src/main/activemq/transport/failover/FailoverTransport.h File Reference	4201
7.132src/main/activemq/transport/failover/FailoverTransportFactory.h File Reference	4202
7.133src/main/activemq/transport/failover/FailoverTransportListener.h File Reference	4203
7.134src/main/activemq/transport/failover/URIPool.h File Reference	4204

7.135src/main/activemq/transport/inactivity/InactivityMonitor.h File Reference	4205
7.136src/main/activemq/transport/inactivity/ReadChecker.h File Reference	4206
7.137src/main/activemq/transport/inactivity/WriteChecker.h File Reference	4207
7.138src/main/activemq/transport/IOTransport.h File Reference	4208
7.139src/main/activemq/transport/logging/LoggingTransport.h File Reference	4209
7.140src/main/activemq/transport/mock/InternalCommandListener.h File Reference . .	4210
7.141src/main/activemq/transport/mock/MockTransport.h File Reference	4211
7.142src/main/activemq/transport/mock/MockTransportFactory.h File Reference . . .	4212
7.143src/main/activemq/transport/mock/ResponseBuilder.h File Reference	4213
7.144src/main/activemq/transport/tcp/SslTransport.h File Reference	4214
7.145src/main/activemq/transport/tcp/SslTransportFactory.h File Reference	4215
7.146src/main/activemq/transport/tcp/TcpTransport.h File Reference	4216
7.147src/main/activemq/transport/tcp/TcpTransportFactory.h File Reference	4217
7.148src/main/activemq/transport/Transport.h File Reference	4218
7.149src/main/activemq/transport/TransportFactory.h File Reference	4219
7.150src/main/activemq/transport/TransportFilter.h File Reference	4220
7.151src/main/activemq/transport/TransportListener.h File Reference	4221
7.152src/main/activemq/transport/TransportRegistry.h File Reference	4222
7.153src/main/activemq/util/ActiveMQProperties.h File Reference	4223
7.154src/main/activemq/util/CMSExceptionSupport.h File Reference	4224
7.154.1 Define Documentation	4224
7.154.1.1 AMQ_CATCH_ALL_THROW_CMSEXCEPTION	4224
7.155src/main/activemq/util/CompositeData.h File Reference	4226
7.156src/main/activemq/util/Config.h File Reference	4227
7.156.1 Define Documentation	4227
7.156.1.1 AMQCPP_API	4227
7.157src/main/cms/Config.h File Reference	4228
7.157.1 Define Documentation	4228
7.157.1.1 CMS_API	4228
7.158src/main/decaf/util/Config.h File Reference	4229
7.158.1 Define Documentation	4229
7.158.1.1 DECAF_API	4229
7.158.1.2 DECAF_UNUSED	4229
7.159src/main/activemq/util/IdGenerator.h File Reference	4230
7.160src/main/activemq/util/LongSequenceGenerator.h File Reference	4231
7.161src/main/activemq/util/MarshallingSupport.h File Reference	4232

7.162src/main/activemq/util/MemoryUsage.h File Reference	4233
7.163src/main/activemq/util/PrimitiveList.h File Reference	4234
7.164src/main/activemq/util/PrimitiveMap.h File Reference	4235
7.165src/main/activemq/util/PrimitiveValueConverter.h File Reference	4236
7.166src/main/activemq/util/PrimitiveValueNode.h File Reference	4237
7.167src/main/activemq/util/URISupport.h File Reference	4238
7.168src/main/activemq/util/Usage.h File Reference	4239
7.169src/main/activemq/wireformat/MarshalAware.h File Reference	4240
7.170src/main/activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h File Reference	4241
7.171src/main/activemq/wireformat/openwire/marshal/DataStreamMarshaller.h File Reference	4242
7.172src/main/activemq/wireformat/openwire/marshal/PrimitiveTypesMarshaller.h File Reference	4243
7.173src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBlobMessageMarshaller.h File Reference	4244
7.174src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBlobMessageMarshaller.h File Reference	4245
7.175src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBlobMessageMarshaller.h File Reference	4246
7.176src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBlobMessageMarshaller.h File Reference	4247
7.177src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBlobMessageMarshaller.h File Reference	4248
7.178src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBlobMessageMarshaller.h File Reference	4249
7.179src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBytesMessageMarshaller.h File Reference	4250
7.180src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBytesMessageMarshaller.h File Reference	4251
7.181src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBytesMessageMarshaller.h File Reference	4252
7.182src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBytesMessageMarshaller.h File Reference	4253
7.183src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBytesMessageMarshaller.h File Reference	4254
7.184src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBytesMessageMarshaller.h File Reference	4255
7.185src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h File Reference	4256
7.186src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h File Reference	4257

7.187	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h	
	File Reference	4258
7.188	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h	
	File Reference	4259
7.189	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h	
	File Reference	4260
7.190	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQDestinationMarshaller.h	
	File Reference	4261
7.191	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMapMessageMarshaller.h	
	File Reference	4262
7.192	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMapMessageMarshaller.h	
	File Reference	4263
7.193	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMapMessageMarshaller.h	
	File Reference	4264
7.194	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMapMessageMarshaller.h	
	File Reference	4265
7.195	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMapMessageMarshaller.h	
	File Reference	4266
7.196	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQMapMessageMarshaller.h	
	File Reference	4267
7.197	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMessageMarshaller.h	
	File Reference	4268
7.198	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMessageMarshaller.h	
	File Reference	4269
7.199	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMessageMarshaller.h	
	File Reference	4270
7.200	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMessageMarshaller.h	
	File Reference	4271
7.201	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMessageMarshaller.h	
	File Reference	4272
7.202	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQMessageMarshaller.h	
	File Reference	4273
7.203	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQObjectMessageMarshaller.h	
	File Reference	4274
7.204	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQObjectMessageMarshaller.h	
	File Reference	4275
7.205	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQObjectMessageMarshaller.h	
	File Reference	4276
7.206	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQObjectMessageMarshaller.h	
	File Reference	4277
7.207	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQObjectMessageMarshaller.h	
	File Reference	4278
7.208	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQObjectMessageMarshaller.h	
	File Reference	4279

7.209	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQQueueMarshaller.h	
	File Reference	4280
7.210	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQQueueMarshaller.h	
	File Reference	4281
7.211	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQQueueMarshaller.h	
	File Reference	4282
7.212	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h	
	File Reference	4283
7.213	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQQueueMarshaller.h	
	File Reference	4284
7.214	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQQueueMarshaller.h	
	File Reference	4285
7.215	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQStreamMessageMarshaller.h	
	File Reference	4286
7.216	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQStreamMessageMarshaller.h	
	File Reference	4287
7.217	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQStreamMessageMarshaller.h	
	File Reference	4288
7.218	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQStreamMessageMarshaller.h	
	File Reference	4289
7.219	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQStreamMessageMarshaller.h	
	File Reference	4290
7.220	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQStreamMessageMarshaller.h	
	File Reference	4291
7.221	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h	
	File Reference	4292
7.222	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h	
	File Reference	4293
7.223	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h	
	File Reference	4294
7.224	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h	
	File Reference	4295
7.225	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h	
	File Reference	4296
7.226	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h	
	File Reference	4297
7.227	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempQueueMarshaller.h	
	File Reference	4298
7.228	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempQueueMarshaller.h	
	File Reference	4299
7.229	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempQueueMarshaller.h	
	File Reference	4300
7.230	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempQueueMarshaller.h	
	File Reference	4301

7.231	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempQueueMarshaller.h	
	File Reference	4302
7.232	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempQueueMarshaller.h	
	File Reference	4303
7.233	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h	
	File Reference	4304
7.234	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempTopicMarshaller.h	
	File Reference	4305
7.235	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempTopicMarshaller.h	
	File Reference	4306
7.236	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempTopicMarshaller.h	
	File Reference	4307
7.237	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempTopicMarshaller.h	
	File Reference	4308
7.238	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempTopicMarshaller.h	
	File Reference	4309
7.239	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTextMessageMarshaller.h	
	File Reference	4310
7.240	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTextMessageMarshaller.h	
	File Reference	4311
7.241	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTextMessageMarshaller.h	
	File Reference	4312
7.242	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTextMessageMarshaller.h	
	File Reference	4313
7.243	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTextMessageMarshaller.h	
	File Reference	4314
7.244	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTextMessageMarshaller.h	
	File Reference	4315
7.245	src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTopicMarshaller.h	
	File Reference	4316
7.246	src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTopicMarshaller.h	
	File Reference	4317
7.247	src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTopicMarshaller.h	
	File Reference	4318
7.248	src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTopicMarshaller.h	
	File Reference	4319
7.249	src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTopicMarshaller.h	
	File Reference	4320
7.250	src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTopicMarshaller.h	
	File Reference	4321
7.251	src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h	
	File Reference	4322
7.252	src/main/activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h	
	File Reference	4323

7.253src/main/activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h	
File Reference	4324
7.254src/main/activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h	
File Reference	4325
7.255src/main/activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h	
File Reference	4326
7.256src/main/activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h	
File Reference	4327
7.257src/main/activemq/wireformat/openwire/marshal/v1/BrokerIdMarshaller.h	File
Reference	4328
7.258src/main/activemq/wireformat/openwire/marshal/v2/BrokerIdMarshaller.h	File
Reference	4329
7.259src/main/activemq/wireformat/openwire/marshal/v3/BrokerIdMarshaller.h	File
Reference	4330
7.260src/main/activemq/wireformat/openwire/marshal/v4/BrokerIdMarshaller.h	File
Reference	4331
7.261src/main/activemq/wireformat/openwire/marshal/v5/BrokerIdMarshaller.h	File
Reference	4332
7.262src/main/activemq/wireformat/openwire/marshal/v6/BrokerIdMarshaller.h	File
Reference	4333
7.263src/main/activemq/wireformat/openwire/marshal/v1/BrokerInfoMarshaller.h	File
Reference	4334
7.264src/main/activemq/wireformat/openwire/marshal/v2/BrokerInfoMarshaller.h	File
Reference	4335
7.265src/main/activemq/wireformat/openwire/marshal/v3/BrokerInfoMarshaller.h	File
Reference	4336
7.266src/main/activemq/wireformat/openwire/marshal/v4/BrokerInfoMarshaller.h	File
Reference	4337
7.267src/main/activemq/wireformat/openwire/marshal/v5/BrokerInfoMarshaller.h	File
Reference	4338
7.268src/main/activemq/wireformat/openwire/marshal/v6/BrokerInfoMarshaller.h	File
Reference	4339
7.269src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h	
File Reference	4340
7.270src/main/activemq/wireformat/openwire/marshal/v2/ConnectionControlMarshaller.h	
File Reference	4341
7.271src/main/activemq/wireformat/openwire/marshal/v3/ConnectionControlMarshaller.h	
File Reference	4342
7.272src/main/activemq/wireformat/openwire/marshal/v4/ConnectionControlMarshaller.h	
File Reference	4343
7.273src/main/activemq/wireformat/openwire/marshal/v5/ConnectionControlMarshaller.h	
File Reference	4344
7.274src/main/activemq/wireformat/openwire/marshal/v6/ConnectionControlMarshaller.h	
File Reference	4345

7.275	src/main/activemq/wireformat/openwire/marshal/v1/ConnectionErrorMarshaller.h	
	File Reference	4346
7.276	src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h	
	File Reference	4347
7.277	src/main/activemq/wireformat/openwire/marshal/v3/ConnectionErrorMarshaller.h	
	File Reference	4348
7.278	src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h	
	File Reference	4349
7.279	src/main/activemq/wireformat/openwire/marshal/v5/ConnectionErrorMarshaller.h	
	File Reference	4350
7.280	src/main/activemq/wireformat/openwire/marshal/v6/ConnectionErrorMarshaller.h	
	File Reference	4351
7.281	src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h	
	File Reference	4352
7.282	src/main/activemq/wireformat/openwire/marshal/v2/ConnectionIdMarshaller.h	
	File Reference	4353
7.283	src/main/activemq/wireformat/openwire/marshal/v3/ConnectionIdMarshaller.h	
	File Reference	4354
7.284	src/main/activemq/wireformat/openwire/marshal/v4/ConnectionIdMarshaller.h	
	File Reference	4355
7.285	src/main/activemq/wireformat/openwire/marshal/v5/ConnectionIdMarshaller.h	
	File Reference	4356
7.286	src/main/activemq/wireformat/openwire/marshal/v6/ConnectionIdMarshaller.h	
	File Reference	4357
7.287	src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h	
	File Reference	4358
7.288	src/main/activemq/wireformat/openwire/marshal/v2/ConnectionInfoMarshaller.h	
	File Reference	4359
7.289	src/main/activemq/wireformat/openwire/marshal/v3/ConnectionInfoMarshaller.h	
	File Reference	4360
7.290	src/main/activemq/wireformat/openwire/marshal/v4/ConnectionInfoMarshaller.h	
	File Reference	4361
7.291	src/main/activemq/wireformat/openwire/marshal/v5/ConnectionInfoMarshaller.h	
	File Reference	4362
7.292	src/main/activemq/wireformat/openwire/marshal/v6/ConnectionInfoMarshaller.h	
	File Reference	4363
7.293	src/main/activemq/wireformat/openwire/marshal/v1/ConsumerControlMarshaller.h	
	File Reference	4364
7.294	src/main/activemq/wireformat/openwire/marshal/v2/ConsumerControlMarshaller.h	
	File Reference	4365
7.295	src/main/activemq/wireformat/openwire/marshal/v3/ConsumerControlMarshaller.h	
	File Reference	4366
7.296	src/main/activemq/wireformat/openwire/marshal/v4/ConsumerControlMarshaller.h	
	File Reference	4367

7.297	src/main/activemq/wireformat/openwire/marshal/v5/ConsumerControlMarshaller.h	
	File Reference	4368
7.298	src/main/activemq/wireformat/openwire/marshal/v6/ConsumerControlMarshaller.h	
	File Reference	4369
7.299	src/main/activemq/wireformat/openwire/marshal/v1/ConsumerIdMarshaller.h	
	File Reference	4370
7.300	src/main/activemq/wireformat/openwire/marshal/v2/ConsumerIdMarshaller.h	
	File Reference	4371
7.301	src/main/activemq/wireformat/openwire/marshal/v3/ConsumerIdMarshaller.h	
	File Reference	4372
7.302	src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h	
	File Reference	4373
7.303	src/main/activemq/wireformat/openwire/marshal/v5/ConsumerIdMarshaller.h	
	File Reference	4374
7.304	src/main/activemq/wireformat/openwire/marshal/v6/ConsumerIdMarshaller.h	
	File Reference	4375
7.305	src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h	
	File Reference	4376
7.306	src/main/activemq/wireformat/openwire/marshal/v2/ConsumerInfoMarshaller.h	
	File Reference	4377
7.307	src/main/activemq/wireformat/openwire/marshal/v3/ConsumerInfoMarshaller.h	
	File Reference	4378
7.308	src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h	
	File Reference	4379
7.309	src/main/activemq/wireformat/openwire/marshal/v5/ConsumerInfoMarshaller.h	
	File Reference	4380
7.310	src/main/activemq/wireformat/openwire/marshal/v6/ConsumerInfoMarshaller.h	
	File Reference	4381
7.311	src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h	
	File Reference	4382
7.312	src/main/activemq/wireformat/openwire/marshal/v2/ControlCommandMarshaller.h	
	File Reference	4383
7.313	src/main/activemq/wireformat/openwire/marshal/v3/ControlCommandMarshaller.h	
	File Reference	4384
7.314	src/main/activemq/wireformat/openwire/marshal/v4/ControlCommandMarshaller.h	
	File Reference	4385
7.315	src/main/activemq/wireformat/openwire/marshal/v5/ControlCommandMarshaller.h	
	File Reference	4386
7.316	src/main/activemq/wireformat/openwire/marshal/v6/ControlCommandMarshaller.h	
	File Reference	4387
7.317	src/main/activemq/wireformat/openwire/marshal/v1/DataArrayResponseMarshaller.h	
	File Reference	4388
7.318	src/main/activemq/wireformat/openwire/marshal/v2/DataArrayResponseMarshaller.h	
	File Reference	4389

7.319	src/main/activemq/wireformat/openwire/marshal/v3/DataArrayResponseMarshaller.h	
	File Reference	4390
7.320	src/main/activemq/wireformat/openwire/marshal/v4/DataArrayResponseMarshaller.h	
	File Reference	4391
7.321	src/main/activemq/wireformat/openwire/marshal/v5/DataArrayResponseMarshaller.h	
	File Reference	4392
7.322	src/main/activemq/wireformat/openwire/marshal/v6/DataArrayResponseMarshaller.h	
	File Reference	4393
7.323	src/main/activemq/wireformat/openwire/marshal/v1/DataResponseMarshaller.h	
	File Reference	4394
7.324	src/main/activemq/wireformat/openwire/marshal/v2/DataResponseMarshaller.h	
	File Reference	4395
7.325	src/main/activemq/wireformat/openwire/marshal/v3/DataResponseMarshaller.h	
	File Reference	4396
7.326	src/main/activemq/wireformat/openwire/marshal/v4/DataResponseMarshaller.h	
	File Reference	4397
7.327	src/main/activemq/wireformat/openwire/marshal/v5/DataResponseMarshaller.h	
	File Reference	4398
7.328	src/main/activemq/wireformat/openwire/marshal/v6/DataResponseMarshaller.h	
	File Reference	4399
7.329	src/main/activemq/wireformat/openwire/marshal/v1/DestinationInfoMarshaller.h	
	File Reference	4400
7.330	src/main/activemq/wireformat/openwire/marshal/v2/DestinationInfoMarshaller.h	
	File Reference	4401
7.331	src/main/activemq/wireformat/openwire/marshal/v3/DestinationInfoMarshaller.h	
	File Reference	4402
7.332	src/main/activemq/wireformat/openwire/marshal/v4/DestinationInfoMarshaller.h	
	File Reference	4403
7.333	src/main/activemq/wireformat/openwire/marshal/v5/DestinationInfoMarshaller.h	
	File Reference	4404
7.334	src/main/activemq/wireformat/openwire/marshal/v6/DestinationInfoMarshaller.h	
	File Reference	4405
7.335	src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryEventMarshaller.h	
	File Reference	4406
7.336	src/main/activemq/wireformat/openwire/marshal/v2/DiscoveryEventMarshaller.h	
	File Reference	4407
7.337	src/main/activemq/wireformat/openwire/marshal/v3/DiscoveryEventMarshaller.h	
	File Reference	4408
7.338	src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryEventMarshaller.h	
	File Reference	4409
7.339	src/main/activemq/wireformat/openwire/marshal/v5/DiscoveryEventMarshaller.h	
	File Reference	4410
7.340	src/main/activemq/wireformat/openwire/marshal/v6/DiscoveryEventMarshaller.h	
	File Reference	4411

7.341	src/main/activemq/wireformat/openwire/marshal/v1/ExceptionResponseMarshaller.h	
	File Reference	4412
7.342	src/main/activemq/wireformat/openwire/marshal/v2/ExceptionResponseMarshaller.h	
	File Reference	4413
7.343	src/main/activemq/wireformat/openwire/marshal/v3/ExceptionResponseMarshaller.h	
	File Reference	4414
7.344	src/main/activemq/wireformat/openwire/marshal/v4/ExceptionResponseMarshaller.h	
	File Reference	4415
7.345	src/main/activemq/wireformat/openwire/marshal/v5/ExceptionResponseMarshaller.h	
	File Reference	4416
7.346	src/main/activemq/wireformat/openwire/marshal/v6/ExceptionResponseMarshaller.h	
	File Reference	4417
7.347	src/main/activemq/wireformat/openwire/marshal/v1/FlushCommandMarshaller.h	
	File Reference	4418
7.348	src/main/activemq/wireformat/openwire/marshal/v2/FlushCommandMarshaller.h	
	File Reference	4419
7.349	src/main/activemq/wireformat/openwire/marshal/v3/FlushCommandMarshaller.h	
	File Reference	4420
7.350	src/main/activemq/wireformat/openwire/marshal/v4/FlushCommandMarshaller.h	
	File Reference	4421
7.351	src/main/activemq/wireformat/openwire/marshal/v5/FlushCommandMarshaller.h	
	File Reference	4422
7.352	src/main/activemq/wireformat/openwire/marshal/v6/FlushCommandMarshaller.h	
	File Reference	4423
7.353	src/main/activemq/wireformat/openwire/marshal/v1/IntegerResponseMarshaller.h	
	File Reference	4424
7.354	src/main/activemq/wireformat/openwire/marshal/v2/IntegerResponseMarshaller.h	
	File Reference	4425
7.355	src/main/activemq/wireformat/openwire/marshal/v3/IntegerResponseMarshaller.h	
	File Reference	4426
7.356	src/main/activemq/wireformat/openwire/marshal/v4/IntegerResponseMarshaller.h	
	File Reference	4427
7.357	src/main/activemq/wireformat/openwire/marshal/v5/IntegerResponseMarshaller.h	
	File Reference	4428
7.358	src/main/activemq/wireformat/openwire/marshal/v6/IntegerResponseMarshaller.h	
	File Reference	4429
7.359	src/main/activemq/wireformat/openwire/marshal/v1/JournalQueueAckMarshaller.h	
	File Reference	4430
7.360	src/main/activemq/wireformat/openwire/marshal/v2/JournalQueueAckMarshaller.h	
	File Reference	4431
7.361	src/main/activemq/wireformat/openwire/marshal/v3/JournalQueueAckMarshaller.h	
	File Reference	4432
7.362	src/main/activemq/wireformat/openwire/marshal/v4/JournalQueueAckMarshaller.h	
	File Reference	4433

7.363	src/main/activemq/wireformat/openwire/marshal/v5/JournalQueueAckMarshaller.h	
	File Reference	4434
7.364	src/main/activemq/wireformat/openwire/marshal/v6/JournalQueueAckMarshaller.h	
	File Reference	4435
7.365	src/main/activemq/wireformat/openwire/marshal/v1/JournalTopicAckMarshaller.h	
	File Reference	4436
7.366	src/main/activemq/wireformat/openwire/marshal/v2/JournalTopicAckMarshaller.h	
	File Reference	4437
7.367	src/main/activemq/wireformat/openwire/marshal/v3/JournalTopicAckMarshaller.h	
	File Reference	4438
7.368	src/main/activemq/wireformat/openwire/marshal/v4/JournalTopicAckMarshaller.h	
	File Reference	4439
7.369	src/main/activemq/wireformat/openwire/marshal/v5/JournalTopicAckMarshaller.h	
	File Reference	4440
7.370	src/main/activemq/wireformat/openwire/marshal/v6/JournalTopicAckMarshaller.h	
	File Reference	4441
7.371	src/main/activemq/wireformat/openwire/marshal/v1/JournalTraceMarshaller.h	
	File Reference	4442
7.372	src/main/activemq/wireformat/openwire/marshal/v2/JournalTraceMarshaller.h	
	File Reference	4443
7.373	src/main/activemq/wireformat/openwire/marshal/v3/JournalTraceMarshaller.h	
	File Reference	4444
7.374	src/main/activemq/wireformat/openwire/marshal/v4/JournalTraceMarshaller.h	
	File Reference	4445
7.375	src/main/activemq/wireformat/openwire/marshal/v5/JournalTraceMarshaller.h	
	File Reference	4446
7.376	src/main/activemq/wireformat/openwire/marshal/v6/JournalTraceMarshaller.h	
	File Reference	4447
7.377	src/main/activemq/wireformat/openwire/marshal/v1/JournalTransactionMarshaller.h	
	File Reference	4448
7.378	src/main/activemq/wireformat/openwire/marshal/v2/JournalTransactionMarshaller.h	
	File Reference	4449
7.379	src/main/activemq/wireformat/openwire/marshal/v3/JournalTransactionMarshaller.h	
	File Reference	4450
7.380	src/main/activemq/wireformat/openwire/marshal/v4/JournalTransactionMarshaller.h	
	File Reference	4451
7.381	src/main/activemq/wireformat/openwire/marshal/v5/JournalTransactionMarshaller.h	
	File Reference	4452
7.382	src/main/activemq/wireformat/openwire/marshal/v6/JournalTransactionMarshaller.h	
	File Reference	4453
7.383	src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h	
	File Reference	4454
7.384	src/main/activemq/wireformat/openwire/marshal/v2/KeepAliveInfoMarshaller.h	
	File Reference	4455

7.385	src/main/activemq/wireformat/openwire/marshal/v3/KeepAliveInfoMarshaller.h	
	File Reference	4456
7.386	src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h	
	File Reference	4457
7.387	src/main/activemq/wireformat/openwire/marshal/v5/KeepAliveInfoMarshaller.h	
	File Reference	4458
7.388	src/main/activemq/wireformat/openwire/marshal/v6/KeepAliveInfoMarshaller.h	
	File Reference	4459
7.389	src/main/activemq/wireformat/openwire/marshal/v1/LastPartialCommandMarshaller.h	
	File Reference	4460
7.390	src/main/activemq/wireformat/openwire/marshal/v2/LastPartialCommandMarshaller.h	
	File Reference	4461
7.391	src/main/activemq/wireformat/openwire/marshal/v3/LastPartialCommandMarshaller.h	
	File Reference	4462
7.392	src/main/activemq/wireformat/openwire/marshal/v4/LastPartialCommandMarshaller.h	
	File Reference	4463
7.393	src/main/activemq/wireformat/openwire/marshal/v5/LastPartialCommandMarshaller.h	
	File Reference	4464
7.394	src/main/activemq/wireformat/openwire/marshal/v6/LastPartialCommandMarshaller.h	
	File Reference	4465
7.395	src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionIdMarshaller.h	
	File Reference	4466
7.396	src/main/activemq/wireformat/openwire/marshal/v2/LocalTransactionIdMarshaller.h	
	File Reference	4467
7.397	src/main/activemq/wireformat/openwire/marshal/v3/LocalTransactionIdMarshaller.h	
	File Reference	4468
7.398	src/main/activemq/wireformat/openwire/marshal/v4/LocalTransactionIdMarshaller.h	
	File Reference	4469
7.399	src/main/activemq/wireformat/openwire/marshal/v5/LocalTransactionIdMarshaller.h	
	File Reference	4470
7.400	src/main/activemq/wireformat/openwire/marshal/v6/LocalTransactionIdMarshaller.h	
	File Reference	4471
7.401	src/main/activemq/wireformat/openwire/marshal/v1/MarshallerFactory.h	File
	Reference	4472
7.402	src/main/activemq/wireformat/openwire/marshal/v2/MarshallerFactory.h	File
	Reference	4473
7.403	src/main/activemq/wireformat/openwire/marshal/v3/MarshallerFactory.h	File
	Reference	4474
7.404	src/main/activemq/wireformat/openwire/marshal/v4/MarshallerFactory.h	File
	Reference	4475
7.405	src/main/activemq/wireformat/openwire/marshal/v5/MarshallerFactory.h	File
	Reference	4476
7.406	src/main/activemq/wireformat/openwire/marshal/v6/MarshallerFactory.h	File
	Reference	4477

7.407src/main/activemq/wireformat/openwire/marshall/v1/MessageAckMarshaller.h	
File Reference	4478
7.408src/main/activemq/wireformat/openwire/marshall/v2/MessageAckMarshaller.h	
File Reference	4479
7.409src/main/activemq/wireformat/openwire/marshall/v3/MessageAckMarshaller.h	
File Reference	4480
7.410src/main/activemq/wireformat/openwire/marshall/v4/MessageAckMarshaller.h	
File Reference	4481
7.411src/main/activemq/wireformat/openwire/marshall/v5/MessageAckMarshaller.h	
File Reference	4482
7.412src/main/activemq/wireformat/openwire/marshall/v6/MessageAckMarshaller.h	
File Reference	4483
7.413src/main/activemq/wireformat/openwire/marshall/v1/MessageDispatchMarshaller.h	
File Reference	4484
7.414src/main/activemq/wireformat/openwire/marshall/v2/MessageDispatchMarshaller.h	
File Reference	4485
7.415src/main/activemq/wireformat/openwire/marshall/v3/MessageDispatchMarshaller.h	
File Reference	4486
7.416src/main/activemq/wireformat/openwire/marshall/v4/MessageDispatchMarshaller.h	
File Reference	4487
7.417src/main/activemq/wireformat/openwire/marshall/v5/MessageDispatchMarshaller.h	
File Reference	4488
7.418src/main/activemq/wireformat/openwire/marshall/v6/MessageDispatchMarshaller.h	
File Reference	4489
7.419src/main/activemq/wireformat/openwire/marshall/v1/MessageDispatchNotificationMarshaller.h	
File Reference	4490
7.420src/main/activemq/wireformat/openwire/marshall/v2/MessageDispatchNotificationMarshaller.h	
File Reference	4491
7.421src/main/activemq/wireformat/openwire/marshall/v3/MessageDispatchNotificationMarshaller.h	
File Reference	4492
7.422src/main/activemq/wireformat/openwire/marshall/v4/MessageDispatchNotificationMarshaller.h	
File Reference	4493
7.423src/main/activemq/wireformat/openwire/marshall/v5/MessageDispatchNotificationMarshaller.h	
File Reference	4494
7.424src/main/activemq/wireformat/openwire/marshall/v6/MessageDispatchNotificationMarshaller.h	
File Reference	4495
7.425src/main/activemq/wireformat/openwire/marshall/v1/MessageIdMarshaller.h	File
Reference	4496
7.426src/main/activemq/wireformat/openwire/marshall/v2/MessageIdMarshaller.h	File
Reference	4497
7.427src/main/activemq/wireformat/openwire/marshall/v3/MessageIdMarshaller.h	File
Reference	4498
7.428src/main/activemq/wireformat/openwire/marshall/v4/MessageIdMarshaller.h	File
Reference	4499

7.429	src/main/activemq/wireformat/openwire/marshal/v5/MessageIdMarshaller.h	File	
	Reference		4500
7.430	src/main/activemq/wireformat/openwire/marshal/v6/MessageIdMarshaller.h	File	
	Reference		4501
7.431	src/main/activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h	File	
	Reference		4502
7.432	src/main/activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h	File	
	Reference		4503
7.433	src/main/activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h	File	
	Reference		4504
7.434	src/main/activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h	File	
	Reference		4505
7.435	src/main/activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h	File	
	Reference		4506
7.436	src/main/activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h	File	
	Reference		4507
7.437	src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h		
	File Reference		4508
7.438	src/main/activemq/wireformat/openwire/marshal/v2/MessagePullMarshaller.h		
	File Reference		4509
7.439	src/main/activemq/wireformat/openwire/marshal/v3/MessagePullMarshaller.h		
	File Reference		4510
7.440	src/main/activemq/wireformat/openwire/marshal/v4/MessagePullMarshaller.h		
	File Reference		4511
7.441	src/main/activemq/wireformat/openwire/marshal/v5/MessagePullMarshaller.h		
	File Reference		4512
7.442	src/main/activemq/wireformat/openwire/marshal/v6/MessagePullMarshaller.h		
	File Reference		4513
7.443	src/main/activemq/wireformat/openwire/marshal/v1/NetworkBridgeFilterMarshaller.h		
	File Reference		4514
7.444	src/main/activemq/wireformat/openwire/marshal/v2/NetworkBridgeFilterMarshaller.h		
	File Reference		4515
7.445	src/main/activemq/wireformat/openwire/marshal/v3/NetworkBridgeFilterMarshaller.h		
	File Reference		4516
7.446	src/main/activemq/wireformat/openwire/marshal/v4/NetworkBridgeFilterMarshaller.h		
	File Reference		4517
7.447	src/main/activemq/wireformat/openwire/marshal/v5/NetworkBridgeFilterMarshaller.h		
	File Reference		4518
7.448	src/main/activemq/wireformat/openwire/marshal/v6/NetworkBridgeFilterMarshaller.h		
	File Reference		4519
7.449	src/main/activemq/wireformat/openwire/marshal/v1/PartialCommandMarshaller.h		
	File Reference		4520
7.450	src/main/activemq/wireformat/openwire/marshal/v2/PartialCommandMarshaller.h		
	File Reference		4521

7.451src/main/activemq/wireformat/openwire/marshal/v3/PartialCommandMarshaller.h	
File Reference	4522
7.452src/main/activemq/wireformat/openwire/marshal/v4/PartialCommandMarshaller.h	
File Reference	4523
7.453src/main/activemq/wireformat/openwire/marshal/v5/PartialCommandMarshaller.h	
File Reference	4524
7.454src/main/activemq/wireformat/openwire/marshal/v6/PartialCommandMarshaller.h	
File Reference	4525
7.455src/main/activemq/wireformat/openwire/marshal/v1/ProducerAckMarshaller.h	
File Reference	4526
7.456src/main/activemq/wireformat/openwire/marshal/v2/ProducerAckMarshaller.h	
File Reference	4527
7.457src/main/activemq/wireformat/openwire/marshal/v3/ProducerAckMarshaller.h	
File Reference	4528
7.458src/main/activemq/wireformat/openwire/marshal/v4/ProducerAckMarshaller.h	
File Reference	4529
7.459src/main/activemq/wireformat/openwire/marshal/v5/ProducerAckMarshaller.h	
File Reference	4530
7.460src/main/activemq/wireformat/openwire/marshal/v6/ProducerAckMarshaller.h	
File Reference	4531
7.461src/main/activemq/wireformat/openwire/marshal/v1/ProducerIdMarshaller.h	
File Reference	4532
7.462src/main/activemq/wireformat/openwire/marshal/v2/ProducerIdMarshaller.h	
File Reference	4533
7.463src/main/activemq/wireformat/openwire/marshal/v3/ProducerIdMarshaller.h	
File Reference	4534
7.464src/main/activemq/wireformat/openwire/marshal/v4/ProducerIdMarshaller.h	
File Reference	4535
7.465src/main/activemq/wireformat/openwire/marshal/v5/ProducerIdMarshaller.h	
File Reference	4536
7.466src/main/activemq/wireformat/openwire/marshal/v6/ProducerIdMarshaller.h	
File Reference	4537
7.467src/main/activemq/wireformat/openwire/marshal/v1/ProducerInfoMarshaller.h	
File Reference	4538
7.468src/main/activemq/wireformat/openwire/marshal/v2/ProducerInfoMarshaller.h	
File Reference	4539
7.469src/main/activemq/wireformat/openwire/marshal/v3/ProducerInfoMarshaller.h	
File Reference	4540
7.470src/main/activemq/wireformat/openwire/marshal/v4/ProducerInfoMarshaller.h	
File Reference	4541
7.471src/main/activemq/wireformat/openwire/marshal/v5/ProducerInfoMarshaller.h	
File Reference	4542
7.472src/main/activemq/wireformat/openwire/marshal/v6/ProducerInfoMarshaller.h	
File Reference	4543

7.473	src/main/activemq/wireformat/openwire/marshal/v1/RemoveInfoMarshaller.h	
	File Reference	4544
7.474	src/main/activemq/wireformat/openwire/marshal/v2/RemoveInfoMarshaller.h	
	File Reference	4545
7.475	src/main/activemq/wireformat/openwire/marshal/v3/RemoveInfoMarshaller.h	
	File Reference	4546
7.476	src/main/activemq/wireformat/openwire/marshal/v4/RemoveInfoMarshaller.h	
	File Reference	4547
7.477	src/main/activemq/wireformat/openwire/marshal/v5/RemoveInfoMarshaller.h	
	File Reference	4548
7.478	src/main/activemq/wireformat/openwire/marshal/v6/RemoveInfoMarshaller.h	
	File Reference	4549
7.479	src/main/activemq/wireformat/openwire/marshal/v1/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4550
7.480	src/main/activemq/wireformat/openwire/marshal/v2/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4551
7.481	src/main/activemq/wireformat/openwire/marshal/v3/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4552
7.482	src/main/activemq/wireformat/openwire/marshal/v4/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4553
7.483	src/main/activemq/wireformat/openwire/marshal/v5/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4554
7.484	src/main/activemq/wireformat/openwire/marshal/v6/RemoveSubscriptionInfoMarshaller.h	
	File Reference	4555
7.485	src/main/activemq/wireformat/openwire/marshal/v1/ReplayCommandMarshaller.h	
	File Reference	4556
7.486	src/main/activemq/wireformat/openwire/marshal/v2/ReplayCommandMarshaller.h	
	File Reference	4557
7.487	src/main/activemq/wireformat/openwire/marshal/v3/ReplayCommandMarshaller.h	
	File Reference	4558
7.488	src/main/activemq/wireformat/openwire/marshal/v4/ReplayCommandMarshaller.h	
	File Reference	4559
7.489	src/main/activemq/wireformat/openwire/marshal/v5/ReplayCommandMarshaller.h	
	File Reference	4560
7.490	src/main/activemq/wireformat/openwire/marshal/v6/ReplayCommandMarshaller.h	
	File Reference	4561
7.491	src/main/activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h	File
	Reference	4562
7.492	src/main/activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h	File
	Reference	4563
7.493	src/main/activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h	File
	Reference	4564
7.494	src/main/activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h	File
	Reference	4565

7.495	src/main/activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h	File	
	Reference		4566
7.496	src/main/activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h	File	
	Reference		4567
7.497	src/main/activemq/wireformat/openwire/marshal/v1/SessionIdMarshaller.h	File	
	Reference		4568
7.498	src/main/activemq/wireformat/openwire/marshal/v2/SessionIdMarshaller.h	File	
	Reference		4569
7.499	src/main/activemq/wireformat/openwire/marshal/v3/SessionIdMarshaller.h	File	
	Reference		4570
7.500	src/main/activemq/wireformat/openwire/marshal/v4/SessionIdMarshaller.h	File	
	Reference		4571
7.501	src/main/activemq/wireformat/openwire/marshal/v5/SessionIdMarshaller.h	File	
	Reference		4572
7.502	src/main/activemq/wireformat/openwire/marshal/v6/SessionIdMarshaller.h	File	
	Reference		4573
7.503	src/main/activemq/wireformat/openwire/marshal/v1/SessionInfoMarshaller.h	File	
	File Reference		4574
7.504	src/main/activemq/wireformat/openwire/marshal/v2/SessionInfoMarshaller.h	File	
	File Reference		4575
7.505	src/main/activemq/wireformat/openwire/marshal/v3/SessionInfoMarshaller.h	File	
	File Reference		4576
7.506	src/main/activemq/wireformat/openwire/marshal/v4/SessionInfoMarshaller.h	File	
	File Reference		4577
7.507	src/main/activemq/wireformat/openwire/marshal/v5/SessionInfoMarshaller.h	File	
	File Reference		4578
7.508	src/main/activemq/wireformat/openwire/marshal/v6/SessionInfoMarshaller.h	File	
	File Reference		4579
7.509	src/main/activemq/wireformat/openwire/marshal/v1/ShutdownInfoMarshaller.h	File	
	File Reference		4580
7.510	src/main/activemq/wireformat/openwire/marshal/v2/ShutdownInfoMarshaller.h	File	
	File Reference		4581
7.511	src/main/activemq/wireformat/openwire/marshal/v3/ShutdownInfoMarshaller.h	File	
	File Reference		4582
7.512	src/main/activemq/wireformat/openwire/marshal/v4/ShutdownInfoMarshaller.h	File	
	File Reference		4583
7.513	src/main/activemq/wireformat/openwire/marshal/v5/ShutdownInfoMarshaller.h	File	
	File Reference		4584
7.514	src/main/activemq/wireformat/openwire/marshal/v6/ShutdownInfoMarshaller.h	File	
	File Reference		4585
7.515	src/main/activemq/wireformat/openwire/marshal/v1/SubscriptionInfoMarshaller.h	File	
	File Reference		4586
7.516	src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h	File	
	File Reference		4587

7.517src/main/activemq/wireformat/openwire/marshal/v3/SubscriptionInfoMarshaller.h	
File Reference	4588
7.518src/main/activemq/wireformat/openwire/marshal/v4/SubscriptionInfoMarshaller.h	
File Reference	4589
7.519src/main/activemq/wireformat/openwire/marshal/v5/SubscriptionInfoMarshaller.h	
File Reference	4590
7.520src/main/activemq/wireformat/openwire/marshal/v6/SubscriptionInfoMarshaller.h	
File Reference	4591
7.521src/main/activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h	
File Reference	4592
7.522src/main/activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h	
File Reference	4593
7.523src/main/activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h	
File Reference	4594
7.524src/main/activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h	
File Reference	4595
7.525src/main/activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h	
File Reference	4596
7.526src/main/activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h	
File Reference	4597
7.527src/main/activemq/wireformat/openwire/marshal/v1/TransactionInfoMarshaller.h	
File Reference	4598
7.528src/main/activemq/wireformat/openwire/marshal/v2/TransactionInfoMarshaller.h	
File Reference	4599
7.529src/main/activemq/wireformat/openwire/marshal/v3/TransactionInfoMarshaller.h	
File Reference	4600
7.530src/main/activemq/wireformat/openwire/marshal/v4/TransactionInfoMarshaller.h	
File Reference	4601
7.531src/main/activemq/wireformat/openwire/marshal/v5/TransactionInfoMarshaller.h	
File Reference	4602
7.532src/main/activemq/wireformat/openwire/marshal/v6/TransactionInfoMarshaller.h	
File Reference	4603
7.533src/main/activemq/wireformat/openwire/marshal/v1/WireFormatInfoMarshaller.h	
File Reference	4604
7.534src/main/activemq/wireformat/openwire/marshal/v2/WireFormatInfoMarshaller.h	
File Reference	4605
7.535src/main/activemq/wireformat/openwire/marshal/v3/WireFormatInfoMarshaller.h	
File Reference	4606
7.536src/main/activemq/wireformat/openwire/marshal/v4/WireFormatInfoMarshaller.h	
File Reference	4607
7.537src/main/activemq/wireformat/openwire/marshal/v5/WireFormatInfoMarshaller.h	
File Reference	4608
7.538src/main/activemq/wireformat/openwire/marshal/v6/WireFormatInfoMarshaller.h	
File Reference	4609

7.539	src/main/activemq/wireformat/openwire/marshall/v1/XATransactionIdMarshaller.h	
	File Reference	4610
7.540	src/main/activemq/wireformat/openwire/marshall/v2/XATransactionIdMarshaller.h	
	File Reference	4611
7.541	src/main/activemq/wireformat/openwire/marshall/v3/XATransactionIdMarshaller.h	
	File Reference	4612
7.542	src/main/activemq/wireformat/openwire/marshall/v4/XATransactionIdMarshaller.h	
	File Reference	4613
7.543	src/main/activemq/wireformat/openwire/marshall/v5/XATransactionIdMarshaller.h	
	File Reference	4614
7.544	src/main/activemq/wireformat/openwire/marshall/v6/XATransactionIdMarshaller.h	
	File Reference	4615
7.545	src/main/activemq/wireformat/openwire/OpenWireFormat.h	File Reference
		4616
7.546	src/main/activemq/wireformat/openwire/OpenWireFormatFactory.h	File Reference
		4617
7.547	src/main/activemq/wireformat/openwire/OpenWireFormatNegotiator.h	File Ref-
	erence	4618
7.548	src/main/activemq/wireformat/openwire/OpenWireResponseBuilder.h	File Refer-
	ence	4619
7.549	src/main/activemq/wireformat/openwire/utis/BooleanStream.h	File Reference
		4620
7.550	src/main/activemq/wireformat/openwire/utis/HexTable.h	File Reference
		4621
7.551	src/main/activemq/wireformat/openwire/utis/MessagePropertyInterceptor.h	File
	Reference	4622
7.552	src/main/activemq/wireformat/stomp/StompCommandConstants.h	File Reference
		4623
7.553	src/main/activemq/wireformat/stomp/StompFrame.h	File Reference
		4624
7.554	src/main/activemq/wireformat/stomp/StompHelper.h	File Reference
		4625
7.555	src/main/activemq/wireformat/stomp/StompWireFormat.h	File Reference
		4626
7.556	src/main/activemq/wireformat/stomp/StompWireFormatFactory.h	File Reference
		4627
7.557	src/main/activemq/wireformat/WireFormat.h	File Reference
		4628
7.558	src/main/activemq/wireformat/WireFormatFactory.h	File Reference
		4629
7.559	src/main/activemq/wireformat/WireFormatNegotiator.h	File Reference
		4630
7.560	src/main/activemq/wireformat/WireFormatRegistry.h	File Reference
		4631
7.561	src/main/cms/BytesMessage.h	File Reference
		4632
7.562	src/main/cms/Closeable.h	File Reference
		4633
7.563	src/main/decaf/io/Closeable.h	File Reference
		4634
7.564	src/main/cms/CMSException.h	File Reference
		4635
7.565	src/main/cms/CMSProperties.h	File Reference
		4636
7.566	src/main/cms/CMSSecurityException.h	File Reference
		4637
7.567	src/main/cms/Connection.h	File Reference
		4638
7.568	src/main/cms/ConnectionFactory.h	File Reference
		4639

7.569src/main/cms/ConnectionMetaData.h File Reference	4640
7.570src/main/cms/DeliveryMode.h File Reference	4641
7.571src/main/cms/Destination.h File Reference	4642
7.572src/main/cms/ExceptionListener.h File Reference	4643
7.573src/main/cms/IllegalStateException.h File Reference	4644
7.574src/main/decaf/lang/exceptions/IllegalStateException.h File Reference	4645
7.575src/main/cms/InvalidClientIdException.h File Reference	4646
7.576src/main/cms/InvalidDestinationException.h File Reference	4647
7.577src/main/cms/InvalidSelectorException.h File Reference	4648
7.578src/main/cms/MapMessage.h File Reference	4649
7.579src/main/cms/MessageConsumer.h File Reference	4650
7.580src/main/cms/MessageEnumeration.h File Reference	4651
7.581src/main/cms/MessageEOFException.h File Reference	4652
7.582src/main/cms/MessageFormatException.h File Reference	4653
7.583src/main/cms/MessageListener.h File Reference	4654
7.584src/main/cms/MessageNotReadableException.h File Reference	4655
7.585src/main/cms/MessageNotWriteableException.h File Reference	4656
7.586src/main/cms/MessageProducer.h File Reference	4657
7.587src/main/cms/ObjectMessage.h File Reference	4658
7.588src/main/cms/Queue.h File Reference	4659
7.589src/main/decaf/util/Queue.h File Reference	4660
7.590src/main/cms/QueueBrowser.h File Reference	4661
7.591src/main/cms/Session.h File Reference	4662
7.592src/main/cms/Startable.h File Reference	4663
7.593src/main/cms/Stoppable.h File Reference	4664
7.594src/main/cms/StreamMessage.h File Reference	4665
7.595src/main/cms/TemporaryQueue.h File Reference	4666
7.596src/main/cms/TemporaryTopic.h File Reference	4667
7.597src/main/cms/TextMessage.h File Reference	4668
7.598src/main/cms/Topic.h File Reference	4669
7.599src/main/cms/UnsupportedOperationException.h File Reference	4670
7.600src/main/decaf/lang/exceptions/UnsupportedOperationException.h File Reference	4671
7.601src/main/decaf/internal/AprPool.h File Reference	4672
7.602src/main/decaf/internal/DecafRuntime.h File Reference	4673
7.603src/main/decaf/internal/io/StandardErrorOutputStream.h File Reference	4674
7.604src/main/decaf/internal/io/StandardInputStream.h File Reference	4675

7.605src/main/decaf/internal/io/StandardOutputStream.h File Reference	4676
7.606src/main/decaf/internal/net/DefaultServerSocketFactory.h File Reference	4677
7.607src/main/decaf/internal/net/DefaultSocketFactory.h File Reference	4678
7.608src/main/decaf/internal/net/Network.h File Reference	4679
7.609src/main/decaf/internal/net/SocketFileDescriptor.h File Reference	4680
7.610src/main/decaf/internal/net/ssl/DefaultSSLContext.h File Reference	4681
7.611src/main/decaf/internal/net/ssl/DefaultSSLServerSocketFactory.h File Reference .	4682
7.612src/main/decaf/internal/net/ssl/DefaultSSLSocketFactory.h File Reference	4683
7.613src/main/decaf/internal/net/ssl/openssl/OpenSSLContextSpi.h File Reference . .	4684
7.614src/main/decaf/internal/net/ssl/openssl/OpenSSLParameters.h File Reference . .	4685
7.615src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocket.h File Reference .	4686
7.616src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h File Ref- erence	4687
7.617src/main/decaf/internal/net/ssl/openssl/OpenSSLSocket.h File Reference	4688
7.618src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketException.h File Reference	4689
7.619src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h File Reference .	4690
7.620src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketInputStream.h File Ref- erence	4691
7.621src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketOutputStream.h File Reference	4692
7.622src/main/decaf/internal/net/tcp/TcpSocket.h File Reference	4693
7.623src/main/decaf/internal/net/tcp/TcpSocketInputStream.h File Reference	4694
7.624src/main/decaf/internal/net/tcp/TcpSocketOutputStream.h File Reference	4695
7.625src/main/decaf/internal/net/URIEncoderDecoder.h File Reference	4696
7.626src/main/decaf/internal/net/URIHelper.h File Reference	4697
7.627src/main/decaf/internal/net/URIType.h File Reference	4698
7.628src/main/decaf/internal/nio/BufferFactory.h File Reference	4699
7.629src/main/decaf/internal/nio/ByteArrayBuffer.h File Reference	4700
7.630src/main/decaf/internal/nio/CharArrayBuffer.h File Reference	4701
7.631src/main/decaf/internal/nio/DoubleArrayBuffer.h File Reference	4702
7.632src/main/decaf/internal/nio/FloatArrayBuffer.h File Reference	4703
7.633src/main/decaf/internal/nio/IntArrayBuffer.h File Reference	4704
7.634src/main/decaf/internal/nio/LongArrayBuffer.h File Reference	4705
7.635src/main/decaf/internal/nio/ShortArrayBuffer.h File Reference	4706
7.636src/main/decaf/internal/security/unix/SecureRandomImpl.h File Reference	4707
7.637src/main/decaf/internal/security/windows/SecureRandomImpl.h File Reference . .	4708
7.638src/main/decaf/internal/util/ByteArrayAdapter.h File Reference	4709

7.639	src/main/decaf/internal/util/concurrent/ConditionImpl.h File Reference	4710
7.640	src/main/decaf/internal/util/concurrent/MutexImpl.h File Reference	4711
7.641	src/main/decaf/internal/util/concurrent/SynchronizableImpl.h File Reference . . .	4712
7.642	src/main/decaf/internal/util/concurrent/Transferer.h File Reference	4713
7.643	src/main/decaf/internal/util/concurrent/TransferQueue.h File Reference	4714
7.644	src/main/decaf/internal/util/concurrent/TransferStack.h File Reference	4715
7.645	src/main/decaf/internal/util/concurrent/unix/ConditionHandle.h File Reference .	4716
7.646	src/main/decaf/internal/util/concurrent/windows/ConditionHandle.h File Reference	4717
7.647	src/main/decaf/internal/util/concurrent/unix/MutexHandle.h File Reference . . .	4718
7.648	src/main/decaf/internal/util/concurrent/windows/MutexHandle.h File Reference .	4719
7.649	src/main/decaf/internal/util/GenericResource.h File Reference	4720
7.650	src/main/decaf/internal/util/HexStringParser.h File Reference	4721
7.651	src/main/decaf/internal/util/Resource.h File Reference	4722
7.652	src/main/decaf/internal/util/TimerTaskHeap.h File Reference	4723
7.653	src/main/decaf/internal/util/zip/crc32.h File Reference	4724
7.653.1	Variable Documentation	4724
7.653.1.1	crc_table	4724
7.654	src/main/decaf/internal/util/zip/deflate.h File Reference	4725
7.654.1	Define Documentation	4726
7.654.1.1	_tr_tally_dist	4726
7.654.1.2	_tr_tally_lit	4726
7.654.1.3	BL_CODES	4727
7.654.1.4	BUSY_STATE	4727
7.654.1.5	Code	4727
7.654.1.6	COMMENT_STATE	4727
7.654.1.7	d_code	4727
7.654.1.8	D_CODES	4727
7.654.1.9	Dad	4727
7.654.1.10	EXTRA_STATE	4727
7.654.1.11	FINISH_STATE	4727
7.654.1.12	Freq	4727
7.654.1.13	GZIP	4727
7.654.1.14	HCRC_STATE	4727
7.654.1.15	HEAP_SIZE	4727
7.654.1.16	NIT_STATE	4727
7.654.1.17	L_CODES	4727

7.654.1.1	Len	4727
7.654.1.1	LENGTH_CODES	4727
7.654.1.2	LITERALS	4727
7.654.1.2	MAX_BITS	4727
7.654.1.2	MAX_DIST	4727
7.654.1.2	max_insert_length	4727
7.654.1.2	MIN_LOOKAHEAD	4727
7.654.1.2	NAME_STATE	4727
7.654.1.2	put_byte	4727
7.654.1.2	WIN_INIT	4727
7.654.2	Typedef Documentation	4727
7.654.2.1	ct_data	4727
7.654.2.2	deflate_state	4727
7.654.2.3	IPos	4727
7.654.2.4	Pos	4727
7.654.2.5	Posf	4727
7.654.2.6	static_tree_desc	4727
7.654.2.7	tree_desc	4727
7.654.3	Function Documentation	4727
7.654.3.1	OF	4727
7.654.3.2	OF	4727
7.654.3.3	OF	4727
7.654.4	Variable Documentation	4727
7.654.4.1	_dist_code	4727
7.654.4.2	_length_code	4727
7.655	src/main/decaf/internal/util/zip/gzguts.h File Reference	4728
7.655.1	Define Documentation	4729
7.655.1.1	COPY	4729
7.655.1.2	GT_OFF	4729
7.655.1.3	GZ_APPEND	4729
7.655.1.4	GZ_NONE	4729
7.655.1.5	GZ_READ	4729
7.655.1.6	GZ_WRITE	4729
7.655.1.7	GZBUFSIZE	4729
7.655.1.8	GZIP	4729
7.655.1.9	local	4729

7.655.1.1	LOOK	4729
7.655.1.1	ZLIB_INTERNAL	4729
7.655.1.2	zsterror	4729
7.655.2	Typedef Documentation	4729
7.655.2.1	gz_statep	4729
7.655.3	Function Documentation	4729
7.655.3.1	OF	4729
7.655.3.2	OF	4729
7.655.3.3	OF	4729
7.655.3.4	OF	4729
7.655.3.5	OF	4729
7.655.3.6	OF	4729
7.655.3.7	OF	4729
7.656src/main/decaf/internal/util/zip/inffast.h	File Reference	4730
7.656.1	Function Documentation	4730
7.656.1.1	OF	4730
7.657src/main/decaf/internal/util/zip/inffixed.h	File Reference	4731
7.658src/main/decaf/internal/util/zip/inflate.h	File Reference	4732
7.658.1	Define Documentation	4732
7.658.1.1	GUNZIP	4732
7.658.2	Enumeration Type Documentation	4732
7.658.2.1	inflate_mode	4732
7.659src/main/decaf/internal/util/zip/inftrees.h	File Reference	4734
7.659.1	Define Documentation	4734
7.659.1.1	ENOUGH	4734
7.659.1.2	ENOUGH_DISTS	4734
7.659.1.3	ENOUGH_LENS	4734
7.659.2	Enumeration Type Documentation	4734
7.659.2.1	codetype	4734
7.659.3	Function Documentation	4734
7.659.3.1	OF	4734
7.660src/main/decaf/internal/util/zip/trees.h	File Reference	4735
7.660.1	Variable Documentation	4735
7.660.1.1	_dist_code	4735
7.660.1.2	_length_code	4735
7.660.1.3	base_dist	4736

7.660.1.4	base_length	4736
7.660.1.5	static_dtree	4736
7.660.1.6	static_ltree	4736
7.661	src/main/decaf/internal/util/zip/zconf.h File Reference	4737
7.661.1	Define Documentation	4738
7.661.1.1	const	4738
7.661.1.2	MAX_MEM_LEVEL	4738
7.661.1.3	MAX_WBITS	4738
7.661.1.4	OF	4738
7.661.1.5	SEEK_CUR	4738
7.661.1.6	SEEK_END	4738
7.661.1.7	SEEK_SET	4738
7.661.1.8	z_off64_t	4738
7.661.1.9	z_off_t	4738
7.661.1.10	ZEXTERN	4738
7.661.2	Typedef Documentation	4738
7.661.2.1	Byte	4738
7.661.2.2	Bytef	4738
7.661.2.3	charf	4738
7.661.2.4	intf	4738
7.661.2.5	uInt	4738
7.661.2.6	uIntf	4738
7.661.2.7	uLong	4738
7.661.2.8	uLongf	4738
7.661.2.9	voidp	4738
7.661.2.10	voidpc	4738
7.661.2.11	voidpf	4738
7.662	src/main/decaf/internal/util/zip/zlib.h File Reference	4739
7.662.1	Define Documentation	4741
7.662.1.1	deflateInit	4741
7.662.1.2	deflateInit2	4741
7.662.1.3	inflateBackInit	4741
7.662.1.4	inflateInit	4742
7.662.1.5	inflateInit2	4742
7.662.1.6	Z_ASCII	4742
7.662.1.7	Z_BEST_COMPRESSION	4742

7.662.1.8 Z_BEST_SPEED	4742
7.662.1.9 Z_BINARY	4742
7.662.1.10 Z_BLOCK	4742
7.662.1.11 Z_BUF_ERROR	4742
7.662.1.12 Z_DATA_ERROR	4742
7.662.1.13 Z_DEFAULT_COMPRESSION	4742
7.662.1.14 Z_DEFAULT_STRATEGY	4742
7.662.1.15 Z_DEFLATED	4742
7.662.1.16 Z_ERRNO	4742
7.662.1.17 Z_FILTERED	4742
7.662.1.18 Z_FINISH	4742
7.662.1.19 Z_FIXED	4742
7.662.1.20 Z_FULL_FLUSH	4742
7.662.1.21 Z_HUFFMAN_ONLY	4742
7.662.1.22 Z_MEM_ERROR	4742
7.662.1.23 Z_NEED_DICT	4742
7.662.1.24 Z_NO_COMPRESSION	4742
7.662.1.25 Z_NO_FLUSH	4742
7.662.1.26 Z_NULL	4742
7.662.1.27 Z_OK	4742
7.662.1.28 Z_PARTIAL_FLUSH	4742
7.662.1.29 Z_RLE	4742
7.662.1.30 Z_STREAM_END	4742
7.662.1.31 Z_STREAM_ERROR	4742
7.662.1.32 Z_SYNC_FLUSH	4742
7.662.1.33 Z_TEXT	4742
7.662.1.34 Z_TREES	4742
7.662.1.35 Z_UNKNOWN	4742
7.662.1.36 Z_VERSION_ERROR	4742
7.662.1.37 ZLIB_VER_MAJOR	4742
7.662.1.38 ZLIB_VER_MINOR	4742
7.662.1.39 ZLIB_VER_REVISION	4742
7.662.1.40 ZLIB_VER_SUBREVISION	4742
7.662.1.41 ZLIB_VERNUM	4742
7.662.1.42 lib_version	4742
7.662.1.43 ZLIB_VERSION	4742

7.662.2 Typedef Documentation	4742
7.662.2.1 gz_header	4742
7.662.2.2 gz_headerp	4742
7.662.2.3 gzFile	4742
7.662.2.4 OF	4742
7.662.2.5 z_stream	4742
7.662.2.6 z_streamp	4742
7.662.3 Function Documentation	4742
7.662.3.1 OF	4742
7.662.3.2 OF	4742
7.662.3.3 OF	4742
7.662.3.4 OF	4742
7.662.3.5 OF	4742
7.662.3.6 OF	4742
7.662.3.7 OF	4742
7.662.3.8 OF	4742
7.662.3.9 OF	4742
7.662.3.10OF	4742
7.662.3.11OF	4742
7.662.3.12OF	4742
7.662.3.13OF	4742
7.662.3.14OF	4742
7.662.3.15OF	4742
7.662.3.16OF	4742
7.662.3.17OF	4742
7.662.3.18OF	4742
7.662.3.19OF	4742
7.662.3.20OF	4742
7.662.3.21OF	4742
7.662.3.22OF	4742
7.662.3.23OF	4742
7.662.3.24OF	4742
7.662.3.25OF	4742
7.662.3.26OF	4742
7.662.3.27OF	4742
7.662.3.28OF	4742

7.662.3.29OF	4742
7.662.3.30OF	4742
7.662.3.31OF	4742
7.662.3.32OF	4742
7.662.3.33OF	4742
7.662.3.34OF	4742
7.662.3.35OF	4742
7.662.3.36OF	4742
7.662.3.37OF	4742
7.662.3.38OF	4742
7.662.3.39OF	4742
7.662.3.40OF	4742
7.662.3.41OF	4742
7.662.3.42OF	4742
7.663src/main/decaf/internal/util/zip/zutil.h File Reference	4743
7.663.1 Define Documentation	4745
7.663.1.1 Assert	4745
7.663.1.2 DEF_MEM_LEVEL	4745
7.663.1.3 DEF_WBITS	4745
7.663.1.4 DYN_TREES	4745
7.663.1.5 ERR_MSG	4745
7.663.1.6 ERR_RETURN	4745
7.663.1.7 F_OPEN	4745
7.663.1.8 MAX_MATCH	4745
7.663.1.9 MIN_MATCH	4745
7.663.1.10OS_CODE	4745
7.663.1.11PRESET_DICT	4745
7.663.1.12STATIC_TREES	4745
7.663.1.13STORED_BLOCK	4745
7.663.1.14Trace	4745
7.663.1.15Tracec	4745
7.663.1.16Tracecv	4745
7.663.1.17Tracev	4745
7.663.1.18Tracevv	4745
7.663.1.19TRY_FREE	4745
7.663.1.20ZALLOC	4745

7.663.1.2IZFREE	4745
7.663.1.2ZLIB_INTERNAL	4745
7.663.2 Typedef Documentation	4745
7.663.2.1 uch	4745
7.663.2.2 uchf	4745
7.663.2.3 ulg	4745
7.663.2.4 ush	4745
7.663.2.5 ushf	4745
7.663.3 Function Documentation	4745
7.663.3.1 OF	4745
7.663.3.2 OF	4745
7.663.3.3 OF	4745
7.663.3.4 OF	4745
7.663.3.5 OF	4745
7.663.3.6 OF	4745
7.663.4 Variable Documentation	4745
7.663.4.1 z_errmsg	4745
7.664src/main/decaf/io/BlockingByteArrayInputStream.h File Reference	4746
7.665src/main/decaf/io/BufferedInputStream.h File Reference	4747
7.666src/main/decaf/io/BufferedOutputStream.h File Reference	4748
7.667src/main/decaf/io/ByteArrayInputStream.h File Reference	4749
7.668src/main/decaf/io/ByteArrayOutputStream.h File Reference	4750
7.669src/main/decaf/io/DataInput.h File Reference	4751
7.670src/main/decaf/io/DataInputStream.h File Reference	4752
7.671src/main/decaf/io/DataOutput.h File Reference	4753
7.672src/main/decaf/io/DataOutputStream.h File Reference	4754
7.673src/main/decaf/io/EOFException.h File Reference	4755
7.674src/main/decaf/io/FileDescriptor.h File Reference	4756
7.675src/main/decaf/io/FilterInputStream.h File Reference	4757
7.676src/main/decaf/io/FilterOutputStream.h File Reference	4758
7.677src/main/decaf/io/Flushable.h File Reference	4759
7.678src/main/decaf/io/InputStream.h File Reference	4760
7.679src/main/decaf/io/InputStreamReader.h File Reference	4761
7.680src/main/decaf/io/InterruptedIOException.h File Reference	4762
7.681src/main/decaf/io/IOException.h File Reference	4763
7.682src/main/decaf/io/OutputStream.h File Reference	4764

7.683src/main/decaf/io/OutputStreamWriter.h File Reference	4765
7.684src/main/decaf/io/PushbackInputStream.h File Reference	4766
7.685src/main/decaf/io/Reader.h File Reference	4767
7.686src/main/decaf/io/UnsupportedEncodingException.h File Reference	4768
7.687src/main/decaf/io/UTFDataFormatException.h File Reference	4769
7.688src/main/decaf/io/Writer.h File Reference	4770
7.689src/main/decaf/lang/Appendable.h File Reference	4771
7.690src/main/decaf/lang/ArrayPointer.h File Reference	4772
7.691src/main/decaf/lang/Boolean.h File Reference	4774
7.692src/main/decaf/lang/Byte.h File Reference	4775
7.693src/main/decaf/lang/Character.h File Reference	4776
7.694src/main/decaf/lang/CharSequence.h File Reference	4777
7.695src/main/decaf/lang/Comparable.h File Reference	4778
7.696src/main/decaf/lang/Double.h File Reference	4779
7.697src/main/decaf/lang/Exception.h File Reference	4780
7.698src/main/decaf/lang/exceptions/ClassCastException.h File Reference	4781
7.699src/main/decaf/lang/exceptions/IllegalArgumentException.h File Reference	4782
7.700src/main/decaf/lang/exceptions/IllegalMonitorStateException.h File Reference	4783
7.701src/main/decaf/lang/exceptions/IllegalThreadStateException.h File Reference	4784
7.702src/main/decaf/lang/exceptions/IndexOutOfBoundsException.h File Reference	4785
7.703src/main/decaf/lang/exceptions/InterruptedException.h File Reference	4786
7.704src/main/decaf/lang/exceptions/InvalidStateException.h File Reference	4787
7.705src/main/decaf/lang/exceptions/NoSuchElementException.h File Reference	4788
7.706src/main/decaf/lang/exceptions/NullPointerException.h File Reference	4789
7.707src/main/decaf/lang/exceptions/NumberFormatException.h File Reference	4790
7.708src/main/decaf/lang/exceptions/RuntimeException.h File Reference	4791
7.709src/main/decaf/lang/Float.h File Reference	4792
7.710src/main/decaf/lang/Integer.h File Reference	4793
7.711src/main/decaf/lang/Iterable.h File Reference	4794
7.712src/main/decaf/lang/Long.h File Reference	4795
7.713src/main/decaf/lang/Math.h File Reference	4796
7.714src/main/decaf/lang/Number.h File Reference	4797
7.715src/main/decaf/lang/Pointer.h File Reference	4798
7.716src/main/decaf/lang/Readable.h File Reference	4799
7.717src/main/decaf/lang/Runnable.h File Reference	4800
7.718src/main/decaf/lang/Runtime.h File Reference	4801

7.719src/main/decaf/lang/Short.h File Reference	4802
7.720src/main/decaf/lang/String.h File Reference	4803
7.721src/main/decaf/lang/System.h File Reference	4804
7.722src/main/decaf/lang/Thread.h File Reference	4805
7.723src/main/decaf/lang/ThreadGroup.h File Reference	4806
7.724src/main/decaf/lang/Throwable.h File Reference	4807
7.725src/main/decaf/net/BindException.h File Reference	4808
7.726src/main/decaf/net/ConnectException.h File Reference	4809
7.727src/main/decaf/net/HttpRetryException.h File Reference	4810
7.728src/main/decaf/net/Inet4Address.h File Reference	4811
7.729src/main/decaf/net/Inet6Address.h File Reference	4812
7.730src/main/decaf/net/InetAddress.h File Reference	4813
7.731src/main/decaf/net/InetSocketAddress.h File Reference	4814
7.732src/main/decaf/net/MalformedURLException.h File Reference	4815
7.733src/main/decaf/net/NoRouteToHostException.h File Reference	4816
7.734src/main/decaf/net/PortUnreachableException.h File Reference	4817
7.735src/main/decaf/net/ProtocolException.h File Reference	4818
7.736src/main/decaf/net/ServerSocket.h File Reference	4819
7.737src/main/decaf/net/ServerSocketFactory.h File Reference	4820
7.738src/main/decaf/net/Socket.h File Reference	4821
7.739src/main/decaf/net/SocketAddress.h File Reference	4822
7.740src/main/decaf/net/SocketError.h File Reference	4823
7.741src/main/decaf/net/SocketException.h File Reference	4824
7.742src/main/decaf/net/SocketFactory.h File Reference	4825
7.743src/main/decaf/net/SocketImpl.h File Reference	4826
7.744src/main/decaf/net/SocketImplFactory.h File Reference	4827
7.745src/main/decaf/net/SocketOptions.h File Reference	4828
7.746src/main/decaf/net/SocketTimeoutException.h File Reference	4829
7.747src/main/decaf/net/ssl/SSLContext.h File Reference	4830
7.748src/main/decaf/net/ssl/SSLContextSpi.h File Reference	4831
7.749src/main/decaf/net/ssl/SSLParameters.h File Reference	4832
7.750src/main/decaf/net/ssl/SSLServerSocket.h File Reference	4833
7.751src/main/decaf/net/ssl/SSLServerSocketFactory.h File Reference	4834
7.752src/main/decaf/net/ssl/SSLSocket.h File Reference	4835
7.753src/main/decaf/net/ssl/SSLSocketFactory.h File Reference	4836
7.754src/main/decaf/net/UnknownHostException.h File Reference	4837

7.755src/main/decaf/net/UnknownServiceException.h File Reference	4838
7.756src/main/decaf/net/URL.h File Reference	4839
7.757src/main/decaf/net/URISyntaxException.h File Reference	4840
7.758src/main/decaf/net/URL.h File Reference	4841
7.759src/main/decaf/net/URLDecoder.h File Reference	4842
7.760src/main/decaf/net/URLEncoder.h File Reference	4843
7.761src/main/decaf/nio/Buffer.h File Reference	4844
7.762src/main/decaf/nio/BufferOverflowException.h File Reference	4845
7.763src/main/decaf/nio/BufferUnderflowException.h File Reference	4846
7.764src/main/decaf/nio/ByteBuffer.h File Reference	4847
7.765src/main/decaf/nio/CharBuffer.h File Reference	4848
7.766src/main/decaf/nio/DoubleBuffer.h File Reference	4849
7.767src/main/decaf/nio/FloatBuffer.h File Reference	4850
7.768src/main/decaf/nio/IntBuffer.h File Reference	4851
7.769src/main/decaf/nio/InvalidMarkException.h File Reference	4852
7.770src/main/decaf/nio/LongBuffer.h File Reference	4853
7.771src/main/decaf/nio/ReadOnlyBufferException.h File Reference	4854
7.772src/main/decaf/nio/ShortBuffer.h File Reference	4855
7.773src/main/decaf/security/auth/x500/X500Principal.h File Reference	4856
7.774src/main/decaf/security/cert/Certificate.h File Reference	4857
7.775src/main/decaf/security/cert/CertificateEncodingException.h File Reference	4858
7.776src/main/decaf/security/cert/CertificateException.h File Reference	4859
7.777src/main/decaf/security/cert/CertificateExpiredException.h File Reference	4860
7.778src/main/decaf/security/cert/CertificateNotYetValidException.h File Reference	4861
7.779src/main/decaf/security/cert/CertificateParsingException.h File Reference	4862
7.780src/main/decaf/security/cert/X509Certificate.h File Reference	4863
7.781src/main/decaf/security/GeneralSecurityException.h File Reference	4864
7.782src/main/decaf/security/InvalidKeyException.h File Reference	4865
7.783src/main/decaf/security/Key.h File Reference	4866
7.784src/main/decaf/security/KeyException.h File Reference	4867
7.785src/main/decaf/security/KeyManagementException.h File Reference	4868
7.786src/main/decaf/security/NoSuchAlgorithmException.h File Reference	4869
7.787src/main/decaf/security/NoSuchProviderException.h File Reference	4870
7.788src/main/decaf/security/Principal.h File Reference	4871
7.789src/main/decaf/security/PublicKey.h File Reference	4872
7.790src/main/decaf/security/SecureRandom.h File Reference	4873

7.791src/main/decaf/security/SecureRandomSpi.h File Reference	4874
7.792src/main/decaf/security/SignatureException.h File Reference	4875
7.793src/main/decaf/util/AbstractCollection.h File Reference	4876
7.794src/main/decaf/util/AbstractList.h File Reference	4877
7.795src/main/decaf/util/AbstractMap.h File Reference	4878
7.796src/main/decaf/util/AbstractQueue.h File Reference	4879
7.797src/main/decaf/util/AbstractSequentialList.h File Reference	4880
7.798src/main/decaf/util/AbstractSet.h File Reference	4881
7.799src/main/decaf/util/Collection.h File Reference	4882
7.800src/main/decaf/util/Comparator.h File Reference	4883
7.801src/main/decaf/util/comparators/Less.h File Reference	4884
7.802src/main/decaf/util/concurrent/atomic/AtomicBoolean.h File Reference	4885
7.803src/main/decaf/util/concurrent/atomic/AtomicInteger.h File Reference	4886
7.804src/main/decaf/util/concurrent/atomic/AtomicRefCounter.h File Reference	4887
7.805src/main/decaf/util/concurrent/atomic/AtomicReference.h File Reference	4888
7.806src/main/decaf/util/concurrent/BlockingQueue.h File Reference	4889
7.807src/main/decaf/util/concurrent/BrokenBarrierException.h File Reference	4890
7.808src/main/decaf/util/concurrent/Callable.h File Reference	4891
7.809src/main/decaf/util/concurrent/CancellationException.h File Reference	4892
7.810src/main/decaf/util/concurrent/Concurrent.h File Reference	4893
7.810.1 Define Documentation	4893
7.810.1.1 synchronized	4893
7.810.1.2 WAIT_INFINITE	4893
7.811src/main/decaf/util/concurrent/ConcurrentMap.h File Reference	4894
7.812src/main/decaf/util/concurrent/ConcurrentStlMap.h File Reference	4895
7.813src/main/decaf/util/concurrent/CountDownLatch.h File Reference	4896
7.814src/main/decaf/util/concurrent/Delayed.h File Reference	4897
7.815src/main/decaf/util/concurrent/ExecutionException.h File Reference	4898
7.816src/main/decaf/util/concurrent/Executor.h File Reference	4899
7.817src/main/decaf/util/concurrent/ExecutorService.h File Reference	4900
7.818src/main/decaf/util/concurrent/Future.h File Reference	4901
7.819src/main/decaf/util/concurrent/Lock.h File Reference	4902
7.820src/main/decaf/util/concurrent/locks/Lock.h File Reference	4903
7.821src/main/decaf/util/concurrent/locks/Condition.h File Reference	4904
7.822src/main/decaf/util/concurrent/locks/LockSupport.h File Reference	4905
7.823src/main/decaf/util/concurrent/locks/ReadWriteLock.h File Reference	4906

7.824src/main/decaf/util/concurrent/locks/ReentrantLock.h File Reference	4907
7.825src/main/decaf/util/concurrent/Mutex.h File Reference	4908
7.826src/main/decaf/util/concurrent/PooledThread.h File Reference	4909
7.827src/main/decaf/util/concurrent/PooledThreadListener.h File Reference	4910
7.828src/main/decaf/util/concurrent/RejectedExecutionException.h File Reference . . .	4911
7.829src/main/decaf/util/concurrent/RejectedExecutionHandler.h File Reference . . .	4912
7.830src/main/decaf/util/concurrent/Semaphore.h File Reference	4913
7.831src/main/decaf/util/concurrent/Synchronizable.h File Reference	4914
7.832src/main/decaf/util/concurrent/SynchronousQueue.h File Reference	4915
7.833src/main/decaf/util/concurrent/TaskListener.h File Reference	4916
7.834src/main/decaf/util/concurrent/ThreadFactory.h File Reference	4917
7.835src/main/decaf/util/concurrent/ThreadPool.h File Reference	4918
7.836src/main/decaf/util/concurrent/TimeoutException.h File Reference	4919
7.837src/main/decaf/util/concurrent/TimeUnit.h File Reference	4920
7.838src/main/decaf/util/Date.h File Reference	4921
7.839src/main/decaf/util/Iterator.h File Reference	4922
7.840src/main/decaf/util/List.h File Reference	4923
7.841src/main/decaf/util/ListIterator.h File Reference	4924
7.842src/main/decaf/util/logging/ConsoleHandler.h File Reference	4925
7.843src/main/decaf/util/logging/ErrorHandler.h File Reference	4926
7.844src/main/decaf/util/logging/Filter.h File Reference	4927
7.845src/main/decaf/util/logging/Formatter.h File Reference	4928
7.846src/main/decaf/util/logging/Handler.h File Reference	4929
7.847src/main/decaf/util/logging/Level.h File Reference	4930
7.848src/main/decaf/util/logging/Logger.h File Reference	4931
7.849src/main/decaf/util/logging/LoggerCommon.h File Reference	4932
7.850src/main/decaf/util/logging/LoggerDefines.h File Reference	4933
7.850.1 Define Documentation	4933
7.850.1.1 LOGDECAF_DEBUG	4933
7.850.1.2 LOGDECAF_DEBUG_1	4933
7.850.1.3 LOGDECAF_DECLARE	4934
7.850.1.4 LOGDECAF_DECLARE_LOCAL	4934
7.850.1.5 LOGDECAF_ERROR	4934
7.850.1.6 LOGDECAF_FATAL	4934
7.850.1.7 LOGDECAF_INFO	4934
7.850.1.8 LOGDECAF_INITIALIZE	4934

7.850.1.9 LOGDECAF_ WARN	4934
7.851src/main/decaf/util/logging/LoggerHierarchy.h File Reference	4935
7.852src/main/decaf/util/logging/LogManager.h File Reference	4936
7.853src/main/decaf/util/logging/LogRecord.h File Reference	4937
7.854src/main/decaf/util/logging/LogWriter.h File Reference	4938
7.855src/main/decaf/util/logging/MarkBlockLogger.h File Reference	4939
7.856src/main/decaf/util/logging/PropertiesChangeListener.h File Reference	4940
7.857src/main/decaf/util/logging/SimpleFormatter.h File Reference	4941
7.858src/main/decaf/util/logging/SimpleLogger.h File Reference	4942
7.859src/main/decaf/util/logging/StreamHandler.h File Reference	4943
7.860src/main/decaf/util/logging/XMLFormatter.h File Reference	4944
7.861src/main/decaf/util/Map.h File Reference	4945
7.862src/main/decaf/util/PriorityQueue.h File Reference	4946
7.863src/main/decaf/util/Properties.h File Reference	4947
7.864src/main/decaf/util/Random.h File Reference	4948
7.865src/main/decaf/util/Set.h File Reference	4949
7.866src/main/decaf/util/StlList.h File Reference	4950
7.867src/main/decaf/util/StlMap.h File Reference	4951
7.868src/main/decaf/util/StlQueue.h File Reference	4952
7.869src/main/decaf/util/StlSet.h File Reference	4953
7.870src/main/decaf/util/StringTokenizer.h File Reference	4954
7.871src/main/decaf/util/Timer.h File Reference	4955
7.872src/main/decaf/util/TimerTask.h File Reference	4956
7.873src/main/decaf/util/UUID.h File Reference	4957
7.874src/main/decaf/util/zip/Adler32.h File Reference	4958
7.875src/main/decaf/util/zip/CheckedInputStream.h File Reference	4959
7.876src/main/decaf/util/zip/CheckedOutputStream.h File Reference	4960
7.877src/main/decaf/util/zip/Checksum.h File Reference	4961
7.878src/main/decaf/util/zip/CRC32.h File Reference	4962
7.879src/main/decaf/util/zip/DataFormatException.h File Reference	4963
7.880src/main/decaf/util/zip/Deflater.h File Reference	4964
7.881src/main/decaf/util/zip/DeflaterOutputStream.h File Reference	4965
7.882src/main/decaf/util/zip/Inflater.h File Reference	4966
7.883src/main/decaf/util/zip/InflaterInputStream.h File Reference	4967
7.884src/main/decaf/util/zip/ZipException.h File Reference	4968

Chapter 1

Namespace Index

1.1 Namespace List

Here is a list of all namespaces with brief descriptions:

activemq (Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements)	85
activemq::cmsutil	86
activemq::commands	87
activemq::core	89
activemq::core::policies	91
activemq::exceptions	92
activemq::io	93
activemq::library	94
activemq::state	95
activemq::threads	96
activemq::transport	97
activemq::transport::correlator	98
activemq::transport::failover	99
activemq::transport::inactivity	100
activemq::transport::logging	101
activemq::transport::mock	102
activemq::transport::tcp	103
activemq::util	104
activemq::wireformat	105
activemq::wireformat::openwire	106
activemq::wireformat::openwire::marshal	107
activemq::wireformat::openwire::marshal::v1	108
activemq::wireformat::openwire::marshal::v2	113
activemq::wireformat::openwire::marshal::v3	118
activemq::wireformat::openwire::marshal::v4	123
activemq::wireformat::openwire::marshal::v5	128
activemq::wireformat::openwire::marshal::v6	133
activemq::wireformat::openwire::utils	138
activemq::wireformat::stomp	139
cms (Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements)	140

decaf (Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements)	143
decaf::internal	144
decaf::internal::io	145
decaf::internal::net	146
decaf::internal::net::ssl	147
decaf::internal::net::ssl::openssl	148
decaf::internal::net::tcp	149
decaf::internal::nio	150
decaf::internal::security	151
decaf::internal::util	152
decaf::internal::util::concurrent	153
decaf::io	154
decaf::lang	156
decaf::lang::exceptions	159
decaf::net	160
decaf::net::ssl	162
decaf::nio	163
decaf::security	164
decaf::security::auth	165
decaf::security::auth::x500	166
decaf::security::cert	167
decaf::util	168
decaf::util::comparators	170
decaf::util::concurrent	171
decaf::util::concurrent::atomic	173
decaf::util::concurrent::locks	174
decaf::util::logging	175
decaf::util::zip	177
std	178

Chapter 2

Data Structure Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

activemq::core::ActiveMQAckHandler	203
activemq::core::ActiveMQConstants	307
activemq::library::ActiveMQCPP	320
activemq::core::ActiveMQTransactionContext	719
decaf::lang::Appendable	725
decaf::io::Writer	4021
decaf::io::OutputStreamWriter	2915
decaf::nio::CharBuffer	1119
decaf::internal::nio::CharArrayBuffer	1108
decaf::internal::AprPool	728
decaf::lang::ArrayPointer< T, REFCOUNTER >	730
decaf::util::concurrent::atomic::AtomicBoolean	738
decaf::util::concurrent::atomic::AtomicRefCounter	746
decaf::util::concurrent::atomic::AtomicReference< T >	749
binary_function	835
decaf::util::Comparator< ArrayPointer< T, R > >	1217
decaf::lang::ArrayPointerComparator< T, R >	737
decaf::util::Comparator< Pointer< T, R > >	1217
decaf::lang::PointerComparator< T, R >	2954
std::less< decaf::lang::ArrayPointer< T > >	2330
std::less< decaf::lang::Pointer< T > >	2331
activemq::wireformat::openwire::utils::BooleanStream	857
decaf::nio::Buffer	928
decaf::nio::ByteBuffer	1031
decaf::internal::nio::ByteBuffer	991
decaf::nio::CharBuffer	1119
decaf::nio::DoubleBuffer	1809
decaf::internal::nio::DoubleArrayBuffer	1799
decaf::nio::FloatBuffer	1925
decaf::internal::nio::FloatArrayBuffer	1915
decaf::nio::IntBuffer	2066
decaf::internal::nio::IntArrayBuffer	2056

decaf::nio::LongBuffer	2444
decaf::internal::nio::LongArrayBuffer	2434
decaf::nio::ShortBuffer	3459
decaf::internal::nio::ShortArrayBuffer	3449
decaf::internal::nio::BufferFactory	942
decaf::internal::util::ByteArrayAdapter	969
decaf::util::concurrent::Callable< V >	1082
decaf::security::cert::Certificate	1086
decaf::security::cert::X509Certificate	4028
decaf::lang::CharSequence	1135
decaf::lang::String	3665
decaf::nio::CharBuffer	1119
decaf::util::zip::Checksum	1142
decaf::util::zip::Adler32	722
decaf::util::zip::CRC32	1524
cms::Closeable	1148
activemq::commands::ActiveMQTempDestination	576
activemq::commands::ActiveMQTempQueue	604
activemq::commands::ActiveMQTempTopic	633
cms::Connection	1262
activemq::core::ActiveMQConnection	273
cms::MessageConsumer	2589
activemq::cmsutil::CachedConsumer	1071
activemq::core::ActiveMQConsumer	310
cms::MessageProducer	2725
activemq::cmsutil::CachedProducer	1075
activemq::core::ActiveMQProducer	470
cms::QueueBrowser	3153
activemq::core::ActiveMQQueueBrowser	487
cms::Session	3365
activemq::cmsutil::PooledSession	2955
activemq::core::ActiveMQSession	515
decaf::io::Closeable	1149
activemq::transport::Transport	3883
activemq::transport::CompositeTransport	1226
activemq::transport::failover::FailoverTransport	1873
activemq::transport::IOTransport	2145
activemq::transport::mock::MockTransport	2768
activemq::transport::TransportFilter	3891
activemq::transport::correlator::ResponseCorrelator	3291
activemq::transport::inactivity::InactivityMonitor	2004
activemq::transport::logging::LoggingTransport	2403
activemq::transport::tcp::TcpTransport	3752
activemq::transport::tcp::SslTransport	3574
activemq::wireformat::WireFormatNegotiator	4016
activemq::wireformat::openwire::OpenWireFormatNegotiator	2901
decaf::io::InputStream	2043
decaf::internal::io::StandardInputStream	3582
decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream	2882
decaf::internal::net::tcp::TcpSocketInputStream	3747
decaf::io::BlockingByteArrayInputStream	839

decaf::io::ByteArrayInputStream	1020
decaf::io::FilterInputStream	1894
activemq::io::LoggingInputStream	2399
decaf::io::BufferedInputStream	934
decaf::io::DataInputStream	1566
decaf::io::PushbackInputStream	3141
decaf::util::zip::CheckedInputStream	1137
decaf::util::zip::InflaterInputStream	2035
decaf::io::OutputStream	2907
decaf::internal::io::StandardErrorOutputStream	3579
decaf::internal::io::StandardOutputStream	3584
decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream	2885
decaf::internal::net::tcp::TcpSocketOutputStream	3750
decaf::io::ByteArrayOutputStream	1028
decaf::io::FilterOutputStream	1900
activemq::io::LoggingOutputStream	2401
decaf::io::BufferedOutputStream	940
decaf::io::DataOutputStream	1579
decaf::util::zip::CheckedOutputStream	1140
decaf::util::zip::DeflaterOutputStream	1716
decaf::io::Reader	3163
decaf::io::InputStreamReader	2053
decaf::io::Writer	4021
decaf::net::Socket	3503
decaf::net::ssl::SSLSocket	3563
decaf::internal::net::ssl::openssl::OpenSSLSocket	2858
decaf::util::logging::Handler	1978
decaf::util::logging::StreamHandler	3649
decaf::util::logging::ConsoleHandler	1399
activemq::cmsutil::CmsAccessor	1153
activemq::cmsutil::CmsDestinationAccessor	1157
activemq::cmsutil::CmsTemplate	1170
cms::CMSException	1160
cms::CMSSecurityException	1169
cms::IllegalStateException	1997
cms::InvalidClientIdException	2130
cms::InvalidDestinationException	2131
cms::InvalidSelectorException	2138
cms::MessageEOFException	2661
cms::MessageFormatException	2662
cms::MessageNotReadableException	2723
cms::MessageNotWriteableException	2724
cms::UnsupportedOperationException	3919
activemq::util::CMSExceptionSupport	1163
cms::CMSProperties	1165
activemq::util::ActiveMQProperties	478
code	1183
activemq::state::CommandVisitor	1200
activemq::state::CommandVisitorAdapter	1208
activemq::state::ConnectionStateTracker	1392
decaf::lang::Comparable< T >	1214

decaf::lang::Comparable< bool >	1214
decaf::lang::Boolean	850
decaf::lang::Comparable< Boolean >	1214
decaf::lang::Boolean	850
decaf::lang::Comparable< BrokerId >	1214
activemq::commands::BrokerId	869
decaf::lang::Comparable< Byte >	1214
decaf::lang::Byte	960
decaf::lang::Comparable< ByteBuffer >	1214
decaf::nio::ByteBuffer	1031
decaf::lang::Comparable< char >	1214
decaf::lang::Character	1100
decaf::lang::Comparable< Character >	1214
decaf::lang::Character	1100
decaf::lang::Comparable< CharBuffer >	1214
decaf::nio::CharBuffer	1119
decaf::lang::Comparable< ConnectionId >	1214
activemq::commands::ConnectionId	1327
decaf::lang::Comparable< ConsumerId >	1214
activemq::commands::ConsumerId	1430
decaf::lang::Comparable< Date >	1214
decaf::util::Date	1665
decaf::lang::Comparable< Delayed >	1214
decaf::util::concurrent::Delayed	1720
decaf::lang::Comparable< Double >	1214
decaf::lang::Double	1788
decaf::lang::Comparable< double >	1214
decaf::lang::Double	1788
decaf::lang::Comparable< DoubleBuffer >	1214
decaf::nio::DoubleBuffer	1809
decaf::lang::Comparable< float >	1214
decaf::lang::Float	1904
decaf::lang::Comparable< Float >	1214
decaf::lang::Float	1904
decaf::lang::Comparable< FloatBuffer >	1214
decaf::nio::FloatBuffer	1925
decaf::lang::Comparable< int >	1214
decaf::lang::Integer	2077
decaf::lang::Comparable< IntBuffer >	1214
decaf::nio::IntBuffer	2066
decaf::lang::Comparable< Integer >	1214
decaf::lang::Integer	2077
decaf::lang::Comparable< Level >	1214
decaf::util::logging::Level	2332
decaf::lang::Comparable< LocalTransactionId >	1214
activemq::commands::LocalTransactionId	2347

decaf::lang::Comparable< Long >	1214
decaf::lang::Long	2420
decaf::lang::Comparable< long long >	1214
decaf::lang::Long	2420
decaf::lang::Comparable< LongBuffer >	1214
decaf::nio::LongBuffer	2444
decaf::lang::Comparable< MessageId >	1214
activemq::commands::MessageId	2663
decaf::lang::Comparable< ProducerId >	1214
activemq::commands::ProducerId	3067
decaf::lang::Comparable< SessionId >	1214
activemq::commands::SessionId	3379
decaf::lang::Comparable< Short >	1214
decaf::lang::Short	3440
decaf::lang::Comparable< short >	1214
decaf::lang::Short	3440
decaf::lang::Comparable< ShortBuffer >	1214
decaf::nio::ShortBuffer	3459
decaf::lang::Comparable< TimeUnit >	1214
decaf::util::concurrent::TimeUnit	3807
decaf::lang::Comparable< TransactionId >	1214
activemq::commands::TransactionId	3819
activemq::commands::LocalTransactionId	2347
activemq::commands::XATransactionId	4031
decaf::lang::Comparable< unsigned char >	1214
decaf::lang::Byte	960
decaf::lang::Comparable< URI >	1214
decaf::net::URI	3921
decaf::lang::Comparable< UUID >	1214
decaf::util::UUID	3969
decaf::lang::Comparable< XATransactionId >	1214
activemq::commands::XATransactionId	4031
decaf::util::Comparator< T >	1217
activemq::util::CompositeData	1219
decaf::util::concurrent::locks::Condition	1249
decaf::util::concurrent::ConditionHandle	1255
decaf::internal::util::concurrent::ConditionImpl	1257
cms::ConnectionFactory	1324
activemq::core::ActiveMQConnectionFactory	292
cms::ConnectionMetaData	1385
activemq::core::ActiveMQConnectionMetaData	303
activemq::state::ConnectionState	1389
activemq::state::ConsumerState	1492
decaf::util::concurrent::CountDownLatch	1521
ct_data_s	1527
decaf::io::DataInput	1558
decaf::io::DataOutput	1574
activemq::wireformat::openwire::marshal::DataStreamMarshaller	1610

activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller	807
activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller . . .	337
activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller	495
activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller	584
activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller	613
activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller	646
activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller	703
activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller	779
activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller	912
activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller . .	1280
activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller . . .	1312
activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller	1373
activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller . . .	1418
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller	1480
activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller . . .	1509
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller	1744
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller	1956
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller	2289
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller	2581
activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller . . .	2622
activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller	2651
activemq::wireformat::openwire::marshal::v1::MessageMarshaller	2713
activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller	213
activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller	253
activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller	378
activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller .	405
activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller	450
activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller	556
activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller	675
activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller	2760
activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller	3060
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller	3109
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	3210
activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller	3227
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller . . .	3258
activemq::wireformat::openwire::marshal::v1::ResponseMarshaller	3315
activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller	1543
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller . . .	1606
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller	1862
activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller . .	2110
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller	3419
activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller	3481
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller . . .	3855
activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller	880
activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller	1343
activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller	1447
activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller	1778
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	2179
activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller	2208
activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller	2231
activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller . . .	2262
activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller	2688
activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller . . .	2816

activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller	2942
activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller	2324
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller	3092
activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller	3403
activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller	3680
activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller	3827
activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller	2371
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller	4048
activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller	4008
activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller	349
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller	507
activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller	596
activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller	625
activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller	654
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller	715
activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller	800
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller	924
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller	1292
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller	1300
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller	1361
activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller	1406
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller	1468
activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller	1497
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller	1732
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller	1944
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller	2273
activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller	2569
activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller	2606
activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller	2639
activemq::wireformat::openwire::marshal::v2::MessageMarshaller	2703
activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller	221
activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller	269
activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller	390
activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller	417
activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller	462
activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller	568
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller	687
activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller	2744
activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller	3040
activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller	3105
activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller	3198
activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller	3235
activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller	3262
activemq::wireformat::openwire::marshal::v2::ResponseMarshaller	3300
activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller	1531
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	1594
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	1846
activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller	2098
activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller	3427
activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller	3477
activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller	3871
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller	892
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller	1331

activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller	1435
activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller	1766
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	2163
activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller	2192
activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller	2215
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller	2246
activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2668
activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller	2796
activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller	2926
activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller	2312
activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller	3072
activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller	3383
activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	3696
activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller	3831
activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller	2355
activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller	4040
activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller	4000
activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller	333
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller	491
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller	580
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	609
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller	638
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller	695
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller	765
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	904
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	1272
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	1304
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	1365
activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller	1410
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	1472
activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller	1501
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	1736
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	1948
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller	2277
activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller	2573
activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2610
activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller	2643
activemq::wireformat::openwire::marshal::v3::MessageMarshaller	2698
activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller	209
activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller	249
activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller	374
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller	401
activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller	446
activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller	552
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	667
activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller	2752
activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller	3048
activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller	3117
activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller	3206
activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller	3231
activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	3266
activemq::wireformat::openwire::marshal::v3::ResponseMarshaller	3310
activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller	1535

activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller . . .	1598
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller . . .	1850
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller . . .	2102
activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller	3423
activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller	3489
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller	3859
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	872
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	1335
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	1439
activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller	1770
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	2171
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller	2196
activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller	2219
activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller	2250
activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	2680
activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller	2808
activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller	2934
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	2308
activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller	3080
activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller	3399
activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller	3676
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	3835
activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller	2359
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	4052
activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	4012
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	341
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller	499
activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller	588
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	617
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller	642
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller	699
activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller	772
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	908
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	1276
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller	1308
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	1369
activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller	1414
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	1476
activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller	1505
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller	1740
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller	1952
activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller	2281
activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller	2577
activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller	2618
activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller	2647
activemq::wireformat::openwire::marshal::v4::MessageMarshaller	2708
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller	217
activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller	257
activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller	382
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	409
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller	454
activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller	560
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	671

activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller	2756
activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller	3044
activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller	3101
activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller	3218
activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller	3247
activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller . . .	3254
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	3295
activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller	1539
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller . . .	1602
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller	1858
activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller . .	2106
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	3431
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	3493
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	3867
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	876
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller	1339
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	1443
activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller	1774
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller	2175
activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller	2204
activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller	2227
activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller	2258
activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller	2672
activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller . . .	2812
activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller	2938
activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller .	2320
activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller	3076
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	3387
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	3688
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	3839
activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller . .	2367
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller . . .	4044
activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller	4004
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller . . .	345
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	503
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	592
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	621
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	650
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	707
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller	786
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller	916
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller . .	1284
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller . . .	1316
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller	1377
activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller . . .	1422
activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller	1484
activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller . . .	1513
activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller	1752
activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller	1960
activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller	2285
activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller	2585
activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller . . .	2614
activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller	2655

activemq::wireformat::openwire::marshal::v5::MessageMarshaller	2693
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller	225
activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller	261
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	386
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller . . .	413
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	458
activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller	564
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	679
activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller	2748
activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller	3052
activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller	3113
activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller	3214
activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller	3243
activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller . . .	3274
activemq::wireformat::openwire::marshal::v5::ResponseMarshaller	3305
activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller	1547
activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller . . .	1586
activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller	1854
activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller . .	2114
activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller	3415
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller	3485
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller . . .	3851
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	884
activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller	1347
activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller	1451
activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller	1782
activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller	2167
activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller	2188
activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller	2235
activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller . . .	2254
activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller	2676
activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller . .	2804
activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller	2930
activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller .	2316
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	3084
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller	3395
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller	3684
activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller	3823
activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller . .	2363
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller . . .	4056
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller	3992
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller . .	353
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller	511
activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller	600
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	629
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	658
activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller	711
activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller	793
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller	920
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller . .	1288
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller . . .	1320
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller	1381
activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller . . .	1426

activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller	1488
activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller	1517
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller	1748
activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller	1940
activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller	2269
activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller	2565
activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller	2626
activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller	2635
activemq::wireformat::openwire::marshal::v6::MessageMarshaller	2718
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller	229
activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller	265
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller	394
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	421
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller	466
activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller	572
activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller	683
activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller	2764
activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller	3056
activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller	3121
activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller	3202
activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller	3239
activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller	3270
activemq::wireformat::openwire::marshal::v6::ResponseMarshaller	3320
activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller	1551
activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller	1590
activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller	1842
activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller	2094
activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller	3411
activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller	3473
activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller	3863
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller	888
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller	1351
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller	1455
activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller	1762
activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller	2159
activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller	2200
activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller	2223
activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller	2242
activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller	2684
activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller	2800
activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller	2922
activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller	2304
activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller	3088
activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller	3391
activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller	3692
activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller	3843
activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller	2351
activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller	4036
activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller	3996
decaf::internal::net::ssl::DefaultSSLContext	1691
decaf::util::zip::Deflater	1706
cms::DeliveryMode	1721
cms::Destination	1723

cms::Queue	3148
activemq::commands::ActiveMQQueue	483
cms::TemporaryQueue	3759
activemq::commands::ActiveMQTempQueue	604
cms::TemporaryTopic	3761
activemq::commands::ActiveMQTempTopic	633
cms::Topic	3817
activemq::commands::ActiveMQTopic	691
activemq::commands::ActiveMQDestination::DestinationFilter	1726
activemq::cmsutil::DestinationResolver	1756
activemq::cmsutil::DynamicDestinationResolver	1821
activemq::core::DispatchData	1786
activemq::core::Dispatcher	1787
activemq::core::ActiveMQConsumer	310
activemq::core::ActiveMQSession	515
decaf::lang::DYNAMIC_CAST_TOKEN	1820
decaf::util::Map< K, V, COMPARATOR >::Entry	1824
decaf::util::logging::ErrorManager	1828
cms::ExceptionListener	1838
decaf::util::concurrent::Executor	1869
decaf::util::concurrent::ExecutorService	1871
decaf::io::FileDescriptor	1891
decaf::internal::net::SocketFileDescriptor	3528
decaf::util::logging::Filter	1893
decaf::io::Flushable	1936
decaf::io::OutputStream	2907
decaf::io::Writer	4021
decaf::util::logging::Formatter	1964
decaf::util::logging::SimpleFormatter	3500
decaf::util::logging::XMLFormatter	4060
decaf::util::concurrent::Future< V >	1966
activemq::transport::correlator::FutureResponse	1969
gz_header_s	1975
gz_state	1976
decaf::internal::util::HexStringParser	1982
activemq::wireformat::openwire::utils::HexTable	1984
activemq::util::IdGenerator	1989
decaf::net::InetAddress	2016
decaf::net::Inet4Address	2011
decaf::net::Inet6Address	2015
inflate_state	2024
decaf::util::zip::Inflater	2027
internal_state	2118
decaf::lang::Iterable< E >	2152
decaf::util::Collection< E >	1184
decaf::util::AbstractCollection< E >	179
decaf::util::List< E >	2337
decaf::util::AbstractList< E >	192
decaf::util::AbstractSequentialList< E >	198
decaf::util::StlList< E >	3589

decaf::util::Queue< E >	3149
decaf::util::AbstractQueue< E >	194
decaf::util::concurrent::BlockingQueue< E >	843
decaf::util::concurrent::SynchronousQueue< E >	3716
decaf::util::PriorityQueue< E >	3028
decaf::util::Set< E >	3439
decaf::util::AbstractSet< E >	199
decaf::util::StlSet< E >	3623
decaf::lang::Iterable< PrimitiveValueNode >	2152
decaf::util::Collection< PrimitiveValueNode >	1184
decaf::util::AbstractCollection< PrimitiveValueNode >	179
decaf::util::List< PrimitiveValueNode >	2337
decaf::util::StlList< PrimitiveValueNode >	3589
activemq::util::PrimitiveList	2980
decaf::util::Iterator< T >	2154
decaf::util::Iterator< E >	2154
decaf::util::ListIterator< E >	2344
decaf::security::Key	2293
decaf::security::PublicKey	3140
decaf::util::comparators::Less< E >	2328
decaf::util::concurrent::Lock	2375
decaf::util::concurrent::locks::Lock	2377
decaf::util::concurrent::locks::ReentrantLock	3182
decaf::util::concurrent::locks::LockSupport	2383
decaf::util::logging::Logger	2386
decaf::util::logging::LoggerHierarchy	2398
decaf::util::logging::LogManager	2406
decaf::util::logging::LogRecord	2413
decaf::util::logging::LogWriter	2418
activemq::util::LongSequenceGenerator	2455
decaf::util::logging::MarkBlockLogger	2483
activemq::wireformat::MarshalAware	2484
activemq::commands::DataStructure	1660
activemq::commands::BaseDataStructure	830
activemq::commands::ActiveMQDestination	322
activemq::commands::ActiveMQQueue	483
activemq::commands::ActiveMQTempDestination	576
activemq::commands::ActiveMQTopic	691
activemq::commands::BooleanExpression	855
activemq::commands::BrokerId	869
activemq::commands::Command	1194
activemq::commands::BaseCommand	758
activemq::commands::BrokerError	863
activemq::commands::BrokerInfo	896
activemq::commands::ConnectionControl	1267
activemq::commands::ConnectionError	1296
activemq::commands::ConnectionInfo	1355
activemq::commands::ConsumerControl	1401
activemq::commands::ConsumerInfo	1459
activemq::commands::ControlCommand	1493
activemq::commands::DestinationInfo	1727

activemq::commands::FlushCommand	1937
activemq::commands::KeepAliveInfo	2266
activemq::commands::Message	2516
activemq::commands::ActiveMQMessageTemplate< T >	425
activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >	425
activemq::commands::ActiveMQBytesMessage	233
activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >	425
activemq::commands::ActiveMQMapMessage	360
activemq::commands::ActiveMQMessageTemplate< cms::Message >	425
activemq::commands::ActiveMQBlobMessage	204
activemq::commands::ActiveMQMessage	398
activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >	425
activemq::commands::ActiveMQObjectMessage	443
activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >	425
activemq::commands::ActiveMQStreamMessage	537
activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >	425
activemq::commands::ActiveMQTextMessage	662
activemq::commands::MessageAck	2559
activemq::commands::MessageDispatch	2594
activemq::commands::MessageDispatchNotification	2630
activemq::commands::MessagePull	2739
activemq::commands::ProducerAck	3036
activemq::commands::ProducerInfo	3096
activemq::commands::RemoveInfo	3194
activemq::commands::RemoveSubscriptionInfo	3222
activemq::commands::ReplayCommand	3251
activemq::commands::Response	3285
activemq::commands::DataArrayResponse	1528
activemq::commands::DataResponse	1583
activemq::commands::ExceptionResponse	1839
activemq::commands::IntegerResponse	2091
activemq::state::Tracked	3818
activemq::commands::SessionInfo	3407
activemq::commands::ShutdownInfo	3470
activemq::commands::TransactionInfo	3847
activemq::commands::WireFormatInfo	3982
activemq::commands::ConnectionId	1327
activemq::commands::ConsumerId	1430
activemq::commands::DiscoveryEvent	1758
activemq::commands::JournalQueueAck	2156
activemq::commands::JournalTopicAck	2183
activemq::commands::JournalTrace	2212
activemq::commands::JournalTransaction	2239
activemq::commands::MessageId	2663
activemq::commands::NetworkBridgeFilter	2793
activemq::commands::PartialCommand	2918
activemq::commands::LastPartialCommand	2301
activemq::commands::ProducerId	3067
activemq::commands::SessionId	3379
activemq::commands::SubscriptionInfo	3671
activemq::commands::TransactionId	3819

activemq::wireformat::openwire::marshal::v6::MarshallerFactory	2487
activemq::wireformat::openwire::marshal::v3::MarshallerFactory	2488
activemq::wireformat::openwire::marshal::v4::MarshallerFactory	2489
activemq::wireformat::openwire::marshal::v5::MarshallerFactory	2490
activemq::wireformat::openwire::marshal::v1::MarshallerFactory	2491
activemq::wireformat::openwire::marshal::v2::MarshallerFactory	2492
activemq::util::MarshallingSupport	2493
decaf::lang::Math	2497
cms::Message	2534
activemq::commands::ActiveMQMessageTemplate< cms::Message >	425
cms::BytesMessage	1056
activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >	425
cms::MapMessage	2472
activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >	425
cms::ObjectMessage	2841
activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >	425
cms::StreamMessage	3652
activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >	425
cms::TextMessage	3763
activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >	425
activemq::cmsutil::MessageCreator	2593
cms::MessageEnumeration	2659
activemq::core::ActiveMQQueueBrowser	487
cms::MessageListener	2692
activemq::wireformat::openwire::utils::MessagePropertyInterceptor	2732
decaf::util::concurrent::MutexHandle	2787
decaf::internal::util::concurrent::MutexImpl	2788
decaf::internal::net::Network	2790
decaf::lang::Number	2835
decaf::lang::Byte	960
decaf::lang::Character	1100
decaf::lang::Double	1788
decaf::lang::Float	1904
decaf::lang::Integer	2077
decaf::lang::Long	2420
decaf::lang::Short	3440
decaf::util::concurrent::atomic::AtomicInteger	741
decaf::internal::net::ssl::openssl::OpenSSLParameters	2845
decaf::lang::Pointer< T, REFCOUNTER >	2946
decaf::util::concurrent::PooledThreadListener	2971
decaf::util::concurrent::ThreadPool	3777
activemq::core::PrefetchPolicy	2976
activemq::core::policies::DefaultPrefetchPolicy	1673
activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller	3001
activemq::util::PrimitiveValueNode::PrimitiveValue	3008
activemq::util::PrimitiveValueConverter	3010
activemq::util::PrimitiveValueNode	3012
decaf::security::Principal	3026
decaf::security::auth::x500::X500Principal	4027
activemq::cmsutil::ProducerCallback	3064
activemq::cmsutil::CmsTemplate::SendExecutor	3350

activemq::state::ProducerState	3125
decaf::util::Properties	3126
decaf::util::logging::PropertiesChangeListener	3135
decaf::util::Random	3155
decaf::security::SecureRandom	3331
decaf::lang::Readable	3160
decaf::io::Reader	3163
decaf::util::concurrent::locks::ReadWriteLock	3172
activemq::core::RedeliveryPolicy	3177
activemq::core::policies::DefaultRedeliveryPolicy	1677
decaf::util::concurrent::RejectedExecutionHandler	3192
decaf::internal::util::Resource	3280
decaf::internal::util::GenericResource< T >	1974
decaf::internal::util::ResourceLifecycleManager	3281
activemq::cmsutil::ResourceLifecycleManager	3282
activemq::transport::mock::ResponseBuilder	3289
activemq::wireformat::openwire::OpenWireResponseBuilder	2905
decaf::lang::Runnable	3325
activemq::threads::CompositeTaskRunner	1223
activemq::threads::DedicatedTaskRunner	1671
activemq::transport::IOTransport	2145
decaf::lang::Thread	3765
activemq::transport::mock::InternalCommandListener	2122
decaf::util::concurrent::PooledThread	2968
decaf::util::TimerTask	3801
activemq::transport::inactivity::ReadChecker	3162
activemq::transport::inactivity::WriteChecker	4020
decaf::lang::Runtime	3326
decaf::internal::DecafRuntime	1670
decaf::security::SecureRandomSpi	3339
decaf::internal::security::SecureRandomImpl	3336
decaf::internal::security::SecureRandomImpl	3336
decaf::util::concurrent::Semaphore	3341
decaf::net::ServerSocket	3352
decaf::net::ssl::SSLServerSocket	3554
decaf::internal::net::ssl::openssl::OpenSSLServerSocket	2847
decaf::net::ServerSocketFactory	3361
decaf::internal::net::DefaultServerSocketFactory	1682
decaf::net::ssl::SSLServerSocketFactory	3560
decaf::internal::net::ssl::DefaultSSLServerSocketFactory	1692
decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory	2853
activemq::cmsutil::SessionCallback	3378
activemq::cmsutil::CmsTemplate::ProducerExecutor	3065
activemq::cmsutil::CmsTemplate::ResolveProducerExecutor	3278
activemq::cmsutil::CmsTemplate::ReceiveExecutor	3174
activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor	3279
activemq::cmsutil::SessionPool	3435
activemq::state::SessionState	3437
decaf::util::logging::SimpleLogger	3501
decaf::net::SocketAddress	3519

decaf::net::InetSocketAddress	2023
decaf::net::SocketError	3520
decaf::net::SocketFactory	3524
decaf::internal::net::DefaultSocketFactory	1686
decaf::net::ssl::SSLSocketFactory	3571
decaf::internal::net::ssl::DefaultSSLSocketFactory	1697
decaf::internal::net::ssl::openssl::OpenSSLSocketFactory	2875
decaf::net::SocketImplFactory	3537
decaf::net::SocketOptions	3538
decaf::net::SocketImpl	3529
decaf::internal::net::tcp::TcpSocket	3738
decaf::net::ssl::SSLContext	3545
decaf::net::ssl::SSLContextSpi	3548
decaf::internal::net::ssl::openssl::OpenSSLContextSpi	2842
decaf::net::ssl::SSLParameters	3551
activemq::commands::BrokerError::StackTraceElement	3578
cms::Startable	3586
cms::Connection	1262
decaf::lang::STATIC_CAST_TOKEN	3587
activemq::core::ActiveMQConstants::StaticInitializer	3588
activemq::wireformat::stomp::StompCommandConstants	3629
activemq::wireformat::stomp::StompFrame	3633
activemq::wireformat::stomp::StompHelper	3638
cms::Stoppable	3648
cms::Connection	1262
decaf::util::StringTokenizer	3668
decaf::util::concurrent::Synchronizable	3700
activemq::core::MessageDispatchChannel	2599
decaf::util::Collection< PrimitiveValueNode >	1184
decaf::internal::util::concurrent::SynchronizableImpl	3711
decaf::io::InputStream	2043
decaf::io::OutputStream	2907
decaf::util::Collection< E >	1184
decaf::util::concurrent::Mutex	2782
decaf::util::Map< K, V, COMPARATOR >	2459
decaf::util::AbstractMap< K, V, COMPARATOR >	193
decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >	1228
decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >	1233
decaf::util::StlMap< K, V, COMPARATOR >	3602
decaf::util::StlQueue< T >	3615
decaf::util::Map< std::string, PrimitiveValueNode, std::less< std::string > >	2459
decaf::util::StlMap< std::string, PrimitiveValueNode >	3602
activemq::util::PrimitiveMap	2991
activemq::core::Synchronization	3715
decaf::lang::System	3726
activemq::threads::Task	3734
activemq::core::ActiveMQSessionExecutor	533
activemq::threads::CompositeTask	1221
activemq::transport::failover::BackupTransportPool	755
activemq::transport::failover::CloseTransportsTask	1151
activemq::transport::failover::FailoverTransport	1873

activemq::threads::CompositeTaskRunner	1223
decaf::util::concurrent::TaskListener	3735
activemq::threads::TaskRunner	3736
activemq::threads::CompositeTaskRunner	1223
activemq::threads::DedicatedTaskRunner	1671
decaf::util::concurrent::ThreadFactory	3774
decaf::lang::ThreadGroup	3776
decaf::lang::Throwable	3783
decaf::lang::Exception	1831
activemq::exceptions::ActiveMQException	357
activemq::exceptions::BrokerException	867
decaf::io::IOException	2142
decaf::io::EOFException	1825
decaf::io::InterruptedIOException	2127
decaf::net::SocketTimeoutException	3542
decaf::io::UnsupportedEncodingException	3913
decaf::io::UTFDataFormatException	3966
decaf::net::HttpRetryException	1986
decaf::net::MalformedURLException	2456
decaf::net::ProtocolException	3137
decaf::net::SocketException	3521
decaf::internal::net::ssl::openssl::OpenSSLSocketException	2871
decaf::net::BindException	836
decaf::net::ConnectException	1259
decaf::net::NoRouteToHostException	2820
decaf::net::PortUnreachableException	2973
decaf::net::UnknownHostException	3907
decaf::net::UnknownServiceException	3910
decaf::util::zip::ZipException	4064
decaf::lang::exceptions::ClassCastException	1145
decaf::lang::exceptions::IllegalArgumentException	1991
decaf::lang::exceptions::IllegalMonitorStateException	1994
decaf::lang::exceptions::IllegalStateException	1998
decaf::nio::InvalidMarkException	2135
decaf::lang::exceptions::IllegalThreadStateException	2001
decaf::lang::exceptions::IndexOutOfBoundsException	2008
decaf::lang::exceptions::InterruptedException	2124
decaf::lang::exceptions::InvalidStateException	2139
decaf::lang::exceptions::NoSuchElementException	2826
decaf::lang::exceptions::NullPointerException	2832
decaf::lang::exceptions::NumberFormatException	2838
decaf::lang::exceptions::RuntimeException	3328
decaf::lang::exceptions::UnsupportedOperationException	3916
decaf::nio::ReadOnlyBufferException	3169
decaf::net::URISyntaxException	3948
decaf::nio::BufferOverflowException	954
decaf::nio::BufferUnderflowException	957
decaf::security::GeneralSecurityException	1971
decaf::security::cert::CertificateException	1092
decaf::security::cert::CertificateEncodingException	1090
decaf::security::cert::CertificateExpiredException	1094
decaf::security::cert::CertificateNotYetValidException	1096

decaf::security::cert::CertificateParsingException	1098
decaf::security::KeyException	2295
decaf::security::InvalidKeyException	2132
decaf::security::KeyManagementException	2298
decaf::security::NoSuchAlgorithmException	2823
decaf::security::NoSuchProviderException	2829
decaf::security::SignatureException	3497
decaf::util::concurrent::BrokenBarrierException	860
decaf::util::concurrent::CancellationException	1083
decaf::util::concurrent::ExecutionException	1866
decaf::util::concurrent::RejectedExecutionException	3189
decaf::util::concurrent::TimeoutException	3787
decaf::util::zip::DataFormatException	1555
decaf::util::Timer	3790
decaf::internal::util::TimerTaskHeap	3804
activemq::state::TransactionState	3875
decaf::internal::util::concurrent::Transferer< E >	3877
decaf::internal::util::concurrent::TransferQueue< E >	3878
decaf::internal::util::concurrent::TransferStack< E >	3881
activemq::transport::TransportFactory	3889
activemq::transport::AbstractTransportFactory	201
activemq::transport::failover::FailoverTransportFactory	1885
activemq::transport::mock::MockTransportFactory	2779
activemq::transport::tcp::TcpTransportFactory	3756
activemq::transport::tcp::SslTransportFactory	3576
activemq::transport::TransportListener	3900
activemq::core::ActiveMQConnection	273
activemq::transport::DefaultTransportListener	1704
activemq::transport::failover::BackupTransport	752
activemq::transport::mock::InternalCommandListener	2122
activemq::transport::failover::FailoverTransportListener	1888
activemq::transport::TransportFilter	3891
activemq::transport::TransportRegistry	3902
tree_desc_s	3905
decaf::lang::Thread::UncaughtExceptionHandler	3906
decaf::internal::net::URIEncoderDecoder	3932
decaf::internal::net::URIHelper	3935
activemq::transport::failover::URIPool	3942
activemq::util::URISupport	3945
decaf::internal::net::URIType	3952
decaf::net::URL	3960
decaf::net::URLDecoder	3962
decaf::net::URLEncoder	3963
activemq::util::Usage	3964
activemq::util::MemoryUsage	2512
activemq::wireformat::WireFormat	3976
activemq::wireformat::openwire::OpenWireFormat	2887
activemq::wireformat::stomp::StompWireFormat	3643
activemq::wireformat::WireFormatFactory	3980
activemq::wireformat::openwire::OpenWireFormatFactory	2899
activemq::wireformat::stomp::StompWireFormatFactory	3647

activemq::wireformat::WireFormatRegistry	4017
z_stream_s	4062

Chapter 3

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

decaf::util::AbstractCollection < E > (This class provides a skeletal implementation of the Collection (p. 1184) interface, to minimize the effort required to implement this interface)	179
decaf::util::AbstractList < E > (This class provides a skeletal implementation of the List (p. 2337) interface to minimize the effort required to implement this interface backed by a "random access" data store (such as an array))	192
decaf::util::AbstractMap < K , V , COMPARATOR > (This class provides a skeletal implementation of the Map (p. 2459) interface, to minimize the effort required to implement this interface)	193
decaf::util::AbstractQueue < E > (This class provides skeletal implementations of some Queue (p. 3149) operations)	194
decaf::util::AbstractSequentialList < E > (This class provides a skeletal implementation of the List (p. 2337) interface to minimize the effort required to implement this interface backed by a "sequential access" data store (such as a linked list))	198
decaf::util::AbstractSet < E > (This class provides a skeletal implementation of the Set (p. 3439) interface to minimize the effort required to implement this interface)	199
activemq::transport::AbstractTransportFactory (Abstract implementation of the TransportFactory (p. 3889) interface, providing the base functionality that's common to most of the TransportFactory (p. 3889) instances)	201
activemq::core::ActiveMQAckHandler (Interface class that is used to give CMS Messages an interface to Ack themselves with)	203
activemq::commands::ActiveMQBlobMessage	204
activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p. 209))	209
activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p. 213))	213
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p. 217))	217

activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p.221))	221
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p.225))	225
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBlobMessageMarshaller (p.229))	229
activemq::commands::ActiveMQBytesMessage	233
activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.249))	249
activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.253))	253
activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.257))	257
activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.261))	261
activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.265))	265
activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQBytesMessageMarshaller (p.269))	269
activemq::core::ActiveMQConnection (Concrete connection used for all connectors to the ActiveMQ broker)	273
activemq::core::ActiveMQConnectionFactory	292
activemq::core::ActiveMQConnectionMetaData (This class houses all the various settings and information that is used by an instance of an ActiveMQConnection (p.273) class)	303
activemq::core::ActiveMQConstants (Class holding constant values for various ActiveMQ specific things Each constant is defined as an enumeration and has functions that convert back and forth between string and enum values)	307
activemq::core::ActiveMQConsumer	310
activemq::library::ActiveMQCPP	320
activemq::commands::ActiveMQDestination	322
activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.333))	333
activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.337))	337
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.341))	341
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.345))	345

activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.349))	349
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQDestinationMarshaller (p.353))	353
activemq::exceptions::ActiveMQException	357
activemq::commands::ActiveMQMapMessage	360
activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.374))	374
activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.378))	378
activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.382))	382
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.386))	386
activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.390))	390
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMapMessageMarshaller (p.394))	394
activemq::commands::ActiveMQMessage	398
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.401))	401
activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.405))	405
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.409))	409
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.413))	413
activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.417))	417
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQMessageMarshaller (p.421))	421
activemq::commands::ActiveMQMessageTemplate< T >	425
activemq::commands::ActiveMQObjectMessage	443
activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p.446))	446
activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller (Marshaling code (p.1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p.450))	450

activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p. 454))	454
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p. 458))	458
activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p. 462))	462
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQObjectMessageMarshaller (p. 466))	466
activemq::core::ActiveMQProducer	470
activemq::util::ActiveMQProperties (Implementation of the CMSProperties interface that delegates to a decaf::util::Properties (p. 3126) object)	478
activemq::commands::ActiveMQQueue	483
activemq::core::ActiveMQQueueBrowser	487
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 491))	491
activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 495))	495
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 499))	499
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 503))	503
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 507))	507
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQQueueMarshaller (p. 511))	511
activemq::core::ActiveMQSession	515
activemq::core::ActiveMQSessionExecutor (Delegate dispatcher for a single session)	533
activemq::commands::ActiveMQStreamMessage	537
activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 552))	552
activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 556))	556
activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 560))	560
activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 564))	564
activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 568))	568

activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQStreamMessageMarshaller (p. 572))	572
activemq::commands::ActiveMQTempDestination	576
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 580))	580
activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 584))	584
activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 588))	588
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 592))	592
activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 596))	596
activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempDestinationMarshaller (p. 600))	600
activemq::commands::ActiveMQTempQueue	604
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 609))	609
activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 613))	613
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 617))	617
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 621))	621
activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 625))	625
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempQueueMarshaller (p. 629))	629
activemq::commands::ActiveMQTempTopic	633
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 638))	638
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 642))	642
activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 646))	646
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 650))	650

activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 654))	654
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 658))	658
activemq::commands::ActiveMQTextMessage	662
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 667))	667
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 671))	671
activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 675))	675
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 679))	679
activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 683))	683
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 687))	687
activemq::commands::ActiveMQTopic	691
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 695))	695
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 699))	699
activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 703))	703
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 707))	707
activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 711))	711
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller (Marshaling code (p. 1183) for Open Wire Format for ActiveMQTopicMarshaller (p. 715))	715
activemq::core::ActiveMQTransactionContext (Transaction Management class, hold messages that are to be redelivered upon a request to roll-back)	719
decaf::util::zip::Adler32 (Clas that can be used to compute an Adler-32 Checksum (p. 1142) for a data stream)	722
decaf::lang::Appendable (An object to which char sequences and values can be appended)	725
decaf::internal::AprPool (Wraps an APR pool object so that classes in decaf (p. 143) can create a static member for use in static methods where apr function calls that need a pool are made)	728

decaf::lang::ArrayPointer< T, REFCOUNTER > (Decaf's implementation of a Smart Pointer (p. 2946) that is a template on a Type and is Thread (p. 3765) Safe if the default Reference Counter is used)	730
decaf::lang::ArrayPointerComparator< T, R > (This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the value of the actual pointer to the array being contained in this ArrayPointer (p. 730))	737
decaf::util::concurrent::atomic::AtomicBoolean (A boolean value that may be updated atomically)	738
decaf::util::concurrent::atomic::AtomicInteger (An int value that may be updated atomically)	741
decaf::util::concurrent::atomic::AtomicRefCounter	746
decaf::util::concurrent::atomic::AtomicReference< T > (An Pointer reference that may be updated atomically)	749
activemq::transport::failover::BackupTransport	752
activemq::transport::failover::BackupTransportPool	755
activemq::commands::BaseCommand	758
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 765))	765
activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 772))	772
activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 779))	779
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 786))	786
activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 793))	793
activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for BaseCommandMarshaller (p. 800))	800
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller (Base class for all Marshallers that marshal (p. 107) DataStructures to and from the wire using the OpenWire protocol)	807
activemq::commands::BaseDataStructure	830
binary_function	835
decaf::net::BindException	836
decaf::io::BlockingByteArrayInputStream (This is a blocking version of a byte buffer stream)	839
decaf::util::concurrent::BlockingQueue< E > (A decaf::util::Queue (p. 3149) that additionally supports operations that wait for the queue to become non-empty when retrieving an element, and wait for space to become available in the queue when storing an element)	843
decaf::lang::Boolean	850
activemq::commands::BooleanExpression	855
activemq::wireformat::openwire::utils::BooleanStream (Manages the writing and reading of boolean data streams to and from a data source such as a DataInputStream or DataOutputStream)	857
decaf::util::concurrent::BrokenBarrierException	860

activemq::commands::BrokerError (This class represents an Exception sent from the Broker)	863
activemq::exceptions::BrokerException	867
activemq::commands::BrokerId	869
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 872)) . . .	872
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 876)) . . .	876
activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 880)) . . .	880
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 884)) . . .	884
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 888)) . . .	888
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerIdMarshaller (p. 892)) . . .	892
activemq::commands::BrokerInfo	896
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 904))	904
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 908))	908
activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 912))	912
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 916))	916
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 920))	920
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for BrokerInfoMarshaller (p. 924))	924
decaf::nio::Buffer (A container for data of a specific primitive type)	928
decaf::io::BufferedInputStream (A wrapper around another input stream that performs a buffered read, where it reads more data than it needs in order to reduce the number of io (p. 154) operations on the input stream)	934
decaf::io::BufferedOutputStream (Wrapper around another output stream that buffers output before writing to the target output stream)	940
decaf::internal::nio::BufferFactory (Factory class used by static methods in the decaf::nio (p. 163) package to create the various default version of the NIO interfaces)	942
decaf::nio::BufferOverflowException	954
decaf::nio::BufferUnderflowException	957
decaf::lang::Byte	960
decaf::internal::util::ByteArrayAdapter (This class adapts primitive type arrays to a base byte array so that the classes can inter-operate on the same base byte array without copying data)	969
decaf::internal::nio::ByteArrayBuffer (This class defines six categories of operations upon byte buffers:)	991
decaf::io::ByteArrayInputStream (A ByteArrayInputStream (p. 1020) contains an internal (p. 144) buffer that contains bytes that may be read from the stream) 1020	

decaf::io::ByteArrayOutputStream	1028
decaf::nio::ByteBuffer (This class defines six categories of operations upon byte buffers:)	1031
cms::BytesMessage (A BytesMessage (p.1056) object is used to send a message containing a stream of unsigned bytes)	1056
activemq::cmsutil::CachedConsumer (A cached message consumer contained within a pooled session)	1071
activemq::cmsutil::CachedProducer (A cached message producer contained within a pooled session)	1075
decaf::util::concurrent::Callable< V > (A task that returns a result and may throw an exception)	1082
decaf::util::concurrent::CancellationException	1083
decaf::security::cert::Certificate (Base interface for all identity certificates)	1086
decaf::security::cert::CertificateEncodingException	1090
decaf::security::cert::CertificateException	1092
decaf::security::cert::CertificateExpiredException	1094
decaf::security::cert::CertificateNotYetValidException	1096
decaf::security::cert::CertificateParsingException	1098
decaf::lang::Character	1100
decaf::internal::nio::CharArrayBuffer	1108
decaf::nio::CharBuffer (This class defines four categories of operations upon character buffers:)	1119
decaf::lang::CharSequence (A CharSequence (p. 1135) is a readable sequence of char values)	1135
decaf::util::zip::CheckedInputStream (An implementation of a FilterInputStream that will maintain a Checksum (p.1142) of the bytes read, the Checksum (p.1142) can then be used to verify the integrity of the input stream)	1137
decaf::util::zip::CheckedOutputStream (An implementation of a FilterOutputStream that will maintain a Checksum (p.1142) of the bytes written, the Checksum (p.1142) can then be used to verify the integrity of the output stream)	1140
decaf::util::zip::Checksum (An interface used to represent Checksum (p.1142) values in the Zip package)	1142
decaf::lang::exceptions::ClassCastException	1145
cms::Closeable (Interface for a class that implements the close method)	1148
decaf::io::Closeable (Interface for a class that implements the close method)	1149
activemq::transport::failover::CloseTransportsTask	1151
activemq::cmsutil::CmsAccessor (Base class for activemq::cmsutil::CmsTemplate (p.1170) and other CMS-accessing gateway helpers, defining common properties such as the CMS cms.ConnectionFactory (p.1324) to operate on)	1153
activemq::cmsutil::CmsDestinationAccessor (Extends the CmsAccessor (p.1153) to add support for resolving destination names)	1157
cms::CMSException (CMS API Exception that is the base for all exceptions thrown from CMS classes)	1160
activemq::util::CMSExceptionSupport	1163
cms::CMSProperties (Interface for a Java-like properties object)	1165
cms::CMSSecurityException (This exception must be thrown when a provider rejects a user name/password submitted by a client)	1169
activemq::cmsutil::CmsTemplate (CmsTemplate (p.1170) simplifies performing synchronous CMS operations)	1170
code	1183
decaf::util::Collection< E > (The root interface in the collection hierarchy)	1184
activemq::commands::Command	1194

activemq::state::CommandVisitor (Interface for an Object that can visit the various Command Objects that are sent from and to this client)	1200
activemq::state::CommandVisitorAdapter (Default Implementation of a CommandVisitor (p. 1200) that returns NULL for all calls)	1208
decaf::lang::Comparable< T > (This interface imposes a total ordering on the objects of each class that implements it)	1214
decaf::util::Comparator< T > (A comparison function, which imposes a total ordering on some collection of objects)	1217
activemq::util::CompositeData (Represents a Composite URI)	1219
activemq::threads::CompositeTask (Represents a single task that can be part of a set of Tasks that are contained in a CompositeTaskRunner (p. 1223))	1221
activemq::threads::CompositeTaskRunner (A Task (p. 3734) Runner that can contain one or more CompositeTasks that are each checked for pending work and run if any is present in the order that the tasks were added)	1223
activemq::transport::CompositeTransport (A Composite Transport (p. 3883) is a Transport (p. 3883) implementation that is composed of several Transports) .	1226
decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR > (Interface for a Map (p. 2459) type that provides additional atomic (p. 173) putIfAbsent , remove , and replace methods alongside the already available Map (p. 2459) interface)	1228
decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map) . . .	1233
decaf::util::concurrent::locks::Condition (Condition (p. 1249) factors out the Mutex (p. 2782) monitor methods (wait , notify and notifyAll) into distinct objects to give the effect of having multiple wait-sets per object, by combining them with the use of arbitrary Lock (p. 2377) implementations)	1249
decaf::util::concurrent::ConditionHandle	1255
decaf::internal::util::concurrent::ConditionImpl	1257
decaf::net::ConnectException	1259
cms::Connection (The client's connection to its provider)	1262
activemq::commands::ConnectionControl	1267
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1272))	1272
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1276))	1276
activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1280))	1280
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1284))	1284
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1288))	1288
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1292))	1292
activemq::commands::ConnectionError	1296
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1300))	1300

activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1304))	1304
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1308))	1308
activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1312))	1312
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1316))	1316
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionErrorMarshaller (p. 1320))	1320
cms::ConnectionFactory (Defines the interface for a factory that creates connection objects, the Connection (p. 1262) objects returned implement the CMS Connection (p. 1262) interface and hide the CMS Provider specific implementation details behind that interface)	1324
activemq::commands::ConnectionId	1327
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1331))	1331
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1335))	1335
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1339))	1339
activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1343))	1343
activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1347))	1347
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionIdMarshaller (p. 1351))	1351
activemq::commands::ConnectionInfo	1355
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1361))	1361
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1365))	1365
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1369))	1369
activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1373))	1373
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1377))	1377

activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConnectionInfoMarshaller (p. 1381))	1381
cms::ConnectionMetaData (A ConnectionMetaData (p. 1385) object provides information describing the Connection (p. 1262) object)	1385
activemq::state::ConnectionState	1389
activemq::state::ConnectionStateTracker	1392
decaf::util::logging::ConsoleHandler (This Handler (p. 1978) publishes log records to System.err)	1399
activemq::commands::ConsumerControl	1401
activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1406))	1406
activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1410))	1410
activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1414))	1414
activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1418))	1418
activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1422))	1422
activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1426))	1426
activemq::commands::ConsumerId	1430
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1435))	1435
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1439))	1439
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1443))	1443
activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1447))	1447
activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1451))	1451
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerIdMarshaller (p. 1455))	1455
activemq::commands::ConsumerInfo	1459
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1468))	1468
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1472))	1472

activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1476))	1476
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1480))	1480
activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1484))	1484
activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for ConsumerInfoMarshaller (p. 1488))	1488
activemq::state::ConsumerState	1492
activemq::commands::ControlCommand	1493
activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1497))	1497
activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1501))	1501
activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1505))	1505
activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1509))	1509
activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1513))	1513
activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ControlCommandMarshaller (p. 1517))	1517
decaf::util::concurrent::CountDownLatch	1521
decaf::util::zip::CRC32 (Class that can be used to compute a CRC-32 checksum for a data stream)	1524
ct_data_s	1527
activemq::commands::DataArrayResponse	1528
activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1531))	1531
activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1535))	1535
activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1539))	1539
activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1543))	1543
activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1547))	1547

activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataArrayResponseMarshaller (p. 1551))	1551
decaf::util::zip::DataFormatException	1555
decaf::io::DataInput (The DataInput (p. 1558) interface provides for reading bytes from a binary stream and reconstructing from them data in any of the C++ primitive types)	1558
decaf::io::DataInputStream (A data input stream lets an application read primitive Java data types from an underlying input stream in a machine-independent way)	1566
decaf::io::DataOutput (The DataOutput (p. 1574) interface provides for converting data from any of the C++ primitive types to a series of bytes and writing these bytes to a binary stream)	1574
decaf::io::DataOutputStream (A data output stream lets an application write primitive Java data types to an output stream in a portable way)	1579
activemq::commands::DataResponse	1583
activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1586))	1586
activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1590))	1590
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1594))	1594
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1598))	1598
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1602))	1602
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for DataResponseMarshaller (p. 1606))	1606
activemq::wireformat::openwire::marshal::DataStreamMarshaller (Base class for all classes that marshal (p. 107) commands (p. 87) for Openwire)	1610
activemq::commands::DataStructure	1660
decaf::util::Date (Wrapper class around a time value in milliseconds)	1665
decaf::internal::DecafRuntime (Handles APR initialization and termination)	1670
activemq::threads::DedicatedTaskRunner	1671
activemq::core::policies::DefaultPrefetchPolicy	1673
activemq::core::policies::DefaultRedeliveryPolicy	1677
decaf::internal::net::DefaultServerSocketFactory (Default implementation of the Decaf ServerSocketFactory, creates ServerSocket objects with supplied options)	1682
decaf::internal::net::DefaultSocketFactory (SocketFactory implementation that is used to create Sockets)	1686
decaf::internal::net::ssl::DefaultSSLContext (Default SSLContext manager for the Decaf library)	1691
decaf::internal::net::ssl::DefaultSSLServerSocketFactory (Default implementation of the SSLServerSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds)	1692

decaf::internal::net::ssl::DefaultSSLSocketFactory (Default implementation of the SSLSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds)	1697
activemq::transport::DefaultTransportListener	1704
decaf::util::zip::Deflater (This class compresses data using the <i>DEFLATE</i> algorithm (see specification))	1706
decaf::util::zip::DeflaterOutputStream (Provides a FilterOutputStream instance that compresses the data before writing it to the wrapped OutputStream) . .	1716
decaf::util::concurrent::Delayed (A mix-in style interface for marking objects that should be acted upon after a given delay)	1720
cms::DeliveryMode (This is an Abstract class whose purpose is to provide a container for the delivery mode enumeration for CMS messages)	1721
cms::Destination (A Destination (p. 1723) object encapsulates a provider-specific address)	1723
activemq::commands::ActiveMQDestination::DestinationFilter	1726
activemq::commands::DestinationInfo	1727
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1732))	1732
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1736))	1736
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1740))	1740
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1744))	1744
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1748))	1748
activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for DestinationInfoMarshaller (p. 1752))	1752
activemq::cmsutil::DestinationResolver (Resolves a CMS destination name to a Destination)	1756
activemq::commands::DiscoveryEvent	1758
activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (Marshaling code (p. 1183) for Open Wire Format for DiscoveryEventMarshaller (p. 1762))	1762
activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller (Marshaling code (p. 1183) for Open Wire Format for DiscoveryEventMarshaller (p. 1766))	1766
activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (Marshaling code (p. 1183) for Open Wire Format for DiscoveryEventMarshaller (p. 1770))	1770
activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (Marshaling code (p. 1183) for Open Wire Format for DiscoveryEventMarshaller (p. 1774))	1774
activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (Marshaling code (p. 1183) for Open Wire Format for DiscoveryEventMarshaller (p. 1778))	1778

activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller (Marshaling code (p.1183) for Open Wire Format for DiscoveryEventMarshaller (p.1782))	1782
activemq::core::DispatchData (Simple POJO that contains the information necessary to route a message to a specified consumer)	1786
activemq::core::Dispatcher (Interface for an object responsible for dispatching messages to consumers)	1787
decaf::lang::Double	1788
decaf::internal::nio::DoubleArrayBuffer	1799
decaf::nio::DoubleBuffer (This class defines four categories of operations upon double buffers:)	1809
decaf::lang::DYNAMIC_CAST_TOKEN	1820
activemq::cmsutil::DynamicDestinationResolver (Resolves a CMS destination name to a Destination)	1821
decaf::util::Map< K, V, COMPARATOR >::Entry	1824
decaf::io::EOFException	1825
decaf::util::logging::ErrorManager (ErrorManager (p.1828) objects can be attached to Handlers to process any error that occur on a Handler (p.1978) during Logging)	1828
decaf::lang::Exception	1831
cms::ExceptionListener (If a CMS provider detects a serious problem, it notifies the client application through an ExceptionListener (p.1838) that is registered with the Connection (p.1262))	1838
activemq::commands::ExceptionResponse	1839
activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1842))	1842
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1846))	1846
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1850))	1850
activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1854))	1854
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1858))	1858
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (Marshaling code (p.1183) for Open Wire Format for ExceptionResponseMarshaller (p.1862))	1862
decaf::util::concurrent::ExecutionException	1866
decaf::util::concurrent::Executor (An object that executes submitted decaf.lang Runnable (p.3325) tasks)	1869
decaf::util::concurrent::ExecutorService (An Executor (p.1869) that provides methods to manage termination and methods that can produce a Future (p.1966) for tracking progress of one or more asynchronous tasks)	1871
activemq::transport::failover::FailoverTransport	1873
activemq::transport::failover::FailoverTransportFactory (Creates an instance of a FailoverTransport (p.1873))	1885
activemq::transport::failover::FailoverTransportListener (Utility class used by the Transport (p.3883) to perform the work of responding to events from the active Transport (p.3883))	1888

decaf::io::FileDescriptor (This class servers as an opaque wrapper around an underlying OS level resource that can be used as a source / sink for byte level data such as sockets and files)	1891
decaf::util::logging::Filter (A Filter (p. 1893) can be used to provide fine grain control over what is logged, beyond the control provided by log levels)	1893
decaf::io::FilterInputStream (A FilterInputStream (p. 1894) contains some other input stream, which it uses as its basic source of data, possibly transforming the data along the way or providing additional functionality)	1894
decaf::io::FilterOutputStream (This class is the superclass of all classes that filter output streams)	1900
decaf::lang::Float	1904
decaf::internal::nio::FloatArrayBuffer	1915
decaf::nio::FloatBuffer (This class defines four categories of operations upon float buffers:)	1925
decaf::io::Flushable (A Flushable (p. 1936) is a destination of data that can be flushed)	1936
activemq::commands::FlushCommand	1937
activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1940))	1940
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1944))	1944
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1948))	1948
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1952))	1952
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1956))	1956
activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for FlushCommandMarshaller (p. 1960))	1960
decaf::util::logging::Formatter (A Formatter (p. 1964) provides support for formatting LogRecords)	1964
decaf::util::concurrent::Future< V > (A Future (p. 1966) represents the result of an asynchronous computation)	1966
activemq::transport::correlator::FutureResponse (A container that holds a response object)	1969
decaf::security::GeneralSecurityException	1971
decaf::internal::util::GenericResource< T > (A Generic Resource (p. 3280) wraps some type and will delete it when the Resource (p. 3280) itself is deleted) . .	1974
gz_header_s	1975
gz_state	1976
decaf::util::logging::Handler (A Handler (p. 1978) object takes log messages from a Logger (p. 2386) and exports them)	1978
decaf::internal::util::HexStringParser	1982
activemq::wireformat::openwire::utils::HexTable (Maps hexadecimal strings to the value of an index into the table, i.e)	1984
decaf::net::HttpRetryException	1986
activemq::util::IdGenerator	1989
decaf::lang::exceptions::IllegalArgumentException	1991
decaf::lang::exceptions::IllegalMonitorStateException	1994

cms::IllegalStateException (This exception is thrown when a method is invoked at an illegal or inappropriate time or if the provider is not in an appropriate state for the requested operation)	1997
decaf::lang::exceptions::IllegalStateException	1998
decaf::lang::exceptions::IllegalThreadStateException	2001
activemq::transport::inactivity::InactivityMonitor	2004
decaf::lang::exceptions::IndexOutOfBoundsException	2008
decaf::net::Inet4Address	2011
decaf::net::Inet6Address	2015
decaf::net::InetAddress (Represents an IP address)	2016
decaf::net::InetSocketAddress	2023
inflate_state	2024
decaf::util::zip::Inflater (This class uncompresses data that was compressed using the <i>DEFLATE</i> algorithm (see <i>specification</i>))	2027
decaf::util::zip::InflaterInputStream (A <i>FilterInputStream</i> that decompresses data read from the wrapped <i>InputStream</i> instance)	2035
decaf::io::InputStream (A base class that must be implemented by all classes wishing to provide a class that reads in a stream of bytes)	2043
decaf::io::InputStreamReader (An <i>InputStreamReader</i> (p. 2053) is a bridge from byte streams to character streams)	2053
decaf::internal::nio::IntArrayBuffer	2056
decaf::nio::IntBuffer (This class defines four categories of operations upon int buffers:)	2066
decaf::lang::Integer	2077
activemq::commands::IntegerResponse	2091
activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2094))	2094
activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2098))	2098
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2102))	2102
activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2106))	2106
activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2110))	2110
activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (Marshaling <i>code</i> (p. 1183) for Open Wire Format for <i>IntegerResponseMarshaller</i> (p. 2114))	2114
internal_state	2118
activemq::transport::mock::InternalCommandListener (Listens for Commands sent from the <i>MockTransport</i> (p. 2768))	2122
decaf::lang::exceptions::InterruptedException	2124
decaf::io::InterruptedException	2127
cms::InvalidClientIdException (This exception must be thrown when a client attempts to set a connection's client ID to a value that is rejected by a provider)	2130
cms::InvalidDestinationException (This exception must be thrown when a destination either is not understood by a provider or is no longer valid)	2131
decaf::security::InvalidKeyException	2132
decaf::nio::InvalidMarkException	2135

cms::InvalidSelectorException (This exception must be thrown when a CMS client attempts to give a provider a message selector with invalid syntax)	2138
decaf::lang::exceptions::InvalidStateException	2139
decaf::io::IOException	2142
activemq::transport::IOTransport (Implementation of the Transport (p. 3883) interface that performs marshaling of commands (p. 87) to IO streams)	2145
decaf::lang::Iterable< E > (Implementing this interface allows an object to be cast to an Iterable (p. 2152) type for generic collections API calls)	2152
decaf::util::Iterator< T > (Defines an object that can be used to iterate over the elements of a collection)	2154
activemq::commands::JournalQueueAck	2156
activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2159))	2159
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2163))	2163
activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2167))	2167
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2171))	2171
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2175))	2175
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2179))	2179
activemq::commands::JournalTopicAck	2183
activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2188))	2188
activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2192))	2192
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2196))	2196
activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2200))	2200
activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2204))	2204
activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTopicAckMarshaller (p. 2208))	2208
activemq::commands::JournalTrace	2212
activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller (Marshaling code (p. 1183) for Open Wire Format for JournalTraceMarshaller (p. 2215))	2215

activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTraceMarshaller (p. 2219))	2219
activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTraceMarshaller (p. 2223))	2223
activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTraceMarshaller (p. 2227))	2227
activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTraceMarshaller (p. 2231))	2231
activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTraceMarshaller (p. 2235))	2235
activemq::commands::JournalTransaction	2239
activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2242))	2242
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2246))	2246
activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2250))	2250
activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2254))	2254
activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2258))	2258
activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (Marshaling code (p.1183) for Open Wire Format for JournalTransactionMarshaller (p. 2262))	2262
activemq::commands::KeepAliveInfo	2266
activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2269))	2269
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2273))	2273
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2277))	2277
activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2281))	2281
activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2285))	2285
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for KeepAliveInfoMarshaller (p. 2289))	2289
decaf::security::Key (The Key (p.2293) interface is the top-level interface for all keys)	2293

decaf::security::KeyException	2295
decaf::security::KeyManagementException	2298
activemq::commands::LastPartialCommand	2301
activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2304))	2304
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2308))	2308
activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2312))	2312
activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2316))	2316
activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2320))	2320
activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for LastPartialCommand- Marshaller (p. 2324))	2324
decaf::util::comparators::Less< E > (Simple Less (p. 2328) Comparator (p. 1217) that compares to elements to determine if the first is less than the second) . .	2328
std::less< decaf::lang::ArrayPointer< T > > (An override of the less function object so that the Pointer objects can be stored in STL Maps, etc)	2330
std::less< decaf::lang::Pointer< T > > (An override of the less function object so that the Pointer objects can be stored in STL Maps, etc)	2331
decaf::util::logging::Level (Defines a set of standard logging (p. 175) levels that can be used to control logging (p. 175) output)	2332
decaf::util::List< E > (An ordered collection (also known as a sequence))	2337
decaf::util::ListIterator< E > (An iterator for lists that allows the programmer to traverse the list in either direction, modify the list during iteration, and obtain the iterator's current position in the list)	2344
activemq::commands::LocalTransactionId	2347
activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2351))	2351
activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2355))	2355
activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2359))	2359
activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2363))	2363
activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2367))	2367
activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for LocalTransactionId- Marshaller (p. 2371))	2371
decaf::util::concurrent::Lock (A wrapper class around a given synchronization mech- anism that provides automatic release upon destruction)	2375

decaf::util::concurrent::locks::Lock (Lock (p. 2377) implementations provide more extensive locking operations than can be obtained using synchronized statements)	2377
decaf::util::concurrent::locks::LockSupport (Basic thread blocking primitives for creating locks (p. 174) and other synchronization classes)	2383
decaf::util::logging::Logger (A Logger (p. 2386) object is used to log messages for a specific system or application component)	2386
decaf::util::logging::LoggerHierarchy	2398
activemq::io::LoggingInputStream	2399
activemq::io::LoggingOutputStream (OutputStream filter that just logs the data being written)	2401
activemq::transport::logging::LoggingTransport (A transport (p. 97) filter that logs commands (p. 87) as they are sent/received)	2403
decaf::util::logging::LogManager (There is a single global LogManager (p. 2406) object that is used to maintain a set of shared state about Loggers and log services)	2406
decaf::util::logging::LogRecord (LogRecord (p. 2413) objects are used to pass logging (p. 175) requests between the logging (p. 175) framework and individual log Handlers)	2413
decaf::util::logging::LogWriter	2418
decaf::lang::Long	2420
decaf::internal::nio::LongArrayBuffer	2434
decaf::nio::LongBuffer (This class defines four categories of operations upon long long buffers:)	2444
activemq::util::LongSequenceGenerator (This class is used to generate a sequence of long long values that are incremented each time a new value is requested)	2455
decaf::net::MalformedURLException	2456
decaf::util::Map< K, V, COMPARATOR > (Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map)	2459
cms::MapMessage (A MapMessage (p. 2472) object is used to send a set of name-value pairs)	2472
decaf::util::logging::MarkBlockLogger (Defines a class that can be used to mark the entry and exit from scoped blocks)	2483
activemq::wireformat::MarshalAware	2484
activemq::wireformat::openwire::marshal::v6::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2487
activemq::wireformat::openwire::marshal::v3::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2488
activemq::wireformat::openwire::marshal::v4::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2489
activemq::wireformat::openwire::marshal::v5::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2490
activemq::wireformat::openwire::marshal::v1::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2491
activemq::wireformat::openwire::marshal::v2::MarshallerFactory (Used to create marshallers for a specific version of the wire protocol)	2492
activemq::util::MarshallingSupport	2493
decaf::lang::Math (The class Math (p. 2497) contains methods for performing basic numeric operations such as the elementary exponential, logarithm, square root, and trigonometric functions)	2497
activemq::util::MemoryUsage	2512
activemq::commands::Message	2516
cms::Message (Root of all messages)	2534
activemq::commands::MessageAck	2559

activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2565))	2565
activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2569))	2569
activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2573))	2573
activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2577))	2577
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2581))	2581
activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageAckMarshaller (p. 2585))	2585
cms::MessageConsumer (A client uses a MessageConsumer (p. 2589) to received messages from a destination)	2589
activemq::cmsutil::MessageCreator (Creates the user-defined message to be sent by the CmsTemplate (p. 1170))	2593
activemq::commands::MessageDispatch	2594
activemq::core::MessageDispatchChannel	2599
activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2606))	2606
activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2610))	2610
activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2614))	2614
activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2618))	2618
activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2622))	2622
activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p. 2626))	2626
activemq::commands::MessageDispatchNotification	2630
activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2635))	2635
activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2639))	2639
activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller (Marshaling code (p.1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2643))	2643

activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2647))	2647
activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2651))	2651
activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2655))	2655
cms::MessageEnumeration (Defines an object that enumerates a collection of Messages)	2659
cms::MessageEOFException (This exception must be thrown when an unexpected end of stream has been reached when a StreamMessage (p. 3652) or BytesMessage (p. 1056) is being read)	2661
cms::MessageFormatException (This exception must be thrown when a CMS client attempts to use a data type not supported by a message or attempts to read data in a message as the wrong type)	2662
activemq::commands::MessageId	2663
activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2668))	2668
activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2672))	2672
activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2676))	2676
activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2680))	2680
activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2684))	2684
activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageIdMarshaller (p. 2688))	2688
cms::MessageListener (A MessageListener (p. 2692) object is used to receive asynchronously delivered messages)	2692
activemq::wireformat::openwire::marshal::v5::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2693))	2693
activemq::wireformat::openwire::marshal::v3::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2698))	2698
activemq::wireformat::openwire::marshal::v2::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2703))	2703
activemq::wireformat::openwire::marshal::v4::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2708))	2708
activemq::wireformat::openwire::marshal::v1::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2713))	2713
activemq::wireformat::openwire::marshal::v6::MessageMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessageMarshaller (p. 2718))	2718
cms::MessageNotReadableException (This exception must be thrown when a CMS client attempts to read a write-only message)	2723
cms::MessageNotWritableException (This exception must be thrown when a CMS client attempts to write to a read-only message)	2724

cms::MessageProducer (A client uses a MessageProducer (p. 2725) object to send messages to a Destination (p. 1723))	2725
activemq::wireformat::openwire::utils::MessagePropertyInterceptor (Used the base ActiveMQMessage class to intercept calls to get and set properties in order to capture the calls that use the reserved JMS properties and get and set them in the OpenWire Message properties)	2732
activemq::commands::MessagePull	2739
activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2744))	2744
activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2748))	2748
activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2752))	2752
activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2756))	2756
activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2760))	2760
activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (Marshaling code (p. 1183) for Open Wire Format for MessagePullMarshaller (p. 2764))	2764
activemq::transport::mock::MockTransport (The MockTransport (p. 2768) defines a base level Transport (p. 3883) class that is intended to be used in place of an a regular protocol Transport (p. 3883) such as TCP)	2768
activemq::transport::mock::MockTransportFactory (Manufactures MockTransports , which are objects that read from input streams and write to output streams)	2779
decaf::util::concurrent::Mutex (Mutex (p. 2782) object that offers recursive support on all platforms as well as providing the ability to use the standard wait / notify pattern used in languages like Java)	2782
decaf::util::concurrent::MutexHandle	2787
decaf::internal::util::concurrent::MutexImpl	2788
decaf::internal::net::Network (Internal class used to manage Networking related resources and hide platform dependent calls from the higher level API)	2790
activemq::commands::NetworkBridgeFilter	2793
activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2796))	2796
activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2800))	2800
activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2804))	2804
activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2808))	2808
activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2812))	2812

activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller (Marshaling code (p. 1183) for Open Wire Format for NetworkBridgeFilterMarshaller (p. 2816))	2816
decaf::net::NoRouteToHostException	2820
decaf::security::NoSuchAlgorithmException	2823
decaf::lang::exceptions::NoSuchElementException	2826
decaf::security::NoSuchProviderException	2829
decaf::lang::exceptions::NullPointerException	2832
decaf::lang::Number (The abstract class Number (p. 2835) is the superclass of classes Byte (p. 960), Double (p. 1788), Float (p. 1904), Integer (p. 2077), Long (p. 2420), and Short (p. 3440))	2835
decaf::lang::exceptions::NumberFormatException	2838
cms::ObjectMessage (Place holder for interaction with JMS systems that support Java, the C++ client is not responsible for deserializing the contained Object) . . .	2841
decaf::internal::net::ssl::openssl::OpenSSLContextSpi (Provides an SSLContext that wraps the OpenSSL API)	2842
decaf::internal::net::ssl::openssl::OpenSSLParameters (Container class for parameters that are Common to OpenSSL socket classes)	2845
decaf::internal::net::ssl::openssl::OpenSSLServerSocket (SSLServerSocket based on OpenSSL library code (p. 1183))	2847
decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory (SSLServerSocketFactory that creates Server Sockets that use OpenSSL)	2853
decaf::internal::net::ssl::openssl::OpenSSLSocket (Wraps a a Normal Socket object and extends or overrides functions in that class to make use of the OpenSSL Socket API)	2858
decaf::internal::net::ssl::openssl::OpenSSLSocketException (Subclass of the standard SocketException that knows how to produce an error message from the OpenSSL error stack)	2871
decaf::internal::net::ssl::openssl::OpenSSLSocketFactory (Client Socket Factory that creates SSL based client sockets using the OpenSSL library)	2875
decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream (An output stream for reading data from an OpenSSL Socket instance)	2882
decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream (OutputStream implementation used to write data to an OpenSSLSocket (p. 2858) instance)	2885
activemq::wireformat::openwire::OpenWireFormat	2887
activemq::wireformat::openwire::OpenWireFormatFactory	2899
activemq::wireformat::openwire::OpenWireFormatNegotiator	2901
activemq::wireformat::openwire::OpenWireResponseBuilder	2905
decaf::io::OutputStream (Base interface for any class that wants to represent an output stream of bytes)	2907
decaf::io::OutputStreamWriter (A class for turning a character stream into a byte stream)	2915
activemq::commands::PartialCommand	2918
activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for PartialCommandMarshaller (p. 2922))	2922
activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for PartialCommandMarshaller (p. 2926))	2926
activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for PartialCommandMarshaller (p. 2930))	2930

activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (Marshaling code (p.1183) for Open Wire Format for PartialCommandMarshaller (p.2934))	2934
activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (Marshaling code (p.1183) for Open Wire Format for PartialCommandMarshaller (p.2938))	2938
activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller (Marshaling code (p.1183) for Open Wire Format for PartialCommandMarshaller (p.2942))	2942
decaf::lang::Pointer< T, REFCOUNTER > (Decaf's implementation of a Smart Pointer (p.2946) that is a template on a Type and is Thread (p.3765) Safe if the default Reference Counter is used)	2946
decaf::lang::PointerComparator< T, R > (This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the Object being Pointed to and not the value of the contained pointer in the Pointer (p.2946) instance)	2954
activemq::cmsutil::PooledSession (A pooled session object that wraps around a delegate session)	2955
decaf::util::concurrent::PooledThread	2968
decaf::util::concurrent::PooledThreadListener (Abstract Listener Interface for users of ThreadPool (p.3777))	2971
decaf::net::PortUnreachableException	2973
activemq::core::PrefetchPolicy (Interface for a Policy object that controls message Prefetching on various destination types in ActiveMQ-CPP)	2976
activemq::util::PrimitiveList (List of primitives)	2980
activemq::util::PrimitiveMap (Map of named primitives)	2991
activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller (This class wraps the functionality needed to marshal (p.107) a primitive map to the Openwire Format's expectation of what the map looks like on the wire) . .	3001
activemq::util::PrimitiveValueNode::PrimitiveValue (Define a union type comprised of the various types)	3008
activemq::util::PrimitiveValueConverter (Class controls the conversion of data contained in a PrimitiveValueNode (p.3012) from one type to another)	3010
activemq::util::PrimitiveValueNode (Class that wraps around a single value of one of the many types)	3012
decaf::security::Principal (Base interface for a principal, which can represent an individual or organization)	3026
decaf::util::PriorityQueue< E > (An unbounded priority queue based on a binary heap algorithm)	3028
activemq::commands::ProducerAck	3036
activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3040))	3040
activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3044))	3044
activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3048))	3048
activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3052))	3052

activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3056))	3056
activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerAckMarshaller (p.3060))	3060
activemq::cmsutil::ProducerCallback (Callback for sending a message to a CMS destination)	3064
activemq::cmsutil::CmsTemplate::ProducerExecutor	3065
activemq::commands::ProducerId	3067
activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3072))	3072
activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3076))	3076
activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3080))	3080
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3084))	3084
activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3088))	3088
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerIdMarshaller (p.3092))	3092
activemq::commands::ProducerInfo	3096
activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3101))	3101
activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3105))	3105
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3109))	3109
activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3113))	3113
activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3117))	3117
activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ProducerInfoMarshaller (p.3121))	3121
activemq::state::ProducerState	3125
decaf::util::Properties (Java-like properties class for mapping string names to string values)	3126
decaf::util::logging::PropertiesChangeListener (Defines the interface that classes can use to listen for change events on Properties (p.3126))	3135
decaf::net::ProtocolException	3137
decaf::security::PublicKey (A public key)	3140

decaf::io::PushbackInputStream (A PushbackInputStream (p. 3141) adds functionality to another input stream, namely the ability to "push back" or "unread" one byte)	3141
cms::Queue (An interface encapsulating a provider-specific queue name)	3148
decaf::util::Queue< E > (A kind of collection provides advanced operations than other basic collections, such as insertion, extraction, and inspection)	3149
cms::QueueBrowser (This class implements in interface for browsing the messages in a Queue (p. 3148) without removing them)	3153
decaf::util::Random (Random (p. 3155) Value Generator which is used to generate a stream of pseudorandom numbers)	3155
decaf::lang::Readable (A Readable (p. 3160) is a source of characters)	3160
activemq::transport::inactivity::ReadChecker (Runnable class that is used by the {)	3162
decaf::io::Reader	3163
decaf::nio::ReadOnlyBufferException	3169
decaf::util::concurrent::locks::ReadWriteLock (A ReadWriteLock (p. 3172) maintains a pair of associated locks (p. 174), one for read-only operations and one for writing)	3172
activemq::cmsutil::CmsTemplate::ReceiveExecutor	3174
activemq::core::RedeliveryPolicy (Interface for a RedeliveryPolicy (p. 3177) object that controls how message Redelivery is handled in ActiveMQ-CPP when a transaction is rolled back)	3177
decaf::util::concurrent::locks::ReentrantLock (A reentrant mutual exclusion Lock (p. 2377) with extended capabilities)	3182
decaf::util::concurrent::RejectedExecutionException	3189
decaf::util::concurrent::RejectedExecutionHandler (A handler for tasks that cannot be executed by a ThreadPoolExecutor (p. ??))	3192
activemq::commands::RemoveInfo	3194
activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3198))	3198
activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3202))	3202
activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3206))	3206
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3210))	3210
activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3214))	3214
activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveInfoMarshaller (p. 3218))	3218
activemq::commands::RemoveSubscriptionInfo	3222
activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscriptionInfoMarshaller (p. 3227))	3227
activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscriptionInfoMarshaller (p. 3231))	3231

activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscription-InfoMarshaller (p. 3235))	3235
activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscription-InfoMarshaller (p. 3239))	3239
activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscription-InfoMarshaller (p. 3243))	3243
activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for RemoveSubscription-InfoMarshaller (p. 3247))	3247
activemq::commands::ReplayCommand	3251
activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3254))	3254
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3258))	3258
activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3262))	3262
activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3266))	3266
activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3270))	3270
activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller (Marshaling code (p. 1183) for Open Wire Format for ReplayCommand-Marshaller (p. 3274))	3274
activemq::cmsutil::CmsTemplate::ResolveProducerExecutor	3278
activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor	3279
decaf::internal::util::Resource (Interface for all Managed Resources in Decaf, these objects are added to the Runtime System and are destroyed at shutdown) . .	3280
decaf::internal::util::ResourceLifecycleManager	3281
activemq::cmsutil::ResourceLifecycleManager (Manages the lifecycle of a set of CMS resources)	3282
activemq::commands::Response	3285
activemq::transport::mock::ResponseBuilder (Interface for all Protocols to implement that defines the behavior of the Broker in response to messages of that protocol)	3289
activemq::transport::correlator::ResponseCorrelator (This type of transport (p. 97) filter is responsible for correlating asynchronous responses with requests) .	3291
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3295)) . .	3295
activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3300)) . .	3300
activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3305)) . .	3305
activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3310)) . .	3310
activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3315)) . .	3315

activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (Marshaling code (p. 1183) for Open Wire Format for ResponseMarshaller (p. 3320)) . .	3320
decaf::lang::Runnable (Interface for a runnable object - defines a task that can be run by a thread)	3325
decaf::lang::Runtime	3326
decaf::lang::exceptions::RuntimeException	3328
decaf::security::SecureRandom	3331
decaf::internal::security::SecureRandomImpl (Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources)	3336
decaf::security::SecureRandomSpi (Interface class used by Security Service Providers to implement a source of secure random bytes)	3339
decaf::util::concurrent::Semaphore (A counting semaphore)	3341
activemq::cmsutil::CmsTemplate::SendExecutor	3350
decaf::net::ServerSocket (This class implements server sockets)	3352
decaf::net::ServerSocketFactory (Class used to create Server Sockets, subclasses can be created that create certain types of server sockets according to specific policies)	3361
cms::Session (A Session (p. 3365) object is a single-threaded context for producing and consuming messages)	3365
activemq::cmsutil::SessionCallback (Callback for executing any number of operations on a provided CMS Session)	3378
activemq::commands::SessionId	3379
activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3383)) . .	3383
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3387)) . .	3387
activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3391)) . .	3391
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3395)) . .	3395
activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3399)) . .	3399
activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionIdMarshaller (p. 3403)) . .	3403
activemq::commands::SessionInfo	3407
activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3411))	3411
activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3415))	3415
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3419))	3419
activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3423))	3423
activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3427))	3427
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SessionInfoMarshaller (p. 3431))	3431

activemq::cmsutil::SessionPool (A pool of CMS sessions from the same connection and with the same acknowledge mode)	3435
activemq::state::SessionState	3437
decaf::util::Set< E > (A collection that contains no duplicate elements)	3439
decaf::lang::Short	3440
decaf::internal::nio::ShortArrayBuffer	3449
decaf::nio::ShortBuffer (This class defines four categories of operations upon short buffers:)	3459
activemq::commands::ShutdownInfo	3470
activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3473))	3473
activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3477))	3477
activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3481))	3481
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3485))	3485
activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3489))	3489
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (Marshaling code (p.1183) for Open Wire Format for ShutdownInfoMarshaller (p.3493))	3493
decaf::security::SignatureException	3497
decaf::util::logging::SimpleFormatter (Print a brief summary of the LogRecord (p.2413) in a human readable format)	3500
decaf::util::logging::SimpleLogger	3501
decaf::net::Socket	3503
decaf::net::SocketAddress (Base class for protocol specific Socket (p.3503) addresses)	3519
decaf::net::SocketError (Static utility class to simplify handling of error codes for socket operations)	3520
decaf::net::SocketException (Exception for errors when manipulating sockets)	3521
decaf::net::SocketFactory (The SocketFactory (p.3524) is used to create Socket (p.3503) objects and can be sub-classed to provide other types of Sockets or Sockets with varying configurations)	3524
decaf::internal::net::SocketFileDescriptor (File Descriptor type used internally by Decaf Socket objects)	3528
decaf::net::SocketImpl (Acts as a base class for all physical Socket (p.3503) implementations)	3529
decaf::net::SocketImplFactory (Factory class interface for a Factory that creates SocketImpl objects)	3537
decaf::net::SocketOptions	3538
decaf::net::SocketTimeoutException	3542
decaf::net::ssl::SSLContext (Represents on implementation of the Secure Socket (p.3503) Layer for streaming based sockets)	3545
decaf::net::ssl::SSLContextSpi (Defines the interface that should be provided by an SSLContext (p.3545) provider)	3548
decaf::net::ssl::SSLParameters	3551

decaf::net::ssl::SSLServerSocket (Represents a server socket that is used to accept connections from clients using the Secure Sockets protocol or the Top Level Security protocol)	3554
decaf::net::ssl::SSLServerSocketFactory (Factory class interface that provides methods to create SSL Server Sockets)	3560
decaf::net::ssl::SSLSocket	3563
decaf::net::ssl::SSLSocketFactory (Factory class interface for a SocketFactory (p. 3524) that can create SSLSocket (p. 3563) objects)	3571
activemq::transport::tcp::SslTransport (Transport (p. 3883) for connecting to a Broker using an SSL Socket)	3574
activemq::transport::tcp::SslTransportFactory	3576
activemq::commands::BrokerError::StackTraceElement	3578
decaf::internal::io::StandardErrorOutputStream (Wrapper Around the Standard error Output facility on the current platform)	3579
decaf::internal::io::StandardInputStream	3582
decaf::internal::io::StandardOutputStream	3584
cms::Startable (Interface for a class that implements the start method)	3586
decaf::lang::STATIC_CAST_TOKEN	3587
activemq::core::ActiveMQConstants::StaticInitializer	3588
decaf::util::StlList< E > (List (p. 2337) class that wraps the STL list object to provide a simpler interface and additional methods not provided by the STL type)	3589
decaf::util::StlMap< K, V, COMPARATOR > (Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map)	3602
decaf::util::StlQueue< T > (The Queue (p. 3149) class accepts messages with an psuh(m) command where m is the message to be queued)	3615
decaf::util::StlSet< E > (Set (p. 3439) template that wraps around a std::set to provide a more user-friendly interface and to provide common functions that do not exist in std::set)	3623
activemq::wireformat::stomp::StompCommandConstants	3629
activemq::wireformat::stomp::StompFrame (A Stomp-level message frame that encloses all messages to and from the broker)	3633
activemq::wireformat::stomp::StompHelper (Utility Methods used when marshaling to and from StompFrame's)	3638
activemq::wireformat::stomp::StompWireFormat	3643
activemq::wireformat::stomp::StompWireFormatFactory (Factory used to create the Stomp Wire Format instance)	3647
cms::Stoppable (Interface for a class that implements the stop method)	3648
decaf::util::logging::StreamHandler (Stream based logging (p. 175) Handler (p. 1978))	3649
cms::StreamMessage (Interface for a StreamMessage (p. 3652))	3652
decaf::lang::String (Immutable sequence of chars)	3665
decaf::util::StringTokenizer	3668
activemq::commands::SubscriptionInfo	3671
activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3676))	3676
activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3680))	3680
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3684))	3684

activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3688))	3688
activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3692))	3692
activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for SubscriptionInfoMarshaller (p. 3696))	3696
decaf::util::concurrent::Synchronizable (The interface for all synchronizable objects (that is, objects that can be locked and unlocked))	3700
decaf::internal::util::concurrent::SynchronizableImpl (A convenience class used by some Decaf classes to implement the Synchronizable interface when there is no issues related to multiple inheritance)	3711
activemq::core::Synchronization (Transacted Object Synchronization (p. 3715), used to sync the events of a Transaction with the items in the Transaction)	3715
decaf::util::concurrent::SynchronousQueue< E > (A blocking queue (p. 843) in which each insert operation must wait for a corresponding remove operation by another thread, and vice versa)	3716
decaf::lang::System (Static methods for accessing system level resources and performing some system dependent tasks such as looking up environment values and copying memory and arrays)	3726
activemq::threads::Task (Represents a unit of work that requires one or more iterations to complete)	3734
decaf::util::concurrent::TaskListener	3735
activemq::threads::TaskRunner	3736
decaf::internal::net::tcp::TcpSocket (Platform-independent implementation of the socket interface)	3738
decaf::internal::net::tcp::TcpSocketInputStream (Input stream for performing reads on a socket)	3747
decaf::internal::net::tcp::TcpSocketOutputStream (Output stream for performing write operations on a socket)	3750
activemq::transport::tcp::TcpTransport (Implements a TCP/IP based transport (p. 97) filter, this transport (p. 97) is meant to wrap an instance of an IOTransport (p. 2145))	3752
activemq::transport::tcp::TcpTransportFactory (Factory Responsible for creating the TcpTransport (p. 3752))	3756
cms::TemporaryQueue (Defines a Temporary Queue (p. 3148) based Destination (p. 1723))	3759
cms::TemporaryTopic (Defines a Temporary Topic (p. 3817) based Destination (p. 1723))	3761
cms::TextMessage (Interface for a text message)	3763
decaf::lang::Thread (A Thread (p. 3765) is a concurrent unit of execution)	3765
decaf::util::concurrent::ThreadFactory (Public interface ThreadFactory (p. 3774))	3774
decaf::lang::ThreadGroup	3776
decaf::util::concurrent::ThreadPool (Defines a Thread Pool object that implements the functionality of pooling threads to perform user tasks)	3777
decaf::lang::Throwable (This class represents an error that has occurred)	3783
decaf::util::concurrent::TimeoutException	3787
decaf::util::Timer (A facility for threads to schedule tasks for future execution in a background thread)	3790
decaf::util::TimerTask (A Base class for a task object that can be scheduled for one-time or repeated execution by a Timer (p. 3790))	3801

decaf::internal::util::TimerTaskHeap (A Binary Heap implemented specifically for the Timer class in Decaf Util)	3804
decaf::util::concurrent::TimeUnit (A TimeUnit (p. 3807) represents time durations at a given unit of granularity and provides utility methods to convert across units, and to perform timing and delay operations in these units)	3807
cms::Topic (An interface encapsulating a provider-specific topic name)	3817
activemq::state::Tracked	3818
activemq::commands::TransactionId	3819
activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3823))	3823
activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3827))	3827
activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3831))	3831
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3835))	3835
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3839))	3839
activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionIdMarshaller (p. 3843))	3843
activemq::commands::TransactionInfo	3847
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3851))	3851
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3855))	3855
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3859))	3859
activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3863))	3863
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3867))	3867
activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for TransactionInfoMarshaller (p. 3871))	3871
activemq::state::TransactionState	3875
decaf::internal::util::concurrent::Transferer< E > (Shared internal (p. 144) API for dual stacks and queues)	3877
decaf::internal::util::concurrent::TransferQueue< E > (This extends Scherer-Scott dual queue algorithm, differing, among other ways, by using modes within nodes rather than marked pointers)	3878
decaf::internal::util::concurrent::TransferStack< E >	3881
activemq::transport::Transport (Interface for a transport (p. 97) layer for command objects)	3883

activemq::transport::TransportFactory (Defines the interface for Factories that create Transports or TransportFilters)	3889
activemq::transport::TransportFilter (A filter on the transport (p. 97) layer)	3891
activemq::transport::TransportListener (A listener of asynchronous exceptions (p. 92) from a command transport (p. 97) object)	3900
activemq::transport::TransportRegistry (Registry of all Transport (p. 3883) Factories that are available to the client at runtime)	3902
tree_desc_s	3905
decaf::lang::Thread::UncaughtExceptionHandler (Interface for handlers invoked when a Thread (p. 3765) abruptly terminates due to an uncaught exception)	3906
decaf::net::UnknownHostException	3907
decaf::net::UnknownServiceException	3910
decaf::io::UnsupportedEncodingException (Thrown when the the Character Encoding is not supported)	3913
decaf::lang::exceptions::UnsupportedOperationException	3916
cms::UnsupportedOperationException (This exception must be thrown when a CMS client attempts use a CMS method that is not implemented or not supported by the CMS Provider in use)	3919
decaf::net::URI (This class represents an instance of a URI (p. 3921) as defined by RFC 2396)	3921
decaf::internal::net::URIEncoderDecoder	3932
decaf::internal::net::URIHelper (Helper class used by the URI classes in encoding and decoding of URI's)	3935
activemq::transport::failover::URIPool	3942
activemq::util::URISupport	3945
decaf::net::URISyntaxException	3948
decaf::internal::net::URIType (Basic type object that holds data that composes a given URI)	3952
decaf::net::URL (Class URL (p. 3960) represents a Uniform Resource Locator, a pointer to a "resource" on the World Wide Web)	3960
decaf::net::URLDecoder	3962
decaf::net::URLEncoder	3963
activemq::util::Usage	3964
decaf::io::UTFDataFormatException (Thrown from classes that attempt to read or write a UTF-8 encoded string and an encoding error is encountered)	3966
decaf::util::UUID (A class that represents an immutable universally unique identifier (UUID (p. 3969)))	3969
activemq::wireformat::WireFormat (Provides a mechanism to marshal commands (p. 87) into and out of packets or into and out of streams, Channels and Data-grams)	3976
activemq::wireformat::WireFormatFactory (The WireFormatFactory (p. 3980) is the interface that all WireFormatFactory (p. 3980) classes must extend)	3980
activemq::commands::WireFormatInfo	3982
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 3992))	3992
activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 3996))	3996
activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 4000))	4000

activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 4004))	4004
activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 4008))	4008
activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller (Marshaling code (p. 1183) for Open Wire Format for WireFormatInfoMarshaller (p. 4012))	4012
activemq::wireformat::WireFormatNegotiator (Defines a WireFormatNegotiator (p. 4016) which allows a WireFormat (p. 3976) to)	4016
activemq::wireformat::WireFormatRegistry (Registry of all WireFormat (p. 3976) Factories that are available to the client at runtime)	4017
activemq::transport::inactivity::WriteChecker (Runnable class used by the {)	4020
decaf::io::Writer	4021
decaf::security::auth::x500::X500Principal	4027
decaf::security::cert::X509Certificate (Base interface for all identity certificates)	4028
activemq::commands::XATransactionId	4031
activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4036))	4036
activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4040))	4040
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4044))	4044
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4048))	4048
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4052))	4052
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4056))	4056
decaf::util::logging::XMLFormatter (Format a LogRecord (p. 2413) into a standard XML format)	4060
z_stream_s	4062
decaf::util::zip::ZipException	4064

Chapter 4

File Index

4.1 File List

Here is a list of all files with brief descriptions:

src/main/activemq/cmsutil/	CachedConsumer.h	4067
src/main/activemq/cmsutil/	CachedProducer.h	4068
src/main/activemq/cmsutil/	CmsAccessor.h	4069
src/main/activemq/cmsutil/	CmsDestinationAccessor.h	4070
src/main/activemq/cmsutil/	CmsTemplate.h	4071
src/main/activemq/cmsutil/	DestinationResolver.h	4072
src/main/activemq/cmsutil/	DynamicDestinationResolver.h	4073
src/main/activemq/cmsutil/	MessageCreator.h	4074
src/main/activemq/cmsutil/	PooledSession.h	4075
src/main/activemq/cmsutil/	ProducerCallback.h	4076
src/main/activemq/cmsutil/	ResourceLifecycleManager.h	4077
src/main/activemq/cmsutil/	SessionCallback.h	4079
src/main/activemq/cmsutil/	SessionPool.h	4080
src/main/activemq/commands/	ActiveMQBlobMessage.h	4081
src/main/activemq/commands/	ActiveMQBytesMessage.h	4082
src/main/activemq/commands/	ActiveMQDestination.h	4083
src/main/activemq/commands/	ActiveMQMapMessage.h	4084
src/main/activemq/commands/	ActiveMQMessage.h	4085
src/main/activemq/commands/	ActiveMQMessageTemplate.h	4086
src/main/activemq/commands/	ActiveMQObjectMessage.h	4087
src/main/activemq/commands/	ActiveMQQueue.h	4088
src/main/activemq/commands/	ActiveMQStreamMessage.h	4089
src/main/activemq/commands/	ActiveMQTempDestination.h	4090
src/main/activemq/commands/	ActiveMQTempQueue.h	4091
src/main/activemq/commands/	ActiveMQTempTopic.h	4092
src/main/activemq/commands/	ActiveMQTextMessage.h	4093
src/main/activemq/commands/	ActiveMQTopic.h	4094
src/main/activemq/commands/	BaseCommand.h	4095
src/main/activemq/commands/	BaseDataStructure.h	4096
src/main/activemq/commands/	BooleanExpression.h	4097
src/main/activemq/commands/	BrokerError.h	4098
src/main/activemq/commands/	BrokerId.h	4099
src/main/activemq/commands/	BrokerInfo.h	4100

src/main/activemq/commands/	Command.h	4101
src/main/activemq/commands/	ConnectionControl.h	4102
src/main/activemq/commands/	ConnectionError.h	4103
src/main/activemq/commands/	ConnectionId.h	4104
src/main/activemq/commands/	ConnectionInfo.h	4105
src/main/activemq/commands/	ConsumerControl.h	4106
src/main/activemq/commands/	ConsumerId.h	4107
src/main/activemq/commands/	ConsumerInfo.h	4108
src/main/activemq/commands/	ControlCommand.h	4109
src/main/activemq/commands/	DataArrayResponse.h	4110
src/main/activemq/commands/	DataResponse.h	4111
src/main/activemq/commands/	DataStructure.h	4112
src/main/activemq/commands/	DestinationInfo.h	4113
src/main/activemq/commands/	DiscoveryEvent.h	4114
src/main/activemq/commands/	ExceptionResponse.h	4115
src/main/activemq/commands/	FlushCommand.h	4116
src/main/activemq/commands/	IntegerResponse.h	4117
src/main/activemq/commands/	JournalQueueAck.h	4118
src/main/activemq/commands/	JournalTopicAck.h	4119
src/main/activemq/commands/	JournalTrace.h	4120
src/main/activemq/commands/	JournalTransaction.h	4121
src/main/activemq/commands/	KeepAliveInfo.h	4122
src/main/activemq/commands/	LastPartialCommand.h	4123
src/main/activemq/commands/	LocalTransactionId.h	4124
src/main/activemq/commands/	Message.h	4125
src/main/activemq/commands/	MessageAck.h	4127
src/main/activemq/commands/	MessageDispatch.h	4128
src/main/activemq/commands/	MessageDispatchNotification.h	4129
src/main/activemq/commands/	MessageId.h	4130
src/main/activemq/commands/	MessagePull.h	4131
src/main/activemq/commands/	NetworkBridgeFilter.h	4132
src/main/activemq/commands/	PartialCommand.h	4133
src/main/activemq/commands/	ProducerAck.h	4134
src/main/activemq/commands/	ProducerId.h	4135
src/main/activemq/commands/	ProducerInfo.h	4136
src/main/activemq/commands/	RemoveInfo.h	4137
src/main/activemq/commands/	RemoveSubscriptionInfo.h	4138
src/main/activemq/commands/	ReplayCommand.h	4139
src/main/activemq/commands/	Response.h	4140
src/main/activemq/commands/	SessionId.h	4141
src/main/activemq/commands/	SessionInfo.h	4142
src/main/activemq/commands/	ShutdownInfo.h	4143
src/main/activemq/commands/	SubscriptionInfo.h	4144
src/main/activemq/commands/	TransactionId.h	4145
src/main/activemq/commands/	TransactionInfo.h	4146
src/main/activemq/commands/	WireFormatInfo.h	4147
src/main/activemq/commands/	XATransactionId.h	4148
src/main/activemq/core/	ActiveMQAckHandler.h	4149
src/main/activemq/core/	ActiveMQConnection.h	4150
src/main/activemq/core/	ActiveMQConnectionFactory.h	4151
src/main/activemq/core/	ActiveMQConnectionMetaData.h	4152
src/main/activemq/core/	ActiveMQConstants.h	4153
src/main/activemq/core/	ActiveMQConsumer.h	4154
src/main/activemq/core/	ActiveMQProducer.h	4155

src/main/activemq/core/ActiveMQQueueBrowser.h	4156
src/main/activemq/core/ActiveMQSession.h	4157
src/main/activemq/core/ActiveMQSessionExecutor.h	4158
src/main/activemq/core/ActiveMQTransactionContext.h	4159
src/main/activemq/core/DispatchData.h	4160
src/main/activemq/core/Dispatcher.h	4161
src/main/activemq/core/MessageDispatchChannel.h	4162
src/main/activemq/core/PrefetchPolicy.h	4165
src/main/activemq/core/RedeliveryPolicy.h	4166
src/main/activemq/core/Synchronization.h	4167
src/main/activemq/core/policies/DefaultPrefetchPolicy.h	4163
src/main/activemq/core/policies/DefaultRedeliveryPolicy.h	4164
src/main/activemq/exceptions/ActiveMQException.h	4168
src/main/activemq/exceptions/BrokerException.h	4169
src/main/activemq/exceptions/ExceptionDefines.h	4170
src/main/activemq/io/LoggingInputStream.h	4175
src/main/activemq/io/LoggingOutputStream.h	4176
src/main/activemq/library/ActiveMQCPP.h	4177
src/main/activemq/state/CommandVisitor.h	4178
src/main/activemq/state/CommandVisitorAdapter.h	4179
src/main/activemq/state/ConnectionState.h	4181
src/main/activemq/state/ConnectionStateTracker.h	4182
src/main/activemq/state/ConsumerState.h	4183
src/main/activemq/state/ProducerState.h	4184
src/main/activemq/state/SessionState.h	4185
src/main/activemq/state/Tracked.h	4186
src/main/activemq/state/TransactionState.h	4187
src/main/activemq/threads/CompositeTask.h	4188
src/main/activemq/threads/CompositeTaskRunner.h	4189
src/main/activemq/threads/DedicatedTaskRunner.h	4190
src/main/activemq/threads/Task.h	4191
src/main/activemq/threads/TaskRunner.h	4192
src/main/activemq/transport/AbstractTransportFactory.h	4193
src/main/activemq/transport/CompositeTransport.h	4194
src/main/activemq/transport/DefaultTransportListener.h	4197
src/main/activemq/transport/IOTransport.h	4208
src/main/activemq/transport/Transport.h	4218
src/main/activemq/transport/TransportFactory.h	4219
src/main/activemq/transport/TransportFilter.h	4220
src/main/activemq/transport/TransportListener.h	4221
src/main/activemq/transport/TransportRegistry.h	4222
src/main/activemq/transport/correlator/FutureResponse.h	4195
src/main/activemq/transport/correlator/ResponseCorrelator.h	4196
src/main/activemq/transport/failover/BackupTransport.h	4198
src/main/activemq/transport/failover/BackupTransportPool.h	4199
src/main/activemq/transport/failover/CloseTransportsTask.h	4200
src/main/activemq/transport/failover/FailoverTransport.h	4201
src/main/activemq/transport/failover/FailoverTransportFactory.h	4202
src/main/activemq/transport/failover/FailoverTransportListener.h	4203
src/main/activemq/transport/failover/URIPool.h	4204
src/main/activemq/transport/inactivity/InactivityMonitor.h	4205
src/main/activemq/transport/inactivity/ReadChecker.h	4206
src/main/activemq/transport/inactivity/WriteChecker.h	4207
src/main/activemq/transport/logging/LoggingTransport.h	4209

src/main/activemq/transport/mock/ InternalCommandListener.h	4210
src/main/activemq/transport/mock/ MockTransport.h	4211
src/main/activemq/transport/mock/ MockTransportFactory.h	4212
src/main/activemq/transport/mock/ ResponseBuilder.h	4213
src/main/activemq/transport/tcp/ SslTransport.h	4214
src/main/activemq/transport/tcp/ SslTransportFactory.h	4215
src/main/activemq/transport/tcp/ TcpTransport.h	4216
src/main/activemq/transport/tcp/ TcpTransportFactory.h	4217
src/main/activemq/util/ ActiveMQProperties.h	4223
src/main/activemq/util/ CMSExceptionSupport.h	4224
src/main/activemq/util/ CompositeData.h	4226
src/main/activemq/util/ Config.h	4227
src/main/activemq/util/ IdGenerator.h	4230
src/main/activemq/util/ LongSequenceGenerator.h	4231
src/main/activemq/util/ MarshallingSupport.h	4232
src/main/activemq/util/ MemoryUsage.h	4233
src/main/activemq/util/ PrimitiveList.h	4234
src/main/activemq/util/ PrimitiveMap.h	4235
src/main/activemq/util/ PrimitiveValueConverter.h	4236
src/main/activemq/util/ PrimitiveValueNode.h	4237
src/main/activemq/util/ URISupport.h	4238
src/main/activemq/util/ Usage.h	4239
src/main/activemq/wireformat/ MarshalAware.h	4240
src/main/activemq/wireformat/ WireFormat.h	4628
src/main/activemq/wireformat/ WireFormatFactory.h	4629
src/main/activemq/wireformat/ WireFormatNegotiator.h	4630
src/main/activemq/wireformat/ WireFormatRegistry.h	4631
src/main/activemq/wireformat/openwire/ OpenWireFormat.h	4616
src/main/activemq/wireformat/openwire/ OpenWireFormatFactory.h	4617
src/main/activemq/wireformat/openwire/ OpenWireFormatNegotiator.h	4618
src/main/activemq/wireformat/openwire/ OpenWireResponseBuilder.h	4619
src/main/activemq/wireformat/openwire/marshal/ BaseDataStreamMarshaller.h	4241
src/main/activemq/wireformat/openwire/marshal/ DataStreamMarshaller.h	4242
src/main/activemq/wireformat/openwire/marshal/ PrimitiveTypesMarshaller.h	4243
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQBlobMessageMarshaller.h	4244
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQBytesMessageMarshaller.h	4250
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQDestinationMarshaller.h	4256
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQMapMessageMarshaller.h	4262
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQMessageMarshaller.h	4268
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQObjectMessageMarshaller.h	4274
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQQueueMarshaller.h	4280
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQStreamMessageMarshaller.h	4286
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQTempDestinationMarshaller.h	4292
src/main/activemq/wireformat/openwire/marshal/v1/ ActiveMQTempQueueMarshaller.h	4298

src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h	
4304	
src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTextMessageMarshaller.h	
4310	
src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTopicMarshaller.h	4316
src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h	4322
src/main/activemq/wireformat/openwire/marshal/v1/BrokerIdMarshaller.h . . .	4328
src/main/activemq/wireformat/openwire/marshal/v1/BrokerInfoMarshaller.h . . .	4334
src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h	
4340	
src/main/activemq/wireformat/openwire/marshal/v1/ConnectionErrorMarshaller.h	
4346	
src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h .	4352
src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h	4358
src/main/activemq/wireformat/openwire/marshal/v1/ConsumerControlMarshaller.h	
4364	
src/main/activemq/wireformat/openwire/marshal/v1/ConsumerIdMarshaller.h . .	4370
src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h .	4376
src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h	
4382	
src/main/activemq/wireformat/openwire/marshal/v1/DataArrayResponseMarshaller.h	
4388	
src/main/activemq/wireformat/openwire/marshal/v1/DataResponseMarshaller.h .	4394
src/main/activemq/wireformat/openwire/marshal/v1/DestinationInfoMarshaller.h	4400
src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryEventMarshaller.h	4406
src/main/activemq/wireformat/openwire/marshal/v1/ExceptionResponseMarshaller.h	
4412	
src/main/activemq/wireformat/openwire/marshal/v1/FlushCommandMarshaller.h	4418
src/main/activemq/wireformat/openwire/marshal/v1/IntegerResponseMarshaller.h	
4424	
src/main/activemq/wireformat/openwire/marshal/v1/JournalQueueAckMarshaller.h	
4430	
src/main/activemq/wireformat/openwire/marshal/v1/JournalTopicAckMarshaller.h	
4436	
src/main/activemq/wireformat/openwire/marshal/v1/JournalTraceMarshaller.h . .	4442
src/main/activemq/wireformat/openwire/marshal/v1/JournalTransactionMarshaller.h	
4448	
src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h .	4454
src/main/activemq/wireformat/openwire/marshal/v1/LastPartialCommandMarshaller.h	
4460	
src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionIdMarshaller.h	
4466	
src/main/activemq/wireformat/openwire/marshal/v1/MarshallerFactory.h	4472
src/main/activemq/wireformat/openwire/marshal/v1/MessageAckMarshaller.h . .	4478
src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchMarshaller.h	
4484	
src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchNotificationMarshaller.h	
4490	
src/main/activemq/wireformat/openwire/marshal/v1/MessageIdMarshaller.h . . .	4496
src/main/activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h	4502
src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h . .	4508
src/main/activemq/wireformat/openwire/marshal/v1/NetworkBridgeFilterMarshaller.h	
4514	

src/main/activemq/wireformat/openwire/marshal/v1/PartialCommandMarshaller.h	
4520	
src/main/activemq/wireformat/openwire/marshal/v1/ProducerAckMarshaller.h	4526
src/main/activemq/wireformat/openwire/marshal/v1/ProducerIdMarshaller.h	4532
src/main/activemq/wireformat/openwire/marshal/v1/ProducerInfoMarshaller.h	4538
src/main/activemq/wireformat/openwire/marshal/v1/RemoveInfoMarshaller.h	4544
src/main/activemq/wireformat/openwire/marshal/v1/RemoveSubscriptionInfoMarshaller.h	
4550	
src/main/activemq/wireformat/openwire/marshal/v1/ReplayCommandMarshaller.h	
4556	
src/main/activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h	4562
src/main/activemq/wireformat/openwire/marshal/v1/SessionIdMarshaller.h	4568
src/main/activemq/wireformat/openwire/marshal/v1/SessionInfoMarshaller.h	4574
src/main/activemq/wireformat/openwire/marshal/v1/ShutdownInfoMarshaller.h	4580
src/main/activemq/wireformat/openwire/marshal/v1/SubscriptionInfoMarshaller.h	
4586	
src/main/activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h	4592
src/main/activemq/wireformat/openwire/marshal/v1/TransactionInfoMarshaller.h	4598
src/main/activemq/wireformat/openwire/marshal/v1/WireFormatInfoMarshaller.h	4604
src/main/activemq/wireformat/openwire/marshal/v1/XATransactionIdMarshaller.h	
4610	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBlobMessageMarshaller.h	
4245	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBytesMessageMarshaller.h	
4251	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h	
4257	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMapMessageMarshaller.h	
4263	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMessageMarshaller.h	
4269	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQObjectMessageMarshaller.h	
4275	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQQueueMarshaller.h	
4281	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQStreamMessageMarshaller.h	
4287	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h	
4293	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempQueueMarshaller.h	
4299	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempTopicMarshaller.h	
4305	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTextMessageMarshaller.h	
4311	
src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTopicMarshaller.h	4317
src/main/activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h	4323
src/main/activemq/wireformat/openwire/marshal/v2/BrokerIdMarshaller.h	4329
src/main/activemq/wireformat/openwire/marshal/v2/BrokerInfoMarshaller.h	4335
src/main/activemq/wireformat/openwire/marshal/v2/ConnectionControlMarshaller.h	
4341	
src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h	
4347	
src/main/activemq/wireformat/openwire/marshal/v2/ConnectionIdMarshaller.h	4353

src/main/activemq/wireformat/openwire/marshall/v2/	ConnectionInfoMarshaller.h	4359
src/main/activemq/wireformat/openwire/marshall/v2/	ConsumerControlMarshaller.h	4365
src/main/activemq/wireformat/openwire/marshall/v2/	ConsumerIdMarshaller.h	4371
src/main/activemq/wireformat/openwire/marshall/v2/	ConsumerInfoMarshaller.h	4377
src/main/activemq/wireformat/openwire/marshall/v2/	ControlCommandMarshaller.h	4383
src/main/activemq/wireformat/openwire/marshall/v2/	DataArrayResponseMarshaller.h	4389
src/main/activemq/wireformat/openwire/marshall/v2/	DataResponseMarshaller.h	4395
src/main/activemq/wireformat/openwire/marshall/v2/	DestinationInfoMarshaller.h	4401
src/main/activemq/wireformat/openwire/marshall/v2/	DiscoveryEventMarshaller.h	4407
src/main/activemq/wireformat/openwire/marshall/v2/	ExceptionResponseMarshaller.h	4413
src/main/activemq/wireformat/openwire/marshall/v2/	FlushCommandMarshaller.h	4419
src/main/activemq/wireformat/openwire/marshall/v2/	IntegerResponseMarshaller.h	4425
src/main/activemq/wireformat/openwire/marshall/v2/	JournalQueueAckMarshaller.h	4431
src/main/activemq/wireformat/openwire/marshall/v2/	JournalTopicAckMarshaller.h	4437
src/main/activemq/wireformat/openwire/marshall/v2/	JournalTraceMarshaller.h	4443
src/main/activemq/wireformat/openwire/marshall/v2/	JournalTransactionMarshaller.h	4449
src/main/activemq/wireformat/openwire/marshall/v2/	KeepAliveInfoMarshaller.h	4455
src/main/activemq/wireformat/openwire/marshall/v2/	LastPartialCommandMarshaller.h	4461
src/main/activemq/wireformat/openwire/marshall/v2/	LocalTransactionIdMarshaller.h	4467
src/main/activemq/wireformat/openwire/marshall/v2/	MarshallerFactory.h	4473
src/main/activemq/wireformat/openwire/marshall/v2/	MessageAckMarshaller.h	4479
src/main/activemq/wireformat/openwire/marshall/v2/	MessageDispatchMarshaller.h	4485
src/main/activemq/wireformat/openwire/marshall/v2/	MessageDispatchNotificationMarshaller.h	4491
src/main/activemq/wireformat/openwire/marshall/v2/	MessageIdMarshaller.h	4497
src/main/activemq/wireformat/openwire/marshall/v2/	MessageMarshaller.h	4503
src/main/activemq/wireformat/openwire/marshall/v2/	MessagePullMarshaller.h	4509
src/main/activemq/wireformat/openwire/marshall/v2/	NetworkBridgeFilterMarshaller.h	4515
src/main/activemq/wireformat/openwire/marshall/v2/	PartialCommandMarshaller.h	4521
src/main/activemq/wireformat/openwire/marshall/v2/	ProducerAckMarshaller.h	4527
src/main/activemq/wireformat/openwire/marshall/v2/	ProducerIdMarshaller.h	4533
src/main/activemq/wireformat/openwire/marshall/v2/	ProducerInfoMarshaller.h	4539
src/main/activemq/wireformat/openwire/marshall/v2/	RemoveInfoMarshaller.h	4545
src/main/activemq/wireformat/openwire/marshall/v2/	RemoveSubscriptionInfoMarshaller.h	4551
src/main/activemq/wireformat/openwire/marshall/v2/	ReplayCommandMarshaller.h	4557
src/main/activemq/wireformat/openwire/marshall/v2/	ResponseMarshaller.h	4563
src/main/activemq/wireformat/openwire/marshall/v2/	SessionIdMarshaller.h	4569
src/main/activemq/wireformat/openwire/marshall/v2/	SessionInfoMarshaller.h	4575
src/main/activemq/wireformat/openwire/marshall/v2/	ShutdownInfoMarshaller.h	4581

src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h	
4587	
src/main/activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h	4593
src/main/activemq/wireformat/openwire/marshal/v2/TransactionInfoMarshaller.h	4599
src/main/activemq/wireformat/openwire/marshal/v2/WireFormatInfoMarshaller.h	4605
src/main/activemq/wireformat/openwire/marshal/v2/XATransactionIdMarshaller.h	
4611	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBlobMessageMarshaller.h	
4246	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBytesMessageMarshaller.h	
4252	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h	
4258	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMapMessageMarshaller.h	
4264	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMessageMarshaller.h	
4270	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQObjectMessageMarshaller.h	
4276	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQQueueMarshaller.h	
4282	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQStreamMessageMarshaller.h	
4288	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h	
4294	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempQueueMarshaller.h	
4300	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempTopicMarshaller.h	
4306	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTextMessageMarshaller.h	
4312	
src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTopicMarshaller.h	4318
src/main/activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h	4324
src/main/activemq/wireformat/openwire/marshal/v3/BrokerIdMarshaller.h	4330
src/main/activemq/wireformat/openwire/marshal/v3/BrokerInfoMarshaller.h	4336
src/main/activemq/wireformat/openwire/marshal/v3/ConnectionControlMarshaller.h	
4342	
src/main/activemq/wireformat/openwire/marshal/v3/ConnectionErrorMarshaller.h	
4348	
src/main/activemq/wireformat/openwire/marshal/v3/ConnectionIdMarshaller.h	4354
src/main/activemq/wireformat/openwire/marshal/v3/ConnectionInfoMarshaller.h	4360
src/main/activemq/wireformat/openwire/marshal/v3/ConsumerControlMarshaller.h	
4366	
src/main/activemq/wireformat/openwire/marshal/v3/ConsumerIdMarshaller.h	4372
src/main/activemq/wireformat/openwire/marshal/v3/ConsumerInfoMarshaller.h	4378
src/main/activemq/wireformat/openwire/marshal/v3/ControlCommandMarshaller.h	
4384	
src/main/activemq/wireformat/openwire/marshal/v3/DataArrayResponseMarshaller.h	
4390	
src/main/activemq/wireformat/openwire/marshal/v3/DataResponseMarshaller.h	4396
src/main/activemq/wireformat/openwire/marshal/v3/DestinationInfoMarshaller.h	4402
src/main/activemq/wireformat/openwire/marshal/v3/DiscoveryEventMarshaller.h	4408
src/main/activemq/wireformat/openwire/marshal/v3/ExceptionResponseMarshaller.h	
4414	

src/main/activemq/wireformat/openwire/marshal/v3/FlushCommandMarshaller.h	4420
src/main/activemq/wireformat/openwire/marshal/v3/IntegerResponseMarshaller.h	4426
src/main/activemq/wireformat/openwire/marshal/v3/JournalQueueAckMarshaller.h	4432
src/main/activemq/wireformat/openwire/marshal/v3/JournalTopicAckMarshaller.h	4438
src/main/activemq/wireformat/openwire/marshal/v3/JournalTraceMarshaller.h	4444
src/main/activemq/wireformat/openwire/marshal/v3/JournalTransactionMarshaller.h	4450
src/main/activemq/wireformat/openwire/marshal/v3/KeepAliveInfoMarshaller.h	4456
src/main/activemq/wireformat/openwire/marshal/v3/LastPartialCommandMarshaller.h	4462
src/main/activemq/wireformat/openwire/marshal/v3/LocalTransactionIdMarshaller.h	4468
src/main/activemq/wireformat/openwire/marshal/v3/MarshallerFactory.h	4474
src/main/activemq/wireformat/openwire/marshal/v3/MessageAckMarshaller.h	4480
src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchMarshaller.h	4486
src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchNotificationMarshaller.h	4492
src/main/activemq/wireformat/openwire/marshal/v3/MessageIdMarshaller.h	4498
src/main/activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h	4504
src/main/activemq/wireformat/openwire/marshal/v3/MessagePullMarshaller.h	4510
src/main/activemq/wireformat/openwire/marshal/v3/NetworkBridgeFilterMarshaller.h	4516
src/main/activemq/wireformat/openwire/marshal/v3/PartialCommandMarshaller.h	4522
src/main/activemq/wireformat/openwire/marshal/v3/ProducerAckMarshaller.h	4528
src/main/activemq/wireformat/openwire/marshal/v3/ProducerIdMarshaller.h	4534
src/main/activemq/wireformat/openwire/marshal/v3/ProducerInfoMarshaller.h	4540
src/main/activemq/wireformat/openwire/marshal/v3/RemoveInfoMarshaller.h	4546
src/main/activemq/wireformat/openwire/marshal/v3/RemoveSubscriptionInfoMarshaller.h	4552
src/main/activemq/wireformat/openwire/marshal/v3/ReplayCommandMarshaller.h	4558
src/main/activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h	4564
src/main/activemq/wireformat/openwire/marshal/v3/SessionIdMarshaller.h	4570
src/main/activemq/wireformat/openwire/marshal/v3/SessionInfoMarshaller.h	4576
src/main/activemq/wireformat/openwire/marshal/v3/ShutdownInfoMarshaller.h	4582
src/main/activemq/wireformat/openwire/marshal/v3/SubscriptionInfoMarshaller.h	4588
src/main/activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h	4594
src/main/activemq/wireformat/openwire/marshal/v3/TransactionInfoMarshaller.h	4600
src/main/activemq/wireformat/openwire/marshal/v3/WireFormatInfoMarshaller.h	4606
src/main/activemq/wireformat/openwire/marshal/v3/XATransactionIdMarshaller.h	4612
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBlobMessageMarshaller.h	4247
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBytesMessageMarshaller.h	4253
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h	4259

src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMapMessageMarshaller.h	
4265	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMessageMarshaller.h	
4271	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQObjectMessageMarshaller.h	
4277	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h	
4283	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQStreamMessageMarshaller.h	
4289	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h	
4295	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempQueueMarshaller.h	
4301	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempTopicMarshaller.h	
4307	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTextMessageMarshaller.h	
4313	
src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTopicMarshaller.h	4319
src/main/activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h	4325
src/main/activemq/wireformat/openwire/marshal/v4/BrokerIdMarshaller.h	4331
src/main/activemq/wireformat/openwire/marshal/v4/BrokerInfoMarshaller.h	4337
src/main/activemq/wireformat/openwire/marshal/v4/ConnectionControlMarshaller.h	
4343	
src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h	
4349	
src/main/activemq/wireformat/openwire/marshal/v4/ConnectionIdMarshaller.h	4355
src/main/activemq/wireformat/openwire/marshal/v4/ConnectionInfoMarshaller.h	4361
src/main/activemq/wireformat/openwire/marshal/v4/ConsumerControlMarshaller.h	
4367	
src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h	4373
src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h	4379
src/main/activemq/wireformat/openwire/marshal/v4/ControlCommandMarshaller.h	
4385	
src/main/activemq/wireformat/openwire/marshal/v4/DataArrayResponseMarshaller.h	
4391	
src/main/activemq/wireformat/openwire/marshal/v4/DataResponseMarshaller.h	4397
src/main/activemq/wireformat/openwire/marshal/v4/DestinationInfoMarshaller.h	4403
src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryEventMarshaller.h	4409
src/main/activemq/wireformat/openwire/marshal/v4/ExceptionResponseMarshaller.h	
4415	
src/main/activemq/wireformat/openwire/marshal/v4/FlushCommandMarshaller.h	4421
src/main/activemq/wireformat/openwire/marshal/v4/IntegerResponseMarshaller.h	
4427	
src/main/activemq/wireformat/openwire/marshal/v4/JournalQueueAckMarshaller.h	
4433	
src/main/activemq/wireformat/openwire/marshal/v4/JournalTopicAckMarshaller.h	
4439	
src/main/activemq/wireformat/openwire/marshal/v4/JournalTraceMarshaller.h	4445
src/main/activemq/wireformat/openwire/marshal/v4/JournalTransactionMarshaller.h	
4451	
src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h	4457
src/main/activemq/wireformat/openwire/marshal/v4/LastPartialCommandMarshaller.h	
4463	

src/main/activemq/wireformat/openwire/marshall/v4/LocalTransactionIdMarshaller.h	
4469	
src/main/activemq/wireformat/openwire/marshall/v4/MarshallerFactory.h	4475
src/main/activemq/wireformat/openwire/marshall/v4/MessageAckMarshaller.h . .	4481
src/main/activemq/wireformat/openwire/marshall/v4/MessageDispatchMarshaller.h	
4487	
src/main/activemq/wireformat/openwire/marshall/v4/MessageDispatchNotificationMarshaller.h	
4493	
src/main/activemq/wireformat/openwire/marshall/v4/MessageIdMarshaller.h . . .	4499
src/main/activemq/wireformat/openwire/marshall/v4/MessageMarshaller.h	4505
src/main/activemq/wireformat/openwire/marshall/v4/MessagePullMarshaller.h . .	4511
src/main/activemq/wireformat/openwire/marshall/v4/NetworkBridgeFilterMarshaller.h	
4517	
src/main/activemq/wireformat/openwire/marshall/v4/PartialCommandMarshaller.h	
4523	
src/main/activemq/wireformat/openwire/marshall/v4/ProducerAckMarshaller.h . .	4529
src/main/activemq/wireformat/openwire/marshall/v4/ProducerIdMarshaller.h . . .	4535
src/main/activemq/wireformat/openwire/marshall/v4/ProducerInfoMarshaller.h . .	4541
src/main/activemq/wireformat/openwire/marshall/v4/RemoveInfoMarshaller.h . .	4547
src/main/activemq/wireformat/openwire/marshall/v4/RemoveSubscriptionInfoMarshaller.h	
4553	
src/main/activemq/wireformat/openwire/marshall/v4/ReplayCommandMarshaller.h	
4559	
src/main/activemq/wireformat/openwire/marshall/v4/ResponseMarshaller.h	4565
src/main/activemq/wireformat/openwire/marshall/v4/SessionIdMarshaller.h	4571
src/main/activemq/wireformat/openwire/marshall/v4/SessionInfoMarshaller.h . . .	4577
src/main/activemq/wireformat/openwire/marshall/v4/ShutdownInfoMarshaller.h .	4583
src/main/activemq/wireformat/openwire/marshall/v4/SubscriptionInfoMarshaller.h	
4589	
src/main/activemq/wireformat/openwire/marshall/v4/TransactionIdMarshaller.h .	4595
src/main/activemq/wireformat/openwire/marshall/v4/TransactionInfoMarshaller.h	4601
src/main/activemq/wireformat/openwire/marshall/v4/WireFormatInfoMarshaller.h	4607
src/main/activemq/wireformat/openwire/marshall/v4/XATransactionIdMarshaller.h	
4613	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQBlobMessageMarshaller.h	
4248	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQBytesMessageMarshaller.h	
4254	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQDestinationMarshaller.h	
4260	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQMapMessageMarshaller.h	
4266	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQMessageMarshaller.h	
4272	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQObjectMessageMarshaller.h	
4278	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQQueueMarshaller.h	
4284	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQStreamMessageMarshaller.h	
4290	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQTempDestinationMarshaller.h	
4296	
src/main/activemq/wireformat/openwire/marshall/v5/ActiveMQTempQueueMarshaller.h	
4302	

src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempTopicMarshaller.h	
4308	
src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTextMessageMarshaller.h	
4314	
src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTopicMarshaller.h	4320
src/main/activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h	4326
src/main/activemq/wireformat/openwire/marshal/v5/BrokerIdMarshaller.h . . .	4332
src/main/activemq/wireformat/openwire/marshal/v5/BrokerInfoMarshaller.h . . .	4338
src/main/activemq/wireformat/openwire/marshal/v5/ConnectionControlMarshaller.h	
4344	
src/main/activemq/wireformat/openwire/marshal/v5/ConnectionErrorMarshaller.h	
4350	
src/main/activemq/wireformat/openwire/marshal/v5/ConnectionIdMarshaller.h .	4356
src/main/activemq/wireformat/openwire/marshal/v5/ConnectionInfoMarshaller.h	4362
src/main/activemq/wireformat/openwire/marshal/v5/ConsumerControlMarshaller.h	
4368	
src/main/activemq/wireformat/openwire/marshal/v5/ConsumerIdMarshaller.h . .	4374
src/main/activemq/wireformat/openwire/marshal/v5/ConsumerInfoMarshaller.h .	4380
src/main/activemq/wireformat/openwire/marshal/v5/ControlCommandMarshaller.h	
4386	
src/main/activemq/wireformat/openwire/marshal/v5/DataArrayResponseMarshaller.h	
4392	
src/main/activemq/wireformat/openwire/marshal/v5/DataResponseMarshaller.h .	4398
src/main/activemq/wireformat/openwire/marshal/v5/DestinationInfoMarshaller.h	4404
src/main/activemq/wireformat/openwire/marshal/v5/DiscoveryEventMarshaller.h	4410
src/main/activemq/wireformat/openwire/marshal/v5/ExceptionResponseMarshaller.h	
4416	
src/main/activemq/wireformat/openwire/marshal/v5/FlushCommandMarshaller.h	4422
src/main/activemq/wireformat/openwire/marshal/v5/IntegerResponseMarshaller.h	
4428	
src/main/activemq/wireformat/openwire/marshal/v5/JournalQueueAckMarshaller.h	
4434	
src/main/activemq/wireformat/openwire/marshal/v5/JournalTopicAckMarshaller.h	
4440	
src/main/activemq/wireformat/openwire/marshal/v5/JournalTraceMarshaller.h . .	4446
src/main/activemq/wireformat/openwire/marshal/v5/JournalTransactionMarshaller.h	
4452	
src/main/activemq/wireformat/openwire/marshal/v5/KeepAliveInfoMarshaller.h .	4458
src/main/activemq/wireformat/openwire/marshal/v5/LastPartialCommandMarshaller.h	
4464	
src/main/activemq/wireformat/openwire/marshal/v5/LocalTransactionIdMarshaller.h	
4470	
src/main/activemq/wireformat/openwire/marshal/v5/MarshallerFactory.h	4476
src/main/activemq/wireformat/openwire/marshal/v5/MessageAckMarshaller.h . .	4482
src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchMarshaller.h	
4488	
src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchNotificationMarshaller.h	
4494	
src/main/activemq/wireformat/openwire/marshal/v5/MessageIdMarshaller.h . . .	4500
src/main/activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h	4506
src/main/activemq/wireformat/openwire/marshal/v5/MessagePullMarshaller.h . .	4512
src/main/activemq/wireformat/openwire/marshal/v5/NetworkBridgeFilterMarshaller.h	
4518	

src/main/activemq/wireformat/openwire/marshall/v5/PartialCommandMarshaller.h	
4524	
src/main/activemq/wireformat/openwire/marshall/v5/ProducerAckMarshaller.h . .	4530
src/main/activemq/wireformat/openwire/marshall/v5/ProducerIdMarshaller.h . . .	4536
src/main/activemq/wireformat/openwire/marshall/v5/ProducerInfoMarshaller.h . .	4542
src/main/activemq/wireformat/openwire/marshall/v5/RemoveInfoMarshaller.h . .	4548
src/main/activemq/wireformat/openwire/marshall/v5/RemoveSubscriptionInfoMarshaller.h	
4554	
src/main/activemq/wireformat/openwire/marshall/v5/ReplayCommandMarshaller.h	
4560	
src/main/activemq/wireformat/openwire/marshall/v5/ResponseMarshaller.h	4566
src/main/activemq/wireformat/openwire/marshall/v5/SessionIdMarshaller.h	4572
src/main/activemq/wireformat/openwire/marshall/v5/SessionInfoMarshaller.h . . .	4578
src/main/activemq/wireformat/openwire/marshall/v5/ShutdownInfoMarshaller.h .	4584
src/main/activemq/wireformat/openwire/marshall/v5/SubscriptionInfoMarshaller.h	
4590	
src/main/activemq/wireformat/openwire/marshall/v5/TransactionIdMarshaller.h .	4596
src/main/activemq/wireformat/openwire/marshall/v5/TransactionInfoMarshaller.h	4602
src/main/activemq/wireformat/openwire/marshall/v5/WireFormatInfoMarshaller.h	4608
src/main/activemq/wireformat/openwire/marshall/v5/XATransactionIdMarshaller.h	
4614	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQBlobMessageMarshaller.h	
4249	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQBytesMessageMarshaller.h	
4255	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQDestinationMarshaller.h	
4261	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQMapMessageMarshaller.h	
4267	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQMessageMarshaller.h	
4273	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQObjectMessageMarshaller.h	
4279	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQQueueMarshaller.h	
4285	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQStreamMessageMarshaller.h	
4291	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQTempDestinationMarshaller.h	
4297	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQTempQueueMarshaller.h	
4303	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQTempTopicMarshaller.h	
4309	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQTextMessageMarshaller.h	
4315	
src/main/activemq/wireformat/openwire/marshall/v6/ActiveMQTopicMarshaller.h	4321
src/main/activemq/wireformat/openwire/marshall/v6/BaseCommandMarshaller.h	4327
src/main/activemq/wireformat/openwire/marshall/v6/BrokerIdMarshaller.h	4333
src/main/activemq/wireformat/openwire/marshall/v6/BrokerInfoMarshaller.h . . .	4339
src/main/activemq/wireformat/openwire/marshall/v6/ConnectionControlMarshaller.h	
4345	
src/main/activemq/wireformat/openwire/marshall/v6/ConnectionErrorMarshaller.h	
4351	
src/main/activemq/wireformat/openwire/marshall/v6/ConnectionIdMarshaller.h .	4357

src/main/activemq/wireformat/openwire/marshal/v6/	ConnectionInfoMarshaller.h	4363
src/main/activemq/wireformat/openwire/marshal/v6/	ConsumerControlMarshaller.h	4369
src/main/activemq/wireformat/openwire/marshal/v6/	ConsumerIdMarshaller.h	4375
src/main/activemq/wireformat/openwire/marshal/v6/	ConsumerInfoMarshaller.h	4381
src/main/activemq/wireformat/openwire/marshal/v6/	ControlCommandMarshaller.h	4387
src/main/activemq/wireformat/openwire/marshal/v6/	DataArrayResponseMarshaller.h	4393
src/main/activemq/wireformat/openwire/marshal/v6/	DataResponseMarshaller.h	4399
src/main/activemq/wireformat/openwire/marshal/v6/	DestinationInfoMarshaller.h	4405
src/main/activemq/wireformat/openwire/marshal/v6/	DiscoveryEventMarshaller.h	4411
src/main/activemq/wireformat/openwire/marshal/v6/	ExceptionResponseMarshaller.h	4417
src/main/activemq/wireformat/openwire/marshal/v6/	FlushCommandMarshaller.h	4423
src/main/activemq/wireformat/openwire/marshal/v6/	IntegerResponseMarshaller.h	4429
src/main/activemq/wireformat/openwire/marshal/v6/	JournalQueueAckMarshaller.h	4435
src/main/activemq/wireformat/openwire/marshal/v6/	JournalTopicAckMarshaller.h	4441
src/main/activemq/wireformat/openwire/marshal/v6/	JournalTraceMarshaller.h	4447
src/main/activemq/wireformat/openwire/marshal/v6/	JournalTransactionMarshaller.h	4453
src/main/activemq/wireformat/openwire/marshal/v6/	KeepAliveInfoMarshaller.h	4459
src/main/activemq/wireformat/openwire/marshal/v6/	LastPartialCommandMarshaller.h	4465
src/main/activemq/wireformat/openwire/marshal/v6/	LocalTransactionIdMarshaller.h	4471
src/main/activemq/wireformat/openwire/marshal/v6/	MarshallerFactory.h	4477
src/main/activemq/wireformat/openwire/marshal/v6/	MessageAckMarshaller.h	4483
src/main/activemq/wireformat/openwire/marshal/v6/	MessageDispatchMarshaller.h	4489
src/main/activemq/wireformat/openwire/marshal/v6/	MessageDispatchNotificationMarshaller.h	4495
src/main/activemq/wireformat/openwire/marshal/v6/	MessageIdMarshaller.h	4501
src/main/activemq/wireformat/openwire/marshal/v6/	MessageMarshaller.h	4507
src/main/activemq/wireformat/openwire/marshal/v6/	MessagePullMarshaller.h	4513
src/main/activemq/wireformat/openwire/marshal/v6/	NetworkBridgeFilterMarshaller.h	4519
src/main/activemq/wireformat/openwire/marshal/v6/	PartialCommandMarshaller.h	4525
src/main/activemq/wireformat/openwire/marshal/v6/	ProducerAckMarshaller.h	4531
src/main/activemq/wireformat/openwire/marshal/v6/	ProducerIdMarshaller.h	4537
src/main/activemq/wireformat/openwire/marshal/v6/	ProducerInfoMarshaller.h	4543
src/main/activemq/wireformat/openwire/marshal/v6/	RemoveInfoMarshaller.h	4549
src/main/activemq/wireformat/openwire/marshal/v6/	RemoveSubscriptionInfoMarshaller.h	4555
src/main/activemq/wireformat/openwire/marshal/v6/	ReplayCommandMarshaller.h	4561
src/main/activemq/wireformat/openwire/marshal/v6/	ResponseMarshaller.h	4567
src/main/activemq/wireformat/openwire/marshal/v6/	SessionIdMarshaller.h	4573
src/main/activemq/wireformat/openwire/marshal/v6/	SessionInfoMarshaller.h	4579
src/main/activemq/wireformat/openwire/marshal/v6/	ShutdownInfoMarshaller.h	4585

src/main/activemq/wireformat/openwire/marshall/v6/SubscriptionInfoMarshaller.h	
4591	
src/main/activemq/wireformat/openwire/marshall/v6/TransactionIdMarshaller.h	4597
src/main/activemq/wireformat/openwire/marshall/v6/TransactionInfoMarshaller.h	4603
src/main/activemq/wireformat/openwire/marshall/v6/WireFormatInfoMarshaller.h	4609
src/main/activemq/wireformat/openwire/marshall/v6/XATransactionIdMarshaller.h	4615
src/main/activemq/wireformat/openwire/utils/BooleanStream.h	4620
src/main/activemq/wireformat/openwire/utils/HexTable.h	4621
src/main/activemq/wireformat/openwire/utils/MessagePropertyInterceptor.h	4622
src/main/activemq/wireformat/stomp/StompCommandConstants.h	4623
src/main/activemq/wireformat/stomp/StompFrame.h	4624
src/main/activemq/wireformat/stomp/StompHelper.h	4625
src/main/activemq/wireformat/stomp/StompWireFormat.h	4626
src/main/activemq/wireformat/stomp/StompWireFormatFactory.h	4627
src/main/cms/BytesMessage.h	4632
src/main/cms/Closeable.h	4633
src/main/cms/CMSException.h	4635
src/main/cms/CMSProperties.h	4636
src/main/cms/CMSSecurityException.h	4637
src/main/cms/Config.h	4228
src/main/cms/Connection.h	4638
src/main/cms/ConnectionFactory.h	4639
src/main/cms/ConnectionMetaData.h	4640
src/main/cms/DeliveryMode.h	4641
src/main/cms/Destination.h	4642
src/main/cms/ExceptionListener.h	4643
src/main/cms/IllegalStateException.h	4644
src/main/cms/InvalidClientIdException.h	4646
src/main/cms/InvalidDestinationException.h	4647
src/main/cms/InvalidSelectorException.h	4648
src/main/cms/MapMessage.h	4649
src/main/cms/Message.h	4126
src/main/cms/MessageConsumer.h	4650
src/main/cms/MessageEnumeration.h	4651
src/main/cms/MessageEOFException.h	4652
src/main/cms/MessageFormatException.h	4653
src/main/cms/MessageListener.h	4654
src/main/cms/MessageNotReadableException.h	4655
src/main/cms/MessageNotWriteableException.h	4656
src/main/cms/MessageProducer.h	4657
src/main/cms/ObjectMessage.h	4658
src/main/cms/Queue.h	4659
src/main/cms/QueueBrowser.h	4661
src/main/cms/Session.h	4662
src/main/cms/Startable.h	4663
src/main/cms/Stopable.h	4664
src/main/cms/StreamMessage.h	4665
src/main/cms/TemporaryQueue.h	4666
src/main/cms/TemporaryTopic.h	4667
src/main/cms/TextMessage.h	4668
src/main/cms/Topic.h	4669
src/main/cms/UnsupportedOperationException.h	4670
src/main/decaf/internal/AprPool.h	4672

src/main/decaf/internal/ DecafRuntime.h	4673
src/main/decaf/internal/io/ StandardErrorOutputStream.h	4674
src/main/decaf/internal/io/ StandardInputStream.h	4675
src/main/decaf/internal/io/ StandardOutputStream.h	4676
src/main/decaf/internal/net/ DefaultServerSocketFactory.h	4677
src/main/decaf/internal/net/ DefaultSocketFactory.h	4678
src/main/decaf/internal/net/ Network.h	4679
src/main/decaf/internal/net/ SocketFileDescriptor.h	4680
src/main/decaf/internal/net/ URIEncoderDecoder.h	4696
src/main/decaf/internal/net/ URIHelper.h	4697
src/main/decaf/internal/net/ URIType.h	4698
src/main/decaf/internal/net/ssl/ DefaultSSLContext.h	4681
src/main/decaf/internal/net/ssl/ DefaultSSLServerSocketFactory.h	4682
src/main/decaf/internal/net/ssl/ DefaultSSLSocketFactory.h	4683
src/main/decaf/internal/net/ssl/openssl/ OpenSSLContextSpi.h	4684
src/main/decaf/internal/net/ssl/openssl/ OpenSSLParameters.h	4685
src/main/decaf/internal/net/ssl/openssl/ OpenSSLServerSocket.h	4686
src/main/decaf/internal/net/ssl/openssl/ OpenSSLServerSocketFactory.h	4687
src/main/decaf/internal/net/ssl/openssl/ OpenSSLSocket.h	4688
src/main/decaf/internal/net/ssl/openssl/ OpenSSLSocketException.h	4689
src/main/decaf/internal/net/ssl/openssl/ OpenSSLSocketFactory.h	4690
src/main/decaf/internal/net/ssl/openssl/ OpenSSLSocketInputStream.h	4691
src/main/decaf/internal/net/ssl/openssl/ OpenSSLSocketOutputStream.h	4692
src/main/decaf/internal/net/tcp/ TcpSocket.h	4693
src/main/decaf/internal/net/tcp/ TcpSocketInputStream.h	4694
src/main/decaf/internal/net/tcp/ TcpSocketOutputStream.h	4695
src/main/decaf/internal/nio/ BufferFactory.h	4699
src/main/decaf/internal/nio/ ByteBuffer.h	4700
src/main/decaf/internal/nio/ CharArrayBuffer.h	4701
src/main/decaf/internal/nio/ DoubleArrayBuffer.h	4702
src/main/decaf/internal/nio/ FloatArrayBuffer.h	4703
src/main/decaf/internal/nio/ IntArrayBuffer.h	4704
src/main/decaf/internal/nio/ LongArrayBuffer.h	4705
src/main/decaf/internal/nio/ ShortArrayBuffer.h	4706
src/main/decaf/internal/security/unix/ SecureRandomImpl.h	4707
src/main/decaf/internal/security/windows/ SecureRandomImpl.h	4708
src/main/decaf/internal/util/ ByteArrayAdapter.h	4709
src/main/decaf/internal/util/ GenericResource.h	4720
src/main/decaf/internal/util/ HexStringParser.h	4721
src/main/decaf/internal/util/ Resource.h	4722
src/main/decaf/internal/util/ ResourceLifecycleManager.h	4078
src/main/decaf/internal/util/ TimerTaskHeap.h	4723
src/main/decaf/internal/util/concurrent/ ConditionImpl.h	4710
src/main/decaf/internal/util/concurrent/ MutexImpl.h	4711
src/main/decaf/internal/util/concurrent/ SynchronizableImpl.h	4712
src/main/decaf/internal/util/concurrent/ Transferer.h	4713
src/main/decaf/internal/util/concurrent/ TransferQueue.h	4714
src/main/decaf/internal/util/concurrent/ TransferStack.h	4715
src/main/decaf/internal/util/concurrent/unix/ ConditionHandle.h	4716
src/main/decaf/internal/util/concurrent/unix/ MutexHandle.h	4718
src/main/decaf/internal/util/concurrent/windows/ ConditionHandle.h	4717
src/main/decaf/internal/util/concurrent/windows/ MutexHandle.h	4719
src/main/decaf/internal/util/zip/ crc32.h	4724
src/main/decaf/internal/util/zip/ deflate.h	4725

src/main/decaf/internal/util/zip/gzguts.h	4728
src/main/decaf/internal/util/zip/inffast.h	4730
src/main/decaf/internal/util/zip/inffixed.h	4731
src/main/decaf/internal/util/zip/inflate.h	4732
src/main/decaf/internal/util/zip/inftrees.h	4734
src/main/decaf/internal/util/zip/trees.h	4735
src/main/decaf/internal/util/zip/zconf.h	4737
src/main/decaf/internal/util/zip/zlib.h	4739
src/main/decaf/internal/util/zip/zutil.h	4743
src/main/decaf/io/BlockingByteArrayInputStream.h	4746
src/main/decaf/io/BufferedInputStream.h	4747
src/main/decaf/io/BufferedOutputStream.h	4748
src/main/decaf/io/ByteArrayInputStream.h	4749
src/main/decaf/io/ByteArrayOutputStream.h	4750
src/main/decaf/io/Closeable.h	4634
src/main/decaf/io/DataInput.h	4751
src/main/decaf/io/DataInputStream.h	4752
src/main/decaf/io/DataOutput.h	4753
src/main/decaf/io/DataOutputStream.h	4754
src/main/decaf/io/EOFException.h	4755
src/main/decaf/io/FileDescriptor.h	4756
src/main/decaf/io/FilterInputStream.h	4757
src/main/decaf/io/FilterOutputStream.h	4758
src/main/decaf/io/Flushable.h	4759
src/main/decaf/io/InputStream.h	4760
src/main/decaf/io/InputStreamReader.h	4761
src/main/decaf/io/InterruptedIOException.h	4762
src/main/decaf/io/IOException.h	4763
src/main/decaf/io/OutputStream.h	4764
src/main/decaf/io/OutputStreamWriter.h	4765
src/main/decaf/io/PushbackInputStream.h	4766
src/main/decaf/io/Reader.h	4767
src/main/decaf/io/UnsupportedEncodingException.h	4768
src/main/decaf/io/UTFDataFormatException.h	4769
src/main/decaf/io/Writer.h	4770
src/main/decaf/lang/Appendable.h	4771
src/main/decaf/lang/ArrayPointer.h	4772
src/main/decaf/lang/Boolean.h	4774
src/main/decaf/lang/Byte.h	4775
src/main/decaf/lang/Character.h	4776
src/main/decaf/lang/CharSequence.h	4777
src/main/decaf/lang/Comparable.h	4778
src/main/decaf/lang/Double.h	4779
src/main/decaf/lang/Exception.h	4780
src/main/decaf/lang/Float.h	4792
src/main/decaf/lang/Integer.h	4793
src/main/decaf/lang/Iterable.h	4794
src/main/decaf/lang/Long.h	4795
src/main/decaf/lang/Math.h	4796
src/main/decaf/lang/Number.h	4797
src/main/decaf/lang/Pointer.h	4798
src/main/decaf/lang/Readable.h	4799
src/main/decaf/lang/Runnable.h	4800
src/main/decaf/lang/Runtime.h	4801

src/main/decaf/lang/ Short.h	4802
src/main/decaf/lang/ String.h	4803
src/main/decaf/lang/ System.h	4804
src/main/decaf/lang/ Thread.h	4805
src/main/decaf/lang/ ThreadGroup.h	4806
src/main/decaf/lang/ Throwable.h	4807
src/main/decaf/lang/exceptions/ ClassCastException.h	4781
src/main/decaf/lang/exceptions/ ExceptionDefines.h	4173
src/main/decaf/lang/exceptions/ IllegalArgumentException.h	4782
src/main/decaf/lang/exceptions/ IllegalMonitorStateException.h	4783
src/main/decaf/lang/exceptions/ IllegalStateException.h	4645
src/main/decaf/lang/exceptions/ IllegalThreadStateException.h	4784
src/main/decaf/lang/exceptions/ IndexOutOfBoundsException.h	4785
src/main/decaf/lang/exceptions/ InterruptedException.h	4786
src/main/decaf/lang/exceptions/ InvalidStateException.h	4787
src/main/decaf/lang/exceptions/ NoSuchElementException.h	4788
src/main/decaf/lang/exceptions/ NullPointerException.h	4789
src/main/decaf/lang/exceptions/ NumberFormatException.h	4790
src/main/decaf/lang/exceptions/ RuntimeException.h	4791
src/main/decaf/lang/exceptions/ UnsupportedOperationException.h	4671
src/main/decaf/net/ BindException.h	4808
src/main/decaf/net/ ConnectException.h	4809
src/main/decaf/net/ HttpRetryException.h	4810
src/main/decaf/net/ Inet4Address.h	4811
src/main/decaf/net/ Inet6Address.h	4812
src/main/decaf/net/ InetAddress.h	4813
src/main/decaf/net/ InetSocketAddress.h	4814
src/main/decaf/net/ MalformedURLException.h	4815
src/main/decaf/net/ NoRouteToHostException.h	4816
src/main/decaf/net/ PortUnreachableException.h	4817
src/main/decaf/net/ ProtocolException.h	4818
src/main/decaf/net/ ServerSocket.h	4819
src/main/decaf/net/ ServerSocketFactory.h	4820
src/main/decaf/net/ Socket.h	4821
src/main/decaf/net/ SocketAddress.h	4822
src/main/decaf/net/ SocketError.h	4823
src/main/decaf/net/ SocketException.h	4824
src/main/decaf/net/ SocketFactory.h	4825
src/main/decaf/net/ SocketImpl.h	4826
src/main/decaf/net/ SocketImplFactory.h	4827
src/main/decaf/net/ SocketOptions.h	4828
src/main/decaf/net/ SocketTimeoutException.h	4829
src/main/decaf/net/ UnknownHostException.h	4837
src/main/decaf/net/ UnknownServiceException.h	4838
src/main/decaf/net/ URI.h	4839
src/main/decaf/net/ URISyntaxException.h	4840
src/main/decaf/net/ URL.h	4841
src/main/decaf/net/ URLDecoder.h	4842
src/main/decaf/net/ URLEncoder.h	4843
src/main/decaf/net/ssl/ SSLContext.h	4830
src/main/decaf/net/ssl/ SSLContextSpi.h	4831
src/main/decaf/net/ssl/ SSLParameters.h	4832
src/main/decaf/net/ssl/ SSLServerSocket.h	4833
src/main/decaf/net/ssl/ SSLServerSocketFactory.h	4834

src/main/decaf/net/ssl/SSLSocket.h	4835
src/main/decaf/net/ssl/SSLSocketFactory.h	4836
src/main/decaf/nio/Buffer.h	4844
src/main/decaf/nio/BufferOverflowException.h	4845
src/main/decaf/nio/BufferUnderflowException.h	4846
src/main/decaf/nio/ByteBuffer.h	4847
src/main/decaf/nio/CharBuffer.h	4848
src/main/decaf/nio/DoubleBuffer.h	4849
src/main/decaf/nio/FloatBuffer.h	4850
src/main/decaf/nio/IntBuffer.h	4851
src/main/decaf/nio/InvalidMarkException.h	4852
src/main/decaf/nio/LongBuffer.h	4853
src/main/decaf/nio/ReadOnlyBufferException.h	4854
src/main/decaf/nio/ShortBuffer.h	4855
src/main/decaf/security/GeneralSecurityException.h	4864
src/main/decaf/security/InvalidKeyException.h	4865
src/main/decaf/security/Key.h	4866
src/main/decaf/security/KeyException.h	4867
src/main/decaf/security/KeyManagementException.h	4868
src/main/decaf/security/NoSuchAlgorithmException.h	4869
src/main/decaf/security/NoSuchProviderException.h	4870
src/main/decaf/security/Principal.h	4871
src/main/decaf/security/PublicKey.h	4872
src/main/decaf/security/SecureRandom.h	4873
src/main/decaf/security/SecureRandomSpi.h	4874
src/main/decaf/security/SignatureException.h	4875
src/main/decaf/security/auth/x500/X500Principal.h	4856
src/main/decaf/security/cert/Certificate.h	4857
src/main/decaf/security/cert/CertificateEncodingException.h	4858
src/main/decaf/security/cert/CertificateException.h	4859
src/main/decaf/security/cert/CertificateExpiredException.h	4860
src/main/decaf/security/cert/CertificateNotYetValidException.h	4861
src/main/decaf/security/cert/CertificateParsingException.h	4862
src/main/decaf/security/cert/X509Certificate.h	4863
src/main/decaf/util/AbstractCollection.h	4876
src/main/decaf/util/AbstractList.h	4877
src/main/decaf/util/AbstractMap.h	4878
src/main/decaf/util/AbstractQueue.h	4879
src/main/decaf/util/AbstractSequentialList.h	4880
src/main/decaf/util/AbstractSet.h	4881
src/main/decaf/util/Collection.h	4882
src/main/decaf/util/Comparator.h	4883
src/main/decaf/util/Config.h	4229
src/main/decaf/util/Date.h	4921
src/main/decaf/util/Iterator.h	4922
src/main/decaf/util/List.h	4923
src/main/decaf/util/ListIterator.h	4924
src/main/decaf/util/Map.h	4945
src/main/decaf/util/PriorityQueue.h	4946
src/main/decaf/util/Properties.h	4947
src/main/decaf/util/Queue.h	4660
src/main/decaf/util/Random.h	4948
src/main/decaf/util/Set.h	4949
src/main/decaf/util/StlList.h	4950

src/main/decaf/util/ StlMap.h	4951
src/main/decaf/util/ StlQueue.h	4952
src/main/decaf/util/ StlSet.h	4953
src/main/decaf/util/ StringTokenizer.h	4954
src/main/decaf/util/ Timer.h	4955
src/main/decaf/util/ TimerTask.h	4956
src/main/decaf/util/ UUID.h	4957
src/main/decaf/util/comparators/ Less.h	4884
src/main/decaf/util/concurrent/ BlockingQueue.h	4889
src/main/decaf/util/concurrent/ BrokenBarrierException.h	4890
src/main/decaf/util/concurrent/ Callable.h	4891
src/main/decaf/util/concurrent/ CancellationException.h	4892
src/main/decaf/util/concurrent/ Concurrent.h	4893
src/main/decaf/util/concurrent/ ConcurrentMap.h	4894
src/main/decaf/util/concurrent/ ConcurrentStlMap.h	4895
src/main/decaf/util/concurrent/ CountDownLatch.h	4896
src/main/decaf/util/concurrent/ Delayed.h	4897
src/main/decaf/util/concurrent/ ExecutionException.h	4898
src/main/decaf/util/concurrent/ Executor.h	4899
src/main/decaf/util/concurrent/ ExecutorService.h	4900
src/main/decaf/util/concurrent/ Future.h	4901
src/main/decaf/util/concurrent/ Lock.h	4902
src/main/decaf/util/concurrent/ Mutex.h	4908
src/main/decaf/util/concurrent/ PooledThread.h	4909
src/main/decaf/util/concurrent/ PooledThreadListener.h	4910
src/main/decaf/util/concurrent/ RejectedExecutionException.h	4911
src/main/decaf/util/concurrent/ RejectedExecutionHandler.h	4912
src/main/decaf/util/concurrent/ Semaphore.h	4913
src/main/decaf/util/concurrent/ Synchronizable.h	4914
src/main/decaf/util/concurrent/ SynchronousQueue.h	4915
src/main/decaf/util/concurrent/ TaskListener.h	4916
src/main/decaf/util/concurrent/ ThreadFactory.h	4917
src/main/decaf/util/concurrent/ ThreadPool.h	4918
src/main/decaf/util/concurrent/ TimeoutException.h	4919
src/main/decaf/util/concurrent/ TimeUnit.h	4920
src/main/decaf/util/concurrent/atomic/ AtomicBoolean.h	4885
src/main/decaf/util/concurrent/atomic/ AtomicInteger.h	4886
src/main/decaf/util/concurrent/atomic/ AtomicReferenceCounter.h	4887
src/main/decaf/util/concurrent/atomic/ AtomicReference.h	4888
src/main/decaf/util/concurrent/locks/ Condition.h	4904
src/main/decaf/util/concurrent/locks/ Lock.h	4903
src/main/decaf/util/concurrent/locks/ LockSupport.h	4905
src/main/decaf/util/concurrent/locks/ ReadWriteLock.h	4906
src/main/decaf/util/concurrent/locks/ ReentrantLock.h	4907
src/main/decaf/util/logging/ ConsoleHandler.h	4925
src/main/decaf/util/logging/ ErrorManager.h	4926
src/main/decaf/util/logging/ Filter.h	4927
src/main/decaf/util/logging/ Formatter.h	4928
src/main/decaf/util/logging/ Handler.h	4929
src/main/decaf/util/logging/ Level.h	4930
src/main/decaf/util/logging/ Logger.h	4931
src/main/decaf/util/logging/ LoggerCommon.h	4932
src/main/decaf/util/logging/ LoggerDefines.h	4933
src/main/decaf/util/logging/ LoggerHierarchy.h	4935

src/main/decaf/util/logging/ LogManager.h	4936
src/main/decaf/util/logging/ LogRecord.h	4937
src/main/decaf/util/logging/ LogWriter.h	4938
src/main/decaf/util/logging/ MarkBlockLogger.h	4939
src/main/decaf/util/logging/ PropertiesChangeListener.h	4940
src/main/decaf/util/logging/ SimpleFormatter.h	4941
src/main/decaf/util/logging/ SimpleLogger.h	4942
src/main/decaf/util/logging/ StreamHandler.h	4943
src/main/decaf/util/logging/ XMLFormatter.h	4944
src/main/decaf/util/zip/ Adler32.h	4958
src/main/decaf/util/zip/ CheckedInputStream.h	4959
src/main/decaf/util/zip/ CheckedOutputStream.h	4960
src/main/decaf/util/zip/ Checksum.h	4961
src/main/decaf/util/zip/ CRC32.h	4962
src/main/decaf/util/zip/ DataFormatException.h	4963
src/main/decaf/util/zip/ Deflater.h	4964
src/main/decaf/util/zip/ DeflaterOutputStream.h	4965
src/main/decaf/util/zip/ Inflater.h	4966
src/main/decaf/util/zip/ InflaterInputStream.h	4967
src/main/decaf/util/zip/ ZipException.h	4968

Chapter 5

Namespace Documentation

5.1 activemq Namespace Reference

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

Namespaces

- namespace **cmsutil**
- namespace **commands**
- namespace **core**
- namespace **exceptions**
- namespace **io**
- namespace **library**
- namespace **state**
- namespace **threads**
- namespace **transport**
- namespace **util**
- namespace **wireformat**

5.1.1 Detailed Description

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements. See the NOTICE file distributed with this work for additional information regarding copyright ownership. The ASF licenses this file to You under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

5.2 activemq::cmsutil Namespace Reference

Data Structures

- class **CachedConsumer**
A cached message consumer contained within a pooled session.
- class **CachedProducer**
A cached message producer contained within a pooled session.
- class **CmsAccessor**
Base class for `activemq.cmsutil.CmsTemplate` (p. 1170) and other CMS-accessing gateway helpers, defining common properties such as the CMS `cms.ConnectionFactory` (p. 1324) to operate on.
- class **CmsDestinationAccessor**
Extends the `CmsAccessor` (p. 1153) to add support for resolving destination names.
- class **CmsTemplate**
`CmsTemplate` (p. 1170) simplifies performing synchronous CMS operations.
- class **DestinationResolver**
Resolves a CMS destination name to a `Destination`.
- class **DynamicDestinationResolver**
Resolves a CMS destination name to a `Destination`.
- class **MessageCreator**
Creates the user-defined message to be sent by the `CmsTemplate` (p. 1170).
- class **PooledSession**
A pooled session object that wraps around a delegate session.
- class **ProducerCallback**
Callback for sending a message to a CMS destination.
- class **ResourceLifecycleManager**
Manages the lifecycle of a set of CMS resources.
- class **SessionCallback**
Callback for executing any number of operations on a provided CMS Session.
- class **SessionPool**
A pool of CMS sessions from the same connection and with the same acknowledge mode.

5.3 activemq::commands Namespace Reference

Data Structures

- class **ActiveMQBlobMessage**
- class **ActiveMQBytesMessage**
- class **ActiveMQDestination**
- class **ActiveMQMapMessage**
- class **ActiveMQMessage**
- class **ActiveMQMessageTemplate**
- class **ActiveMQObjectMessage**
- class **ActiveMQQueue**
- class **ActiveMQStreamMessage**
- class **ActiveMQTempDestination**
- class **ActiveMQTempQueue**
- class **ActiveMQTempTopic**
- class **ActiveMQTextMessage**
- class **ActiveMQTopic**
- class **BaseCommand**
- class **BaseDataStructure**
- class **BooleanExpression**
- class **BrokerError**

This class represents an Exception sent from the Broker.

- class **BrokerId**
- class **BrokerInfo**
- class **Command**
- class **ConnectionControl**
- class **ConnectionError**
- class **ConnectionId**
- class **ConnectionInfo**
- class **ConsumerControl**
- class **ConsumerId**
- class **ConsumerInfo**
- class **ControlCommand**
- class **DataArrayResponse**
- class **DataResponse**
- class **DataStructure**
- class **DestinationInfo**
- class **DiscoveryEvent**
- class **ExceptionResponse**
- class **FlushCommand**
- class **IntegerResponse**
- class **JournalQueueAck**
- class **JournalTopicAck**
- class **JournalTrace**
- class **JournalTransaction**
- class **KeepAliveInfo**
- class **LastPartialCommand**
- class **LocalTransactionId**

- class **Message**
- class **MessageAck**
- class **MessageDispatch**
- class **MessageDispatchNotification**
- class **MessageId**
- class **MessagePull**
- class **NetworkBridgeFilter**
- class **PartialCommand**
- class **ProducerAck**
- class **ProducerId**
- class **ProducerInfo**
- class **RemoveInfo**
- class **RemoveSubscriptionInfo**
- class **ReplayCommand**
- class **Response**
- class **SessionId**
- class **SessionInfo**
- class **ShutdownInfo**
- class **SubscriptionInfo**
- class **TransactionId**
- class **TransactionInfo**
- class **WireFormatInfo**
- class **XATransactionId**

5.4 activemq::core Namespace Reference

Namespaces

- namespace **policies**

Data Structures

- class **ActiveMQAckHandler**

Interface class that is used to give CMS Messages an interface to Ack themselves with.

- class **ActiveMQConnection**

Concrete connection used for all connectors to the ActiveMQ broker.

- class **ActiveMQConnectionFactory**

- class **ActiveMQConnectionMetaData**

*This class houses all the various settings and information that is used by an instance of an **ActiveMQConnection** (p. 273) class.*

- class **ActiveMQConstants**

Class holding constant values for various ActiveMQ specific things Each constant is defined as an enumeration and has functions that convert back and forth between string and enum values.

- class **ActiveMQConsumer**

- class **ActiveMQProducer**

- class **ActiveMQQueueBrowser**

- class **ActiveMQSession**

- class **ActiveMQSessionExecutor**

Delegate dispatcher for a single session.

- class **ActiveMQTransactionContext**

Transaction Management class, hold messages that are to be redelivered upon a request to roll-back.

- class **DispatchData**

Simple POCO that contains the information necessary to route a message to a specified consumer.

- class **Dispatcher**

Interface for an object responsible for dispatching messages to consumers.

- class **MessageDispatchChannel**

- class **PrefetchPolicy**

Interface for a Policy object that controls message Prefetching on various destination types in ActiveMQ-CPP.

- class **RedeliveryPolicy**

*Interface for a **RedeliveryPolicy** (p. 3177) object that controls how message Redelivery is handled in ActiveMQ-CPP when a transaction is rolled back.*

- class **Synchronization**

*Transacted Object **Synchronization** (p. 3715), used to sync the events of a Transaction with the items in the Transaction.*

5.5 activemq::core::policies Namespace Reference

Data Structures

- class **DefaultPrefetchPolicy**
- class **DefaultRedeliveryPolicy**

5.6 activemq::exceptions Namespace Reference

Data Structures

- class **ActiveMQException**
- class **BrokerException**

5.7 activemq::io Namespace Reference

Data Structures

- class **LoggingInputStream**
- class **LoggingOutputStream**

OutputStream filter that just logs the data being written.

5.8 activemq::library Namespace Reference

Data Structures

- class `ActiveMQCPP`

5.9 activemq::state Namespace Reference

Data Structures

- class **CommandVisitor**

Interface for an Object that can visit the various Command Objects that are sent from and to this client.

- class **CommandVisitorAdapter**

*Default Implementation of a **CommandVisitor** (p. 1200) that returns NULL for all calls.*

- class **ConnectionState**
- class **ConnectionStateTracker**
- class **ConsumerState**
- class **ProducerState**
- class **SessionState**
- class **Tracked**
- class **TransactionState**

5.10 activemq::threads Namespace Reference

Data Structures

- class **CompositeTask**

Represents a single task that can be part of a set of Tasks that are contained in a `CompositeTaskRunner` (p. 1223).

- class **CompositeTaskRunner**

*A **Task** (p. 3734) Runner that can contain one or more `CompositeTasks` that are each checked for pending work and run if any is present in the order that the tasks were added.*

- class **DedicatedTaskRunner**

- class **Task**

Represents a unit of work that requires one or more iterations to complete.

- class **TaskRunner**

5.11 activemq::transport Namespace Reference

Namespaces

- namespace **correlator**
- namespace **failover**
- namespace **inactivity**
- namespace **logging**
- namespace **mock**
- namespace **tcp**

Data Structures

- class **AbstractTransportFactory**
*Abstract implementation of the **TransportFactory** (p. 3889) interface, providing the base functionality that's common to most of the **TransportFactory** (p. 3889) instances.*
- class **CompositeTransport**
*A Composite **Transport** (p. 3883) is a **Transport** (p. 3883) implementation that is composed of several Transports.*
- class **DefaultTransportListener**
- class **IOTransport**
*Implementation of the **Transport** (p. 3883) interface that performs marshaling of **commands** (p. 87) to IO streams.*
- class **Transport**
*Interface for a **transport** (p. 97) layer for command objects.*
- class **TransportFactory**
Defines the interface for Factories that create Transports or TransportFilters.
- class **TransportFilter**
*A filter on the **transport** (p. 97) layer.*
- class **TransportListener**
*A listener of asynchronous **exceptions** (p. 92) from a command **transport** (p. 97) object.*
- class **TransportRegistry**
*Registry of all **Transport** (p. 3883) Factories that are available to the client at runtime.*

5.12 activemq::transport::correlator Namespace Reference

Data Structures

- class **FutureResponse**

A container that holds a response object.

- class **ResponseCorrelator**

*This type of **transport** (p. 97) filter is responsible for correlating asynchronous responses with requests.*

5.13 activemq::transport::failover Namespace Reference

Data Structures

- class **BackupTransport**
- class **BackupTransportPool**
- class **CloseTransportsTask**
- class **FailoverTransport**
- class **FailoverTransportFactory**

*Creates an instance of a **FailoverTransport** (p. 1873).*

- class **FailoverTransportListener**

*Utility class used by the **Transport** (p. 3883) to perform the work of responding to events from the active **Transport** (p. 3883).*

- class **URIPool**

5.14 activemq::transport::inactivity Namespace Reference

Data Structures

- class **InactivityMonitor**
- class **ReadChecker**
Runnable class that is used by the {}.
- class **WriteChecker**
Runnable class used by the {}.

5.15 activemq::transport::logging Namespace Reference

Data Structures

- class **LoggingTransport**

*A **transport** (p. 97) filter that logs **commands** (p. 87) as they are sent/received.*

5.16 activemq::transport::mock Namespace Reference

Data Structures

- class **InternalCommandListener**

*Listens for Commands sent from the **MockTransport** (p. 2768).*

- class **MockTransport**

*The **MockTransport** (p. 2768) defines a base level **Transport** (p. 3883) class that is intended to be used in place of an a regular protocol **Transport** (p. 3883) such as TCP.*

- class **MockTransportFactory**

Manufactures MockTransports, which are objects that read from input streams and write to output streams.

- class **ResponseBuilder**

Interface for all Protocols to implement that defines the behavior of the Broker in response to messages of that protocol.

5.17 activemq::transport::tcp Namespace Reference

Data Structures

- class **SslTransport**

***Transport** (p. 3883) for connecting to a Broker using an SSL Socket.*

- class **SslTransportFactory**

- class **TcpTransport**

*Implements a TCP/IP based **transport** (p. 97) filter, this **transport** (p. 97) is meant to wrap an instance of an **IOTransport** (p. 2145).*

- class **TcpTransportFactory**

*Factory Responsible for creating the **TcpTransport** (p. 3752).*

5.18 activemq::util Namespace Reference

Data Structures

- class **ActiveMQProperties**

Implementation of the `CMSProperties` interface that delegates to a `decaf::util::Properties` (p. 3126) object.

- class **CMSExceptionSupport**
- class **CompositeData**

Represents a Composite URI.

- class **IdGenerator**
- class **LongSequenceGenerator**

This class is used to generate a sequence of long long values that are incremented each time a new value is requested.

- class **MarshallingSupport**
- class **MemoryUsage**
- class **PrimitiveList**

List of primitives.

- class **PrimitiveMap**

Map of named primitives.

- class **PrimitiveValueConverter**

Class controls the conversion of data contained in a `PrimitiveValueNode` (p. 3012) from one type to another.

- class **PrimitiveValueNode**

Class that wraps around a single value of one of the many types.

- class **URISupport**
- class **Usage**

5.19 activemq::wireformat Namespace Reference

Namespaces

- namespace **openwire**
- namespace **stomp**

Data Structures

- class **MarshalAware**
- class **WireFormat**
*Provides a mechanism to marshal **commands** (p. 87) into and out of packets or into and out of streams, Channels and Datagrams.*
- class **WireFormatFactory**
*The **WireFormatFactory** (p. 3980) is the interface that all **WireFormatFactory** (p. 3980) classes must extend.*
- class **WireFormatNegotiator**
*Defines a **WireFormatNegotiator** (p. 4016) which allows a **WireFormat** (p. 3976) to.*
- class **WireFormatRegistry**
*Registry of all **WireFormat** (p. 3976) Factories that are available to the client at runtime.*

5.20 activemq::wireformat::openwire Namespace Reference

Namespaces

- namespace **marshal**
- namespace **utils**

Data Structures

- class **OpenWireFormat**
- class **OpenWireFormatFactory**
- class **OpenWireFormatNegotiator**
- class **OpenWireResponseBuilder**

5.21 activemq::wireformat::openwire::marshal Namespace Reference

Namespaces

- namespace **v1**
- namespace **v2**
- namespace **v3**
- namespace **v4**
- namespace **v5**
- namespace **v6**

Data Structures

- class **BaseDataStreamMarshaller**
*Base class for all Marshallers that **marshal** (p. 107) DataStructures to and from the wire using the OpenWire protocol.*
- class **DataStreamMarshaller**
*Base class for all classes that **marshal** (p. 107) **commands** (p. 87) for Openwire.*
- class **PrimitiveTypesMarshaller**
*This class wraps the functionality needed to **marshal** (p. 107) a primitive map to the Openwire Format's expectation of what the map looks like on the wire.*

5.22 activemq::wireformat::openwire::marshal::v1 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 213).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 253).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 337).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 378).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 405).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 450).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 495).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 556).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 584).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 613).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 646).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 675).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 703).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 779).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 880).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 912).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1280).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1312).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1343).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1373).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1418).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1447).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1480).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1509).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1543).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1606).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1744).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1778).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1862).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1956).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2110).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2179).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2208).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2231).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2262).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2289).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2324).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2371).*
- class **MarshallerFactory**
Used to createmarshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2581).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2622).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2651).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2688).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2713).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2760).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2816).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2942).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3060).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3092).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3109).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3210).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3227).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3258).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3315).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3403).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3419).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3481).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3680).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3827).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3855).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4008).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4048).*

5.23 activemq:wireformat::openwire::marshal:v2 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 221).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 269).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 349).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 390).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 417).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 462).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 507).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 568).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 596).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 625).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 654).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 687).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 715).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 800).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 892).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 924).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1292).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1300).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1331).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1361).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1406).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1435).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1468).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1497).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1531).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1594).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1732).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1766).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1846).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1944).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2098).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2163).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2192).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2215).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2246).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2273).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2312).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2355).*
- class **MarshallerFactory**
Used to createmarshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2569).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2606).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2639).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2668).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2703).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2744).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2796).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2926).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3040).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3072).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3105).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3198).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3235).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3262).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3300).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3383).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3427).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3477).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3696).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3831).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3871).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4000).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4040).*

5.24 activemq::wireformat::openwire::marshal::v3 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 209).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 249).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 333).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 374).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 401).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 446).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 491).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 552).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 580).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 609).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 638).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 667).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 695).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 765).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 872).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 904).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1272).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1304).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1335).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1365).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1410).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1439).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1472).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1501).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1535).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1598).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1736).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1770).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1850).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1948).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2102).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2171).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2196).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2219).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2250).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2277).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2308).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2359).*
- class **MarshallerFactory**
Used to createmarshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2573).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2610).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2643).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2680).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2698).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2752).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2808).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2934).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3048).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3080).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3117).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3206).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3231).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3266).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3310).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3399).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3423).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3489).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3676).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3835).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3859).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4012).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4052).*

5.25 activemq:wireformat::openwire::marshal:v4 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 217).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 257).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 341).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 382).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 409).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 454).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 499).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 560).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 588).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 617).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 642).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 671).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 699).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 772).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 876).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 908).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1276).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1308).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1339).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1369).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1414).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1443).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1476).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1505).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1539).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1602).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1740).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1774).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1858).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1952).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2106).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2175).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2204).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2227).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2258).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2281).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2320).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2367).*
- class **MarshallerFactory**
Used to createmarshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2577).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2618).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2647).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2672).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2708).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2756).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2812).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2938).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3044).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3076).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3101).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3218).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3247).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3254).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3295).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3387).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3431).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3493).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3688).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3839).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3867).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4004).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4044).*

5.26 activemq::wireformat::openwire::marshal::v5 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 225).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 261).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 345).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 386).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 413).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 458).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 503).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 564).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 592).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 621).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 650).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 679).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 707).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 786).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 884).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 916).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1284).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1316).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1347).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1377).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1422).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1451).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1484).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1513).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1547).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1586).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1752).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1782).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1854).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1960).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2114).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2167).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2188).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2235).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2254).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2285).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2316).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2363).*
- class **MarshallerFactory**
Used to createmarshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2585).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2614).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2655).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2676).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2693).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2748).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2804).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2930).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3052).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3084).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3113).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3214).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3243).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3274).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3305).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3395).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3415).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3485).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3684).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3823).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3851).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3992).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4056).*

5.27 activemq:wireformat::openwire::marshal:v6 Namespace Reference

Data Structures

- class **ActiveMQBlobMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 229).*
- class **ActiveMQBytesMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 265).*
- class **ActiveMQDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 353).*
- class **ActiveMQMapMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 394).*
- class **ActiveMQMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 421).*
- class **ActiveMQObjectMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 466).*
- class **ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 511).*
- class **ActiveMQStreamMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 572).*
- class **ActiveMQTempDestinationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 600).*
- class **ActiveMQTempQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 629).*
- class **ActiveMQTempTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 658).*
- class **ActiveMQTextMessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 683).*

- class **ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 711).*
- class **BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 793).*
- class **BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 888).*
- class **BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 920).*
- class **ConnectionControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1288).*
- class **ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1320).*
- class **ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1351).*
- class **ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1381).*
- class **ConsumerControlMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1426).*
- class **ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1455).*
- class **ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1488).*
- class **ControlCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1517).*
- class **DataArrayResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1551).*
- class **DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1590).*
- class **DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1748).*

- class **DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1762).*
- class **ExceptionResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1842).*
- class **FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1940).*
- class **IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2094).*
- class **JournalQueueAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2159).*
- class **JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2200).*
- class **JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2223).*
- class **JournalTransactionMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2242).*
- class **KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2269).*
- class **LastPartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2304).*
- class **LocalTransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2351).*
- class **MarshallerFactory**
Used to create marshallers for a specific version of the wire protocol.
- class **MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2565).*
- class **MessageDispatchMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchMarshaller** (p. 2626).*
- class **MessageDispatchNotificationMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p. 2635).*

- class **MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2684).*
- class **MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2718).*
- class **MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2764).*
- class **NetworkBridgeFilterMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2800).*
- class **PartialCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2922).*
- class **ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3056).*
- class **ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3088).*
- class **ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3121).*
- class **RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3202).*
- class **RemoveSubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3239).*
- class **ReplayCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3270).*
- class **ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3320).*
- class **SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3391).*
- class **SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3411).*
- class **ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3473).*
- class **SubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3692).*

- class **TransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3843).*

- class **TransactionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3863).*

- class **WireFormatInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3996).*

- class **XATransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4036).*

5.28 activemq::wireformat::openwire::utils Namespace Reference

Data Structures

- class **BooleanStream**

Manages the writing and reading of boolean data streams to and from a data source such as a `DataInputStream` or `DataOutputStream`.

- class **HexTable**

*The **HexTable** (p. 1984) class maps hexadecimal strings to the value of an index into the table, i.e.*

- class **MessagePropertyInterceptor**

Used the base `ActiveMQMessage` class to intercept calls to get and set properties in order to capture the calls that use the reserved JMS properties and get and set them in the `OpenWireMessage` properties.

5.29 activemq::wireformat::stomp Namespace Reference

Data Structures

- class **StompCommandConstants**
- class **StompFrame**

A Stomp-level message frame that encloses all messages to and from the broker.

- class **StompHelper**

Utility Methods used when marshaling to and from StompFrame's.

- class **StompWireFormat**
- class **StompWireFormatFactory**

Factory used to create the Stomp Wire Format instance.

5.30 cms Namespace Reference

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

Data Structures

- class **BytesMessage**

*A **BytesMessage** (p. 1056) object is used to send a message containing a stream of unsigned bytes.*

- class **Closeable**

Interface for a class that implements the close method.

- class **CMSException**

CMS API Exception that is the base for all exceptions thrown from CMS classes.

- class **CMSProperties**

Interface for a Java-like properties object.

- class **CMSSecurityException**

This exception must be thrown when a provider rejects a user name/password submitted by a client.

- class **Connection**

The client's connection to its provider.

- class **ConnectionFactory**

*Defines the interface for a factory that creates connection objects, the **Connection** (p. 1262) objects returned implement the CMS **Connection** (p. 1262) interface and hide the CMS Provider specific implementation details behind that interface.*

- class **ConnectionMetaData**

*A **ConnectionMetaData** (p. 1385) object provides information describing the **Connection** (p. 1262) object.*

- class **DeliveryMode**

This is an Abstract class whose purpose is to provide a container for the delivery mode enumeration for CMS messages.

- class **Destination**

*A **Destination** (p. 1723) object encapsulates a provider-specific address.*

- class **ExceptionListener**

*If a CMS provider detects a serious problem, it notifies the client application through an **ExceptionListener** (p. 1838) that is registered with the **Connection** (p. 1262).*

- class **IllegalStateException**

This exception is thrown when a method is invoked at an illegal or inappropriate time or if the provider is not in an appropriate state for the requested operation.

- class **InvalidClientIdException**

This exception must be thrown when a client attempts to set a connection's client ID to a value that is rejected by a provider.

- class **InvalidDestinationException**

This exception must be thrown when a destination either is not understood by a provider or is no longer valid.

- class **InvalidSelectorException**

This exception must be thrown when a CMS client attempts to give a provider a message selector with invalid syntax.

- class **MapMessage**

*A **MapMessage** (p. 2472) object is used to send a set of name-value pairs.*

- class **Message**

Root of all messages.

- class **MessageConsumer**

*A client uses a **MessageConsumer** (p. 2589) to received messages from a destination.*

- class **MessageEnumeration**

Defines an object that enumerates a collection of Messages.

- class **MessageEOFException**

*This exception must be thrown when an unexpected end of stream has been reached when a **StreamMessage** (p. 3652) or **BytesMessage** (p. 1056) is being read.*

- class **MessageFormatException**

This exception must be thrown when a CMS client attempts to use a data type not supported by a message or attempts to read data in a message as the wrong type.

- class **MessageListener**

*A **MessageListener** (p. 2692) object is used to receive asynchronously delivered messages.*

- class **MessageNotReadableException**

This exception must be thrown when a CMS client attempts to read a write-only message.

- class **MessageNotWriteableException**

This exception must be thrown when a CMS client attempts to write to a read-only message.

- class **MessageProducer**

*A client uses a **MessageProducer** (p. 2725) object to send messages to a **Destination** (p. 1723).*

- class **ObjectMessage**

Place holder for interaction with JMS systems that support Java, the C++ client is not responsible for deserializing the contained Object.

- class **Queue**

An interface encapsulating a provider-specific queue name.

- class **QueueBrowser**
*This class implements in interface for browsing the messages in a **Queue** (p. 3148) without removing them.*
- class **Session**
*A **Session** (p. 3365) object is a single-threaded context for producing and consuming messages.*
- class **Startable**
Interface for a class that implements the start method.
- class **Stoppable**
Interface for a class that implements the stop method.
- class **StreamMessage**
*Interface for a **StreamMessage** (p. 3652).*
- class **TemporaryQueue**
*Defines a Temporary **Queue** (p. 3148) based **Destination** (p. 1723).*
- class **TemporaryTopic**
*Defines a Temporary **Topic** (p. 3817) based **Destination** (p. 1723).*
- class **TextMessage**
Interface for a text message.
- class **Topic**
An interface encapsulating a provider-specific topic name.
- class **UnsupportedOperationException**
This exception must be thrown when a CMS client attempts use a CMS method that is not implemented or not supported by the CMS Provider in use.

5.30.1 Detailed Description

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements. See the NOTICE file distributed with this work for additional information regarding copyright ownership. The ASF licenses this file to You under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

5.31 decaf Namespace Reference

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

Namespaces

- namespace **internal**
- namespace **io**
- namespace **lang**
- namespace **net**
- namespace **nio**
- namespace **security**
- namespace **util**

5.31.1 Detailed Description

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements. See the NOTICE file distributed with this work for additional information regarding copyright ownership. The ASF licenses this file to You under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

5.32 decaf::internal Namespace Reference

Namespaces

- namespace **io**
- namespace **net**
- namespace **nio**
- namespace **security**
- namespace **util**

Data Structures

- class **AprPool**
*Wraps an APR pool object so that classes in **decaf** (p. 143) can create a static member for use in static methods where apr function calls that need a pool are made.*
- class **DecafRuntime**
Handles APR initialization and termination.

5.33 decaf::internal::io Namespace Reference

Data Structures

- class **StandardErrorOutputStream**

Wrapper Around the Standard error Output facility on the current platform.

- class **StandardInputStream**
- class **StandardOutputStream**

5.34 decaf::internal::net Namespace Reference

Namespaces

- namespace **ssl**
- namespace **tcp**

Data Structures

- class **DefaultServerSocketFactory**
Default implementation of the Decaf ServerSocketFactory, creates ServerSocket objects with supplied options.
- class **DefaultSocketFactory**
SocketFactory implementation that is used to create Sockets.
- class **Network**
Internal class used to manage Networking related resources and hide platform dependent calls from the higher level API.
- class **SocketFileDescriptor**
File Descriptor type used internally by Decaf Socket objects.
- class **URIEncoderDecoder**
- class **URIHelper**
Helper class used by the URI classes in encoding and decoding of URI's.
- class **URIType**
Basic type object that holds data that composes a given URI.

5.35 decaf::internal::net::ssl Namespace Reference

Namespaces

- namespace **openssl**

Data Structures

- class **DefaultSSLContext**
Default SSL Context manager for the Decaf library.
- class **DefaultSSLServerSocketFactory**
Default implementation of the SSLServerSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.
- class **DefaultSSLSocketFactory**
Default implementation of the SSLSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

5.36 decaf::internal::net::ssl::openssl Namespace Reference

Data Structures

- class **OpenSSLContextSpi**
Provides an SSLContext that wraps the OpenSSL API.
- class **OpenSSLParameters**
Container class for parameters that are Common to OpenSSL socket classes.
- class **OpenSSLServerSocket**
SSLServerSocket based on OpenSSL library `code` (p. 1183).
- class **OpenSSLServerSocketFactory**
SSLServerSocketFactory that creates Server Sockets that use OpenSSL.
- class **OpenSSLSocket**
Wraps a a Normal Socket object and extends or overrides functions in that class to make use of the OpenSSL Socket API.
- class **OpenSSLSocketException**
Subclass of the standard SocketException that knows how to produce an error message from the OpenSSL error stack.
- class **OpenSSLSocketFactory**
Client Socket Factory that creates SSL based client sockets using the OpenSSL library.
- class **OpenSSLSocketInputStream**
An output stream for reading data from an OpenSSL Socket instance.
- class **OpenSSLSocketOutputStream**
*OutputStream implementation used to write data to an **OpenSSLSocket** (p. 2858) instance.*

5.37 decaf::internal::net::tcp Namespace Reference

Data Structures

- class **TcpSocket**
Platform-independent implementation of the socket interface.
- class **TcpSocketInputStream**
Input stream for performing reads on a socket.
- class **TcpSocketOutputStream**
Output stream for performing write operations on a socket.

5.38 `decaf::internal::nio` Namespace Reference

Data Structures

- class **BufferFactory**

Factory class used by static methods in the `decaf::nio` (p. 163) package to create the various default version of the NIO interfaces.

- class **ByteBuffer**

This class defines six categories of operations upon byte buffers:.

- class **CharArrayBuffer**
- class **DoubleArrayBuffer**
- class **FloatArrayBuffer**
- class **IntArrayBuffer**
- class **LongArrayBuffer**
- class **ShortArrayBuffer**

5.39 decaf::internal::security Namespace Reference

Data Structures

- class **SecureRandomImpl**

Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources.

5.40 decaf::internal::util Namespace Reference

Namespaces

- namespace **concurrent**

Data Structures

- class **ByteArrayAdapter**

This class adapts primitive type arrays to a base byte array so that the classes can inter-operate on the same base byte array without copying data.

- class **GenericResource**

*A Generic **Resource** (p. 3280) wraps some type and will delete it when the **Resource** (p. 3280) itself is deleted.*

- class **HexStringParser**

- class **Resource**

Interface for all Managed Resources in Decaf, these objects are added to the Runtime System and are destroyed at shutdown.

- class **ResourceLifecycleManager**

- class **TimerTaskHeap**

A Binary Heap implemented specifically for the Timer class in Decaf Util.

5.41 decaf::internal::util::concurrent Namespace Reference

Data Structures

- class **ConditionImpl**
- class **MutexImpl**
- class **SynchronizableImpl**

A convenience class used by some Decaf classes to implement the Synchronizable interface when there is no issues related to multiple inheritance.

- class **Transferer**

*Shared **internal** (p. 144) API for dual stacks and queues.*

- class **TransferQueue**

This extends Scherer-Scott dual queue algorithm, differing, among other ways, by using modes within nodes rather than marked pointers.

- class **TransferStack**

5.42 decaf::io Namespace Reference

Data Structures

- class **BlockingByteArrayInputStream**
This is a blocking version of a byte buffer stream.
- class **BufferedInputStream**
*A wrapper around another input stream that performs a buffered read, where it reads more data than it needs in order to reduce the number of **io** (p. 154) operations on the input stream.*
- class **BufferedOutputStream**
Wrapper around another output stream that buffers output before writing to the target output stream.
- class **ByteArrayInputStream**
*A **ByteArrayInputStream** (p. 1020) contains an **internal** (p. 144) buffer that contains bytes that may be read from the stream.*
- class **ByteArrayOutputStream**
- class **Closeable**
Interface for a class that implements the close method.
- class **DataInput**
*The **DataInput** (p. 1558) interface provides for reading bytes from a binary stream and reconstructing from them data in any of the C++ primitive types.*
- class **DataInputStream**
A data input stream lets an application read primitive Java data types from an underlying input stream in a machine-independent way.
- class **DataOutput**
*The **DataOutput** (p. 1574) interface provides for converting data from any of the C++ primitive types to a series of bytes and writing these bytes to a binary stream.*
- class **DataOutputStream**
A data output stream lets an application write primitive Java data types to an output stream in a portable way.
- class **EOFException**
- class **FileDescriptor**
This class servers as an opaque wrapper around an underlying OS level resource that can be used as a source / sink for byte level data such as sockets and files.
- class **FilterInputStream**
*A **FilterInputStream** (p. 1894) contains some other input stream, which it uses as its basic source of data, possibly transforming the data along the way or providing additional functionality.*
- class **FilterOutputStream**
This class is the superclass of all classes that filter output streams.

- class **Flushable**

*A **Flushable** (p. 1936) is a destination of data that can be flushed.*

- class **InputStream**

A base class that must be implemented by all classes wishing to provide a class that reads in a stream of bytes.

- class **InputStreamReader**

*An **InputStreamReader** (p. 2053) is a bridge from byte streams to character streams.*

- class **InterruptedIOException**

- class **IOException**

- class **OutputStream**

Base interface for any class that wants to represent an output stream of bytes.

- class **OutputStreamWriter**

A class for turning a character stream into a byte stream.

- class **PushbackInputStream**

*A **PushbackInputStream** (p. 3141) adds functionality to another input stream, namely the ability to "push back" or "unread" one byte.*

- class **Reader**

- class **UnsupportedEncodingException**

Thrown when the the Character Encoding is not supported.

- class **UTFDataFormatException**

Thrown from classes that attempt to read or write a UTF-8 encoded string and an encoding error is encountered.

- class **Writer**

5.43 decaf::lang Namespace Reference

Namespaces

- namespace **exceptions**

Data Structures

- class **Appendable**

An object to which char sequences and values can be appended.

- class **ArrayPointer**

*Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a **Type** and is **Thread** (p. 3765) Safe if the default Reference Counter is used.*

- class **ArrayPointerComparator**

*This implementation of **Comparator** is designed to allows objects in a **Collection** to be sorted or tested for equality based on the value of the value of the actual pointer to the array being contained in this **ArrayPointer** (p. 730).*

- class **Boolean**
- class **Byte**
- class **Character**
- class **CharSequence**

*A **CharSequence** (p. 1135) is a readable sequence of char values.*

- class **Comparable**

This interface imposes a total ordering on the objects of each class that implements it.

- class **Double**
- class **Exception**
- class **Float**
- class **Integer**
- class **Iterable**

*Implementing this interface allows an object to be cast to an **Iterable** (p. 2152) type for generic collections API calls.*

- class **Long**
- class **Math**

*The class **Math** (p. 2497) contains methods for performing basic numeric operations such as the elementary exponential, logarithm, square root, and trigonometric functions.*

- class **Number**

*The abstract class **Number** (p. 2835) is the superclass of classes **Byte** (p. 960), **Double** (p. 1788), **Float** (p. 1904), **Integer** (p. 2077), **Long** (p. 2420), and **Short** (p. 3440).*

- struct **STATIC_CAST_TOKEN**
- struct **DYNAMIC_CAST_TOKEN**
- class **Pointer**

*Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a **Type** and is **Thread** (p. 3765) Safe if the default Reference Counter is used.*

- class **PointerComparator**

*This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the Object being Pointed to and not the value of the contained pointer in the **Pointer** (p. 2946) instance.*

- class **Readable**

*A **Readable** (p. 3160) is a source of characters.*

- class **Runnable**

Interface for a runnable object - defines a task that can be run by a thread.

- class **Runtime**

- class **Short**

- class **String**

*The **String** (p. 3665) class represents an immutable sequence of chars.*

- class **System**

*The **System** (p. 3726) class provides static methods for accessing system level resources and performing some system dependent tasks such as looking up environment values and copying memory and arrays.*

- class **Thread**

*A **Thread** (p. 3765) is a concurrent unit of execution.*

- class **ThreadGroup**

- class **Throwable**

This class represents an error that has occurred.

Functions

- `template<typename T , typename R , typename U >`
`bool operator== (const ArrayPointer< T, R > &left, const U *right)`
- `template<typename T , typename R , typename U >`
`bool operator== (const U *left, const ArrayPointer< T, R > &right)`
- `template<typename T , typename R , typename U >`
`bool operator!= (const ArrayPointer< T, R > &left, const U *right)`
- `template<typename T , typename R , typename U >`
`bool operator!= (const U *left, const ArrayPointer< T, R > &right)`
- `template<typename T , typename R , typename U >`
`bool operator== (const Pointer< T, R > &left, const U *right)`
- `template<typename T , typename R , typename U >`
`bool operator== (const U *left, const Pointer< T, R > &right)`
- `template<typename T , typename R , typename U >`
`bool operator!= (const Pointer< T, R > &left, const U *right)`
- `template<typename T , typename R , typename U >`
`bool operator!= (const U *left, const Pointer< T, R > &right)`

5.43.1 Function Documentation

5.43.1.1 `template<typename T , typename R , typename U > bool
decaf::lang::operator!= (const U * left, const Pointer< T, R > & right)
[inline]`

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

5.43.1.2 `template<typename T , typename R , typename U > bool
decaf::lang::operator!= (const Pointer< T, R > & left, const U * right)
[inline]`

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

5.43.1.3 `template<typename T , typename R , typename U > bool
decaf::lang::operator!= (const U * left, const ArrayPointer< T, R > & right) [inline]`

References `decaf::lang::ArrayPointer< T, REFCOUNTER >::get()`.

5.43.1.4 `template<typename T , typename R , typename U > bool
decaf::lang::operator!= (const ArrayPointer< T, R > & left, const U * right) [inline]`

References `decaf::lang::ArrayPointer< T, REFCOUNTER >::get()`.

5.43.1.5 `template<typename T , typename R , typename U > bool
decaf::lang::operator== (const U * left, const Pointer< T, R > & right)
[inline]`

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

5.43.1.6 `template<typename T , typename R , typename U > bool
decaf::lang::operator== (const Pointer< T, R > & left, const U * right)
[inline]`

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

5.43.1.7 `template<typename T , typename R , typename U > bool
decaf::lang::operator== (const U * left, const ArrayPointer< T, R > & right) [inline]`

References `decaf::lang::ArrayPointer< T, REFCOUNTER >::get()`.

5.43.1.8 `template<typename T , typename R , typename U > bool
decaf::lang::operator== (const ArrayPointer< T, R > & left, const U * right) [inline]`

References `decaf::lang::ArrayPointer< T, REFCOUNTER >::get()`.

5.44 decaf::lang::exceptions Namespace Reference

Data Structures

- class **ClassCastException**
- class **IllegalArgumentException**
- class **IllegalMonitorStateException**
- class **IllegalStateException**
- class **IllegalThreadStateException**
- class **IndexOutOfBoundsException**
- class **InterruptedException**
- class **InvalidStateException**
- class **NoSuchElementException**
- class **NullPointerException**
- class **NumberFormatException**
- class **RuntimeException**
- class **UnsupportedOperationException**

5.45 decaf::net Namespace Reference

Namespaces

- namespace **ssl**

Data Structures

- class **BindException**
- class **ConnectException**
- class **HttpRetryException**
- class **Inet4Address**
- class **Inet6Address**
- class **InetAddress**

Represents an IP address.

- class **InetSocketAddress**
- class **MalformedURLException**
- class **NoRouteToHostException**
- class **PortUnreachableException**
- class **ProtocolException**
- class **ServerSocket**

This class implements server sockets.

- class **ServerSocketFactory**

Class used to create Server Sockets, subclasses can be created that create certain types of server sockets according to specific policies.

- class **Socket**
- class **SocketAddress**

*Base class for protocol specific **Socket** (p. 3503) addresses.*

- class **SocketError**

Static utility class to simplify handling of error codes for socket operations.

- class **SocketException**

Exception for errors when manipulating sockets.

- class **SocketFactory**

*The **SocketFactory** (p. 3524) is used to create **Socket** (p. 3503) objects and can be sub-classed to provide other types of Sockets or Sockets with varying configurations.*

- class **SocketImpl**

*Acts as a base class for all physical **Socket** (p. 3503) implementations.*

- class **SocketImplFactory**

Factory class interface for a Factory that creates SocketImpl objects.

- class **SocketOptions**
- class **SocketTimeoutException**

- class **UnknownHostException**
- class **UnknownServiceException**
- class **URI**

*This class represents an instance of a **URI** (p. 3921) as defined by RFC 2396.*

- class **URISyntaxException**
- class **URL**

*Class **URL** (p. 3960) represents a Uniform Resource Locator, a pointer to a "resource" on the World Wide Web.*

- class **URLDecoder**
- class **URLEncoder**

5.46 decaf::net::ssl Namespace Reference

Data Structures

- class **SSLContext**
*Represents an implementation of the Secure **Socket** (p. 3503) Layer for streaming based sockets.*
- class **SSLContextSpi**
*Defines the interface that should be provided by an **SSLContext** (p. 3545) provider.*
- class **SSLParameters**
- class **SSLServerSocket**
Represents a server socket that is used to accept connections from clients using the Secure Sockets protocol or the Top Level Security protocol.
- class **SSLServerSocketFactory**
Factory class interface that provides methods to create SSL Server Sockets.
- class **SSLSocket**
- class **SSLSocketFactory**
*Factory class interface for a **SocketFactory** (p. 3524) that can create **SSLSocket** (p. 3563) objects.*

5.47 decaf::nio Namespace Reference

Data Structures

- class **Buffer**

A container for data of a specific primitive type.

- class **BufferOverflowException**
- class **BufferUnderflowException**
- class **ByteBuffer**

This class defines six categories of operations upon byte buffers:.

- class **CharBuffer**

This class defines four categories of operations upon character buffers:.

- class **DoubleBuffer**

This class defines four categories of operations upon double buffers:.

- class **FloatBuffer**

This class defines four categories of operations upon float buffers:.

- class **IntBuffer**

This class defines four categories of operations upon int buffers:.

- class **InvalidMarkException**

- class **LongBuffer**

This class defines four categories of operations upon long long buffers:.

- class **ReadOnlyBufferException**

- class **ShortBuffer**

This class defines four categories of operations upon short buffers:.

5.48 decaf::security Namespace Reference

Namespaces

- namespace **auth**
- namespace **cert**

Data Structures

- class **GeneralSecurityException**
- class **InvalidKeyException**
- class **Key**

*The **Key** (p. 2293) interface is the top-level interface for all keys.*

- class **KeyException**
- class **KeyManagementException**
- class **NoSuchAlgorithmException**
- class **NoSuchProviderException**
- class **Principal**

Base interface for a principal, which can represent an individual or organization.

- class **PublicKey**

A public key.

- class **SecureRandom**
- class **SecureRandomSpi**

Interface class used by Security Service Providers to implement a source of secure random bytes.

- class **SignatureException**

5.49 decaf::security::auth Namespace Reference

Namespaces

- namespace **x500**

5.50 decaf::security::auth::x500 Namespace Reference

Data Structures

- class **X500Principal**

5.51 decaf::security::cert Namespace Reference

Data Structures

- class **Certificate**
Base interface for all identity certificates.
- class **CertificateEncodingException**
- class **CertificateException**
- class **CertificateExpiredException**
- class **CertificateNotYetValidException**
- class **CertificateParsingException**
- class **X509Certificate**
Base interface for all identity certificates.

5.52 decaf::util Namespace Reference

Namespaces

- namespace **comparators**
- namespace **concurrent**
- namespace **logging**
- namespace **zip**

Data Structures

- class **AbstractCollection**
*This class provides a skeletal implementation of the **Collection** (p. 1184) interface, to minimize the effort required to implement this interface.*
- class **AbstractList**
*This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "random access" data store (such as an array).*
- class **AbstractMap**
*This class provides a skeletal implementation of the **Map** (p. 2459) interface, to minimize the effort required to implement this interface.*
- class **AbstractQueue**
*This class provides skeletal implementations of some **Queue** (p. 3149) operations.*
- class **AbstractSequentialList**
*This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "sequential access" data store (such as a linked list).*
- class **AbstractSet**
*This class provides a skeletal implementation of the **Set** (p. 3439) interface to minimize the effort required to implement this interface.*
- class **Collection**
The root interface in the collection hierarchy.
- class **Comparator**
A comparison function, which imposes a total ordering on some collection of objects.
- class **Date**
Wrapper class around a time value in milliseconds.
- class **Iterator**
Defines an object that can be used to iterate over the elements of a collection.
- class **List**
An ordered collection (also known as a sequence).

- class **ListIterator**

An iterator for lists that allows the programmer to traverse the list in either direction, modify the list during iteration, and obtain the iterator's current position in the list.

- class **Map**

***Map** (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.*

- class **PriorityQueue**

An unbounded priority queue based on a binary heap algorithm.

- class **Properties**

Java-like properties class for mapping string names to string values.

- class **Queue**

A kind of collection provides advanced operations than other basic collections, such as insertion, extraction, and inspection.

- class **Random**

***Random** (p. 3155) Value Generator which is used to generate a stream of pseudorandom numbers.*

- class **Set**

A collection that contains no duplicate elements.

- class **StlList**

***List** (p. 2337) class that wraps the STL list object to provide a simpler interface and additional methods not provided by the STL type.*

- class **StlMap**

***Map** (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.*

- class **StlQueue**

*The **Queue** (p. 3149) class accepts messages with an `psuh(m)` command where `m` is the message to be queued.*

- class **StlSet**

***Set** (p. 3439) template that wraps around a `std::set` to provide a more user-friendly interface and to provide common functions that do not exist in `std::set`.*

- class **StringTokenizer**

- class **Timer**

A facility for threads to schedule tasks for future execution in a background thread.

- class **TimerTask**

*A Base class for a task object that can be scheduled for one-time or repeated execution by a **Timer** (p. 3790).*

- class **UUID**

*A class that represents an immutable universally unique identifier (**UUID** (p. 3969)).*

5.53 decaf::util::comparators Namespace Reference

Data Structures

- class **Less**

*Simple **Less** (p. 2328) **Comparator** (p. 1217) that compares to elements to determine if the first is less than the second.*

5.54 decaf::util::concurrent Namespace Reference

Namespaces

- namespace **atomic**
- namespace **locks**

Data Structures

- class **ConditionHandle**
- class **MutexHandle**
- class **BlockingQueue**

A *decaf::util::Queue* (p. 3149) that additionally supports operations that wait for the queue to become non-empty when retrieving an element, and wait for space to become available in the queue when storing an element.

- class **BrokenBarrierException**
- class **Callable**

A task that returns a result and may throw an exception.

- class **CancellationException**
- class **ConcurrentMap**

Interface for a **Map** (p. 2459) type that provides additional **atomic** (p. 173) *putIfAbsent*, *remove*, and *replace* methods alongside the already available **Map** (p. 2459) interface.

- class **ConcurrentStlMap**

Map (p. 2459) template that wraps around a *std::map* to provide a more user-friendly interface and to provide common functions that do not exist in *std::map*.

- class **CountDownLatch**
- class **Delayed**

A *mix-in* style interface for marking objects that should be acted upon after a given delay.

- class **ExecutionException**
- class **Executor**

An object that executes submitted *decaf.lang Runnable* (p. 3325) tasks.

- class **ExecutorService**

An **Executor** (p. 1869) that provides methods to manage termination and methods that can produce a **Future** (p. 1966) for tracking progress of one or more asynchronous tasks.

- class **Future**

A **Future** (p. 1966) represents the result of an asynchronous computation.

- class **Lock**

A wrapper class around a given synchronization mechanism that provides automatic release upon destruction.

- class **Mutex**

Mutex (p. 2782) object that offers recursive support on all platforms as well as providing the ability to use the standard *wait / notify* pattern used in languages like Java.

- class **PooledThread**
- class **PooledThreadListener**
*Abstract Listener Interface for users of **ThreadPool** (p. 3777).*
- class **RejectedExecutionException**
- class **RejectedExecutionHandler**
*A handler for tasks that cannot be executed by a **ThreadPoolExecutor** (p. ??).*
- class **Semaphore**
A counting semaphore.
- class **Synchronizable**
The interface for all synchronizable objects (that is, objects that can be locked and unlocked).
- class **SynchronousQueue**
*A **blocking queue** (p. 843) in which each insert operation must wait for a corresponding remove operation by another thread, and vice versa.*
- class **TaskListener**
- class **ThreadFactory**
*public interface **ThreadFactory** (p. 3774)*
- class **ThreadPool**
Defines a Thread Pool object that implements the functionality of pooling threads to perform user tasks.
- class **TimeoutException**
- class **TimeUnit**
*A **TimeUnit** (p. 3807) represents time durations at a given unit of granularity and provides utility methods to convert across units, and to perform timing and delay operations in these units.*

5.55 decaf::util::concurrent::atomic Namespace Reference

Data Structures

- class **AtomicBoolean**
A boolean value that may be updated atomically.
- class **AtomicInteger**
An int value that may be updated atomically.
- class **AtomicRefCounter**
- class **AtomicReference**
An Pointer reference that may be updated atomically.

5.56 decaf::util::concurrent::locks Namespace Reference

Data Structures

- class **Condition**

***Condition** (p. 1249) factors out the **Mutex** (p. 2782) monitor methods (wait, notify and notifyAll) into distinct objects to give the effect of having multiple wait-sets per object, by combining them with the use of arbitrary **Lock** (p. 2377) implementations.*

- class **Lock**

***Lock** (p. 2377) implementations provide more extensive locking operations than can be obtained using synchronized statements.*

- class **LockSupport**

*Basic thread blocking primitives for creating **locks** (p. 174) and other synchronization classes.*

- class **ReadWriteLock**

*A **ReadWriteLock** (p. 3172) maintains a pair of associated **locks** (p. 174), one for read-only operations and one for writing.*

- class **ReentrantLock**

*A reentrant mutual exclusion **Lock** (p. 2377) with extended capabilities.*

5.57 decaf::util::logging Namespace Reference

Data Structures

- class **ConsoleHandler**
*This **Handler** (p. 1978) publishes log records to `System.err`.*
- class **ErrorManager**
***ErrorManager** (p. 1828) objects can be attached to **Handlers** to process any error that occur on a **Handler** (p. 1978) during Logging.*
- class **Filter**
*A **Filter** (p. 1893) can be used to provide fine grain control over what is logged, beyond the control provided by log levels.*
- class **Formatter**
*A **Formatter** (p. 1964) provides support for formatting **LogRecords**.*
- class **Handler**
*A **Handler** (p. 1978) object takes log messages from a **Logger** (p. 2386) and exports them.*
- class **Level**
*The **Level** (p. 2332) class defines a set of standard **logging** (p. 175) levels that can be used to control **logging** (p. 175) output.*
- class **Logger**
*A **Logger** (p. 2386) object is used to log messages for a specific system or application component.*
- class **LoggerHierarchy**
- class **LogManager**
*There is a single global **LogManager** (p. 2406) object that is used to maintain a set of shared state about **Loggers** and log services.*
- class **LogRecord**
***LogRecord** (p. 2413) objects are used to pass **logging** (p. 175) requests between the **logging** (p. 175) framework and individual log **Handlers**.*
- class **LogWriter**
- class **MarkBlockLogger**
Defines a class that can be used to mark the entry and exit from scoped blocks.
- class **PropertiesChangeListener**
*Defines the interface that classes can use to listen for change events on **Properties** (p. 3126).*
- class **SimpleFormatter**
*Print a brief summary of the **LogRecord** (p. 2413) in a human readable format.*
- class **SimpleLogger**
- class **StreamHandler**
*Stream based **logging** (p. 175) **Handler** (p. 1978).*

- class **XMLFormatter**

*Format a **LogRecord** (p. 2413) into a standard XML format.*

Enumerations

- enum **Levels** {
 Off, **Null**, **Markblock**, **Debug**,
 Info, **Warn**, **Error**, **Fatal**,
 Throwing }

Defines an enumeration for logging levels.

5.57.1 Enumeration Type Documentation

5.57.1.1 enum decaf::util::logging::Levels

Defines an enumeration for **logging** (p. 175) levels.

Enumerator:

Off

Null

Markblock

Debug

Info

Warn

Error

Fatal

Throwing

5.58 decaf::util::zip Namespace Reference

Data Structures

- class **Adler32**
*Class that can be used to compute an Adler-32 **Checksum** (p. 1142) for a data stream.*
- class **CheckedInputStream**
*An implementation of a **FilterInputStream** that will maintain a **Checksum** (p. 1142) of the bytes read, the **Checksum** (p. 1142) can then be used to verify the integrity of the input stream.*
- class **CheckedOutputStream**
*An implementation of a **FilterOutputStream** that will maintain a **Checksum** (p. 1142) of the bytes written, the **Checksum** (p. 1142) can then be used to verify the integrity of the output stream.*
- class **Checksum**
*An interface used to represent **Checksum** (p. 1142) values in the Zip package.*
- class **CRC32**
Class that can be used to compute a CRC-32 checksum for a data stream.
- class **DataFormatException**
- class **Deflater**
*This class compresses data using the DEFLATE algorithm (see **specification**).*
- class **DeflaterOutputStream**
*Provides a **FilterOutputStream** instance that compresses the data before writing it to the wrapped **OutputStream**.*
- class **Inflater**
*This class uncompresses data that was compressed using the DEFLATE algorithm (see **specification**).*
- class **InflaterInputStream**
*A **FilterInputStream** that decompresses data read from the wrapped **InputStream** instance.*
- class **ZipException**

5.59 std Namespace Reference

Data Structures

- struct `less< decaf::lang::ArrayPointer< T > >`

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

- struct `less< decaf::lang::Pointer< T > >`

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

Chapter 6

Data Structure Documentation

6.1 decaf::util::AbstractCollection< E > Class Template Reference

This class provides a skeletal implementation of the **Collection** (p. 1184) interface, to minimize the effort required to implement this interface.

#include <src/main/decaf/util/AbstractCollection.h> Inheritance diagram for decaf::util::AbstractCollection< E >:

Public Member Functions

- **AbstractCollection** ()
- virtual ~**AbstractCollection** ()
- **AbstractCollection**< E > & **operator=** (const **AbstractCollection**< E > &collection)
Assignment Operator, copy element from the source collection to this collection after clearing any element stored in this collection.
- virtual bool **add** (const E &value DECAF_UNUSED)
throw (lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Ensures that this collection contains the specified element (optional operation).
- virtual bool **addAll** (const **Collection**< E > &collection)
throw (lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Adds all of the elements in the specified collection to this collection (optional operation).
- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)
Removes all of the elements from this collection (optional operation).
- virtual void **copy** (const **Collection**< E > &collection)
*Renders this **Collection** (p. 1184) as a Copy of the given **Collection** (p. 1184).*

- virtual bool **contains** (const E &value) const throw (lang::Exception)
Returns true if this collection contains the specified element.
- virtual bool **containsAll** (const **Collection**< E > &collection) const throw (lang::Exception)
Returns true if this collection contains all of the elements in the specified collection.
- virtual bool **equals** (const **Collection**< E > &collection) const
*Answers true if this **Collection** (p. 1184) and the one given are the same size and if each element contained in the **Collection** (p. 1184) given is equal to an element contained in this collection.*
- virtual bool **isEmpty** () const
Returns true if this collection contains no elements.
- virtual bool **remove** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes a single instance of the specified element from this collection, if it is present (optional operation).
- virtual bool **removeAll** (const **Collection**< E > &collection) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes all of this collection's elements that are also contained in the specified collection (optional operation).
- virtual bool **retainAll** (const **Collection**< E > &collection) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Retains only the elements in this collection that are contained in the specified collection (optional operation).
- virtual std::vector< E > **toArray** () const
*Answers an STL vector containing copies of all elements contained in this **Collection** (p. 1184).*
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals a waiter on this object that it can now wake up and continue.

- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals the waiters on this object that it can now wake up and continue.

Protected Attributes

- util::concurrent::Mutex mutex

6.1.1 Detailed Description

template<typename E> class decaf::util::AbstractCollection< E >

This class provides a skeletal implementation of the **Collection** (p. 1184) interface, to minimize the effort required to implement this interface. To implement an unmodifiable collection, the programmer needs only to extend this class and provide implementations for the iterator and size methods. (The iterator returned by the iterator method must implement hasNext and next.)

To implement a modifiable collection, the programmer must additionally override this class's add method (which otherwise throws an UnsupportedOperationException), and the iterator returned by the iterator method must additionally implement its remove method.

The programmer should generally provide a void (no argument) and **Collection** (p. 1184) constructor, as per the recommendation in the **Collection** (p. 1184) interface specification.

The documentation for each non-abstract method in this class describes its implementation in detail. Each of these methods may be overridden if the collection being implemented admits a more efficient implementation.

Since:

1.0

6.1.2 Constructor & Destructor Documentation

6.1.2.1 `template<typename E> decaf::util::AbstractCollection< E
>::AbstractCollection () [inline]`

6.1.2.2 `template<typename E> virtual decaf::util::AbstractCollection< E
>::~AbstractCollection () [inline, virtual]`

6.1.3 Member Function Documentation

6.1.3.1 `template<typename E> virtual bool decaf::util::AbstractCollection<
E >::add (const E &value DECAF_UNUSED) throw
(lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException,
lang::exceptions::IllegalStateException) [inline,
virtual]`

Ensures that this collection contains the specified element (optional operation). Returns true if this collection changed as a result of the call. (Returns false if this collection does not permit duplicates and already contains the specified element.)

Collections that support this operation may place limitations on what elements may be added to this collection. **Collection** (p. 1184) classes should clearly specify in their documentation any restrictions on what elements may be added.

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

This implementation always throws an `UnsupportedOperationException`.

Parameters:

value - The element that must be ensured to be in this collection.

Returns:

true if the collection was changed as a result of this call.

Exceptions:

UnsupportedOperationException if the add operation is not supported by this collection

IllegalArgumentException if some property of the element prevents it from being added to this collection

IllegalStateException if the element cannot be added at this time due to insertion restrictions

Referenced by `decaf::util::AbstractCollection< cms::Connection * >::addAll()`,
`decaf::util::AbstractCollection< cms::Connection * >::copy()`, and
`decaf::util::AbstractCollection< cms::Connection * >::operator=()`.

```

6.1.3.2  template<typename E> virtual bool decaf::util::AbstractCollection<
        E >::addAll (const Collection< E > & collection) throw
        ( lang::exceptions::UnsupportedOperationException,
        lang::exceptions::IllegalArgumentException,
        lang::exceptions::IllegalStateException ) [inline,
        virtual]

```

Adds all of the elements in the specified collection to this collection (optional operation). The behavior of this operation is undefined if the specified collection is modified while the operation is in progress. (This implies that the behavior of this call is undefined if the specified collection is this collection, and this collection is nonempty.)

This implementation iterates over the specified collection, and adds each object returned by the iterator to this collection, in turn.

Note that this implementation will throw an `UnsupportedOperationException` unless `add` is overridden (assuming the specified collection is non-empty).

Parameters:

collection - The **Collection** (p.1184) whose elements are to be added to this **Collection** (p.1184).

Returns:

true if the collection was changed as a result of this call.

Exceptions:

UnsupportedOperationException if the `addAll` operation is not supported by this collection

IllegalArgumentException if some property of the element prevents it from being added to this collection

IllegalStateException if the element cannot be added at this time due to insertion restrictions

Reimplemented in `decaf::util::AbstractQueue< E >` (p.195).

```

6.1.3.3  template<typename E> virtual void decaf::util::AbstractCollection< E
        >::clear () throw ( lang::exceptions::UnsupportedOperationException )
        [inline, virtual]

```

Removes all of the elements from this collection (optional operation). The collection will be empty after this method returns.

This implementation iterates over this collection, removing each element using the **Iterator.remove** (p.2155) operation. Most implementations will probably choose to override this method for efficiency.

Note that this implementation will throw an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the `remove` method and this collection is non-empty.

Exceptions:

UnsupportedOperationException if the `clear` operation is not supported by this collection

Implements **decaf::util::Collection**< **E** > (p. 1187).

Reimplemented in **decaf::util::AbstractQueue**< **E** > (p. 196), **decaf::util::concurrent::SynchronousQueue**< **E** > (p. 3718), **decaf::util::PriorityQueue**< **E** > (p. 3031), **decaf::util::StlList**< **E** > (p. 3596), **decaf::util::StlSet**< **E** > (p. 3626), **decaf::util::StlList**< **cms::MessageConsumer** * > (p. 3596), **decaf::util::StlList**< **CompositeTask** * > (p. 3596), **decaf::util::StlList**< **URI** > (p. 3596), **decaf::util::StlList**< **Pointer**< **DestinationInfo** > > (p. 3596), **decaf::util::StlList**< **PrimitiveValueNode** > (p. 3596), **decaf::util::StlList**< **Pointer**< **Command** > > (p. 3596), **decaf::util::StlList**< **Pointer**< **BackupTransport** > > (p. 3596), **decaf::util::StlList**< **cms::MessageProducer** * > (p. 3596), **decaf::util::StlList**< **cms::Destination** * > (p. 3596), **decaf::util::StlList**< **cms::Session** * > (p. 3596), **decaf::util::StlList**< **cms::Connection** * > (p. 3596), **decaf::util::StlSet**< **transport::TransportListener** * > (p. 3626), **decaf::util::StlSet**< **Pointer**< **Synchronization** > > (p. 3626), **decaf::util::StlSet**< **Resource** * > (p. 3626), and **decaf::util::StlSet**< **ActiveMQSession** * > (p. 3626).

Referenced by **decaf::util::AbstractCollection**< **cms::Connection** * >::copy(), and **decaf::util::AbstractCollection**< **cms::Connection** * >::operator=().

6.1.3.4 `template<typename E> virtual bool decaf::util::AbstractCollection< E >::contains (const E & value) const throw (lang::Exception) [inline, virtual]`

Returns true if this collection contains the specified element. This implementation iterates over the elements in the collection, checking each element in turn for equality with the specified element.

Parameters:

value - the value whose presence is to be queried for in this **Collection** (p. 1184).

Returns:

true if the value is contained in this collection

Exceptions:

Exception if an error occurs,

Implements **decaf::util::Collection**< **E** > (p. 1188).

Reimplemented in **decaf::util::StlList**< **E** > (p. 3596), **decaf::util::StlSet**< **E** > (p. 3627), **decaf::util::StlList**< **cms::MessageConsumer** * > (p. 3596), **decaf::util::StlList**< **CompositeTask** * > (p. 3596), **decaf::util::StlList**< **URI** > (p. 3596), **decaf::util::StlList**< **Pointer**< **DestinationInfo** > > (p. 3596), **decaf::util::StlList**< **PrimitiveValueNode** > (p. 3596), **decaf::util::StlList**< **Pointer**< **Command** > > (p. 3596), **decaf::util::StlList**< **Pointer**< **BackupTransport** > > (p. 3596), **decaf::util::StlList**< **cms::MessageProducer** * > (p. 3596), **decaf::util::StlList**< **cms::Destination** * > (p. 3596), **decaf::util::StlList**< **cms::Session** * > (p. 3596), **decaf::util::StlList**< **cms::Connection** * > (p. 3596), **decaf::util::StlSet**< **transport::TransportListener** * > (p. 3627), **decaf::util::StlSet**< **Pointer**< **Synchronization** > > (p. 3627), **decaf::util::StlSet**< **Resource** * > (p. 3627), and **decaf::util::StlSet**< **ActiveMQSession** * > (p. 3627).

Referenced by **decaf::util::AbstractCollection**< **cms::Connection** * >::containsAll().

6.1.3.5 `template<typename E> virtual bool decaf::util::AbstractCollection< E >::containsAll (const Collection< E > & collection) const throw (lang::Exception) [inline, virtual]`

Returns true if this collection contains all of the elements in the specified collection. This implementation iterates over the specified collection, checking each element returned by the iterator in turn to see if it's contained in this collection. If all elements are so contained true is returned, otherwise false.

Parameters:

collection collection to be checked for containment in this collection

Returns:

true if this collection contains all of the elements in the specified collection.

Exceptions:

Exception if an error occurs,

Reimplemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3719).

Referenced by `decaf::util::AbstractCollection< cms::Connection * >::equals()`.

6.1.3.6 `template<typename E> virtual void decaf::util::AbstractCollection< E >::copy (const Collection< E > & collection) [inline, virtual]`

Renders this **Collection** (p. 1184) as a Copy of the given **Collection** (p. 1184). This implementation iterates over the contents of the given collection adding each to this collection after first calling this Collection's clear method.

Parameters:

collection - the collection to mirror.

6.1.3.7 `template<typename E> virtual bool decaf::util::AbstractCollection< E >::equals (const Collection< E > & collection) const [inline, virtual]`

Answers true if this **Collection** (p. 1184) and the one given are the same size and if each element contained in the **Collection** (p. 1184) given is equal to an element contained in this collection.

Parameters:

collection - The **Collection** (p. 1184) to be compared to this one.

Returns:

true if this **Collection** (p. 1184) is equal to the one given.

Reimplemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3720).

6.1.3.8 `template<typename E> virtual bool decaf::util::AbstractCollection< E >::isEmpty () const [inline, virtual]`

Returns true if this collection contains no elements. This implementation returns `size()` (p. 1192) == 0.

Returns:

true if the size method return 0.

Implements `decaf::util::Collection< E >` (p. 1189).

Reimplemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3721), `decaf::util::StlList< E >` (p. 3598), `decaf::util::StlSet< E >` (p. 3627), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), `decaf::util::StlList< cms::Connection * >` (p. 3598), `decaf::util::StlSet< transport::TransportListener * >` (p. 3627), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3627), `decaf::util::StlSet< Resource * >` (p. 3627), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3627).

Referenced by `decaf::util::AbstractQueue< E >::clear()`.

6.1.3.9 `template<typename E> virtual void decaf::util::AbstractCollection< E >::lock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3701).

6.1.3.10 `template<typename E> virtual void decaf::util::AbstractCollection< E >::notify () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [inline, virtual]`

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements `decaf::util::concurrent::Synchronizable` (p. 3702).

6.1.3.11 `template<typename E> virtual void decaf::util::AbstractCollection< E >::notifyAll () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [inline, virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements `decaf::util::concurrent::Synchronizable` (p. 3703).

6.1.3.12 `template<typename E> AbstractCollection<E>& decaf::util::AbstractCollection< E >::operator= (const AbstractCollection< E > & collection) [inline]`

Assignment Operator, copy element from the source collection to this collection after clearing any element stored in this collection.

Parameters:

collection - the collection to copy

Returns:

a reference to this collection

Reimplemented in `decaf::util::PriorityQueue< E >` (p. 3033).

6.1.3.13 `template<typename E> virtual bool decaf::util::AbstractCollection< E >::remove (const E & value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException) [inline, virtual]`

Removes a single instance of the specified element from this collection, if it is present (optional operation). More formally, removes the first element *e* such that *e* == *o*, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection.

IllegalArgumentException If the value is not a valid entry for this **Collection** (p. 1184).

Implements **decaf::util::Collection< E >** (p. 1190).

Reimplemented in **decaf::util::PriorityQueue< E >** (p. 3034), **decaf::util::StlList< E >** (p. 3600), **decaf::util::StlSet< E >** (p. 3628), **decaf::util::StlList< cms::MessageConsumer * >** (p. 3600), **decaf::util::StlList< CompositeTask * >** (p. 3600), **decaf::util::StlList< URI >** (p. 3600), **decaf::util::StlList< Pointer< DestinationInfo > >** (p. 3600), **decaf::util::StlList< PrimitiveValueNode >** (p. 3600), **decaf::util::StlList< Pointer< Command > >** (p. 3600), **decaf::util::StlList< Pointer< BackupTransport > >** (p. 3600), **decaf::util::StlList< cms::MessageProducer * >** (p. 3600), **decaf::util::StlList< cms::Destination * >** (p. 3600), **decaf::util::StlList< cms::Session * >** (p. 3600), **decaf::util::StlList< cms::Connection * >** (p. 3600), **decaf::util::StlSet< transport::TransportListener * >** (p. 3628), **decaf::util::StlSet< Pointer< Synchronization > >** (p. 3628), **decaf::util::StlSet< Resource * >** (p. 3628), and **decaf::util::StlSet< ActiveMQSession * >** (p. 3628).

```
6.1.3.14 template<typename E> virtual bool decaf::util::AbstractCollection<
E >::removeAll (const Collection< E > & collection)
throw ( lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException ) [inline, virtual]
```

Removes all of this collection's elements that are also contained in the specified collection (optional operation). After this call returns, this collection will contain no elements in common with the specified collection.

This implementation iterates over this collection, checking each element returned by the iterator in turn to see if it's contained in the specified collection. If it's so contained, it's removed from this collection with the iterator's remove method.

Note that this implementation will throw an **UnsupportedOperationException** if the iterator returned by the iterator method does not implement the remove method and this collection contains one or more elements in common with the specified collection.

Parameters:

collection - collection containing elements to be removed from this collection

Returns:

true if this collection changed as a result of the call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection

IllegalArgumentException.

Reimplemented in **decaf::util::AbstractSet< E >** (p. 199), **decaf::util::AbstractSet< transport::TransportListener * >** (p. 199), **decaf::util::AbstractSet< Pointer< Synchronization > >** (p. 199), **decaf::util::AbstractSet< Resource * >** (p. 199), and **decaf::util::AbstractSet< ActiveMQSession * >** (p. 199).

```

6.1.3.15  template<typename E> virtual bool decaf::util::AbstractCollection<
           E >::retainAll (const Collection< E > & collection)
           throw ( lang::exceptions::UnsupportedOperationException,
                   lang::exceptions::IllegalArgumentException ) [inline, virtual]

```

Retains only the elements in this collection that are contained in the specified collection (optional operation). In other words, removes from this collection all of its elements that are not contained in the specified collection.

This implementation iterates over this collection, checking each element returned by the iterator in turn to see if it's contained in the specified collection. If it's not so contained, it's removed from this collection with the iterator's remove method.

Note that this implementation will throw an `UnsupportedOperationException` if the iterator returned by the iterator method does not implement the remove method and this collection contains one or more elements not present in the specified collection.

Parameters:

collection - collection containing elements to be retained in this collection

Returns:

true if this collection changed as a result of the call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection

IllegalArgumentException.

```

6.1.3.16  template<typename E> virtual std::vector<E>
           decaf::util::AbstractCollection< E >::toArray () const [inline, virtual]

```

Answers an STL vector containing copies of all elements contained in this **Collection** (p. 1184). All the elements in the array will not be referenced by the collection. The elements in the returned array will be sorted to the same order as those returned by the iterator of this collection itself if the collection guarantees the order.

Returns:

an vector of copies of all the elements from this **Collection** (p. 1184)

Implements `decaf::util::Collection< E >` (p. 1192).

Reimplemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3724).

```

6.1.3.17  template<typename E> virtual bool decaf::util::AbstractCollection<
           E >::tryLock () throw ( decaf::lang::exceptions::RuntimeException )
           [inline, virtual]

```

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

```
6.1.3.18  template<typename E> virtual void decaf::util::AbstractCollection< E
           >::unlock () throw ( decaf::lang::exceptions::RuntimeException ) [inline,
           virtual]
```

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

```
6.1.3.19  template<typename E> virtual void decaf::util::AbstractCollection<
           E >::wait (long long millisecs, int nanos) throw
           ( decaf::lang::exceptions::RuntimeException, de-
           ccaf::lang::exceptions::IllegalArgumentException,
           decaf::lang::exceptions::IllegalMonitorStateException,
           decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.1.3.20 `template<typename E> virtual void decaf::util::AbstractCollection< E >::wait (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3708).

6.1.3.21 `template<typename E> virtual void decaf::util::AbstractCollection< E >::wait () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3709).

6.1.4 Field Documentation

6.1.4.1 `template<typename E> util::concurrent::Mutex decaf::util::AbstractCollection< E >::mutex [mutable, protected]`

Referenced by `decaf::util::AbstractCollection< cms::Connection * >::lock()`, `decaf::util::AbstractCollection< cms::Connection * >::notify()`, `decaf::util::AbstractCollection< cms::Connection * >::notifyAll()`, `decaf::util::AbstractCollection< cms::Connection * >::tryLock()`, `decaf::util::AbstractCollection< cms::Connection * >::unlock()`, and `decaf::util::AbstractCollection< cms::Connection * >::wait()`.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/AbstractCollection.h`

6.2 decaf::util::AbstractList< E > Class Template Reference

This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "random access" data store (such as an array).

#include <src/main/decaf/util/AbstractList.h> Inheritance diagram for decaf::util::AbstractList< E >:

Public Member Functions

- virtual ~**AbstractList** ()

6.2.1 Detailed Description

template<typename E> class decaf::util::AbstractList< E >

This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "random access" data store (such as an array). For sequential access data (such as a linked list), **AbstractSequentialList** (p. 198) should be used in preference to this class.

To implement an unmodifiable list, the programmer needs only to extend this class and provide implementations for the `get(int)` and `size()` (p. 1192) methods.

To implement a modifiable list, the programmer must additionally override the `set(int, E)` method (which otherwise throws an `UnsupportedOperationException`). If the list is variable-size the programmer must additionally override the `add(int, E)` and `remove(int)` methods.

The programmer should generally provide a void (no argument) and collection constructor, as per the recommendation in the **Collection** (p. 1184) interface specification.

Unlike the other abstract collection implementations, the programmer does not have to provide an iterator implementation; the iterator and list iterator are implemented by this class, on top of the "random access" methods: `get(int)`, `set(int, E)`, `add(int, E)` and `remove(int)`.

The documentation for each non-abstract method in this class describes its implementation in detail. Each of these methods may be overridden if the collection being implemented admits a more efficient implementation.

Since:

1.0

6.2.2 Constructor & Destructor Documentation

6.2.2.1 template<typename E > virtual decaf::util::AbstractList< E >::~~AbstractList () [inline, virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/util/**AbstractList.h**

6.3 decaf::util::AbstractMap< K, V, COMPARATOR > Class Template Reference

This class provides a skeletal implementation of the **Map** (p. 2459) interface, to minimize the effort required to implement this interface.

#include <src/main/decaf/util/AbstractMap.h> Inheritance diagram for decaf::util::AbstractMap< K, V, COMPARATOR >:

Public Member Functions

- virtual ~AbstractMap ()

6.3.1 Detailed Description

```
template<typename K, typename V, typename COMPARATOR> class
decaf::util::AbstractMap< K, V, COMPARATOR >
```

This class provides a skeletal implementation of the **Map** (p. 2459) interface, to minimize the effort required to implement this interface. To implement an unmodifiable map, the programmer needs only to extend this class and provide an implementation for the `entrySet` method, which returns a set-view of the map's mappings. Typically, the returned set will, in turn, be implemented atop **AbstractSet** (p. 199). This set should not support the `add` or `remove` methods, and its iterator should not support the `remove` method.

To implement a modifiable map, the programmer must additionally override this class's `put` method (which otherwise throws an `UnsupportedOperationException`), and the iterator returned by `entrySet().iterator()` must additionally implement its `remove` method.

The programmer should generally provide a void (no argument) and map constructor, as per the recommendation in the **Map** (p. 2459) interface specification.

The documentation for each non-abstract method in this class describes its implementation in detail. Each of these methods may be overridden if the map being implemented admits a more efficient implementation.

Since:

1.0

6.3.2 Constructor & Destructor Documentation

```
6.3.2.1 template<typename K , typename V , typename COMPARATOR >
virtual decaf::util::AbstractMap< K, V, COMPARATOR >::~~AbstractMap
() [inline, virtual]
```

The documentation for this class was generated from the following file:

- src/main/decaf/util/**AbstractMap.h**

6.4 decaf::util::AbstractQueue< E > Class Template Reference

This class provides skeletal implementations of some **Queue** (p. 3149) operations.

#include <src/main/decaf/util/AbstractQueue.h> Inheritance diagram for decaf::util::AbstractQueue< E >:

Public Member Functions

- **AbstractQueue** ()
- virtual ~**AbstractQueue** ()
- virtual bool **add** (const E &value) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Inserts the specified element into this queue if it is possible to do so immediately without violating capacity restrictions, returning true upon success and throwing an IllegalStateException if no space is currently available.
- virtual bool **addAll** (const **Collection**< E > &collection) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Adds all the elements of a collection to the queue.
- virtual E **remove** () throw (decaf::lang::exceptions::NoSuchElementException)
Retrieves and removes the head of this queue.
- virtual E **element** () const throw (decaf::lang::exceptions::NoSuchElementException)
Retrieves, but does not remove, the head of this queue.
- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)
Removes all elements of the queue.

6.4.1 Detailed Description

template<typename E> class decaf::util::AbstractQueue< E >

This class provides skeletal implementations of some **Queue** (p. 3149) operations. Methods add, remove, and element are based on offer, poll, and peek, respectively.

A **Queue** (p. 3149) implementation that extends this class must minimally define a method **Queue** (p. 3149). **offer**(E) which does not permit insertion of null elements, along with methods **Queue** (p. 3149). **peek**() (p. 3151), **Queue.poll**() (p. 3151), **Collection.size**() (p. 1192), and a **Collection.iterator**() (p. 2152) supporting **Iterator.remove**() (p. 2155). Typically, additional methods will be overridden as well. If these requirements cannot be met, consider instead subclassing **AbstractCollection** (p. 179).

Since:

1.0

6.4.2 Constructor & Destructor Documentation

6.4.2.1 `template<typename E > decaf::util::AbstractQueue< E >::AbstractQueue()` [inline]

6.4.2.2 `template<typename E > virtual decaf::util::AbstractQueue< E >::~~AbstractQueue()` [inline, virtual]

6.4.3 Member Function Documentation

6.4.3.1 `template<typename E > virtual bool decaf::util::AbstractQueue< E >::add (const E & value) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)` [inline, virtual]

Inserts the specified element into this queue if it is possible to do so immediately without violating capacity restrictions, returning true upon success and throwing an `IllegalStateException` if no space is currently available. This implementation returns true if offer succeeds, else throws an `IllegalStateException`.

Parameters:

value - the element to offer to the **Queue** (p. 3149).

Returns:

true if the add succeeds.

Exceptions:

IllegalArgumentException if the element cannot be added.

Implements `decaf::util::Collection< E >` (p. 1186).

Reimplemented in `decaf::util::PriorityQueue< E >` (p. 3031).

References `decaf::util::Queue< E >::offer()`.

6.4.3.2 `template<typename E > virtual bool decaf::util::AbstractQueue< E >::addAll (const Collection< E > & collection) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)` [inline, virtual]

Adds all the elements of a collection to the queue. If the collection is the queue itself, then an `IllegalArgumentException` will be thrown out. If during the process, some runtime exception is thrown out, then part of the elements in the collection that have successfully added will remain in the queue.

The result of the method is undefined if the collection is modified during the process of the method.

Parameters:

collection - the collection to be added to the queue.

Returns:

true if the operation succeeds.

Exceptions:

IllegalArgumentException If the collection to be added to the queue is the queue itself.

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 183).

6.4.3.3 `template<typename E > virtual void decaf::util::AbstractQueue< E >::clear
() throw (lang::exceptions::UnsupportedOperationException) [inline,
virtual]`

Removes all elements of the queue. This implementation repeatedly invokes poll until it returns the empty marker.

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 183).

Reimplemented in **decaf::util::concurrent::SynchronousQueue< E >** (p. 3718), and **decaf::util::PriorityQueue< E >** (p. 3031).

References **decaf::util::AbstractCollection< E >::isEmpty()**, and **decaf::util::Queue< E >::poll()**.

6.4.3.4 `template<typename E > virtual E decaf::util::AbstractQueue< E >::element
() const throw (decaf::lang::exceptions::NoSuchElementException)
[inline, virtual]`

Retrieves, but does not remove, the head of this queue. This method differs from peek only in that it throws an exception if this queue is empty.

This implementation returns the result of peek unless the queue is empty.

Returns:

the element in the head of the queue.

Exceptions:

NoSuchElementException if the queue is empty.

Implements **decaf::util::Queue< E >** (p. 3150).

References **decaf::util::Queue< E >::peek()**.

Referenced by **decaf::util::concurrent::SynchronousQueue< E >::drainTo()**.

6.4.3.5 `template<typename E > virtual E decaf::util::AbstractQueue< E >::remove
() throw (decaf::lang::exceptions::NoSuchElementException) [inline,
virtual]`

Retrieves and removes the head of this queue. This method differs from poll only in that it throws an exception if this queue is empty.

This implementation returns the result of poll unless the queue is empty.

Returns:

a copy of the element in the head of the queue.

Exceptions:

NoSuchElementException if the queue is empty.

Implements **decaf::util::Queue< E >** (p. 3151).

Reimplemented in **decaf::util::PriorityQueue< E >** (p. 3034).

References **decaf::util::Queue< E >::poll()**.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/AbstractQueue.h`

6.5 decaf::util::AbstractSequentialList< E > Class Template Reference

This class provides a skeletal implementation of the **List** (p.2337) interface to minimize the effort required to implement this interface backed by a "sequential access" data store (such as a linked list).

#include <src/main/decaf/util/AbstractSequentialList.h> Inheritance diagram for decaf::util::AbstractSequentialList< E >:

Public Member Functions

- virtual ~AbstractSequentialList ()

6.5.1 Detailed Description

template<typename E> class decaf::util::AbstractSequentialList< E >

This class provides a skeletal implementation of the **List** (p.2337) interface to minimize the effort required to implement this interface backed by a "sequential access" data store (such as a linked list). For random access data (such as an array), **AbstractList** (p.192) should be used in preference to this class.

This class is the opposite of the **AbstractList** (p.192) class in the sense that it implements the "random access" methods (get(int index), set(int index, E element), add(int index, E element) and remove(int index)) on top of the list's list iterator, instead of the other way around.

To implement a list the programmer needs only to extend this class and provide implementations for the listIterator and size methods. For an unmodifiable list, the programmer need only implement the list iterator's hasNext, next, hasPrevious, previous and index methods.

For a modifiable list the programmer should additionally implement the list iterator's set method. For a variable-size list the programmer should additionally implement the list iterator's remove and add methods.

The programmer should generally provide a void (no argument) and collection constructor, as per the recommendation in the **Collection** (p.1184) interface specification.

Since:

1.0

6.5.2 Constructor & Destructor Documentation

6.5.2.1 template<typename E > virtual decaf::util::AbstractSequentialList< E >::~AbstractSequentialList () [inline, virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/util/AbstractSequentialList.h

6.6 decaf::util::AbstractSet< E > Class Template Reference

This class provides a skeletal implementation of the **Set** (p. 3439) interface to minimize the effort required to implement this interface.

```
#include <src/main/decaf/util/AbstractSet.h> Inheritance      diagram      for
decaf::util::AbstractSet< E >:
```

Public Member Functions

- virtual **~AbstractSet** ()
- virtual bool **removeAll** (const **Collection**< E > &collection) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes from this set all of its elements that are contained in the specified collection (optional operation).

6.6.1 Detailed Description

template<typename E> class decaf::util::AbstractSet< E >

This class provides a skeletal implementation of the **Set** (p. 3439) interface to minimize the effort required to implement this interface. The process of implementing a set by extending this class is identical to that of implementing a **Collection** (p. 1184) by extending **AbstractCollection** (p. 179), except that all of the methods and constructors in subclasses of this class must obey the additional constraints imposed by the **Set** (p. 3439) interface (for instance, the add method must not permit addition of multiple instances of an object to a set).

Since:

1.0

6.6.2 Constructor & Destructor Documentation

6.6.2.1 **template<typename E> virtual decaf::util::AbstractSet< E >::~~AbstractSet**
() [inline, virtual]

6.6.3 Member Function Documentation

6.6.3.1 **template<typename E> virtual bool decaf::util::AbstractSet<**
E >::removeAll (const **Collection**< E > & *collection*)
throw (lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException) [inline, virtual]

Removes from this set all of its elements that are contained in the specified collection (optional operation). If the specified collection is also a set, this operation effectively modifies this set so that its value is the asymmetric set difference of the two sets.

This implementation determines which is the smaller of this set and the specified collection, by invoking the size method on each. If this set has fewer elements, then the implementation iterates

over this set, checking each element returned by the iterator in turn to see if it is contained in the specified collection. If it is so contained, it is removed from this set with the iterator's remove method. If the specified collection has fewer elements, then the implementation iterates over the specified collection, removing from this set each element returned by the iterator, using this set's remove method.

Note that this implementation will throw an `UnsupportedOperationException` if the iterator returned by the iterator method does not implement the remove method.

Parameters:

collection - The **Collection** (p. 1184) whose elements are to be retained

Returns:

true if the collection changed as a result of this call

Exceptions:

UnsupportedOperationException

IllegalArgumentException

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 188).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/AbstractSet.h`

6.7 activemq::transport::AbstractTransportFactory Class Reference

Abstract implementation of the **TransportFactory** (p. 3889) interface, providing the base functionality that's common to most of the **TransportFactory** (p. 3889) instances.

#include <src/main/activemq/transport/AbstractTransportFactory.h> Inheritance diagram for activemq::transport::AbstractTransportFactory:

Public Member Functions

- virtual `~AbstractTransportFactory()`

Protected Member Functions

- virtual `Pointer<wireformat::WireFormat> createWireFormat(const decaf::util::Properties &properties) throw (decaf::lang::exceptions::NoSuchElementException)`

*Creates the WireFormat that is configured for this **Transport** (p. 3883) and returns it.*

6.7.1 Detailed Description

Abstract implementation of the **TransportFactory** (p. 3889) interface, providing the base functionality that's common to most of the **TransportFactory** (p. 3889) instances.

Since:

3.0

6.7.2 Constructor & Destructor Documentation

- 6.7.2.1 virtual `activemq::transport::AbstractTransportFactory::~AbstractTransportFactory()` [inline, virtual]

6.7.3 Member Function Documentation

- 6.7.3.1 virtual `Pointer<wireformat::WireFormat> activemq::transport::AbstractTransportFactory::createWireFormat(const decaf::util::Properties & properties) throw (decaf::lang::exceptions::NoSuchElementException)` [protected, virtual]

Creates the WireFormat that is configured for this **Transport** (p.3883) and returns it. The default WireFormat is Openwire.

Parameters:

properties The properties that were configured on the URI.

Returns:

a pointer to a `WireFormat` instance that the caller then owns.

Exceptions:

NoSuchElementException if the configured `WireFormat` is not found.

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/AbstractTransportFactory.h`

6.8 activemq::core::ActiveMQAckHandler Class Reference

Interface class that is used to give CMS Messages an interface to Ack themselves with.

```
#include <src/main/activemq/core/ActiveMQAckHandler.h>
```

Public Member Functions

- virtual `~ActiveMQAckHandler ()`
- virtual void `acknowledgeMessage (const commands::Message *message)=0` throw (cms::CMSException)

Method called to acknowledge the message passed.

6.8.1 Detailed Description

Interface class that is used to give CMS Messages an interface to Ack themselves with.

Since:

2.0

6.8.2 Constructor & Destructor Documentation

- 6.8.2.1 virtual `activemq::core::ActiveMQAckHandler::~~ActiveMQAckHandler ()`
[inline, virtual]

6.8.3 Member Function Documentation

- 6.8.3.1 virtual void `activemq::core::ActiveMQAckHandler::acknowledgeMessage (const commands::Message * message)` throw (cms::CMSException)
[pure virtual]

Method called to acknowledge the message passed.

Parameters:

message Message to Acknowledge

Exceptions:

CMSException

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQAckHandler.h`

6.9 activemq::commands::ActiveMQBlobMessage Class Reference

#include <src/main/activemq/commands/ActiveMQBlobMessage.h> Inheritance diagram for activemq::commands::ActiveMQBlobMessage:

Public Member Functions

- **ActiveMQBlobMessage** ()
- virtual **~ActiveMQBlobMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ActiveMQBlobMessage * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual **cms::Message * clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- std::string **getRemoteBlobUrl** () const
Get the Remote URL of the Blob.
- void **setRemoteBlobUrl** (const std::string &remoteURL)
Set the Remote URL of the Blob.
- std::string **getMimeType** () const
Get the Mime Type of the Blob.
- void **setMimeType** (const std::string &mimeType)
Set the Mime Type of the Blob.
- std::string **getName** () const
Gets the Name of the Blob.
- void **setName** (const std::string &name)
Sets the Name of the Blob.

- bool **isDeletedByBroker** () const
Gets if this Blob is deleted by the Broker.
- void **setDeletedByBroker** (bool value)
Sets the Deleted By Broker flag.

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQBLOBMESSAGE** = 29
- static const std::string **BINARY_MIME_TYPE**

6.9.1 Constructor & Destructor Documentation

6.9.1.1 `activemq::commands::ActiveMQBlobMessage::ActiveMQBlobMessage ()`

6.9.1.2 `virtual
activemq::commands::ActiveMQBlobMessage::~ActiveMQBlobMessage ()
[inline, virtual]`

6.9.2 Member Function Documentation

6.9.2.1 `virtual cms::Message* activemq::commands::ActiveMQBlobMessage::clone
() const [inline, virtual]`

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements **cms::Message** (p. 2539).

6.9.2.2 `virtual ActiveMQBlobMessage* ac-
tivemq::commands::ActiveMQBlobMessage::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::Message** (p. 2520).

6.9.2.3 `virtual void ac-
tivemq::commands::ActiveMQBlobMessage::copyDataStructure (const
DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::Message` (p. 2521).

6.9.2.4 `virtual bool activemq::commands::ActiveMQBlobMessage::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 429).

6.9.2.5 `virtual unsigned char activemq::commands::ActiveMQBlobMessage::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Reimplemented from `activemq::commands::Message` (p. 2523).

6.9.2.6 `std::string activemq::commands::ActiveMQBlobMessage::getMimeType () const` [inline]

Get the Mime Type of the Blob.

Returns:

string holding the MIME Type.

6.9.2.7 `std::string activemq::commands::ActiveMQBlobMessage::getName () const` [inline]

Gets the Name of the Blob.

Returns:

string name of the Blob.

6.9.2.8 `std::string activemq::commands::ActiveMQBlobMessage::getRemoteBlobUrl () const` [inline]

Get the Remote URL of the Blob.

Returns:

string from of the Remote Blob URL.

6.9.2.9 `bool activemq::commands::ActiveMQBlobMessage::isDeletedByBroker () const` [inline]

Gets if this Blob is deleted by the Broker.

Returns:

true if the Blob is deleted by the Broker.

6.9.2.10 `void activemq::commands::ActiveMQBlobMessage::setDeletedByBroker (bool value)` [inline]

Sets the Deleted By Broker flag.

Parameters:

value - set the Delete by broker flag to value.

6.9.2.11 `void activemq::commands::ActiveMQBlobMessage::setMimeType (const std::string & mimeType)` [inline]

Set the Mime Type of the Blob.

Parameters:

mimeType - String holding the MIME Type.

6.9.2.12 `void activemq::commands::ActiveMQBlobMessage::setName (const std::string & name)` [inline]

Sets the Name of the Blob.

Parameters:

name - Name of the Blob.

6.9.2.13 `void activemq::commands::ActiveMQBlobMessage::setRemoteBlobUrl (const std::string & remoteURL)` [inline]

Set the Remote URL of the Blob.

Parameters:

remoteURL - String form of the Remote URL.

6.9.2.14 `virtual std::string activemq::commands::ActiveMQBlobMessage::toString
() const [virtual]`

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::Message` (p. 2530).

6.9.3 Field Documentation

6.9.3.1 `const std::string activemq::commands::ActiveMQBlobMessage::BINARY_-
MIME_TYPE [static]`

6.9.3.2 `const unsigned char activemq::commands::ActiveMQBlobMessage::ID_-
ACTIVEMQBLOBMESSAGE = 29 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQBlobMessage.h`

6.10 activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.209).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBlobMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.10.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.209). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.10.2 Constructor & Destructor Documentation

6.10.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.10.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.10.3 Member Function Documentation

6.10.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.10.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.10.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.10.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.10.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700).

6.10.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

6.10.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBlobMessageMarshaller.h`

6.11 activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.213).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBlobMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.11.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.213). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.11.2 Constructor & Destructor Documentation

6.11.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.11.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.11.3 Member Function Documentation

6.11.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.11.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.11.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::marshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.11.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.11.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2715).

6.11.3.6 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

6.11.3.7 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBlobMessageMarshaller.h`

6.12 activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.217).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBlobMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.12.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.217). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.12.2 Constructor & Destructor Documentation

6.12.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.12.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.12.3 Member Function Documentation

6.12.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.12.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.12.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.12.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.12.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2710).

6.12.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

6.12.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBlobMessageMarshaller.h`

6.13 activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.221).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBlobMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.13.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.221). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.13.2 Constructor & Destructor Documentation

6.13.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.13.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.13.3 Member Function Documentation

6.13.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.13.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.13.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.13.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.13.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705).

6.13.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

6.13.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBlobMessageMarshaller.h`

6.14 activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.225).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBlobMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.14.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.225). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.14.2 Constructor & Destructor Documentation

6.14.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.14.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.14.3 Member Function Documentation

6.14.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.14.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.14.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::marshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.14.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.14.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2695).

6.14.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

6.14.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBlobMessageMarshaller.h`

6.15 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.229).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBlobMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller:

Public Member Functions

- **ActiveMQBlobMessageMarshaller** ()
- virtual **~ActiveMQBlobMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.15.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p.229). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.15.2 Constructor & Destructor Documentation

6.15.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::ActiveMQBlobMessageMarshaller()` [inline]

6.15.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::~~ActiveMQBlobMessageMarshaller()` [inline, virtual]

6.15.3 Member Function Documentation

6.15.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.15.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.15.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.15.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.15.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2720).

6.15.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

6.15.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBlobMessageMarshaller.h`

6.16 activemq::commands::ActiveMQBytesMessage Class Reference

#include <src/main/activemq/commands/ActiveMQBytesMessage.h> Inheritance diagram for activemq::commands::ActiveMQBytesMessage:

Public Member Functions

- **ActiveMQBytesMessage** ()
- virtual **~ActiveMQBytesMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ActiveMQBytesMessage** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual **cms::BytesMessage** * **clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- virtual void **clearBody** () throw (cms::CMSException)
Clears out the body of the message.
- virtual void **onSend** ()
Store the Data that was written to the stream before a send.
- virtual void **setBodyBytes** (const unsigned char *buffer, int numBytes) throw (cms::MessageNotWriteableException, cms::CMSException)
sets the bytes given to the message body.
- virtual unsigned char * **getBodyBytes** () const throw (cms::MessageNotReadableException, cms::CMSException)
Gets the bytes that are contained in this message, user should copy this data into a user allocated buffer.
- virtual int **getBodyLength** () const throw (cms::MessageNotReadableException, cms::CMSException)
Returns the number of bytes contained in the body of this message.

- virtual void **reset** () throw (cms::MessageFormatException, cms::CMSEException)
Puts the message body in read-only mode and repositions the stream of bytes to the beginning.
- virtual bool **readBoolean** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Boolean from the Bytes message stream.
- virtual void **writeBoolean** (bool value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a boolean to the bytes message stream as a 1-byte value.
- virtual unsigned char **readByte** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Byte from the Bytes message stream.
- virtual void **writeByte** (unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte to the bytes message stream as a 1-byte value.
- virtual int **readBytes** (std::vector< unsigned char > &value) const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a byte array from the bytes message stream.
- virtual void **writeBytes** (const std::vector< unsigned char > &value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte array to the bytes message stream using the vector size as the number of bytes to write.
- virtual int **readBytes** (unsigned char *buffer, int length) const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a portion of the bytes message stream.
- virtual void **writeBytes** (const unsigned char *value, int offset, int length) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a portion of a byte array to the bytes message stream.
- virtual char **readChar** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Char from the Bytes message stream.
- virtual void **writeChar** (char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a char to the bytes message stream as a 1-byte value.
- virtual float **readFloat** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 32 bit float from the Bytes message stream.

- virtual void **writeFloat** (float value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a float to the bytes message stream as a 4 byte value.
- virtual double **readDouble** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 64 bit double from the Bytes message stream.
- virtual void **writeDouble** (double value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a double to the bytes message stream as a 8 byte value.
- virtual short **readShort** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 16 bit signed short from the Bytes message stream.
- virtual void **writeShort** (short value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a signed short to the bytes message stream as a 2 byte value.
- virtual unsigned short **readUnsignedShort** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 16 bit unsigned short from the Bytes message stream.
- virtual void **writeUnsignedShort** (unsigned short value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a unsigned short to the bytes message stream as a 2 byte value.
- virtual int **readInt** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 32 bit signed integer from the Bytes message stream.
- virtual void **writeInt** (int value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a signed int to the bytes message stream as a 4 byte value.
- virtual long long **readLong** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 64 bit long from the Bytes message stream.
- virtual void **writeLong** (long long value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a long long to the bytes message stream as a 8 byte value.
- virtual std::string **readString** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads an ASCII String from the Bytes message stream.
- virtual void **writeString** (const std::string &value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes an ASCII String to the Bytes message stream.

- virtual std::string **readUTF** () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads an UTF String from the BytesMessage stream.

- virtual void **writeUTF** (const std::string &value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes an UTF String to the BytesMessage stream.

Static Public Attributes

- static const unsigned char **ID _ACTIVEMQBYTESMESSAGE** = 24

6.16.1 Constructor & Destructor Documentation

6.16.1.1 `activemq::commands::ActiveMQBytesMessage::ActiveMQBytesMessage ()`

6.16.1.2 `virtual
activemq::commands::ActiveMQBytesMessage::~~ActiveMQBytesMessage
() [virtual]`

6.16.2 Member Function Documentation

6.16.2.1 `virtual void activemq::commands::ActiveMQBytesMessage::clearBody ()
throw (cms::CMSEException) [virtual]`

Clears out the body of the message. This does not clear the headers or properties.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 428).

6.16.2.2 `virtual cms::BytesMessage* ac-
tivemq::commands::ActiveMQBytesMessage::clone () const
[inline, virtual]`

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements `cms::BytesMessage` (p. 1059).

6.16.2.3 `virtual ActiveMQBytesMessage* ac-
tivemq::commands::ActiveMQBytesMessage::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::Message** (p. 2520).

6.16.2.4 virtual void activemq::commands::ActiveMQBytesMessage::copyDataStructure (const DataStructure * src) [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::Message** (p. 2521).

6.16.2.5 virtual bool activemq::commands::ActiveMQBytesMessage::equals (const DataStructure * value) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Parameters:

value The **Command** (p. 1194) to compare to this one.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >** (p. 429).

6.16.2.6 virtual unsigned char* activemq::commands::ActiveMQBytesMessage::getBodyBytes () const throw (cms::MessageNotReadableException, cms::CMSEException) [virtual]

Gets the bytes that are contained in this message, user should copy this data into a user allocated buffer. Call **getBodyLength** to determine the number of bytes to expect.

Returns:

const pointer to a byte buffer

Exceptions:

CMSEException - If an internal error occurs.

MessageNotReadableException - If the message is in Write Only Mode.

Implements **cms::BytesMessage** (p. 1059).

6.16.2.7 `virtual int activemq::commands::ActiveMQBytesMessage::getBodyLength
() const throw (cms::MessageNotReadableException, cms::CMSException
) [virtual]`

Returns the number of bytes contained in the body of this message.

Returns:

number of bytes.

Exceptions:

CMSException - If an internal error occurs.

MessageNotReadableException - If the message is in Write Only Mode.

Implements `cms::BytesMessage` (p. 1060).

6.16.2.8 `virtual unsigned char ac-
tivemq::commands::ActiveMQBytesMessage::getDataStructureType ()
const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Reimplemented from `activemq::commands::Message` (p. 2523).

6.16.2.9 `virtual void activemq::commands::ActiveMQBytesMessage::onSend ()
[virtual]`

Store the Data that was written to the stream before a send.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate<
cms::BytesMessage >` (p. 436).

6.16.2.10 `virtual bool activemq::commands::ActiveMQBytesMessage::readBoolean
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]`

Reads a Boolean from the Bytes message stream.

Returns:

boolean value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::BytesMessage` (p. 1060).

6.16.2.11 `virtual unsigned char activemq::commands::ActiveMQBytesMessage::readByte
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]`

Reads a Byte from the Bytes message stream.

Returns:

unsigned char value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::BytesMessage` (p.1060).

6.16.2.12 `virtual int activemq::commands::ActiveMQBytesMessage::readBytes
(unsigned char * buffer, int length) const throw (cms::MessageEOFException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a portion of the bytes message stream. If the length of array value is less than the number of bytes remaining to be read from the stream, the array should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of array value, the bytes should be read into the array. The return value of the total number of bytes read will be less than the length of the array, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

If length is negative, or length is greater than the length of the array value, then an `IndexOutOfBoundsException` is thrown. No bytes will be read from the stream for this exception case.

Parameters:

buffer the buffer into which the data is read

length the number of bytes to read; must be less than or equal to value.length

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::BytesMessage` (p.1061).

6.16.2.13 `virtual int activemq::commands::ActiveMQBytesMessage::readBytes
(std::vector< unsigned char > & value) const throw (
cms::MessageEOFException, cms::MessageNotReadableException,
cms::CMSEException) [virtual]`

Reads a byte array from the bytes message stream. If the length of vector *value* is less than the number of bytes remaining to be read from the stream, the vector should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of vector *value*, the bytes should be read into the vector. The return value of the total number of bytes read will be less than the length of the vector, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

Parameters:

value buffer to place data in

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::BytesMessage` (p.1061).

6.16.2.14 `virtual char activemq::commands::ActiveMQBytesMessage::readChar
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]`

Reads a Char from the Bytes message stream.

Returns:

char value from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::BytesMessage` (p.1062).

6.16.2.15 `virtual double ac-
tivemq::commands::ActiveMQBytesMessage::readDouble
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]`

Reads a 64 bit double from the Bytes message stream.

Returns:

double value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1062).

6.16.2.16 virtual float activemq::commands::ActiveMQBytesMessage::readFloat
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]

Reads a 32 bit float from the Bytes message stream.

Returns:

double value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1063).

6.16.2.17 virtual int activemq::commands::ActiveMQBytesMessage::readInt
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]

Reads a 32 bit signed integer from the Bytes message stream.

Returns:

int value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1063).

6.16.2.18 virtual long long ac-
tivismq::commands::ActiveMQBytesMessage::readLong
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]

Reads a 64 bit long from the Bytes message stream.

Returns:

long long value from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1063).

6.16.2.19 virtual short activemq::commands::ActiveMQBytesMessage::readShort
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]

Reads a 16 bit signed short from the Bytes message stream.

Returns:

short value from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1064).

6.16.2.20 virtual std::string ac-
tivismq::commands::ActiveMQBytesMessage::readString
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]

Reads an ASCII String from the Bytes message stream.

Returns:

String from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::BytesMessage** (p.1064).

6.16.2.21 virtual unsigned short activemq::commands::ActiveMQBytesMessage::readUnsignedShort
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]

Reads a 16 bit unsigned short from the Bytes message stream.

Returns:

unsigned short value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements cms::BytesMessage (p.1064).

6.16.2.22 virtual std::string activemq::commands::ActiveMQBytesMessage::readUTF
() const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSException) [virtual]

Reads an UTF String from the BytesMessage stream.

Returns:

String from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements cms::BytesMessage (p.1065).

6.16.2.23 virtual void activemq::commands::ActiveMQBytesMessage::reset ()
throw (cms::MessageFormatException, cms::CMSException) [virtual]

Puts the message body in read-only mode and repositions the stream of bytes to the beginning.

Exceptions:

CMSException - If the provider fails to perform the reset operation.

MessageFormatException - If the Message (p.2516) has an invalid format.

Implements cms::BytesMessage (p.1065).

6.16.2.24 `virtual void activemq::commands::ActiveMQBytesMessage::setBodyBytes (const unsigned char * buffer, int numBytes) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

sets the bytes given to the message body.

Parameters:

buffer Byte Buffer to copy

numBytes Number of bytes in Buffer to copy

Exceptions:

CMSException - If an internal error occurs.

MessageNotWriteableException - if in Read Only Mode.

Implements `cms::BytesMessage` (p.1065).

6.16.2.25 `virtual std::string activemq::commands::ActiveMQBytesMessage::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::Message` (p.2530).

6.16.2.26 `virtual void activemq::commands::ActiveMQBytesMessage::writeBoolean (bool value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Writes a boolean to the bytes message stream as a 1-byte value. The value true is written as the value (byte)1; the value false is written as the value (byte)0.

Parameters:

value boolean to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements `cms::BytesMessage` (p.1066).

6.16.2.27 `virtual void activemq::commands::ActiveMQBytesMessage::writeByte (unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Writes a byte to the bytes message stream as a 1-byte value.

Parameters:

value byte to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p.1066).

6.16.2.28 virtual void activemq::commands::ActiveMQBytesMessage::writeBytes (const unsigned char * *value*, int *offset*, int *length*) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]

Writes a portion of a byte array to the bytes message stream. size as the number of bytes to write.

Parameters:

value bytes to write to the stream

offset the initial offset within the byte array

length the number of bytes to use

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p.1066).

6.16.2.29 virtual void activemq::commands::ActiveMQBytesMessage::writeBytes (const std::vector< unsigned char > & *value*) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]

Writes a byte array to the bytes message stream using the vector size as the number of bytes to write.

Parameters:

value bytes to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p.1067).

6.16.2.30 virtual void activemq::commands::ActiveMQBytesMessage::writeChar (char *value*) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]

Writes a char to the bytes message stream as a 1-byte value.

Parameters:

value char to write to the stream

Exceptions:

CMSEException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1067).

6.16.2.31 `virtual void activemq::commands::ActiveMQBytesMessage::writeDouble
(double value) throw (cms::MessageNotWriteableException,
cms::CMSEException) [virtual]`

Writes a double to the bytes message stream as a 8 byte value.

Parameters:

value double to write to the stream

Exceptions:

CMSEException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1067).

6.16.2.32 `virtual void activemq::commands::ActiveMQBytesMessage::writeFloat
(float value) throw (cms::MessageNotWriteableException,
cms::CMSEException) [virtual]`

Writes a float to the bytes message stream as a 4 byte value.

Parameters:

value float to write to the stream

Exceptions:

CMSEException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1068).

6.16.2.33 `virtual void activemq::commands::ActiveMQBytesMessage::writeInt (int
value) throw (cms::MessageNotWriteableException, cms::CMSEException
) [virtual]`

Writes a signed int to the bytes message stream as a 4 byte value.

Parameters:

value signed int to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1068).

6.16.2.34 virtual void activemq::commands::ActiveMQBytesMessage::writeLong
(long long *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a long long to the bytes message stream as a 8 byte value.

Parameters:

value signed long long to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1068).

6.16.2.35 virtual void activemq::commands::ActiveMQBytesMessage::writeShort
(short *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a signed short to the bytes message stream as a 2 byte value.

Parameters:

value signed short to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1069).

6.16.2.36 virtual void activemq::commands::ActiveMQBytesMessage::writeString
(const std::string & *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes an ASCII String to the Bytes message stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::BytesMessage** (p. 1069).

6.16.2.37 virtual void activemq::commands::ActiveMQBytesMessage::writeUnsignedShort (unsigned short *value*) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]

Writes a unsigned short to the bytes message stream as a 2 byte value.

Parameters:

value unsigned short to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements cms::BytesMessage (p. 1069).

6.16.2.38 virtual void activemq::commands::ActiveMQBytesMessage::writeUTF (const std::string & *value*) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]

Writes an UTF String to the BytesMessage stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of bytes stream has been reached.

MessageNotReadableException - if the message is in write-only mode.

Implements cms::BytesMessage (p. 1070).

6.16.3 Field Documentation

6.16.3.1 const unsigned char activemq::commands::ActiveMQBytesMessage::ID_ - ACTIVEMQBYTESMESSAGE = 24 [static]

The documentation for this class was generated from the following file:

- src/main/activemq/commands/**ActiveMQBytesMessage.h**

6.17

activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller

Class Reference

6.17 ~~activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller~~²⁴⁹

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.249).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBytesMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual **~ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.17.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.249). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.17.2 Constructor & Destructor Documentation

6.17.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.17.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.17.3 Member Function Documentation

6.17.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.17.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.17.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.17

activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller

Class Reference

251

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2699).

6.17.3.4 virtual void ac-

```
ativemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2699).

6.17.3.5 virtual int ac-

```
ativemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2700).

6.17.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

6.17.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBytesMessageMarshaller.h`

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 253).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBytesMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual **~ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.18.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 253). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.18.2 Constructor & Destructor Documentation

6.18.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.18.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.18.3 Member Function Documentation

6.18.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.18.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.18.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.18

activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller

Class Reference

255

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2714).

6.18.3.4 virtual void ac-

```
ativemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2714).

6.18.3.5 virtual int ac-

```
ativemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2715).

6.18.3.6 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

6.18.3.7 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBytesMessageMarshaller.h`

6.19

activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller

Class Reference

6.19 ~~activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller~~²⁵⁷

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.257).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBytesMessageMarshaller.h> Include diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual ~**ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.19.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.257). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.19.2 Constructor & Destructor Documentation

6.19.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.19.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.19.3 Member Function Documentation

6.19.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.19.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.19.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.19

activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller

Class Reference

259

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2709).

6.19.3.4 virtual void ac-

```
ativemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2709).

6.19.3.5 virtual int ac-

```
ativemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2710).

6.19.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

6.19.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQBytesMessageMarshaller.h`

6.20

activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller

Class Reference

6.20 ~~activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller~~²⁶¹

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.261).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBytesMessageMarshaller.h> Include diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual ~**ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.20.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.261). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.20.2 Constructor & Destructor Documentation

6.20.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.20.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.20.3 Member Function Documentation

6.20.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.20.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.20.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::looseMarshal(const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.20

activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller

Class Reference

263

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2694).

6.20.3.4 virtual void ac-

```
timemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2694).

6.20.3.5 virtual int ac-

```
timemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2695).

6.20.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

6.20.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBytesMessageMarshaller.h`

6.21

activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller

Class Reference

6.21 ~~activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller~~²⁶⁵

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.265).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBytesMessageMarshaller.h> Include diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual ~**ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.21.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p.265). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.21.2 Constructor & Destructor Documentation

6.21.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.21.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.21.3 Member Function Documentation

6.21.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.21.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.21.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.21

activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller

Class Reference

267

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2719).

6.21.3.4 virtual void ac-

```
ativemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2719).

6.21.3.5 virtual int ac-

```
ativemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2720).

6.21.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

6.21.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQBytesMessageMarshaller.h`

6.22

activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller

Class Reference

6.22 ~~activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller~~²⁶⁹

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 269).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBytesMessageMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller:

Public Member Functions

- **ActiveMQBytesMessageMarshaller** ()
- virtual **~ActiveMQBytesMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.22.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 269). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.22.2 Constructor & Destructor Documentation

6.22.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::ActiveMQBytesMessageMarshaller()` [inline]

6.22.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::~~ActiveMQBytesMessageMarshaller()` [inline, virtual]

6.22.3 Member Function Documentation

6.22.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.22.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.22.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.22

activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller

Class Reference

271

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2704).

6.22.3.4 virtual void ac-

```
ativemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn) throw (
    decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2704).

6.22.3.5 virtual int ac-

```
ativemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException )
[virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2705).

6.22.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

6.22.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQBytesMessageMarshaller.h`

6.23 activemq::core::ActiveMQConnection Class Reference

Concrete connection used for all connectors to the ActiveMQ broker.

#include <src/main/activemq/core/ActiveMQConnection.h> Inheritance diagram for activemq::core::ActiveMQConnection:

Public Member Functions

- **ActiveMQConnection** (const **Pointer**< **transport::Transport** > &transport, const **Pointer**< **decaf::util::Properties** > &properties)

Constructor.

- virtual ~**ActiveMQConnection** ()
- virtual void **removeSession** (**ActiveMQSession** *session) throw (cms::CMSException)

Removes the session resources for the given session instance.

- virtual void **addProducer** (**ActiveMQProducer** *producer) throw (cms::CMSException)

Adds an active Producer to the Set of known producers.

- virtual void **removeProducer** (const **Pointer**< **commands::ProducerId** > &producerId) throw (cms::CMSException)

Removes an active Producer to the Set of known producers.

- virtual void **addDispatcher** (const **Pointer**< **commands::ConsumerId** > &consumer, **Dispatcher** *dispatcher) throw (cms::CMSException)

Adds a dispatcher for a consumer.

- virtual void **removeDispatcher** (const **Pointer**< **commands::ConsumerId** > &consumer) throw (cms::CMSException)

Removes the dispatcher for a consumer.

- virtual void **sendPullRequest** (const **commands::ConsumerInfo** *consumer, long long timeout) throw (exceptions::ActiveMQException)

If supported sends a message pull request to the service provider asking for the delivery of a new message.

- bool **isClosed** () const

Checks if this connection has been closed.

- bool **isStarted** () const

Check if this connection has been started.

- bool **isTransportFailed** () const

Checks if the Connection's Transport has failed.

- virtual void **destroyDestination** (const **commands::ActiveMQDestination** *destination) throw (**decaf::lang::exceptions::NullPointerException**, **decaf::lang::exceptions::IllegalStateException**, **decaf::lang::exceptions::UnsupportedOperationException**, **activemq::exceptions::ActiveMQException**)

Requests that the Broker removes the given Destination.

- virtual void **destroyDestination** (const **cms::Destination** *destination) throw (**decaf::lang::exceptions::NullPointerException**, **decaf::lang::exceptions::IllegalStateException**, **decaf::lang::exceptions::UnsupportedOperationException**, **activemq::exceptions::ActiveMQException**)

Requests that the Broker removes the given Destination.

- virtual const **cms::ConnectionMetaData** * **getMetaData** () const throw (**cms::CMSEException**)

Gets the metadata for this connection.

- virtual **cms::Session** * **createSession** () throw (**cms::CMSEException**)

Creates a new Session to work for this Connection.

- virtual std::string **getClientID** () const

*Get the Client Id for this session, the client Id is provider specific and is either assigned by the connection factory or set using the **setClientID** method.*

Returns:

*Client Id String for this **Connection** (p. 1262).*

Exceptions:

CMSEException (p. 1160) if the provider fails to return the client id or an internal error occurs.

- virtual void **setClientID** (const std::string &clientID)

Sets the client identifier for this connection.

*The preferred way to assign a CMS client's client identifier is for it to be configured in a client-specific **ConnectionFactory** (p. 1324) object and transparently assigned to the **Connection** (p. 1262) object it creates.*

*If a client sets the client identifier explicitly, it must do so immediately after it creates the connection and before any other action on the connection is taken. After this point, setting the client identifier is a programming error that should throw an **IllegalStateException** (p. 1997).*

Parameters:

clientID *The unique client identifier to assign to the **Connection** (p. 1262).*

Exceptions:

CMSEException (p. 1160) if the provider fails to set the client id due to some internal error.

InvalidClientIDException if the id given is somehow invalid or is a duplicate.

IllegalStateException (p. 1997) if the client tries to set the id after a **Connection** (p. 1262) method has been called.

- virtual **cms::Session** * **createSession** (**cms::Session::AcknowledgeMode** ackMode) throw (**cms::CMSEException**)

Creates a new Session to work for this Connection using the specified acknowledgment mode.

- virtual void **close** () throw (**cms::CMSEException**)

Closes this connection as well as any Sessions created from it (and those Sessions' consumers and producers).

- virtual void **start** () throw (cms::CMSException)
Starts or (restarts) a connections delivery of incoming messages.
- virtual void **stop** () throw (cms::CMSException)
Stop the flow of incoming messages.
- virtual cms::ExceptionListener * **getExceptionListener** () const
Gets the registered Exception Listener for this connection.
- virtual void **setExceptionListener** (cms::ExceptionListener *listener)
Sets the registered Exception Listener for this connection.
- void **setUsername** (const std::string &username)
Sets the username that should be used when creating a new connection.
- const std::string & **getUsername** () const
Gets the username that this factory will use when creating a new connection instance.
- void **setPassword** (const std::string &password)
Sets the password that should be used when creating a new connection.
- const std::string & **getPassword** () const
Gets the password that this factory will use when creating a new connection instance.
- void **setDefaultClientId** (const std::string &clientId)
Sets the Client Id.
- void **setBrokerURL** (const std::string &brokerURL)
Sets the Broker URL that should be used when creating a new connection instance.
- const std::string & **getBrokerURL** () const
Gets the Broker URL that this factory will use when creating a new connection instance.
- void **setPrefetchPolicy** (PrefetchPolicy *policy)
*Sets the **PrefetchPolicy** (p. 2976) instance that this factory should use when it creates new Connection instances.*
- PrefetchPolicy * **getPrefetchPolicy** () const
*Gets the pointer to the current **PrefetchPolicy** (p. 2976) that is in use by this ConnectionFactory.*
- void **setRedeliveryPolicy** (RedeliveryPolicy *policy)
*Sets the **RedeliveryPolicy** (p. 3177) instance that this factory should use when it creates new Connection instances.*
- RedeliveryPolicy * **getRedeliveryPolicy** () const
*Gets the pointer to the current **RedeliveryPolicy** (p. 3177) that is in use by this ConnectionFactory.*

- **bool isDispatchAsync () const**
- **void setDispatchAsync (bool value)**
Should messages be dispatched synchronously or asynchronously from the producer thread for non-durable topics in the broker? For fast consumers set this to false.
- **bool isAlwaysSyncSend () const**
Gets if the Connection should always send things Synchronously.
- **void setAlwaysSyncSend (bool value)**
Sets if the Connection should always send things Synchronously.
- **bool isUseAsyncSend () const**
Gets if the useAsyncSend option is set.
- **void setUseAsyncSend (bool value)**
Sets the useAsyncSend option.
- **bool isUseCompression () const**
Gets if the Connection is configured for Message body compression.
- **void setUseCompression (bool value)**
Sets whether Message body compression is enabled.
- **unsigned int getSendTimeout () const**
Gets the assigned send timeout for this Connector.
- **void setSendTimeout (unsigned int timeout)**
Sets the send timeout to use when sending Message objects, this will cause all messages to be sent using a Synchronous request is non-zero.
- **unsigned int getCloseTimeout () const**
Gets the assigned close timeout for this Connector.
- **void setCloseTimeout (unsigned int timeout)**
Sets the close timeout to use when sending the disconnect request.
- **unsigned int getProducerWindowSize () const**
Gets the configured producer window size for Producers that are created from this connector.
- **void setProducerWindowSize (unsigned int windowSize)**
Sets the size in Bytes of messages that a producer can send before it is blocked to await a ProducerAck from the broker that frees enough memory to allow another message to be sent.
- **long long getNextSessionId ()**
Get the Next available Session Id.
- **long long getNextTempDestinationId ()**
Get the Next Temporary Destination Id.
- **long long getNextLocalTransactionId ()**

Get the Next Temporary Destination Id.

- void **addTransportListener** (**transport::TransportListener** *transportListener)
*Adds a **transport** (p. 97) listener so that a client can be notified of events in the underlying **transport** (p. 97), client's are always notified after the event has been processed by the **Connection** class.*
- void **removeTransportListener** (**transport::TransportListener** *transportListener)
*Removes a registered **TransportListener** from the **Connection**'s set of **Transport** listeners, this listener will no longer receive any **Transport** related events.*
- virtual void **onCommand** (const **Pointer**< **commands::Command** > &command)
*Event handler for the receipt of a non-response command from the **transport** (p. 97).*
- virtual void **onException** (const **decaf::lang::Exception** &ex)
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **transportInterrupted** ()
*The **transport** (p. 97) has suffered an interruption from which it hopes to recover.*
- virtual void **transportResumed** ()
*The **transport** (p. 97) has resumed after an interruption.*
- const **commands::ConnectionInfo** & **getConnectionInfo** () const throw (exceptions::ActiveMQException)
*Gets the **ConnectionInfo** for this **Object**, if the **Connection** is not open than this method throws an exception.*
- const **commands::ConnectionId** & **getConnectionId** () const throw (exceptions::ActiveMQException)
*Gets the **ConnectionId** for this **Object**, if the **Connection** is not open than this method throws an exception.*
- **transport::Transport** & **getTransport** () const
*Gets a reference to this object's **Transport** instance.*
- void **oneway** (**Pointer**< **commands::Command** > command) throw (activemq::exceptions::ActiveMQException)
Sends a oneway message.
- void **syncRequest** (**Pointer**< **commands::Command** > command, unsigned int timeout=0) throw (activemq::exceptions::ActiveMQException)
Sends a synchronous request and returns the response from the broker.
- virtual void **fire** (const exceptions::ActiveMQException &ex)
Notify the exception listener.
- void **setTransportInterruptionProcessingComplete** ()
*Indicates that a **Connection** resource that is processing the **transportInterrupted** event has completed.*

6.23.1 Detailed Description

Concrete connection used for all connectors to the ActiveMQ broker.

Since:

2.0

6.23.2 Constructor & Destructor Documentation

6.23.2.1 `activemq::core::ActiveMQConnection::ActiveMQConnection (const Pointer< transport::Transport > & transport, const Pointer< decaf::util::Properties > & properties)`

Constructor.

Parameters:

transport (p. 97) The Transport requested for this connection to the Broker.
properties The Properties that were defined for this connection

6.23.2.2 `virtual activemq::core::ActiveMQConnection::~~ActiveMQConnection ()`
 [virtual]

6.23.3 Member Function Documentation

6.23.3.1 `virtual void activemq::core::ActiveMQConnection::addDispatcher (const Pointer< commands::ConsumerId > & consumer, Dispatcher * dispatcher) throw (cms::CMSException)` [virtual]

Adds a dispatcher for a consumer.

Parameters:

consumer - The consumer for which to register a dispatcher.
dispatcher - The dispatcher to handle incoming messages for the consumer.

6.23.3.2 `virtual void activemq::core::ActiveMQConnection::addProducer (ActiveMQProducer * producer) throw (cms::CMSException)` [virtual]

Adds an active Producer to the Set of known producers.

Parameters:

producer - The Producer to add from the the known set.

6.23.3.3 `void activemq::core::ActiveMQConnection::addTransportListener (transport::TransportListener * transportListener)`

Adds a **transport** (p.97) listener so that a client can be notified of events in the underlying **transport** (p.97), client's are always notified after the event has been processed by the Connection class. Client's should ensure that the registered listener does not block or take a long amount of time to execute in order to not degrade performance of this Connection.

Parameters:

transportListener The TransportListener instance to add to this Connection's set of listeners to notify of Transport events.

6.23.3.4 virtual void activemq::core::ActiveMQConnection::close () throw (cms::CMSException) [virtual]

Closes this connection as well as any Sessions created from it (and those Sessions' consumers and producers).

Exceptions:

CMSException

Implements **cms::Connection** (p. 1263).

6.23.3.5 virtual cms::Session* activemq::core::ActiveMQConnection::createSession (cms::Session::AcknowledgeMode *ackMode*) throw (cms::CMSException) [virtual]

Creates a new Session to work for this Connection using the specified acknowledgment mode.

Parameters:

ackMode the Acknowledgment Mode to use.

Exceptions:

CMSException

Implements **cms::Connection** (p. 1264).

6.23.3.6 virtual cms::Session* activemq::core::ActiveMQConnection::createSession () throw (cms::CMSException) [virtual]

Creates a new Session to work for this Connection.

Exceptions:

CMSException

Implements **cms::Connection** (p. 1264).

6.23.3.7 virtual void activemq::core::ActiveMQConnection::destroyDestination (const cms::Destination * *destination*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::UnsupportedOperationException, activemq::exceptions::ActiveMQException) [virtual]

Requests that the Broker removes the given Destination. Calling this method implies that the client is finished with the Destination and that no other messages will be sent or received for the given Destination. The Broker frees all resources it has associated with this Destination.

Parameters:

destination The CMS Destination the Broker will be requested to remove.

Exceptions:

NullPointerException If the passed Destination is Null

IllegalStateException If the connection is closed.

UnsupportedOperationException If the wire format in use does not support this operation.

ActiveMQException If any other error occurs during the attempt to destroy the destination.

```
6.23.3.8  virtual void activemq::core::ActiveMQConnection::destroyDestination
          (const commands::ActiveMQDestination * destination)
          throw ( decaf::lang::exceptions::NullPointerException,
                  decaf::lang::exceptions::IllegalStateException, de-
                  ccaf::lang::exceptions::UnsupportedOperationException,
                  activemq::exceptions::ActiveMQException ) [virtual]
```

Requests that the Broker removes the given Destination. Calling this method implies that the client is finished with the Destination and that no other messages will be sent or received for the given Destination. The Broker frees all resources it has associated with this Destination.

Parameters:

destination The Destination the Broker will be requested to remove.

Exceptions:

NullPointerException If the passed Destination is Null

IllegalStateException If the connection is closed.

UnsupportedOperationException If the wire format in use does not support this operation.

ActiveMQException If any other error occurs during the attempt to destroy the destination.

```
6.23.3.9  virtual void activemq::core::ActiveMQConnection::fire (const
          exceptions::ActiveMQException & ex) [virtual]
```

Notify the exception listener.

Parameters:

ex the exception to fire

```
6.23.3.10  const std::string& activemq::core::ActiveMQConnection::getBrokerURL
          () const
```

Gets the Broker URL that this factory will use when creating a new connection instance.

Returns:

brokerURL string

6.23.3.11 `virtual std::string activemq::core::ActiveMQConnection::getClientID ()
const [virtual]`

Get the Client Id for this session, the client Id is provider specific and is either assigned by the connection factory or set using the setClientID method.

Returns:

Client Id String for this **Connection** (p. 1262).

Exceptions:

CMSEException (p. 1160) if the provider fails to return the client id or an internal error occurs.

Implements **cms::Connection** (p. 1264).

6.23.3.12 `unsigned int activemq::core::ActiveMQConnection::getCloseTimeout ()
const`

Gets the assigned close timeout for this Connector.

Returns:

the close timeout configured in the connection uri

6.23.3.13 `const commands::ConnectionId& ac-
tivemq::core::ActiveMQConnection::getConnectionId ()
const throw (exceptions::ActiveMQException)`

Gets the ConnectionId for this Object, if the Connection is not open than this method throws an exception.

6.23.3.14 `const commands::ConnectionInfo& ac-
tivemq::core::ActiveMQConnection::getConnectionInfo ()
const throw (exceptions::ActiveMQException)`

Gets the ConnectionInfo for this Object, if the Connection is not open than this method throws an exception.

6.23.3.15 `virtual cms::ExceptionListener* ac-
tivemq::core::ActiveMQConnection::getExceptionListener
() const [virtual]`

Gets the registered Exception Listener for this connection.

Returns:

pointer to an exception listener or NULL

Implements **cms::Connection** (p. 1264).

6.23.3.16 `virtual const cms::ConnectionMetaData* activemq::core::ActiveMQConnection::getMetaData () const throw (cms::CMSException) [inline, virtual]`

Gets the metadata for this connection.

Returns:

the connection MetaData pointer (caller does not own it).

Exceptions:

CMSException if the provider fails to get the connection metadata for this connection.

See also:

ConnectionMetaData

Since:

2.0

Implements **cms::Connection** (p. 1265).

6.23.3.17 `long long activemq::core::ActiveMQConnection::getNextLocalTransactionId ()`

Get the Next Temporary Destination Id.

Returns:

the next id in the sequence.

6.23.3.18 `long long activemq::core::ActiveMQConnection::getNextSessionId ()`

Get the Next available Session Id.

Returns:

the next id in the sequence.

6.23.3.19 `long long activemq::core::ActiveMQConnection::getNextTempDestinationId ()`

Get the Next Temporary Destination Id.

Returns:

the next id in the sequence.

6.23.3.20 `const std::string& activemq::core::ActiveMQConnection::getPassword () const`

Gets the password that this factory will use when creating a new connection instance.

Returns:

password string, "" for default credentials

6.23.3.21 `PrefetchPolicy* activemq::core::ActiveMQConnection::getPrefetchPolicy () const`

Gets the pointer to the current **PrefetchPolicy** (p. 2976) that is in use by this ConnectionFactory.

Returns:

a pointer to this objects **PrefetchPolicy** (p. 2976).

6.23.3.22 `unsigned int activemq::core::ActiveMQConnection::getProducerWindowSize () const`

Gets the configured producer window size for Producers that are created from this connector. This only applies if there is no send timeout and the producer is able to send asynchronously.

Returns:

size in bytes of messages that this producer can produce before it must block and wait for ProducerAck messages to free resources.

6.23.3.23 `RedeliveryPolicy* activemq::core::ActiveMQConnection::getRedeliveryPolicy () const`

Gets the pointer to the current **RedeliveryPolicy** (p. 3177) that is in use by this ConnectionFactory.

Returns:

a pointer to this objects **RedeliveryPolicy** (p. 3177).

6.23.3.24 `unsigned int activemq::core::ActiveMQConnection::getSendTimeout () const`

Gets the assigned send timeout for this Connector.

Returns:

the send timeout configured in the connection uri

6.23.3.25 `transport::Transport& activemq::core::ActiveMQConnection::getTransport () const`

Gets a reference to this object's Transport instance.

Returns:

a reference to the Transport that is in use by this Connection.

6.23.3.26 `const std::string& activemq::core::ActiveMQConnection::getUsername () const`

Gets the username that this factory will use when creating a new connection instance.

Returns:

username string, "" for default credentials

6.23.3.27 `bool activemq::core::ActiveMQConnection::isAlwaysSyncSend () const`

Gets if the Connection should always send things Synchronously.

Returns:

true if sends should always be Synchronous.

6.23.3.28 `bool activemq::core::ActiveMQConnection::isClosed () const [inline]`

Checks if this connection has been closed.

Returns:

true if the connection is closed

6.23.3.29 `bool activemq::core::ActiveMQConnection::isDispatchAsync () const`

Returns:

The value of the dispatch asynchronously option sent to the broker.

6.23.3.30 `bool activemq::core::ActiveMQConnection::isStarted () const [inline]`

Check if this connection has been started.

Returns:

true if the start method has been called.

6.23.3.31 `bool activemq::core::ActiveMQConnection::isTransportFailed () const`
[inline]

Checks if the Connection's Transport has failed.

Returns:

true if the Connection's Transport has failed.

6.23.3.32 `bool activemq::core::ActiveMQConnection::isUseAsyncSend () const`

Gets if the useAsyncSend option is set.

Returns:

true if on false if not.

6.23.3.33 `bool activemq::core::ActiveMQConnection::isUseCompression () const`

Gets if the Connection is configured for Message body compression.

Returns:

if the Message body will be Compressed or not.

6.23.3.34 `virtual void activemq::core::ActiveMQConnection::onCommand (const
Pointer< commands::Command > & command)` [virtual]

Event handler for the receipt of a non-response command from the **transport** (p. 97).

Parameters:

command the received command object.

Implements `activemq::transport::TransportListener` (p. 3900).

6.23.3.35 `void activemq::core::ActiveMQConnection::oneway
(Pointer< commands::Command > command) throw (
activemq::exceptions::ActiveMQException)`

Sends a oneway message.

Parameters:

command The message to send.

Exceptions:

ConnectorException if not currently connected, or if the operation fails for any reason.

6.23.3.36 `virtual void activemq::core::ActiveMQConnection::onException (const decaf::lang::Exception & ex) [virtual]`

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception.

Implements **activemq::transport::TransportListener** (p. 3901).

6.23.3.37 `virtual void activemq::core::ActiveMQConnection::removeDispatcher (const Pointer< commands::ConsumerId > & consumer) throw (cms::CMSException) [virtual]`

Removes the dispatcher for a consumer.

Parameters:

consumer - The consumer for which to remove the dispatcher.

6.23.3.38 `virtual void activemq::core::ActiveMQConnection::removeProducer (const Pointer< commands::ProducerId > & producerId) throw (cms::CMSException) [virtual]`

Removes an active Producer to the Set of known producers.

Parameters:

producerId - The ProducerId to remove from the the known set.

6.23.3.39 `virtual void activemq::core::ActiveMQConnection::removeSession (ActiveMQSession * session) throw (cms::CMSException) [virtual]`

Removes the session resources for the given session instance.

Parameters:

session The session to be unregistered from this connection.

6.23.3.40 `void activemq::core::ActiveMQConnection::removeTransportListener (transport::TransportListener * transportListener)`

Removes a registered TransportListener from the Connection's set of Transport listeners, this listener will no longer receive any Transport related events. The caller is responsible for freeing the listener in all cases.

Parameters:

transportListener The pointer to the TransportListener to remove from the set of listeners.

6.23.3.41 `virtual void activemq::core::ActiveMQConnection::sendPullRequest (const commands::ConsumerInfo * consumer, long long timeout) throw (exceptions::ActiveMQException)` [virtual]

If supported sends a message pull request to the service provider asking for the delivery of a new message. This is used in the case where the service provider has been configured with a zero prefetch or is only capable of delivering messages on a pull basis.

Parameters:

consumer - the ConsumerInfo for the requesting Consumer.

timeout - the time that the client is willing to wait.

6.23.3.42 `void activemq::core::ActiveMQConnection::setAlwaysSyncSend (bool value)`

Sets if the Connection should always send things Synchronously.

Parameters:

value true if sends should always be Synchronous.

6.23.3.43 `void activemq::core::ActiveMQConnection::setBrokerURL (const std::string & brokerURL)`

Sets the Broker URL that should be used when creating a new connection instance.

Parameters:

brokerURL string

6.23.3.44 `virtual void activemq::core::ActiveMQConnection::setClientID (const std::string & clientID)` [virtual]

Sets the client identifier for this connection.

The preferred way to assign a CMS client's client identifier is for it to be configured in a client-specific **ConnectionFactory** (p.1324) object and transparently assigned to the **Connection** (p.1262) object it creates.

If a client sets the client identifier explicitly, it must do so immediately after it creates the connection and before any other action on the connection is taken. After this point, setting the client identifier is a programming error that should throw an **IllegalStateException** (p.1997).

Parameters:

clientID The unique client identifier to assign to the **Connection** (p.1262).

Exceptions:

CMSException (p. 1160) if the provider fails to set the client id due to some internal error.

InvalidClientIDException if the id given is somehow invalid or is a duplicate.

IllegalStateException (p. 1997) if the client tries to set the id after a **Connection** (p. 1262) method has been called.

Implements **cms::Connection** (p. 1265).

6.23.3.45 `void activemq::core::ActiveMQConnection::setCloseTimeout (unsigned int timeout)`

Sets the close timeout to use when sending the disconnect request.

Parameters:

timeout - The time to wait for a close message.

6.23.3.46 `void activemq::core::ActiveMQConnection::setDefaultClientId (const std::string & clientId)`

Sets the Client Id.

Parameters:

clientId - The new clientId value.

6.23.3.47 `void activemq::core::ActiveMQConnection::setDispatchAsync (bool value)`

Should messages be dispatched synchronously or asynchronously from the producer thread for non-durable topics in the broker? For fast consumers set this to false. For slow consumers set it to true so that dispatching will not block fast consumers. .

Parameters:

value The value of the dispatch asynchronously option sent to the broker.

6.23.3.48 `virtual void activemq::core::ActiveMQConnection::setExceptionListener (cms::ExceptionListener * listener) [virtual]`

Sets the registered Exception Listener for this connection.

Parameters:

listener pointer to and ExceptionListener

Implements **cms::Connection** (p. 1265).

6.23.3.49 `void activemq::core::ActiveMQConnection::setPassword (const std::string & password)`

Sets the password that should be used when creating a new connection.

Parameters:

password string

6.23.3.50 void activemq::core::ActiveMQConnection::setPrefetchPolicy
(PrefetchPolicy * *policy*)

Sets the **PrefetchPolicy** (p. 2976) instance that this factory should use when it creates new Connection instances. The **PrefetchPolicy** (p. 2976) passed becomes the property of the factory and will be deleted when the factory is destroyed.

Parameters:

policy The new **PrefetchPolicy** (p. 2976) that the ConnectionFactory should clone for Connections.

6.23.3.51 void activemq::core::ActiveMQConnection::setProducerWindowSize
(unsigned int *windowSize*)

Sets the size in Bytes of messages that a producer can send before it is blocked to await a ProducerAck from the broker that frees enough memory to allow another message to be sent.

Parameters:

windowSize - The size in bytes of the Producers memory window.

6.23.3.52 void activemq::core::ActiveMQConnection::setRedeliveryPolicy
(RedeliveryPolicy * *policy*)

Sets the **RedeliveryPolicy** (p. 3177) instance that this factory should use when it creates new Connection instances. The **RedeliveryPolicy** (p. 3177) passed becomes the property of the factory and will be deleted when the factory is destroyed.

Parameters:

policy The new **RedeliveryPolicy** (p. 3177) that the ConnectionFactory should clone for Connections.

6.23.3.53 void activemq::core::ActiveMQConnection::setSendTimeout (unsigned int *timeout*)

Sets the send timeout to use when sending Message objects, this will cause all messages to be sent using a Synchronous request is non-zero.

Parameters:

timeout - The time to wait for a response.

6.23.3.54 void activemq::core::ActiveMQConnection::setTransportInterruptProcessingComplete
()

Indicates that a Connection resource that is processing the transportInterrupted event has completed.

6.23.3.55 `void activemq::core::ActiveMQConnection::setUseAsyncSend (bool value)`

Sets the useAsyncSend option.

Parameters:

value - true to activate, false to disable.

6.23.3.56 `void activemq::core::ActiveMQConnection::setUseCompression (bool value)`

Sets whether Message body compression is enabled.

Parameters:

value Boolean indicating if Message body compression is enabled.

6.23.3.57 `void activemq::core::ActiveMQConnection::setUsername (const std::string & username)`

Sets the username that should be used when creating a new connection.

Parameters:

username string

6.23.3.58 `virtual void activemq::core::ActiveMQConnection::start () throw (cms::CMSEException) [virtual]`

Starts or (restarts) a connections delivery of incoming messages.

Exceptions:

CMSEException

Implements `cms::Startable` (p. 3586).

6.23.3.59 `virtual void activemq::core::ActiveMQConnection::stop () throw (cms::CMSEException) [virtual]`

Stop the flow of incoming messages.

Exceptions:

CMSEException

Implements `cms::Stoppable` (p. 3648).

6.23.3.60 `void activemq::core::ActiveMQConnection::syncRequest (Pointer< commands::Command > command, unsigned int timeout = 0) throw (activemq::exceptions::ActiveMQException)`

Sends a synchronous request and returns the response from the broker. Converts any error responses into an exception.

Parameters:

command The request command.

timeout The time to wait for a response, default is zero or infinite.

Exceptions:

ConnectorException thrown if an error response was received from the broker, or if any other error occurred.

6.23.3.61 `virtual void activemq::core::ActiveMQConnection::transportInterrupted () [virtual]`

The **transport** (p.97) has suffered an interruption from which it hopes to recover.

Implements **activemq::transport::TransportListener** (p.3901).

6.23.3.62 `virtual void activemq::core::ActiveMQConnection::transportResumed () [virtual]`

The **transport** (p.97) has resumed after an interruption.

Implements **activemq::transport::TransportListener** (p.3901).

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQConnection.h`

6.24 activemq::core::ActiveMQConnectionFactory Class Reference

#include <src/main/activemq/core/ActiveMQConnectionFactory.h> Inheritance diagram for activemq::core::ActiveMQConnectionFactory:

Public Member Functions

- **ActiveMQConnectionFactory** ()
- **ActiveMQConnectionFactory** (const std::string &url, const std::string &username="", const std::string &password="")
Constructor.
- virtual ~**ActiveMQConnectionFactory** ()
- virtual **cms::Connection * createConnection** () throw (cms::CMSException)
Creates a connection with the default user identity.
- virtual **cms::Connection * createConnection** (const std::string &username, const std::string &password) throw (cms::CMSException)
Creates a connection with the specified user identity.
- virtual **cms::Connection * createConnection** (const std::string &username, const std::string &password, const std::string &clientId) throw (cms::CMSException)
Creates a connection with the specified user identity.
- void **setUsername** (const std::string &username)
Sets the username that should be used when creating a new connection.
- const std::string & **getUsername** () const
Gets the username that this factory will use when creating a new connection instance.
- void **setPassword** (const std::string &password)
Sets the password that should be used when creating a new connection.
- const std::string & **getPassword** () const
Gets the password that this factory will use when creating a new connection instance.
- std::string **getClientId** () const
Gets the Configured Client Id.
- void **setClientId** (const std::string &clientId)
Sets the Client Id.
- void **setBrokerURL** (const std::string &brokerURL)
Sets the Broker URL that should be used when creating a new connection instance.
- const std::string & **getBrokerURL** () const

Gets the Broker URL that this factory will use when creating a new connection instance.

- **void setExceptionListener (cms::ExceptionListener *listener)**
Set an CMS ExceptionListener that will be set on eat connection once it has been created.
- **cms::ExceptionListener * getExceptionListener () const**
Returns the currently set ExceptionListener that will be set on any new Connection instance that is created by this factory.
- **void setPrefetchPolicy (PrefetchPolicy *policy)**
*Sets the **PrefetchPolicy** (p. 2976) instance that this factory should use when it creates new Connection instances.*
- **PrefetchPolicy * getPrefetchPolicy () const**
*Gets the pointer to the current **PrefetchPolicy** (p. 2976) that is in use by this ConnectionFactory.*
- **void setRedeliveryPolicy (RedeliveryPolicy *policy)**
*Sets the **RedeliveryPolicy** (p. 3177) instance that this factory should use when it creates new Connection instances.*
- **RedeliveryPolicy * getRedeliveryPolicy () const**
*Gets the pointer to the current **RedeliveryPolicy** (p. 3177) that is in use by this ConnectionFactory.*
- **bool isDispatchAsync () const**
- **void setDispatchAsync (bool value)**
Should messages be dispatched synchronously or asynchronously from the producer thread for non-durable topics in the broker? For fast consumers set this to false.
- **bool isAlwaysSyncSend () const**
Gets if the Connection should always send things Synchronously.
- **void setAlwaysSyncSend (bool value)**
Sets if the Connection should always send things Synchronously.
- **bool isUseAsyncSend () const**
Gets if the useAsyncSend option is set.
- **void setUseAsyncSend (bool value)**
Sets the useAsyncSend option.
- **bool isUseCompression () const**
Gets if the Connection is configured for Message body compression.
- **void setUseCompression (bool value)**
Sets whether Message body compression is enabled.
- **unsigned int getSendTimeout () const**
Gets the assigned send timeout for this Connector.

- void **setSendTimeout** (unsigned int timeout)
Sets the send timeout to use when sending Message objects, this will cause all messages to be sent using a Synchronous request is non-zero.
- unsigned int **getCloseTimeout** () const
Gets the assigned close timeout for this Connector.
- void **setCloseTimeout** (unsigned int timeout)
Sets the close timeout to use when sending the disconnect request.
- unsigned int **getProducerWindowSize** () const
Gets the configured producer window size for Producers that are created from this connector.
- void **setProducerWindowSize** (unsigned int windowSize)
Sets the size in Bytes of messages that a producer can send before it is blocked to await a ProducerAck from the broker that frees enough memory to allow another message to be sent.

Static Public Member Functions

- static **cms::Connection * createConnection** (const std::string &url, const std::string &username, const std::string &password, const std::string &clientId="") throw (cms::CMSException)
Creates a connection with the specified user identity.

Static Public Attributes

- static const std::string **DEFAULT_URI**

6.24.1 Constructor & Destructor Documentation

- 6.24.1.1 **activemq::core::ActiveMQConnectionFactory::ActiveMQConnectionFactory** ()
- 6.24.1.2 **activemq::core::ActiveMQConnectionFactory::ActiveMQConnectionFactory** (const std::string & *url*, const std::string & *username* = "", const std::string & *password* = "")

Constructor.

Parameters:

- url* the URL of the Broker we are connecting to.
- username* to authenticate with, defaults to ""
- password* to authenticate with, defaults to ""

6.24.1.3 **virtual**
 activemq::core::ActiveMQConnectionFactory::~~ActiveMQConnectionFactory
 () [virtual]

6.24.2 Member Function Documentation

6.24.2.1 **static cms::Connection* ac-**
 tivemq::core::ActiveMQConnectionFactory::createConnection (const
 std::string & url, const std::string & username, const std::string &
 password, const std::string & clientId = "") throw (cms::CMSEException
) [static]

Creates a connection with the specified user identity. The connection is created in stopped mode. No messages will be delivered until the Connection.start method is explicitly called.

Parameters:

url the URL of the Broker we are connecting to.
username to authenticate with
password to authenticate with
clientId to assign to connection, defaults to ""

Exceptions:

CMSEException.

6.24.2.2 **virtual cms::Connection* ac-**
 tivemq::core::ActiveMQConnectionFactory::createConnection (const
 std::string & username, const std::string & password, const std::string &
 clientId) throw (cms::CMSEException) [virtual]

Creates a connection with the specified user identity. The connection is created in stopped mode. No messages will be delivered until the Connection.start method is explicitly called. The username and password values passed here do not change the defaults, subsequent calls to the parameterless createConnection will continue to use the default values that were set in the Constructor.

Parameters:

username to authenticate with
password to authenticate with
clientId to assign to connection if "" then a random client Id is created for this connection.

Returns:

a Connection Pointer

Exceptions:

CMSEException

Implements **cms::ConnectionFactory** (p. 1325).

6.24.2.3 `virtual cms::Connection* activemq::core::ActiveMQConnectionFactory::createConnection (const std::string & username, const std::string & password) throw (cms::CMSException)` [virtual]

Creates a connection with the specified user identity. The connection is created in stopped mode. No messages will be delivered until the Connection.start method is explicitly called. The username and password values passed here do not change the defaults, subsequent calls to the parameterless createConnection will continue to use the default values that were set in the Constructor.

Parameters:

username to authenticate with

password to authenticate with

Returns:

a Connection Pointer

Exceptions:

CMSException

Implements **cms::ConnectionFactory** (p. 1326).

6.24.2.4 `virtual cms::Connection* activemq::core::ActiveMQConnectionFactory::createConnection () throw (cms::CMSException)` [virtual]

Creates a connection with the default user identity. The connection is created in stopped mode. No messages will be delivered until the Connection.start method is explicitly called.

Returns:

a Connection Pointer

Exceptions:

CMSException

Implements **cms::ConnectionFactory** (p. 1326).

6.24.2.5 `const std::string& activemq::core::ActiveMQConnectionFactory::getBrokerURL () const`

Gets the Broker URL that this factory will use when creating a new connection instance.

Returns:

brokerURL string

6.24.2.6 `std::string activemq::core::ActiveMQConnectionFactory::getClientId () const`

Gets the Configured Client Id.

Returns:

the clientId.

6.24.2.7 `unsigned int activemq::core::ActiveMQConnectionFactory::getCloseTimeout () const`

Gets the assigned close timeout for this Connector.

Returns:

the close timeout configured in the connection uri

6.24.2.8 `cms::ExceptionListener* activemq::core::ActiveMQConnectionFactory::getExceptionListener () const`

Returns the currently set ExceptionListener that will be set on any new Connection instance that is created by this factory.

Returns:

a pointer to a CMS ExceptionListener instance or NULL if not set.

6.24.2.9 `const std::string& activemq::core::ActiveMQConnectionFactory::getPassword () const`

Gets the password that this factory will use when creating a new connection instance.

Returns:

password string, "" for default credentials

6.24.2.10 `PrefetchPolicy* activemq::core::ActiveMQConnectionFactory::getPrefetchPolicy () const`

Gets the pointer to the current **PrefetchPolicy** (p. 2976) that is in use by this ConnectionFactory.

Returns:

a pointer to this objects **PrefetchPolicy** (p. 2976).

6.24.2.11 `unsigned int activemq::core::ActiveMQConnectionFactory::getProducerWindowSize () const`

Gets the configured producer window size for Producers that are created from this connector. This only applies if there is no send timeout and the producer is able to send asynchronously.

Returns:

size in bytes of messages that this producer can produce before it must block and wait for ProducerAck messages to free resources.

6.24.2.12 `RedeliveryPolicy* activemq::core::ActiveMQConnectionFactory::getRedeliveryPolicy () const`

Gets the pointer to the current **RedeliveryPolicy** (p. 3177) that is in use by this ConnectionFactory.

Returns:

a pointer to this objects **RedeliveryPolicy** (p. 3177).

6.24.2.13 `unsigned int activemq::core::ActiveMQConnectionFactory::getSendTimeout () const`

Gets the assigned send timeout for this Connector.

Returns:

the send timeout configured in the connection uri

6.24.2.14 `const std::string& activemq::core::ActiveMQConnectionFactory::getUsername () const`

Gets the username that this factory will use when creating a new connection instance.

Returns:

username string, "" for default credentials

6.24.2.15 `bool activemq::core::ActiveMQConnectionFactory::isAlwaysSyncSend () const`

Gets if the Connection should always send things Synchronously.

Returns:

true if sends should always be Synchronous.

6.24.2.16 `bool activemq::core::ActiveMQConnectionFactory::isDispatchAsync ()`
 `const`

Returns:

The value of the dispatch asynchronously option sent to the broker.

6.24.2.17 `bool activemq::core::ActiveMQConnectionFactory::isUseAsyncSend ()`
 `const`

Gets if the useAsyncSend option is set.

Returns:

true if on false if not.

6.24.2.18 `bool activemq::core::ActiveMQConnectionFactory::isUseCompression ()`
 `const`

Gets if the Connection is configured for Message body compression.

Returns:

if the Message body will be Compressed or not.

6.24.2.19 `void activemq::core::ActiveMQConnectionFactory::setAlwaysSyncSend`
 `(bool value)`

Sets if the Connection should always send things Synchronously.

Parameters:

value true if sends should always be Synchronous.

6.24.2.20 `void activemq::core::ActiveMQConnectionFactory::setBrokerURL (const`
 `std::string & brokerURL)`

Sets the Broker URL that should be used when creating a new connection instance.

Parameters:

brokerURL string

6.24.2.21 `void activemq::core::ActiveMQConnectionFactory::setClientId (const`
 `std::string & clientId)`

Sets the Client Id.

Parameters:

clientId - The new clientId value.

6.24.2.22 void activemq::core::ActiveMQConnectionFactory::setCloseTimeout (unsigned int *timeout*)

Sets the close timeout to use when sending the disconnect request.

Parameters:

timeout - The time to wait for a close message.

6.24.2.23 void activemq::core::ActiveMQConnectionFactory::setDispatchAsync (bool *value*)

Should messages be dispatched synchronously or asynchronously from the producer thread for non-durable topics in the broker? For fast consumers set this to false. For slow consumers set it to true so that dispatching will not block fast consumers. .

Parameters:

value The value of the dispatch asynchronously option sent to the broker.

6.24.2.24 void activemq::core::ActiveMQConnectionFactory::setExceptionListener (cms::ExceptionListener * *listener*)

Set an CMS ExceptionListener that will be set on eat connection once it has been created. The factory does not take ownership of this pointer, the client must ensure that its lifetime is scoped to the connection that it is applied to.

Parameters:

listener The listener to set on the connection or NULL for no listener.

6.24.2.25 void activemq::core::ActiveMQConnectionFactory::setPassword (const std::string & *password*)

Sets the password that should be used when creating a new connection.

Parameters:

password string

6.24.2.26 void activemq::core::ActiveMQConnectionFactory::setPrefetchPolicy (PrefetchPolicy * *policy*)

Sets the **PrefetchPolicy** (p.2976) instance that this factory should use when it creates new Connection instances. The **PrefetchPolicy** (p.2976) passed becomes the property of the factory and will be deleted when the factory is destroyed.

Parameters:

policy The new **PrefetchPolicy** (p.2976) that the ConnectionFactory should clone for Connections.

6.24.2.27 void activemq::core::ActiveMQConnectionFactory::setProducerWindowSize (unsigned int *windowSize*)

Sets the size in Bytes of messages that a producer can send before it is blocked to await a ProducerAck from the broker that frees enough memory to allow another message to be sent.

Parameters:

windowSize - The size in bytes of the Producers memory window.

6.24.2.28 void activemq::core::ActiveMQConnectionFactory::setRedeliveryPolicy (RedeliveryPolicy * *policy*)

Sets the **RedeliveryPolicy** (p. 3177) instance that this factory should use when it creates new Connection instances. The **RedeliveryPolicy** (p. 3177) passed becomes the property of the factory and will be deleted when the factory is destroyed.

Parameters:

policy The new **RedeliveryPolicy** (p. 3177) that the ConnectionFactory should clone for Connections.

6.24.2.29 void activemq::core::ActiveMQConnectionFactory::setSendTimeout (unsigned int *timeout*)

Sets the send timeout to use when sending Message objects, this will cause all messages to be sent using a Synchronous request is non-zero.

Parameters:

timeout - The time to wait for a response.

6.24.2.30 void activemq::core::ActiveMQConnectionFactory::setUseAsyncSend (bool *value*)

Sets the useAsyncSend option.

Parameters:

value - true to activate, false to disable.

6.24.2.31 void activemq::core::ActiveMQConnectionFactory::setUseCompression (bool *value*)

Sets whether Message body compression is enabled.

Parameters:

value Boolean indicating if Message body compression is enabled.

6.24.2.32 `void activemq::core::ActiveMQConnectionFactory::setUsername (const std::string & username)`

Sets the username that should be used when creating a new connection.

Parameters:

username string

6.24.3 Field Documentation

6.24.3.1 `const std::string
activemq::core::ActiveMQConnectionFactory::DEFAULT _ -
URI [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQConnectionFactory.h`

6.25 activemq::core::ActiveMQConnectionMetaData Class Reference

This class houses all the various settings and information that is used by an instance of an **ActiveMQConnection** (p. 273) class.

#include <src/main/activemq/core/ActiveMQConnectionMetaData.h> Inheritance diagram for activemq::core::ActiveMQConnectionMetaData:

Public Member Functions

- **ActiveMQConnectionMetaData** ()
- virtual **~ActiveMQConnectionMetaData** ()
- virtual std::string **getCMSVersion** () const throw (cms::CMSEException)
Gets the CMS API version.
- virtual int **getCMSMajorVersion** () const throw (cms::CMSEException)
Gets the CMS major version number.
- virtual int **getCMSMinorVersion** () const throw (cms::CMSEException)
Gets the CMS minor version number.
- virtual std::string **getCMSProviderName** () const throw (cms::CMSEException)
Gets the CMS provider name.
- virtual std::string **getProviderVersion** () const throw (cms::CMSEException)
Gets the CMS provider version.
- virtual int **getProviderMajorVersion** () const throw (cms::CMSEException)
Gets the CMS provider major version number.
- virtual int **getProviderMinorVersion** () const throw (cms::CMSEException)
Gets the CMS provider minor version number.
- virtual std::vector< std::string > **getCMSXPropertyNames** () const throw (cms::CMSEException)
Gets an Vector of the CMSX property names.

6.25.1 Detailed Description

This class houses all the various settings and information that is used by an instance of an **ActiveMQConnection** (p. 273) class.

Since:

3.0

6.25.2 Constructor & Destructor Documentation

6.25.2.1 `activemq::core::ActiveMQConnectionMetaData::ActiveMQConnectionMetaData()`

6.25.2.2 `virtual activemq::core::ActiveMQConnectionMetaData::~~ActiveMQConnectionMetaData()` [virtual]

6.25.3 Member Function Documentation

6.25.3.1 `virtual int activemq::core::ActiveMQConnectionMetaData::getCMSMajorVersion()`
`const throw (cms::CMSEException)` [virtual]

Gets the CMS major version number.

Returns:

the CMS API major version number

Exceptions:

CMSEException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements `cms::ConnectionMetaData` (p.1386).

6.25.3.2 `virtual int activemq::core::ActiveMQConnectionMetaData::getCMSMinorVersion()`
`const throw (cms::CMSEException)` [virtual]

Gets the CMS minor version number.

Returns:

the CMS API minor version number

Exceptions:

CMSEException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements `cms::ConnectionMetaData` (p.1386).

6.25.3.3 `virtual std::string activemq::core::ActiveMQConnectionMetaData::getCMSProviderName()`
`const throw (cms::CMSEException)` [virtual]

Gets the CMS provider name.

Returns:

the CMS provider name

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements **cms::ConnectionMetaData** (p.1386).

6.25.3.4 `virtual std::string activemq::core::ActiveMQConnectionMetaData::getCMSVersion () const throw (cms::CMSException) [virtual]`

Gets the CMS API version.

Returns:

the CMS API Version in String form.

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements **cms::ConnectionMetaData** (p.1387).

6.25.3.5 `virtual std::vector<std::string> activemq::core::ActiveMQConnectionMetaData::getCMSXPropertyNames () const throw (cms::CMSException) [virtual]`

Gets an Vector of the CMSX property names.

Returns:

an Vector of CMSX property names

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements **cms::ConnectionMetaData** (p.1387).

6.25.3.6 `virtual int activemq::core::ActiveMQConnectionMetaData::getProviderMajorVersion () const throw (cms::CMSException) [virtual]`

Gets the CMS provider major version number.

Returns:

the CMS provider major version number

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements **cms::ConnectionMetaData** (p.1387).

6.25.3.7 `virtual int activemq::core::ActiveMQConnectionMetaData::getProviderMinorVersion () const throw (cms::CMSException) [virtual]`

Gets the CMS provider minor version number.

Returns:

the CMS provider minor version number

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements `cms::ConnectionMetaData` (p.1387).

6.25.3.8 `virtual std::string activemq::core::ActiveMQConnectionMetaData::getProviderVersion () const throw (cms::CMSException) [virtual]`

Gets the CMS provider version.

Returns:

the CMS provider version

Exceptions:

CMSException If the CMS Provider fails to retrieve the metadata due to some internal error.

Implements `cms::ConnectionMetaData` (p.1388).

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQConnectionMetaData.h`

6.26 activemq::core::ActiveMQConstants Class Reference

Class holding constant values for various ActiveMQ specific things Each constant is defined as an enumeration and has functions that convert back and forth between string and enum values.

```
#include <src/main/activemq/core/ActiveMQConstants.h>
```

Data Structures

- class `StaticInitializer`

Public Types

- enum `TransactionState` {
`TRANSACTION_STATE_BEGIN` = 0, `TRANSACTION_STATE_PREPARE` = 1, `TRANSACTION_STATE_COMMITONEPHASE` = 2, `TRANSACTION_STATE_COMMITTWOPHASE` = 3,
`TRANSACTION_STATE_ROLLBACK` = 4, `TRANSACTION_STATE_RECOVER` = 5, `TRANSACTION_STATE_FORGET` = 6, `TRANSACTION_STATE_END` = 7 }
 - enum `DestinationActions` { `DESTINATION_ADD_OPERATION` = 0, `DESTINATION_REMOVE_OPERATION` = 1 }
 - enum `AckType` {
`ACK_TYPE_DELIVERED` = 0, `ACK_TYPE_POISON` = 1, `ACK_TYPE_CONSUMED` = 2, `ACK_TYPE_REDELIVERED` = 3,
`ACK_TYPE_INDIVIDUAL` = 4 }
 - enum `DestinationOption` {
`CONSUMER_PREFETCHSIZE`, `CONSUMER_MAXPENDINGMSGLIMIT`, `CONSUMER_NOLOCAL`, `CONSUMER_DISPATCHASYNC`,
`CONSUMER_RETROACTIVE`, `CONSUMER_SELECTOR`, `CONSUMER_EXCLUSIVE`, `CONSUMER_PRIORITY`,
`NUM_OPTIONS` }
- These values represent the options that can be appended to an Destination name, i.e.*
- enum `URIParam` {
`CONNECTION_SENDTIMEOUT`, `CONNECTION_PRODUCERWINDOWSIZE`, `CONNECTION_CLOSETIMEOUT`,
`CONNECTION_ALWAYSSENDCONNECTION_USEASYNCSEND`, `CONNECTION_USECOMPRESSION`,
`CONNECTION_DISPATCHASYNC`, `PARAM_USERNAME`,
`PARAM_PASSWORD`, `PARAM_CLIENTID`, `NUM_PARAMS` }
- These values represent the parameters that can be added to the connection URI that affect the ActiveMQ Core API.*

Static Public Member Functions

- static const std::string & **toString** (const **DestinationOption** option)
- static **DestinationOption** **toDestinationOption** (const std::string &option)
- static const std::string & **toString** (const **URIParam** option)
- static **URIParam** **toURIOption** (const std::string &option)

6.26.1 Detailed Description

Class holding constant values for various ActiveMQ specific things Each constant is defined as an enumeration and has functions that convert back and forth between string and enum values.

6.26.2 Member Enumeration Documentation

6.26.2.1 enum activemq::core::ActiveMQConstants::AckType

Enumerator:

```
ACK_TYPE_DELIVERED
ACK_TYPE_POISON
ACK_TYPE_CONSUMED
ACK_TYPE_REDELIVERED
ACK_TYPE_INDIVIDUAL
```

6.26.2.2 enum activemq::core::ActiveMQConstants::DestinationActions

Enumerator:

```
DESTINATION_ADD_OPERATION
DESTINATION_REMOVE_OPERATION
```

6.26.2.3 enum activemq::core::ActiveMQConstants::DestinationOption

These values represent the options that can be appended to an Destination name, i.e. /topic/-foo?consumer.exclusive=true

Enumerator:

```
CONSUMER_PREFETCHSIZE
CUNSUMER_MAXPENDINGMSGLIMIT
CONSUMER_NOLOCAL
CONSUMER_DISPATCHASYNC
CONSUMER_RETROACTIVE
CONSUMER_SELECTOR
CONSUMER_EXCLUSIVE
CONSUMER_PRIORITY
NUM_OPTIONS
```

6.26.2.4 enum activemq::core::ActiveMQConstants::TransactionState

Enumerator:

```
TRANSACTION_STATE_BEGIN
TRANSACTION_STATE_PREPARE
TRANSACTION_STATE_COMMITONEPHASE
TRANSACTION_STATE_COMMITTWOPHASE
TRANSACTION_STATE_ROLLBACK
TRANSACTION_STATE_RECOVER
TRANSACTION_STATE_FORGET
TRANSACTION_STATE_END
```

6.26.2.5 enum activemq::core::ActiveMQConstants::URIParam

These values represent the parameters that can be added to the connection URI that affect the ActiveMQ Core API.

Enumerator:

```
CONNECTION_SENDTIMEOUT
CONNECTION_PRODUCERWINDOWSIZE
CONNECTION_CLOSETIMEOUT
CONNECTION_ALWAYS_SYNC_SEND
CONNECTION_USE_ASYNC_SEND
CONNECTION_USE_COMPRESSION
CONNECTION_DISPATCH_ASYNC
PARAM_USERNAME
PARAM_PASSWORD
PARAM_CLIENTID
NUM_PARAMS
```

6.26.3 Member Function Documentation

6.26.3.1 static DestinationOption activemq::core::ActiveMQConstants::toDestinationOption
(const std::string & option) [inline, static]

6.26.3.2 static const std::string& activemq::core::ActiveMQConstants::toString
(const URIParam option) [inline, static]

6.26.3.3 static const std::string& activemq::core::ActiveMQConstants::toString
(const DestinationOption option) [inline, static]

6.26.3.4 static URIParam activemq::core::ActiveMQConstants::toURIOption
(const std::string & option) [inline, static]

The documentation for this class was generated from the following file:

- src/main/activemq/core/ActiveMQConstants.h

6.27 activemq::core::ActiveMQConsumer Class Reference

#include <src/main/activemq/core/ActiveMQConsumer.h> Inheritance diagram for activemq::core::ActiveMQConsumer:

Public Member Functions

- **ActiveMQConsumer** (**ActiveMQSession** *session, const **Pointer**< **commands::ConsumerId** > &id, const **Pointer**< **commands::ActiveMQDestination** > &destination, const std::string &name, const std::string &selector, int prefetch, int maxPendingMessageCount, bool noLocal, bool browser, bool dispatchAsync, **cms::MessageListener** *listener)
Constructor.
- virtual ~**ActiveMQConsumer** ()
- virtual void **start** ()
Starts the Consumer if not already started and not closed.
- virtual void **stop** ()
Stops a Consumer, the Consumer will not deliver any messages that are dispatched to it until it is started again.
- virtual void **close** () throw (cms::CMSEException)
Closes the Consumer.
- virtual **cms::Message** * **receive** () throw (cms::CMSEException)
Synchronously Receive a Message.
- virtual **cms::Message** * **receive** (int millisecs) throw (cms::CMSEException)
Synchronously Receive a Message, time out after defined interval.
- virtual **cms::Message** * **receiveNoWait** () throw (cms::CMSEException)
Receive a Message, does not wait if there isn't a new message to read, returns NULL if nothing read.
- virtual void **setMessageListener** (**cms::MessageListener** *listener) throw (cms::CMSEException)
Sets the MessageListener that this class will send notifs on.
- virtual **cms::MessageListener** * **getMessageListener** () const throw (cms::CMSEException)
Gets the MessageListener that this class will send events to.
- virtual std::string **getMessageSelector** () const throw (cms::CMSEException)
Gets this message consumer's message selector expression.
- virtual void **acknowledge** (const **Pointer**< **commands::MessageDispatch** > &dispatch) throw (cms::CMSEException)

Method called to acknowledge the message passed, called from a message when the mode is client ack.

- virtual void **dispatch** (const **Pointer**< **MessageDispatch** > &message)
Called asynchronously by the session to dispatch a message.
- void **acknowledge** () throw (cms::CMSException)
Method called to acknowledge all messages that have been received so far.
- void **commit** () throw (exceptions::ActiveMQException)
Called to Commit the current set of messages in this Transaction.
- void **rollback** () throw (exceptions::ActiveMQException)
Called to Roll back the current set of messages in this Transaction.
- void **doClose** () throw (exceptions::ActiveMQException)
Performs the actual close operation on this consumer.
- const **Pointer**< **commands::ConsumerInfo** > & **getConsumerInfo** () const
Get the Consumer information for this consumer.
- const **Pointer**< **commands::ConsumerId** > & **getConsumerId** () const
Get the Consumer Id for this consumer.
- bool **isClosed** () const
- bool **isSynchronizationRegistered** () const
*Has this Consumer Transaction **Synchronization** (p. 3715) been added to the transaction.*
- void **setSynchronizationRegistered** (bool value)
*Sets the **Synchronization** (p. 3715) Registered **state** (p. 95) of this consumer.*
- bool **iterate** ()
Deliver any pending messages to the registered MessageListener if there is one, return true if not all dispatched, or false if no listener or all pending messages have been dispatched.
- void **deliverAcks** () throw (exceptions::ActiveMQException)
Forces this consumer to send all pending acks to the broker.
- void **clearMessagesInProgress** ()
Called on a Failover to clear any pending messages.
- void **inProgressClearRequired** ()
Signals that a Failure occurred and that anything in-progress in the consumer should be cleared.
- long long **getLastDeliveredSequenceId** () const
Gets the currently set Last Delivered Sequence Id.
- void **setLastDeliveredSequenceId** (long long value)
Sets the value of the Last Delivered Sequence Id.

- `int getMessageAvailableCount () const`
- `void setRedeliveryPolicy (RedeliveryPolicy *policy)`
*Sets the **RedeliveryPolicy** (p. 3177) this Consumer should use when a rollback is performed on a transacted Consumer.*
- `RedeliveryPolicy * getRedeliveryPolicy () const`
Gets a pointer to this Consumer's Redelivery Policy object, the Consumer retains ownership of this pointer so the caller should not delete it.

Protected Member Functions

- `Pointer< MessageDispatch > dequeue (long long timeout) throw (cms::CMSEException)`
Used by synchronous receive methods to wait for messages to come in.
- `void beforeMessageIsConsumed (const Pointer< commands::MessageDispatch > &dispatch)`
Pre-consume processing.
- `void afterMessageIsConsumed (const Pointer< commands::MessageDispatch > &dispatch, bool messageExpired)`
Post-consume processing.

6.27.1 Constructor & Destructor Documentation

- 6.27.1.1 `activemq::core::ActiveMQConsumer::ActiveMQConsumer (ActiveMQSession * session, const Pointer< commands::ConsumerId > & id, const Pointer< commands::ActiveMQDestination > & destination, const std::string & name, const std::string & selector, int prefetch, int maxPendingMessageCount, bool noLocal, bool browser, bool dispatchAsync, cms::MessageListener * listener)`

Constructor.

- 6.27.1.2 `virtual activemq::core::ActiveMQConsumer::~~ActiveMQConsumer ()`
[virtual]

6.27.2 Member Function Documentation

- 6.27.2.1 `void activemq::core::ActiveMQConsumer::acknowledge () throw (cms::CMSEException)`

Method called to acknowledge all messages that have been received so far.

Exceptions:

CMSEException

6.27.2.2 `virtual void activemq::core::ActiveMQConsumer::acknowledge (const Pointer< commands::MessageDispatch > & dispatch) throw (cms::CMSException) [virtual]`

Method called to acknowledge the message passed, called from a message when the mode is client ack.

Parameters:

message the Message to Acknowledge

Exceptions:

CMSException

6.27.2.3 `void activemq::core::ActiveMQConsumer::afterMessageIsConsumed (const Pointer< commands::MessageDispatch > & dispatch, bool messageExpired) [protected]`

Post-consume processing.

Parameters:

dispatch - the consumed message

messageExpired - flag indicating if the message has expired.

6.27.2.4 `void activemq::core::ActiveMQConsumer::beforeMessageIsConsumed (const Pointer< commands::MessageDispatch > & dispatch) [protected]`

Pre-consume processing.

Parameters:

dispatch - the message being consumed.

6.27.2.5 `void activemq::core::ActiveMQConsumer::clearMessagesInProgress ()`

Called on a Failover to clear any pending messages.

6.27.2.6 `virtual void activemq::core::ActiveMQConsumer::close () throw (cms::CMSException) [virtual]`

Closes the Consumer. This will return all allocated resources and purge any outstanding messages. This method will block if there is a call to receive in progress, or a dispatch to a MessageListener in place

Exceptions:

CMSException

Implements `cms::Closeable` (p.1148).

6.27.2.7 `void activemq::core::ActiveMQConsumer::commit () throw (exceptions::ActiveMQException)`

Called to Commit the current set of messages in this Transaction.

Exceptions:

ActiveMQException

6.27.2.8 `void activemq::core::ActiveMQConsumer::deliverAcks () throw (exceptions::ActiveMQException)`

Forces this consumer to send all pending acks to the broker.

6.27.2.9 `Pointer<MessageDispatch> activemq::core::ActiveMQConsumer::dequeue (long long timeout) throw (cms::CMSException) [protected]`

Used by synchronous receive methods to wait for messages to come in.

Parameters:

timeout - The maximum number of milliseconds to wait before returning. If -1, it will block until a messages is received or this consumer is closed. If 0, will not block at all. If > 0, will wait at a maximum the specified number of milliseconds before returning.

Returns:

the message, if received within the allotted time. Otherwise NULL.

Exceptions:

InvalidStateException if this consumer is closed upon entering this method.

6.27.2.10 `virtual void activemq::core::ActiveMQConsumer::dispatch (const Pointer< MessageDispatch > & message) [virtual]`

Called asynchronously by the session to dispatch a message.

Parameters:

message dispatch object pointer

Implements `activemq::core::Dispatcher` (p. 1787).

6.27.2.11 `void activemq::core::ActiveMQConsumer::doClose () throw (exceptions::ActiveMQException)`

Performs the actual close operation on this consumer.

Exceptions:

ActiveMQException

6.27.2.12 `const Pointer<commands::ConsumerId>& activemq::core::ActiveMQConsumer::getConsumerId () const [inline]`

Get the Consumer Id for this consumer.

Returns:

Reference to a Consumer Id Object

6.27.2.13 `const Pointer<commands::ConsumerInfo>& activemq::core::ActiveMQConsumer::getConsumerInfo () const [inline]`

Get the Consumer information for this consumer.

Returns:

Reference to a Consumer Info Object

6.27.2.14 `long long activemq::core::ActiveMQConsumer::getLastDeliveredSequenceId () const [inline]`

Gets the currently set Last Delivered Sequence Id.

Returns:

long long containing the sequence id of the last delivered Message.

6.27.2.15 `int activemq::core::ActiveMQConsumer::getMessageAvailableCount () const`

Returns:

the number of Message's this consumer is waiting to Dispatch.

6.27.2.16 `virtual cms::MessageListener* activemq::core::ActiveMQConsumer::getMessageListener () const throw (cms::CMSException) [inline, virtual]`

Gets the MessageListener that this class will send events to.

Returns:

the currently registered MessageListener interface pointer.

Implements `cms::MessageConsumer` (p. 2590).

6.27.2.17 `virtual std::string activemq::core::ActiveMQConsumer::getMessageSelector ()
const throw (cms::CMSException) [virtual]`

Gets this message consumer's message selector expression.

Returns:

This Consumer's selector expression or "".

Exceptions:

cms::CMSException (p. 1160)

Implements `cms::MessageConsumer` (p. 2590).

6.27.2.18 `RedeliveryPolicy* activemq::core::ActiveMQConsumer::getRedeliveryPolicy ()
const [inline]`

Gets a pointer to this Consumer's Redelivery Policy object, the Consumer retains ownership of this pointer so the caller should not delete it.

Returns:

a Pointer to a **RedeliveryPolicy** (p. 3177) that is in use by this Consumer.

6.27.2.19 `void activemq::core::ActiveMQConsumer::inProgressClearRequired ()`

Signals that a Failure occurred and that anything in-progress in the consumer should be cleared.

6.27.2.20 `bool activemq::core::ActiveMQConsumer::isClosed () const [inline]`

Returns:

if this Consumer has been closed.

6.27.2.21 `bool activemq::core::ActiveMQConsumer::isSynchronizationRegistered ()
const [inline]`

Has this Consumer Transaction **Synchronization** (p. 3715) been added to the transaction.

Returns:

true if the synchronization has been added.

6.27.2.22 `bool activemq::core::ActiveMQConsumer::iterate ()`

Deliver any pending messages to the registered MessageListener if there is one, return true if not all dispatched, or false if no listener or all pending messages have been dispatched.

6.27.2.23 `virtual cms::Message* activemq::core::ActiveMQConsumer::receive (int milliseconds) throw (cms::CMSException) [virtual]`

Synchronously Receive a Message, time out after defined interval. Returns null if nothing read.

Parameters:

milliseconds the time in milliseconds to wait before returning

Returns:

new message or null on timeout

Exceptions:

CMSException

Implements `cms::MessageConsumer` (p. 2590).

6.27.2.24 `virtual cms::Message* activemq::core::ActiveMQConsumer::receive () throw (cms::CMSException) [virtual]`

Synchronously Receive a Message.

Returns:

new message

Exceptions:

CMSException

Implements `cms::MessageConsumer` (p. 2591).

6.27.2.25 `virtual cms::Message* activemq::core::ActiveMQConsumer::receiveNoWait () throw (cms::CMSException) [virtual]`

Receive a Message, does not wait if there isn't a new message to read, returns NULL if nothing read.

Returns:

new message

Exceptions:

CMSException

Implements `cms::MessageConsumer` (p. 2591).

6.27.2.26 `void activemq::core::ActiveMQConsumer::rollback () throw (exceptions::ActiveMQException)`

Called to Roll back the current set of messages in this Transaction.

Exceptions:

ActiveMQException

6.27.2.27 `void activemq::core::ActiveMQConsumer::setLastDeliveredSequenceId
(long long value) [inline]`

Sets the value of the Last Delivered Sequence Id.

Parameters:

value The new value to assign to the Last Delivered Sequence Id property.

6.27.2.28 `virtual void activemq::core::ActiveMQConsumer::setMessageListener
(cms::MessageListener * listener) throw (cms::CMSException)
[virtual]`

Sets the MessageListener that this class will send notifs on.

Parameters:

listener MessageListener interface pointer

Implements `cms::MessageConsumer` (p. 2591).

6.27.2.29 `void activemq::core::ActiveMQConsumer::setRedeliveryPolicy
(RedeliveryPolicy * policy) [inline]`

Sets the **RedeliveryPolicy** (p. 3177) this Consumer should use when a rollback is performed on a transacted Consumer. The Consumer takes ownership of the passed pointer. The Consumer's redelivery policy can never be null, a call to this method with a NULL pointer is ignored.

Parameters:

policy Pointer to a Redelivery Policy object that his Consumer will use.

6.27.2.30 `void activemq::core::ActiveMQConsumer::setSynchronizationRegistered
(bool value) [inline]`

Sets the **Synchronization** (p. 3715) Registered **state** (p. 95) of this consumer.

Parameters:

value - true if registered false otherwise.

6.27.2.31 `virtual void activemq::core::ActiveMQConsumer::start () [virtual]`

Starts the Consumer if not already started and not closed. A consumer will no deliver messages until started.

6.27.2.32 virtual void activemq::core::ActiveMQConsumer::stop () [virtual]

Stops a Consumer, the Consumer will not deliver any messages that are dispatched to it until it is started again. A Closed Consumer is also a stopped consumer.

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQConsumer.h`

6.28 activemq::library::ActiveMQCPP Class Reference

```
#include <src/main/activemq/library/ActiveMQCPP.h>
```

Public Member Functions

- virtual `~ActiveMQCPP ()`

Static Public Member Functions

- static void `initializeLibrary ()`
*Initialize the ActiveMQ-CPP Library constructs, this method will init all the internal Registry objects and initialize the Decaf **library** (p. 94).*
- static void `initializeLibrary (int argc, char **argv)`
*Initialize the ActiveMQ-CPP Library constructs, this method will initialize all the internal Registry objects and initialize the Decaf **library** (p. 94).*
- static void `shutdownLibrary ()`
Shutdown the ActiveMQ-CPP Library, freeing any resources that could not be freed up to this point.

Protected Member Functions

- `ActiveMQCPP ()`
- `ActiveMQCPP (const ActiveMQCPP &)`
- `ActiveMQCPP & operator= (const ActiveMQCPP &)`

6.28.1 Constructor & Destructor Documentation

6.28.1.1 `activemq::library::ActiveMQCPP::ActiveMQCPP () [inline, protected]`

6.28.1.2 `activemq::library::ActiveMQCPP::ActiveMQCPP (const ActiveMQCPP &) [protected]`

6.28.1.3 `virtual activemq::library::ActiveMQCPP::~~ActiveMQCPP () [inline, virtual]`

6.28.2 Member Function Documentation

6.28.2.1 `static void activemq::library::ActiveMQCPP::initializeLibrary (int argc, char ** argv) [static]`

Initialize the ActiveMQ-CPP Library constructs, this method will initialize all the internal Registry objects and initialize the Decaf **library** (p.94). This method takes the args passed to the main method of process for use is setting system properties and configuring the ActiveMQ-CPP Library.

Parameters:

argc - the count of arguments passed to this Process.

argv - the array of string arguments passed to this process.

Exceptions:

runtime_error if an error occurs while initializing this **library** (p. 94).

6.28.2.2 static void activemq::library::ActiveMQCPP::initializeLibrary () [static]

Initialize the ActiveMQ-CPP Library constructs, this method will init all the internal Registry objects and initialize the Decaf **library** (p. 94).

Exceptions:

runtime_error if an error occurs while initializing this **library** (p. 94).

6.28.2.3 ActiveMQCPP& activemq::library::ActiveMQCPP::operator= (const ActiveMQCPP &) [protected]

6.28.2.4 static void activemq::library::ActiveMQCPP::shutdownLibrary () [static]

Shutdown the ActiveMQ-CPP Library, freeing any resources that could not be freed up to this point. All the user created ActiveMQ-CPP objects and Decaf Library objects should have been destroyed by the time this method is called.

The documentation for this class was generated from the following file:

- src/main/activemq/library/**ActiveMQCPP.h**

6.29 activemq::commands::ActiveMQDestination Class Reference

#include <src/main/activemq/commands/ActiveMQDestination.h> Inheritance diagram for activemq::commands::ActiveMQDestination:

Data Structures

- struct **DestinationFilter**

Public Member Functions

- **ActiveMQDestination** ()
- **ActiveMQDestination** (const std::string &**physicalName**)
- virtual ~**ActiveMQDestination** ()
- virtual **ActiveMQDestination** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual const std::string & **getPhysicalName** () const
Fetch this destination's physical name.
- virtual std::string & **getPhysicalName** ()
- virtual void **setPhysicalName** (const std::string &**physicalName**)
Set this destination's physical name.
- virtual bool **isAdvisory** () const
- virtual void **setAdvisory** (bool **advisory**)
- virtual bool **isConsumerAdvisory** () const
- virtual bool **isProducerAdvisory** () const
- virtual bool **isConnectionAdvisory** () const
- virtual bool **isExclusive** () const
- virtual void **setExclusive** (bool **exclusive**)
- virtual bool **isOrdered** () const

- virtual void **setOrdered** (bool **ordered**)
- virtual std::string **getOrderedTarget** () const
- virtual void **setOrderedTarget** (const std::string &**orderedTarget**)
- virtual **cms::Destination::DestinationType** **getDestinationType** () const =0
Returns the Type of Destination that this object represents.
- virtual bool **isTemporary** () const
Returns true if a temporary Destination.
- virtual bool **isTopic** () const
Returns true if a Topic Destination.
- virtual bool **isQueue** () const
Returns true if a Queue Destination.
- virtual bool **isComposite** () const
Returns true if this destination represents a collection of destinations; allowing a set of destinations to be published to or subscribed from in one CMS operation.
- virtual bool **isWildcard** () const
- const **activemq::util::ActiveMQProperties** & **getOptions** () const
- virtual const **cms::Destination** * **getCMSDestination** () const

Static Public Member Functions

- static std::string **createTemporaryName** (const std::string &clientId)
Create a temporary name from the clientId.
- static std::string **getClientId** (const **ActiveMQDestination** *destination)
From a temporary destination find the clientId of the Connection that created it.
- static **Pointer< ActiveMQDestination >** **createDestination** (int type, const std::string &name)
Creates a Destination given the String Name to use and a Type.

Static Public Attributes

- static const unsigned char **ID _ACTIVEMQDESTINATION** = 0

Protected Attributes

- bool **exclusive**
- bool **ordered**
- bool **advisory**
- std::string **orderedTarget**
- std::string **physicalName**
- **util::ActiveMQProperties** **options**

Static Protected Attributes

- static const std::string **ADVISORY_PREFIX**
prefix for Advisory message destinations
- static const std::string **CONSUMER_ADVISORY_PREFIX**
prefix for consumer advisory destinations
- static const std::string **PRODUCER_ADVISORY_PREFIX**
prefix for producer advisory destinations
- static const std::string **CONNECTION_ADVISORY_PREFIX**
prefix for connection advisory destinations
- static const std::string **DEFAULT_ORDERED_TARGET**
The default target for ordered destinations.
- static const std::string **TEMP_PREFIX**
- static const std::string **TEMP_POSTFIX**
- static const std::string **COMPOSITE_SEPARATOR**
- static const std::string **QUEUE_QUALIFIED_PREFIX**
- static const std::string **TOPIC_QUALIFIED_PREFIX**
- static const std::string **TEMP_QUEUE_QUALIFIED_PREFIX**
- static const std::string **TEMP_TOPIC_QUALIFIED_PREFIX**

6.29.1 Constructor & Destructor Documentation

6.29.1.1 `activemq::commands::ActiveMQDestination::ActiveMQDestination ()`

6.29.1.2 `activemq::commands::ActiveMQDestination::ActiveMQDestination (const std::string & physicalName)`

6.29.1.3 `virtual
activemq::commands::ActiveMQDestination::~~ActiveMQDestination ()
[inline, virtual]`

6.29.2 Member Function Documentation

6.29.2.1 `virtual ActiveMQDestination* ac-
tivemq::commands::ActiveMQDestination::cloneDataStructure () const
[inline, virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

Reimplemented in `activemq::commands::ActiveMQQueue` (p. 484),
`activemq::commands::ActiveMQTempDestination` (p. 577), **ac-**
`tivemq::commands::ActiveMQTempQueue` (p. 605), **ac-**
`tivemq::commands::ActiveMQTempTopic` (p. 634), and **ac-**
`tivemq::commands::ActiveMQTopic` (p. 692).

6.29.2.2 virtual void `activemq::commands::ActiveMQDestination::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

`src` - Source Object

Reimplemented in `activemq::commands::ActiveMQQueue` (p. 484),
`activemq::commands::ActiveMQTempDestination` (p. 577), **ac-**
`tivemq::commands::ActiveMQTempQueue` (p. 606), **ac-**
`tivemq::commands::ActiveMQTempTopic` (p. 635), and **ac-**
`tivemq::commands::ActiveMQTopic` (p. 692).

Referenced by `activemq::commands::ActiveMQTempDestination::copyDataStructure()`.

6.29.2.3 static `Pointer<ActiveMQDestination> activemq::commands::ActiveMQDestination::createDestination (int type, const std::string & name)` [static]

Creates a Destination given the String Name to use and a Type.

Parameters:

type - The Type of Destination to Create

name - The Name to use in the creation of the Destination

Returns:

Pointer to a new `ActiveMQDestination` (p. 322) instance.

6.29.2.4 static `std::string activemq::commands::ActiveMQDestination::createTemporaryName (const std::string & clientId)` [inline, static]

Create a temporary name from the `clientId`.

Parameters:

clientId

Returns:

6.29.2.5 `virtual bool activemq::commands::ActiveMQDestination::equals (const DataStructure * value) const` [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented in `activemq::commands::ActiveMQQueue` (p. 485),
`activemq::commands::ActiveMQTempDestination` (p. 578), **ac-**
`tivemq::commands::ActiveMQTempQueue` (p. 606), **ac-**
`tivemq::commands::ActiveMQTempTopic` (p. 635), and **ac-**
`tivemq::commands::ActiveMQTopic` (p. 693).

Referenced by `activemq::commands::ActiveMQTopic::equals()`, and `ac-`
`tivemq::commands::ActiveMQTempDestination::equals()`.

6.29.2.6 `static std::string activemq::commands::ActiveMQDestination::getClientId (const ActiveMQDestination * destination)` [static]

From a temporary destination find the clientId of the Connection that created it.

Parameters:

destination

Returns:

the clientId or null if not a temporary destination

6.29.2.7 `virtual const cms::Destination* activemq::commands::ActiveMQDestination::getCMSDestination ()` const [inline, virtual]

Returns:

the **cms::Destination** (p. 1723) interface pointer that the objects that derive from this class implement.

Reimplemented in `activemq::commands::ActiveMQQueue` (p. 485),
`activemq::commands::ActiveMQTempQueue` (p. 606), **ac-**
`tivemq::commands::ActiveMQTempTopic` (p. 635), and **ac-**
`tivemq::commands::ActiveMQTopic` (p. 693).

6.29.2.8 `virtual unsigned char activemq::commands::ActiveMQDestination::getDataStructureType ()` const [virtual]

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Implements **activemq::commands::DataStructure** (p. 1662).

Reimplemented in **activemq::commands::ActiveMQQueue** (p. 485),
activemq::commands::ActiveMQTempDestination (p. 578), **ac-**
tivemq::commands::ActiveMQTempQueue (p. 607), **ac-**
tivemq::commands::ActiveMQTempTopic (p. 636), and **ac-**
tivemq::commands::ActiveMQTopic (p. 693).

6.29.2.9 virtual cms::Destination::DestinationType ac-
tivemq::commands::ActiveMQDestination::getDestinationType () const
[pure virtual]

Returns the Type of Destination that this object represents.

Returns:

int type qualifier.

Implemented in **activemq::commands::ActiveMQQueue** (p. 485),
activemq::commands::ActiveMQTempQueue (p. 607), **ac-**
tivemq::commands::ActiveMQTempTopic (p. 636), and **ac-**
tivemq::commands::ActiveMQTopic (p. 693).

6.29.2.10 const activemq::util::ActiveMQProperties& ac-
tivemq::commands::ActiveMQDestination::getOptions () const
[inline]

Returns:

a reference (const) to the options properties for this Destination.

6.29.2.11 virtual std::string ac-
tivemq::commands::ActiveMQDestination::getOrderedTarget () const
[inline, virtual]

Returns:

Returns the orderedTarget.

6.29.2.12 virtual std::string& ac-
tivemq::commands::ActiveMQDestination::getPhysicalName () [inline,
virtual]

6.29.2.13 virtual const std::string& ac-
tivemq::commands::ActiveMQDestination::getPhysicalName () const
[inline, virtual]

Fetch this destination's physical name.

Returns:

const string containing the name

6.29.2.14 `virtual bool activemq::commands::ActiveMQDestination::isAdvisory () const [inline, virtual]`

Returns:

Returns the advisory.

6.29.2.15 `virtual bool activemq::commands::ActiveMQDestination::isComposite () const [inline, virtual]`

Returns true if this destination represents a collection of destinations; allowing a set of destinations to be published to or subscribed from in one CMS operation.

Returns:

true if this destination represents a collection of child destinations.

6.29.2.16 `virtual bool activemq::commands::ActiveMQDestination::isConnectionAdvisory () const [inline, virtual]`

Returns:

true if this is a destination for Connection advisories

6.29.2.17 `virtual bool activemq::commands::ActiveMQDestination::isConsumerAdvisory () const [inline, virtual]`

Returns:

true if this is a destination for Consumer advisories

6.29.2.18 `virtual bool activemq::commands::ActiveMQDestination::isExclusive () const [inline, virtual]`

Returns:

Returns the exclusive.

6.29.2.19 `virtual bool activemq::commands::ActiveMQDestination::isOrdered () const [inline, virtual]`

Returns:

Returns the ordered.

6.29.2.20 `virtual bool activemq::commands::ActiveMQDestination::isProducerAdvisory () const`
[inline, virtual]

Returns:

true if this is a destination for Producer advisories

6.29.2.21 `virtual bool activemq::commands::ActiveMQDestination::isQueue () const`
[inline, virtual]

Returns true if a Queue Destination.

Returns:

true/false

6.29.2.22 `virtual bool activemq::commands::ActiveMQDestination::isTemporary () const`
[inline, virtual]

Returns true if a temporary Destination.

Returns:

true/false

References cms::Destination::TEMPORARY_QUEUE, and cms::Destination::TEMPORARY_TOPIC.

6.29.2.23 `virtual bool activemq::commands::ActiveMQDestination::isTopic () const`
[inline, virtual]

Returns true if a Topic Destination.

Returns:

true/false

References cms::Destination::TEMPORARY_TOPIC, and cms::Destination::TOPIC.

6.29.2.24 `virtual bool activemq::commands::ActiveMQDestination::isWildcard () const`
[inline, virtual]

Returns:

true if the destination matches multiple possible destinations

6.29.2.25 `virtual void activemq::commands::ActiveMQDestination::setAdvisory (bool advisory)` [inline, virtual]

Parameters:

advisory The advisory to set.

6.29.2.26 virtual void activemq::commands::ActiveMQDestination::setExclusive (bool *exclusive*) [inline, virtual]

Parameters:

exclusive The exclusive to set.

6.29.2.27 virtual void activemq::commands::ActiveMQDestination::setOrdered (bool *ordered*) [inline, virtual]

Parameters:

ordered The ordered to set.

6.29.2.28 virtual void activemq::commands::ActiveMQDestination::setOrderedTarget (const std::string & *orderedTarget*) [inline, virtual]

Parameters:

orderedTarget The orderedTarget to set.

6.29.2.29 virtual void activemq::commands::ActiveMQDestination::setPhysicalName (const std::string & *physicalName*) [virtual]

Set this destination's physical name.

Returns:

const string containing the name

6.29.2.30 virtual std::string activemq::commands::ActiveMQDestination::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p.833).

Reimplemented in **activemq::commands::ActiveMQQueue** (p.486),
activemq::commands::ActiveMQTempDestination (p.578), **ac-**
tivemq::commands::ActiveMQTempQueue (p.607), **ac-**
tivemq::commands::ActiveMQTempTopic (p.636), and **ac-**
tivemq::commands::ActiveMQTopic (p.694).

6.29.3 Field Documentation

6.29.3.1 `bool activemq::commands::ActiveMQDestination::advisory` [protected]

6.29.3.2 `const std::string
activemq::commands::ActiveMQDestination::ADVISORY_
PREFIX` [static, protected]

prefix for Advisory message destinations

6.29.3.3 `const std::string
activemq::commands::ActiveMQDestination::COMPOSITE_
SEPARATOR` [static, protected]

6.29.3.4 `const std::string
activemq::commands::ActiveMQDestination::CONNECTION_
ADVISORY_PREFIX` [static, protected]

prefix for connection advisory destinations

6.29.3.5 `const std::string
activemq::commands::ActiveMQDestination::CONSUMER_
ADVISORY_PREFIX` [static, protected]

prefix for consumer advisory destinations

6.29.3.6 `const std::string
activemq::commands::ActiveMQDestination::DEFAULT_
ORDERED_TARGET` [static, protected]

The default target for ordered destinations.

6.29.3.7 `bool activemq::commands::ActiveMQDestination::exclusive` [protected]

6.29.3.8 `const unsigned char activemq::commands::ActiveMQDestination::ID _ - ACTIVEMQDESTINATION = 0` [static]

6.29.3.9 `util::ActiveMQProperties activemq::commands::ActiveMQDestination::options` [protected]

6.29.3.10 `bool activemq::commands::ActiveMQDestination::ordered` [protected]

6.29.3.11 `std::string activemq::commands::ActiveMQDestination::orderedTarget` [protected]

6.29.3.12 `std::string activemq::commands::ActiveMQDestination::physicalName` [protected]

6.29.3.13 `const std::string activemq::commands::ActiveMQDestination::PRODUCER _ - ADVISORY _ PREFIX` [static, protected]

prefix for producer advisory destinations

6.29.3.14 `const std::string activemq::commands::ActiveMQDestination::QUEUE _ - QUALIFIED _ PREFIX` [static, protected]

6.29.3.15 `const std::string activemq::commands::ActiveMQDestination::TEMP _ - POSTFIX` [static, protected]

6.29.3.16 `const std::string activemq::commands::ActiveMQDestination::TEMP _ - PREFIX` [static, protected]

6.29.3.17 `const std::string activemq::commands::ActiveMQDestination::TEMP _ - QUEUE _ QUALIFIED _ PREFIX` [static, protected]

6.29.3.18 `const std::string activemq::commands::ActiveMQDestination::TEMP _ - TOPIC _ QUALIFIED _ PREFIX` [static, protected]

6.29.3.19 `const std::string activemq::commands::ActiveMQDestination::TOPIC _ - QUALIFIED _ PREFIX` [static, protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQDestination.h`

6.30 activemq:wireformat::openwire::marshal:v3::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 333).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h>Inheritance diagram for activemq:wireformat::openwire::marshal:v3::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.30.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 333). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.30.2 Constructor & Destructor Documentation

6.30.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.30.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.30.3 Member Function Documentation

6.30.3.1 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller` (p. 492), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 581), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller` (p. 610), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller` (p. 639), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller` (p. 696).

6.30.3.2 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller** (p. 493), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 581), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 611), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 640), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller** (p. 697).

6.30.3.3 virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)
 [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller** (p. 493), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 582), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 611), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 640), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller** (p. 697).

6.30.3.4 virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller** (p. 493), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 582), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 611), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 640), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller** (p. 697).

6.30.3.5 virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

- wireFormat*** - describes the wire format of the broker.
- dataStructure*** - Object to be un-marshaled.
- dataIn*** - BinaryReader that provides that data.
- bs*** - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller** (p. 494), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 583), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 612), **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 641), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller** (p. 698).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h`

6.31 activemq:wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 337).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h> Inheritance diagram for activemq:wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.31.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 337). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.31.2 Constructor & Destructor Documentation

6.31.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.31.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.31.3 Member Function Documentation

6.31.3.1 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller` (p. 496), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 585), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller` (p. 614), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller` (p. 647), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller` (p. 704).

6.31.3.2 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller** (p. 497), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 585), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 615), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 648), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller** (p. 705).

6.31.3.3 virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller** (p. 497), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 586), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 615), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 648), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller** (p. 705).

6.31.3.4 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller** (p. 497), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 586), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 615), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 648), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller** (p. 705).

6.31.3.5 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

- wireFormat*** - describes the wire format of the broker.
- dataStructure*** - Object to be un-marshaled.
- dataIn*** - BinaryReader that provides that data.
- bs*** - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller** (p. 498), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 587), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 616), **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 649), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller** (p. 706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h`

6.32 activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.341).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.32.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.341). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.32.2 Constructor & Destructor Documentation

6.32.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.32.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.32.3 Member Function Documentation

6.32.3.1 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller` (p. 500), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 589), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller` (p. 618), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller` (p. 643), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller` (p. 700).

6.32.3.2 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller** (p. 501), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 589), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 619), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 644), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller** (p. 701).

6.32.3.3 virtual int ac-
tivemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::tightMarshal
(OpenWireFormat * *wireFormat*, commands::DataStructure *
***dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException)**
[virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller** (p. 501), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 590), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 619), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 644), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller** (p. 701).

6.32.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::tightMarshal2
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataOutputStream * *dataOut*,**
utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller** (p. 501), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 590), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 619), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 644), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller** (p. 701).

6.32.3.5 virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

- wireFormat*** - describes the wire format of the broker.
- dataStructure*** - Object to be un-marshaled.
- dataIn*** - BinaryReader that provides that data.
- bs*** - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller** (p. 502), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 591), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 620), **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 645), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller** (p. 702).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h`

6.33 activemq:wireformat::openwire::marshal:v5::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.345).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h>Inheritance diagram for activemq:wireformat::openwire::marshal:v5::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.33.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.345). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.33.2 Constructor & Destructor Documentation

6.33.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.33.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.33.3 Member Function Documentation

6.33.3.1 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller` (p. 504), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 593), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller` (p. 622), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller` (p. 651), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller` (p. 708).

6.33.3.2 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller** (p. 505), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 593), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 623), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 652), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller** (p. 709).

6.33.3.3 virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller** (p. 505), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 594), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 623), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 652), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller** (p. 709).

6.33.3.4 virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller** (p. 505), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 594), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 623), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 652), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller** (p. 709).

6.33.3.5 virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

- wireFormat*** - describes the wire format of the broker.
- dataStructure*** - Object to be un-marshaled.
- dataIn*** - BinaryReader that provides that data.
- bs*** - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller** (p. 506), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 595), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 624), **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 653), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller** (p. 710).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h`

6.34 activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.349).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.34.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p.349). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.34.2 Constructor & Destructor Documentation

6.34.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.34.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.34.3 Member Function Documentation

6.34.3.1 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller` (p. 508), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 626), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 655), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller` (p. 716).

6.34.3.2 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller` (p. 509), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 627), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 656), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller` (p. 717).

6.34.3.3 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller` (p. 509), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 598), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 627), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 656), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller` (p. 717).

6.34.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller** (p. 509), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 598), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller** (p. 627), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller** (p. 656), and **activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller** (p. 717).

6.34.3.5 virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller** (p. 510), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 599), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller** (p. 628), **activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller** (p. 657), and **activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller** (p. 718).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h`

6.35 activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 353).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQDestinationMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller:

Public Member Functions

- **ActiveMQDestinationMarshaller** ()
- virtual ~**ActiveMQDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.35.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 353). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.35.2 Constructor & Destructor Documentation

6.35.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::ActiveMQDestinationMarshaller()` [inline]

6.35.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::~~ActiveMQDestinationMarshaller()` [inline, virtual]

6.35.3 Member Function Documentation

6.35.3.1 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller` (p. 512), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 601), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller` (p. 630), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller` (p. 659), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller` (p. 712).

6.35.3.2 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller** (p. 513), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 601), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 631), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 660), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller** (p. 713).

6.35.3.3 virtual int ac-
tivemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::tightMarshal
(OpenWireFormat * *wireFormat*, commands::DataStructure *
***dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException)**
[virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller** (p. 513), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 602), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 631), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 660), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller** (p. 713).

6.35.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::tightMarshal2
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataOutputStream * *dataOut*,**
utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller** (p. 513), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 602), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 631), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 660), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller** (p. 713).

6.35.3.5 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

- wireFormat*** - describes the wire format of the broker.
- dataStructure*** - Object to be un-marshaled.
- dataIn*** - BinaryReader that provides that data.
- bs*** - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller** (p. 514), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 603), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 632), **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 661), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller** (p. 714).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQDestinationMarshaller.h`

6.36 activemq::exceptions::ActiveMQException Class Reference

#include <src/main/activemq/exceptions/ActiveMQException.h> Inheritance diagram for activemq::exceptions::ActiveMQException:

Public Member Functions

- **ActiveMQException** () throw ()
Default Constructor.
- **ActiveMQException** (const **ActiveMQException** &ex) throw ()
Copy Constructor.
- **ActiveMQException** (const **decaf::lang::Exception** &ex) throw ()
Copy Constructor.
- **ActiveMQException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual ~**ActiveMQException** () throw ()
- virtual **ActiveMQException** * **clone** () const
Clones this exception.
- virtual **cms::CMSException** **convertToCMSException** () const
Converts this exception to a new CMSException.

6.36.1 Constructor & Destructor Documentation

6.36.1.1 activemq::exceptions::ActiveMQException::ActiveMQException () throw ()

Default Constructor.

6.36.1.2 activemq::exceptions::ActiveMQException::ActiveMQException (const ActiveMQException & ex) throw ()

Copy Constructor.

Parameters:

ex The Exception whose internal data is copied into this instance.

6.36.1.3 `activemq::exceptions::ActiveMQException::ActiveMQException (const decaf::lang::Exception & ex) throw ()`

Copy Constructor.

Parameters:

ex The Exception whose internal data is copied into this instance.

6.36.1.4 `activemq::exceptions::ActiveMQException::ActiveMQException (const char * file, const int lineNumber, const char * msg, ...) throw ()`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message.

Parameters:

file The file name where exception occurs.

lineNumber The line number where the exception occurred.

msg The message to report.

... The list of primitives that are formatted into the message.

6.36.1.5 `virtual activemq::exceptions::ActiveMQException::~~ActiveMQException () throw () [virtual]`

6.36.2 Member Function Documentation

6.36.2.1 `virtual ActiveMQException* activemq::exceptions::ActiveMQException::clone () const [virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

Copy of this Exception object

Reimplemented from `decaf::lang::Exception` (p. 1834).

Reimplemented in `activemq::exceptions::BrokerException` (p. 867).

6.36.2.2 `virtual cms::CMSEException activemq::exceptions::ActiveMQException::convertToCMSEException () const [virtual]`

Converts this exception to a new CMSEException.

Returns:

a CMSEException with the data from this exception

The documentation for this class was generated from the following file:

- `src/main/activemq/exceptions/ActiveMQException.h`

6.37 activemq::commands::ActiveMQMapMessage Class Reference

#include <src/main/activemq/commands/ActiveMQMapMessage.h> Inheritance diagram for activemq::commands::ActiveMQMapMessage:

Public Member Functions

- **ActiveMQMapMessage** ()
- virtual **~ActiveMQMapMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual bool **isMarshalAware** () const
Determine if this object is aware of marshaling and should have its before and after marshaling methods called.
- virtual **ActiveMQMapMessage** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual void **beforeMarshal** (**wireformat::WireFormat** *wireFormat) throw (decaf::io::IOException)
Perform any processing needed before an marshal.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **clearBody** () throw (cms::CMSEException)
Clears out the body of the message.
- virtual **cms::MapMessage** * **clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- virtual std::vector< std::string > **getMapNames** () const throw (cms::CMSEException)
Returns an Enumeration of all the names in the MapMessage object.
- virtual bool **itemExists** (const std::string &name) const throw (cms::CMSEException)
Indicates whether an item exists in this MapMessage object.

- virtual bool **getBoolean** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Boolean value of the Specified name.
- virtual void **setBoolean** (const std::string &name, bool value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a boolean value with the specified name into the Map.
- virtual unsigned char **getByte** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Byte value of the Specified name.
- virtual void **setByte** (const std::string &name, unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Byte value with the specified name into the Map.
- virtual std::vector< unsigned char > **getBytes** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Bytes value of the Specified name.
- virtual void **setBytes** (const std::string &name, const std::vector< unsigned char > &value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Bytes value with the specified name into the Map.
- virtual char **getChar** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Char value of the Specified name.
- virtual void **setChar** (const std::string &name, char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Char value with the specified name into the Map.
- virtual double **getDouble** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Double value of the Specified name.
- virtual void **setDouble** (const std::string &name, double value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Double value with the specified name into the Map.
- virtual float **getFloat** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Float value of the Specified name.
- virtual void **setFloat** (const std::string &name, float value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Float value with the specified name into the Map.
- virtual int **getInt** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Int value of the Specified name.

- virtual void **setInt** (const std::string &name, int value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Int value with the specified name into the Map.
- virtual long long **getLong** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Long value of the Specified name.
- virtual void **setLong** (const std::string &name, long long value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Long value with the specified name into the Map.
- virtual short **getShort** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the Short value of the Specified name.
- virtual void **setShort** (const std::string &name, short value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Short value with the specified name into the Map.
- virtual std::string **getString** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Returns the String value of the Specified name.
- virtual void **setString** (const std::string &name, const std::string &value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a String value with the specified name into the Map.

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQMAPMESSAGE** = 25

Protected Member Functions

- **util::PrimitiveMap & getMap** () throw (decaf::lang::exceptions::NullPointerException)
Fetches a reference to this objects PrimitiveMap, if one needs to be created or unmarshaled, this will perform the correct steps.
- const **util::PrimitiveMap & getMap** () const throw (decaf::lang::exceptions::NullPointerException)
- virtual void **checkMapIsUnmarshalled** () const throw (decaf::lang::exceptions::NullPointerException)
Performs the unmarshal on the Map if needed, otherwise just returns.

6.37.1 Constructor & Destructor Documentation

6.37.1.1 `activemq::commands::ActiveMQMapMessage::ActiveMQMapMessage ()`

6.37.1.2 `virtual
activemq::commands::ActiveMQMapMessage::~~ActiveMQMapMessage ()
[virtual]`

6.37.2 Member Function Documentation

6.37.2.1 `virtual void activemq::commands::ActiveMQMapMessage::beforeMarshal
(wireformat::WireFormat * wireFormat) throw (decaf::io::IOException)
[virtual]`

Perform any processing needed before an marshal.

Parameters:

wireFormat - the OpenWireFormat object in use.

Implements `activemq::wireformat::MarshalAware` (p. 2485).

6.37.2.2 `virtual void ac-
tivemq::commands::ActiveMQMapMessage::checkMapIsUnmarshalled ()
const throw (decaf::lang::exceptions::NullPointerException) [protected,
virtual]`

Performs the unmarshal on the Map if needed, otherwise just returns.

6.37.2.3 `virtual void activemq::commands::ActiveMQMapMessage::clearBody ()
throw (cms::CMSException) [virtual]`

Clears out the body of the message. This does not clear the headers or properties.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 428).

6.37.2.4 `virtual cms::MapMessage* ac-
tivemq::commands::ActiveMQMapMessage::clone () const
[inline, virtual]`

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements `cms::Message` (p. 2539).

6.37.2.5 `virtual ActiveMQMapMessage* activemq::commands::ActiveMQMapMessage::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Message` (p. 2520).

6.37.2.6 `virtual void activemq::commands::ActiveMQMapMessage::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::Message` (p. 2521).

6.37.2.7 `virtual bool activemq::commands::ActiveMQMapMessage::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 429).

6.37.2.8 `virtual bool activemq::commands::ActiveMQMapMessage::getBoolean (const std::string & name) const throw (cms::MessageFormatException, cms::CMSException) [virtual]`

Returns the Boolean value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements `cms::MapMessage` (p. 2474).

6.37.2.9 virtual unsigned char activemq::commands::ActiveMQMapMessage::getByte (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [virtual]

Returns the Byte value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements cms::MapMessage (p. 2475).

6.37.2.10 virtual std::vector<unsigned char> activemq::commands::ActiveMQMapMessage::getBytes (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [virtual]

Returns the Bytes value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements cms::MapMessage (p. 2475).

6.37.2.11 virtual char activemq::commands::ActiveMQMapMessage::getChar (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [virtual]

Returns the Char value of the Specified name.

Parameters:

name name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements cms::MapMessage (p. 2475).

6.37.2.12 `virtual unsigned char activemq::commands::ActiveMQMapMessage::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Message** (p. 2523).

6.37.2.13 `virtual double activemq::commands::ActiveMQMapMessage::getDouble (const std::string & name) const throw (cms::MessageFormatException, cms::CMSException) [virtual]`

Returns the Double value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements **cms::MapMessage** (p. 2476).

6.37.2.14 `virtual float activemq::commands::ActiveMQMapMessage::getFloat (const std::string & name) const throw (cms::MessageFormatException, cms::CMSException) [virtual]`

Returns the Float value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements **cms::MapMessage** (p. 2476).

6.37.2.15 `virtual int activemq::commands::ActiveMQMapMessage::getInt (const std::string & name) const throw (cms::MessageFormatException, cms::CMSException) [virtual]`

Returns the Int value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements **cms::MapMessage** (p. 2476).

6.37.2.16 `virtual long long activemq::commands::ActiveMQMapMessage::getLong (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException) [virtual]`

Returns the Long value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements **cms::MapMessage** (p. 2477).

6.37.2.17 `const util::PrimitiveMap& activemq::commands::ActiveMQMapMessage::getMap () const throw (decaf::lang::exceptions::NullPointerException) [protected]`

6.37.2.18 `util::PrimitiveMap& activemq::commands::ActiveMQMapMessage::getMap () throw (decaf::lang::exceptions::NullPointerException) [protected]`

Fetches a reference to this objects PrimitiveMap, if one needs to be created or unmarshaled, this will perform the correct steps.

Returns:

reference to a PrimitiveMap.

6.37.2.19 `virtual std::vector< std::string > activemq::commands::ActiveMQMapMessage::getMapNames () const throw (cms::CMSEException) [virtual]`

Returns an Enumeration of all the names in the MapMessage object.

Returns:

STL Vector of String values, each of which is the name of an item in the MapMessage

Exceptions:

CMSEException - if the operation fails due to an internal error.

Implements **cms::MapMessage** (p. 2477).

6.37.2.20 `virtual short activemq::commands::ActiveMQMapMessage::getShort
(const std::string & name) const throw (cms::MessageFormatException,
cms::CMSException) [virtual]`

Returns the Short value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements `cms::MapMessage` (p. 2477).

6.37.2.21 `virtual std::string ac-
tivismq::commands::ActiveMQMapMessage::getString
(const std::string & name) const throw (cms::MessageFormatException,
cms::CMSException) [virtual]`

Returns the String value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implements `cms::MapMessage` (p. 2477).

6.37.2.22 `virtual bool ac-
tivismq::commands::ActiveMQMapMessage::isMarshalAware () const
[inline, virtual]`

Determine if this object is aware of marshaling and should have its before and after marshaling methods called. Defaults to false.

Returns:

true if aware of marshaling

Reimplemented from `activemq::commands::Message` (p. 2526).

6.37.2.23 `virtual bool activemq::commands::ActiveMQMapMessage::itemExists
(const std::string & name) const throw (cms::CMSException)
[virtual]`

Indicates whether an item exists in this MapMessage object.

Parameters:

name String name of the Object in question

Returns:

boolean value indicating if the name is in the map

Exceptions:

CMSEException - if the operation fails due to an internal error.

Implements **cms::MapMessage** (p. 2478).

6.37.2.24 `virtual void activemq::commands::ActiveMQMapMessage::setBoolean (const std::string & name, bool value) throw (cms::MessageNotWriteableException, cms::CMSEException)` [virtual]

Sets a boolean value with the specified name into the Map.

Parameters:

name the name of the boolean

value the boolean value to set in the Map

Exceptions:

CMSEException - if the operation fails due to an internal error.

MessageNotWriteableException - if the **Message** (p. 2516) is in Read-only Mode.

Implements **cms::MapMessage** (p. 2478).

6.37.2.25 `virtual void activemq::commands::ActiveMQMapMessage::setByte (const std::string & name, unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSEException)` [virtual]

Sets a Byte value with the specified name into the Map.

Parameters:

name the name of the Byte

value the Byte value to set in the Map

Exceptions:

CMSEException - if the operation fails due to an internal error.

MessageNotWriteableException - if the **Message** (p. 2516) is in Read-only Mode.

Implements **cms::MapMessage** (p. 2478).

6.37.2.26 `virtual void activemq::commands::ActiveMQMapMessage::setBytes (const std::string & name, const std::vector< unsigned char > & value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Bytes value with the specified name into the Map.

Parameters:

name The name of the Bytes

value The Bytes value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2479).

6.37.2.27 `virtual void activemq::commands::ActiveMQMapMessage::setChar (const std::string & name, char value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Char value with the specified name into the Map.

Parameters:

name the name of the Char

value the Char value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2479).

6.37.2.28 `virtual void activemq::commands::ActiveMQMapMessage::setDouble (const std::string & name, double value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Double value with the specified name into the Map.

Parameters:

name The name of the Double

value The Double value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2480).

6.37.2.29 `virtual void activemq::commands::ActiveMQMapMessage::setFloat (const std::string & name, float value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Float value with the specified name into the Map.

Parameters:

name The name of the Float

value The Float value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2480).

6.37.2.30 `virtual void activemq::commands::ActiveMQMapMessage::setInt (const std::string & name, int value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Int value with the specified name into the Map.

Parameters:

name The name of the Int

value The Int value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2480).

6.37.2.31 `virtual void activemq::commands::ActiveMQMapMessage::setLong (const std::string & name, long long value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Sets a Long value with the specified name into the Map.

Parameters:

name The name of the Long

value The Long value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the Message (p. 2516) is in Read-only Mode.

Implements `cms::MapMessage` (p. 2481).

6.37.2.32 `virtual void activemq::commands::ActiveMQMapMessage::setShort (const std::string & name, short value) throw (cms::MessageNotWriteableException, cms::CMSException)` [virtual]

Sets a Short value with the specified name into the Map.

Parameters:

name The name of the Short

value The Short value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the **Message** (p. 2516) is in Read-only Mode.

Implements **cms::MapMessage** (p. 2481).

6.37.2.33 `virtual void activemq::commands::ActiveMQMapMessage::setString (const std::string & name, const std::string & value) throw (cms::MessageNotWriteableException, cms::CMSException)` [virtual]

Sets a String value with the specified name into the Map.

Parameters:

name The name of the String

value The String value to set in the Map

Exceptions:

CMSException - if the operation fails due to an internal error.

MessageNotWriteableException - if the **Message** (p. 2516) is in Read-only Mode.

Implements **cms::MapMessage** (p. 2481).

6.37.2.34 `virtual std::string activemq::commands::ActiveMQMapMessage::toString () const` [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Message** (p. 2530).

6.37.3 Field Documentation

6.37.3.1 `const unsigned char activemq::commands::ActiveMQMapMessage::ID_ - ACTIVEMQMAPMESSAGE = 25` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQMapMessage.h`

6.38 activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.374).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.38.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.374). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.38.2 Constructor & Destructor Documentation

6.38.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()` [inline]

6.38.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()` [inline, virtual]

6.38.3 Member Function Documentation

6.38.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::createObject(const std::string& name) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.38.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.38.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::looseMarshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.38.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.38.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700).

6.38.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p.2701).

6.38.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p.2701).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMapMessageMarshaller.h`

6.39 activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.378).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.39.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.378). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.39.2 Constructor & Destructor Documentation

6.39.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()` [inline]

6.39.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()` [inline, virtual]

6.39.3 Member Function Documentation

6.39.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::createObject(const std::string&)` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.39.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::getDataStructureType()` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.39.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::looseMarshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.39.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.39.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2715).

6.39.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

6.39.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMapMessageMarshaller.h

6.40 activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.382).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.40.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.382). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.40.2 Constructor & Destructor Documentation

6.40.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()` [inline]

6.40.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()` [inline, virtual]

6.40.3 Member Function Documentation

6.40.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::createObject(const std::string& name) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.40.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.40.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::looseMarshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.40.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.40.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2710).

6.40.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p.2711).

6.40.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p.2711).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ActiveMQMapMessageMarshaller.h**

6.41 activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.386).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.41.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.386). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.41.2 Constructor & Destructor Documentation

6.41.2.1 **activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()** [inline]

6.41.2.2 **virtual activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()** [inline, virtual]

6.41.3 Member Function Documentation

6.41.3.1 **virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::createObject(const std::string& name) const** [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1611).

6.41.3.2 **virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::getDataStructureType() const** [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1617).

6.41.3.3 **virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::looseMarshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)** [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.41.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.41.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2695).

6.41.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

6.41.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMapMessageMarshaller.h`

6.42 activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.390).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.42.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p.390). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.42.2 Constructor & Destructor Documentation

6.42.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()` [inline]

6.42.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()` [inline, virtual]

6.42.3 Member Function Documentation

6.42.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.42.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.42.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::looseMarshal(const commands::DataStructure&, const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.42.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.42.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705).

6.42.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

6.42.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMapMessageMarshaller.h`

6.43 activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 394).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQMapMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller:

Public Member Functions

- **ActiveMQMapMessageMarshaller** ()
- virtual **~ActiveMQMapMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.43.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 394). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.43.2 Constructor & Destructor Documentation

6.43.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::ActiveMQMapMessageMarshaller()` [inline]

6.43.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::~~ActiveMQMapMessageMarshaller()` [inline, virtual]

6.43.3 Member Function Documentation

6.43.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::createObject(const std::string&)` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.43.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::getDataStructureType()` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.43.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::looseMarshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.43.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.43.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2720).

6.43.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p.2721).

6.43.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p.2721).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ActiveMQMapMessageMarshaller.h**

6.44 activemq::commands::ActiveMQMessage Class Reference

#include <src/main/activemq/commands/ActiveMQMessage.h> Inheritance diagram for activemq::commands::ActiveMQMessage:

Public Member Functions

- **ActiveMQMessage** ()
- virtual **~ActiveMQMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual **ActiveMQMessage** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual **cms::Message** * **clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQMESSAGE** = 23

6.44.1 Constructor & Destructor Documentation

6.44.1.1 **activemq::commands::ActiveMQMessage::ActiveMQMessage** ()

6.44.1.2 **virtual activemq::commands::ActiveMQMessage::~~ActiveMQMessage** ()
[inline, virtual]

6.44.2 Member Function Documentation

6.44.2.1 **virtual cms::Message* activemq::commands::ActiveMQMessage::clone** ()
const [inline, virtual]

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements **cms::Message** (p. 2539).

6.44.2.2 `virtual ActiveMQMessage* activemq::commands::ActiveMQMessage::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::Message** (p. 2520).

6.44.2.3 `virtual void activemq::commands::ActiveMQMessage::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::Message** (p. 2521).

6.44.2.4 `virtual bool activemq::commands::ActiveMQMessage::equals (const DataStructure * value) const [virtual]`

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQMessageTemplate< cms::Message >** (p. 429).

6.44.2.5 `virtual unsigned char activemq::commands::ActiveMQMessage::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Message** (p. 2523).

6.44.2.6 `virtual std::string activemq::commands::ActiveMQMessage::toString ()` `const` [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::Message` (p. 2530).

6.44.3 Field Documentation

6.44.3.1 `const unsigned char activemq::commands::ActiveMQMessage::ID_-` `ACTIVEMQMESSAGE = 23` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQMessage.h`

6.45 activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 401).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.45.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 401).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.45.2 Constructor & Destructor Documentation

6.45.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.45.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.45.3 Member Function Documentation

6.45.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.45.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.45.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.45.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.45.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700).

```

6.45.3.6 virtual void ac-
tivemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::tightMarshal2
(OpenWireFormat * wireFormat, commands::DataStructure
* dataStructure, decaf::io::DataOutputStream * dataOut,
utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

```

6.45.3.7 virtual void ac-
tivemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller::tightUnmarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
* bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMessageMarshaller.h

6.46 activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 405).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.46.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 405).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.46.2 Constructor & Destructor Documentation

6.46.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.46.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.46.3 Member Function Documentation

6.46.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.46.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.46.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.46.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.46.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2715).

6.46.3.6 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

6.46.3.7 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMessageMarshaller.h`

6.47 activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 409).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.47.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 409).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.47.2 Constructor & Destructor Documentation

6.47.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.47.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.47.3 Member Function Documentation

6.47.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.47.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.47.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.47.3.4 virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::looseUnmarshal (`OpenWireFormat * wireFormat`, `commands::DataStructure * dataStructure`, `decaf::io::DataInputStream * dataIn`) throw (`decaf::io::IOException`) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.47.3.5 virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::tightMarshal1 (`OpenWireFormat * wireFormat`, `commands::DataStructure * dataStructure`, `utils::BooleanStream * bs`) throw (`decaf::io::IOException`) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2710).

6.47.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

6.47.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQMessageMarshaller.h`

6.48 activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 413).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.48.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 413).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.48.2 Constructor & Destructor Documentation

6.48.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.48.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.48.3 Member Function Documentation

6.48.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.48.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.48.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.48.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.48.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2695).

6.48.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

6.48.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMessageMarshaller.h`

6.49 activemq:wireformat::openwire::marshal:v2::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 417).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq:wireformat::openwire::marshal:v2::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.49.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 417).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.49.2 Constructor & Destructor Documentation

6.49.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.49.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.49.3 Member Function Documentation

6.49.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.49.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.49.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.49.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.49.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705).

6.49.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

6.49.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQMessageMarshaller.h`

6.50 activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 421).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller:

Public Member Functions

- **ActiveMQMessageMarshaller** ()
- virtual **~ActiveMQMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.50.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQMessageMarshaller** (p. 421).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.50.2 Constructor & Destructor Documentation

6.50.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::ActiveMQMessageMarshaller()` [inline]

6.50.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::~~ActiveMQMessageMarshaller()` [inline, virtual]

6.50.3 Member Function Documentation

6.50.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.50.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.50.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.50.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.50.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2720).

6.50.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

6.50.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQMessageMarshaller.h`

6.51 activemq::commands::ActiveMQMessageTemplate< T > Class Template Reference

#include <src/main/activemq/commands/ActiveMQMessageTemplate.h> Inheritance diagram for activemq::commands::ActiveMQMessageTemplate< T >:

Public Member Functions

- **ActiveMQMessageTemplate** ()
- virtual **~ActiveMQMessageTemplate** ()
- virtual void **acknowledge** () const throw (cms::IllegalStateException, cms::CMSEException)
Acknowledges all consumed messages of the session of this consumed message.
- virtual void **onSend** ()
*Resets the **Message** (p. 2516) to a Read-Only **state** (p. 95).*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **clearBody** () throw (cms::CMSEException)
Clears out the body of the message.
- virtual void **clearProperties** () throw (cms::CMSEException)
Clears the message properties.
- virtual std::vector< std::string > **getPropertyNames** () const throw (cms::CMSEException)
Retrieves the property names.
- virtual bool **propertyExists** (const std::string &name) const throw (cms::CMSEException)
Indicates whether or not a given property exists.
- virtual bool **getBooleanProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Gets a boolean property.
- virtual unsigned char **getByteProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Gets a byte property.
- virtual double **getDoubleProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)
Gets a double property.
- virtual float **getFloatProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)

Gets a float property.

- virtual int **getIntProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)

Gets a int property.

- virtual long long **getLongProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)

Gets a long property.

- virtual short **getShortProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)

Gets a short property.

- virtual std::string **getStringProperty** (const std::string &name) const throw (cms::MessageFormatException, cms::CMSEException)

Gets a string property.

- virtual void **setBooleanProperty** (const std::string &name, bool value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a boolean property.

- virtual void **setByteProperty** (const std::string &name, unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a byte property.

- virtual void **setDoubleProperty** (const std::string &name, double value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a double property.

- virtual void **setFloatProperty** (const std::string &name, float value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a float property.

- virtual void **setIntProperty** (const std::string &name, int value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a int property.

- virtual void **setLongProperty** (const std::string &name, long long value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a long property.

- virtual void **setShortProperty** (const std::string &name, short value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a short property.

- virtual void **setStringProperty** (const std::string &name, const std::string &value) throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a string property.

- virtual std::string **getCMSCorrelationID** () const throw (cms::CMSEException)

Get the Correlation Id for this message.

- virtual void **setCMSCorrelationID** (const std::string &correlationId) throw (cms::CMSEException)

Sets the Correlation Id used by this message.

- virtual int **getCMSDeliveryMode** () const throw (cms::CMSEException)

Gets the DeliveryMode for this message.

- virtual void **setCMSDeliveryMode** (int mode) throw (cms::CMSEException)

Sets the DeliveryMode for this message.

- virtual const cms::Destination * **getCMSDestination** () const throw (cms::CMSEException)

*Gets the Destination for this **Message** (p. 2516), returns a.*

- virtual void **setCMSDestination** (const cms::Destination *destination) throw (cms::CMSEException)

Sets the Destination for this message.

- virtual long long **getCMSExpiration** () const throw (cms::CMSEException)

*Gets the Expiration Time for this **Message** (p. 2516).*

- virtual void **setCMSExpiration** (long long expireTime) throw (cms::CMSEException)

Sets the Expiration Time for this message.

- virtual std::string **getCMSMessageID** () const throw (cms::CMSEException)

*Gets the CMS **Message** (p. 2516) Id for this **Message** (p. 2516).*

- virtual void **setCMSMessageID** (const std::string &id AMQCPP_UNUSED) throw (cms::CMSEException)

*Sets the CMS **Message** (p. 2516) Id for this message.*

- virtual int **getCMSPriority** () const throw (cms::CMSEException)

*Gets the Priority Value for this **Message** (p. 2516).*

- virtual void **setCMSPriority** (int priority) throw (cms::CMSEException)

Sets the Priority Value for this message.

- virtual bool **getCMSRedelivered** () const throw (cms::CMSEException)

*Gets the Redelivered Flag for this **Message** (p. 2516).*

- virtual void **setCMSRedelivered** (bool redelivered AMQCPP_UNUSED) throw (cms::CMSEException)

Sets the Redelivered Flag for this message.

- virtual const cms::Destination * **getCMSReplyTo** () const throw (cms::CMSEException)

*Gets the CMS Reply To Address for this **Message** (p. 2516).*

- virtual void **setCMSReplyTo** (const **cms::Destination** *destination) throw (cms::CMSException)
Sets the CMS Reply To Address for this message.
- virtual long long **getCMSTimestamp** () const throw (cms::CMSException)
*Gets the Time Stamp for this **Message** (p. 2516).*
- virtual void **setCMSTimestamp** (long long timeStamp) throw (cms::CMSException)
Sets the Time Stamp for this message.
- virtual std::string **getCMSType** () const throw (cms::CMSException)
*Gets the CMS **Message** (p. 2516) Type for this **Message** (p. 2516).*
- virtual void **setCMSType** (const std::string &type) throw (cms::CMSException)
*Sets the CMS **Message** (p. 2516) Type for this message.*

Protected Member Functions

- void **failIfWriteOnlyBody** () const
- void **failIfReadOnlyBody** () const
- void **failIfReadOnlyProperties** () const

```
template<typename T> class activemq::commands::ActiveMQMessageTemplate< T
>
```

6.51.1 Constructor & Destructor Documentation

- 6.51.1.1 `template<typename T>
activemq::commands::ActiveMQMessageTemplate< T
>::ActiveMQMessageTemplate () [inline]`
- 6.51.1.2 `template<typename T> virtual
activemq::commands::ActiveMQMessageTemplate< T
>::~~ActiveMQMessageTemplate () [inline, virtual]`

6.51.2 Member Function Documentation

- 6.51.2.1 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::acknowledge () const throw (cms::IllegalStateException,
cms::CMSException) [inline, virtual]`

Acknowledges all consumed messages of the session of this consumed message.

- 6.51.2.2 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::clearBody () throw (cms::CMSException) [inline, virtual]`

Clears out the body of the message. This does not clear the headers or properties.

Reimplemented in **activemq::commands::ActiveMQBytesMessage** (p. 236), **activemq::commands::ActiveMQMapMessage** (p. 363), **activemq::commands::ActiveMQStreamMessage** (p. 540), and **activemq::commands::ActiveMQTextMessage** (p. 663).

6.51.2.3 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::clearProperties () throw (cms::CMSException) [inline, virtual]`

Clears the message properties. Does not clear the body or header values.

6.51.2.4 `template<typename T> virtual bool
activemq::commands::ActiveMQMessageTemplate< T
>::equals (const DataStructure * value) const [inline, virtual]`

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::Message** (p. 2521).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 206), **activemq::commands::ActiveMQBytesMessage** (p. 237), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage** (p. 444), **activemq::commands::ActiveMQStreamMessage** (p. 541), and **activemq::commands::ActiveMQTextMessage** (p. 664).

6.51.2.5 `template<typename T> void
activemq::commands::ActiveMQMessageTemplate< T
>::failIfReadOnlyBody () const [inline, protected]`

6.51.2.6 `template<typename T> void
activemq::commands::ActiveMQMessageTemplate< T
>::failIfReadOnlyProperties () const [inline, protected]`

6.51.2.7 `template<typename T> void
activemq::commands::ActiveMQMessageTemplate< T
>::failIfWriteOnlyBody () const [inline, protected]`

6.51.2.8 `template<typename T> virtual bool
activemq::commands::ActiveMQMessageTemplate< T
>::getBooleanProperty (const std::string & name) const throw (
cms::MessageFormatException, cms::CMSException) [inline, virtual]`

Gets a boolean property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

```
6.51.2.9  template<typename T> virtual unsigned char
          activemq::commands::ActiveMQMessageTemplate< T >::getByteProperty
          (const std::string & name) const throw ( cms::MessageFormatException,
          cms::CMSEException ) [inline, virtual]
```

Gets a byte property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

```
6.51.2.10 template<typename T> virtual std::string
          activemq::commands::ActiveMQMessageTemplate< T
          >::getCMSCorrelationID () const throw ( cms::CMSEException )
          [inline, virtual]
```

Get the Correlation Id for this message.

Returns:

string representation of the correlation Id

Exceptions:

CMSEException

```
6.51.2.11 template<typename T> virtual int
          activemq::commands::ActiveMQMessageTemplate< T
          >::getCMSDeliveryMode () const throw ( cms::CMSEException )
          [inline, virtual]
```

Gets the DeliveryMode for this message.

Returns:

DeliveryMode enumerated value.

Exceptions:

CMSException

6.51.2.12 `template<typename T> virtual const cms::Destination*
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSDestination () const throw (cms::CMSException) [inline,
virtual]`

Gets the Destination for this **Message** (p. 2516), returns a.

Returns:

Destination object

Exceptions:

CMSException

6.51.2.13 `template<typename T> virtual long long
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSExpiration () const throw (cms::CMSException) [inline,
virtual]`

Gets the Expiration Time for this **Message** (p. 2516).

Returns:

time value

Exceptions:

CMSException

6.51.2.14 `template<typename T> virtual std::string
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSMessageID () const throw (cms::CMSException) [inline,
virtual]`

Gets the CMS **Message** (p. 2516) Id for this **Message** (p. 2516).

Returns:

time value

Exceptions:

CMSException

6.51.2.15 `template<typename T> virtual int
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSPriority () const throw (cms::CMSException) [inline,
virtual]`

Gets the Priority Value for this **Message** (p. 2516).

Returns:

priority value

Exceptions:

CMSException

6.51.2.16 `template<typename T> virtual bool
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSRedelivered () const throw (cms::CMSException) [inline,
virtual]`

Gets the Redelivered Flag for this **Message** (p. 2516).

Returns:

redelivered value

Exceptions:

CMSException

6.51.2.17 `template<typename T> virtual const cms::Destination*
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSReplyTo () const throw (cms::CMSException) [inline,
virtual]`

Gets the CMS Reply To Address for this **Message** (p. 2516).

Returns:

Reply To Value

Exceptions:

CMSException

6.51.2.18 `template<typename T> virtual long long
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSTimestamp () const throw (cms::CMSException) [inline,
virtual]`

Gets the Time Stamp for this **Message** (p. 2516).

Returns:

time stamp value

Exceptions:

CMSEException

6.51.2.19 `template<typename T> virtual std::string
activemq::commands::ActiveMQMessageTemplate< T
>::getCMSType () const throw (cms::CMSEException) [inline,
virtual]`

Gets the CMS Message (p. 2516) Type for this Message (p. 2516).

Returns:

type value

Exceptions:

CMSEException

6.51.2.20 `template<typename T> virtual double
activemq::commands::ActiveMQMessageTemplate< T
>::getDoubleProperty (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException) [inline, virtual]`

Gets a double property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

6.51.2.21 `template<typename T> virtual float
activemq::commands::ActiveMQMessageTemplate< T
>::getFloatProperty (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException) [inline, virtual]`

Gets a float property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

```
6.51.2.22  template<typename T> virtual int
             activemq::commands::ActiveMQMessageTemplate< T
             >::getIntProperty (const std::string & name) const throw (
             cms::MessageFormatException, cms::CMSEException ) [inline, virtual]
```

Gets a int property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

```
6.51.2.23  template<typename T> virtual long long
             activemq::commands::ActiveMQMessageTemplate< T
             >::getLongProperty (const std::string & name) const throw (
             cms::MessageFormatException, cms::CMSEException ) [inline, virtual]
```

Gets a long property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.


```
6.51.2.24  template<typename T> virtual std::vector<std::string>
           activemq::commands::ActiveMQMessageTemplate< T
           >::getPropertyNames () const throw ( cms::CMSEException ) [inline,
           virtual]
```

Retrieves the property names.

Returns:

The complete set of property names currently in this message.

```
6.51.2.25  template<typename T> virtual short
           activemq::commands::ActiveMQMessageTemplate< T
           >::getShortProperty (const std::string & name) const throw (
           cms::MessageFormatException, cms::CMSEException ) [inline, virtual]
```

Gets a short property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

```
6.51.2.26  template<typename T> virtual std::string
           activemq::commands::ActiveMQMessageTemplate< T
           >::getStringProperty (const std::string & name) const throw (
           cms::MessageFormatException, cms::CMSEException ) [inline, virtual]
```

Gets a string property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException if the property does not exist.

MessageFormatException - if this type conversion is invalid.

6.51.2.27 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::onSend () [inline, virtual]`

Resets the **Message** (p. 2516) to a Read-Only state (p. 95).

Reimplemented from **activemq::commands::Message** (p. 2527).

Reimplemented in **activemq::commands::ActiveMQBytesMessage** (p. 238), and **activemq::commands::ActiveMQStreamMessage** (p. 541).

6.51.2.28 `template<typename T> virtual bool
activemq::commands::ActiveMQMessageTemplate< T
>::propertyExists (const std::string & name) const throw (cms::CMSException) [inline, virtual]`

Indicates whether or not a given property exists.

Parameters:

name The name of the property to look up.

Returns:

True if the property exists in this message.

6.51.2.29 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setBooleanProperty (const std::string & name, bool value) throw (cms::MessageNotWriteableException, cms::CMSException) [inline, virtual]`

Sets a boolean property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.30 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setByteProperty (const std::string & name, unsigned char value)
throw (cms::MessageNotWriteableException, cms::CMSException)
[inline, virtual]`

Sets a byte property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.31 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSCorrelationID (const std::string & correlationId) throw (cms::CMSException) [inline, virtual]`

Sets the Correlation Id used by this message.

Parameters:

correlationId - String representing the correlation id.

Exceptions:

CMSException

6.51.2.32 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSDeliveryMode (int mode) throw (cms::CMSException) [inline, virtual]`

Sets the DeliveryMode for this message.

Parameters:

mode - DeliveryMode enumerated value.

Exceptions:

CMSException

6.51.2.33 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSDestination (const cms::Destination * destination) throw (cms::CMSException) [inline, virtual]`

Sets the Destination for this message.

Parameters:

destination - Destination Object

Exceptions:

CMSException

6.51.2.34 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSExpiration (long long expireTime) throw (cms::CMSException)` [inline, virtual]

Sets the Expiration Time for this message.

Parameters:

expireTime - time value

Exceptions:

CMSException

6.51.2.35 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSMessageID (const std::string &id AMQCPP_UNUSED)
throw (cms::CMSException)` [inline, virtual]

Sets the CMS Message (p. 2516) Id for this message.

Parameters:

id - time value

Exceptions:

CMSException

6.51.2.36 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSPriority (int priority) throw (cms::CMSException)` [inline, virtual]

Sets the Priority Value for this message.

Parameters:

priority - priority value for this message

Exceptions:

CMSException

6.51.2.37 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setCMSRedelivered (bool redelivered AMQCPP_UNUSED) throw (cms::CMSException)` [inline, virtual]

Sets the Redelivered Flag for this message.

Parameters:

redelivered - boolean redelivered value

Exceptions:

CMSException

```
6.51.2.38  template<typename T> virtual void
           activemq::commands::ActiveMQMessageTemplate< T
           >::setCMSReplyTo (const cms::Destination * destination) throw (
           cms::CMSException ) [inline, virtual]
```

Sets the CMS Reply To Address for this message.

Parameters:

destination Pointer to the CMS Destination that is the Reply-To value.

Exceptions:

CMSException

```
6.51.2.39  template<typename T> virtual void
           activemq::commands::ActiveMQMessageTemplate< T
           >::setCMSTimestamp (long long timeStamp) throw (
           cms::CMSException ) [inline, virtual]
```

Sets the Time Stamp for this message.

Parameters:

timeStamp - integer time stamp value

Exceptions:

CMSException

```
6.51.2.40  template<typename T> virtual void
           activemq::commands::ActiveMQMessageTemplate< T
           >::setCMSType (const std::string & type) throw ( cms::CMSException )
           [inline, virtual]
```

Sets the CMS **Message** (p. 2516) Type for this message.

Parameters:

type - message type value string

Exceptions:

CMSException

6.51.2.41 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setDoubleProperty (const std::string & name, double value) throw (
cms::MessageNotWriteableException, cms::CMSEException) [inline,
virtual]`

Sets a double property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSEException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.42 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setFloatProperty (const std::string & name, float value) throw (
cms::MessageNotWriteableException, cms::CMSEException) [inline,
virtual]`

Sets a float property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSEException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.43 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setIntProperty (const std::string & name, int value) throw (
cms::MessageNotWriteableException, cms::CMSEException) [inline,
virtual]`

Sets a int property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSEException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.44 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setLongProperty (const std::string & name, long long value) throw (
cms::MessageNotWriteableException, cms::CMSException) [inline,
virtual]`

Sets a long property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.45 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setShortProperty (const std::string & name, short value) throw (
cms::MessageNotWriteableException, cms::CMSException) [inline,
virtual]`

Sets a short property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

6.51.2.46 `template<typename T> virtual void
activemq::commands::ActiveMQMessageTemplate< T
>::setStringProperty (const std::string & name, const std::string &
value) throw (cms::MessageNotWriteableException, cms::CMSException
) [inline, virtual]`

Sets a string property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException - if the name is an empty string.

MessageNotWriteableException - if properties are read-only

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQMessageTemplate.h`

6.52 activemq::commands::ActiveMQObjectMessage Class Reference

#include <src/main/activemq/commands/ActiveMQObjectMessage.h> Inheritance diagram for activemq::commands::ActiveMQObjectMessage:

Public Member Functions

- **ActiveMQObjectMessage** ()
- virtual **~ActiveMQObjectMessage** ()
- virtual unsigned char **getDataStructureType** () const

Get the unique identifier that this object and its own Marshaler share.

- virtual **ActiveMQObjectMessage * cloneDataStructure** () const

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

- virtual void **copyDataStructure** (const **DataStructure** *src)

Copy the contents of the passed object into this objects members, overwriting any existing data.

- virtual std::string **toString** () const

*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*

- virtual bool **equals** (const **DataStructure** *value) const

*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

- virtual **cms::Message * clone** () const

Clone this message exactly, returns a new instance that the caller is required to delete.

Static Public Attributes

- static const unsigned char **ID _ACTIVEMQOBJECTMESSAGE** = 26

6.52.1 Constructor & Destructor Documentation

6.52.1.1 `activemq::commands::ActiveMQObjectMessage::ActiveMQObjectMessage()`

6.52.1.2 `virtual activemq::commands::ActiveMQObjectMessage::~~ActiveMQObjectMessage()` [inline, virtual]

6.52.2 Member Function Documentation

6.52.2.1 `virtual cms::Message* activemq::commands::ActiveMQObjectMessage::clone() const` [inline, virtual]

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements `cms::Message` (p. 2539).

6.52.2.2 `virtual ActiveMQObjectMessage* activemq::commands::ActiveMQObjectMessage::cloneDataStructure() const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Message` (p. 2520).

6.52.2.3 `virtual void activemq::commands::ActiveMQObjectMessage::copyDataStructure(const DataStructure * src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::Message` (p. 2521).

6.52.2.4 `virtual bool activemq::commands::ActiveMQObjectMessage::equals(const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 429).

6.52.2.5 `virtual unsigned char activemq::commands::ActiveMQObjectMessage::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from `activemq::commands::Message` (p. 2523).

6.52.2.6 `virtual std::string activemq::commands::ActiveMQObjectMessage::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::Message` (p. 2530).

6.52.3 Field Documentation

6.52.3.1 `const unsigned char activemq::commands::ActiveMQObjectMessage::ID_-ACTIVEMQOBJECTMESSAGE = 26 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQObjectMessage.h`

6.53 activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 446).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.53.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 446). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.53.2 Constructor & Destructor Documentation

6.53.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()` [inline]

6.53.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()` [inline, virtual]

6.53.3 Member Function Documentation

6.53.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.53.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.53.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure&, OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.53.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.53.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700).

```

6.53.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

```

6.53.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQObjectMessageMarshaller.h

6.54 activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 450).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller`:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.54.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 450). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.54

activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller
Class Reference

451

6.54.2 Constructor & Destructor Documentation

6.54.2.1 **activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()** [inline]

6.54.2.2 **virtual activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()** [inline, virtual]

6.54.3 Member Function Documentation

6.54.3.1 **virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::createObject(const unsigned char*)** [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1611).

6.54.3.2 **virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::getDataStructureType()** [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1617).

6.54.3.3 **virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)** [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.54.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.54.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2715).

```

6.54.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

```

6.54.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQObjectMessageMarshaller.h

6.55 activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 454).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.55.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 454). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.55.2 Constructor & Destructor Documentation

6.55.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()` [inline]

6.55.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()` [inline, virtual]

6.55.3 Member Function Documentation

6.55.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::createObject(const std::string& name) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.55.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.55.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.55.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.55.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2710).

```

6.55.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

```

6.55.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQObjectMessageMarshaller.h

6.56 activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 458).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller`:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.56.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 458). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.56.2 Constructor & Destructor Documentation

6.56.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()` [inline]

6.56.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()` [inline, virtual]

6.56.3 Member Function Documentation

6.56.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.56.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.56.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure& dataStructure, decaf::io::DataOutputStream& dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.56.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.56.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2695).

```

6.56.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

```

6.56.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQObjectMessageMarshaller.h

6.57 activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 462).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller`:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.57.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 462). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.57.2 Constructor & Destructor Documentation

6.57.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()` [inline]

6.57.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()` [inline, virtual]

6.57.3 Member Function Documentation

6.57.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.57.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.57.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure& dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.57.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.57.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705).

```

6.57.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

```

6.57.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQObjectMessageMarshaller.h

6.58 activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 466).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQObjectMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller:

Public Member Functions

- **ActiveMQObjectMessageMarshaller** ()
- virtual **~ActiveMQObjectMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.58.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 466). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.58.2 Constructor & Destructor Documentation

6.58.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::ActiveMQObjectMessageMarshaller()` [inline]

6.58.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::~~ActiveMQObjectMessageMarshaller()` [inline, virtual]

6.58.3 Member Function Documentation

6.58.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.58.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.58.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::marshal(const commands::DataStructure&, OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.58.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.58.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2720).

```

6.58.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::tightMarshal
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

```

6.58.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller::tightUnma
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQObjectMessageMarshaller.h

6.59 activemq::core::ActiveMQProducer Class Reference

#include <src/main/activemq/core/ActiveMQProducer.h> Inheritance diagram for activemq::core::ActiveMQProducer:

Public Member Functions

- **ActiveMQProducer** (**ActiveMQSession** *session, const **Pointer**< **commands::ProducerId** > &producerId, const **Pointer**< **commands::ActiveMQDestination** > &destination, long long sendTimeout)

*Constructor, creates an instance of an **ActiveMQProducer** (p. 470).*

- virtual ~**ActiveMQProducer** ()
- virtual void **close** () throw (cms::CMSEException)

Closes the Consumer.

- virtual void **send** (cms::Message *message) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.

- virtual void **send** (cms::Message *message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.

- virtual void **send** (const cms::Destination *destination, cms::Message *message) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.

- virtual void **send** (const cms::Destination *destination, cms::Message *message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.

- virtual void **setDeliveryMode** (int mode) throw (cms::CMSEException)

Sets the delivery mode for this Producer.

- virtual int **getDeliveryMode** () const throw (cms::CMSEException)

Gets the delivery mode for this Producer.

- virtual void **setDisableMessageID** (bool value) throw (cms::CMSEException)

Sets if Message Ids are disabled for this Producer.

- virtual bool **getDisableMessageID** () const throw (cms::CMSEException)
Gets if Message Ids are disabled for this Producer.
- virtual void **setDisableMessageTimeStamp** (bool value) throw (cms::CMSEException)
Sets if Message Time Stamps are disabled for this Producer.
- virtual bool **getDisableMessageTimeStamp** () const throw (cms::CMSEException)
Gets if Message Time Stamps are disabled for this Producer.
- virtual void **setPriority** (int priority) throw (cms::CMSEException)
Sets the Priority that this Producers sends messages at.
- virtual int **getPriority** () const throw (cms::CMSEException)
Gets the Priority level that this producer sends messages at.
- virtual void **setTimeToLive** (long long time) throw (cms::CMSEException)
Sets the Time to Live that this Producers sends messages with.
- virtual long long **getTimeToLive** () const throw (cms::CMSEException)
Gets the Time to Live that this producer sends messages with.
- virtual void **setSendTimeout** (long long time) throw (cms::CMSEException)
Sets the Send Timeout that this Producers sends messages with.
- virtual long long **getSendTimeout** () const throw (cms::CMSEException)
Gets the Send Timeout that this producer sends messages with.
- bool **isClosed** () const
- const **Pointer**< **commands::ProducerInfo** > & **getProducerInfo** () const
Retries this object ProducerInfo pointer.
- const **Pointer**< **commands::ProducerId** > & **getProducerId** () const
Retries this object ProducerId or NULL if closed.
- virtual void **onProducerAck** (const **commands::ProducerAck** &ack)
Handles the work of Processing a ProducerAck Command from the Broker.

6.59.1 Constructor & Destructor Documentation

6.59.1.1 **activemq::core::ActiveMQProducer::ActiveMQProducer**
(**ActiveMQSession** * *session*, const **Pointer**< **commands::ProducerId** >
& *producerId*, const **Pointer**< **commands::ActiveMQDestination** > &
destination, long long *sendTimeout*)

Constructor, creates an instance of an **ActiveMQProducer** (p. 470).

Parameters:

session The Session which is the parent of this Producer.

producerId Pointer to a ProducerId object which identifies this producer.

destination The assigned Destination this Producer sends to, or null if not set. The Producer does not own the Pointer passed.

sendTimeout The configured send timeout for this Producer.

6.59.1.2 `virtual activemq::core::ActiveMQProducer::~~ActiveMQProducer ()`
[virtual]

6.59.2 Member Function Documentation

6.59.2.1 `virtual void activemq::core::ActiveMQProducer::close () throw (`
`cms::CMSException)` [virtual]

Closes the Consumer. This will return all allocated resources and purge any outstanding messages. This method will block if there is a call to receive in progress, or a dispatch to a MessageListener in place

Exceptions:

CMSException

Implements **cms::Closeable** (p. 1148).

6.59.2.2 `virtual int activemq::core::ActiveMQProducer::getDeliveryMode () const`
`throw (cms::CMSException)` [inline, virtual]

Gets the delivery mode for this Producer.

Returns:

The DeliveryMode

Implements **cms::MessageProducer** (p. 2726).

6.59.2.3 `virtual bool activemq::core::ActiveMQProducer::getDisableMessageID ()`
`const throw (cms::CMSException)` [inline, virtual]

Gets if Message Ids are disabled for this Producer.

Returns:

a boolean indicating **state** (p. 95) enable / disable (true / false) for MessageIds.

Implements **cms::MessageProducer** (p. 2727).

6.59.2.4 `virtual bool ac-`
`tivemq::core::ActiveMQProducer::getDisableMessageTimeStamp () const`
`throw (cms::CMSException)` [inline, virtual]

Gets if Message Time Stamps are disabled for this Producer.

Returns:

boolean indicating **state** (p. 95) of enable / disable (true / false)

Implements **cms::MessageProducer** (p. 2727).

6.59.2.5 `virtual int activemq::core::ActiveMQProducer::getPriority () const throw (cms::CMSEException) [inline, virtual]`

Gets the Priority level that this producer sends messages at.

Returns:

int based priority level

Implements **cms::MessageProducer** (p. 2727).

6.59.2.6 `const Pointer<commands::ProducerId>& activemq::core::ActiveMQProducer::getProducerId () const [inline]`

Retries this object ProducerId or NULL if closed.

Returns:

ProducerId Reference

6.59.2.7 `const Pointer<commands::ProducerInfo>& activemq::core::ActiveMQProducer::getProducerInfo () const [inline]`

Retries this object ProducerInfo pointer.

Returns:

ProducerInfo Reference

6.59.2.8 `virtual long long activemq::core::ActiveMQProducer::getSendTimeout () const throw (cms::CMSEException) [inline, virtual]`

Gets the Send Timeout that this producer sends messages with.

Returns:

The default send timeout value in milliseconds.

6.59.2.9 `virtual long long activemq::core::ActiveMQProducer::getTimeToLive () const throw (cms::CMSEException) [inline, virtual]`

Gets the Time to Live that this producer sends messages with.

Returns:

The default time to live value in milliseconds.

Implements **cms::MessageProducer** (p. 2728).

6.59.2.10 bool activemq::core::ActiveMQProducer::isClosed () const [inline]**Returns:**

true if this Producer has been closed.

6.59.2.11 virtual void activemq::core::ActiveMQProducer::onProducerAck (const commands::ProducerAck & ack) [virtual]

Handles the work of Processing a ProducerAck Command from the Broker.

Parameters:

ack - The ProducerAck message received from the Broker.

6.59.2.12 virtual void activemq::core::ActiveMQProducer::send (const cms::Destination * destination, cms::Message * message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException) [virtual]

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

destination The destination on which to send the message

message The message to be sent.

deliveryMode The delivery mode to be used.

priority The priority for this message.

timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements **cms::MessageProducer** (p. 2728).

6.59.2.13 virtual void activemq::core::ActiveMQProducer::send (const cms::Destination * *destination*, cms::Message * *message*) throw (cms::CMSException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException) [virtual]

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

destination The destination on which to send the message

message the message to be sent.

Exceptions:

CMSException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements cms::MessageProducer (p. 2728).

6.59.2.14 virtual void activemq::core::ActiveMQProducer::send (cms::Message * *message*, int *deliveryMode*, int *priority*, long long *timeToLive*) throw (cms::CMSException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException) [virtual]

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

message The message to be sent.

deliveryMode The delivery mode to be used.

priority The priority for this message.

timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements cms::MessageProducer (p. 2729).

6.59.2.15 `virtual void activemq::core::ActiveMQProducer::send (cms::Message * message) throw (cms::CMSException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException) [virtual]`

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

message The message to be sent.

Exceptions:

CMSException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements **cms::MessageProducer** (p. 2729).

6.59.2.16 `virtual void activemq::core::ActiveMQProducer::setDeliveryMode (int mode) throw (cms::CMSException) [inline, virtual]`

Sets the delivery mode for this Producer.

Parameters:

mode - The DeliveryMode to use for Message sends.

Implements **cms::MessageProducer** (p. 2730).

6.59.2.17 `virtual void activemq::core::ActiveMQProducer::setDisableMessageID (bool value) throw (cms::CMSException) [inline, virtual]`

Sets if Message Ids are disabled for this Producer.

Parameters:

value - boolean indicating enable / disable (true / false)

Implements **cms::MessageProducer** (p. 2730).

6.59.2.18 `virtual void activemq::core::ActiveMQProducer::setDisableMessageTimeStamp (bool value) throw (cms::CMSException) [inline, virtual]`

Sets if Message Time Stamps are disabled for this Producer.

Parameters:

value - boolean indicating enable / disable (true / false)

Implements **cms::MessageProducer** (p. 2730).

6.59.2.19 `virtual void activemq::core::ActiveMQProducer::setPriority (int priority) throw (cms::CMSException) [inline, virtual]`

Sets the Priority that this Producers sends messages at.

Parameters:

priority int value for Priority level

Implements **cms::MessageProducer** (p. 2731).

6.59.2.20 `virtual void activemq::core::ActiveMQProducer::setSendTimeout (long long time) throw (cms::CMSException) [inline, virtual]`

Sets the Send Timeout that this Producers sends messages with.

Parameters:

time The new default send timeout value in milliseconds.

6.59.2.21 `virtual void activemq::core::ActiveMQProducer::setTimeToLive (long long time) throw (cms::CMSException) [inline, virtual]`

Sets the Time to Live that this Producers sends messages with.

Parameters:

time The new default time to live value in milliseconds.

Implements **cms::MessageProducer** (p. 2731).

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQProducer.h`

6.60 activemq::util::ActiveMQProperties Class Reference

Implementation of the CMSProperties interface that delegates to a **decaf::util::Properties** (p. 3126) object.

#include <src/main/activemq/util/ActiveMQProperties.h> Inheritance diagram for activemq::util::ActiveMQProperties:

Public Member Functions

- **ActiveMQProperties** ()
- virtual **~ActiveMQProperties** ()
- virtual **decaf::util::Properties** & **getProperties** ()
- virtual const **decaf::util::Properties** & **getProperties** () const
- virtual void **setProperties** (decaf::util::Properties &props)
- virtual bool **isEmpty** () const
Returns true if the properties object is empty.
- virtual const char * **getProperty** (const std::string &name) const
Looks up the value for the given property.
- virtual std::string **getProperty** (const std::string &name, const std::string &defaultValue) const
Looks up the value for the given property.
- virtual void **setProperty** (const std::string &name, const std::string &value)
Sets the value for a given property.
- virtual bool **hasProperty** (const std::string &name) const
Check to see if the Property exists in the set.
- virtual void **remove** (const std::string &name)
Removes the property with the given name.
- virtual std::vector< std::pair< std::string, std::string > > **toArray** () const
Method that serializes the contents of the property map to an array.
- virtual void **copy** (const CMSProperties *source)
Copies the contents of the given properties object to this one.
- virtual CMSProperties * **clone** () const
Clones this object.
- virtual void **clear** ()
Clears all properties from the map.
- virtual std::string **toString** () const
Formats the contents of the Properties Object into a string that can be logged, etc.

6.60.1 Detailed Description

Implementation of the CMSProperties interface that delegates to a **decaf::util::Properties** (p. 3126) object.

Since:

2.0

6.60.2 Constructor & Destructor Documentation

6.60.2.1 `activemq::util::ActiveMQProperties::ActiveMQProperties ()`

6.60.2.2 `virtual activemq::util::ActiveMQProperties::~~ActiveMQProperties ()`
[virtual]

6.60.3 Member Function Documentation

6.60.3.1 `virtual void activemq::util::ActiveMQProperties::clear ()` [inline, virtual]

Clears all properties from the map.

Implements **cms::CMSProperties** (p. 1166).

6.60.3.2 `virtual CMSProperties* activemq::util::ActiveMQProperties::clone ()`
`const` [virtual]

Clones this object.

Returns:

a replica of this object.

Implements **cms::CMSProperties** (p. 1166).

6.60.3.3 `virtual void activemq::util::ActiveMQProperties::copy (const CMSProperties * source)` [virtual]

Copies the contents of the given properties object to this one.

Parameters:

source The source properties object.

6.60.3.4 `virtual const decaf::util::Properties& activemq::util::ActiveMQProperties::getProperties () const` [inline, virtual]

6.60.3.5 `virtual decaf::util::Properties& activemq::util::ActiveMQProperties::getProperties ()` [inline, virtual]

6.60.3.6 `virtual std::string activemq::util::ActiveMQProperties::getProperty (const std::string & name, const std::string & defaultValue) const` [inline, virtual]

Looks up the value for the given property.

Parameters:

name the name of the property to be looked up.

defaultValue The value to be returned if the given property does not exist.

Returns:

The value of the property specified by *name*, if it exists, otherwise the *defaultValue*.

Implements **cms::CMSProperties** (p. 1166).

6.60.3.7 `virtual const char* activemq::util::ActiveMQProperties::getProperty (const std::string & name) const` [inline, virtual]

Looks up the value for the given property.

Parameters:

name The name of the property to be looked up.

Returns:

the value of the property with the given name, if it exists. If it does not exist, returns NULL.

Implements **cms::CMSProperties** (p. 1167).

6.60.3.8 `virtual bool activemq::util::ActiveMQProperties::hasProperty (const std::string & name) const` [inline, virtual]

Check to see if the Property exists in the set.

Parameters:

name - property name to check for in this properties set.

Returns:

true if property exists, false otherwise.

Implements **cms::CMSProperties** (p. 1167).

6.60.3.9 virtual bool activemq::util::ActiveMQProperties::isEmpty () const
[inline, virtual]

Returns true if the properties object is empty.

Returns:

true if empty

Implements **cms::CMSProperties** (p. 1167).

6.60.3.10 virtual void activemq::util::ActiveMQProperties::remove (const std::string & name) [inline, virtual]

Removes the property with the given name.

Parameters:

name the name of the property to remove.

Implements **cms::CMSProperties** (p. 1167).

6.60.3.11 virtual void activemq::util::ActiveMQProperties::setProperties (decaf::util::Properties & props) [inline, virtual]**6.60.3.12 virtual void activemq::util::ActiveMQProperties::setProperty (const std::string & name, const std::string & value)** [inline, virtual]

Sets the value for a given property. If the property already exists, overwrites the value.

Parameters:

name The name of the value to be written.

value The value to be written.

Implements **cms::CMSProperties** (p. 1168).

6.60.3.13 virtual std::vector< std::pair< std::string, std::string > > activemq::util::ActiveMQProperties::toArray () const [inline, virtual]

Method that serializes the contents of the property map to an array.

Returns:

list of pairs where the first is the name and the second is the value.

Implements **cms::CMSProperties** (p. 1168).

6.60.3.14 virtual std::string activemq::util::ActiveMQProperties::toString () const
[inline, virtual]

Formats the contents of the Properties Object into a string that can be logged, etc.

Returns:

string value of this object.

Implements **cms::CMSProperties** (p. 1168).

The documentation for this class was generated from the following file:

- `src/main/activemq/util/ActiveMQProperties.h`

6.61 activemq::commands::ActiveMQQueue Class Reference

#include <src/main/activemq/commands/ActiveMQQueue.h> Inheritance diagram for activemq::commands::ActiveMQQueue:

Public Member Functions

- **ActiveMQQueue** ()
- **ActiveMQQueue** (const std::string &name)
- virtual ~**ActiveMQQueue** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **ActiveMQQueue** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const cms::Destination * **getCMSDestination** () const
- virtual cms::Destination::DestinationType **getDestinationType** () const
Retrieve the Destination Type for this Destination.
- virtual cms::Destination * **clone** () const
Creates a new instance of this destination type that is a copy of this one, and returns it.
- virtual void **copy** (const cms::Destination &source)
Copies the contents of the given Destinastion object to this one.
- virtual const cms::CMSProperties & **getCMSProperties** () const
Retrieve any properties that might be part of the destination that was specified.
- virtual std::string **getQueueName** () const throw (cms::CMSException)
Gets the name of this queue.

Static Public Attributes

- static const unsigned char **ID _ACTIVEMQQUEUE** = 100

6.61.1 Constructor & Destructor Documentation

6.61.1.1 `activemq::commands::ActiveMQQueue::ActiveMQQueue ()`

6.61.1.2 `activemq::commands::ActiveMQQueue::ActiveMQQueue (const std::string & name)`

6.61.1.3 `virtual activemq::commands::ActiveMQQueue::~~ActiveMQQueue ()`
[inline, virtual]

6.61.2 Member Function Documentation

6.61.2.1 `virtual cms::Destination* activemq::commands::ActiveMQQueue::clone ()`
`const` [inline, virtual]

Creates a new instance of this destination type that is a copy of this one, and returns it.

Returns:

cloned copy of this object

Implements **cms::Destination** (p.1724).

6.61.2.2 `virtual ActiveMQQueue* activemq::commands::ActiveMQQueue::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::ActiveMQDestination** (p.324).

6.61.2.3 `virtual void activemq::commands::ActiveMQQueue::copy (const cms::Destination & source)` [inline, virtual]

Copies the contents of the given Destination object to this one.

Parameters:

source The source Destination object.

6.61.2.4 `virtual void activemq::commands::ActiveMQQueue::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::ActiveMQDestination** (p.325).

6.61.2.5 virtual bool activemq::commands::ActiveMQQueue::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

6.61.2.6 virtual const cms::Destination* activemq::commands::ActiveMQQueue::getCMSDestination () const [inline, virtual]**Returns:**

the **cms::Destination** (p. 1723) interface pointer that the objects that derive from this class implement.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

6.61.2.7 virtual const cms::CMSProperties& activemq::commands::ActiveMQQueue::getCMSProperties () const [inline, virtual]

Retrieve any properties that might be part of the destination that was specified. This is a deviation from the JMS spec but necessary due to C++ restrictions.

Returns:

const reference to a properties object.

Implements **cms::Destination** (p. 1724).

6.61.2.8 virtual unsigned char activemq::commands::ActiveMQQueue::getDataStructureType () const [virtual]

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

6.61.2.9 virtual cms::Destination::DestinationType activemq::commands::ActiveMQQueue::getDestinationType () const [inline, virtual]

Retrieve the Destination Type for this Destination.

Returns:

The Destination Type

Implements **activemq::commands::ActiveMQDestination** (p. 327).

References **cms::Destination::QUEUE**.

6.61.2.10 **virtual std::string activemq::commands::ActiveMQQueue::getQueueName
() const throw (cms::CMSExcption) [inline, virtual]**

Gets the name of this queue.

Returns:

The queue name.

Implements **cms::Queue** (p. 3148).

6.61.2.11 **virtual std::string activemq::commands::ActiveMQQueue::toString ()
const [virtual]**

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 330).

6.61.3 Field Documentation

6.61.3.1 **const unsigned char activemq::commands::ActiveMQQueue::ID_-
ACTIVEMQQUEUE = 100 [static]**

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQQueue.h`

6.62 activemq::core::ActiveMQQueueBrowser Class Reference

#include <src/main/activemq/core/ActiveMQQueueBrowser.h> Inheritance diagram for activemq::core::ActiveMQQueueBrowser:

Public Member Functions

- **ActiveMQQueueBrowser** (**ActiveMQSession** *session, const **Pointer**<**commands::ConsumerId** > &consumerId, const **Pointer**<**commands::ActiveMQDestination** > &destination, const std::string &selector, bool dispatchAsync)
- virtual ~**ActiveMQQueueBrowser** ()
- virtual const **cms::Queue** * **getQueue** () const throw (cms::CMSException)
- virtual std::string **getMessageSelector** () const throw (cms::CMSException)
- virtual **cms::MessageEnumeration** * **getEnumeration** () throw (cms::CMSException)

Gets a pointer to an Enumeration object for browsing the Messages currently in the Queue in the order that a client would receive them.

- virtual void **close** () throw (cms::CMSException)

Closes this object and deallocates the appropriate resources.

- virtual bool **hasMoreMessages** ()

*Returns true if there are more Message in the Browser that can be retrieved via the **nextMessage** method.*

- virtual **cms::Message** * **nextMessage** () throw (cms::CMSException)

Returns the Next Message in the Queue if one is present, if no more Message's are available then an Exception is thrown.

Friends

- class **Browser**

6.62.1 Constructor & Destructor Documentation

- 6.62.1.1** `activemq::core::ActiveMQQueueBrowser::ActiveMQQueueBrowser (ActiveMQSession * session, const Pointer< commands::ConsumerId > & consumerId, const Pointer< commands::ActiveMQDestination > & destination, const std::string & selector, bool dispatchAsync)`
- 6.62.1.2** `virtual
activemq::core::ActiveMQQueueBrowser::~~ActiveMQQueueBrowser ()
[virtual]`

6.62.2 Member Function Documentation

- 6.62.2.1** `virtual void activemq::core::ActiveMQQueueBrowser::close () throw (cms::CMSException) [virtual]`

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

CMSException - If an error occurs while the resource is being closed.

Implements `cms::Closeable` (p.1148).

- 6.62.2.2** `virtual cms::MessageEnumeration* activemq::core::ActiveMQQueueBrowser::getEnumeration ()
throw (cms::CMSException) [virtual]`

Gets a pointer to an Enumeration object for browsing the Messages currently in the Queue in the order that a client would receive them. The pointer returned is owned by the browser and should not be deleted by the client application.

Returns:

a pointer to a Queue Enumeration, this Pointer is owned by the QueueBrowser and should not be deleted by the client.

Exceptions:

CMSException if an internal error occurs.

Implements `cms::QueueBrowser` (p.3153).

- 6.62.2.3** `virtual std::string activemq::core::ActiveMQQueueBrowser::getMessageSelector () const throw (cms::CMSException) [virtual]`

Returns:

the MessageSelector that is used on when this browser was created or empty string if no selector was present.

Exceptions:

CMSEException if an internal error occurs.

Implements **cms::QueueBrowser** (p. 3154).

```
6.62.2.4 virtual const cms::Queue* ac-
        tivemq::core::ActiveMQQueueBrowser::getQueue () const
        throw ( cms::CMSEException ) [virtual]
```

Returns:

the Queue that this browser is listening on.

Exceptions:

CMSEException if an internal error occurs.

Implements **cms::QueueBrowser** (p. 3154).

```
6.62.2.5 virtual bool activemq::core::ActiveMQQueueBrowser::hasMoreMessages ()
        [virtual]
```

Returns true if there are more Message in the Browser that can be retrieved via the **nextMessage** method. If this method returns false and the **nextMessage** method is called then an Exception will be thrown.

Returns:

true if more Message's are available in the Browser.

Implements **cms::MessageEnumeration** (p. 2659).

```
6.62.2.6 virtual cms::Message* ac-
        tivemq::core::ActiveMQQueueBrowser::nextMessage ()
        throw ( cms::CMSEException ) [virtual]
```

Returns the Next Message in the Queue if one is present, if no more Message's are available then an Exception is thrown. If a Message object pointer is returned then that object becomes the property of the caller and must be deleted by the caller when finished.

Returns:

The next Message in the Queue.

Exceptions:

CMSEException if no more Message's currently in the Queue.

Implements **cms::MessageEnumeration** (p. 2660).

6.62.3 Friends And Related Function Documentation

6.62.3.1 friend class Browser [friend]

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQQueueBrowser.h`

6.63 activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 491).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.63.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 491).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.63.2 Constructor & Destructor Documentation

6.63.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.63.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.63.3 Member Function Documentation

6.63.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.63.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.63.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 334).

6.63.3.4 virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 334).

6.63.3.5 virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 335).

```

6.63.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 335).

```

6.63.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 336).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ActiveMQQueueMarshaller.h**

6.64 activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 495).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.64.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 495).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.64.2 Constructor & Destructor Documentation

6.64.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.64.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.64.3 Member Function Documentation

6.64.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.64.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.64.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 338).

6.64.3.4 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 338).

6.64.3.5 virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 339).

```

6.64.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 339).

```

6.64.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 340).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ActiveMQQueueMarshaller.h**

6.65 activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 499).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.65.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 499).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.65.2 Constructor & Destructor Documentation

6.65.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.65.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.65.3 Member Function Documentation

6.65.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.65.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.65.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 342).

6.65.3.4 virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 342).

6.65.3.5 virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 343).

```

6.65.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 343).

```

6.65.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 344).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h

6.66 activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 503).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.66.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 503).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.66.2 Constructor & Destructor Documentation

6.66.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.66.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.66.3 Member Function Documentation

6.66.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.66.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.66.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 346).

6.66.3.4 virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 346).

6.66.3.5 virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 347).

```

6.66.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 347).

```

6.66.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 348).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ActiveMQQueueMarshaller.h**

6.67 activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p.507).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.67.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p.507).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.67.2 Constructor & Destructor Documentation

6.67.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.67.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.67.3 Member Function Documentation

6.67.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.67.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.67.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 350).

6.67.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::looseUnmarshal
(**OpenWireFormat * wireFormat**, **commands::DataStructure * dataStructure**, **decaf::io::DataInputStream * dataIn**) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 350).

6.67.3.5 virtual int ac-
tivemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::tightMarshal1
(**OpenWireFormat * wireFormat**, **commands::DataStructure * dataStructure**, **utils::BooleanStream * bs**) throw (**decaf::io::IOException**)
[virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 351).

```

6.67.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 351).

```

6.67.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 352).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ActiveMQQueueMarshaller.h**

6.68 activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 511).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQQueueMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller:

Public Member Functions

- **ActiveMQQueueMarshaller** ()
- virtual **~ActiveMQQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.68.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 511).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.68.2 Constructor & Destructor Documentation

6.68.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::ActiveMQQueueMarshaller()` [inline]

6.68.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::~~ActiveMQQueueMarshaller()` [inline, virtual]

6.68.3 Member Function Documentation

6.68.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.68.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.68.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 354).

6.68.3.4 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 354).

6.68.3.5 virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 355).

```

6.68.3.6 virtual void ac-
    tivemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::tightMarshal2
    (OpenWireFormat * wireFormat, commands::DataStructure
    * dataStructure, decaf::io::DataOutputStream * dataOut,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 355).

```

6.68.3.7 virtual void ac-
    tivemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller::tightUnmarshal
    (OpenWireFormat * wireFormat, commands::DataStructure *
    dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
    * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 356).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQQueueMarshaller.h

6.69 activemq::core::ActiveMQSession Class Reference

#include <src/main/activemq/core/ActiveMQSession.h> Inheritance diagram for activemq::core::ActiveMQSession:

Public Member Functions

- **ActiveMQSession** (const **Pointer**< **commands::SessionInfo** > &sessionInfo, **cms::Session::AcknowledgeMode** ackMode, const **decaf::util::Properties** &properties, **ActiveMQConnection** *connection)
- virtual **~ActiveMQSession** ()
- void **redispatch** (**MessageDispatchChannel** &unconsumedMessages)
Redispatches the given set of unconsumed messages to the consumers.
- void **start** ()
Stops asynchronous message delivery.
- void **stop** ()
Starts asynchronous message delivery.
- bool **isStarted** () const
*Indicates whether or not the session is currently in the started **state** (p. 95).*
- bool **isAutoAcknowledge** () const
- bool **isDupsOkAcknowledge** () const
- bool **isClientAcknowledge** () const
- bool **isIndividualAcknowledge** () const
- void **fire** (const **exceptions::ActiveMQException** &ex)
Fires the given exception to the exception listener of the connection.
- virtual void **dispatch** (const **Pointer**< **MessageDispatch** > &message)
Dispatches a message to a particular consumer.
- virtual void **close** () throw (**cms::CMSEException**)
Closes this session as well as any active child consumers or producers.
- virtual void **commit** () throw (**cms::CMSEException**)
Commits all messages done in this transaction and releases any locks currently held.
- virtual void **rollback** () throw (**cms::CMSEException**)
Rollsback all messages done in this transaction and releases any locks currently held.
- virtual void **recover** () throw (**cms::CMSEException**)
Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message.
- virtual **cms::MessageConsumer** * **createConsumer** (const **cms::Destination** *destination) throw (**cms::CMSEException**)

Creates a MessageConsumer for the specified destination.

- virtual **cms::MessageConsumer** * **createConsumer** (const **cms::Destination** *destination, const std::string &selector) throw (cms::CMSEException)

Creates a MessageConsumer for the specified destination, using a message selector.

- virtual **cms::MessageConsumer** * **createConsumer** (const **cms::Destination** *destination, const std::string &selector, bool noLocal) throw (cms::CMSEException)

Creates a MessageConsumer for the specified destination, using a message selector.

- virtual **cms::MessageConsumer** * **createDurableConsumer** (const **cms::Topic** *destination, const std::string &name, const std::string &selector, bool noLocal=false) throw (cms::CMSEException)

Creates a durable subscriber to the specified topic, using a message selector.

- virtual **cms::MessageProducer** * **createProducer** (const **cms::Destination** *destination) throw (cms::CMSEException)

Creates a MessageProducer to send messages to the specified destination.

- virtual **cms::QueueBrowser** * **createBrowser** (const **cms::Queue** *queue) throw (cms::CMSEException)

Creates a new QueueBrowser to peek at Messages on the given Queue.

- virtual **cms::QueueBrowser** * **createBrowser** (const **cms::Queue** *queue, const std::string &selector) throw (cms::CMSEException)

Creates a new QueueBrowser to peek at Messages on the given Queue.

- virtual **cms::Queue** * **createQueue** (const std::string &queueName) throw (cms::CMSEException)

Creates a queue identity given a Queue name.

- virtual **cms::Topic** * **createTopic** (const std::string &topicName) throw (cms::CMSEException)

Creates a topic identity given a Queue name.

- virtual **cms::TemporaryQueue** * **createTemporaryQueue** () throw (cms::CMSEException)

Creates a TemporaryQueue object.

- virtual **cms::TemporaryTopic** * **createTemporaryTopic** () throw (cms::CMSEException)

Creates a TemporaryTopic object.

- virtual **cms::Message** * **createMessage** () throw (cms::CMSEException)

Creates a new Message.

- virtual **cms::BytesMessage** * **createBytesMessage** () throw (cms::CMSEException)

Creates a BytesMessage.

- virtual **cms::BytesMessage** * **createBytesMessage** (const unsigned char *bytes, int bytesize) throw (cms::CMSEException)
Creates a BytesMessage and sets the pay-load to the passed value.
- virtual **cms::StreamMessage** * **createStreamMessage** () throw (cms::CMSEException)
Creates a new StreamMessage.
- virtual **cms::TextMessage** * **createTextMessage** () throw (cms::CMSEException)
Creates a new TextMessage.
- virtual **cms::TextMessage** * **createTextMessage** (const std::string &text) throw (cms::CMSEException)
Creates a new TextMessage and set the text to the value given.
- virtual **cms::MapMessage** * **createMapMessage** () throw (cms::CMSEException)
Creates a new MapMessage.
- virtual **cms::Session::AcknowledgeMode** **getAcknowledgeMode** () const throw (cms::CMSEException)
Returns the acknowledgment mode of the session.
- virtual bool **isTransacted** () const throw (cms::CMSEException)
Gets if the Sessions is a Transacted Session.
- virtual void **unsubscribe** (const std::string &name) throw (cms::CMSEException)
Unsubscribes a durable subscription that has been created by a client.
- void **send** (cms::Message *message, ActiveMQProducer *producer, util::Usage *usage) throw (cms::CMSEException)
Sends a message from the Producer specified using this session's connection the message will be sent using the best available means depending on the configuration of the connection.
- **cms::ExceptionListener** * **getExceptionListener** ()
This method gets any registered exception listener of this sessions connection and returns it.
- const **commands::SessionInfo** & **getSessionInfo** () const
Gets the Session Information object for this session, if the session is closed than this method throws an exception.
- const **commands::SessionId** & **getSessionId** () const
Gets the Session Id object for this session, if the session is closed than this method throws an exception.
- **ActiveMQConnection** * **getConnection** () const
*Gets the **ActiveMQConnection** (p. 273) that is associated with this session.*
- long long **getLastDeliveredSequenceId** () const
Gets the currently set Last Delivered Sequence Id.
- void **setLastDeliveredSequenceId** (long long value)

Sets the value of the Last Delivered Sequence Id.

- void **oneway** (**Pointer**< **commands::Command** > command) throw (**activemq::exceptions::ActiveMQException**)

Sends a oneway message.

- void **syncRequest** (**Pointer**< **commands::Command** > command, unsigned int timeout=0) throw (**activemq::exceptions::ActiveMQException**)

Sends a synchronous request and returns the response from the broker.

- void **addConsumer** (**ActiveMQConsumer** *consumer) throw (**activemq::exceptions::ActiveMQException**)

Adds a MessageConsumer to this session registering it with the Connection and store a reference to it so the session can ensure that all resources are closed when the session is closed.

- void **removeConsumer** (const **Pointer**< **commands::ConsumerId** > &consumerId, long long lastDeliveredSequenceId=0) throw (**activemq::exceptions::ActiveMQException**)

Dispose of a MessageConsumer from this session.

- void **addProducer** (**ActiveMQProducer** *consumer) throw (**activemq::exceptions::ActiveMQException**)

Adds a MessageProducer to this session registering it with the Connection and store a reference to it so the session can ensure that all resources are closed when the session is closed.

- void **removeProducer** (const **Pointer**< **commands::ProducerId** > &producerId) throw (**activemq::exceptions::ActiveMQException**)

Dispose of a MessageProducer from this session.

- void **doStartTransaction** () throw (**exceptions::ActiveMQException**)

Starts if not already start a Transaction for this Session.

- **Pointer**< **ActiveMQTransactionContext** > **getTransactionContext** ()

Gets the Pointer to this Session's TransactionContext.

- void **acknowledge** ()

Request that the Session inform all its consumers to Acknowledge all Message's that have been received so far.

- void **deliverAcks** ()

Request that this Session inform all of its consumers to deliver their pending acks.

- void **clearMessagesInProgress** ()

Request that this Session inform all of its consumers to clear all messages that are currently in progress.

- void **wakeup** ()

Causes the Session to wakeup its executer and ensure all messages are dispatched.

- **Pointer**< **commands::ConsumerId** > **getNextConsumerId** ()

Get the Next available Consumer Id.

- `Pointer< commands::ProducerId > getNextProducerId ()`
Get the Next available Producer Id.

Friends

- class `ActiveMQSessionExecutor`

6.69.1 Constructor & Destructor Documentation

6.69.1.1 `activemq::core::ActiveMQSession::ActiveMQSession (const Pointer< commands::SessionInfo > & sessionInfo, cms::Session::AcknowledgeMode ackMode, const decaf::util::Properties & properties, ActiveMQConnection * connection)`

6.69.1.2 `virtual activemq::core::ActiveMQSession::~~ActiveMQSession ()` [virtual]

6.69.2 Member Function Documentation

6.69.2.1 `void activemq::core::ActiveMQSession::acknowledge ()`

Request that the Session inform all its consumers to Acknowledge all Message's that have been received so far.

6.69.2.2 `void activemq::core::ActiveMQSession::addConsumer (ActiveMQConsumer * consumer) throw (activemq::exceptions::ActiveMQException)`

Adds a MessageConsumer to this session registering it with the Connection and store a reference to it so the session can ensure that all resources are closed when the session is closed.

Parameters:

consumer The `ActiveMQConsumer` (p. 310) instance to add to this session.

Exceptions:

ActiveMQException if an internal error occurs.

6.69.2.3 `void activemq::core::ActiveMQSession::addProducer (ActiveMQProducer * consumer) throw (activemq::exceptions::ActiveMQException)`

Adds a MessageProducer to this session registering it with the Connection and store a reference to it so the session can ensure that all resources are closed when the session is closed.

Parameters:

consumer The `ActiveMQProducer` (p. 470) instance to add to this session.

Exceptions:

ActiveMQException if an internal error occurs.

6.69.2.4 void activemq::core::ActiveMQSession::clearMessagesInProgress ()

Request that this Session inform all of its consumers to clear all messages that are currently in progress.

6.69.2.5 virtual void activemq::core::ActiveMQSession::close () throw (cms::CMSException) [virtual]

Closes this session as well as any active child consumers or producers.

Exceptions:

CMSException

Implements **cms::Session** (p. 3368).

6.69.2.6 virtual void activemq::core::ActiveMQSession::commit () throw (cms::CMSException) [virtual]

Commits all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSException

Implements **cms::Session** (p. 3369).

6.69.2.7 virtual cms::QueueBrowser* activemq::core::ActiveMQSession::createBrowser (const cms::Queue * *queue*, const std::string & *selector*) throw (cms::CMSException) [virtual]

Creates a new QueueBrowser to peek at Messages on the given Queue.

Parameters:

queue the Queue to browse

selector the Message selector to filter which messages are browsed.

Returns:

New QueueBrowser that is owned by the caller.

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if the destination given is invalid.

Implements **cms::Session** (p. 3369).

6.69.2.8 `virtual cms::QueueBrowser* activemq::core::ActiveMQSession::createBrowser (const cms::Queue * queue) throw (cms::CMSException)` [virtual]

Creates a new QueueBrowser to peek at Messages on the given Queue.

Parameters:

queue the Queue to browse

Returns:

New QueueBrowser that is owned by the caller.

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if the destination given is invalid.

Implements **cms::Session** (p. 3369).

6.69.2.9 `virtual cms::BytesMessage* activemq::core::ActiveMQSession::createBytesMessage (const unsigned char * bytes, int bytesSize) throw (cms::CMSException)` [virtual]

Creates a BytesMessage and sets the pay-load to the passed value.

Parameters:

bytes - an array of bytes to set in the message

bytesSize - the size of the bytes array, or number of bytes to use

Returns:

a newly created BytesMessage.

Exceptions:

CMSException

Implements **cms::Session** (p. 3370).

6.69.2.10 `virtual cms::BytesMessage* activemq::core::ActiveMQSession::createBytesMessage () throw (cms::CMSException)` [virtual]

Creates a BytesMessage.

Returns:

a newly created BytesMessage.

Exceptions:

CMSException

Implements **cms::Session** (p. 3370).

6.69.2.11 `virtual cms::MessageConsumer* activemq::core::ActiveMQSession::createConsumer (const cms::Destination * destination, const std::string & selector, bool noLocal) throw (cms::CMSException) [virtual]`

Creates a MessageConsumer for the specified destination, using a message selector.

Parameters:

destination - The Destination that this consumer receiving messages for.

selector - The Message Selector string to use for this destination

noLocal - if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Exceptions:

CMSException

Implements `cms::Session` (p. 3370).

6.69.2.12 `virtual cms::MessageConsumer* activemq::core::ActiveMQSession::createConsumer (const cms::Destination * destination, const std::string & selector) throw (cms::CMSException) [virtual]`

Creates a MessageConsumer for the specified destination, using a message selector.

Parameters:

destination - The Destination that this consumer receiving messages for.

selector - The Message Selector string to use for this destination

Exceptions:

CMSException

Implements `cms::Session` (p. 3371).

6.69.2.13 `virtual cms::MessageConsumer* activemq::core::ActiveMQSession::createConsumer (const cms::Destination * destination) throw (cms::CMSException) [virtual]`

Creates a MessageConsumer for the specified destination.

Parameters:

destination - The Destination that this consumer receiving messages for.

Exceptions:

CMSException

Implements `cms::Session` (p. 3371).

6.69.2.14 `virtual cms::MessageConsumer* activemq::core::ActiveMQSession::createDurableConsumer (const cms::Topic * destination, const std::string & name, const std::string & selector, bool noLocal = false) throw (cms::CMSException) [virtual]`

Creates a durable subscriber to the specified topic, using a message selector.

Parameters:

destination - the topic to subscribe to

name - The name used to identify the subscription

selector - only messages matching the selector are received

noLocal - if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Exceptions:

CMSException

Implements **cms::Session** (p. 3372).

6.69.2.15 `virtual cms::MapMessage* activemq::core::ActiveMQSession::createMapMessage () throw (cms::CMSException) [virtual]`

Creates a new MapMessage.

Returns:

a newly created MapMessage.

Exceptions:

CMSException

Implements **cms::Session** (p. 3372).

6.69.2.16 `virtual cms::Message* activemq::core::ActiveMQSession::createMessage () throw (cms::CMSException) [virtual]`

Creates a new Message.

Exceptions:

CMSException

Implements **cms::Session** (p. 3372).

6.69.2.17 `virtual cms::MessageProducer* activemq::core::ActiveMQSession::createProducer (const cms::Destination * destination) throw (cms::CMSException) [virtual]`

Creates a MessageProducer to send messages to the specified destination.

Parameters:

destination - the Destination to publish on

Exceptions:

CMSException

Implements `cms::Session` (p. 3373).

6.69.2.18 `virtual cms::Queue* activemq::core::ActiveMQSession::createQueue (const std::string & queueName) throw (cms::CMSException) [virtual]`

Creates a queue identity given a Queue name.

Parameters:

queueName - the name of the new Queue

Exceptions:

CMSException

Implements `cms::Session` (p. 3373).

6.69.2.19 `virtual cms::StreamMessage* activemq::core::ActiveMQSession::createStreamMessage () throw (cms::CMSException) [virtual]`

Creates a new StreamMessage.

Returns:

a newly created StreamMessage.

Exceptions:

CMSException

Implements `cms::Session` (p. 3373).

6.69.2.20 `virtual cms::TemporaryQueue* activemq::core::ActiveMQSession::createTemporaryQueue () throw (cms::CMSException) [virtual]`

Creates a TemporaryQueue object.

Exceptions:

CMSException

Implements **cms::Session** (p. 3374).

6.69.2.21 `virtual cms::TemporaryTopic* activemq::core::ActiveMQSession::createTemporaryTopic () throw (cms::CMSException) [virtual]`

Creates a TemporaryTopic object.

Exceptions:

CMSException

Implements **cms::Session** (p. 3374).

6.69.2.22 `virtual cms::TextMessage* activemq::core::ActiveMQSession::createTextMessage (const std::string & text) throw (cms::CMSException) [virtual]`

Creates a new TextMessage and set the text to the value given.

Parameters:

text - The initial text for the message

Returns:

a newly created TextMessage with the given Text set in the Message body.

Exceptions:

CMSException

Implements **cms::Session** (p. 3374).

6.69.2.23 `virtual cms::TextMessage* activemq::core::ActiveMQSession::createTextMessage () throw (cms::CMSException) [virtual]`

Creates a new TextMessage.

Returns:

a newly created TextMessage.

Exceptions:

CMSException

Implements **cms::Session** (p. 3374).

6.69.2.24 `virtual cms::Topic* activemq::core::ActiveMQSession::createTopic (const std::string & topicName) throw (cms::CMSException) [virtual]`

Creates a topic identity given a Queue name.

Parameters:

topicName - the name of the new Topic

Exceptions:

CMSException

Implements `cms::Session` (p. 3375).

6.69.2.25 `void activemq::core::ActiveMQSession::deliverAcks ()`

Request that this Session inform all of its consumers to deliver their pending acks.

6.69.2.26 `virtual void activemq::core::ActiveMQSession::dispatch (const Pointer< MessageDispatch > & message) [virtual]`

Dispatches a message to a particular consumer.

Parameters:

message - the message to be dispatched

Implements `activemq::core::Dispatcher` (p. 1787).

6.69.2.27 `void activemq::core::ActiveMQSession::doStartTransaction () throw (exceptions::ActiveMQException)`

Starts if not already start a Transaction for this Session. If the session is not a Transacted Session then an exception is thrown. If a transaction is already in progress then this method has no effect.

Exceptions:

ActiveMQException if this is not a Transacted Session.

6.69.2.28 `void activemq::core::ActiveMQSession::fire (const exceptions::ActiveMQException & ex)`

Fires the given exception to the exception listener of the connection.

6.69.2.29 `virtual cms::Session::AcknowledgeMode activemq::core::ActiveMQSession::getAcknowledgeMode () const throw (cms::CMSException) [virtual]`

Returns the acknowledgment mode of the session.

Returns:

the Sessions Acknowledge Mode

Implements **cms::Session** (p. 3375).

**6.69.2.30 ActiveMQConnection* activemq::core::ActiveMQSession::getConnection
() const [inline]**

Gets the **ActiveMQConnection** (p. 273) that is associated with this session.

**6.69.2.31 cms::ExceptionListener* activemq::core::ActiveMQSession::getExceptionListener
()**

This method gets any registered exception listener of this sessions connection and returns it. Mainly intended for use by the objects that this session creates so that they can notify the client of **exceptions** (p. 92) that occur in the context of another thread.

Returns:

cms::ExceptionListener (p. 1838) pointer or NULL

**6.69.2.32 long long activemq::core::ActiveMQSession::getLastDeliveredSequenceId
() const [inline]**

Gets the currently set Last Delivered Sequence Id.

Returns:

long long containing the sequence id of the last delivered Message.

**6.69.2.33 Pointer<commands::ConsumerId> activemq::core::ActiveMQSession::getNextConsumerId
()**

Get the Next available Consumer Id.

Returns:

the next id in the sequence.

**6.69.2.34 Pointer<commands::ProducerId> activemq::core::ActiveMQSession::getNextProducerId
()**

Get the Next available Producer Id.

Returns:

the next id in the sequence.

6.69.2.35 `const commands::SessionId& activemq::core::ActiveMQSession::getSessionId () const`
[inline]

Gets the Session Id object for this session, if the session is closed than this method throws an exception.

Returns:

SessionId Reference

6.69.2.36 `const commands::SessionInfo& activemq::core::ActiveMQSession::getSessionInfo () const`
[inline]

Gets the Session Information object for this session, if the session is closed than this method throws an exception.

Returns:

SessionInfo Reference

6.69.2.37 `Pointer<ActiveMQTransactionContext> activemq::core::ActiveMQSession::getTransactionContext ()`
[inline]

Gets the Pointer to this Session's TransactionContext.

Returns:

a Pointer to this Session's TransactionContext

6.69.2.38 `bool activemq::core::ActiveMQSession::isAutoAcknowledge () const`
[inline]

References cms::Session::AUTO_ACKNOWLEDGE.

6.69.2.39 `bool activemq::core::ActiveMQSession::isClientAcknowledge () const`
[inline]

References cms::Session::CLIENT_ACKNOWLEDGE.

6.69.2.40 `bool activemq::core::ActiveMQSession::isDupsOkAcknowledge () const`
[inline]

References cms::Session::DUPS_OK_ACKNOWLEDGE.

6.69.2.41 `bool activemq::core::ActiveMQSession::isIndividualAcknowledge () const`
[inline]

References cms::Session::INDIVIDUAL_ACKNOWLEDGE.

6.69.2.42 `bool activemq::core::ActiveMQSession::isStarted () const`

Indicates whether or not the session is currently in the started **state** (p. 95).

6.69.2.43 `virtual bool activemq::core::ActiveMQSession::isTransacted () const
throw (cms::CMSException) [virtual]`

Gets if the Sessions is a Transacted Session.

Returns:

transacted true - false.

Implements **cms::Session** (p. 3375).

6.69.2.44 `void activemq::core::ActiveMQSession::oneway
(Pointer< commands::Command > command) throw (
activemq::exceptions::ActiveMQException)`

Sends a oneway message.

Parameters:

command The message to send.

Exceptions:

ActiveMQException if not currently connected, or if the operation fails for any reason.

6.69.2.45 `virtual void activemq::core::ActiveMQSession::recover () throw (
cms::CMSException) [virtual]`

Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message. All consumers deliver messages in a serial order. Acknowledging a received message automatically acknowledges all messages that have been delivered to the client.

Restarting a session causes it to take the following actions:

- Stop message delivery
- Mark all messages that might have been delivered but not acknowledged as "redelivered"
- Restart the delivery sequence including all unacknowledged messages that had been previously delivered. Redelivered messages do not have to be delivered in exactly their original delivery order.

Exceptions:

CMSException - if the CMS provider fails to stop and restart message delivery due to some internal error.

IllegalStateException - if the method is called by a transacted session.

Implements **cms::Session** (p. 3376).

6.69.2.46 void activemq::core::ActiveMQSession::redispatch
(MessageDispatchChannel & *unconsumedMessages*)

Redispatches the given set of unconsumed messages to the consumers.

Parameters:

unconsumedMessages - unconsumed messages to be redelivered.

6.69.2.47 void activemq::core::ActiveMQSession::removeConsumer
(const Pointer< commands::ConsumerId > & *consumerId*,
long long *lastDeliveredSequenceId* = 0) throw (
activemq::exceptions::ActiveMQException)

Dispose of a MessageConsumer from this session. Removes it from the Connection and clean up any resources associated with it.

Parameters:

consumerId The ConsumerId of the MessageConsumer to remove from this Session.

lastDeliveredSequenceId The sequenceId of the last Message the consumer delivered.

Exceptions:

ActiveMQException if an internal error occurs.

6.69.2.48 void activemq::core::ActiveMQSession::removeProducer (const
Pointer< commands::ProducerId > & *producerId*) throw (
activemq::exceptions::ActiveMQException)

Dispose of a MessageProducer from this session. Removes it from the Connection and clean up any resources associated with it.

Parameters:

producerId The ProducerId of the MessageProducer to remove from this session.

Exceptions:

ActiveMQException if an internal error occurs.

6.69.2.49 virtual void activemq::core::ActiveMQSession::rollback () throw (
cms::CMSException) [virtual]

Rollsback all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSException

Implements **cms::Session** (p. 3376).

6.69.2.50 void activemq::core::ActiveMQSession::send (cms::Message * *message*, ActiveMQProducer * *producer*, util::Usage * *usage*) throw (cms::CMSEException)

Sends a message from the Producer specified using this session's connection the message will be sent using the best available means depending on the configuration of the connection. Asynchronous sends will be chosen if at all possible.

Parameters:

message The message to send to the broker.

producer The sending Producer

usage Pointer to a Usage tracker which if set will be increased by the size of the given message.

Exceptions:

CMSEException

6.69.2.51 void activemq::core::ActiveMQSession::setLastDeliveredSequenceId (long long *value*) [inline]

Sets the value of the Last Delivered Sequence Id.

Parameters:

value The new value to assign to the Last Delivered Sequence Id property.

6.69.2.52 void activemq::core::ActiveMQSession::start ()

Stops asynchronous message delivery.

6.69.2.53 void activemq::core::ActiveMQSession::stop ()

Starts asynchronous message delivery.

6.69.2.54 void activemq::core::ActiveMQSession::syncRequest (Pointer< commands::Command > *command*, unsigned int *timeout* = 0) throw (activemq::exceptions::ActiveMQException)

Sends a synchronous request and returns the response from the broker. Converts any error responses into an exception.

Parameters:

command The request command.

timeout The time to wait for a response, default is zero or infinite.

Exceptions:

ActiveMQException thrown if an error response was received from the broker, or if any other error occurred.

6.69.2.55 `virtual void activemq::core::ActiveMQSession::unsubscribe (const std::string & name) throw (cms::CMSException)` [virtual]

Unsubscribes a durable subscription that has been created by a client. This method deletes the **state** (p. 95) being maintained on behalf of the subscriber by its provider. It is erroneous for a client to delete a durable subscription while there is an active MessageConsumer or Subscriber for the subscription, or while a consumed message is part of a pending transaction or has not been acknowledged in the session.

Parameters:

name the name used to identify this subscription

Exceptions:

CMSException

Implements **cms::Session** (p. 3376).

6.69.2.56 `void activemq::core::ActiveMQSession::wakeup ()`

Causes the Session to wakeup its executor and ensure all messages are dispatched.

6.69.3 Friends And Related Function Documentation

6.69.3.1 `friend class ActiveMQSessionExecutor` [friend]

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQSession.h`

6.70 activemq::core::ActiveMQSessionExecutor Class Reference

Delegate dispatcher for a single session.

#include <src/main/activemq/core/ActiveMQSessionExecutor.h> Inheritance diagram for activemq::core::ActiveMQSessionExecutor:

Public Member Functions

- **ActiveMQSessionExecutor** (**ActiveMQSession** *session)
Creates an un-started executor for the given session.
- virtual **~ActiveMQSessionExecutor** ()
*Calls **stop()** (p. 536) then **clear()** (p. 534).*
- virtual void **execute** (const **Pointer**< **MessageDispatch** > &data)
Executes the dispatch.
- virtual void **executeFirst** (const **Pointer**< **MessageDispatch** > &data)
Executes the dispatch.
- virtual void **clearMessagesInProgress** ()
Removes all messages in the Dispatch Channel so that non are delivered.
- virtual bool **hasUnconsumedMessages** () const
- virtual void **wakeup** ()
wakeup this executor and dispatch any pending messages.
- virtual void **start** ()
Starts the dispatching.
- virtual void **stop** ()
Stops dispatching.
- virtual void **close** ()
Terminates the dispatching thread.
- virtual bool **isRunning** () const
- virtual bool **isEmpty** ()
- virtual void **clear** ()
Removes all queued messages and destroys them.
- virtual bool **iterate** ()
*Iterates on the **MessageDispatchChannel** (p. 2599) sending all pending messages to the Consumers they are destined for.*
- std::vector< **Pointer**< **MessageDispatch** > > **getUnconsumedMessages** ()

6.70.1 Detailed Description

Delegate dispatcher for a single session. Contains a thread to provide for asynchronous dispatching.

6.70.2 Constructor & Destructor Documentation

6.70.2.1 `activemq::core::ActiveMQSessionExecutor::ActiveMQSessionExecutor (ActiveMQSession * session)`

Creates an un-started executor for the given session.

6.70.2.2 `virtual activemq::core::ActiveMQSessionExecutor::~~ActiveMQSessionExecutor () [virtual]`

Calls `stop()` (p. 536) then `clear()` (p. 534).

6.70.3 Member Function Documentation

6.70.3.1 `virtual void activemq::core::ActiveMQSessionExecutor::clear () [inline, virtual]`

Removes all queued messages and destroys them.

6.70.3.2 `virtual void activemq::core::ActiveMQSessionExecutor::clearMessagesInProgress () [inline, virtual]`

Removes all messages in the Dispatch Channel so that non are delivered.

6.70.3.3 `virtual void activemq::core::ActiveMQSessionExecutor::close () [inline, virtual]`

Terminates the dispatching thread. Once this is called, the executor is no longer usable.

6.70.3.4 `virtual void activemq::core::ActiveMQSessionExecutor::execute (const Pointer< MessageDispatch > & data) [virtual]`

Executes the dispatch. Adds the given data to the end of the queue.

Parameters:

data - the data to be dispatched.

6.70.3.5 `virtual void activemq::core::ActiveMQSessionExecutor::executeFirst (const Pointer< MessageDispatch > & data) [virtual]`

Executes the dispatch. Adds the given data to the beginning of the queue.

Parameters:

data - the data to be dispatched.

6.70.3.6 `std::vector< Pointer<MessageDispatch> > activemq::core::ActiveMQSessionExecutor::getUnconsumedMessages ()`
[inline]

Returns:

a vector containing all the unconsumed messages, this clears the Message Dispatch Channel when called.

6.70.3.7 `virtual bool activemq::core::ActiveMQSessionExecutor::hasUnconsumedMessages ()`
`const` [inline, virtual]

Returns:

true if there are any pending messages in the dispatch channel.

6.70.3.8 `virtual bool activemq::core::ActiveMQSessionExecutor::isEmpty ()`
[inline, virtual]

Returns:

true if there are no messages in the Dispatch Channel.

6.70.3.9 `virtual bool activemq::core::ActiveMQSessionExecutor::isRunning ()` `const`
[inline, virtual]

Returns:

true indicates if the executor is started

6.70.3.10 `virtual bool activemq::core::ActiveMQSessionExecutor::iterate ()`
[virtual]

Iterates on the **MessageDispatchChannel** (p. 2599) sending all pending messages to the Consumers they are destined for.

Returns:

false if there are no more messages to dispatch.

Implements **activemq::threads::Task** (p. 3734).

6.70.3.11 `virtual void activemq::core::ActiveMQSessionExecutor::start ()`
[virtual]

Starts the dispatching.

6.70.3.12 `virtual void activemq::core::ActiveMQSessionExecutor::stop ()` [virtual]

Stops dispatching.

6.70.3.13 `virtual void activemq::core::ActiveMQSessionExecutor::wakeup ()`
[virtual]

wakeup this executer and dispatch any pending messages.

The documentation for this class was generated from the following file:

- `src/main/activemq/core/ActiveMQSessionExecutor.h`

6.71 activemq::commands::ActiveMQStreamMessage Class Reference

#include <src/main/activemq/commands/ActiveMQStreamMessage.h> Inheritance diagram for activemq::commands::ActiveMQStreamMessage:

Public Member Functions

- **ActiveMQStreamMessage** ()
- virtual **~ActiveMQStreamMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ActiveMQStreamMessage * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **onSend** ()
Store the Data that was written to the stream before a send.
- virtual **cms::StreamMessage * clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- virtual void **clearBody** () throw (cms::CMSException)
Clears out the body of the message.
- virtual void **reset** () throw (cms::CMSException)
Puts the message body in read-only mode and repositions the stream of bytes to the beginning.
- virtual bool **readBoolean** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads a Boolean from the Stream message stream.
- virtual void **writeBoolean** (bool value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a boolean to the Stream message stream as a 1-byte value.

- virtual unsigned char **readByte** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Byte from the Stream message stream.
- virtual void **writeByte** (unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte to the Stream message stream as a 1-byte value.
- virtual int **readBytes** (std::vector< unsigned char > &value) const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a byte array from the Stream message stream.
- virtual void **writeBytes** (const std::vector< unsigned char > &value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte array to the Stream message stream using the vector size as the number of bytes to write.
- virtual int **readBytes** (unsigned char *buffer, int length) const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a portion of the Stream message stream.
- virtual void **writeBytes** (const unsigned char *value, int offset, int length) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a portion of a byte array to the Stream message stream.
- virtual char **readChar** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Char from the Stream message stream.
- virtual void **writeChar** (char value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a char to the Stream message stream as a 1-byte value.
- virtual float **readFloat** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 32 bit float from the Stream message stream.
- virtual void **writeFloat** (float value) throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a float to the Stream message stream as a 4 byte value.
- virtual double **readDouble** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 64 bit double from the Stream message stream.

- virtual void **writeDouble** (double value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a double to the Stream message stream as a 8 byte value.
- virtual short **readShort** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads a 16 bit signed short from the Stream message stream.
- virtual void **writeShort** (short value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a signed short to the Stream message stream as a 2 byte value.
- virtual unsigned short **readUnsignedShort** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads a 16 bit unsigned short from the Stream message stream.
- virtual void **writeUnsignedShort** (unsigned short value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a unsigned short to the Stream message stream as a 2 byte value.
- virtual int **readInt** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads a 32 bit signed integer from the Stream message stream.
- virtual void **writeInt** (int value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a signed int to the Stream message stream as a 4 byte value.
- virtual long long **readLong** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads a 64 bit long from the Stream message stream.
- virtual void **writeLong** (long long value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes a long long to the Stream message stream as a 8 byte value.
- virtual std::string **readString** () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)
Reads an ASCII String from the Stream message stream.
- virtual void **writeString** (const std::string &value) throw (cms::MessageNotWriteableException, cms::CMSException)
Writes an ASCII String to the Stream message stream.

Static Public Attributes

- static const unsigned char `ID_ACTIVEMQSTREAMMESSAGE` = 27

6.71.1 Constructor & Destructor Documentation

6.71.1.1 `activemq::commands::ActiveMQStreamMessage::ActiveMQStreamMessage()`

6.71.1.2 `virtual activemq::commands::ActiveMQStreamMessage::~~ActiveMQStreamMessage()` [virtual]

6.71.2 Member Function Documentation

6.71.2.1 `virtual void activemq::commands::ActiveMQStreamMessage::clearBody () throw (cms::CMSException)` [virtual]

Clears out the body of the message. This does not clear the headers or properties.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 428).

6.71.2.2 `virtual cms::StreamMessage* activemq::commands::ActiveMQStreamMessage::clone () const` [inline, virtual]

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements `cms::Message` (p. 2539).

6.71.2.3 `virtual ActiveMQStreamMessage* activemq::commands::ActiveMQStreamMessage::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Message` (p. 2520).

6.71.2.4 `virtual void activemq::commands::ActiveMQStreamMessage::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::Message** (p. 2521).

6.71.2.5 virtual bool activemq::commands::ActiveMQStreamMessage::equals (const DataStructure * value) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >** (p. 429).

6.71.2.6 virtual unsigned char activemq::commands::ActiveMQStreamMessage::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Message** (p. 2523).

6.71.2.7 virtual void activemq::commands::ActiveMQStreamMessage::onSend () [virtual]

Store the Data that was written to the stream before a send.

Reimplemented from **activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >** (p. 436).

6.71.2.8 virtual bool activemq::commands::ActiveMQStreamMessage::readBoolean () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException) [virtual]

Reads a Boolean from the Stream message stream.

Returns:

boolean value from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3655).

6.71.2.9 `virtual unsigned char activemq::commands::ActiveMQStreamMessage::readByte ()
const throw (cms::MessageEOFException, cms::MessageFormatException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]`

Reads a Byte from the Stream message stream.

Returns:

unsigned char value from stream

Exceptions:

CMSEException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3655).

6.71.2.10 `virtual int activemq::commands::ActiveMQStreamMessage::readBytes
(unsigned char * buffer, int length) const throw (
cms::MessageEOFException, cms::MessageFormatException,
cms::MessageNotReadableException, cms::CMSEException) [virtual]`

Reads a portion of the Stream message stream. If the length of array value is less than the number of bytes remaining to be read from the stream, the array should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of array value, the bytes should be read into the array. The return value of the total number of bytes read will be less than the length of the array, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

If length is negative, or length is greater than the length of the array value, then an CMSEException is thrown. No bytes will be read from the stream for this exception case.

Parameters:

buffer the buffer into which the data is read

length the number of bytes to read; must be less than or equal to value.length

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::StreamMessage** (p. 3656).

6.71.2.11 `virtual int activemq::commands::ActiveMQStreamMessage::readBytes
(std::vector< unsigned char > & value) const throw (
cms::MessageEOFException, cms::MessageFormatException,
cms::MessageNotReadableException, cms::CMSException)` [virtual]

Reads a byte array from the Stream message stream. If the length of vector value is less than the number of bytes remaining to be read from the stream, the vector should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of vector value, the bytes should be read into the vector. The return value of the total number of bytes read will be less than the length of the vector, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

Parameters:

value buffer to place data in

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements **cms::StreamMessage** (p. 3656).

6.71.2.12 `virtual char activemq::commands::ActiveMQStreamMessage::readChar
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException)` [virtual]

Reads a Char from the Stream message stream.

Returns:

char value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3657).

6.71.2.13 `virtual double activemq::commands::ActiveMQStreamMessage::readDouble
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a 64 bit double from the Stream message stream.

Returns:

double value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3657).

6.71.2.14 `virtual float activemq::commands::ActiveMQStreamMessage::readFloat
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a 32 bit float from the Stream message stream.

Returns:

double value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3658).

6.71.2.15 `virtual int activemq::commands::ActiveMQStreamMessage::readInt
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a 32 bit signed integer from the Stream message stream.

Returns:

int value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3658).

6.71.2.16 `virtual long long ac-
tivismq::commands::ActiveMQStreamMessage::readLong
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a 64 bit long from the Stream message stream.

Returns:

long long value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3658).

6.71.2.17 `virtual short activemq::commands::ActiveMQStreamMessage::readShort
() const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [virtual]`

Reads a 16 bit signed short from the Stream message stream.

Returns:

short value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3659).

```
6.71.2.18 virtual std::string ac-
tivismq::commands::ActiveMQStreamMessage::readString
() const throw ( cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException ) [virtual]
```

Reads an ASCII String from the Stream message stream.

Returns:

String from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3659).

```
6.71.2.19 virtual unsigned short ac-
tivismq::commands::ActiveMQStreamMessage::readUnsignedShort
() const throw ( cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException ) [virtual]
```

Reads a 16 bit unsigned short from the Stream message stream.

Returns:

unsigned short value from stream

Exceptions:

CMSException - if the CMS provider fails to read the message due to some internal error.

MessageEOFException - if unexpected end of message stream has been reached.

MessageFormatException - if this type conversion is invalid.

MessageNotReadableException - if the message is in write-only mode.

Implements `cms::StreamMessage` (p. 3660).

6.71.2.20 virtual void activemq::commands::ActiveMQStreamMessage::reset ()
throw (cms::CMSException) [virtual]

Puts the message body in read-only mode and repositions the stream of bytes to the beginning.

Exceptions:

CMSException

6.71.2.21 virtual std::string activemq::commands::ActiveMQStreamMessage::toString ()
const [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Message** (p. 2530).

6.71.2.22 virtual void activemq::commands::ActiveMQStreamMessage::writeBoolean (bool *value*)
throw (cms::MessageNotWriteableException, cms::CMSException)
[virtual]

Writes a boolean to the Stream message stream as a 1-byte value. The value true is written as the value (byte)1; the value false is written as the value (byte)0.

Parameters:

value boolean to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::StreamMessage** (p. 3660).

6.71.2.23 virtual void activemq::commands::ActiveMQStreamMessage::writeByte
(unsigned char *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a byte to the Stream message stream as a 1-byte value.

Parameters:

value byte to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements `cms::StreamMessage` (p. 3660).

6.71.2.24 `virtual void activemq::commands::ActiveMQStreamMessage::writeBytes (const unsigned char * value, int offset, int length) throw (cms::MessageNotWriteableException, cms::CMSEException) [virtual]`

Writes a portion of a byte array to the Stream message stream. size as the number of bytes to write.

Parameters:

value bytes to write to the stream

offset the initial offset within the byte array

length the number of bytes to use

Exceptions:

CMSEException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements `cms::StreamMessage` (p. 3661).

6.71.2.25 `virtual void activemq::commands::ActiveMQStreamMessage::writeBytes (const std::vector< unsigned char > & value) throw (cms::MessageNotWriteableException, cms::CMSEException) [virtual]`

Writes a byte array to the Stream message stream using the vector size as the number of bytes to write.

Parameters:

value bytes to write to the stream

Exceptions:

CMSEException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements `cms::StreamMessage` (p. 3661).

6.71.2.26 `virtual void activemq::commands::ActiveMQStreamMessage::writeChar (char value) throw (cms::MessageNotWriteableException, cms::CMSEException) [virtual]`

Writes a char to the Stream message stream as a 1-byte value.

Parameters:

value char to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::StreamMessage** (p. 3661).

6.71.2.27 virtual void activemq::commands::ActiveMQStreamMessage::writeDouble
(double *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a double to the Stream message stream as a 8 byte value.

Parameters:

value double to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::StreamMessage** (p. 3662).

6.71.2.28 virtual void activemq::commands::ActiveMQStreamMessage::writeFloat
(float *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a float to the Stream message stream as a 4 byte value.

Parameters:

value float to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::StreamMessage** (p. 3662).

6.71.2.29 virtual void activemq::commands::ActiveMQStreamMessage::writeInt
(int *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a signed int to the Stream message stream as a 4 byte value.

Parameters:

value signed int to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements **cms::StreamMessage** (p. 3662).

6.71.2.30 virtual void activemq::commands::ActiveMQStreamMessage::writeLong
(long long *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a long long to the Stream message stream as a 8 byte value.

Parameters:

value signed long long to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements cms::StreamMessage (p. 3663).

6.71.2.31 virtual void activemq::commands::ActiveMQStreamMessage::writeShort
(short *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes a signed short to the Stream message stream as a 2 byte value.

Parameters:

value signed short to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements cms::StreamMessage (p. 3663).

6.71.2.32 virtual void activemq::commands::ActiveMQStreamMessage::writeString
(const std::string & *value*) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]

Writes an ASCII String to the Stream message stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements cms::StreamMessage (p. 3663).

6.71.2.33 `virtual void activemq::commands::ActiveMQStreamMessage::writeUnsignedShort (unsigned short value) throw (cms::MessageNotWriteableException, cms::CMSException) [virtual]`

Writes a unsigned short to the Stream message stream as a 2 byte value.

Parameters:

value unsigned short to write to the stream

Exceptions:

CMSException - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException - if the message is in read-only mode.

Implements `cms::StreamMessage` (p. 3664).

6.71.3 Field Documentation

6.71.3.1 `const unsigned char activemq::commands::ActiveMQStreamMessage::ID_ - ACTIVEMQSTREAMMESSAGE = 27 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQStreamMessage.h`

6.72 activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller Class Reference

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 552).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.72.1 Detailed Description

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 552). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.72.2 Constructor & Destructor Documentation

6.72.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` `[inline]`

6.72.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::~~ActiveMQStreamMessageMarshaller()` `[inline, virtual]`

6.72.3 Member Function Documentation

6.72.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::createObject(const std::string& name) const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.72.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::getDataStructureType() const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.72.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::marshal(const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.72.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699).

6.72.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700).

6.72

activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller

Class Reference

555

```
6.72.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

```
6.72.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2701).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ActiveMQStreamMessageMarshaller.h**

6.73 activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller Class Reference

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 556).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.73.1 Detailed Description

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 556). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.73.2 Constructor & Destructor Documentation

6.73.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` `[inline]`

6.73.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::~~ActiveMQStreamMessageMarshaller()` `[inline, virtual]`

6.73.3 Member Function Documentation

6.73.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::createObject(const std::string&)` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.73.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.73.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::marshal(const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.73.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714).

6.73.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2715).

```

6.73.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

- IOException* if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

```

6.73.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2716).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ActiveMQStreamMessageMarshaller.h**

6.74 activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 560).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller`:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.74.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 560). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.74.2 Constructor & Destructor Documentation

6.74.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` [inline]

6.74.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::~~ActiveMQStreamMessageMarshaller()` [inline, virtual]

6.74.3 Member Function Documentation

6.74.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.74.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.74.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::marshal(commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.74.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709).

6.74.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2710).


```

6.74.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

- IOException* if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

```

6.74.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2711).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ActiveMQStreamMessageMarshaller.h**

6.75 activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 564).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller`:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.75.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 564). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.75.2 Constructor & Destructor Documentation

6.75.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` [inline]

6.75.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::~ActiveMQStreamMessageMarshaller()` [inline, virtual]

6.75.3 Member Function Documentation

6.75.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.75.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.75.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::marshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.75.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694).

6.75.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2695).

```

6.75.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]

```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

```

6.75.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ActiveMQStreamMessageMarshaller.h**

6.76 activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 568).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller`:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.76.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 568). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.76.2 Constructor & Destructor Documentation

6.76.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` `[inline]`

6.76.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::~~ActiveMQStreamMessageMarshaller()` `[inline, virtual]`

6.76.3 Member Function Documentation

6.76.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::createObject() const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.76.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::getDataStructureType() const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.76.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::marshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.76.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704).

6.76.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705).

6.76

activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller

Class Reference

571

```
6.76.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller**
(p. 2706).

```
6.76.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller**
(p. 2706).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ActiveMQStreamMessageMarshaller.h**

6.77 activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller Class Reference

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 572).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQStreamMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller:

Public Member Functions

- **ActiveMQStreamMessageMarshaller** ()
- virtual **~ActiveMQStreamMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.77.1 Detailed Description

Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 572). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.77.2 Constructor & Destructor Documentation

6.77.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::ActiveMQStreamMessageMarshaller()` [inline]

6.77.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::~ActiveMQStreamMessageMarshaller()` [inline, virtual]

6.77.3 Member Function Documentation

6.77.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.77.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.77.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::marshal(commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.77.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719).

6.77.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2720).

6.77

activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller

Class Reference

575

```
6.77.3.6 virtual void ac-
        tivemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::tightMars
        (OpenWireFormat * wireFormat, commands::DataStructure
        * dataStructure, decaf::io::DataOutputStream * dataOut,
        utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryReader that provides that data sink
- bs* - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

```
6.77.3.7 virtual void ac-
        tivemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller::tightUnm
        (OpenWireFormat * wireFormat, commands::DataStructure *
        dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream
        * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ActiveMQStreamMessageMarshaller.h**

6.78 activemq::commands::ActiveMQTempDestination Class Reference

#include <src/main/activemq/commands/ActiveMQTempDestination.h> Inheritance diagram for activemq::commands::ActiveMQTempDestination:

Public Member Functions

- **ActiveMQTempDestination** ()
- **ActiveMQTempDestination** (const std::string &name)
- virtual ~**ActiveMQTempDestination** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **ActiveMQTempDestination** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **close** () throw (cms::CMSException)
Closes down this Destination resulting in a call to dispose of the TempDestination resource at the Broker.
- void **setConnection** (core::ActiveMQConnection *connection)
Sets the Parent Connection that is notified when this destination is destroyed.

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQTEMPDESTINATION** = 0

Protected Attributes

- core::ActiveMQConnection * **connection**
Connection that we call back on close to allow this resource to be cleaned up correctly at this end and at the Broker End.

6.78.1 Constructor & Destructor Documentation

- 6.78.1.1** `activemq::commands::ActiveMQTempDestination::ActiveMQTempDestination()`
- 6.78.1.2** `activemq::commands::ActiveMQTempDestination::ActiveMQTempDestination(const std::string & name)`
- 6.78.1.3** `virtual
activemq::commands::ActiveMQTempDestination::~~ActiveMQTempDestination()
()` [virtual]

6.78.2 Member Function Documentation

- 6.78.2.1** `virtual ActiveMQTempDestination* activemq::commands::ActiveMQTempDestination::cloneDataStructure()
const` [inline, virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 324).

Reimplemented in `activemq::commands::ActiveMQTempQueue` (p. 605), and `activemq::commands::ActiveMQTempTopic` (p. 634).

- 6.78.2.2** `virtual void activemq::commands::ActiveMQTempDestination::close()
throw (cms::CMSEException)` [virtual]

Closes down this Destination resulting in a call to dispose of the TempDestination resource at the Broker. This should only be called when the user is certain that they are finished with this destination. The TempDestination is not closed automatically on shutdown. throws `cms::CMSEException` (p. 1160)

Implements `cms::Closeable` (p. 1148).

- 6.78.2.3** `virtual void activemq::commands::ActiveMQTempDestination::copyDataStructure(const DataStructure * src)` [inline, virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 325).

Reimplemented in `activemq::commands::ActiveMQTempQueue` (p. 606), and `activemq::commands::ActiveMQTempTopic` (p. 635).

References `activemq::commands::ActiveMQDestination::copyDataStructure()`.

6.78.2.4 `virtual bool activemq::commands::ActiveMQTempDestination::equals (const DataStructure * value) const` [inline, virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 326).

Reimplemented in `activemq::commands::ActiveMQTempQueue` (p. 606), and `activemq::commands::ActiveMQTempTopic` (p. 635).

References `activemq::commands::ActiveMQDestination::equals()`.

6.78.2.5 `virtual unsigned char activemq::commands::ActiveMQTempDestination::getDataStructureType () const` [virtual]

Get the **DataStructure** (p. 1660) Type as defined in `CommandTypes.h`.

Returns:

The type of the data structure

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 326).

Reimplemented in `activemq::commands::ActiveMQTempQueue` (p. 607), and `activemq::commands::ActiveMQTempTopic` (p. 636).

6.78.2.6 `void activemq::commands::ActiveMQTempDestination::setConnection (core::ActiveMQConnection * connection)` [inline]

Sets the Parent Connection that is notified when this destination is destroyed.

Parameters:

connection - The parent connection.

6.78.2.7 `virtual std::string activemq::commands::ActiveMQTempDestination::toString () const` [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 330).

Reimplemented in `activemq::commands::ActiveMQTempQueue` (p. 607), and `activemq::commands::ActiveMQTempTopic` (p. 636).

6.78.3 Field Documentation

6.78.3.1 `core::ActiveMQConnection*` `activemq::commands::ActiveMQTempDestination::connection` [protected]

Connection that we call back on close to allow this resource to be cleaned up correctly at this end and at the Broker End.

6.78.3.2 `const unsigned char` `activemq::commands::ActiveMQTempDestination::ID_` - `ACTIVEMQTEMPDESTINATION = 0` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQTempDestination.h`

6.79 activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 580).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual ~**ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.79.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 580). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.79.2 Constructor & Destructor Documentation

6.79.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` [inline]

6.79.2.2 `virtual ~ActiveMQTempDestinationMarshaller()` [inline, virtual]

6.79.3 Member Function Documentation

6.79.3.1 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 334).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller` (p. 610), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller` (p. 639).

6.79.3.2 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 334).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller` (p. 611), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller` (p. 640).

6.79.3.3 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 335).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller` (p. 611), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller` (p. 640).

6.79.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.79

activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller

Class Reference

583

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 335).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 611), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 640).

6.79.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 336).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller** (p. 612), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller** (p. 641).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ActiveMQTempDestinationMarshaller.h**

6.80 activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 584).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual ~**ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.80.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 584). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.80.2 Constructor & Destructor Documentation

6.80.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` `[inline]`

6.80.2.2 `virtual ~ActiveMQTempDestinationMarshaller()` `[inline, virtual]`

6.80.3 Member Function Documentation

6.80.3.1 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 338).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller` (p. 614), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller` (p. 647).

6.80.3.2 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` `[virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 338).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller` (p. 615), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller` (p. 648).

6.80.3.3 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::tightMarshall(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 339).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller` (p. 615), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller` (p. 648).

6.80.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::tightMarshall(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.80

activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller

Class Reference

587

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 339).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 615), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 648).

6.80.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 340).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller** (p. 616), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller** (p. 649).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h`

6.81 activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 588).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual ~**ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.81.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 588). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.81.2 Constructor & Destructor Documentation

6.81.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` `[inline]`

6.81.2.2 `virtual ~ActiveMQTempDestinationMarshaller()` `[inline, virtual]`

6.81.3 Member Function Documentation

6.81.3.1 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 342).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller` (p. 618), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller` (p. 643).

6.81.3.2 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` `[virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 342).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller` (p. 619), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller` (p. 644).

6.81.3.3 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::tightMarshall(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 343).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller` (p. 619), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller` (p. 644).

6.81.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::tightMarshall(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.81

activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller

Class Reference

591

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 343).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 619), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 644).

6.81.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 344).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller** (p. 620), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller** (p. 645).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h`

6.82 activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 592).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual **~ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.82.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 592). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.82.2 Constructor & Destructor Documentation

6.82.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` `[inline]`

6.82.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::~ActiveMQTempDestinationMarshaller()` `[inline, virtual]`

6.82.3 Member Function Documentation

6.82.3.1 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 346).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller` (p. 622), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller` (p. 651).

6.82.3.2 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` `[virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 346).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller` (p. 623), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller` (p. 652).

6.82.3.3 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 347).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller` (p. 623), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller` (p. 652).

6.82.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.82

activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller

Class Reference

595

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 347).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 623), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 652).

6.82.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 348).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller** (p. 624), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller** (p. 653).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h`

6.83 activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 596).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual ~**ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.83.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 596). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.83.2 Constructor & Destructor Documentation

6.83.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` `[inline]`

6.83.2.2 `virtual ~ActiveMQTempDestinationMarshaller()` `[inline, virtual]`

6.83.3 Member Function Documentation

6.83.3.1 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 350).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 626), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 655).

6.83.3.2 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` `[virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 350).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 627), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 656).

6.83.3.3 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 351).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller` (p. 627), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller` (p. 656).

6.83.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.83

activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller

Class Reference

599

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 351).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller** (p. 627), and **activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller** (p. 656).

6.83.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 352).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller** (p. 628), and **activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller** (p. 657).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ActiveMQTempDestinationMarshaller.h**

6.84 activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 600).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h>
 diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller:

Public Member Functions

- **ActiveMQTempDestinationMarshaller** ()
- virtual **~ActiveMQTempDestinationMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.84.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 600). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.84.2 Constructor & Destructor Documentation

6.84.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::ActiveMQTempDestinationMarshaller()` `[inline]`

6.84.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::~ActiveMQTempDestinationMarshaller()` `[inline, virtual]`

6.84.3 Member Function Documentation

6.84.3.1 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 354).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller` (p. 630), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller` (p. 659).

6.84.3.2 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::unmarshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` `[virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 354).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller` (p. 631), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller` (p. 660).

6.84.3.3 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 355).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller` (p. 631), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller` (p. 660).

6.84.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::tightMa (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.84

activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller

Class Reference

603

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 355).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 631), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 660).

6.84.3.5 virtual void ac-

```
timemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller::tightUn  
(OpenWireFormat * wireFormat, commands::DataStructure *  
dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream  
* bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 356).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller** (p. 632), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller** (p. 661).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h`

6.85 activemq::commands::ActiveMQTempQueue Class Reference

#include <src/main/activemq/commands/ActiveMQTempQueue.h> Inheritance diagram for activemq::commands::ActiveMQTempQueue:

Public Member Functions

- **ActiveMQTempQueue** ()
- **ActiveMQTempQueue** (const std::string &name)
- virtual ~**ActiveMQTempQueue** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **ActiveMQTempQueue** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
Converts the Destination Name into a String.
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **cms::Destination** * **getCMSDestination** () const
- virtual **cms::Destination::DestinationType** **getDestinationType** () const
Retrieve the Destination Type for this Destination.
- virtual **cms::Destination** * **clone** () const
Creates a new instance of this destination type that is a copy of this one, and returns it.
- virtual void **copy** (const **cms::Destination** &source)
Copies the contents of the given Destinastion object to this one.
- virtual const **cms::CMSProperties** & **getCMSProperties** () const
Retrieve any properties that might be part of the destination that was specified.
- virtual std::string **getQueueName** () const throw (cms::CMSException)
Gets the name of this queue.
- virtual void **destroy** () throw (cms::CMSException)
Destroy's the Temp Destination at the Broker.

Static Public Attributes

- static const unsigned char `ID_ACTIVEMQTEMPQUEUE` = 102

6.85.1 Constructor & Destructor Documentation

6.85.1.1 `activemq::commands::ActiveMQTempQueue::ActiveMQTempQueue ()`

6.85.1.2 `activemq::commands::ActiveMQTempQueue::ActiveMQTempQueue (const std::string & name)`

6.85.1.3 `virtual
activemq::commands::ActiveMQTempQueue::~~ActiveMQTempQueue ()
[virtual]`

6.85.2 Member Function Documentation

6.85.2.1 `virtual cms::Destination* ac-
tivemq::commands::ActiveMQTempQueue::clone () const
[inline, virtual]`

Creates a new instance of this destination type that is a copy of this one, and returns it.

Returns:

cloned copy of this object

Implements `cms::Destination` (p. 1724).

6.85.2.2 `virtual ActiveMQTempQueue* ac-
tivemq::commands::ActiveMQTempQueue::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::ActiveMQTempDestination` (p. 577).

6.85.2.3 `virtual void activemq::commands::ActiveMQTempQueue::copy (const
cms::Destination & source) [inline, virtual]`

Copies the contents of the given Destination object to this one.

Parameters:

source The source Destination object.

6.85.2.4 `virtual void activemq::commands::ActiveMQTempQueue::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::ActiveMQTempDestination` (p. 577).

6.85.2.5 `virtual void activemq::commands::ActiveMQTempQueue::destroy () throw (cms::CMSException) [virtual]`

Destroy's the Temp Destination at the Broker.

Exceptions:

CMSException

Implements `cms::TemporaryQueue` (p. 3759).

6.85.2.6 `virtual bool activemq::commands::ActiveMQTempQueue::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::ActiveMQTempDestination` (p. 578).

6.85.2.7 `virtual const cms::Destination* activemq::commands::ActiveMQTempQueue::getCMSDestination () const [inline, virtual]`

Returns:

the `cms::Destination` (p. 1723) interface pointer that the objects that derive from this class implement.

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 326).

6.85.2.8 `virtual const cms::CMSProperties& activemq::commands::ActiveMQTempQueue::getCMSProperties () const [inline, virtual]`

Retrieve any properties that might be part of the destination that was specified. This is a deviation from the JMS spec but necessary due to C++ restrictions.

Returns:

const reference to a properties object.

Implements **cms::Destination** (p. 1724).

6.85.2.9 `virtual unsigned char activemq::commands::ActiveMQTempQueue::getDataStructureType () const [virtual]`

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Reimplemented from **activemq::commands::ActiveMQTempDestination** (p. 578).

6.85.2.10 `virtual cms::Destination::DestinationType activemq::commands::ActiveMQTempQueue::getDestinationType () const [inline, virtual]`

Retrieve the Destination Type for this Destination.

Returns:

The Destination Type

Implements **activemq::commands::ActiveMQDestination** (p. 327).

References cms::Destination::TEMPORARY_QUEUE.

6.85.2.11 `virtual std::string activemq::commands::ActiveMQTempQueue::getQueueName () const throw (cms::CMSException) [inline, virtual]`

Gets the name of this queue.

Returns:

The queue name.

Implements **cms::TemporaryQueue** (p. 3760).

6.85.2.12 `virtual std::string activemq::commands::ActiveMQTempQueue::toString () const [virtual]`

Converts the Destination Name into a String.

Returns:

string name

Reimplemented from **activemq::commands::ActiveMQTempDestination** (p. 578).

6.85.3 Field Documentation

6.85.3.1 `const unsigned char activemq::commands::ActiveMQTempQueue::ID_ - ACTIVEMQTEMPQUEUE = 102` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQTempQueue.h`

6.86 activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 609).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.86.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 609). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.86.2 Constructor & Destructor Documentation

6.86.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.86.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.86.3 Member Function Documentation

6.86.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.86.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.86.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 581).

6.86.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 581).

6.86.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 582).

6.86.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 582).

6.86.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 583).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempQueueMarshaller.h`

6.87 activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.613).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.87.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.613). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.87.2 Constructor & Destructor Documentation

6.87.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.87.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.87.3 Member Function Documentation

6.87.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.87.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.87.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 585).

6.87.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 585).

6.87.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 586).

```

6.87.3.6  virtual void ac-
            tivemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::tightMarshal
            (OpenWireFormat * wireFormat,  commands::DataStructure
            * dataStructure,  decaf::io::DataOutputStream * dataOut,
            utils::BooleanStream * bs) throw ( decaf::io::IOException )  [virtual]

```

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 586).

```

6.87.3.7  virtual void ac-
            tivemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller::tightUnmarsh
            (OpenWireFormat * wireFormat,  commands::DataStructure *
            dataStructure,  decaf::io::DataInputStream * dataIn,  utils::BooleanStream
            * bs) throw ( decaf::io::IOException )  [virtual]

```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 587).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ActiveMQTempQueueMarshaller.h**

6.88 activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.617).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.88.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.617). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.88.2 Constructor & Destructor Documentation

6.88.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.88.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.88.3 Member Function Documentation

6.88.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.88.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.88.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 589).

6.88.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 589).

6.88.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 590).

6.88.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 590).

6.88.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 591).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempQueueMarshaller.h`

6.89 activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.621).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.89.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.621). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.89.2 Constructor & Destructor Documentation

6.89.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.89.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.89.3 Member Function Documentation

6.89.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.89.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.89.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 593).

6.89.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 593).

6.89.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 594).

6.89.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 594).

6.89.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 595).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempQueueMarshaller.h`

6.90 activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.625).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.90.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p.625). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.90.2 Constructor & Destructor Documentation

6.90.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.90.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.90.3 Member Function Documentation

6.90.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.90.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.90.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597).

6.90.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597).

6.90.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 598).

6.90.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 598).

6.90.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 599).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempQueueMarshaller.h`

6.91 activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 629).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempQueueMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller:

Public Member Functions

- **ActiveMQTempQueueMarshaller** ()
- virtual **~ActiveMQTempQueueMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.91.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 629). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.91.2 Constructor & Destructor Documentation

6.91.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::ActiveMQTempQueueMarshaller()` [inline]

6.91.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::~~ActiveMQTempQueueMarshaller()` [inline, virtual]

6.91.3 Member Function Documentation

6.91.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.91.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.91.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 601).

6.91.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 601).

6.91.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 602).

6.91.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 602).

6.91.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 603).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempQueueMarshaller.h`

6.92 activemq::commands::ActiveMQTempTopic Class Reference

#include <src/main/activemq/commands/ActiveMQTempTopic.h> Inheritance diagram for activemq::commands::ActiveMQTempTopic:

Public Member Functions

- **ActiveMQTempTopic** ()
- **ActiveMQTempTopic** (const std::string &name)
- virtual ~**ActiveMQTempTopic** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **ActiveMQTempTopic** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
Converts the Destination Name into a String.
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **cms::Destination** * **getCMSDestination** () const
- virtual **cms::Destination::DestinationType** **getDestinationType** () const
Retrieve the Destination Type for this Destination.
- virtual **cms::Destination** * **clone** () const
Creates a new instance of this destination type that is a copy of this one, and returns it.
- virtual void **copy** (const **cms::Destination** &source)
Copies the contents of the given Destinastion object to this one.
- virtual const **cms::CMSProperties** & **getCMSProperties** () const
Retrieve any properties that might be part of the destination that was specified.
- virtual std::string **getTopicName** () const throw (cms::CMSException)
Gets the name of this topic.
- virtual void **destroy** () throw (cms::CMSException)
Destroy's the Temp Destination at the Broker.

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQTEMPTOPIC** = 103

6.92.1 Constructor & Destructor Documentation

6.92.1.1 `activemq::commands::ActiveMQTempTopic::ActiveMQTempTopic ()`

6.92.1.2 `activemq::commands::ActiveMQTempTopic::ActiveMQTempTopic (const std::string & name)`

6.92.1.3 `virtual
activemq::commands::ActiveMQTempTopic::~~ActiveMQTempTopic ()
[virtual]`

6.92.2 Member Function Documentation

6.92.2.1 `virtual cms::Destination* ac-
tivemq::commands::ActiveMQTempTopic::clone () const
[inline, virtual]`

Creates a new instance of this destination type that is a copy of this one, and returns it.

Returns:

cloned copy of this object

Implements **cms::Destination** (p. 1724).

6.92.2.2 `virtual ActiveMQTempTopic* ac-
tivemq::commands::ActiveMQTempTopic::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::ActiveMQTempDestination** (p. 577).

6.92.2.3 `virtual void activemq::commands::ActiveMQTempTopic::copy (const cms::Destination & source) [inline, virtual]`

Copies the contents of the given Destination object to this one.

Parameters:

source The source Destination object.

6.92.2.4 `virtual void activemq::commands::ActiveMQTempTopic::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::ActiveMQTempDestination` (p. 577).

6.92.2.5 `virtual void activemq::commands::ActiveMQTempTopic::destroy () throw (cms::CMSException) [virtual]`

Destroy's the Temp Destination at the Broker.

Exceptions:

CMSException

Implements `cms::TemporaryTopic` (p. 3761).

6.92.2.6 `virtual bool activemq::commands::ActiveMQTempTopic::equals (const DataStructure * value) const [virtual]`

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::ActiveMQTempDestination` (p. 578).

6.92.2.7 `virtual const cms::Destination* activemq::commands::ActiveMQTempTopic::getCMSDestination () const [inline, virtual]`

Returns:

the **cms::Destination** (p. 1723) interface pointer that the objects that derive from this class implement.

Reimplemented from `activemq::commands::ActiveMQDestination` (p. 326).

6.92.2.8 `virtual const cms::CMSProperties& activemq::commands::ActiveMQTempTopic::getCMSProperties () const [inline, virtual]`

Retrieve any properties that might be part of the destination that was specified. This is a deviation from the JMS spec but necessary due to C++ restrictions.

Returns:

const reference to a properties object.

Implements **cms::Destination** (p. 1724).

6.92.2.9 `virtual unsigned char activemq::commands::ActiveMQTempTopic::getDataStructureType () const [virtual]`

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Reimplemented from **activemq::commands::ActiveMQTempDestination** (p. 578).

6.92.2.10 `virtual cms::Destination::DestinationType activemq::commands::ActiveMQTempTopic::getDestinationType () const [inline, virtual]`

Retrieve the Destination Type for this Destination.

Returns:

The Destination Type

Implements **activemq::commands::ActiveMQDestination** (p. 327).

References cms::Destination::TEMPORARY_TOPIC.

6.92.2.11 `virtual std::string activemq::commands::ActiveMQTempTopic::getTopicName () const throw (cms::CMSException) [inline, virtual]`

Gets the name of this topic.

Returns:

The topic name.

Implements **cms::TemporaryTopic** (p. 3762).

6.92.2.12 `virtual std::string activemq::commands::ActiveMQTempTopic::toString () const [virtual]`

Converts the Destination Name into a String.

Returns:

string name

Reimplemented from **activemq::commands::ActiveMQTempDestination** (p. 578).

6.92.3 Field Documentation

6.92.3.1 `const unsigned char activemq::commands::ActiveMQTempTopic::ID_- ACTIVEMQTEMPTOPIC = 103` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQTempTopic.h`

6.93 activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopic Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.638).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempTopicMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.93.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.638). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.93.2 Constructor & Destructor Documentation

6.93.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` `[inline]`

6.93.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` `[inline, virtual]`

6.93.3 Member Function Documentation

6.93.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.93.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.93.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 581).

6.93.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 581).

6.93.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller` (p. 582).

6.93.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 582).

6.93.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller** (p. 583).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempTopicMarshaller.h`

6.94 activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopic Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.642).

`#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempTopicMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller`:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.94.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.642). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.94.2 Constructor & Destructor Documentation

6.94.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` `[inline]`

6.94.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` `[inline, virtual]`

6.94.3 Member Function Documentation

6.94.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.94.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.94.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 589).

6.94.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 589).

6.94.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller` (p. 590).

6.94.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 590).

6.94.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller** (p. 591).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempTopicMarshaller.h`

6.95 activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopic Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.646).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.95.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p.646). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.95.2 Constructor & Destructor Documentation

6.95.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` [inline]

6.95.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` [inline, virtual]

6.95.3 Member Function Documentation

6.95.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.95.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.95.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 585).

6.95.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 585).

6.95.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 586).

6.95.3.6 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 586).

6.95.3.7 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller** (p. 587).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h`

6.96 activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopic Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 650).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempTopicMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.96.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 650). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.96.2 Constructor & Destructor Documentation

6.96.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` [inline]

6.96.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` [inline, virtual]

6.96.3 Member Function Documentation

6.96.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.96.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.96.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 593).

6.96.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 593).

6.96.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::tightMarshal1(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller` (p. 594).

6.96.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 594).

6.96.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller** (p. 595).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempTopicMarshaller.h`

6.97 activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopic Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 654).

`#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempTopicMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller`:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.97.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 654). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.97.2 Constructor & Destructor Documentation

6.97.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` [inline]

6.97.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` [inline, virtual]

6.97.3 Member Function Documentation

6.97.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.97.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.97.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597).

6.97.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 597).

6.97.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller` (p. 598).

6.97.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 598).

6.97.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller** (p. 599).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempTopicMarshaller.h`

6.98 activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopic Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 658).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempTopicMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller:

Public Member Functions

- **ActiveMQTempTopicMarshaller** ()
- virtual **~ActiveMQTempTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.98.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 658). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.98.2 Constructor & Destructor Documentation

6.98.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::ActiveMQTempTopicMarshaller()` [inline]

6.98.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::~~ActiveMQTempTopicMarshaller()` [inline, virtual]

6.98.3 Member Function Documentation

6.98.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.98.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.98.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 601).

6.98.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 601).

6.98.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller` (p. 602).

6.98.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::tightMarshal2(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 602).

6.98.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller** (p. 603).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempTopicMarshaller.h`

6.99 activemq::commands::ActiveMQTextMessage Class Reference

#include <src/main/activemq/commands/ActiveMQTextMessage.h> Inheritance diagram for activemq::commands::ActiveMQTextMessage:

Public Member Functions

- **ActiveMQTextMessage** ()
- virtual **~ActiveMQTextMessage** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ActiveMQTextMessage * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **clearBody** () throw (cms::CMSException)
Clears out the body of the message.
- virtual void **beforeMarshal** (wireformat::WireFormat *wireFormat) throw (decaf::io::IOException)
*Performs any cleanup or other tasks that must be done before the **Message** (p. 2516) is marshalled to its binary WireFormat version.*
- virtual unsigned int **getSize** () const
Returns the Size of this message in Bytes.
- virtual cms::TextMessage * **clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- virtual std::string **getText** () const throw (cms::CMSException)
Gets the message character buffer.
- virtual void **setText** (const char *msg) throw (cms::MessageNotWriteableException, cms::CMSException)
Sets the message contents, does not take ownership of the passed char, but copies it instead.*

- virtual void **setText** (const std::string &msg) throw (cms::MessageNotWriteableException, cms::CMSException)

Sets the message contents.

Data Fields

- std::auto_ptr< std::string > **text**

Static Public Attributes

- static const unsigned char **ID_ACTIVEMQTEXTMESSAGE** = 28

6.99.1 Constructor & Destructor Documentation

6.99.1.1 `activemq::commands::ActiveMQTextMessage::ActiveMQTextMessage ()`

6.99.1.2 `virtual
activemq::commands::ActiveMQTextMessage::~~ActiveMQTextMessage ()
[virtual]`

6.99.2 Member Function Documentation

6.99.2.1 `virtual void activemq::commands::ActiveMQTextMessage::beforeMarshal
(wireformat::WireFormat * wireFormat) throw (decaf::io::IOException)
[virtual]`

Performs any cleanup or other tasks that must be done before the **Message** (p. 2516) is marshalled to its binary WireFormat version.

Parameters:

wireFormat the WireFormat instance that is marshalling this message.

Implements `activemq::wireformat::MarshalAware` (p. 2485).

6.99.2.2 `virtual void activemq::commands::ActiveMQTextMessage::clearBody ()
throw (cms::CMSException) [virtual]`

Clears out the body of the message. This does not clear the headers or properties.

Reimplemented from `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 428).

6.99.2.3 `virtual cms::TextMessage* ac-
tivemq::commands::ActiveMQTextMessage::clone () const
[inline, virtual]`

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implements **cms::Message** (p. 2539).

6.99.2.4 `virtual ActiveMQTextMessage* activemq::commands::ActiveMQTextMessage::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::Message** (p. 2520).

6.99.2.5 `virtual void activemq::commands::ActiveMQTextMessage::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::Message** (p. 2521).

6.99.2.6 `virtual bool activemq::commands::ActiveMQTextMessage::equals (const DataStructure * value) const [virtual]`

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >** (p. 429).

6.99.2.7 `virtual unsigned char activemq::commands::ActiveMQTextMessage::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Message** (p. 2523).

**6.99.2.8 virtual unsigned int activemq::commands::ActiveMQTextMessage::getSize
() const [virtual]**

Returns the Size of this message in Bytes.

Returns:

number of bytes this message equates to.

Reimplemented from **activemq::commands::Message** (p. 2525).

**6.99.2.9 virtual std::string activemq::commands::ActiveMQTextMessage::getText
() const throw (cms::CMSException) [virtual]**

Gets the message character buffer.

Returns:

The message character buffer.

Exceptions:

CMSException - if an internal error occurs.

Implements **cms::TextMessage** (p. 3763).

**6.99.2.10 virtual void activemq::commands::ActiveMQTextMessage::setText
(const std::string & msg) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]**

Sets the message contents.

Parameters:

msg The message buffer.

Exceptions:

CMSException - if an internal error occurs.

MessageNotWriteableException - if the message is in read-only mode..

Implements **cms::TextMessage** (p. 3764).

**6.99.2.11 virtual void activemq::commands::ActiveMQTextMessage::setText
(const char * msg) throw (cms::MessageNotWriteableException,
cms::CMSException) [virtual]**

Sets the message contents, does not take ownership of the passed char*, but copies it instead.

Parameters:

msg The message buffer.

Exceptions:

CMSException - if an internal error occurs.

MessageNotWriteableException - if the message is in read-only mode..

Implements **cms::TextMessage** (p. 3764).

6.99.2.12 `virtual std::string activemq::commands::ActiveMQTextMessage::toString()
() const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Message** (p. 2530).

6.99.3 Field Documentation

6.99.3.1 `const unsigned char activemq::commands::ActiveMQTextMessage::ID_-
ACTIVEMQTEXTMESSAGE = 28 [static]`

6.99.3.2 `std::auto_ptr<std::string> ac-
tivemq::commands::ActiveMQTextMessage::text
[mutable]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQTextMessage.h`

6.100

activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller

Class Reference

6.100 — activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.667).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTextMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual ~**ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure** * **createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.100.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.667). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.100.2 Constructor & Destructor Documentation

6.100.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.100.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.100.3 Member Function Documentation

6.100.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.100.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.100.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.100

activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller

Class Reference

669

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2699).

6.100.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2699).

6.100.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p. 2700).

6.100.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p.2701).

6.100.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::MessageMarshaller** (p.2701).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTextMessageMarshaller.h`

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.671).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTextMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual **~ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.101.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.671). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.101.2 Constructor & Destructor Documentation

6.101.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.101.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.101.3 Member Function Documentation

6.101.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.101.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.101.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.101

activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller

Class Reference

673

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2709).

6.101.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2709).

6.101.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p. 2710).

6.101.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p.2711).

6.101.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::MessageMarshaller** (p.2711).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTextMessageMarshaller.h`

6.102

activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller

Class Reference

6.102 **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller** ⁶⁷⁵

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.675).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTextMessageMarshaller.h> Inheritance diagram for **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller**:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual **~ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.102.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.675). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.102.2 Constructor & Destructor Documentation

6.102.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.102.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.102.3 Member Function Documentation

6.102.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.102.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.102.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.102

activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller

Class Reference

677

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2714).

6.102.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::looseUnmar
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2714).

6.102.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::tightMarsh
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p. 2715).

6.102.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p.2716).

6.102.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::MessageMarshaller** (p.2716).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ActiveMQTextMessageMarshaller.h**

6.103

activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller

Class Reference

6.103 **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller** ⁶⁷⁹

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.679).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTextMessageMarshaller.h> Inheritance diagram for **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller**:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual **~ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.103.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.679). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.103.2 Constructor & Destructor Documentation

6.103.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.103.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.103.3 Member Function Documentation

6.103.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.103.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.103.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.103

activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller

Class Reference

681

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2694).

6.103.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2694).

6.103.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2695).

6.103.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

6.103.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2696).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ActiveMQTextMessageMarshaller.h**

6.104

activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller

Class Reference

6.104 **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller** ⁶⁸³

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.683).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTextMessageMarshaller.h> Inheritance diagram for **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller**:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual **~ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshall an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshall an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.104.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.683). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.104.2 Constructor & Destructor Documentation

6.104.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.104.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.104.3 Member Function Documentation

6.104.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure&) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.104.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.104.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, const commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.104

activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller

Class Reference

685

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2719).

6.104.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::looseUnmar
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2719).

6.104.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::tightMarsh
(OpenWireFormat * *wireFormat*, commands::DataStructure *
***dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException**
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2720).

6.104.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

6.104.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::MessageMarshaller** (p. 2721).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTextMessageMarshaller.h`

6.105

activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller

Class Reference

6.105 ~~activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller~~⁶⁸⁷

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.687).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTextMessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller:

Public Member Functions

- **ActiveMQTextMessageMarshaller** ()
- virtual **~ActiveMQTextMessageMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.105.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p.687). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.105.2 Constructor & Destructor Documentation

6.105.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::ActiveMQTextMessageMarshaller()` [inline]

6.105.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::~~ActiveMQTextMessageMarshaller()` [inline, virtual]

6.105.3 Member Function Documentation

6.105.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.105.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.105.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::looseMarshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.105

activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller

Class Reference

689

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2704).

6.105.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::looseUnmar
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2704).

6.105.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::tightMarsh
(OpenWireFormat * *wireFormat*, commands::DataStructure *
***dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException**
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2705).

6.105.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

6.105.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::MessageMarshaller** (p. 2706).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTextMessageMarshaller.h`

6.106 activemq::commands::ActiveMQTopic Class Reference

#include <src/main/activemq/commands/ActiveMQTopic.h> Inheritance diagram for activemq::commands::ActiveMQTopic:

Public Member Functions

- **ActiveMQTopic** ()
- **ActiveMQTopic** (const std::string &name)
- virtual ~**ActiveMQTopic** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **ActiveMQTopic** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **cms::Destination** * **getCMSDestination** () const
- virtual **cms::Destination::DestinationType** **getDestinationType** () const
Retrieve the Destination Type for this Destination.
- virtual **cms::Destination** * **clone** () const
Creates a new instance of this destination type that is a copy of this one, and returns it.
- virtual void **copy** (const **cms::Destination** &source)
Copies the contents of the given Destination object to this one.
- virtual const **cms::CMSProperties** & **getCMSProperties** () const
Retrieve any properties that might be part of the destination that was specified.
- virtual std::string **getTopicName** () const throw (cms::CMSException)
Gets the name of this topic.

Static Public Attributes

- static const unsigned char **ID _ACTIVEMQTOPIC** = 101

6.106.1 Constructor & Destructor Documentation

6.106.1.1 `activemq::commands::ActiveMQTopic::ActiveMQTopic ()`

6.106.1.2 `activemq::commands::ActiveMQTopic::ActiveMQTopic (const std::string & name)`

6.106.1.3 `virtual activemq::commands::ActiveMQTopic::~~ActiveMQTopic ()`
[virtual]

6.106.2 Member Function Documentation

6.106.2.1 `virtual cms::Destination* activemq::commands::ActiveMQTopic::clone ()`
`const` [inline, virtual]

Creates a new instance of this destination type that is a copy of this one, and returns it.

Returns:

cloned copy of this object

Implements **cms::Destination** (p.1724).

6.106.2.2 `virtual ActiveMQTopic* activemq::commands::ActiveMQTopic::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from **activemq::commands::ActiveMQDestination** (p.324).

6.106.2.3 `virtual void activemq::commands::ActiveMQTopic::copy (const cms::Destination & source)` [inline, virtual]

Copies the contents of the given Destination object to this one.

Parameters:

source The source Destination object.

6.106.2.4 `virtual void activemq::commands::ActiveMQTopic::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::ActiveMQDestination** (p.325).

6.106.2.5 virtual bool activemq::commands::ActiveMQTopic::equals (const DataStructure * *value*) const [inline, virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

References **activemq::commands::ActiveMQDestination::equals()**.

6.106.2.6 virtual const cms::Destination* activemq::commands::ActiveMQTopic::getCMSDestination () const [inline, virtual]**Returns:**

the **cms::Destination** (p. 1723) interface pointer that the objects that derive from this class implement.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

6.106.2.7 virtual const cms::CMSProperties& activemq::commands::ActiveMQTopic::getCMSProperties () const [inline, virtual]

Retrieve any properties that might be part of the destination that was specified. This is a deviation from the JMS spec but necessary due to C++ restrictions.

Returns:

const reference to a properties object.

Implements **cms::Destination** (p. 1724).

6.106.2.8 virtual unsigned char activemq::commands::ActiveMQTopic::getDataStructureType () const [virtual]

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 326).

6.106.2.9 virtual cms::Destination::DestinationType activemq::commands::ActiveMQTopic::getDestinationType () const [inline, virtual]

Retrieve the Destination Type for this Destination.

Returns:

The Destination Type

Implements **activemq::commands::ActiveMQDestination** (p. 327).

References **cms::Destination::TOPIC**.

6.106.2.10 `virtual std::string activemq::commands::ActiveMQTopic::getTopicName
() const throw (cms::CMSException) [inline, virtual]`

Gets the name of this topic.

Returns:

The topic name.

Implements **cms::Topic** (p. 3817).

6.106.2.11 `virtual std::string activemq::commands::ActiveMQTopic::toString ()
const [virtual]`

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::ActiveMQDestination** (p. 330).

6.106.3 Field Documentation

6.106.3.1 `const unsigned char activemq::commands::ActiveMQTopic::ID_-
ACTIVEMQTOPIC = 101 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ActiveMQTopic.h`

6.107 activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 695).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.107.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 695).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.107.2 Constructor & Destructor Documentation

6.107.2.1 `activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.107.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.107.3 Member Function Documentation

6.107.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.107.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.107.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 334).

6.107.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 334).

6.107.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller` (p. 335).

6.107.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 335).

6.107.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller** (p. 336).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTopicMarshaller.h

6.108 activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 699).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.108.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 699).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.108.2 Constructor & Destructor Documentation

6.108.2.1 `activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.108.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.108.3 Member Function Documentation

6.108.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.108.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.108.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 342).

6.108.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 342).

6.108.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller` (p. 343).

6.108.3.6 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 343).

6.108.3.7 `virtual void activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller** (p. 344).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTopicMarshaller.h`

6.109 activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 703).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.109.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 703).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.109.2 Constructor & Destructor Documentation

6.109.2.1 `activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.109.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.109.3 Member Function Documentation

6.109.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.109.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.109.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 338).

6.109.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 338).

6.109.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 339).

6.109.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 339).

6.109.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller** (p. 340).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ActiveMQTopicMarshaller.h**

6.110 activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 707).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.110.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 707).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.110.2 Constructor & Destructor Documentation

6.110.2.1 `activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.110.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.110.3 Member Function Documentation

6.110.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.110.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.110.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 346).

6.110.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 346).

6.110.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller` (p. 347).

6.110.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 347).

6.110.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller** (p. 348).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTopicMarshaller.h`

6.111 activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 711).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.111.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 711).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.111.2 Constructor & Destructor Documentation

6.111.2.1 `activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.111.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.111.3 Member Function Documentation

6.111.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.111.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.111.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 354).

6.111.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 354).

6.111.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller` (p. 355).

6.111.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 355).

6.111.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller** (p. 356).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTopicMarshaller.h

6.112 activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 715).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTopicMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller:

Public Member Functions

- **ActiveMQTopicMarshaller** ()
- virtual **~ActiveMQTopicMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.112.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 715).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.112.2 Constructor & Destructor Documentation

6.112.2.1 `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::ActiveMQTopicMarshaller()` [inline]

6.112.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::~~ActiveMQTopicMarshaller()` [inline, virtual]

6.112.3 Member Function Documentation

6.112.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.112.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.112.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 350).

6.112.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 350).

6.112.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller` (p. 351).

6.112.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 351).

6.112.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller** (p. 352).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTopicMarshaller.h

6.113 activemq::core::ActiveMQTransactionContext Class Reference

Transaction Management class, hold messages that are to be redelivered upon a request to roll-back.

```
#include <src/main/activemq/core/ActiveMQTransactionContext.h>
```

Public Member Functions

- **ActiveMQTransactionContext** (**ActiveMQSession** *session, const **decaf::util::Properties** &properties)
Constructor.
- virtual **~ActiveMQTransactionContext** ()
- virtual void **addSynchronization** (const **Pointer**< **Synchronization** > &sync)
*Adds a **Synchronization** (p. 3715) to this Transaction.*
- virtual void **removeSynchronization** (const **Pointer**< **Synchronization** > &sync)
*Removes a **Synchronization** (p. 3715) to this Transaction.*
- virtual void **begin** () throw (exceptions::ActiveMQException)
Begins a new transaction if one is not currently in progress.
- virtual void **commit** () throw (exceptions::ActiveMQException)
Commit the current Transaction.
- virtual void **rollback** () throw (exceptions::ActiveMQException)
Rollback the current Transaction.
- virtual const **decaf::lang::Pointer**< **commands::TransactionId** > & **getTransactionId** () const
Get the Transaction Id object for the current Transaction, returns NULL if no transaction is running.
- virtual bool **isInTransaction** () const
Checks to see if there is currently a Transaction in progress returns false if not, true otherwise.

6.113.1 Detailed Description

Transaction Management class, hold messages that are to be redelivered upon a request to roll-back. The Transaction represents an always running transaction, when it is committed or rolled back it silently creates a new transaction for the next set of messages. The only way to permanently end this transaction is to delete it.

Since:

2.0

6.113.2 Constructor & Destructor Documentation

6.113.2.1 `activemq::core::ActiveMQTransactionContext::ActiveMQTransactionContext (ActiveMQSession * session, const decaf::util::Properties & properties)`

Constructor.

Parameters:

session The session that contains this transaction
properties Configuration parameters for this object

6.113.2.2 `virtual activemq::core::ActiveMQTransactionContext::~~ActiveMQTransactionContext () [virtual]`

6.113.3 Member Function Documentation

6.113.3.1 `virtual void activemq::core::ActiveMQTransactionContext::addSynchronization (const Pointer< Synchronization > & sync) [virtual]`

Adds a **Synchronization** (p. 3715) to this Transaction.

Parameters:

sync - The **Synchronization** (p. 3715) instance to add.

6.113.3.2 `virtual void activemq::core::ActiveMQTransactionContext::begin () throw (exceptions::ActiveMQException) [virtual]`

Begins a new transaction if one is not currently in progress.

Exceptions:

ActiveMQException

6.113.3.3 `virtual void activemq::core::ActiveMQTransactionContext::commit () throw (exceptions::ActiveMQException) [virtual]`

Commit the current Transaction.

Exceptions:

ActiveMQException

6.113.3.4 `virtual const decaf::lang::Pointer<commands::TransactionId>& activemq::core::ActiveMQTransactionContext::getTransactionId () const [virtual]`

Get the Transaction Id object for the current Transaction, returns NULL if no transaction is running.

Returns:

TransactionInfo

Exceptions:

InvalidStateException if a Transaction is not in progress.

6.113.3.5 virtual bool activemq::core::ActiveMQTransactionContext::isInTransaction () const [virtual]

Checks to see if there is currently a Transaction in progress returns false if not, true otherwise.

Returns:

true if a transaction is in progress.

6.113.3.6 virtual void activemq::core::ActiveMQTransactionContext::removeSynchronization (const Pointer< Synchronization > & sync) [virtual]

Removes a **Synchronization** (p. 3715) to this Transaction.

Parameters:

sync - The **Synchronization** (p. 3715) instance to add.

6.113.3.7 virtual void activemq::core::ActiveMQTransactionContext::rollback () throw (exceptions::ActiveMQException) [virtual]

Rollback the current Transaction.

Exceptions:

ActiveMQException

The documentation for this class was generated from the following file:

- src/main/activemq/core/ActiveMQTransactionContext.h

6.114 decaf::util::zip::Adler32 Class Reference

Clas that can be used to compute an Adler-32 **Checksum** (p. 1142) for a data stream.

```
#include <src/main/decaf/util/zip/Adler32.h>Inheritance diagram for de-
caf::util::zip::Adler32:
```

Public Member Functions

- **Adler32** ()
- virtual **~Adler32** ()
- virtual long long **getValue** () const
- virtual void **reset** ()

Reset the checksum to its initial value.
- virtual void **update** (const std::vector< unsigned char > &buffer)

Updates the current checksum with the specified vector of bytes.
- virtual void **update** (const std::vector< unsigned char > &buffer, int offset, int length)
 throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Updates the current checksum with the specified array of bytes.
- virtual void **update** (const unsigned char *buffer, int size, int off-
 set, int length) throw (decaf::lang::exceptions::NullPointerException, de-
 caf::lang::exceptions::IndexOutOfBoundsException)

Updates the current checksum with the specified array of bytes.
- virtual void **update** (int byte)

Updates the current checksum with the specified byte value.

6.114.1 Detailed Description

Clas that can be used to compute an Adler-32 **Checksum** (p. 1142) for a data stream. The Alder-32 checksum trades reliability for speed over the CRC-32 algorithm.

Since:

1.0

6.114.2 Constructor & Destructor Documentation

6.114.2.1 decaf::util::zip::Adler32::Adler32 ()

6.114.2.2 virtual decaf::util::zip::Adler32::~~Adler32 () [virtual]

6.114.3 Member Function Documentation

6.114.3.1 virtual long long decaf::util::zip::Adler32::getValue () const [virtual]

Returns:

the current checksum value.

Implements **decaf::util::zip::Checksum** (p. 1142).

6.114.3.2 virtual void decaf::util::zip::Adler32::reset () [virtual]

Reset the checksum to its initial value.

Implements **decaf::util::zip::Checksum** (p. 1143).

6.114.3.3 virtual void decaf::util::zip::Adler32::update (int *byte*) [virtual]

Updates the current checksum with the specified byte value.

Parameters:

byte The byte value to update the current **Checksum** (p. 1142) with (0..255).

Implements **decaf::util::zip::Checksum** (p. 1143).

6.114.3.4 virtual void decaf::util::zip::Adler32::update (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

size The size of the passed buffer.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

NullPointerException if the passed buffer is NULL.

IndexOutOfBoundsException if offset + length > size of the buffer.

Implements **decaf::util::zip::Checksum** (p. 1143).

6.114.3.5 `virtual void decaf::util::zip::Adler32::update (const std::vector< unsigned char > & buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

IndexOutOfBoundsException if `offset + length > size` of the buffer.

Implements `decaf::util::zip::Checksum` (p. 1143).

6.114.3.6 `virtual void decaf::util::zip::Adler32::update (const std::vector< unsigned char > & buffer)` [virtual]

Updates the current checksum with the specified vector of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

Implements `decaf::util::zip::Checksum` (p. 1144).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/Adler32.h`

6.115 decaf::lang::Appendable Class Reference

An object to which char sequences and values can be appended.

#include <src/main/decaf/lang/Appendable.h> Inheritance diagram for decaf::lang::Appendable:

Public Member Functions

- virtual **~Appendable** ()
- virtual **Appendable** & **append** (char value)=0 throw (decaf::lang::Exception)

*Appends the specified character to this **Appendable** (p. 725).*

- virtual **Appendable** & **append** (const **CharSequence** *csq)=0 throw (decaf::lang::Exception)

*Appends the specified character sequence to this **Appendable** (p. 725).*

- virtual **Appendable** & **append** (const **CharSequence** *csq, int start, int end)=0 throw (decaf::lang::Exception)

*Appends a subsequence of the specified character sequence to this **Appendable** (p. 725).*

6.115.1 Detailed Description

An object to which char sequences and values can be appended. The **Appendable** (p.725) interface must be implemented by any class whose instances are intended to receive formatted output from a Formatter.

TODO The characters to be appended should be valid Unicode characters as described in Unicode **Character** (p.1100) Representation. Note that supplementary characters may be composed of multiple 16-bit char values.

Appendables are not necessarily safe for multithreaded access. **Thread** (p.3765) safety is the responsibility of classes that extend and implement this interface.

Since this interface may be implemented by existing classes with different styles of error handling there is no guarantee that errors will be propagated to the invoker.

Since:

1.0

6.115.2 Constructor & Destructor Documentation

6.115.2.1 `virtual decaf::lang::Appendable::~~Appendable () [inline, virtual]`

6.115.3 Member Function Documentation

6.115.3.1 `virtual Appendable& decaf::lang::Appendable::append (const CharSequence * csq, int start, int end) throw (decaf::lang::Exception) [pure virtual]`

Appends a subsequence of the specified character sequence to this **Appendable** (p. 725).

Parameters:

csq - The character sequence from which a subsequence will be appended. If *csq* is NULL, then characters will be appended as if *csq* contained the string "null".

start The index of the first character in the subsequence.

end The index of the character following the last character in the subsequence.

Returns:

a Reference to this **Appendable** (p. 725)

Exceptions:

Exception (p. 1831) if an error occurs.

IndexOutOfBoundsException *start* is greater than *end*, or *end* is greater than *csq.length()*

Implemented in **decaf::io::Writer** (p. 4022), and **decaf::nio::CharBuffer** (p. 1123).

6.115.3.2 `virtual Appendable& decaf::lang::Appendable::append (const CharSequence * csq) throw (decaf::lang::Exception) [pure virtual]`

Appends the specified character sequence to this **Appendable** (p. 725).

Parameters:

csq The character sequence from which a subsequence will be appended. If *csq* is NULL, then characters will be appended as if *csq* contained the string "null".

Returns:

a Reference to this **Appendable** (p. 725).

Exceptions:

Exception (p. 1831) if an error occurs.

Implemented in **decaf::io::Writer** (p. 4023), and **decaf::nio::CharBuffer** (p. 1123).

6.115.3.3 `virtual Appendable& decaf::lang::Appendable::append (char value) throw (decaf::lang::Exception) [pure virtual]`

Appends the specified character to this **Appendable** (p. 725).

Parameters:

value The character to append.

Returns:

a Reference to this **Appendable** (p. 725)

Exceptions:

Exception (p. 1831) if an error occurs.

Implemented in **decaf::io::Writer** (p. 4023), and **decaf::nio::CharBuffer** (p. 1124).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Appendable.h**

6.116 decaf::internal::AprPool Class Reference

Wraps an APR pool object so that classes in **decaf** (p. 143) can create a static member for use in static methods where apr function calls that need a pool are made.

```
#include <src/main/decaf/internal/AprPool.h>
```

Public Member Functions

- **AprPool** ()
- virtual **~AprPool** ()
- **apr_pool_t * getAprPool** () const
*Gets the **internal** (p. 144) APR Pool.*
- void **cleanup** ()
Clears data that was allocated by this pool.

Static Public Member Functions

- static **apr_pool_t * getGlobalPool** ()
Gets a pointer to the Global APR Pool used for the Application.

6.116.1 Detailed Description

Wraps an APR pool object so that classes in **decaf** (p. 143) can create a static member for use in static methods where apr function calls that need a pool are made.

6.116.2 Constructor & Destructor Documentation

6.116.2.1 decaf::internal::AprPool::AprPool ()

6.116.2.2 virtual decaf::internal::AprPool::~~AprPool () [virtual]

6.116.3 Member Function Documentation

6.116.3.1 void decaf::internal::AprPool::cleanup ()

Clears data that was allocated by this pool. Users should call this after getting the data from the APR functions and copying it to someplace safe.

6.116.3.2 apr_pool_t* decaf::internal::AprPool::getAprPool () const

Gets the **internal** (p. 144) APR Pool.

Returns:

the **internal** (p. 144) APR pool

6.116.3.3 static apr_pool_t* decaf::internal::AprPool::getGlobalPool () [static]

Gets a pointer to the Global APR Pool used for the Application.

Returns:

pointer to the global APR Pool

The documentation for this class was generated from the following file:

- src/main/decaf/internal/**AprPool.h**

6.117 decaf::lang::ArrayPointer< T, REFCOUNTER > Class Template Reference

Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used.

```
#include <src/main/decaf/lang/ArrayPointer.h>
```

Data Structures

- struct **ArrayData**

Public Types

- typedef T * **PointerType**
- typedef T & **ReferenceType**
- typedef const T & **ConstReferenceType**
- typedef REFCOUNTER **CounterType**

Public Member Functions

- **ArrayPointer** ()
Default Constructor.
- **ArrayPointer** (int size)
*Create a new **ArrayPointer** (p. 730) instance and allocates an **internal** (p. 144) array that is sized using the passed in size value.*
- **ArrayPointer** (const **PointerType** value, int size)
*Explicit Constructor, creates an **ArrayPointer** (p. 730) that contains value with a single reference.*
- **ArrayPointer** (const **ArrayPointer** &value) throw ()
Copy constructor.
- virtual ~**ArrayPointer** () throw ()
- void **reset** (T *value, int size=0)
*Resets the **ArrayPointer** (p. 730) to hold the new value.*
- T * **release** ()
*Releases the **Pointer** (p. 2946) held and resets the **internal** (p. 144) pointer value to Null.*
- **PointerType** **get** () const
*Gets the real array pointer that is contained within this **Pointer** (p. 2946).*
- int **length** () const
Returns the current size of the contained array or zero if the array is NULL.
- void **swap** (**ArrayPointer** &value) throw ()

Exception (p. 1831) Safe Swap Function.

- **ArrayPointer** clone () const

*Creates a new **ArrayPointer** (p. 730) instance that is a clone of the value contained in this **ArrayPointer** (p. 730).*

- **ArrayPointer** & operator= (const **ArrayPointer** &right) throw ()

*Assigns the value of right to this **Pointer** (p. 2946) and increments the reference Count.*

- template<typename T1 , typename R1 >

ArrayPointer & operator= (const **ArrayPointer**< T1, R1 > &right) throw ()

- **ReferenceType** operator[] (int index)

Dereference Operator, returns a reference to the Contained value.

- **ConstReferenceType** operator[] (int index) const

- bool operator! () const

- template<typename T1 , typename R1 >

bool operator== (const **ArrayPointer**< T1, R1 > &right) const

- template<typename T1 , typename R1 >

bool operator!= (const **ArrayPointer**< T1, R1 > &right) const

Friends

- bool operator== (const **ArrayPointer** &left, const T *right)

- bool operator== (const T *left, const **ArrayPointer** &right)

- bool operator!= (const **ArrayPointer** &left, const T *right)

- bool operator!= (const T *left, const **ArrayPointer** &right)

6.117.1 Detailed Description

```
template<typename T, typename REFCOUNTER =  
decaf::util::concurrent::atomic::AtomicRefCounter> class decaf::lang::ArrayPointer<  
T, REFCOUNTER >
```

Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used. This **Pointer** (p. 2946) type allows for the substitution of different Reference Counter implementations which provide a means of using invasive reference counting if desired using a custom implementation of **ReferenceCounter**.

The Decaf smart pointer provide comparison operators for comparing **Pointer** (p. 2946) instances in the same manner as normal pointer, except that it does not provide an overload of operators (<, <=, >, >=). To allow use of a **Pointer** (p. 2946) in a STL container that requires it, **Pointer** (p. 2946) provides an implementation of std::less.

Since:

1.0

6.117.2 Member Typedef Documentation

6.117.2.1 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef const T& decaf::lang::ArrayPointer< T, REFCOUNTER >::ConstReferenceType`

6.117.2.2 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef REFCOUNTER decaf::lang::ArrayPointer< T, REFCOUNTER >::CounterType`

6.117.2.3 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef T* decaf::lang::ArrayPointer< T, REFCOUNTER >::PointerType`

6.117.2.4 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef T& decaf::lang::ArrayPointer< T, REFCOUNTER >::ReferenceType`

6.117.3 Constructor & Destructor Documentation

6.117.3.1 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::ArrayPointer< T, REFCOUNTER >::ArrayPointer () [inline]`

Default Constructor. Initialized the contained array pointer to NULL, using the subscript operator results in an exception unless reset to contain a real value.

Referenced by `decaf::lang::ArrayPointer< unsigned char >::clone()`, and `decaf::lang::ArrayPointer< unsigned char >::reset()`.

6.117.3.2 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::ArrayPointer< T, REFCOUNTER >::ArrayPointer (int size) [inline]`

Create a new **ArrayPointer** (p. 730) instance and allocates an **internal** (p. 144) array that is sized using the passed in size value.

Parameters:

size The size of the array to allocate for this **ArrayPointer** (p. 730) instance.

6.117.3.3 `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::ArrayPointer< T, REFCOUNTER >::ArrayPointer (const PointerType value, int size) [inline, explicit]`

Explicit Constructor, creates an **ArrayPointer** (p. 730) that contains value with a single reference. This object now has ownership until a call to release.

Parameters:

value The pointer to the instance of the array we are taking ownership of.

size The size of the array this object is taking ownership of.

6.117.3.4 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount>
decaf::lang::ArrayPointer< T, REFCOUNTER >::ArrayPointer (const
ArrayPointer< T, REFCOUNTER > & value) throw () [inline]`

Copy constructor. Copies the value contained in the **ArrayPointer** (p. 730) to the new instance and increments the reference counter.

6.117.3.5 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> virtual
decaf::lang::ArrayPointer< T, REFCOUNTER >::~~ArrayPointer ()
throw () [inline, virtual]`

6.117.4 Member Function Documentation

6.117.4.1 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> ArrayPointer
decaf::lang::ArrayPointer< T, REFCOUNTER >::clone () const
[inline]`

Creates a new **ArrayPointer** (p. 730) instance that is a clone of the value contained in this **ArrayPointer** (p. 730).

Returns:

an **ArrayPointer** (p. 730) that contains a copy of the data in this **ArrayPointer** (p. 730).

6.117.4.2 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> PointerType
decaf::lang::ArrayPointer< T, REFCOUNTER >::get () const [inline]`

Gets the real array pointer that is contained within this **Pointer** (p. 2946). This is not really safe since the caller could delete or alter the pointer but it mimics the STL `auto_ptr` and gives access in cases where the caller absolutely needs the real **Pointer** (p. 2946). Use at your own risk.

Returns:

the contained pointer.

Referenced by `decaf::lang::ArrayPointer< unsigned char >::clone()`, `decaf::lang::ArrayPointerComparator< T, R >::compare()`, `decaf::lang::operator!=()`, `decaf::lang::ArrayPointer< unsigned char >::operator!=()`, `std::less< decaf::lang::ArrayPointer< T > >::operator()`, `decaf::lang::ArrayPointerComparator< T, R >::operator()`, `decaf::lang::operator==()`, and `decaf::lang::ArrayPointer< unsigned char >::operator==()`.

```

6.117.4.3  template<typename T, typename REFCOUNTER =
            decaf::util::concurrent::atomic::AtomicRefCounter> int
            decaf::lang::ArrayPointer< T, REFCOUNTER >::length () const
            [inline]

```

Returns the current size of the contained array or zero if the array is NULL.

Returns:

the size of the array or zero if the array is NULL

```

6.117.4.4  template<typename T, typename REFCOUNTER =
            decaf::util::concurrent::atomic::AtomicRefCounter> bool
            decaf::lang::ArrayPointer< T, REFCOUNTER >::operator! () const
            [inline]

```

```

6.117.4.5  template<typename T, typename REFCOUNTER =
            decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
            T1 , typename R1 > bool decaf::lang::ArrayPointer< T, REFCOUNTER
            >::operator!= (const ArrayPointer< T1, R1 > & right) const [inline]

```

```

6.117.4.6  template<typename T, typename REFCOUNTER =
            decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
            T1 , typename R1 > ArrayPointer& decaf::lang::ArrayPointer< T,
            REFCOUNTER >::operator= (const ArrayPointer< T1, R1 > & right)
            throw () [inline]

```

```

6.117.4.7  template<typename T, typename REFCOUNTER =
            decaf::util::concurrent::atomic::AtomicRefCounter> ArrayPointer&
            decaf::lang::ArrayPointer< T, REFCOUNTER >::operator= (const
            ArrayPointer< T, REFCOUNTER > & right) throw () [inline]

```

Assigns the value of *right* to this **Pointer** (p. 2946) and increments the reference Count.

Parameters:

right - **Pointer** (p. 2946) on the right hand side of an operator= call to this.

6.117.4.8 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> template<typename
T1 , typename R1 > bool decaf::lang::ArrayPointer< T, REFCOUNTER
>::operator==(const ArrayPointer< T1, R1 > & right) const [inline]`

6.117.4.9 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> ConstReferenceType
decaf::lang::ArrayPointer< T, REFCOUNTER >::operator[] (int index)
const [inline]`

6.117.4.10 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> ReferenceType
decaf::lang::ArrayPointer< T, REFCOUNTER >::operator[] (int index)
[inline]`

Dereference Operator, returns a reference to the Contained value. This method throws an `NullPointerException` if the contained value is `NULL`.

Returns:

reference to the contained pointer.

Exceptions:

NullPointerException if the contained value is `Null`

6.117.4.11 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> T*
decaf::lang::ArrayPointer< T, REFCOUNTER >::release () [inline]`

Releases the **Pointer** (p. 2946) held and resets the **internal** (p. 144) pointer value to `Null`. This method is not guaranteed to be safe if the **Pointer** (p. 2946) is held by more than one object or this method is called from more than one thread.

Parameters:

value - The new value to contain.

Returns:

The pointer instance that was held by this **Pointer** (p. 2946) object, the pointer is no longer owned by this **Pointer** (p. 2946) and won't be freed when this **Pointer** (p. 2946) goes out of scope.

Referenced by `decaf::lang::ArrayPointer< unsigned char >::ArrayPointer()`.

6.117.4.12 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> void
decaf::lang::ArrayPointer< T, REFCOUNTER >::reset (T * value, int
size = 0) [inline]`

Resets the **ArrayPointer** (p. 730) to hold the new value. Before the new value is stored reset checks if the old value should be destroyed and if so calls `delete`. Call reset with a value of `NULL` is supported and acts to set this **Pointer** (p. 2946) to a `NULL` pointer.

Parameters:

value The new array pointer value to contain.

size The size of the new array value this object now contains.

6.117.4.13 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> void
decaf::lang::ArrayPointer< T, REFCOUNTER >::swap (ArrayPointer<
T, REFCOUNTER > & value) throw () [inline]`

Exception (p.1831) Safe Swap Function.

Parameters:

value - the value to swap with this.

Referenced by `decaf::lang::ArrayPointer< unsigned char >::operator=()`, and `decaf::lang::ArrayPointer< unsigned char >::swap()`.

6.117.5 Friends And Related Function Documentation

6.117.5.1 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> bool operator!=
(const T * left, const ArrayPointer< T, REFCOUNTER > & right)
[friend]`

6.117.5.2 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> bool operator!=
(const ArrayPointer< T, REFCOUNTER > & left, const T * right)
[friend]`

6.117.5.3 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> bool operator==
(const T * left, const ArrayPointer< T, REFCOUNTER > & right)
[friend]`

6.117.5.4 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> bool operator==
(const ArrayPointer< T, REFCOUNTER > & left, const T * right)
[friend]`

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/ArrayPointer.h`

6.118 decaf::lang::ArrayPointerComparator< T, R > Class Template Reference

This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the value of the actual pointer to the array being contained in this **ArrayPointer** (p. 730).

#include <src/main/decaf/lang/ArrayPointer.h>Inheritance diagram for decaf::lang::ArrayPointerComparator< T, R >:

Public Member Functions

- virtual bool **operator()** (const **ArrayPointer**< T, R > &left, const **ArrayPointer**< T, R > &right) const
- virtual int **compare** (const **ArrayPointer**< T, R > &left, const **ArrayPointer**< T, R > &right) const

6.118.1 Detailed Description

```
template<typename T, typename R = decaf::util::concurrent::atomic::AtomicRefCounter>
class decaf::lang::ArrayPointerComparator< T, R >
```

This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the value of the actual pointer to the array being contained in this **ArrayPointer** (p. 730). This allows for a basic ordering to be acheived in Decaf containers.

Custom implementations are possible where an array of some type has a logical natural ordering such as array of integers where the sum of all ints in the array is used.

6.118.2 Member Function Documentation

6.118.2.1 template<typename T , typename R = decaf::util::concurrent::atomic::AtomicRefCounter> virtual int decaf::lang::ArrayPointerComparator< T, R >::compare (const **ArrayPointer**< T, R > & *left*, const **ArrayPointer**< T, R > & *right*) const [inline, virtual]

References decaf::lang::ArrayPointer< T, REFCOUNTER >::get().

6.118.2.2 template<typename T , typename R = decaf::util::concurrent::atomic::AtomicRefCounter> virtual bool decaf::lang::ArrayPointerComparator< T, R >::operator() (const **ArrayPointer**< T, R > & *left*, const **ArrayPointer**< T, R > & *right*) const [inline, virtual]

References decaf::lang::ArrayPointer< T, REFCOUNTER >::get().

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/ArrayPointer.h`

6.119 decaf::util::concurrent::atomic::AtomicBoolean Class Reference

A boolean value that may be updated atomically.

```
#include <src/main/decaf/util/concurrent/atomic/AtomicBoolean.h>
```

Public Member Functions

- **AtomicBoolean** ()
*Creates a new **AtomicBoolean** (p. 738) whose initial value is false.*
- **AtomicBoolean** (bool initialValue)
*Creates a new **AtomicBoolean** (p. 738) with the initial value.*
- virtual **~AtomicBoolean** ()
- bool **get** () const
*Gets the current value of this **AtomicBoolean** (p. 738).*
- void **set** (bool newValue)
Unconditionally sets to the given value.
- bool **compareAndSet** (bool expect, bool update)
Atomically sets the value to the given updated value if the current value == the expected value.
- bool **getAndSet** (bool newValue)
Atomically sets to the given value and returns the previous value.
- std::string **toString** () const
Returns the String representation of the current value.

6.119.1 Detailed Description

A boolean value that may be updated atomically. An **AtomicBoolean** (p. 738) is used in applications such as atomically updated flags, and cannot be used as a replacement for a Boolean.

6.119.2 Constructor & Destructor Documentation

6.119.2.1 decaf::util::concurrent::atomic::AtomicBoolean::AtomicBoolean ()

Creates a new **AtomicBoolean** (p. 738) whose initial value is false.

6.119.2.2 decaf::util::concurrent::atomic::AtomicBoolean::AtomicBoolean (bool initialValue)

Creates a new **AtomicBoolean** (p. 738) with the initial value.

Parameters:

initialValue - The initial value of this boolean.

6.119.2.3 `virtual decaf::util::concurrent::atomic::AtomicBoolean::~~AtomicBoolean()` [inline, virtual]

6.119.3 Member Function Documentation

6.119.3.1 `bool decaf::util::concurrent::atomic::AtomicBoolean::compareAndSet (bool expect, bool update)`

Atomically sets the value to the given updated value if the current value == the expected value.

Parameters:

expect - the expected value

update - the new value

Returns:

true if successful. False return indicates that the actual value was not equal to the expected value.

6.119.3.2 `bool decaf::util::concurrent::atomic::AtomicBoolean::get () const` [inline]

Gets the current value of this **AtomicBoolean** (p. 738).

Returns:

the currently set value.

6.119.3.3 `bool decaf::util::concurrent::atomic::AtomicBoolean::getAndSet (bool new Value)`

Atomically sets to the given value and returns the previous value.

Parameters:

new Value - the new value

Returns:

the previous value

6.119.3.4 `void decaf::util::concurrent::atomic::AtomicBoolean::set (bool new Value)` [inline]

Unconditionally sets to the given value.

Parameters:

new Value - the new value

6.119.3.5 `std::string decaf::util::concurrent::atomic::AtomicBoolean::toString () const`

Returns the String representation of the current value.

Returns:

the String representation of the current value.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/atomic/AtomicBoolean.h`

6.120 decaf::util::concurrent::atomic::AtomicInteger Class Reference

An int value that may be updated atomically.

#include <src/main/decaf/util/concurrent/atomic/AtomicInteger.h> Inheritance diagram for decaf::util::concurrent::atomic::AtomicInteger:

Public Member Functions

- **AtomicInteger** ()
*Create a new **AtomicInteger** (p. 741) with an initial value of 0.*
- **AtomicInteger** (int initialValue)
*Create a new **AtomicInteger** (p. 741) with the given initial value.*
- virtual **~AtomicInteger** ()
- int **get** () const
Gets the current value.
- void **set** (int newValue)
Sets to the given value.
- int **getAndSet** (int newValue)
Atomically sets to the given value and returns the old value.
- bool **compareAndSet** (int expect, int update)
Atomically sets the value to the given updated value if the current value == the expected value.
- int **getAndIncrement** ()
Atomically increments by one the current value.
- int **getAndDecrement** ()
Atomically decrements by one the current value.
- int **getAndAdd** (int delta)
Atomically adds the given value to the current value.
- int **incrementAndGet** ()
Atomically increments by one the current value.
- int **decrementAndGet** ()
Atomically decrements by one the current value.
- int **addAndGet** (int delta)
Atomically adds the given value to the current value.
- std::string **toString** () const

Returns the String representation of the current value.

- `int intValue () const`

Description copied from class: Number Returns the value of the specified number as an int.

- `long long longValue () const`

Description copied from class: Number Returns the value of the specified number as a long.

- `float floatValue () const`

Description copied from class: Number Returns the value of the specified number as a float.

- `double doubleValue () const`

Description copied from class: Number Returns the value of the specified number as a double.

6.120.1 Detailed Description

An int value that may be updated atomically. An **AtomicInteger** (p. 741) is used in applications such as atomically incremented counters, and cannot be used as a replacement for an `Integer`. However, this class does extend `Number` to allow uniform access by tools and utilities that deal with numerically-based classes.

6.120.2 Constructor & Destructor Documentation

6.120.2.1 decaf::util::concurrent::atomic::AtomicInteger::AtomicInteger ()

Create a new **AtomicInteger** (p. 741) with an initial value of 0.

6.120.2.2 decaf::util::concurrent::atomic::AtomicInteger::AtomicInteger (int *initialValue*)

Create a new **AtomicInteger** (p. 741) with the given initial value.

Parameters:

initialValue - The initial value of this object.

6.120.2.3 virtual decaf::util::concurrent::atomic::AtomicInteger::~~AtomicInteger () [inline, virtual]

6.120.3 Member Function Documentation

6.120.3.1 int decaf::util::concurrent::atomic::AtomicInteger::addAndGet (int *delta*)

Atomically adds the given value to the current value.

Parameters:

delta - the value to add.

Returns:

the updated value.

6.120.3.2 `bool decaf::util::concurrent::atomic::AtomicInteger::compareAndSet (int expect, int update)`

Atomically sets the value to the given updated value if the current value == the expected value.

Parameters:

expect - the expected value

update - the new value

Returns:

true if successful. False return indicates that the actual value was not equal to the expected value.

6.120.3.3 `int decaf::util::concurrent::atomic::AtomicInteger::decrementAndGet ()`

Atomically decrements by one the current value.

Returns:

the updated value.

Referenced by `decaf::util::concurrent::atomic::AtomicRefCounter::release()`.

6.120.3.4 `double decaf::util::concurrent::atomic::AtomicInteger::doubleValue () const [virtual]`

Description copied from class: Number Returns the value of the specified number as a double. This may involve rounding.

Returns:

the numeric value represented by this object after conversion to type double.

Implements `decaf::lang::Number` (p. 2836).

6.120.3.5 `float decaf::util::concurrent::atomic::AtomicInteger::floatValue () const [virtual]`

Description copied from class: Number Returns the value of the specified number as a float. This may involve rounding.

Returns:

the numeric value represented by this object after conversion to type float.

Implements `decaf::lang::Number` (p. 2836).

6.120.3.6 `int decaf::util::concurrent::atomic::AtomicInteger::get () const [inline]`

Gets the current value.

Returns:

the current value.

6.120.3.7 `int decaf::util::concurrent::atomic::AtomicInteger::getAndAdd (int delta)`

Atomically adds the given value to the current value.

Parameters:

delta - The value to add.

Returns:

the previous value.

6.120.3.8 `int decaf::util::concurrent::atomic::AtomicInteger::getAndDecrement ()`

Atomically decrements by one the current value.

Returns:

the previous value.

6.120.3.9 `int decaf::util::concurrent::atomic::AtomicInteger::getAndIncrement ()`

Atomically increments by one the current value.

Returns:

the previous value.

6.120.3.10 `int decaf::util::concurrent::atomic::AtomicInteger::getAndSet (int new Value)`

Atomically sets to the given value and returns the old value.

Parameters:

new Value - the new value.

Returns:

the previous value.

6.120.3.11 `int decaf::util::concurrent::atomic::AtomicInteger::incrementAndGet ()`

Atomically increments by one the current value.

Returns:

the updated value.

Referenced by `decaf::util::concurrent::atomic::AtomicRefCounter::AtomicRefCounter()`.

6.120.3.12 `int decaf::util::concurrent::atomic::AtomicInteger::intValue () const`
`[virtual]`

Description copied from class: `Number` Returns the value of the specified number as an int. This may involve rounding or truncation.

Returns:

the numeric value represented by this object after conversion to type int.

Implements `decaf::lang::Number` (p. 2836).

6.120.3.13 `long long decaf::util::concurrent::atomic::AtomicInteger::longValue ()`
`const [virtual]`

Description copied from class: `Number` Returns the value of the specified number as a long. This may involve rounding or truncation.

Returns:

the numeric value represented by this object after conversion to type long long.

Implements `decaf::lang::Number` (p. 2836).

6.120.3.14 `void decaf::util::concurrent::atomic::AtomicInteger::set (int newValue)`
`[inline]`

Sets to the given value.

Parameters:

newValue - the new value

6.120.3.15 `std::string decaf::util::concurrent::atomic::AtomicInteger::toString ()`
`const`

Returns the String representation of the current value.

Returns:

the String representation of the current value.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/atomic/AtomicInteger.h`

6.121 decaf::util::concurrent::atomic::AtomicRefCounter Class Reference

```
#include <src/main/decaf/util/concurrent/atomic/AtomicRefCounter.h>
```

Inherited by `decaf::lang::ArrayPointer< unsigned char >`, `decaf::lang::Pointer< activemq::threads::TaskRunner >`, `decaf::lang::Pointer< ActiveMQDestination >`, `decaf::lang::Pointer< ActiveMQTransactionContext >`, `decaf::lang::Pointer< BackupTransportPool >`, `decaf::lang::Pointer< BooleanExpression >`, `decaf::lang::Pointer< BrokerError >`, `decaf::lang::Pointer< BrokerId >`, `decaf::lang::Pointer< ByteArrayAdapter >`, `decaf::lang::Pointer< CloseTransportsTask >`, `decaf::lang::Pointer< cms::Destination >`, `decaf::lang::Pointer< commands::ActiveMQDestination >`, `decaf::lang::Pointer< commands::ConsumerId >`, `decaf::lang::Pointer< commands::ConsumerInfo >`, `decaf::lang::Pointer< commands::Message >`, `decaf::lang::Pointer< commands::MessageAck >`, `decaf::lang::Pointer< commands::ProducerInfo >`, `decaf::lang::Pointer< commands::SessionInfo >`, `decaf::lang::Pointer< commands::TransactionId >`, `decaf::lang::Pointer< commands::WireFormatInfo >`, `decaf::lang::Pointer< Comparator< E > >`, `decaf::lang::Pointer< CompositeTaskRunner >`, `decaf::lang::Pointer< ConnectionId >`, `decaf::lang::Pointer< ConnectionInfo >`, `decaf::lang::Pointer< ConsumerId >`, `decaf::lang::Pointer< ConsumerInfo >`, `decaf::lang::Pointer< core::ActiveMQAckHandler >`, `decaf::lang::Pointer< DataStructure >`, `decaf::lang::Pointer< decaf::lang::Runnable >`, `decaf::lang::Pointer< decaf::lang::Thread >`, `decaf::lang::Pointer< Exception >`, `decaf::lang::Pointer< LockHandle >`, `decaf::lang::Pointer< LogManagerInternals >`, `decaf::lang::Pointer< Message >`, `decaf::lang::Pointer< MessageAck >`, `decaf::lang::Pointer< MessageId >`, `decaf::lang::Pointer< ProducerId >`, `decaf::lang::Pointer< ProducerInfo >`, `decaf::lang::Pointer< Properties >`, `decaf::lang::Pointer< Response >`, `decaf::lang::Pointer< ResponseBuilder >`, `decaf::lang::Pointer< SessionId >`, `decaf::lang::Pointer< SessionInfo >`, `decaf::lang::Pointer< Tracked >`, `decaf::lang::Pointer< TransactionId >`, `decaf::lang::Pointer< TransactionState >`, `decaf::lang::Pointer< Transport >`, `decaf::lang::Pointer< TransportListener >`, `decaf::lang::Pointer< URI >`, `decaf::lang::Pointer< URIPool >`, and `decaf::lang::Pointer< wireformat::WireFormat >`.

Public Member Functions

- `AtomicRefCounter ()`
- `AtomicRefCounter (const AtomicRefCounter &other)`
- `virtual ~AtomicRefCounter ()`

Protected Member Functions

- `void swap (AtomicRefCounter &other)`

Swaps this instance's reference counter with the one given, this allows for copy-and-swap semantics of this object.

- `bool release ()`

*Removes a reference to the counter Atomically and returns if the counter has reached zero, once the counter hits zero, the **internal** (p. 144) counter is destroyed and this instance is now considered to be unreferenced.*

6.121.1 Constructor & Destructor Documentation

6.121.1.1 `decaf::util::concurrent::atomic::AtomicRefCounter::AtomicRefCounter ()`
[inline]

6.121.1.2 `decaf::util::concurrent::atomic::AtomicRefCounter::AtomicRefCounter`
`(const AtomicRefCounter & other)` [inline]

References `decaf::util::concurrent::atomic::AtomicInteger::incrementAndGet()`.

6.121.1.3 `virtual`
`decaf::util::concurrent::atomic::AtomicRefCounter::~~AtomicRefCounter`
`()` [inline, virtual]

6.121.2 Member Function Documentation

6.121.2.1 `bool decaf::util::concurrent::atomic::AtomicRefCounter::release ()`
[inline, protected]

Removes a reference to the counter Atomically and returns if the counter has reached zero, once the counter hits zero, the **internal** (p. 144) counter is destroyed and this instance is now considered to be unreferenced.

Returns:

true if the count is now zero.

Reimplemented in `decaf::lang::ArrayPointer< unsigned char >` (p. 735), `decaf::lang::Pointer< MessageAck >` (p. 2951), `decaf::lang::Pointer< BooleanExpression >` (p. 2951), `decaf::lang::Pointer< commands::ConsumerId >` (p. 2951), `decaf::lang::Pointer< BrokerError >` (p. 2951), `decaf::lang::Pointer< Transport >` (p. 2951), `decaf::lang::Pointer< wireformat::WireFormat >` (p. 2951), `decaf::lang::Pointer< commands::WireFormatInfo >` (p. 2951), `decaf::lang::Pointer< CloseTransportsTask >` (p. 2951), `decaf::lang::Pointer< CompositeTaskRunner >` (p. 2951), `decaf::lang::Pointer< ActiveMQTransactionContext >` (p. 2951), `decaf::lang::Pointer< commands::ProducerInfo >` (p. 2951), `decaf::lang::Pointer< Comparator< E > >` (p. 2951), `decaf::lang::Pointer< BrokerId >` (p. 2951), `decaf::lang::Pointer< LogManagerInternals >` (p. 2951), `decaf::lang::Pointer< commands::SessionInfo >` (p. 2951), `decaf::lang::Pointer< Message >` (p. 2951), `decaf::lang::Pointer< URI >` (p. 2951), `decaf::lang::Pointer< DataStructure >` (p. 2951), `decaf::lang::Pointer< activemq::threads::TaskRunner >` (p. 2951), `decaf::lang::Pointer< LockHandle >` (p. 2951), `decaf::lang::Pointer< commands::ActiveMQDestination >` (p. 2951), `decaf::lang::Pointer< ConsumerInfo >` (p. 2951), `decaf::lang::Pointer< ConnectionId >` (p. 2951), `decaf::lang::Pointer< decaf::lang::Runnable >` (p. 2951), `decaf::lang::Pointer< Properties >` (p. 2951), `decaf::lang::Pointer< BackupTransportPool >` (p. 2951), `decaf::lang::Pointer< ProducerInfo >` (p. 2951), `decaf::lang::Pointer< decaf::lang::Thread >` (p. 2951), `decaf::lang::Pointer< MessageId >` (p. 2951), `decaf::lang::Pointer< Response >` (p. 2951), `decaf::lang::Pointer< SessionId >` (p. 2951), `decaf::lang::Pointer< cms::Destination >` (p. 2951), `decaf::lang::Pointer< TransportListener >` (p. 2951), `decaf::lang::Pointer< commands::TransactionId >` (p. 2951), `decaf::lang::Pointer< ActiveMQDestination >` (p. 2951), `decaf::lang::Pointer< ProducerId >` (p. 2951), `decaf::lang::Pointer< ResponseBuilder >` (p. 2951), `decaf::lang::Pointer< SessionInfo >` (p. 2951), `decaf::lang::Pointer< commands::Message >` (p. 2951), `decaf::lang::Pointer<`

Tracked > (p. 2951), decaf::lang::Pointer< ConnectionInfo > (p. 2951), decaf::lang::Pointer< commands::MessageAck > (p. 2951), decaf::lang::Pointer< core::ActiveMQAckHandler > (p. 2951), decaf::lang::Pointer< Exception > (p. 2951), decaf::lang::Pointer< TransactionState > (p. 2951), decaf::lang::Pointer< commands::ConsumerInfo > (p. 2951), decaf::lang::Pointer< ConsumerId > (p. 2951), decaf::lang::Pointer< URIPool > (p. 2951), decaf::lang::Pointer< ByteArrayAdapter > (p. 2951), and decaf::lang::Pointer< TransactionId > (p. 2951).

References decaf::util::concurrent::atomic::AtomicInteger::decrementAndGet().

6.121.2.2 void decaf::util::concurrent::atomic::AtomicRefCounter::swap(AtomicRefCounter & *other*) [inline, protected]

Swaps this instance's reference counter with the one given, this allows for copy-and-swap semantics of this object.

Parameters:

other The value to swap with this one's.

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/atomic/AtomicRefCounter.h

6.122 `decaf::util::concurrent::atomic::AtomicReference< T >` Class Template Reference

An Pointer reference that may be updated atomically.

```
#include <src/main/decaf/util/concurrent/atomic/AtomicReference.h>
```

Public Member Functions

- `AtomicReference ()`
- `AtomicReference (T *value)`
- `virtual ~AtomicReference ()`
- `T * get () const`

Gets the Current Value.

- `void set (T *newValue)`

Sets the Current value of this Reference.

- `bool compareAndSet (T *expect, T *update)`

Atomically sets the value to the given updated value if the current value == the expected value.

- `T * getAndSet (T *newValue)`

Atomically sets to the given value and returns the old value.

- `std::string toString () const`

Returns the String representation of the current value.

6.122.1 Detailed Description

```
template<typename T> class decaf::util::concurrent::atomic::AtomicReference< T >
```

An Pointer reference that may be updated atomically.

6.122.2 Constructor & Destructor Documentation

6.122.2.1 `template<typename T >
decaf::util::concurrent::atomic::AtomicReference< T
>::AtomicReference () [inline]`

6.122.2.2 `template<typename T >
decaf::util::concurrent::atomic::AtomicReference< T
>::AtomicReference (T * value) [inline]`

6.122.2.3 `template<typename T > virtual
decaf::util::concurrent::atomic::AtomicReference< T
>::~~AtomicReference () [inline, virtual]`

6.122.3 Member Function Documentation

6.122.3.1 `template<typename T > bool
decaf::util::concurrent::atomic::AtomicReference< T
>::compareAndSet (T * expect, T * update) [inline]`

Atomically sets the value to the given updated value if the current value == the expected value.

Parameters:

expect - the expected value

update - the new value

Returns:

true if successful. False return indicates that the actual value was not equal to the expected value.

6.122.3.2 `template<typename T > T*
decaf::util::concurrent::atomic::AtomicReference< T >::get
() const [inline]`

Gets the Current Value.

Returns:

the current value of this Reference.

6.122.3.3 `template<typename T > T*
decaf::util::concurrent::atomic::AtomicReference< T
>::getAndSet (T * new Value) [inline]`

Atomically sets to the given value and returns the old value.

Parameters:

new Value- the new value

Returns:

the previous value.

6.122.3.4 `template<typename T > void
decaf::util::concurrent::atomic::AtomicReference< T >::set
(T * new Value) [inline]`

Sets the Current value of this Reference.

Parameters:

new Value The new Value of this Reference.

6.122.3.5 `template<typename T > std::string
decaf::util::concurrent::atomic::AtomicReference< T
>::toString () const [inline]`

Returns the String representation of the current value.

Returns:

string representation of the current value.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/atomic/AtomicReference.h`

6.123 activemq::transport::failover::BackupTransport Class Reference

#include <src/main/activemq/transport/failover/BackupTransport.h> Inheritance diagram for activemq::transport::failover::BackupTransport:

Public Member Functions

- **BackupTransport** (**BackupTransportPool** *failover)
- virtual **~BackupTransport** ()
- **decaf::net::URI** **getUri** () const
Gets the URI assigned to this Backup.
- void **setUri** (const **decaf::net::URI** &uri)
*Sets the URI assigned to this **Transport** (p. 3883).*
- const **Pointer**< **Transport** > & **getTransport** ()
*Gets the currently held **transport** (p. 97).*
- void **setTransport** (const **Pointer**< **Transport** > &transport)
*Sets the held **transport** (p. 97), if not NULL then start to listen for **exceptions** (p. 92) from the held **transport** (p. 97).*
- virtual void **onException** (const **decaf::lang::Exception** &ex)
*Event handler for an exception from a command **transport** (p. 97).*
- bool **isClosed** () const
*Has the **Transport** (p. 3883) been shutdown and no longer usable.*
- void **setClosed** (bool value)
*Sets the closed flag on this **Transport** (p. 3883).*

6.123.1 Constructor & Destructor Documentation

- 6.123.1.1 **activemq::transport::failover::BackupTransport::BackupTransport** (**BackupTransportPool** * failover)
- 6.123.1.2 virtual **activemq::transport::failover::BackupTransport::~~BackupTransport** ()
[virtual]

6.123.2 Member Function Documentation

- 6.123.2.1 const **Pointer**<**Transport**>& **activemq::transport::failover::BackupTransport::getTransport** () [inline]

Gets the currently held **transport** (p. 97).

Returns:

pointer to the held **transport** (p. 97) or NULL if not set.

6.123.2.2 **decaf::net::URI activemq::transport::failover::BackupTransport::getUri () const** [inline]

Gets the URI assigned to this Backup.

Returns:

the assigned URI

6.123.2.3 **bool activemq::transport::failover::BackupTransport::isClosed () const** [inline]

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

6.123.2.4 **virtual void activemq::transport::failover::BackupTransport::onException (const decaf::lang::Exception & *ex*)** [virtual]

Event handler for an exception from a command **transport** (p. 97). The **BackupTransport** (p. 752) closes its internal **Transport** (p. 3883) when an exception is received and returns the URI to the pool of URIs to attempt connections to.

Parameters:

ex The exception that was passed to this listener to handle.

Implements **activemq::transport::TransportListener** (p. 3901).

6.123.2.5 **void activemq::transport::failover::BackupTransport::setClosed (bool *value*)** [inline]

Sets the closed flag on this **Transport** (p. 3883).

Parameters:

value - true for closed.

6.123.2.6 **void activemq::transport::failover::BackupTransport::setTransport (const Pointer< Transport > & *transport*)** [inline]

Sets the held **transport** (p. 97), if not NULL then start to listen for **exceptions** (p. 92) from the held **transport** (p. 97).

Parameters:

transport (p. 97) The **transport** (p. 97) to hold.

6.123.2.7 void activemq::transport::failover::BackupTransport::setUri (const decaf::net::URI & *uri*) [inline]

Sets the URI assigned to this **Transport** (p. 3883).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/failover/**BackupTransport.h**

6.124 activemq::transport::failover::BackupTransportPool Class Reference

#include <src/main/activemq/transport/failover/BackupTransportPool.h> Inheritance diagram for activemq::transport::failover::BackupTransportPool:

Public Member Functions

- **BackupTransportPool** (const **Pointer**< **CompositeTaskRunner** > &taskRunner, const **Pointer**< **CloseTransportsTask** > &closeTask, const **Pointer**< **URIPool** > &uriPool)
- **BackupTransportPool** (int backupPoolSize, const **Pointer**< **CompositeTaskRunner** > &taskRunner, const **Pointer**< **CloseTransportsTask** > &closeTask, const **Pointer**< **URIPool** > &uriPool)
- virtual ~**BackupTransportPool** ()
- virtual bool **isPending** () const
Return true if we don't currently have enough Connected Transports.
- **Pointer**< **BackupTransport** > **getBackup** ()
*Get a Connected **Transport** (p. 3883) from the pool of Backups if any are present, otherwise it return a NULL Pointer.*
- virtual bool **iterate** ()
Connect to a Backup Broker if we haven't already connected to the max number of Backups.
- int **getBackupPoolSize** () const
Gets the Max number of Backups this Task will create.
- void **setBackupPoolSize** (int size)
Sets the Max number of Backups this Task will create.
- bool **isEnabled** () const
*Gets if the backup **Transport** (p. 3883) Pool has been enabled or not, when not enabled no backups are created and any that were are destroyed.*
- void **setEnabled** (bool value)
*Sets if this Backup **Transport** (p. 3883) Pool is enabled.*

Friends

- class **BackupTransport**

6.124.1 Constructor & Destructor Documentation

6.124.1.1 `activemq::transport::failover::BackupTransportPool::BackupTransportPool (const Pointer< CompositeTaskRunner > & taskRunner, const Pointer< CloseTransportsTask > & closeTask, const Pointer< URIPool > & uriPool)`

6.124.1.2 `activemq::transport::failover::BackupTransportPool::BackupTransportPool (int backupPoolSize, const Pointer< CompositeTaskRunner > & taskRunner, const Pointer< CloseTransportsTask > & closeTask, const Pointer< URIPool > & uriPool)`

6.124.1.3 `virtual
activemq::transport::failover::BackupTransportPool::~~BackupTransportPool
() [virtual]`

6.124.2 Member Function Documentation

6.124.2.1 `Pointer<BackupTransport> ac-
tivemq::transport::failover::BackupTransportPool::getBackup
()`

Get a Connected **Transport** (p. 3883) from the pool of Backups if any are present, otherwise it return a NULL Pointer.

Returns:

Pointer to a Connected **Transport** (p. 3883) or NULL

6.124.2.2 `int ac-
tivemq::transport::failover::BackupTransportPool::getBackupPoolSize ()
const [inline]`

Gets the Max number of Backups this Task will create.

Returns:

the max number of active BackupTransports that will be created.

6.124.2.3 `bool activemq::transport::failover::BackupTransportPool::isEnabled ()
const [inline]`

Gets if the backup **Transport** (p. 3883) Pool has been enabled or not, when not enabled no backups are created and any that were are destroyed.

Returns:

true if enable.

6.124.2.4 `virtual bool activemq::transport::failover::BackupTransportPool::isPending () const` [virtual]

Return true if we don't currently have enough Connected Transports.

Implements `activemq::threads::CompositeTask` (p. 1221).

6.124.2.5 `virtual bool activemq::transport::failover::BackupTransportPool::iterate ()` [virtual]

Connect to a Backup Broker if we haven't already connected to the max number of Backups.

Implements `activemq::threads::Task` (p. 3734).

6.124.2.6 `void activemq::transport::failover::BackupTransportPool::setBackupPoolSize (int size)` [inline]

Sets the Max number of Backups this Task will create.

Parameters:

size - the max number of active BackupTransports that will be created.

6.124.2.7 `void activemq::transport::failover::BackupTransportPool::setEnabled (bool value)`

Sets if this Backup **Transport** (p. 3883) Pool is enabled. When not enabled no Backups are created and any that were are destroyed.

Parameters:

value - true to enable backup creation, false to disable.

6.124.3 Friends And Related Function Documentation

6.124.3.1 `friend class BackupTransport` [friend]

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/failover/BackupTransportPool.h`

6.125 activemq::commands::BaseCommand Class Reference

#include <src/main/activemq/commands/BaseCommand.h> Inheritance diagram for activemq::commands::BaseCommand:

Public Member Functions

- **BaseCommand** ()
- virtual **~BaseCommand** ()
- virtual void **setCommandId** (int id)
*Sets the **Command** (p. 1194) Id of this **Message** (p. 2516).*
- virtual int **getCommandId** () const
*Gets the **Command** (p. 1194) Id of this **Message** (p. 2516).*
- virtual void **setResponseRequired** (const bool required)
*Set if this **Message** (p. 2516) requires a **Response** (p. 3285).*
- virtual bool **isResponseRequired** () const
*Is a **Response** (p. 3285) required for this **Command** (p. 1194).*
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual bool **isConnectionInfo** () const
- virtual bool **isConsumerInfo** () const
- virtual bool **isBrokerInfo** () const
- virtual bool **isMessage** () const
- virtual bool **isMessageAck** () const
- virtual bool **isKeepAliveInfo** () const
- virtual bool **isMessageDispatch** () const
- virtual bool **isMessageDispatchNotification** () const
- virtual bool **isProducerAck** () const
- virtual bool **isProducerInfo** () const
- virtual bool **isResponse** () const
- virtual bool **isRemoveInfo** () const
- virtual bool **isRemoveSubscriptionInfo** () const
- virtual bool **isShutdownInfo** () const
- virtual bool **isTransactionInfo** () const
- virtual bool **isWireFormatInfo** () const

6.125.1 Constructor & Destructor Documentation

6.125.1.1 `activemq::commands::BaseCommand::BaseCommand () [inline]`

6.125.1.2 `virtual activemq::commands::BaseCommand::~~BaseCommand () [inline, virtual]`

6.125.2 Member Function Documentation

6.125.2.1 `virtual void activemq::commands::BaseCommand::copyDataStructure (const DataStructure * src) [inline, virtual]`

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

`src` - Source Object

Reimplemented in `activemq::commands::ActiveMQBlobMessage` (p. 205), `activemq::commands::ActiveMQBytesMessage` (p. 237), `activemq::commands::ActiveMQMapMessage` (p. 364), `activemq::commands::ActiveMQMessage` (p. 399), `activemq::commands::ActiveMQObjectMessage` (p. 444), `activemq::commands::ActiveMQStreamMessage` (p. 540), `activemq::commands::ActiveMQTextMessage` (p. 664), `activemq::commands::BrokerError` (p. 864), `activemq::commands::BrokerInfo` (p. 898), `activemq::commands::ConnectionControl` (p. 1268), `activemq::commands::ConnectionError` (p. 1297), `activemq::commands::ConnectionInfo` (p. 1357), `activemq::commands::ConsumerControl` (p. 1402), `activemq::commands::ConsumerInfo` (p. 1461), `activemq::commands::ControlCommand` (p. 1494), `activemq::commands::DataArrayResponse` (p. 1529), `activemq::commands::DataResponse` (p. 1584), `activemq::commands::DestinationInfo` (p. 1728), `activemq::commands::ExceptionResponse` (p. 1840), `activemq::commands::FlushCommand` (p. 1938), `activemq::commands::IntegerResponse` (p. 2092), `activemq::commands::KeepAliveInfo` (p. 2267), `activemq::commands::Message` (p. 2521), `activemq::commands::MessageAck` (p. 2560), `activemq::commands::MessageDispatch` (p. 2595), `activemq::commands::MessageDispatchNotification` (p. 2631), `activemq::commands::MessagePull` (p. 2740), `activemq::commands::ProducerAck` (p. 3037), `activemq::commands::ProducerInfo` (p. 3097), `activemq::commands::RemoveInfo` (p. 3195), `activemq::commands::RemoveSubscriptionInfo` (p. 3223), `activemq::commands::ReplayCommand` (p. 3252), `activemq::commands::Response` (p. 3286), `activemq::commands::SessionInfo` (p. 3408), `activemq::commands::ShutdownInfo` (p. 3471), `activemq::commands::TransactionInfo` (p. 3848), and `activemq::commands::WireFormatInfo` (p. 3985).

References `getCommandId()`, and `isResponseRequired()`.

6.125.2.2 `virtual bool activemq::commands::BaseCommand::equals (const DataStructure * value) const [inline, virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 206), **activemq::commands::ActiveMQBytesMessage** (p. 237), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQMessageTemplate< T >** (p. 429), **activemq::commands::ActiveMQObjectMessage** (p. 444), **activemq::commands::ActiveMQStreamMessage** (p. 541), **activemq::commands::ActiveMQTextMessage** (p. 664), **activemq::commands::BrokerInfo** (p. 898), **activemq::commands::ConnectionControl** (p. 1269), **activemq::commands::ConnectionError** (p. 1297), **activemq::commands::ConnectionInfo** (p. 1357), **activemq::commands::ConsumerControl** (p. 1402), **activemq::commands::ConsumerInfo** (p. 1461), **activemq::commands::ControlCommand** (p. 1494), **activemq::commands::DataArrayResponse** (p. 1529), **activemq::commands::DataResponse** (p. 1584), **activemq::commands::DestinationInfo** (p. 1728), **activemq::commands::ExceptionResponse** (p. 1840), **activemq::commands::FlushCommand** (p. 1938), **activemq::commands::IntegerResponse** (p. 2092), **activemq::commands::KeepAliveInfo** (p. 2267), **activemq::commands::Message** (p. 2521), **activemq::commands::MessageAck** (p. 2560), **activemq::commands::MessageDispatch** (p. 2595), **activemq::commands::MessageDispatchNotification** (p. 2631), **activemq::commands::MessagePull** (p. 2740), **activemq::commands::ProducerAck** (p. 3037), **activemq::commands::ProducerInfo** (p. 3097), **activemq::commands::RemoveInfo** (p. 3195), **activemq::commands::RemoveSubscriptionInfo** (p. 3223), **activemq::commands::ReplayCommand** (p. 3252), **activemq::commands::Response** (p. 3286), **activemq::commands::SessionInfo** (p. 3408), **activemq::commands::ShutdownInfo** (p. 3471), **activemq::commands::TransactionInfo** (p. 3848), **activemq::commands::WireFormatInfo** (p. 3985), **activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::Message >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >** (p. 429), and **activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >** (p. 429).

References **activemq::commands::BaseDataStructure::equals()**.

6.125.2.3 virtual int activemq::commands::BaseCommand::getCommandId () const [inline, virtual]

Gets the **Command** (p. 1194) Id of this **Message** (p. 2516).

Returns:

Command (p. 1194) Id

Implements **activemq::commands::Command** (p. 1195).

Referenced by **copyDataStructure()**.

6.125.2.4 `virtual bool activemq::commands::BaseCommand::isBrokerInfo () const`
[inline, virtual]

Implements `activemq::commands::Command` (p. 1195).

Reimplemented in `activemq::commands::BrokerInfo` (p. 900).

6.125.2.5 `virtual bool activemq::commands::BaseCommand::isConnectionInfo ()`
`const` [inline, virtual]

Implements `activemq::commands::Command` (p. 1195).

Reimplemented in `activemq::commands::ConnectionInfo` (p. 1358).

6.125.2.6 `virtual bool activemq::commands::BaseCommand::isConsumerInfo ()`
`const` [inline, virtual]

Implements `activemq::commands::Command` (p. 1195).

Reimplemented in `activemq::commands::ConsumerInfo` (p. 1463).

6.125.2.7 `virtual bool activemq::commands::BaseCommand::isKeepAliveInfo ()`
`const` [inline, virtual]

Implements `activemq::commands::Command` (p. 1195).

Reimplemented in `activemq::commands::KeepAliveInfo` (p. 2268).

6.125.2.8 `virtual bool activemq::commands::BaseCommand::isMessage () const`
[inline, virtual]

Implements `activemq::commands::Command` (p. 1195).

Reimplemented in `activemq::commands::Message` (p. 2527).

6.125.2.9 `virtual bool activemq::commands::BaseCommand::isMessageAck () const`
[inline, virtual]

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::MessageAck` (p. 2562).

6.125.2.10 `virtual bool activemq::commands::BaseCommand::isMessageDispatch ()`
`const` [inline, virtual]

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::MessageDispatch` (p. 2596).

6.125.2.11 `virtual bool activemq::commands::BaseCommand::isMessageDispatchNotification () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::MessageDispatchNotification` (p. 2632).

6.125.2.12 `virtual bool activemq::commands::BaseCommand::isProducerAck () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::ProducerAck` (p. 3038).

6.125.2.13 `virtual bool activemq::commands::BaseCommand::isProducerInfo () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::ProducerInfo` (p. 3098).

6.125.2.14 `virtual bool activemq::commands::BaseCommand::isRemoveInfo () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::RemoveInfo` (p. 3196).

6.125.2.15 `virtual bool activemq::commands::BaseCommand::isRemoveSubscriptionInfo () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::RemoveSubscriptionInfo` (p. 3224).

6.125.2.16 `virtual bool activemq::commands::BaseCommand::isResponse () const [inline, virtual]`

Implements `activemq::commands::Command` (p. 1196).

Reimplemented in `activemq::commands::Response` (p. 3287).

6.125.2.17 `virtual bool activemq::commands::BaseCommand::isResponseRequired () const [inline, virtual]`

Is a **Response** (p. 3285) required for this **Command** (p. 1194).

Returns:

true if a response is required.

Implements **activemq::commands::Command** (p. 1197).

Referenced by `copyDataStructure()`.

6.125.2.18 `virtual bool activemq::commands::BaseCommand::isShutdownInfo ()`
`const [inline, virtual]`

Implements **activemq::commands::Command** (p. 1197).

Reimplemented in **activemq::commands::ShutdownInfo** (p. 3472).

6.125.2.19 `virtual bool activemq::commands::BaseCommand::isTransactionInfo ()`
`const [inline, virtual]`

Implements **activemq::commands::Command** (p. 1197).

Reimplemented in **activemq::commands::TransactionInfo** (p. 3849).

6.125.2.20 `virtual bool activemq::commands::BaseCommand::isWireFormatInfo ()`
`const [inline, virtual]`

Implements **activemq::commands::Command** (p. 1197).

Reimplemented in **activemq::commands::WireFormatInfo** (p. 3989).

6.125.2.21 `virtual void activemq::commands::BaseCommand::setCommandId (int`
`id) [inline, virtual]`

Sets the **Command** (p. 1194) Id of this **Message** (p. 2516).

Parameters:

id **Command** (p. 1194) Id

Implements **activemq::commands::Command** (p. 1197).

6.125.2.22 `virtual void activemq::commands::BaseCommand::setResponseRequired`
`(const bool required) [inline, virtual]`

Set if this **Message** (p. 2516) requires a **Response** (p. 3285).

Parameters:

required true if response is required

Implements **activemq::commands::Command** (p. 1197).

6.125.2.23 `virtual std::string activemq::commands::BaseCommand::toString ()`
`const [inline, virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Implements **activemq::commands::Command** (p. 1198).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 208), **activemq::commands::ActiveMQBytesMessage** (p. 244), **activemq::commands::ActiveMQMapMessage** (p. 372), **activemq::commands::ActiveMQMessage** (p. 400), **activemq::commands::ActiveMQObjectMessage** (p. 445), **activemq::commands::ActiveMQStreamMessage** (p. 547), **activemq::commands::ActiveMQTextMessage** (p. 666), **activemq::commands::BrokerInfo** (p. 901), **activemq::commands::ConnectionControl** (p. 1270), **activemq::commands::ConnectionError** (p. 1298), **activemq::commands::ConnectionInfo** (p. 1359), **activemq::commands::ConsumerControl** (p. 1404), **activemq::commands::ConsumerInfo** (p. 1464), **activemq::commands::ControlCommand** (p. 1495), **activemq::commands::DataArrayResponse** (p. 1530), **activemq::commands::DataResponse** (p. 1585), **activemq::commands::DestinationInfo** (p. 1730), **activemq::commands::ExceptionResponse** (p. 1841), **activemq::commands::FlushCommand** (p. 1939), **activemq::commands::IntegerResponse** (p. 2093), **activemq::commands::KeepAliveInfo** (p. 2268), **activemq::commands::Message** (p. 2530), **activemq::commands::MessageAck** (p. 2563), **activemq::commands::MessageDispatch** (p. 2597), **activemq::commands::MessageDispatchNotification** (p. 2633), **activemq::commands::MessagePull** (p. 2742), **activemq::commands::ProducerAck** (p. 3038), **activemq::commands::ProducerInfo** (p. 3099), **activemq::commands::RemoveInfo** (p. 3196), **activemq::commands::RemoveSubscriptionInfo** (p. 3225), **activemq::commands::ReplayCommand** (p. 3253), **activemq::commands::Response** (p. 3287), **activemq::commands::SessionInfo** (p. 3409), **activemq::commands::ShutdownInfo** (p. 3472), **activemq::commands::TransactionInfo** (p. 3849), and **activemq::commands::WireFormatInfo** (p. 3991).

References **activemq::commands::BaseDataStructure::toString()**.

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/BaseCommand.h`

6.126 activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 765).

#include <src/main/activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.126.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 765).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.126.2 Constructor & Destructor Documentation

6.126.2.1 `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::BaseCommandMarshaller()` `[inline]`

6.126.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::~~BaseCommandMarshaller()` `[inline, virtual]`

6.126.3 Member Function Documentation

6.126.3.1 `virtual void` `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut)` `throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 210), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 250), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 375), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 402), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 447), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 553), `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 668), `activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller` (p. 905), `activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller` (p. 1273), `activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller` (p. 1305), `activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller` (p. 1366), `activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller` (p. 1411), `activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller` (p. 1473), `activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller` (p. 1502), `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1536), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1599), `activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller` (p. 1737), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1851), `activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller` (p. 1949), `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2103), `activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller` (p. 2278), `activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller` (p. 2574), `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller` (p. 2611), `activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller`

(p. 2644), `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2699), `activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller` (p. 2753), `activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller` (p. 3049), `activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller` (p. 3118), `activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller` (p. 3207), `activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller` (p. 3232), `activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller` (p. 3267), `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311), `activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller` (p. 3424), `activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller` (p. 3490), and `activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller` (p. 3860).

6.126.3.2 virtual void `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::looseUnmarshal`
 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 211), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 251), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 376), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 403), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 448), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 554), `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 669), `activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller` (p. 906), `activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller` (p. 1274), `activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller` (p. 1306), `activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller` (p. 1367), `activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller` (p. 1412), `activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller` (p. 1474), `activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller` (p. 1503), `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1537), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1600), `activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller` (p. 1738), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1852), `activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller` (p. 1950), `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2104), `activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller` (p. 2279),

activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (p. 2575), activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller (p. 2612), activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller (p. 2645), activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2699), activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2754), activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3050), activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3119), activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3208), activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller (p. 3233), activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller (p. 3268), activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3312), activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3425), activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3491), and activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3861).

6.126.3.3 virtual int activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller** (p. 211), **activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller** (p. 251), **activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller** (p. 376), **activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller** (p. 403), **activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller** (p. 448), **activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller** (p. 554), **activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller** (p. 669), **activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller** (p. 906), **activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller** (p. 1274), **activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller** (p. 1306), **activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller** (p. 1367), **activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller** (p. 1412), **activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller** (p. 1474), **activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller** (p. 1503), **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller** (p. 1537),

activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1600),
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1738), **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller** (p. 1852),
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1950),
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2104),
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2279),
activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (p. 2575), **activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller** (p. 2612), **activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller** (p. 2645),
activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2700),
activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2754),
activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3050),
activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3119),
activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3208), **activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller** (p. 3233),
activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller (p. 3268), **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p. 3312),
activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3425), **activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller** (p. 3491), and
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3861).

6.126.3.4 virtual void activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::tightMarshal2
 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller** (p. 211), **activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller** (p. 251), **activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller** (p. 376), **activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller** (p. 403), **activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller** (p. 448), **activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller** (p. 554), **activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller** (p. 669), **activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller** (p. 906), **activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller** (p. 1274), **activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller** (p. 1306), **activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller** (p. 1367),

activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1412),
 activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1474),
 activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1503),
 activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1538),
 activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1601),
 activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1738),
 activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1853),
 activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1950),
 activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2105),
 activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2279),
 activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (p. 2575),
 activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller (p. 2612),
 activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller
 (p. 2645),
 activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2701),
 activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2754),
 activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3050),
 activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3119),
 activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3208),
 activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller
 (p. 3233),
 activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller
 (p. 3268),
 activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3313),
 activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3425),
 activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3491), and
 activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3861).

6.126.3.5 virtual void ac-
 tivemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller::tightUnmarshal
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller`
 (p. 212), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller`
 (p. 252), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller`
 (p. 377), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller`
 (p. 404), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller`
 (p. 449), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller`
 (p. 555), `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller`

(p. 670), `activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller` (p. 907), `activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller` (p. 1275), `activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller` (p. 1307), `activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller` (p. 1368), `activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller` (p. 1413), `activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller` (p. 1475), `activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller` (p. 1504), `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1538), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1601), `activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller` (p. 1739), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1853), `activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller` (p. 1951), `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2105), `activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller` (p. 2280), `activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller` (p. 2576), `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller` (p. 2613), `activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller` (p. 2646), `activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2701), `activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller` (p. 2755), `activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller` (p. 3051), `activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller` (p. 3120), `activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller` (p. 3209), `activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller` (p. 3234), `activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller` (p. 3269), `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3314), `activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller` (p. 3426), `activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller` (p. 3492), and `activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller` (p. 3862).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h`

6.127 activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 772).

#include <src/main/activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.127.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 772).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.127.2 Constructor & Destructor Documentation

6.127.2.1 `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::BaseCommandMarshaller()` [inline]

6.127.2.2 `virtual activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::~~BaseCommandMarshaller()` [inline, virtual]

6.127.3 Member Function Documentation

6.127.3.1 `virtual void activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller` (p. 218), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller` (p. 258), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller` (p. 383), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller` (p. 410), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller` (p. 455), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller` (p. 561), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller` (p. 672), `activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller` (p. 909), `activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller` (p. 1277), `activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller` (p. 1309), `activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller` (p. 1370), `activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller` (p. 1415), `activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller` (p. 1477), `activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller` (p. 1506), `activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1540), `activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller` (p. 1603), `activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller` (p. 1741), `activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller` (p. 1859), `activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller` (p. 1953), `activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller` (p. 2107), `activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller` (p. 2282), `activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller` (p. 2578), `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller` (p. 2619), `activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller`

(p. 2648), [activemq::wireformat::openwire::marshal::v4::MessageMarshaller](#) (p. 2709), [activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller](#) (p. 2757), [activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller](#) (p. 3045), [activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller](#) (p. 3102), [activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller](#) (p. 3219), [activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller](#) (p. 3248), [activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller](#) (p. 3255), [activemq::wireformat::openwire::marshal::v4::ResponseMarshaller](#) (p. 3296), [activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller](#) (p. 3432), [activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller](#) (p. 3494), and [activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller](#) (p. 3868).

6.127.3.2 virtual void activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataIn* - BinaryReader that provides that data source

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements [activemq::wireformat::openwire::marshal::DataStreamMarshaller](#) (p. 1631).

Reimplemented in [activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller](#) (p. 219), [activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller](#) (p. 259), [activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller](#) (p. 384), [activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller](#) (p. 411), [activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller](#) (p. 456), [activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller](#) (p. 562), [activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller](#) (p. 673), [activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller](#) (p. 910), [activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller](#) (p. 1278), [activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller](#) (p. 1310), [activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller](#) (p. 1371), [activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller](#) (p. 1416), [activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller](#) (p. 1478), [activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller](#) (p. 1507), [activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller](#) (p. 1541), [activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller](#) (p. 1604), [activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller](#) (p. 1742), [activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller](#) (p. 1860), [activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller](#) (p. 1954), [activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller](#) (p. 2108), [activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller](#) (p. 2283),

`activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller` (p. 2579), `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller` (p. 2620), `activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller` (p. 2649), `activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2709), `activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller` (p. 2758), `activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller` (p. 3046), `activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller` (p. 3103), `activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller` (p. 3220), `activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller` (p. 3249), `activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller` (p. 3256), `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297), `activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller` (p. 3433), `activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller` (p. 3495), and `activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller` (p. 3869).

6.127.3.3 `virtual int activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller` (p. 219), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller` (p. 259), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller` (p. 384), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller` (p. 411), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller` (p. 456), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller` (p. 562), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller` (p. 673), `activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller` (p. 910), `activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller` (p. 1278), `activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller` (p. 1310), `activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller` (p. 1371), `activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller` (p. 1416), `activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller` (p. 1478), `activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller` (p. 1507), `activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1541),

activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1604),
 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1742),
 activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1860),
 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1954),
 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2108),
 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2283),
 activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (p. 2579),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (p. 2620),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller
 (p. 2649), activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2710),
 activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2758),
 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3046),
 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3103),
 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3220),
 activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller
 (p. 3249), activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller
 (p. 3256), activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3297),
 activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3433),
 activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3495), and
 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3869).

6.127.3.4 virtual void `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::tightMarshal2`
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataOutputStream * *dataOut*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1645).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller`
 (p. 219), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller`
 (p. 259), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller`
 (p. 384), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller`
 (p. 411), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller`
 (p. 456), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller`
 (p. 562), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller`
 (p. 673), `activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller` (p. 910),
`activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller` (p. 1278),
`activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller` (p. 1310),
`activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller` (p. 1371),

activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1416),
 activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1478),
 activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1507),
 activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1542),
 activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1605),
 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1742),
 activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1861),
 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1954),
 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2109),
 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2283),
 activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (p. 2579),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (p. 2620),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller
 (p. 2649), activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2711),
 activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2758),
 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3046),
 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3103),
 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3220),
 activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller
 (p. 3249), activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller
 (p. 3256), activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3298),
 activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3433),
 activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3495), and
 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3869).

6.127.3.5 virtual void ac-
 tivemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller::tightUnmarshal
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller`
 (p. 220), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller`
 (p. 260), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller`
 (p. 385), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller`
 (p. 412), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller`
 (p. 457), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller`
 (p. 563), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller`

(p. 674), [activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller](#) (p. 911), [activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller](#) (p. 1279), [activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller](#) (p. 1311), [activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller](#) (p. 1372), [activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller](#) (p. 1417), [activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller](#) (p. 1479), [activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller](#) (p. 1508), [activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller](#) (p. 1542), [activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller](#) (p. 1605), [activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller](#) (p. 1743), [activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller](#) (p. 1861), [activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller](#) (p. 1955), [activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller](#) (p. 2109), [activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller](#) (p. 2284), [activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller](#) (p. 2580), [activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller](#) (p. 2621), [activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller](#) (p. 2650), [activemq::wireformat::openwire::marshal::v4::MessageMarshaller](#) (p. 2711), [activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller](#) (p. 2759), [activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller](#) (p. 3047), [activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller](#) (p. 3104), [activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller](#) (p. 3221), [activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller](#) (p. 3250), [activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller](#) (p. 3257), [activemq::wireformat::openwire::marshal::v4::ResponseMarshaller](#) (p. 3299), [activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller](#) (p. 3434), [activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller](#) (p. 3496), and [activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller](#) (p. 3870).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h`

6.128 activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 779).

#include <src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.128.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 779).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.128.2 Constructor & Destructor Documentation

6.128.2.1 `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::BaseCommandMarshaller()` [inline]

6.128.2.2 `virtual activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::~~BaseCommandMarshaller()` [inline, virtual]

6.128.3 Member Function Documentation

6.128.3.1 `virtual void activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 214), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 254), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 379), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 406), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 451), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 557), `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 676), `activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 913), `activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1281), `activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1313), `activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1374), `activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1419), `activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller` (p. 1481), `activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller` (p. 1510), `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1544), `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1607), `activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller` (p. 1745), `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1863), `activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller` (p. 1957), `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2111), `activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller` (p. 2290), `activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller` (p. 2582), `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller` (p. 2623), `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller`

(p. 2652), `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2714), `activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller` (p. 2761), `activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller` (p. 3061), `activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller` (p. 3110), `activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller` (p. 3211), `activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller` (p. 3228), `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller` (p. 3259), `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316), `activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller` (p. 3420), `activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller` (p. 3482), and `activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller` (p. 3856).

6.128.3.2 `virtual void activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 215), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 255), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 380), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 407), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 452), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 558), `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 677), `activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 914), `activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1282), `activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1314), `activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1375), `activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1420), `activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller` (p. 1482), `activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller` (p. 1511), `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1545), `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1608), `activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller` (p. 1746), `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1864), `activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller` (p. 1958), `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2112), `activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller` (p. 2291),

activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller (p. 2583), activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller (p. 2624), activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller (p. 2653), activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2714), activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2762), activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3062), activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3111), activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3212), activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller (p. 3229), activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller (p. 3260), activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3317), activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3421), activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3483), and activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3857).

6.128.3.3 virtual int activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller** (p. 215), **activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller** (p. 255), **activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller** (p. 380), **activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller** (p. 407), **activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller** (p. 452), **activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller** (p. 558), **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller** (p. 677), **activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller** (p. 914), **activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller** (p. 1282), **activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller** (p. 1314), **activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller** (p. 1375), **activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller** (p. 1420), **activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller** (p. 1482), **activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller** (p. 1511), **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1545),

activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1608),
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1746), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1864),
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1958),
activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2112),
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2291),
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller (p. 2583), **activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller** (p. 2624), **activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller** (p. 2653),
activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2715),
activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2762),
activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3062),
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3111),
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3212), **activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller** (p. 3229),
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller (p. 3260), **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3317),
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3421), **activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller** (p. 3483), and
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3857).

6.128.3.4 virtual void activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::tightMarshal2
 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller** (p. 215), **activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller** (p. 255), **activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller** (p. 380), **activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller** (p. 407), **activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller** (p. 452), **activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller** (p. 558), **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller** (p. 677), **activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller** (p. 914), **activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller** (p. 1282), **activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller** (p. 1314), **activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller** (p. 1375),

activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (p. 1420),
 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1482),
 activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1511),
 activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1546),
 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1609),
 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1746),
 activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1865),
 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1958),
 activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2113),
 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2291),
 activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller (p. 2583),
 activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller (p. 2624),
 activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller
 (p. 2653),
 activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2716),
 activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2762),
 activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3062),
 activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3111),
 activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3212),
 activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller
 (p. 3229),
 activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller
 (p. 3260),
 activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3318),
 activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3421),
 activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3483),
 and
 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3857).

6.128.3.5 virtual void `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller::tightUnmarshal`
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller`
 (p. 216), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller`
 (p. 256), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller`
 (p. 381), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller`
 (p. 408), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller`
 (p. 453), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller`
 (p. 559), `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller`

(p. 678), `activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 915), `activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1283), `activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1315), `activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1376), `activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1421), `activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller` (p. 1483), `activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller` (p. 1512), `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1546), `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1609), `activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller` (p. 1747), `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1865), `activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller` (p. 1959), `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2113), `activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller` (p. 2292), `activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller` (p. 2584), `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller` (p. 2625), `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller` (p. 2654), `activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2716), `activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller` (p. 2763), `activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller` (p. 3063), `activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller` (p. 3112), `activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller` (p. 3213), `activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller` (p. 3230), `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller` (p. 3261), `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3319), `activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller` (p. 3422), `activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller` (p. 3484), and `activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller` (p. 3858).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h`

6.129 activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 786).

#include <src/main/activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.129.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 786).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.129.2 Constructor & Destructor Documentation

6.129.2.1 `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::BaseCommandMarshaller()` [inline]

6.129.2.2 `virtual activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::~~BaseCommandMarshaller()` [inline, virtual]

6.129.3 Member Function Documentation

6.129.3.1 `virtual void activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller` (p. 226), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller` (p. 262), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller` (p. 387), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller` (p. 414), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller` (p. 459), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller` (p. 565), `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller` (p. 680), `activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller` (p. 917), `activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller` (p. 1285), `activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller` (p. 1317), `activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller` (p. 1378), `activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller` (p. 1423), `activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller` (p. 1485), `activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller` (p. 1514), `activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1548), `activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1587), `activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller` (p. 1753), `activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1855), `activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller` (p. 1961), `activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2115), `activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller` (p. 2286), `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller` (p. 2586), `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller` (p. 2615), `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller`

(p. 2656), [activemq::wireformat::openwire::marshal::v5::MessageMarshaller](#) (p. 2694), [activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller](#) (p. 2749), [activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller](#) (p. 3053), [activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller](#) (p. 3114), [activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller](#) (p. 3215), [activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller](#) (p. 3244), [activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller](#) (p. 3275), [activemq::wireformat::openwire::marshal::v5::ResponseMarshaller](#) (p. 3306), [activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller](#) (p. 3416), [activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller](#) (p. 3486), and [activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller](#) (p. 3852).

6.129.3.2 virtual void activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataIn* - BinaryReader that provides that data source

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements [activemq::wireformat::openwire::marshal::DataStreamMarshaller](#) (p. 1631).

Reimplemented in [activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller](#) (p. 227), [activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller](#) (p. 263), [activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller](#) (p. 388), [activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller](#) (p. 415), [activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller](#) (p. 460), [activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller](#) (p. 566), [activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller](#) (p. 681), [activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller](#) (p. 918), [activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller](#) (p. 1286), [activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller](#) (p. 1318), [activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller](#) (p. 1379), [activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller](#) (p. 1424), [activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller](#) (p. 1486), [activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller](#) (p. 1515), [activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller](#) (p. 1549), [activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller](#) (p. 1588), [activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller](#) (p. 1754), [activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller](#) (p. 1856), [activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller](#) (p. 1962), [activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller](#) (p. 2116), [activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller](#) (p. 2287),

activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller (p. 2587), **activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller** (p. 2616), **activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller** (p. 2657), **activemq::wireformat::openwire::marshal::v5::MessageMarshaller** (p. 2694), **activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller** (p. 2750), **activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller** (p. 3054), **activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller** (p. 3115), **activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller** (p. 3216), **activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller** (p. 3245), **activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller** (p. 3276), **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3307), **activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller** (p. 3417), **activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller** (p. 3487), and **activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller** (p. 3853).

6.129.3.3 virtual int activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::tightMarshal1
(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller** (p. 227), **activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller** (p. 263), **activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller** (p. 388), **activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller** (p. 415), **activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller** (p. 460), **activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller** (p. 566), **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller** (p. 681), **activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller** (p. 918), **activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller** (p. 1286), **activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller** (p. 1318), **activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller** (p. 1379), **activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller** (p. 1424), **activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller** (p. 1486), **activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller** (p. 1515), **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1549),

activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1588),
 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1754), ac-
 tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1856),
 activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1962),
 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2116),
 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2287),
 activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller (p. 2587), ac-
 tivemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller (p. 2616), ac-
 tivemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
 (p. 2657), activemq::wireformat::openwire::marshal::v5::MessageMarshaller (p. 2695),
 activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2750),
 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3054),
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3115),
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3216), ac-
 tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
 (p. 3245), activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
 (p. 3276), activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3307),
 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3417), ac-
 tivemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3487), and
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3853).

6.129.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::tightMarshal2
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataOutputStream * *dataOut*,**
utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller**
 (p. 227), **activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller**
 (p. 263), **activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller**
 (p. 388), **activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller**
 (p. 415), **activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller**
 (p. 460), **activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller**
 (p. 566), **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller**
 (p. 681), **activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller** (p. 918),
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (p. 1286),
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (p. 1318),
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (p. 1379),

activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (p. 1424),
 activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (p. 1486),
 activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (p. 1515),
 activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (p. 1550),
 activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1589),
 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1754),
 activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1857),
 activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1962),
 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2117),
 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2287),
 activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller (p. 2587),
 activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller (p. 2616),
 activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
 (p. 2657), activemq::wireformat::openwire::marshal::v5::MessageMarshaller (p. 2696),
 activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2750),
 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3054),
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3115),
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3216),
 activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
 (p. 3245), activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
 (p. 3276), activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3308),
 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3417),
 activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3487), and
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3853).

6.129.3.5 virtual void ac-
 tivemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller::tightUnmarshal
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller`
 (p. 228), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller`
 (p. 264), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller`
 (p. 389), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller`
 (p. 416), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller`
 (p. 461), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller`
 (p. 567), `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller`

(p. 682), `activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller` (p. 919), `activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller` (p. 1287), `activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller` (p. 1319), `activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller` (p. 1380), `activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller` (p. 1425), `activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller` (p. 1487), `activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller` (p. 1516), `activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1550), `activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1589), `activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller` (p. 1755), `activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1857), `activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller` (p. 1963), `activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2117), `activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller` (p. 2288), `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller` (p. 2588), `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller` (p. 2617), `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller` (p. 2658), `activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2696), `activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller` (p. 2751), `activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller` (p. 3055), `activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller` (p. 3116), `activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller` (p. 3217), `activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller` (p. 3246), `activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller` (p. 3277), `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3309), `activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller` (p. 3418), `activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller` (p. 3488), and `activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller` (p. 3854).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h`

6.130 activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 793).

#include <src/main/activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.130.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 793).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.130.2 Constructor & Destructor Documentation

- 6.130.2.1** `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::BaseCommandMarshaller()` `[inline]`
- 6.130.2.2** `virtual activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::~~BaseCommandMarshaller()` `[inline, virtual]`

6.130.3 Member Function Documentation

- 6.130.3.1** `virtual void activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataOut* - BinaryWriter that provides that data sink

Exceptions:

- IOException* if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller` (p. 230), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller` (p. 266), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller` (p. 395), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller` (p. 422), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller` (p. 467), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller` (p. 573), `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller` (p. 684), `activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller` (p. 921), `activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller` (p. 1289), `activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller` (p. 1321), `activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller` (p. 1382), `activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller` (p. 1427), `activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller` (p. 1489), `activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller` (p. 1518), `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1552), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1591), `activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller` (p. 1749), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1843), `activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller` (p. 1941), `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2095), `activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller` (p. 2270), `activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller` (p. 2566), `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller` (p. 2627), `activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller`

(p. 2636), `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719), `activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller` (p. 2765), `activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller` (p. 3057), `activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller` (p. 3122), `activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller` (p. 3203), `activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller` (p. 3240), `activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller` (p. 3271), `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321), `activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller` (p. 3412), `activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller` (p. 3474), and `activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller` (p. 3864).

6.130.3.2 virtual void `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::looseUnmarshal`
**(`OpenWireFormat * wireFormat`, `commands::DataStructure`
`* dataStructure`, `decaf::io::DataInputStream * dataIn`) throw (`decaf::io::IOException`)** [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller` (p. 231), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller` (p. 267), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller` (p. 396), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller` (p. 423), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller` (p. 468), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller` (p. 574), `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller` (p. 685), `activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller` (p. 922), `activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller` (p. 1290), `activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller` (p. 1322), `activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller` (p. 1383), `activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller` (p. 1428), `activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller` (p. 1490), `activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller` (p. 1519), `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1553), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1592), `activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller` (p. 1750), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1844), `activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller` (p. 1942), `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2096), `activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller` (p. 2271),

activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller (p. 2567), activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller (p. 2628), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller (p. 2637), activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2719), activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766), activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058), activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3123), activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3204), activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller (p. 3241), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller (p. 3272), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3322), activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3413), activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3475), and activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3865).

6.130.3.3 virtual int activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- bs* - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller** (p. 231), **activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller** (p. 267), **activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller** (p. 396), **activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller** (p. 423), **activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller** (p. 468), **activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller** (p. 574), **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller** (p. 685), **activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller** (p. 922), **activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller** (p. 1290), **activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller** (p. 1322), **activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller** (p. 1383), **activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller** (p. 1428), **activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller** (p. 1490), **activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller** (p. 1519), **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller** (p. 1553),

activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1592),
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1750), **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller** (p. 1844),
activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1942),
activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2096),
activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2271),
activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller (p. 2567), **activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller** (p. 2628), **activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller** (p. 2637),
activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2720),
activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766),
activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058),
activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3123),
activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3204), **activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller** (p. 3241),
activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller (p. 3272), **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3322),
activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3413), **activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller** (p. 3475), and
activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3865).

6.130.3.4 virtual void activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::tightMarshal2
 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller** (p. 231), **activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller** (p. 267), **activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller** (p. 396), **activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller** (p. 423), **activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller** (p. 468), **activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller** (p. 574), **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller** (p. 685), **activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller** (p. 922), **activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller** (p. 1290), **activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller** (p. 1322), **activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller** (p. 1383),

activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1428),
 activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1490),
 activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1519),
 activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1554),
 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1593),
 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1750),
 activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1845),
 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1942),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2097),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2271),
 activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller (p. 2567),
 activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller (p. 2628),
 activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
 (p. 2637), activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2721),
 activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766),
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058),
 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3123),
 activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3204),
 activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller
 (p. 3241), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller
 (p. 3272), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3323),
 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3413),
 activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3475), and
 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3865).

6.130.3.5 virtual void `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller::tightUnmarshal`
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller`
 (p. 232), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller`
 (p. 268), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller`
 (p. 397), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller`
 (p. 424), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller`
 (p. 469), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller`
 (p. 575), `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller`

(p. 686), `activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller` (p. 923), `activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller` (p. 1291), `activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller` (p. 1323), `activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller` (p. 1384), `activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller` (p. 1429), `activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller` (p. 1491), `activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller` (p. 1520), `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1554), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1593), `activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller` (p. 1751), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1845), `activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller` (p. 1943), `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2097), `activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller` (p. 2272), `activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller` (p. 2568), `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller` (p. 2629), `activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller` (p. 2638), `activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2721), `activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller` (p. 2767), `activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller` (p. 3059), `activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller` (p. 3124), `activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller` (p. 3205), `activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller` (p. 3242), `activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller` (p. 3273), `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3324), `activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller` (p. 3414), `activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller` (p. 3476), and `activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller` (p. 3866).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h`

6.131 activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 800).

#include <src/main/activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller:

Public Member Functions

- **BaseCommandMarshaller** ()
- virtual **~BaseCommandMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.131.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 800).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.131.2 Constructor & Destructor Documentation

6.131.2.1 `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::BaseCommandMarshaller()` [inline]

6.131.2.2 `virtual activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::~~BaseCommandMarshaller()` [inline, virtual]

6.131.3 Member Function Documentation

6.131.3.1 `virtual void activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::marshal(const OpenWireFormat * wireFormat, const commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 222), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 270), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 391), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 418), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 463), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 569), `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 688), `activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 925), `activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1293), `activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1301), `activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1362), `activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1407), `activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1469), `activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1498), `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1532), `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1595), `activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1733), `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1847), `activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1945), `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2099), `activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2274), `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller` (p. 2570), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller` (p. 2607), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller`

(p. 2640), [activemq::wireformat::openwire::marshal::v2::MessageMarshaller](#) (p. 2704), [activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller](#) (p. 2745), [activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller](#) (p. 3041), [activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller](#) (p. 3106), [activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller](#) (p. 3199), [activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller](#) (p. 3236), [activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller](#) (p. 3263), [activemq::wireformat::openwire::marshal::v2::ResponseMarshaller](#) (p. 3301), [activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller](#) (p. 3428), [activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller](#) (p. 3478), and [activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller](#) (p. 3872).

6.131.3.2 virtual void activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker
- dataStructure* - Object to be marshaled
- dataIn* - BinaryReader that provides that data source

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements [activemq::wireformat::openwire::marshal::DataStreamMarshaller](#) (p. 1631).

Reimplemented in [activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller](#) (p. 223), [activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller](#) (p. 271), [activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller](#) (p. 392), [activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller](#) (p. 419), [activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller](#) (p. 464), [activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller](#) (p. 570), [activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller](#) (p. 689), [activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller](#) (p. 926), [activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller](#) (p. 1294), [activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller](#) (p. 1302), [activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller](#) (p. 1363), [activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller](#) (p. 1408), [activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller](#) (p. 1470), [activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller](#) (p. 1499), [activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller](#) (p. 1533), [activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller](#) (p. 1596), [activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller](#) (p. 1734), [activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller](#) (p. 1848), [activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller](#) (p. 1946), [activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller](#) (p. 2100), [activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller](#) (p. 2275),

`activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller` (p. 2571), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller` (p. 2608), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller` (p. 2641), `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2704), `activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller` (p. 2746), `activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller` (p. 3042), `activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller` (p. 3107), `activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller` (p. 3200), `activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller` (p. 3237), `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller` (p. 3264), `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302), `activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller` (p. 3429), `activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller` (p. 3479), and `activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller` (p. 3873).

6.131.3.3 `virtual int activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 223), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 271), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 392), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 419), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 464), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 570), `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 689), `activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 926), `activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1294), `activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1302), `activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1363), `activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1408), `activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1470), `activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1499), `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1533),

activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (p. 1596),
 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (p. 1734),
 activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (p. 1848),
 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (p. 1946),
 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (p. 2100),
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (p. 2275),
 activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller (p. 2571),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller (p. 2608),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
 (p. 2641), activemq::wireformat::openwire::marshal::v2::MessageMarshaller (p. 2705),
 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2746),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3042),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3107),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3200),
 activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller
 (p. 3237), activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller
 (p. 3264), activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3302),
 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3429),
 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3479), and
 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3873).

6.131.3.4 virtual void activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller** (p. 223), **activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller** (p. 271), **activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller** (p. 392), **activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller** (p. 419), **activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller** (p. 464), **activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller** (p. 570), **activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller** (p. 689), **activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller** (p. 926), **activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller** (p. 1294), **activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller** (p. 1302), **activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller** (p. 1363),

activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller (p. 1408),
 activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller (p. 1470),
 activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller (p. 1499),
 activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller (p. 1534),
 activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (p. 1597),
 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (p. 1734),
 activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (p. 1849),
 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (p. 1946),
 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (p. 2101),
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (p. 2275),
 activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller (p. 2571),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller (p. 2608),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
 (p. 2641), activemq::wireformat::openwire::marshal::v2::MessageMarshaller (p. 2706),
 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2746),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3042),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3107),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3200),
 activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller
 (p. 3237), activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller
 (p. 3264), activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3303),
 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3429),
 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3479), and
 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3873).

6.131.3.5 virtual void ac-
 tivemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller::tightUnmarshal
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 * *dataStructure*, decaf::io::DataInputStream * *dataIn*,
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1652).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller`
 (p. 224), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller`
 (p. 272), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller`
 (p. 393), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller`
 (p. 420), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller`
 (p. 465), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller`
 (p. 571), `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller`

(p. 690), `activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 927), `activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1295), `activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1303), `activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1364), `activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1409), `activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1471), `activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1500), `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1534), `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1597), `activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1735), `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1849), `activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1947), `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2101), `activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2276), `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller` (p. 2572), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller` (p. 2609), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller` (p. 2642), `activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2706), `activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller` (p. 2747), `activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller` (p. 3043), `activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller` (p. 3108), `activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller` (p. 3201), `activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller` (p. 3238), `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller` (p. 3265), `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3304), `activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller` (p. 3430), `activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller` (p. 3480), and `activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller` (p. 3874).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h`

6.132 activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller Class Reference

Base class for all Marshallers that **marshal** (p. 107) DataStructures to and from the wire using the OpenWire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
```

Inherits **activemq::wireformat::openwire::marshal::DataStreamMarshaller**.

Inherited by **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller**,
activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller,
activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller,
activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller,
activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller,
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::SessionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller,
activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller,
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller,
activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller,
activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller,
activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::SessionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller,
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller,
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller, **ac-**
tivemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller, **ac-**

tivemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller,	
activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller,	
activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller,	
activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::SessionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller,	
activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller,	
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller,	
activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller,	
activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller,	
activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::SessionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller,	
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller,	
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller,	
activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller,	
activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller,	
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::SessionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller,	
activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller,	
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller,	ac-
tivemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller,	ac-

```

tivemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller,          ac-
tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller,
activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller,           ac-
tivemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller,
activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller,
activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller,          ac-
tivemq::wireformat::openwire::marshal::v6::SessionIdMarshaller,             ac-
tivemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller,      ac-
tivemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller,         and ac-
tivemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller.

```

Public Member Functions

- virtual `~BaseDataStreamMarshaller` ()
- virtual `int tightMarshal1 (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)`
Tight Marshal to the given stream.
- virtual `void tightMarshal2 (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataOutputStream *ds AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)`
Tight Marshal to the given stream.
- virtual `void tightUnmarshal (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataInputStream *dis AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)`
Tight Un-Marshal to the given stream.
- virtual `void looseMarshal (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataOutputStream *ds AMQCPP_UNUSED) throw (decaf::io::IOException)`
Tight Marshal to the given stream.
- virtual `void looseUnmarshal (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataInputStream *dis AMQCPP_UNUSED) throw (decaf::io::IOException)`
Loose Un-Marshal to the given stream.

Static Public Member Functions

- static `std::string toString (const commands::MessageId *id)`
Converts the object to a String.
- static `std::string toString (const commands::ProducerId *id)`
Converts the object to a String.

- static `std::string toString` (`const commands::TransactionId *txnId`)
Converts the given transaction ID into a String.
- static `std::string toHexFromBytes` (`const std::vector< unsigned char > &data`)
given an array of bytes, convert that array to a Hexidecimal coded string that represents that data.

Protected Member Functions

- virtual `commands::DataStructure * tightUnmarshalCachedObject` (`OpenWireFormat *wireFormat`, `decaf::io::DataInputStream *dataIn`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tight Unmarshal the cached object.
- virtual `int tightMarshalCachedObject1` (`OpenWireFormat *wireFormat`, `commands::DataStructure *data`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tightly marshals the passed DataStructure based object to the passed BooleanStream returning the size of the data marshaled.
- virtual `void tightMarshalCachedObject2` (`OpenWireFormat *wireFormat`, `commands::DataStructure *data`, `decaf::io::DataOutputStream *dataOut`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tightly marshals the passed DataStructure based object to the passed streams returning nothing.
- virtual `void looseMarshalCachedObject` (`OpenWireFormat *wireFormat`, `commands::DataStructure *data`, `decaf::io::DataOutputStream *dataOut`) throw (`decaf::io::IOException`)
Loosely marshals the passed DataStructure based object to the passed stream returning nothing.
- virtual `commands::DataStructure * looseUnmarshalCachedObject` (`OpenWireFormat *wireFormat`, `decaf::io::DataInputStream *dataIn`) throw (`decaf::io::IOException`)
Loose Unmarshal the cached object.
- virtual `int tightMarshalNestedObject1` (`OpenWireFormat *wireFormat`, `commands::DataStructure *object`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tightly marshals the passed DataStructure based object to the passed BooleanStream returning the size of the data marshaled.
- virtual `void tightMarshalNestedObject2` (`OpenWireFormat *wireFormat`, `commands::DataStructure *object`, `decaf::io::DataOutputStream *dataOut`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tightly marshals the passed DataStructure based object to the passed streams returning nothing.
- virtual `commands::DataStructure * tightUnmarshalNestedObject` (`OpenWireFormat *wireFormat`, `decaf::io::DataInputStream *dataIn`, `utils::BooleanStream *bs`) throw (`decaf::io::IOException`)
Tight Unmarshal the nested object.

- virtual **commands::DataStructure * looseUnmarshalNestedObject** (**OpenWireFormat *wireFormat**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)

Loose Unmarshal the nested object.

- virtual void **looseMarshalNestedObject** (**OpenWireFormat *wireFormat**, **commands::DataStructure *object**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)

Loose marshal the nested object.

- virtual std::string **tightUnmarshalString** (**decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Performs Tight Unmarshaling of String Objects.

- virtual int **tightMarshalString1** (const std::string &value, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Tight Marshals the String to a Booleans Stream Object, returns the marshaled size.

- virtual void **tightMarshalString2** (const std::string &value, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Tight Marshals the passed string to the streams passed.

- virtual void **looseMarshalString** (const std::string value, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)

Loose Marshal the String to the DataOuputStream passed.

- virtual std::string **looseUnmarshalString** (**decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)

Loose Un-Marshal the String to the DataOuputStream passed.

- virtual int **tightMarshalLong1** (**OpenWireFormat *wireFormat**, long long value, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Tightly marshal (p. 107) the long long to the BooleanStream passed.

- virtual void **tightMarshalLong2** (**OpenWireFormat *wireFormat**, long long value, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Tightly marshal (p. 107) the long long to the Streams passed.

- virtual long long **tightUnmarshalLong** (**OpenWireFormat *wireFormat**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)

Tight marshal (p. 107) the long long type.

- virtual void **looseMarshalLong** (**OpenWireFormat *wireFormat**, long long value, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)

Tightly marshal (p. 107) the long long to the BooleanStream passed.

- virtual long long **looseUnmarshalLong** (**OpenWireFormat** *wireFormat, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Loose marshal (p. 107) the long long type.
- virtual std::vector< unsigned char > **tightUnmarshalByteArray** (**decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Tight Unmarshal an array of char.
- virtual std::vector< unsigned char > **looseUnmarshalByteArray** (**decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Loose Unmarshal an array of char.
- virtual std::vector< unsigned char > **tightUnmarshalConstByteArray** (**decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs, int size) throw (**decaf::io::IOException**)
Tight Unmarshal a fixed size array from that data input stream and return an stl vector of char as the resultant.
- virtual std::vector< unsigned char > **looseUnmarshalConstByteArray** (**decaf::io::DataInputStream** *dataIn, int size) throw (**decaf::io::IOException**)
Tight Unmarshal a fixed size array from that data input stream and return an stl vector of char as the resultant.
- virtual **commands::DataStructure** * **tightUnmarshalBrokerError** (**OpenWireFormat** *wireFormat, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Tight Unmarshal the Error object.
- virtual int **tightMarshalBrokerError1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *data, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Tight Marshal the Error object.
- virtual void **tightMarshalBrokerError2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *data, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Tight Marshal the Error object.
- virtual **commands::DataStructure** * **looseUnmarshalBrokerError** (**OpenWireFormat** *wireFormat, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Loose Unmarshal the Error object.
- virtual void **looseMarshalBrokerError** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *data, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Tight Marshal the Error object.
- template<typename T >
int **tightMarshalObjectArray1** (**OpenWireFormat** *wireFormat, std::vector< T > objects, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Tightly Marshal an array of DataStructure objects to the provided boolean stream, and return the size that the tight marshalling is going to take.

- `template<typename T >`
`void tightMarshalObjectArray2 (OpenWireFormat *wireFormat, std::vector< T > objects, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`

Tightly Marshal an array of DataStructure objects to the provided boolean stream and data output stream.

- `template<typename T >`
`void looseMarshalObjectArray (OpenWireFormat *wireFormat, std::vector< T > objects, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`

Loosely Marshal an array of DataStructure objects to the provided boolean stream and data output stream.

- `virtual std::string readAsciiString (decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`

Given an DataInputStream read a know ASCII formatted string from the input and return that string.

6.132.1 Detailed Description

Base class for all Marshallers that **marshal** (p.107) DataStructures to and from the wire using the OpenWire protocol.

Since:

2.0

6.132.2 Constructor & Destructor Documentation

- 6.132.2.1** `virtual`
`activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::~BaseDataStreamMarshaller() [inline, virtual]`

6.132.3 Member Function Documentation

- 6.132.3.1** `virtual void activate`
`activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshal (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataOutputStream *ds AMQCPP_UNUSED) throw (decaf::io::IOException) [inline, virtual]`

Tight Marshal to the given stream.

Parameters:

format - The OpenwireFormat properties

command - the object to Marshal

ds - DataOutputStream to **marshal** (p.107) to

Exceptions:

IOException if an error occurs.

6.132.3.2 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalBrokerEntry (OpenWireFormat * *wireFormat*, commands::DataStructure * *data*, decaf::io::DataOutputStream * *dataOut*) throw (decaf::io::IOException)
[protected, virtual]

Tight Marshal the Error object.

Parameters:

wireFormat - The OpenwireFormat properties

data - Error to Marshal

dataOut - stream to write marshalled data to

Exceptions:

IOException if an error occurs.

6.132.3.3 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalCachedObject (OpenWireFormat * *wireFormat*, commands::DataStructure * *data*, decaf::io::DataOutputStream * *dataOut*) throw (decaf::io::IOException)
[protected, virtual]

Loosely marshals the passed DataStructure based object to the passed stream returning nothing.

Parameters:

wireFormat - The OpenwireFormat properties

data - DataStructure Object Pointer to **marshal** (p.107)

dataOut - stream to write marshaled data to

Exceptions:

IOException if an error occurs.

6.132.3.4 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalLong (OpenWireFormat * *wireFormat*, long long *value*, decaf::io::DataOutputStream * *dataOut*) throw (decaf::io::IOException)
[protected, virtual]

Tightly **marshal** (p.107) the long long to the BooleanStream passed.

Parameters:

wireFormat - The OpenwireFormat properties

value - long long to **marshal** (p. 107)

dataOut - DataOutputStream to **marshal** (p. 107) to.

Exceptions:

IOException if an error occurs.

6.132.3.5 `virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalNestedObject(OpenWireFormat * wireFormat, commands::DataStructure * object, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)`
[protected, virtual]

Loose marshal the nested object.

Parameters:

wireFormat - The OpenwireFormat properties

object - DataStructure Object Pointer to **marshal** (p. 107)

dataOut - stream to write marshaled data to

Exceptions:

IOException if an error occurs.

6.132.3.6 `template<typename T > void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalObjectArray(OpenWireFormat * wireFormat, std::vector< T > objects, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)`
[inline, protected]

Loosely Marshal an array of DataStructure objects to the provided boolean stream and data output stream.

Parameters:

wireFormat - The OpenwireFormat properties

objects - array of DataStructure object pointers.

dataOut - stream to write marshalled data to

Returns:

size of the marshalled data

Exceptions:

IOException if an error occurs.

References `AMQ_CATCH_EXCEPTION_CONVERT`, `AMQ_CATCH_RETHROW`, and `AMQ_CATCHALL_THROW`.

6.132.3.7 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalString (const std::string *value*, decaf::io::DataOutputStream * *dataOut*) throw (decaf::io::IOException) [protected, virtual]

Loose Marshal the String to the DataOutputStream passed.

Parameters:

value - string to **marshal** (p. 107)

dataOut - stream to write marshaled form to

Exceptions:

IOException if an error occurs.

6.132.3.8 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshal (OpenWireFormat **format* *AMQCPP_UNUSED*, commands::DataStructure **command* *AMQCPP_UNUSED*, decaf::io::DataInputStream **dis* *AMQCPP_UNUSED*) throw (decaf::io::IOException) [inline, virtual]

Loose Un-Marshal to the given stream.

Parameters:

format - The OpenWireFormat properties

command - the object to Un-Marshal

dis - the DataInputStream to Un-Marshal from

Exceptions:

IOException if an error occurs.

6.132.3.9 virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalBroken (OpenWireFormat * *wireFormat*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [protected, virtual]

Loose Unmarshal the Error object.

Parameters:

wireFormat - The OpenWireFormat properties

dataIn - stream to read marshalled form from

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.10 `virtual std::vector<unsigned char> activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalBytes (decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [protected, virtual]

Loose Unmarshal an array of char.

Parameters:

dataIn - the DataInputStream to Un-Marshall from

Returns:

the unmarshalled vector of chars.

Exceptions:

IOException if an error occurs.

6.132.3.11 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalCachedObject (OpenWireFormat * wireFormat, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [protected, virtual]

Loose Unmarshal the cached object.

Parameters:

wireFormat - The OpenWireFormat properties

dataIn - stream to read marshaled form from

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.12 `virtual std::vector<unsigned char> activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalCompact (decaf::io::DataInputStream * dataIn, int size) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshal a fixed size array from that data input stream and return an stl vector of char as the resultant.

Parameters:

dataIn - the DataInputStream to Un-Marshall from

size - size of the const array to unmarshal

Returns:

the unmarshaled vector of chars.

Exceptions:

IOException if an error occurs.

6.132.3.13 virtual long long activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalLong (OpenWireFormat * *wireFormat*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [protected, virtual]

Loose marshal (p.107) the long long type.

Parameters:

wireFormat - The OpenWireFormat properties

dataIn - stream to read marshaled form from

Returns:

the unmarshaled long long

Exceptions:

IOException if an error occurs.

6.132.3.14 virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalNested (OpenWireFormat * *wireFormat*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [protected, virtual]

Loose Unmarshal the nested object.

Parameters:

wireFormat - The OpenWireFormat properties

dataIn - stream to read marshaled form from

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.15 virtual std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseUnmarshalString (decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [protected, virtual]

Loose Un-Marshal the String to the DataOutputStream passed.

Parameters:

dataIn - stream to read marshaled form from

Returns:

the unmarshaled string

Exceptions:

IOException if an error occurs.

6.132.3.16 `virtual std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::readAsciiString (decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)`
[protected, virtual]

Given an DataInputStream read a know ASCII formatted string from the input and return that string.

Parameters:

dataIn - DataInputStream to read from

Returns:

string value read from stream

6.132.3.17 `virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshal1 (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)` [inline, virtual]

Tight Marshal to the given stream.

Parameters:

format - The OpenwireFormat properties

command - the object to Marshal

bs - boolean stream to **marshal** (p.107) to.

Exceptions:

IOException if an error occurs.

6.132.3.18 `virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshal2 (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataOutputStream *ds AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)` [inline, virtual]

Tight Marshal to the given stream.

Parameters:

format - The OpenwireFormat properties
command - the object to Marshal
ds - the DataOutputStream to Marshal to
bs - boolean stream to **marshal** (p.107) to.

Exceptions:

IOException if an error occurs.

6.132.3.19 virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalBroker(OpenWireFormat * *wireFormat*, commands::DataStructure * *data*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tight Marshal the Error object.

Parameters:

wireFormat - The OpenwireFormat properties
data - Error to Marshal
bs - boolean stream to **marshal** (p.107) to.

Returns:

size of the marshalled data

Exceptions:

IOException if an error occurs.

6.132.3.20 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalBroker(OpenWireFormat * *wireFormat*, commands::DataStructure * *data*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tight Marshal the Error object.

Parameters:

wireFormat - The OpenwireFormat properties
data - Error to Marshal
dataOut - stream to write marshalled data to
bs - boolean stream to **marshal** (p.107) to.

Exceptions:

IOException if an error occurs.

6.132.3.21 `virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalCached (OpenWireFormat * wireFormat, commands::DataStructure * data, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tightly marshals the passed DataStructure based object to the passed BooleanStream returning the size of the data marshaled.

Parameters:

wireFormat - The OpenwireFormat properties

data - DataStructure Object Pointer to **marshal** (p.107)

bs - boolean stream to **marshal** (p.107) to.

Returns:

size of data written.

Exceptions:

IOException if an error occurs.

6.132.3.22 `virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalCached (OpenWireFormat * wireFormat, commands::DataStructure * data, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tightly marshals the passed DataStructure based object to the passed streams returning nothing.

Parameters:

wireFormat - The OpenwireFormat properties

data - DataStructure Object Pointer to **marshal** (p.107)

bs - boolean stream to **marshal** (p.107) to.

dataOut - stream to write marshaled data to

Exceptions:

IOException if an error occurs.

6.132.3.23 `virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalLong1 (OpenWireFormat * wireFormat, long long value, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tightly **marshal** (p.107) the long long to the BooleanStream passed.

Parameters:

wireFormat - The OpenwireFormat properties

value - long long to **marshal** (p. 107)

bs - boolean stream to **marshal** (p. 107) to.

Returns:

size of data written.

Exceptions:

IOException if an error occurs.

6.132.3.24 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalLong2 (OpenWireFormat * *wireFormat*, long long *value*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tightly **marshal** (p. 107) the long long to the Streams passed.

Parameters:

wireFormat - The OpenWireFormat properties

value - long long to **marshal** (p. 107)

dataOut - stream to write marshaled form to

bs - boolean stream to **marshal** (p. 107) to.

Exceptions:

IOException if an error occurs.

6.132.3.25 virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalNested (OpenWireFormat * *wireFormat*, commands::DataStructure * *object*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tightly marshals the passed DataStructure based object to the passed BooleanStream returning the size of the data marshaled.

Parameters:

wireFormat - The OpenWireFormat properties

object - DataStructure Object Pointer to **marshal** (p. 107)

bs - boolean stream to **marshal** (p. 107) to.

Returns:

size of data written.

Exceptions:

IOException if an error occurs.

6.132.3.26 `virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalNested(OpenWireFormat * wireFormat, commands::DataStructure * object, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tightly marshals the passed DataStructure based object to the passed streams returning nothing.

Parameters:

wireFormat - The OpenWireFormat properties
object - DataStructure Object Pointer to **marshal** (p.107)
bs - boolean stream to **marshal** (p.107) to.
dataOut - stream to write marshaled data to

Exceptions:

IOException if an error occurs.

6.132.3.27 `template<typename T > int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObject(OpenWireFormat * wireFormat, std::vector< T > objects, utils::BooleanStream * bs) throw (decaf::io::IOException)` [inline, protected]

Tightly Marshal an array of DataStructure objects to the provided boolean stream, and return the size that the tight marshalling is going to take.

Parameters:

wireFormat - The OpenWireFormat properties
objects - array of DataStructure object pointers.
bs - boolean stream to **marshal** (p.107) to.

Returns:

size of the marshalled data

Exceptions:

IOException if an error occurs.

References AMQ_CATCH_EXCEPTION_CONVERT, AMQ_CATCH_RETHROW, and AMQ_CATCHALL_THROW.

6.132.3.28 `template<typename T > void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObject(OpenWireFormat * wireFormat, std::vector< T > objects, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [inline, protected]

Tightly Marshal an array of DataStructure objects to the provided boolean stream and data output stream.

Parameters:

wireFormat - The OpenwireFormat properties
objects - array of DataStructure object pointers.
dataOut - stream to write marshalled data to
bs - boolean stream to **marshal** (p.107) to.

Returns:

size of the marshalled data

Exceptions:

IOException if an error occurs.

References AMQ_CATCH_EXCEPTION_CONVERT, AMQ_CATCH_RETHROW, and AMQ_CATCHALL_THROW.

6.132.3.29 virtual int activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalString1 (const std::string & *value*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tight Marshals the String to a Booleans Stream Object, returns the marshaled size.

Parameters:

value - string to **marshal** (p.107)
bs - BooleanStream to use.

Returns:

size of marshaled string.

Exceptions:

IOException if an error occurs.

6.132.3.30 virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalString2 (const std::string & *value*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [protected, virtual]

Tight Marshals the passed string to the streams passed.

Parameters:

value - string to **marshal** (p.107)
dataOut - the DataOutputStream to Marshal to
bs - boolean stream to **marshal** (p.107) to.

Exceptions:

IOException if an error occurs.

6.132.3.31 `virtual void activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshal (OpenWireFormat *format AMQCPP_UNUSED, commands::DataStructure *command AMQCPP_UNUSED, decaf::io::DataInputStream *dis AMQCPP_UNUSED, utils::BooleanStream *bs AMQCPP_UNUSED) throw (decaf::io::IOException)` [inline, virtual]

Tight Un-Marshall to the given stream.

Parameters:

format - The OpenwireFormat properties
command - the object to Un-Marshall
dis - the DataInputStream to Un-Marshall from
bs - boolean stream to Un-Marshall from.

Exceptions:

IOException if an error occurs.

6.132.3.32 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalBroken (OpenWireFormat * wireFormat, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshall the Error object.

Parameters:

wireFormat - The OpenwireFormat properties
dataIn - stream to read marshalled form from
bs - boolean stream to **marshal** (p.107) to.

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.33 `virtual std::vector<unsigned char> activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalBytes (decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshal an array of char.

Parameters:

dataIn - the DataInputStream to Un-Marshall from

bs - boolean stream to unmarshal from.

Returns:

the unmarshaled vector of chars.

Exceptions:

IOException if an error occurs.

6.132.3.34 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalCached(OpenWireFormat * wireFormat, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshal the cached object.

Parameters:

wireFormat - The OpenWireFormat properties

dataIn - stream to read marshaled form from

bs - boolean stream to **marshal** (p.107) to.

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.35 `virtual std::vector<unsigned char> activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalConstArray(decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs, int size) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshal a fixed size array from that data input stream and return an stl vector of char as the resultant.

Parameters:

dataIn - the DataInputStream to Un-Marshall from

bs - boolean stream to unmarshal from.

size - size of the const array to unmarshal

Returns:

the unmarshaled vector of chars.

Exceptions:

IOException if an error occurs.

6.132.3.36 `virtual long long activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalLong (OpenWireFormat * wireFormat, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tight **marshal** (p.107) the long long type.

Parameters:

wireFormat - The OpenwireFormat properties

dataIn - stream to read marshaled form from

bs - boolean stream to **marshal** (p.107) to.

Returns:

the unmarshaled long long

Exceptions:

IOException if an error occurs.

6.132.3.37 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalNested (OpenWireFormat * wireFormat, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Tight Unmarshal the nested object.

Parameters:

wireFormat - The OpenwireFormat properties

dataIn - stream to read marshaled form from

bs - boolean stream to **marshal** (p.107) to.

Returns:

pointer to a new DataStructure Object

Exceptions:

IOException if an error occurs.

6.132.3.38 `virtual std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightUnmarshalString (decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [protected, virtual]

Performs Tight Unmarshaling of String Objects.

Parameters:

dataIn - the DataInputStream to Un-Marshall from

bs - boolean stream to unmarshal from.

Returns:

the unmarshaled string.

Exceptions:

IOException if an error occurs.

6.132.3.39 static std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::toHexFromBytes (const std::vector< unsigned char > & data) [static]

given an array of bytes, convert that array to a Hexidecimal coded string that represents that data.

Parameters:

data - unsigned char data array pointer

Returns:

a string coded in hex that represents the data

6.132.3.40 static std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::toString (const commands::TransactionId * txnId) [static]

Converts the given transaction ID into a String.

Parameters:

txnId - TransactionId poitner

Returns:

string representation of the id

6.132.3.41 static std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::toString (const commands::ProducerId * id) [static]

Converts the object to a String.

Parameters:

id - ProducerId pointer

Returns:

string representing the id

6.132.3.42 `static std::string activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::toString(const commands::MessageId * id) [static]`

Converts the object to a String.

Parameters:

id - MessageId pointer

Returns:

string representing the id

Referenced by `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getCMSMessageID()`.

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h`

6.133 activemq::commands::BaseDataStructure Class Reference

#include <src/main/activemq/commands/BaseDataStructure.h> Inheritance diagram for activemq::commands::BaseDataStructure:

Public Member Functions

- virtual `~BaseDataStructure ()`
- virtual bool `isMarshalAware ()` const
Determine if this object is aware of marshaling and should have its before and after marshaling methods called.
- virtual void `beforeMarshal (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED) throw (decaf::io::IOException)`
Perform any processing needed before an marshal.
- virtual void `afterMarshal (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED) throw (decaf::io::IOException)`
Perform any processing needed after an unmarshal.
- virtual void `beforeUnmarshal (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED) throw (decaf::io::IOException)`
Perform any processing needed before an unmarshal.
- virtual void `afterUnmarshal (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED) throw (decaf::io::IOException)`
Perform any processing needed after an unmarshal.
- virtual void `setMarshaledForm (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED, const std::vector< char > &data AMQCPP_ -UNUSED)`
Called to set the data to this object that will contain the objects marshaled form.
- virtual std::vector< unsigned char > `getMarshaledForm (wireformat::WireFormat *wireFormat AMQCPP_ -UNUSED)`
Called to get the data to this object that will contain the objects marshaled form.
- virtual void `copyDataStructure (const DataStructure *src AMQCPP_ -UNUSED)`
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string `toString ()` const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool `equals (const DataStructure *value AMQCPP_ -UNUSED)` const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

6.133.1 Constructor & Destructor Documentation

6.133.1.1 `virtual activemq::commands::BaseDataStructure::~~BaseDataStructure ()`
`[inline, virtual]`

6.133.2 Member Function Documentation

6.133.2.1 `virtual void activemq::commands::BaseDataStructure::afterMarshal`
`(wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (`
`decaf::io::IOException) [inline, virtual]`

Perform any processing needed after an unmarshal.

Parameters:

wireformat (p. 105) - the OpenWireFormat object in use.

6.133.2.2 `virtual void activemq::commands::BaseDataStructure::afterUnmarshal`
`(wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (`
`decaf::io::IOException) [inline, virtual]`

Perform any processing needed after an unmarshal.

Parameters:

wireformat (p. 105) - the OpenWireFormat object in use.

Reimplemented in `activemq::commands::Message` (p. 2520), and `activemq::commands::WireFormatInfo` (p. 3984).

6.133.2.3 `virtual void activemq::commands::BaseDataStructure::beforeMarshal`
`(wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (`
`decaf::io::IOException) [inline, virtual]`

Perform any processing needed before an marshal.

Parameters:

wireformat (p. 105) - the OpenWireFormat object in use.

Reimplemented in `activemq::commands::Message` (p. 2520), and `activemq::commands::WireFormatInfo` (p. 3985).

6.133.2.4 `virtual void activemq::commands::BaseDataStructure::beforeUnmarshal`
`(wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (`
`decaf::io::IOException) [inline, virtual]`

Perform any processing needed before an unmarshal.

Parameters:

wireformat (p. 105) - the OpenWireFormat object in use.

6.133.2.5 virtual void activemq::commands::BaseDataStructure::copyDataStructure (const DataStructure *src *AMQCPP_UNUSED*) [inline, virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented in `activemq::commands::BooleanExpression` (p. 856).

6.133.2.6 virtual bool activemq::commands::BaseDataStructure::equals (const DataStructure *value *AMQCPP_UNUSED*) const [inline, virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Referenced by `activemq::commands::BooleanExpression::equals()`, and `activemq::commands::BaseCommand::equals()`.

6.133.2.7 virtual std::vector<unsigned char> activemq::commands::BaseDataStructure::getMarshaledForm (wireformat::WireFormat *wireFormat *AMQCPP_UNUSED*) [inline, virtual]

Called to get the data to this object that will contain the objects marshaled form.

Parameters:

wireFormat - the `wireformat` (p. 105) object to control unmarshaling

Returns:

buffer that holds the objects data.

6.133.2.8 virtual bool activemq::commands::BaseDataStructure::isMarshalAware () const [inline, virtual]

Determine if this object is aware of marshaling and should have its before and after marshaling methods called. Defaults to false.

Returns:

true if aware of marshaling

Implements `activemq::wireformat::MarshalAware` (p. 2486).

Reimplemented in `activemq::commands::ActiveMQMapMessage` (p. 368), `activemq::commands::Message` (p. 2526), and `activemq::commands::WireFormatInfo` (p. 3987).

6.133.2.9 `virtual void activemq::commands::BaseDataStructure::setMarshaledForm (wireformat::WireFormat *wireFormat AMQCPP_UNUSED, const std::vector< char > &data AMQCPP_UNUSED)` [inline, virtual]

Called to set the data to this object that will contain the objects marshaled form.

Parameters:

wireFormat - the **wireformat** (p.105) object to control unmarshaling

data - vector of object binary data

6.133.2.10 `virtual std::string activemq::commands::BaseDataStructure::toString () const` [inline, virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Implements **activemq::commands::DataStructure** (p.1663).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p.208), **activemq::commands::ActiveMQBytesMessage** (p.244), **activemq::commands::ActiveMQDestination** (p.330), **activemq::commands::ActiveMQMapMessage** (p.372), **activemq::commands::ActiveMQMessage** (p.400), **activemq::commands::ActiveMQObjectMessage** (p.445), **activemq::commands::ActiveMQQueue** (p.486), **activemq::commands::ActiveMQStreamMessage** (p.547), **activemq::commands::ActiveMQTempDestination** (p.578), **activemq::commands::ActiveMQTempQueue** (p.607), **activemq::commands::ActiveMQTempTopic** (p.636), **activemq::commands::ActiveMQTextMessage** (p.666), **activemq::commands::ActiveMQTopic** (p.694), **activemq::commands::BaseCommand** (p.763), **activemq::commands::BooleanExpression** (p.856), **activemq::commands::BrokerId** (p.871), **activemq::commands::BrokerInfo** (p.901), **activemq::commands::Command** (p.1198), **activemq::commands::ConnectionControl** (p.1270), **activemq::commands::ConnectionError** (p.1298), **activemq::commands::ConnectionId** (p.1329), **activemq::commands::ConnectionInfo** (p.1359), **activemq::commands::ConsumerControl** (p.1404), **activemq::commands::ConsumerId** (p.1433), **activemq::commands::ConsumerInfo** (p.1464), **activemq::commands::ControlCommand** (p.1495), **activemq::commands::DataArrayResponse** (p.1530), **activemq::commands::DataResponse** (p.1585), **activemq::commands::DestinationInfo** (p.1730), **activemq::commands::DiscoveryEvent** (p.1760), **activemq::commands::ExceptionResponse** (p.1841), **activemq::commands::FlushCommand** (p.1939), **activemq::commands::IntegerResponse** (p.2093), **activemq::commands::JournalQueueAck** (p.2158), **activemq::commands::JournalTopicAck** (p.2186), **activemq::commands::JournalTrace** (p.2214), **activemq::commands::JournalTransaction** (p.2241), **activemq::commands::KeepAliveInfo** (p.2268), **activemq::commands::LastPartialCommand** (p.2302), **activemq::commands::LocalTransactionId** (p.2350), **activemq::commands::Message** (p.2530), **activemq::commands::MessageAck**

(p. 2563), [activemq::commands::MessageDispatch](#) (p. 2597), [activemq::commands::MessageDispatchNotification](#) (p. 2633), [activemq::commands::MessageId](#) (p. 2666), [activemq::commands::MessagePull](#) (p. 2742), [activemq::commands::NetworkBridgeFilter](#) (p. 2795), [activemq::commands::PartialCommand](#) (p. 2920), [activemq::commands::ProducerAck](#) (p. 3038), [activemq::commands::ProducerId](#) (p. 3070), [activemq::commands::ProducerInfo](#) (p. 3099), [activemq::commands::RemoveInfo](#) (p. 3196), [activemq::commands::RemoveSubscriptionInfo](#) (p. 3225), [activemq::commands::ReplayCommand](#) (p. 3253), [activemq::commands::Response](#) (p. 3287), [activemq::commands::SessionId](#) (p. 3382), [activemq::commands::SessionInfo](#) (p. 3409), [activemq::commands::ShutdownInfo](#) (p. 3472), [activemq::commands::SubscriptionInfo](#) (p. 3674), [activemq::commands::TransactionId](#) (p. 3821), [activemq::commands::TransactionInfo](#) (p. 3849), [activemq::commands::WireFormatInfo](#) (p. 3991), and [activemq::commands::XATransactionId](#) (p. 4034).

Referenced by [activemq::commands::BooleanExpression::toString\(\)](#), and [activemq::commands::BaseCommand::toString\(\)](#).

The documentation for this class was generated from the following file:

- [src/main/activemq/commands/BaseDataStructure.h](#)

6.134 `binary_function` Class Reference

Inheritance diagram for `binary_function`:

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Comparator.h`

6.135 decaf::net::BindException Class Reference

#include <src/main/decaf/net/BindException.h> Inheritance diagram for decaf::net::BindException:

Public Member Functions

- **BindException** () throw ()
Default Constructor.
- **BindException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **BindException** (const **BindException** &ex) throw ()
Copy Constructor.
- **BindException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **BindException** (const std::exception *cause) throw ()
Constructor.
- **BindException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **BindException** * clone () const
Clones this exception.
- virtual ~**BindException** () throw ()

6.135.1 Constructor & Destructor Documentation

6.135.1.1 decaf::net::BindException::BindException () throw () [inline]

Default Constructor.

6.135.1.2 decaf::net::BindException::BindException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.135.1.3 `decaf::net::BindException::BindException (const BindException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.135.1.4 `decaf::net::BindException::BindException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.135.1.5 `decaf::net::BindException::BindException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.135.1.6 `decaf::net::BindException::BindException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.135.1.7 `virtual decaf::net::BindException::~~BindException () throw () [inline, virtual]`

6.135.2 Member Function Documentation

6.135.2.1 `virtual BindException* decaf::net::BindException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::net::SocketException** (p. 3522).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/BindException.h`

6.136 decaf::io::BlockingByteArrayInputStream Class Reference

This is a blocking version of a byte buffer stream.

#include <src/main/decaf/io/BlockingByteArrayInputStream.h> Inheritance diagram for decaf::io::BlockingByteArrayInputStream:

Public Member Functions

- **BlockingByteArrayInputStream** ()
*Default Constructor - uses a default **internal** (p. 144) buffer.*
- **BlockingByteArrayInputStream** (const unsigned char *buffer, int bufferSize)
*Constructor that initializes the **internal** (p. 144) buffer.*
- virtual ~**BlockingByteArrayInputStream** ()
- virtual void **setByteArray** (const unsigned char *buffer, int bufferSize)
- virtual int **available** () const throw (decaf::io::IOException)
*Indicates the number of bytes available.
The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.
The default implementation of this method returns zero.*
Returns:
the number of bytes available on this input stream.
Exceptions:
***IOException** (p. 2142) if an I/O error occurs.*
- virtual void **close** () throw (decaf::io::IOException)
*Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream.
The default implementation of this method does nothing.*
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
*Skips over and discards *n* bytes of data from this input stream.
The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until *num* bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*
Parameters:
***num** The number of bytes to skip.*

Returns:*total bytes skipped***Exceptions:**

IOException (p. 2142) if an I/O error occurs.
UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Protected Member Functions

- virtual int **doReadByte** () throw (IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.136.1 Detailed Description

This is a blocking version of a byte buffer stream. Read operations block until the requested data becomes available in the **internal** (p. 144) buffer via a call to **setByteArray**.

6.136.2 Constructor & Destructor Documentation**6.136.2.1 decaf::io::BlockingByteArrayInputStream::BlockingByteArrayInputStream ()**

Default Constructor - uses a default **internal** (p. 144) buffer.

6.136.2.2 decaf::io::BlockingByteArrayInputStream::BlockingByteArrayInputStream (const unsigned char * buffer, int bufferSize)

Constructor that initializes the **internal** (p. 144) buffer.

See also:

setByteArray (p. 841).

6.136.2.3 virtual decaf::io::BlockingByteArrayInputStream::~~BlockingByteArrayInputStream () [virtual]**6.136.3 Member Function Documentation****6.136.3.1 virtual int decaf::io::BlockingByteArrayInputStream::available () const throw (decaf::io::IOException) [virtual]**

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply

return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.136.3.2 `virtual void decaf::io::BlockingByteArrayInputStream::close () throw (decaf::io::IOException) [virtual]`

Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream.

The default implementation of this method does nothing.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.136.3.3 `virtual int decaf::io::BlockingByteArrayInputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]`

Reimplemented from **decaf::io::InputStream** (p. 2046).

6.136.3.4 `virtual int decaf::io::BlockingByteArrayInputStream::doReadByte () throw (IOException) [protected, virtual]`

Implements **decaf::io::InputStream** (p. 2046).

6.136.3.5 `virtual void decaf::io::BlockingByteArrayInputStream::setByteArray (const unsigned char * buffer, int bufferSize) [virtual]`

6.136.3.6 `virtual long long decaf::io::BlockingByteArrayInputStream::skip (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from **decaf::io::InputStream** (p. 2050).

The documentation for this class was generated from the following file:

- src/main/decaf/io/**BlockingByteArrayInputStream.h**

6.137 decaf::util::concurrent::BlockingQueue< E > Class Template Reference

A **decaf::util::Queue** (p. 3149) that additionally supports operations that wait for the queue to become non-empty when retrieving an element, and wait for space to become available in the queue when storing an element.

#include <src/main/decaf/util/concurrent/BlockingQueue.h> Inheritance diagram for decaf::util::concurrent::BlockingQueue< E >:

Public Member Functions

- virtual **~BlockingQueue** ()
- virtual void **put** (const E &value)=0 throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into this queue, waiting if necessary for space to become available.
- virtual bool **offer** (const E &e, long timeout, const **TimeUnit** &unit)=0 throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into this queue, waiting up to the specified wait time if necessary for space to become available.
- virtual E **take** ()=0 throw (decaf::lang::exceptions::InterruptedException)
Retrieves and removes the head of this queue, waiting if necessary until an element becomes available.
- virtual bool **poll** (E &result, long long timeout, const **TimeUnit** &unit)=0 throw (decaf::lang::exceptions::InterruptedException)
Retrieves and removes the head of this queue, waiting up to the specified wait time if necessary for an element to become available.
- virtual int **remainingCapacity** () const =0
*Returns the number of additional elements that this queue can ideally (in the absence of memory or resource constraints) accept without blocking, or **Integer::MAX_VALUE** if there is no intrinsic limit.*
- virtual std::size_t **drainTo** (**Collection**< E > &c)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException)
Removes all available elements from this queue and adds them to the given collection.
- virtual std::size_t **drainTo** (**Collection**< E > &c, std::size_t maxElements)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException)
Removes at most the given number of available elements from this queue and adds them to the given collection.

6.137.1 Detailed Description

`template<typename E> class decaf::util::concurrent::BlockingQueue< E >`

A **decaf::util::Queue** (p. 3149) that additionally supports operations that wait for the queue to become non-empty when retrieving an element, and wait for space to become available in the queue when storing an element. **BlockingQueue** (p. 843) methods come in four forms, with different ways of handling operations that cannot be satisfied immediately, but may be satisfied at some point in the future: one throws an exception, the second returns a special value (either **true** or **false**, depending on the operation), the third blocks the current thread indefinitely until the operation can succeed, and the fourth blocks for only a given maximum time limit before giving up. These methods are summarized in the following table:

	<i>Throws exception</i>	<i>Boolean Flag</i>	<i>Blocks</i>	<i>Times out</i>
Insert	add(e) (p. 195)	offer(e) (p. 847)	put(e) (p. 848)	offer(e, time, unit) (p. ??)
Remove	remove() (p. 196)	poll() (p. 847)	take() (p. 849)	poll(time, unit) (p. ??)
Examine	element() (p. 196)	peek() (p. 3151)	<i>not applicable</i>	<i>not applicable</i>

A **BlockingQueue** (p. 843) may be capacity bounded. At any given time it may have a **remainingCapacity** beyond which no additional elements can be **put** without blocking. A **BlockingQueue** (p. 843) without any intrinsic capacity constraints always reports a remaining capacity of **Integer::MAX_VALUE**.

BlockingQueue (p. 843) implementations are designed to be used primarily for producer-consumer queues, but additionally support **decaf::util::Collection** (p. 1184) interface. So, for example, it is possible to remove an arbitrary element from a queue using **remove(x)**. However, such operations are in general *not* performed very efficiently, and are intended for only occasional use, such as when a queued message is cancelled.

BlockingQueue (p. 843) implementations are thread-safe. All queuing methods achieve their effects atomically using **internal** (p. 144) **locks** (p. 174) or other forms of concurrency control. However, the *bulk* **Collection** (p. 1184) operations **addAll**, **containsAll**, **retainAll** and **removeAll** are *not* necessarily performed atomically unless specified otherwise in an implementation. So it is possible, for example, for **addAll(c)** to fail (throwing an exception) after adding only some of the elements in **c**.

A **BlockingQueue** (p. 843) does *not* intrinsically support any kind of "close" or "shutdown" operation to indicate that no more items will be added. The needs and usage of such features tend to be implementation-dependent. For example, a common tactic is for producers to insert special *end-of-stream* or *poison* objects, that are interpreted accordingly when taken by consumers.

Usage example, based on a typical producer-consumer scenario. Note that a **BlockingQueue** (p. 843) can safely be used with multiple producers and multiple consumers.

```
class Producer : public Runnable {
private:

    BlockingQueue* queue;

public:

    Producer( BlockingQueue* q ) : queue( q ) {}
```

```

    virtual void run() {
        try {
            while( true ) { queue->put( produce() ); }
        } catch( InterruptedException& ex ) { ... handle ...}
    }

    Object produce() { ... }
}

class Consumer : public Runnable {
private:

    BlockingQueue* queue;

public:

    Consumer( BlockingQueue* q ) : queue( q ) {}

    virtual void run() {
        try {
            while( true ) { consume( queue->take() (p.849) ); }
        } catch( InterruptedException& ex ) { ... handle ...}
    }

    void consume( Object& x ) { ... }
}

int main( int argc, char** argv ) {

    BlockingQueue (p.843) q = new SomeQueueImplementation();
    Producer p( &q );
    Consumer c1( &q );
    Consumer c2( &q );
    Thread t1( &p ).start();
    Thread t2( &c1 ).start();
    Thread t3( &c2 ).start();
}

```

Memory consistency effects: As with other **concurrent** (p.171) collections, actions in a thread prior to placing an object into a **BlockingQueue** (p.843) *happen-before* actions subsequent to the access or removal of that element from the **BlockingQueue** (p.843) in another thread.

Since:

1.0

6.137.2 Constructor & Destructor Documentation

6.137.2.1 `template<typename E > virtual decaf::util::concurrent::BlockingQueue< E >::~~BlockingQueue () [inline, virtual]`

6.137.3 Member Function Documentation

6.137.3.1 `template<typename E > virtual std::size_t decaf::util::concurrent::BlockingQueue< E >::drainTo (Collection< E > & c, std::size_t maxElements) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException) [pure virtual]`

Removes at most the given number of available elements from this queue and adds them to the given collection. A failure encountered while attempting to add elements to collection *c* may result in elements being in neither, either or both collections when the associated exception is thrown. Attempts to drain a queue to itself result in `IllegalArgumentException`. Further, the behavior of this operation is undefined if the specified collection is modified while the operation is in progress.

Parameters:

c the collection to transfer elements into
maxElements the maximum number of elements to transfer

Returns:

the number of elements transferred

Exceptions:

UnsupportedOperationException if addition of elements is not supported by the specified collection
IllegalArgumentException if the specified collection is this queue, or some property of an element of this queue prevents it from being added to the specified collection

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3719).

6.137.3.2 `template<typename E > virtual std::size_t decaf::util::concurrent::BlockingQueue< E >::drainTo (Collection< E > & c) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException) [pure virtual]`

Removes all available elements from this queue and adds them to the given collection. This operation may be more efficient than repeatedly polling this queue. A failure encountered while attempting to add elements to collection *c* may result in elements being in neither, either or both collections when the associated exception is thrown. Attempts to drain a queue to itself result in `IllegalArgumentException`. Further, the behavior of this operation is undefined if the specified collection is modified while the operation is in progress.

Parameters:

c the collection to transfer elements into

Returns:

the number of elements transferred

Exceptions:

UnsupportedOperationException if addition of elements is not supported by the specified collection

IllegalArgumentExcepion if the specified collection is this queue, or some property of an element of this queue prevents it from being added to the specified collection

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3720).

6.137.3.3 `template<typename E > virtual bool
decaf::util::concurrent::BlockingQueue< E >::offer
(const E & e, long timeout, const TimeUnit & unit)
throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::exceptions::NullPointerException, de-
caaf::lang::exceptions::IllegalArgumentExcepion) [pure
virtual]`

Inserts the specified element into this queue, waiting up to the specified wait time if necessary for space to become available.

Parameters:

e the element to add

timeout how long to wait before giving up, in units of *unit*

unit a `TimeUnit` (p. 3807) determining how to interpret the *timeout* parameter

Returns:

`true` if successful, or `false` if the specified waiting time elapses before space is available

Exceptions:

InterruptedException if interrupted while waiting

NullPointerException if the specified element is null

IllegalArgumentExcepion if some property of the specified element prevents it from being added to this queue

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3722).

6.137.3.4 `template<typename E > virtual bool
decaf::util::concurrent::BlockingQueue< E >::poll (E &
result, long long timeout, const TimeUnit & unit) throw (
decaf::lang::exceptions::InterruptedException) [pure virtual]`

Retrieves and removes the head of this queue, waiting up to the specified wait time if necessary for an element to become available.

Parameters:

result the referenced value that will be assigned the value retrieved from the **Queue** (p. 3149). Undefined if this methods returned false.

timeout how long to wait before giving up, in units of *unit*

unit a TimeUnit (p. 3807) determining how to interpret the `timeout` parameter.

Returns:

`true` if successful or `false` if the specified waiting time elapses before an element is available.

Exceptions:

InterruptedException if interrupted while waiting

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3722).

6.137.3.5 `template<typename E > virtual void
decaf::util::concurrent::BlockingQueue< E >::put (const E
& value) throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::exceptions::NullPointerException, de-
caf::lang::exceptions::IllegalArgumentException) [pure
virtual]`

Inserts the specified element into this queue, waiting if necessary for space to become available.

Parameters:

value the element to add

Exceptions:

InterruptedException if interrupted while waiting

NullPointerException if the specified element is null

IllegalArgumentException if some property of the specified element prevents it from being added to this queue

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3723).

6.137.3.6 `template<typename E > virtual int
decaf::util::concurrent::BlockingQueue< E >::remainingCapacity () const
[pure virtual]`

Returns the number of additional elements that this queue can ideally (in the absence of memory or resource constraints) accept without blocking, or `Integer::MAX_VALUE` if there is no intrinsic limit. Note that you *cannot* always tell if an attempt to insert an element will succeed by inspecting `remainingCapacity` because it may be the case that another thread is about to insert or remove an element.

Returns:

the remaining capacity

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3723).

```
6.137.3.7  template<typename E > virtual E  
            decaf::util::concurrent::BlockingQueue< E >::take ()  
            throw ( decaf::lang::exceptions::InterruptedException ) [pure virtual]
```

Retrieves and removes the head of this queue, waiting if necessary until an element becomes available.

Returns:

the head of this queue

Exceptions:

InterruptedException if interrupted while waiting

Implemented in **decaf::util::concurrent::SynchronousQueue< E >** (p. 3724).

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/**BlockingQueue.h**

6.138 decaf::lang::Boolean Class Reference

#include <src/main/decaf/lang/Boolean.h> Inheritance diagram for decaf::lang::Boolean:

Public Member Functions

- **Boolean** (bool value)
- **Boolean** (const std::string &value)
- virtual ~**Boolean** ()
- bool **booleanValue** () const
- std::string **toString** () const
- virtual int **compareTo** (const **Boolean** &b) const
*Compares this **Boolean** (p. 850) instance with another.*
- virtual bool **operator==** (const **Boolean** &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Boolean** &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- bool **equals** (const **Boolean** &b) const
- virtual int **compareTo** (const bool &b) const
*Compares this **Boolean** (p. 850) instance with another.*
- virtual bool **operator==** (const bool &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const bool &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- bool **equals** (const bool &b) const

Static Public Member Functions

- static **Boolean** **valueOf** (bool value)
- static **Boolean** **valueOf** (const std::string &value)
- static bool **parseBoolean** (const std::string &value)
*Parses the **String** (p. 3665) passed and extracts an bool.*
- static std::string **toString** (bool value)
*Converts the bool to a **String** (p. 3665) representation.*

Static Public Attributes

- static const **Boolean** **_FALSE**

The Class object representing the primitive false boolean.

- static const **Boolean** **_TRUE**

The Class object representing the primitive type boolean.

6.138.1 Constructor & Destructor Documentation

6.138.1.1 `decaf::lang::Boolean::Boolean (bool value)`

Parameters:

value - primitive boolean to wrap.

6.138.1.2 `decaf::lang::Boolean::Boolean (const std::string & value)`

Parameters:

value - **String** (p. 3665) value to convert to a boolean.

6.138.1.3 `virtual decaf::lang::Boolean::~~Boolean ()` [inline, virtual]

6.138.2 Member Function Documentation

6.138.2.1 `bool decaf::lang::Boolean::booleanValue () const` [inline]

Returns:

the primitive boolean value of this object

6.138.2.2 `virtual int decaf::lang::Boolean::compareTo (const bool & b) const` [virtual]

Compares this **Boolean** (p. 850) instance with another.

Parameters:

b - the **Boolean** (p. 850) instance to be compared

Returns:

zero if this object represents the same boolean value as the argument; a positive value if this object represents true and the argument represents false; and a negative value if this object represents false and the argument represents true

Implements **decaf::lang::Comparable**< **bool** > (p. 1214).

6.138.2.3 `virtual int decaf::lang::Boolean::compareTo (const Boolean & b) const`
[virtual]

Compares this **Boolean** (p. 850) instance with another.

Parameters:

b - the **Boolean** (p. 850) instance to be compared

Returns:

zero if this object represents the same boolean value as the argument; a positive value if this object represents true and the argument represents false; and a negative value if this object represents false and the argument represents true

6.138.2.4 `bool decaf::lang::Boolean::equals (const bool & b) const` [inline,
virtual]**Returns:**

true if the two **Boolean** (p. 850) Objects have the same value.

Implements **decaf::lang::Comparable**< **bool** > (p. 1215).

6.138.2.5 `bool decaf::lang::Boolean::equals (const Boolean & b) const` [inline]**Returns:**

true if the two **Boolean** (p. 850) Objects have the same value.

6.138.2.6 `virtual bool decaf::lang::Boolean::operator< (const bool & value) const`
[virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable**< **bool** > (p. 1215).

6.138.2.7 `virtual bool decaf::lang::Boolean::operator< (const Boolean & value)`
`const` [virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.138.2.8 `virtual bool decaf::lang::Boolean::operator==(const bool & value) const`
[virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< bool >` (p. 1215).

6.138.2.9 `virtual bool decaf::lang::Boolean::operator==(const Boolean & value)`
`const` [virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.138.2.10 `static bool decaf::lang::Boolean::parseBoolean(const std::string &`
`value)` [static]

Parses the **String** (p. 3665) passed and extracts an bool.

Parameters:

value The std::string value to parse

Returns:

bool value

6.138.2.11 static std::string decaf::lang::Boolean::toString (bool *value*) [static]

Converts the bool to a **String** (p. 3665) representation.

Parameters:

value The bool value to convert.

Returns:

std::string representation of the bool value passed.

6.138.2.12 std::string decaf::lang::Boolean::toString () const**Returns:**

the string representation of this Booleans value.

6.138.2.13 static Boolean decaf::lang::Boolean::valueOf (const std::string & *value*) [static]**Parameters:**

value The std::string value to convert to a Boolean (p. 850) instance.

Returns:

a **Boolean** (p. 850) instance of the string value

6.138.2.14 static Boolean decaf::lang::Boolean::valueOf (bool *value*) [static]**Parameters:**

value The bool value to convert to a Boolean (p. 850) instance.

Returns:

a **Boolean** (p. 850) instance of the primitive boolean value

6.138.3 Field Documentation**6.138.3.1 const Boolean decaf::lang::Boolean::_FALSE [static]**

The Class object representing the primitive false boolean.

6.138.3.2 const Boolean decaf::lang::Boolean::_TRUE [static]

The Class object representing the primitive type boolean.

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Boolean.h**

6.139 activemq::commands::BooleanExpression Class Reference

#include <src/main/activemq/commands/BooleanExpression.h> Inheritance diagram for activemq::commands::BooleanExpression:

Public Member Functions

- **BooleanExpression** ()
- virtual **~BooleanExpression** ()
- virtual **DataStructure * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src AMQCPP_UNUSED)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

6.139.1 Constructor & Destructor Documentation

- 6.139.1.1** **activemq::commands::BooleanExpression::BooleanExpression** ()
[inline]
- 6.139.1.2** **virtual activemq::commands::BooleanExpression::~~BooleanExpression** ()
[inline, virtual]

6.139.2 Member Function Documentation

- 6.139.2.1** **virtual DataStructure* activemq::commands::BooleanExpression::cloneDataStructure** () const
[inline, virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.139.2.2 virtual void activemq::commands::BooleanExpression::copyDataStructure (const DataStructure *src *AMQCPP_UNUSED*) [inline, virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::BaseDataStructure** (p. 832).

6.139.2.3 virtual bool activemq::commands::BooleanExpression::equals (const DataStructure * *value*) const [inline, virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

References **activemq::commands::BaseDataStructure::equals()**.

6.139.2.4 virtual std::string activemq::commands::BooleanExpression::toString () const [inline, virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p. 833).

References **activemq::commands::BaseDataStructure::toString()**.

The documentation for this class was generated from the following file:

- src/main/activemq/commands/**BooleanExpression.h**

6.140 activemq::wireformat::openwire::utils::BooleanStream Class Reference

Manages the writing and reading of boolean data streams to and from a data source such as a `DataInputStream` or `DataOutputStream`.

```
#include <src/main/activemq/wireformat/openwire/utils/BooleanStream.h>
```

Public Member Functions

- **BooleanStream** ()
- virtual **~BooleanStream** ()
- bool **readBoolean** () throw (decaf::io::IOException)
Read a boolean data element from the internal data buffer.
- void **writeBoolean** (bool value) throw (decaf::io::IOException)
Writes a Boolean value to the internal data buffer.
- void **marshal** (decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)
Marshal the data to a DataOutputStream.
- void **marshal** (std::vector< unsigned char > &dataOut)
Marshal the data to a STL vector of unsigned chars.
- void **unmarshal** (decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)
Unmarshal a Boolean data stream from the Input Stream.
- void **clear** ()
Clears to old position markers, data starts at the beginning.
- int **marshalledSize** ()
Calc the size that data is marshalled to.

6.140.1 Detailed Description

Manages the writing and reading of boolean data streams to and from a data source such as a `DataInputStream` or `DataOutputStream`. The booleans are stored as single bits in the stream, with the stream size pre-pended to the stream when the data is marshalled.

The serialized form of the size field can be between 1 and 3 bytes. If the number of used bytes < 64, size=1 byte If the number of used bytes >=64 and < 256 (size of an unsigned byte), size=2 bytes If the number of used bytes >=256, size=3 bytes

The high-order 2 bits (128 and 64) of the first byte of the size field are used to encode the information about the number of bytes in the size field. The only time the first byte will contain a value >=64 is if there are more bytes in the size field. If the first byte < 64, the value of the byte is simply the size value. If the first byte = 0xC0, the following unsigned byte is the size field. If the first byte = 0x80, the following short (two bytes) are the size field.

6.140.2 Constructor & Destructor Documentation

6.140.2.1 `activemq::wireformat::openwire::utils::BooleanStream::BooleanStream ()`

6.140.2.2 `virtual
activemq::wireformat::openwire::utils::BooleanStream::~~BooleanStream
() [inline, virtual]`

6.140.3 Member Function Documentation

6.140.3.1 `void activemq::wireformat::openwire::utils::BooleanStream::clear ()`

Clears to old position markers, data starts at the beginning.

6.140.3.2 `void activemq::wireformat::openwire::utils::BooleanStream::marshal
(std::vector< unsigned char > & dataOut)`

Marshal the data to a STL vector of unsigned chars.

Parameters:

dataOut - reference to a vector to write the data to.

6.140.3.3 `void activemq::wireformat::openwire::utils::BooleanStream::marshal
(decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)`

Marshal the data to a DataOutputStream.

Parameters:

dataOut - Stream to write the data to.

6.140.3.4 `int activemq::wireformat::openwire::utils::BooleanStream::marshalledSize
()`

Calc the size that data is marshalled to.

Returns:

int size of marshalled data.

6.140.3.5 `bool activemq::wireformat::openwire::utils::BooleanStream::readBoolean
() throw (decaf::io::IOException)`

Read a boolean data element from the internal data buffer.

Returns:

boolean from the stream

6.140.3.6 `void activemq::wireformat::openwire::utils::BooleanStream::unmarshal
 (decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)`

Unmarshal a Boolean data stream from the Input Stream.

Parameters:

dataIn - Input Stream to read data from.

6.140.3.7 `void activemq::wireformat::openwire::utils::BooleanStream::writeBoolean
 (bool value) throw (decaf::io::IOException)`

Writes a Boolean value to the internal data buffer.

Parameters:

value - boolean data to write.

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/utils/BooleanStream.h`

6.141 decaf::util::concurrent::BrokenBarrierException Class Reference

#include <src/main/decaf/util/concurrent/BrokenBarrierException.h> Inheritance diagram for decaf::util::concurrent::BrokenBarrierException:

Public Member Functions

- **BrokenBarrierException** () throw ()
Default Constructor.
- **BrokenBarrierException** (const decaf::lang::Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **BrokenBarrierException** (const **BrokenBarrierException** &ex) throw ()
Copy Constructor.
- **BrokenBarrierException** (const std::exception *cause) throw ()
Constructor.
- **BrokenBarrierException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **BrokenBarrierException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **BrokenBarrierException** * clone () const
Clones this exception.
- virtual ~**BrokenBarrierException** () throw ()

6.141.1 Constructor & Destructor Documentation

6.141.1.1 decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException () throw () [inline]

Default Constructor.

6.141.1.2 decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References `decaf::lang::Exception::Exception()`.

6.141.1.3 `decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException (const BrokenBarrierException & ex) throw ()` [inline]

Copy Constructor.

Parameters:

ex The Exception to copy in this new instance.

References `decaf::lang::Exception::Exception()`.

6.141.1.4 `decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException (const std::exception * cause) throw ()` [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.141.1.5 `decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException (const char * file, const int lineNumber, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs
lineNumber - The line number where the exception occurred.
msg - The message to report
... - list of primitives that are formatted into the message

6.141.1.6 `decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs
lineNumber - The line number where the exception occurred.
cause - The exception that was the cause for this one to be thrown.
msg - The message to report
... - list of primitives that are formatted into the message

6.141.1.7 **virtual**
 decaf::util::concurrent::BrokenBarrierException::~~BrokenBarrierException
 () throw () [inline, virtual]

6.141.2 Member Function Documentation

6.141.2.1 **virtual BrokenBarrierException* de-**
 caf::util::concurrent::BrokenBarrierException::clone ()
 const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an exception that is a clone of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/BrokenBarrierException.h`

6.142 activemq::commands::BrokerError Class Reference

This class represents an Exception sent from the Broker.

#include <src/main/activemq/commands/BrokerError.h> Inheritance diagram for activemq::commands::BrokerError:

Data Structures

- struct **StackTraceElement**

Public Member Functions

- **BrokerError** ()
- virtual **~BrokerError** ()
- virtual unsigned char **getDataStructureType** () const
*Get the **DataStructure** (p. 1660) Type as defined in **CommandTypes.h**.*
- virtual **BrokerError** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual **decaf::lang::Pointer**< **commands::Command** > **visit** (**activemq::state::CommandVisitor** *visitor) throw (**exceptions::ActiveMQException**)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.
- virtual const std::string & **getMessage** () const
Gets the string holding the error message.
- virtual void **setMessage** (const std::string &message)
*Sets the string that contains the error **Message** (p. 2516).*
- virtual const std::string & **getExceptionClass** () const
Gets the string holding the Exception Class name.
- virtual void **setExceptionClass** (const std::string &exceptionClass)
Sets the string that contains the Exception Class name.
- virtual const **decaf::lang::Pointer**< **BrokerError** > & **getCause** () const
Gets the Broker Error that caused this exception.
- virtual void **setCause** (const **decaf::lang::Pointer**< **BrokerError** > &cause)
Sets the Broker Error that caused this exception.

- virtual const std::vector< **decaf::lang::Pointer< StackTraceElement > >** & **getStackTraceElements** () const
Gets the Stack Trace Elements for the Exception.
- virtual void **setStackTraceElements** (const std::vector< **decaf::lang::Pointer< StackTraceElement > >** & stackTraceElements)
Sets the Stack Trace Elements for this Exception.

6.142.1 Detailed Description

This class represents an Exception sent from the Broker. The Broker sends java Throwables, so we must mimic its structure here.

6.142.2 Constructor & Destructor Documentation

6.142.2.1 **activemq::commands::BrokerError::BrokerError** ()

6.142.2.2 **virtual activemq::commands::BrokerError::~~BrokerError** () [virtual]

6.142.3 Member Function Documentation

6.142.3.1 **virtual BrokerError* activemq::commands::BrokerError::cloneDataStructure** ()
const [inline, virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

References `copyDataStructure()`.

6.142.3.2 **virtual void activemq::commands::BrokerError::copyDataStructure**
(const **DataStructure** * *src*) [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

Referenced by `cloneDataStructure()`.

6.142.3.3 `virtual const decaf::lang::Pointer<BrokerError>& activemq::commands::BrokerError::getCause () const [inline, virtual]`

Gets the Broker Error that caused this exception.

Returns:

Broker Error Pointer

6.142.3.4 `virtual unsigned char activemq::commands::BrokerError::getDataStructureType () const [inline, virtual]`

Get the **DataStructure** (p.1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Implements **activemq::commands::DataStructure** (p.1662).

6.142.3.5 `virtual const std::string& activemq::commands::BrokerError::getExceptionClass () const [inline, virtual]`

Gets the string holding the Exception Class name.

Returns:

Exception Class name

6.142.3.6 `virtual const std::string& activemq::commands::BrokerError::getMessage () const [inline, virtual]`

Gets the string holding the error message.

Returns:

String Message (p.2516)

6.142.3.7 `virtual const std::vector< decaf::lang::Pointer<StackTraceElement> >& activemq::commands::BrokerError::getStackTraceElements () const [inline, virtual]`

Gets the Stack Trace Elements for the Exception.

Returns:

Stack Trace Elements

6.142.3.8 `virtual void activemq::commands::BrokerError::setCause (const decaf::lang::Pointer< BrokerError > & cause)` [inline, virtual]

Sets the Broker Error that caused this exception.

Parameters:

cause - Broker Error

6.142.3.9 `virtual void activemq::commands::BrokerError::setExceptionClass (const std::string & exceptionClass)` [inline, virtual]

Sets the string that contains the Exception Class name.

Parameters:

exceptionClass - String Exception Class name

6.142.3.10 `virtual void activemq::commands::BrokerError::setMessage (const std::string & message)` [inline, virtual]

Sets the string that contains the error **Message** (p.2516).

Parameters:

message - String Error **Message** (p.2516)

6.142.3.11 `virtual void activemq::commands::BrokerError::setStackTraceElements (const std::vector< decaf::lang::Pointer< StackTraceElement > > & stackTraceElements)` [inline, virtual]

Sets the Stack Trace Elements for this Exception.

Parameters:

stackTraceElements - Stack Trace Elements

6.142.3.12 `virtual decaf::lang::Pointer<commands::Command> activemq::commands::BrokerError::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p.3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

The documentation for this class was generated from the following file:

- src/main/activemq/commands/**BrokerError.h**

6.143 activemq::exceptions::BrokerException Class Reference

#include <src/main/activemq/exceptions/BrokerException.h> Inheritance diagram for activemq::exceptions::BrokerException:

Public Member Functions

- **BrokerException** () throw ()
- **BrokerException** (const exceptions::ActiveMQException &ex) throw ()
- **BrokerException** (const **BrokerException** &ex) throw ()
- **BrokerException** (const char *file, const int lineNumber, const char *msg,...) throw ()
- **BrokerException** (const char *file, const int lineNumber, const commands::BrokerError *error) throw ()
- virtual **BrokerException** * clone () const
Clones this exception.
- virtual ~**BrokerException** () throw ()

6.143.1 Constructor & Destructor Documentation

- 6.143.1.1 **activemq::exceptions::BrokerException::BrokerException () throw ()**
[inline]
- 6.143.1.2 **activemq::exceptions::BrokerException::BrokerException (const exceptions::ActiveMQException & ex) throw ()** [inline]
- 6.143.1.3 **activemq::exceptions::BrokerException::BrokerException (const BrokerException & ex) throw ()** [inline]
- 6.143.1.4 **activemq::exceptions::BrokerException::BrokerException (const char * file, const int lineNumber, const char * msg, ...) throw ()** [inline]
- 6.143.1.5 **activemq::exceptions::BrokerException::BrokerException (const char * file, const int lineNumber, const commands::BrokerError * error) throw ()** [inline]

References decaf::lang::Exception::setMark(), and decaf::lang::Exception::setMessage().

- 6.143.1.6 **virtual activemq::exceptions::BrokerException::~~BrokerException () throw ()** [inline, virtual]

6.143.2 Member Function Documentation

- 6.143.2.1 **virtual BrokerException* activemq::exceptions::BrokerException::clone () const** [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Reimplemented from `activemq::exceptions::ActiveMQException` (p. 358).

The documentation for this class was generated from the following file:

- `src/main/activemq/exceptions/BrokerException.h`

6.144 activemq::commands::BrokerId Class Reference

#include <src/main/activemq/commands/BrokerId.h> Inheritance diagram for activemq::commands::BrokerId:

Public Types

- typedef decaf::lang::PointerComparator< BrokerId > COMPARATOR

Public Member Functions

- **BrokerId** ()
- **BrokerId** (const **BrokerId** &other)
- virtual ~**BrokerId** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **BrokerId** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getValue** () const
- virtual std::string & **getValue** ()
- virtual void **setValue** (const std::string &value)
- virtual int **compareTo** (const **BrokerId** &value) const
- virtual bool **equals** (const **BrokerId** &value) const
- virtual bool **operator==** (const **BrokerId** &value) const
- virtual bool **operator<** (const **BrokerId** &value) const
- **BrokerId** & **operator=** (const **BrokerId** &other)

Static Public Attributes

- static const unsigned char **ID_BROKERID** = 124

Protected Attributes

- std::string value

6.144.1 Member Typedef Documentation

6.144.1.1 `typedef decaf::lang::PointerComparator<BrokerId>
activemq::commands::BrokerId::COMPARATOR`

6.144.2 Constructor & Destructor Documentation

6.144.2.1 `activemq::commands::BrokerId::BrokerId ()`

6.144.2.2 `activemq::commands::BrokerId::BrokerId (const BrokerId & other)`

6.144.2.3 `virtual activemq::commands::BrokerId::~~BrokerId () [virtual]`

6.144.3 Member Function Documentation

6.144.3.1 `virtual BrokerId* activemq::commands::BrokerId::cloneDataStructure ()
const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.144.3.2 `virtual int activemq::commands::BrokerId::compareTo (const BrokerId &
value) const [virtual]`

6.144.3.3 `virtual void activemq::commands::BrokerId::copyDataStructure (const
DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.144.3.4 `virtual bool activemq::commands::BrokerId::equals (const BrokerId &
value) const [virtual]`

6.144.3.5 `virtual bool activemq::commands::BrokerId::equals (const DataStructure
* value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.144.3.6 `virtual unsigned char activemq::commands::BrokerId::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.144.3.7 `virtual std::string& activemq::commands::BrokerId::getValue () [virtual]`

6.144.3.8 `virtual const std::string& activemq::commands::BrokerId::getValue () const [virtual]`

6.144.3.9 `virtual bool activemq::commands::BrokerId::operator< (const BrokerId & value) const [virtual]`

6.144.3.10 `BrokerId& activemq::commands::BrokerId::operator= (const BrokerId & other)`

6.144.3.11 `virtual bool activemq::commands::BrokerId::operator== (const BrokerId & value) const [virtual]`

6.144.3.12 `virtual void activemq::commands::BrokerId::setValue (const std::string & value) [virtual]`

6.144.3.13 `virtual std::string activemq::commands::BrokerId::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p. 833).

6.144.4 Field Documentation

6.144.4.1 `const unsigned char activemq::commands::BrokerId::ID_BROKERID = 124 [static]`

6.144.4.2 `std::string activemq::commands::BrokerId::value [protected]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/BrokerId.h`

6.145 activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 872).

#include <src/main/activemq/wireformat/openwire/marshal/v3/BrokerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller:

Public Member Functions

- **BrokerIdMarshaller** ()
- virtual **~BrokerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.145.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 872). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.145.2 Constructor & Destructor Documentation

6.145.2.1 `activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.145.2.2 `virtual activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.145.3 Member Function Documentation

6.145.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.145.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.145.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.145.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.145.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.145.3.6 virtual void activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.145.3.7 virtual void activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**BrokerIdMarshaller.h**

6.146 `activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller` Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 876).

`#include <src/main/activemq/wireformat/openwire/marshal/v4/BrokerIdMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller`:

Public Member Functions

- `BrokerIdMarshaller ()`
- `virtual ~BrokerIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.146.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 876). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.146.2 Constructor & Destructor Documentation

6.146.2.1 `activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.146.2.2 `virtual activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.146.3 Member Function Documentation

6.146.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.146.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.146.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.146.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.146.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.146.3.6 virtual void activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.146.3.7 virtual void activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**BrokerIdMarshaller.h**

6.147 activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 880).

#include <src/main/activemq/wireformat/openwire/marshal/v1/BrokerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller:

Public Member Functions

- **BrokerIdMarshaller** ()
- virtual **~BrokerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.147.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 880). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.147.2 Constructor & Destructor Documentation

6.147.2.1 `activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.147.2.2 `virtual activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.147.3 Member Function Documentation

6.147.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.147.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.147.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.147.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.147.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.147.3.6 virtual void activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.147.3.7 virtual void activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**BrokerIdMarshaller.h**

6.148 activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 884).

#include <src/main/activemq/wireformat/openwire/marshal/v5/BrokerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller:

Public Member Functions

- **BrokerIdMarshaller** ()
- virtual **~BrokerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.148.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 884). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.148.2 Constructor & Destructor Documentation

6.148.2.1 `activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.148.2.2 `virtual activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.148.3 Member Function Documentation

6.148.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.148.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.148.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.148.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.148.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.148.3.6 virtual void activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.148.3.7 virtual void activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**BrokerIdMarshaller.h**

6.149 `activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller` Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 888).

`#include <src/main/activemq/wireformat/openwire/marshal/v6/BrokerIdMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller`:

Public Member Functions

- `BrokerIdMarshaller ()`
- `virtual ~BrokerIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.149.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 888). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.149.2 Constructor & Destructor Documentation

6.149.2.1 `activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.149.2.2 `virtual activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.149.3 Member Function Documentation

6.149.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.149.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.149.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.149.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.149.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.149.3.6 virtual void activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.149.3.7 virtual void activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**BrokerIdMarshaller.h**

6.150 `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller` Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 892).

`#include <src/main/activemq/wireformat/openwire/marshal/v2/BrokerIdMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller`:

Public Member Functions

- `BrokerIdMarshaller ()`
- `virtual ~BrokerIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.150.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `BrokerIdMarshaller` (p. 892). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.150.2 Constructor & Destructor Documentation

6.150.2.1 `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::BrokerIdMarshaller()` [inline]

6.150.2.2 `virtual activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::~~BrokerIdMarshaller()` [inline, virtual]

6.150.3 Member Function Documentation

6.150.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.150.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.150.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.150.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.150.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.150.3.6 virtual void activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.150.3.7 virtual void activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**BrokerIdMarshaller.h**

6.151 activemq::commands::BrokerInfo Class Reference

#include <src/main/activemq/commands/BrokerInfo.h> Inheritance diagram for activemq::commands::BrokerInfo:

Public Member Functions

- **BrokerInfo** ()
- virtual **~BrokerInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **BrokerInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **BrokerId** > & **getBrokerId** () const
- virtual **Pointer**< **BrokerId** > & **getBrokerId** ()
- virtual void **setBrokerId** (const **Pointer**< **BrokerId** > &brokerId)
- virtual const std::string & **getBrokerURL** () const
- virtual std::string & **getBrokerURL** ()
- virtual void **setBrokerURL** (const std::string &brokerURL)
- virtual const std::vector< **decaf::lang::Pointer**< **BrokerInfo** > > & **getPeerBrokerInfos** () const
- virtual std::vector< **decaf::lang::Pointer**< **BrokerInfo** > > & **getPeerBrokerInfos** ()
- virtual void **setPeerBrokerInfos** (const std::vector< **decaf::lang::Pointer**< **BrokerInfo** > > &peerBrokerInfos)
- virtual const std::string & **getBrokerName** () const
- virtual std::string & **getBrokerName** ()
- virtual void **setBrokerName** (const std::string &brokerName)
- virtual bool **isSlaveBroker** () const
- virtual void **setSlaveBroker** (bool slaveBroker)
- virtual bool **isMasterBroker** () const
- virtual void **setMasterBroker** (bool masterBroker)
- virtual bool **isFaultTolerantConfiguration** () const
- virtual void **setFaultTolerantConfiguration** (bool faultTolerantConfiguration)
- virtual bool **isDuplexConnection** () const
- virtual void **setDuplexConnection** (bool duplexConnection)

- virtual bool **isNetworkConnection** () const
- virtual void **setNetworkConnection** (bool **networkConnection**)
- virtual long long **getConnectionId** () const
- virtual void **setConnectionId** (long long **connectionId**)
- virtual const std::string & **getBrokerUploadUrl** () const
- virtual std::string & **getBrokerUploadUrl** ()
- virtual void **setBrokerUploadUrl** (const std::string &**brokerUploadUrl**)
- virtual const std::string & **getNetworkProperties** () const
- virtual std::string & **getNetworkProperties** ()
- virtual void **setNetworkProperties** (const std::string &**networkProperties**)
- virtual bool **isBrokerInfo** () const
- virtual **Pointer< Command > visit** (**activemq::state::CommandVisitor** *visitor) throw (exceptions::ActiveMQException)

Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_BROKERINFO** = 2

Protected Attributes

- **Pointer< BrokerId > brokerId**
- std::string **brokerURL**
- std::vector< decaf::lang::Pointer< BrokerInfo > > **peerBrokerInfos**
- std::string **brokerName**
- bool **slaveBroker**
- bool **masterBroker**
- bool **faultTolerantConfiguration**
- bool **duplexConnection**
- bool **networkConnection**
- long long **connectionId**
- std::string **brokerUploadUrl**
- std::string **networkProperties**

6.151.1 Constructor & Destructor Documentation

6.151.1.1 **activemq::commands::BrokerInfo::BrokerInfo** ()

6.151.1.2 **virtual activemq::commands::BrokerInfo::~~BrokerInfo** () [virtual]

6.151.2 Member Function Documentation

6.151.2.1 **virtual BrokerInfo* activemq::commands::BrokerInfo::cloneDataStructure** () const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.151.2.2 virtual void activemq::commands::BrokerInfo::copyDataStructure (const DataStructure * *src*) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.151.2.3 virtual bool activemq::commands::BrokerInfo::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

- 6.151.2.4 `virtual Pointer<BrokerId>& activemq::commands::BrokerInfo::getBrokerId ()`
[virtual]
- 6.151.2.5 `virtual const Pointer<BrokerId>& activemq::commands::BrokerInfo::getBrokerId () const`
[virtual]
- 6.151.2.6 `virtual std::string& activemq::commands::BrokerInfo::getBrokerName ()`
[virtual]
- 6.151.2.7 `virtual const std::string& activemq::commands::BrokerInfo::getBrokerName () const`
[virtual]
- 6.151.2.8 `virtual std::string& activemq::commands::BrokerInfo::getBrokerUploadUrl ()`
[virtual]
- 6.151.2.9 `virtual const std::string& activemq::commands::BrokerInfo::getBrokerUploadUrl () const` [virtual]
- 6.151.2.10 `virtual std::string& activemq::commands::BrokerInfo::getBrokerURL ()`
[virtual]
- 6.151.2.11 `virtual const std::string& activemq::commands::BrokerInfo::getBrokerURL () const`
[virtual]
- 6.151.2.12 `virtual long long activemq::commands::BrokerInfo::getConnectionId () const` [virtual]
- 6.151.2.13 `virtual unsigned char activemq::commands::BrokerInfo::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.151.2.14 `virtual std::string& activemq::commands::BrokerInfo::getNetworkProperties ()`
[virtual]
- 6.151.2.15 `virtual const std::string& activemq::commands::BrokerInfo::getNetworkProperties ()`
`const` [virtual]
- 6.151.2.16 `virtual std::vector< decaf::lang::Pointer<BrokerInfo> >& activemq::commands::BrokerInfo::getPeerBrokerInfos ()` [virtual]
- 6.151.2.17 `virtual const std::vector< decaf::lang::Pointer<BrokerInfo> >& activemq::commands::BrokerInfo::getPeerBrokerInfos ()` `const`
[virtual]
- 6.151.2.18 `virtual bool activemq::commands::BrokerInfo::isBrokerInfo ()` `const`
[inline, virtual]

Returns:

an answer of true to the `isBrokerInfo()` (p. 900) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 760).

- 6.151.2.19 `virtual bool activemq::commands::BrokerInfo::isDuplexConnection () const [virtual]`
- 6.151.2.20 `virtual bool activemq::commands::BrokerInfo::isFaultTolerantConfiguration () const [virtual]`
- 6.151.2.21 `virtual bool activemq::commands::BrokerInfo::isMasterBroker () const [virtual]`
- 6.151.2.22 `virtual bool activemq::commands::BrokerInfo::isNetworkConnection () const [virtual]`
- 6.151.2.23 `virtual bool activemq::commands::BrokerInfo::isSlaveBroker () const [virtual]`
- 6.151.2.24 `virtual void activemq::commands::BrokerInfo::setBrokerId (const Pointer< BrokerId > & brokerId) [virtual]`
- 6.151.2.25 `virtual void activemq::commands::BrokerInfo::setBrokerName (const std::string & brokerName) [virtual]`
- 6.151.2.26 `virtual void activemq::commands::BrokerInfo::setBrokerUploadUrl (const std::string & brokerUploadUrl) [virtual]`
- 6.151.2.27 `virtual void activemq::commands::BrokerInfo::setBrokerURL (const std::string & brokerURL) [virtual]`
- 6.151.2.28 `virtual void activemq::commands::BrokerInfo::setConnectionId (long long connectionId) [virtual]`
- 6.151.2.29 `virtual void activemq::commands::BrokerInfo::setDuplexConnection (bool duplexConnection) [virtual]`
- 6.151.2.30 `virtual void activemq::commands::BrokerInfo::setFaultTolerantConfiguration (bool faultTolerantConfiguration) [virtual]`
- 6.151.2.31 `virtual void activemq::commands::BrokerInfo::setMasterBroker (bool masterBroker) [virtual]`
- 6.151.2.32 `virtual void activemq::commands::BrokerInfo::setNetworkConnection (bool networkConnection) [virtual]`
- 6.151.2.33 `virtual void activemq::commands::BrokerInfo::setNetworkProperties (const std::string & networkProperties) [virtual]`
- 6.151.2.34 `virtual void activemq::commands::BrokerInfo::setPeerBrokerInfos (const std::vector< decaf::lang::Pointer< BrokerInfo > > & peerBrokerInfos) [virtual]`
- 6.151.2.35 `virtual void activemq::commands::BrokerInfo::setSlaveBroker (bool slaveBroker) [virtual]`
- 6.151.2.36 `virtual std::string activemq::commands::BrokerInfo::toString () const [virtual]` Generated on Wed Nov 10 22:25:45 2010 for activemq-cpp-3.2.3 by Doxygen

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.151.2.37 `virtual Pointer<Command> activemq::commands::BrokerInfo::visit
(activemq::state::CommandVisitor * visitor) throw (
exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.151.3 Field Documentation

- 6.151.3.1 `Pointer<BrokerId> activemq::commands::BrokerInfo::brokerId` [protected]
- 6.151.3.2 `std::string activemq::commands::BrokerInfo::brokerName` [protected]
- 6.151.3.3 `std::string activemq::commands::BrokerInfo::brokerUploadUrl` [protected]
- 6.151.3.4 `std::string activemq::commands::BrokerInfo::brokerURL` [protected]
- 6.151.3.5 `long long activemq::commands::BrokerInfo::connectionId` [protected]
- 6.151.3.6 `bool activemq::commands::BrokerInfo::duplexConnection` [protected]
- 6.151.3.7 `bool activemq::commands::BrokerInfo::faultTolerantConfiguration` [protected]
- 6.151.3.8 `const unsigned char activemq::commands::BrokerInfo::ID_ -
BROKERINFO = 2` [static]
- 6.151.3.9 `bool activemq::commands::BrokerInfo::masterBroker` [protected]
- 6.151.3.10 `bool activemq::commands::BrokerInfo::networkConnection` [protected]
- 6.151.3.11 `std::string activemq::commands::BrokerInfo::networkProperties` [protected]
- 6.151.3.12 `std::vector< decaf::lang::Pointer<BrokerInfo> >
activemq::commands::BrokerInfo::peerBrokerInfos` [protected]
- 6.151.3.13 `bool activemq::commands::BrokerInfo::slaveBroker` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/BrokerInfo.h`

6.152 activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 904).

#include <src/main/activemq/wireformat/openwire/marshal/v3/BrokerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.152.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 904). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.152.2 Constructor & Destructor Documentation

6.152.2.1 `activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.152.2.2 `virtual activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.152.3 Member Function Documentation

6.152.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.152.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.152.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.152.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.152.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.152.3.6 virtual void activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.152.3.7 virtual void activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**BrokerInfoMarshaller.h**

6.153 activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 908).

#include <src/main/activemq/wireformat/openwire/marshal/v4/BrokerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.153.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 908). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.153.2 Constructor & Destructor Documentation

6.153.2.1 `activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.153.2.2 `virtual activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.153.3 Member Function Documentation

6.153.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.153.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.153.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.153.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.153.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.153.3.6 virtual void activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.153.3.7 virtual void activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**BrokerInfoMarshaller.h**

6.154 activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 912).

#include <src/main/activemq/wireformat/openwire/marshal/v1/BrokerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.154.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 912). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.154.2 Constructor & Destructor Documentation

6.154.2.1 `activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.154.2.2 `virtual activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.154.3 Member Function Documentation

6.154.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.154.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.154.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.154.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.154.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.154.3.6 virtual void activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.154.3.7 virtual void activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**BrokerInfoMarshaller.h**

6.155 activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 916).

#include <src/main/activemq/wireformat/openwire/marshal/v5/BrokerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.155.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 916). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.155.2 Constructor & Destructor Documentation

6.155.2.1 `activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.155.2.2 `virtual activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.155.3 Member Function Documentation

6.155.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.155.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.155.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.155.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.155.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.155.3.6 virtual void activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.155.3.7 virtual void activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**BrokerInfoMarshaller.h**

6.156 activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 920).

#include <src/main/activemq/wireformat/openwire/marshal/v6/BrokerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.156.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 920). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.156.2 Constructor & Destructor Documentation

6.156.2.1 `activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.156.2.2 `virtual activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.156.3 Member Function Documentation

6.156.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.156.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.156.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.156.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.156.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.156.3.6 virtual void activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.156.3.7 virtual void activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**BrokerInfoMarshaller.h**

6.157 activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 924).

#include <src/main/activemq/wireformat/openwire/marshal/v2/BrokerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller:

Public Member Functions

- **BrokerInfoMarshaller** ()
- virtual **~BrokerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.157.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 924). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.157.2 Constructor & Destructor Documentation

6.157.2.1 `activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::BrokerInfoMarshaller()` [inline]

6.157.2.2 `virtual activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::~~BrokerInfoMarshaller()` [inline, virtual]

6.157.3 Member Function Documentation

6.157.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.157.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.157.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.157.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.157.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.157.3.6 virtual void activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.157.3.7 virtual void activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**BrokerInfoMarshaller.h**

6.158 decaf::nio::Buffer Class Reference

A container for data of a specific primitive type.

#include <src/main/decaf/nio/Buffer.h> Inheritance diagram for decaf::nio::Buffer:

Public Member Functions

- **Buffer** (int capacity)
- **Buffer** (const **Buffer** &other)
- virtual ~**Buffer** ()
- virtual int **capacity** () const
- virtual int **position** () const
- virtual **Buffer** & **position** (int newPosition) throw (lang::exceptions::IllegalArgumentException)
Sets this buffer's position.
- virtual int **limit** () const
- virtual **Buffer** & **limit** (int newLimit) throw (lang::exceptions::IllegalArgumentException)
Sets this buffer's limit.
- virtual **Buffer** & **mark** ()
Sets this buffer's mark at its position.
- virtual **Buffer** & **reset** () throw (InvalidMarkException)
Resets this buffer's position to the previously-marked position.
- virtual **Buffer** & **clear** ()
Clears this buffer.
- virtual **Buffer** & **flip** ()
Flips this buffer.
- virtual **Buffer** & **rewind** ()
Rewinds this buffer.
- virtual int **remaining** () const
Returns the number of elements between the current position and the limit.
- virtual bool **hasRemaining** () const
Tells whether there are any elements between the current position and the limit.
- virtual bool **isReadOnly** () const =0
Tells whether or not this buffer is read-only.

Protected Attributes

- int **_position**
- int **_capacity**
- int **_limit**
- int **_mark**
- bool **_markSet**

6.158.1 Detailed Description

A container for data of a specific primitive type. A buffer is a linear, finite sequence of elements of a specific primitive type. Aside from its content, the essential properties of a buffer are its capacity, limit, and position:

A buffer's capacity is the number of elements it contains. The capacity of a buffer is never negative and never changes.

A buffer's limit is the index of the first element that should not be read or written. A buffer's limit is never negative and is never greater than its capacity.

A buffer's position is the index of the next element to be read or written. A buffer's position is never negative and is never greater than its limit.

There is one subclass of this class for each non-boolean primitive type.

Transferring data: Each subclass of this class defines two categories of get and put operations: * Relative operations read or write one or more elements starting at the current position and then increment the position by the number of elements transferred. If the requested transfer exceeds the limit then a relative get operation throws a **BufferUnderflowException** (p.957) and a relative put operation throws a **BufferOverflowException** (p.954); in either case, no data is transferred. * Absolute operations take an explicit element index and do not affect the position. Absolute get and put operations throw an **IndexOutOfBoundsException** if the index argument exceeds the limit.

Data may also, of course, be transferred in to or out of a buffer by the I/O operations of an appropriate channel, which are always relative to the current position.

Marking and resetting:

A buffer's mark is the index to which its position will be reset when the reset method is invoked. The mark is not always defined, but when it is defined it is never negative and is never greater than the position. If the mark is defined then it is discarded when the position or the limit is adjusted to a value smaller than the mark. If the mark is not defined then invoking the reset method causes an **InvalidMarkException** (p.2135) to be thrown.

Invariants:

The following invariant holds for the mark, position, limit, and capacity values: $0 \leq \text{mark} \leq \text{position} \leq \text{limit} \leq \text{capacity}$

A newly-created buffer always has a position of zero and a mark that is undefined. The initial limit may be zero, or it may be some other value that depends upon the type of the buffer and the manner in which it is constructed. The initial content of a buffer is, in general, undefined.

Clearing, flipping, and rewinding:

In addition to methods for accessing the position, limit, and capacity values and for marking and resetting, this class also defines the following operations upon buffers:

clear() (p. 930) makes a buffer ready for a new sequence of channel-read or relative put operations: It sets the limit to the capacity and the position to zero.

flip() (p. 931) makes a buffer ready for a new sequence of channel-write or relative get operations: It sets the limit to the current position and then sets the position to zero.

rewind() (p. 933) makes a buffer ready for re-reading the data that it already contains: It leaves the limit unchanged and sets the position to zero.

Read-only buffers:

Every buffer is readable, but not every buffer is writable. The mutation methods of each buffer class are specified as optional operations that will throw a **ReadOnlyBufferException** (p. 3169) when invoked upon a read-only buffer. A read-only buffer does not allow its content to be changed, but its mark, position, and limit values are mutable. Whether or not a buffer is read-only may be determined by invoking its `isReadOnly` method.

Thread safety:

Buffers are not safe for use by multiple concurrent threads. If a buffer is to be used by more than one thread then access to the buffer should be controlled by appropriate synchronization.

Invocation chaining:

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained; for example, the sequence of statements

```
b.flip(); b.position(23); b.limit(42);
```

can be replaced by the single, more compact statement `b.flip().position(23).limit(42);`

6.158.2 Constructor & Destructor Documentation

6.158.2.1 `decaf::nio::Buffer::Buffer (int capacity)`

6.158.2.2 `decaf::nio::Buffer::Buffer (const Buffer & other)`

6.158.2.3 `virtual decaf::nio::Buffer::~~Buffer ()` [inline, virtual]

6.158.3 Member Function Documentation

6.158.3.1 `virtual int decaf::nio::Buffer::capacity () const` [inline, virtual]

Returns:

this buffer's capacity.

6.158.3.2 `virtual Buffer& decaf::nio::Buffer::clear ()` [virtual]

Clears this buffer. The position is set to zero, the limit is set to the capacity, and the mark is discarded.

Invoke this method before using a sequence of channel-read or put operations to fill this buffer. For example:

```
buf.clear(); // Prepare buffer for reading in.read(buf); // Read data
```

This method does not actually erase the data in the buffer, but it is named as if it did because it will most often be used in situations in which that might as well be the case.

Returns:

a reference to this buffer.

6.158.3.3 virtual Buffer& decaf::nio::Buffer::flip () [virtual]

Flips this buffer. The limit is set to the current position and then the position is set to zero. If the mark is defined then it is discarded.

After a sequence of channel-read or put operations, invoke this method to prepare for a sequence of channel-write or relative get operations. For example:

```
buf.put(magic); // Prepend header in.read(buf); // Read data into rest of buffer buf.flip(); //
Flip buffer out.write(buf); // Write header + data to channel
```

This method is often used in conjunction with the compact method when transferring data from one place to another.

Returns:

a reference to this buffer.

6.158.3.4 virtual bool decaf::nio::Buffer::hasRemaining () const [inline, virtual]

Tells whether there are any elements between the current position and the limit.

Returns:

true if, and only if, there is at least one element remaining in this buffer.

6.158.3.5 virtual bool decaf::nio::Buffer::isReadOnly () const [pure virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1013), `decaf::internal::nio::CharArrayBuffer` (p. 1116), `decaf::internal::nio::DoubleArrayBuffer` (p. 1806), `decaf::internal::nio::FloatArrayBuffer` (p. 1922), `decaf::internal::nio::IntArrayBuffer` (p. 2063), `decaf::internal::nio::LongArrayBuffer` (p. 2441), `decaf::internal::nio::ShortArrayBuffer` (p. 3456), and `decaf::nio::ByteBuffer` (p. 1046).

6.158.3.6 virtual Buffer& decaf::nio::Buffer::limit (int *newLimit*) throw (lang::exceptions::IllegalArgumentException) [virtual]

Sets this buffer's limit. If the position is larger than the new limit then it is set to the new limit. If the mark is defined and larger than the new limit then it is discarded.

Parameters:

newLimit The new limit value; must be no larger than this buffer's capacity.

Returns:

A reference to This buffer

Exceptions:

IllegalArgumentException if preconditions on the new pos don't hold.

6.158.3.7 virtual int decaf::nio::Buffer::limit () const [inline, virtual]

Returns:

this buffers Limit

6.158.3.8 virtual Buffer& decaf::nio::Buffer::mark () [virtual]

Sets this buffer's mark at its position.

Returns:

a reference to this buffer.

6.158.3.9 virtual Buffer& decaf::nio::Buffer::position (int *newPosition*) throw (lang::exceptions::IllegalArgumentException) [virtual]

Sets this buffer's position. If the mark is defined and larger than the new position then it is discarded.

Parameters:

newPosition The new postion in the buffer to set.

Returns:

a reference to This buffer.

Exceptions:

IllegalArgumentException if preconditions on the new pos don't hold.

6.158.3.10 virtual int decaf::nio::Buffer::position () const [inline, virtual]

Returns:

the current position in the buffer

6.158.3.11 `virtual int decaf::nio::Buffer::remaining () const` [inline, virtual]

Returns the number of elements between the current position and the limit.

Returns:

The number of elements remaining in this buffer

6.158.3.12 `virtual Buffer& decaf::nio::Buffer::reset () throw (InvalidMarkException)` [virtual]

Resets this buffer's position to the previously-marked position.

Returns:

a reference to this buffer.

Exceptions:

InvalidMarkException (p. 2135) - If the mark has not been set

6.158.3.13 `virtual Buffer& decaf::nio::Buffer::rewind ()` [virtual]

Rewinds this buffer. The position is set to zero and the mark is discarded.

Invoke this method before a sequence of channel-write or get operations, assuming that the limit has already been set appropriately. For example:

```
out.write(buf); // Write remaining data buf.rewind(); // Rewind buffer buf.get(array); // Copy data into array
```

Returns:

a reference to this buffer.

6.158.4 Field Documentation**6.158.4.1** `int decaf::nio::Buffer::_capacity` [protected]**6.158.4.2** `int decaf::nio::Buffer::_limit` [protected]**6.158.4.3** `int decaf::nio::Buffer::_mark` [protected]**6.158.4.4** `bool decaf::nio::Buffer::_markSet` [protected]**6.158.4.5** `int decaf::nio::Buffer::_position` [mutable, protected]

The documentation for this class was generated from the following file:

- `src/main/decaf/nio/Buffer.h`

6.159 decaf::io::BufferedInputStream Class Reference

A wrapper around another input stream that performs a buffered read, where it reads more data than it needs in order to reduce the number of **io** (p. 154) operations on the input stream.

#include <src/main/decaf/io/BufferedInputStream.h> Inheritance diagram for decaf::io::BufferedInputStream:

Public Member Functions

- **BufferedInputStream** (**InputStream** *stream, bool **own**=false)

Constructor.

- **BufferedInputStream** (**InputStream** *stream, int bufferSize, bool **own**=false) throw (lang::exceptions::IllegalArgumentException)

Constructor.

- virtual ~**BufferedInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual void **close** () throw (decaf::io::IOException)

*Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream.*

The default implementation of this method does nothing.

- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Skips over and discards n bytes of data from this input stream.

*The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

- virtual void **mark** (int readLimit)

Marks the current position in the stream. A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

- virtual void **reset** () throw (decaf::io::IOException)

Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual bool **markSupported** () const

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Protected Member Functions

- virtual int **doReadByte** () throw (decaf::io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.159.1 Detailed Description

A wrapper around another input stream that performs a buffered read, where it reads more data than it needs in order to reduce the number of `io` (p. 154) operations on the input stream.

6.159.2 Constructor & Destructor Documentation

6.159.2.1 `decaf::io::BufferedInputStream::BufferedInputStream (InputStream * stream, bool own = false)`

Constructor.

Parameters:

- stream* The target input stream to buffer.
- own* Indicates if we own the stream object, defaults to false.

6.159.2.2 `decaf::io::BufferedInputStream::BufferedInputStream (InputStream * stream, int bufferSize, bool own = false) throw (lang::exceptions::IllegalArgumentException)`

Constructor.

Parameters:

- stream* The target input stream to buffer.
- bufferSize* The size in bytes to allocate for the **internal** (p. 144) buffer.
- own* Indicates if we own the stream object, defaults to false.

Exceptions:

- IllegalArgumentException* is the size is zero or negative.

6.159.2.3 `virtual decaf::io::BufferedInputStream::~~BufferedInputStream ()` [virtual]

6.159.3 Member Function Documentation

6.159.3.1 `virtual int decaf::io::BufferedInputStream::available () const throw (decaf::io::IOException)` [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

- the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::FilterInputStream** (p.1896).

6.159.3.2 virtual void decaf::io::BufferedInputStream::close () throw (decaf::io::IOException) [virtual]

Closes the **InputStream** (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.

The default implementation of this method does nothing.

Reimplemented from **decaf::io::FilterInputStream** (p.1897).

6.159.3.3 virtual int decaf::io::BufferedInputStream::doReadArrayBounded (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p.1897).

6.159.3.4 virtual int decaf::io::BufferedInputStream::doReadByte () throw (decaf::io::IOException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p.1897).

6.159.3.5 virtual void decaf::io::BufferedInputStream::mark (int *readLimit*) [virtual]

Marks the current position in the stream A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Reimplemented from **decaf::io::FilterInputStream** (p.1897).

6.159.3.6 virtual bool decaf::io::BufferedInputStream::markSupported () const [inline, virtual]

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Reimplemented from **decaf::io::FilterInputStream** (p.1898).

6.159.3.7 virtual void decaf::io::BufferedInputStream::reset () throw (decaf::io::IOException) [virtual]

Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p.2142) might be thrown. * If such an **IOException** (p.2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p.2142). * If an **IOException** (p.2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p.2142).

Exceptions:

IOException (p.2142) if an I/O error occurs.

Reimplemented from **decaf::io::FilterInputStream** (p.1898).

6.159.3.8 virtual long long decaf::io::BufferedInputStream::skip (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p.2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from **decaf::io::FilterInputStream** (p.1899).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/BufferedInputStream.h`

6.160 decaf::io::BufferedOutputStream Class Reference

Wrapper around another output stream that buffers output before writing to the target output stream.

#include <src/main/decaf/io/BufferedOutputStream.h> Inheritance diagram for decaf::io::BufferedOutputStream:

Public Member Functions

- **BufferedOutputStream** (**OutputStream** *stream, bool **own**=false)
Constructor.
- **BufferedOutputStream** (**OutputStream** *stream, int bufferSize, bool **own**=false) throw (decaf::lang::exceptions::IllegalArgumentException)
Constructor.
- virtual ~**BufferedOutputStream** ()
- virtual void **flush** () throw (decaf::io::IOException)
inheritDoc
- virtual void **doWriteByte** (unsigned char c) throw (decaf::io::IOException)
- virtual void **doWriteArray** (const unsigned char *buffer, int size) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.160.1 Detailed Description

Wrapper around another output stream that buffers output before writing to the target output stream.

6.160.2 Constructor & Destructor Documentation

6.160.2.1 decaf::io::BufferedOutputStream::BufferedOutputStream (OutputStream * stream, bool own = false)

Constructor.

Parameters:

stream The target output stream.

own Indicates if this class owns the stream pointer.

6.160.2.2 `decaf::io::BufferedOutputStream::BufferedOutputStream`
 (`OutputStream * stream`, `int bufferSize`, `bool own = false`) throw (`decaf::lang::exceptions::IllegalArgumentException`)

Constructor.

Parameters:

stream The target output stream.
bufferSize The size for the **internal** (p.144) buffer.
own Indicates if this class owns the stream pointer.

Exceptions:

IllegalArgumentException if the bufferSize given is negative.

6.160.2.3 `virtual decaf::io::BufferedOutputStream::~~BufferedOutputStream` ()
 [virtual]

6.160.3 Member Function Documentation

6.160.3.1 `virtual void decaf::io::BufferedOutputStream::doWriteArray` (`const unsigned char * buffer`, `int size`) throw (`decaf::io::IOException`)
 [protected, virtual]

Reimplemented from `decaf::io::FilterOutputStream` (p.1902).

6.160.3.2 `virtual void decaf::io::BufferedOutputStream::doWriteArrayBounded`
 (`const unsigned char * buffer`, `int size`, `int offset`, `int length`) throw (`decaf::io::IOException`, `decaf::lang::exceptions::NullPointerException`, `decaf::lang::exceptions::IndexOutOfBoundsException`) [protected, virtual]

Reimplemented from `decaf::io::FilterOutputStream` (p.1902).

6.160.3.3 `virtual void decaf::io::BufferedOutputStream::doWriteByte` (`unsigned char c`) throw (`decaf::io::IOException`) [protected, virtual]

Reimplemented from `decaf::io::FilterOutputStream` (p.1902).

6.160.3.4 `virtual void decaf::io::BufferedOutputStream::flush` () throw (`decaf::io::IOException`) [virtual]

inheritDoc}

Reimplemented from `decaf::io::FilterOutputStream` (p.1902).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/BufferedOutputStream.h`

6.161 decaf::internal::nio::BufferFactory Class Reference

Factory class used by static methods in the **decaf::nio** (p.163) package to create the various default version of the NIO interfaces.

```
#include <src/main/decaf/internal/nio/BufferFactory.h>
```

Public Member Functions

- virtual `~BufferFactory()`

Static Public Member Functions

- static **decaf::nio::ByteBuffer** * **createByteBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Allocates a new byte buffer whose position will be zero its limit will be its capacity and its mark is not set.

- static **decaf::nio::ByteBuffer** * **createByteBuffer** (unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Wraps the passed buffer with a new ByteBuffer.

- static **decaf::nio::ByteBuffer** * **createByteBuffer** (std::vector< unsigned char > &buffer)

Wraps the passed STL Byte Vector in a ByteBuffer.

- static **decaf::nio::CharBuffer** * **createCharBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Allocates a new char buffer whose position will be zero its limit will be its capacity and its mark is not set.

- static **decaf::nio::CharBuffer** * **createCharBuffer** (char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Wraps the passed buffer with a new CharBuffer.

- static **decaf::nio::CharBuffer** * **createCharBuffer** (std::vector< char > &buffer)

Wraps the passed STL Byte Vector in a CharBuffer.

- static **decaf::nio::DoubleBuffer** * **createDoubleBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Allocates a new double buffer whose position will be zero its limit will be its capacity and its mark is not set.

- static **decaf::nio::DoubleBuffer** * **createDoubleBuffer** (double *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Wraps the passed buffer with a new DoubleBuffer.

- static **decaf::nio::DoubleBuffer** * **createDoubleBuffer** (std::vector< double > &buffer)
Wraps the passed STL Double Vector in a DoubleBuffer.
- static **decaf::nio::FloatBuffer** * **createFloatBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Allocates a new float buffer whose position will be zero its limit will be its capacity and its mark is not set.
- static **decaf::nio::FloatBuffer** * **createFloatBuffer** (float *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Wraps the passed buffer with a new FloatBuffer.
- static **decaf::nio::FloatBuffer** * **createFloatBuffer** (std::vector< float > &buffer)
Wraps the passed STL Float Vector in a FloatBuffer.
- static **decaf::nio::LongBuffer** * **createLongBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Allocates a new long long buffer whose position will be zero its limit will be its capacity and its mark is not set.
- static **decaf::nio::LongBuffer** * **createLongBuffer** (long long *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Wraps the passed buffer with a new LongBuffer.
- static **decaf::nio::LongBuffer** * **createLongBuffer** (std::vector< long long > &buffer)
Wraps the passed STL Long Vector in a LongBuffer.
- static **decaf::nio::IntBuffer** * **createIntBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Allocates a new int buffer whose position will be zero its limit will be its capacity and its mark is not set.
- static **decaf::nio::IntBuffer** * **createIntBuffer** (int *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Wraps the passed buffer with a new IntBuffer.
- static **decaf::nio::IntBuffer** * **createIntBuffer** (std::vector< int > &buffer)
Wraps the passed STL int Vector in a IntBuffer.
- static **decaf::nio::ShortBuffer** * **createShortBuffer** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Allocates a new short buffer whose position will be zero its limit will be its capacity and its mark is not set.
- static **decaf::nio::ShortBuffer** * **createShortBuffer** (short *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Wraps the passed buffer with a new ShortBuffer.

- static **decaf::nio::ShortBuffer * createShortBuffer** (std::vector< short > &buffer)
Wraps the passed STL Short Vector in a ShortBuffer.

6.161.1 Detailed Description

Factory class used by static methods in the **decaf::nio** (p.163) package to create the various default version of the NIO interfaces.

Since:

1.0

6.161.2 Constructor & Destructor Documentation

6.161.2.1 **virtual decaf::internal::nio::BufferFactory::~~BufferFactory ()** [inline, virtual]

6.161.3 Member Function Documentation

6.161.3.1 **static decaf::nio::ByteBuffer* decaf::internal::nio::BufferFactory::createByteBuffer** (std::vector< unsigned char > & *buffer*) [static]

Wraps the passed STL Byte Vector in a ByteBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new ByteBuffer that is backed by *buffer*, caller owns.

6.161.3.2 **static decaf::nio::ByteBuffer* decaf::internal::nio::BufferFactory::createByteBuffer** (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Wraps the passed buffer with a new ByteBuffer. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be array length, its position will be *offset*, its limit will be *offset* + *length*, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.
size The size of the specified buffer.
offset The offset of the subarray to be used.
length The length of the subarray to be used.

Returns:

a new ByteBuffer that is backed by buffer, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.
IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.3 `static decaf::nio::ByteBuffer* decaf::internal::nio::BufferFactory::createByteBuffer (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Allocates a new byte buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated ByteBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.4 `static decaf::nio::CharBuffer* decaf::internal::nio::BufferFactory::createCharBuffer (std::vector< char > & buffer) [static]`

Wraps the passed STL Byte Vector in a CharBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be buffer.size(), its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling vector.resize(N).

Returns:

a new CharBuffer that is backed by buffer, caller owns.

6.161.3.5 static decaf::nio::CharBuffer* decaf::internal::nio::BufferFactory::createCharBuffer (char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Wraps the passed buffer with a new CharBuffer. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be array.length, its position will be offset, its limit will be offset + length, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.
size The size of the specified buffer.
offset The offset of the subarray to be used.
length The length of the subarray to be used.

Returns:

a new CharBuffer that is backed by buffer, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.
IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.6 static decaf::nio::CharBuffer* decaf::internal::nio::BufferFactory::createCharBuffer (int *capacity*) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Allocates a new char buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated CharBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.7 static decaf::nio::DoubleBuffer* decaf::internal::nio::BufferFactory::createDoubleBuffer (std::vector< double > & *buffer*) [static]

Wraps the passed STL Double Vector in a DoubleBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa.

The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new `DoubleBuffer` that is backed by `buffer`, caller owns.

```
6.161.3.8 static decaf::nio::DoubleBuffer* de-
caf::internal::nio::BufferFactory::createDoubleBuffer
(double * buffer, int size, int offset, int length)
throw ( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException ) [static]
```

Wraps the passed buffer with a new `DoubleBuffer`. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.

size The size of the specified buffer.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new `DoubleBuffer` that is backed by `buffer`, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.

IndexOutOfBoundsException if the capacity specified is negative.

```
6.161.3.9 static decaf::nio::DoubleBuffer* de-
caf::internal::nio::BufferFactory::createDoubleBuffer (int
capacity) throw ( decaf::lang::exceptions::IndexOutOfBoundsException )
[static]
```

Allocates a new double buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated DoubleBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.10 static decaf::nio::FloatBuffer* decaf::internal::nio::BufferFactory::createFloatBuffer (std::vector< float > & *buffer*) [static]

Wraps the passed STL Float Vector in a FloatBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be buffer.size(), its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling vector.resize(N).

Returns:

a new FloatBuffer that is backed by buffer, caller owns.

6.161.3.11 static decaf::nio::FloatBuffer* decaf::internal::nio::BufferFactory::createFloatBuffer (float * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Wraps the passed buffer with a new FloatBuffer. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be array.length, its position will be offset, its limit will be offset + length, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.

size The size of the specified buffer.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new FloatBuffer that is backed by buffer, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given in Null.

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.12 `static decaf::nio::FloatBuffer* decaf::internal::nio::BufferFactory::createFloatBuffer (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Allocates a new float buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated FloatBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.13 `static decaf::nio::IntBuffer* decaf::internal::nio::BufferFactory::createIntBuffer (std::vector< int > & buffer) [static]`

Wraps the passed STL int Vector in a IntBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new IntBuffer that is backed by *buffer*, caller owns.

6.161.3.14 `static decaf::nio::IntBuffer* decaf::internal::nio::BufferFactory::createIntBuffer (int * buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Wraps the passed buffer with a new IntBuffer. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.

size The size of the specified buffer.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new IntBuffer that is backed by buffer, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.15 `static decaf::nio::IntBuffer* decaf::internal::nio::BufferFactory::createIntBuffer (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Allocates a new int buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated IntBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

6.161.3.16 `static decaf::nio::LongBuffer* decaf::internal::nio::BufferFactory::createLongBuffer (std::vector< long long > & buffer) [static]`

Wraps the passed STL Long Vector in a LongBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be buffer.size(), its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling vector.resize(N).

Returns:

a new LongBuffer that is backed by buffer, caller owns.

```

6.161.3.17 static decaf::nio::LongBuffer* de-
caf::internal::nio::BufferFactory::createLongBuffer
(long long * buffer, int size, int offset, int length)
throw ( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException ) [static]

```

Wraps the passed buffer with a new LongBuffer. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be array.length, its position will be offset, its limit will be offset + length, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.
size The size of the specified buffer.
offset The offset of the subarray to be used.
length The length of the subarray to be used.

Returns:

a new LongBuffer that is backed by buffer, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.
IndexOutOfBoundsException if the capacity specified is negative.

```

6.161.3.18 static decaf::nio::LongBuffer* de-
caf::internal::nio::BufferFactory::createLongBuffer (int
capacity) throw ( decaf::lang::exceptions::IndexOutOfBoundsException
) [static]

```

Allocates a new long long buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity - the **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated DoubleBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

```

6.161.3.19 static decaf::nio::ShortBuffer* de-
caf::internal::nio::BufferFactory::createShortBuffer
(std::vector< short > & buffer) [static]

```

Wraps the passed STL Short Vector in a ShortBuffer. The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The

new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new `DoubleBuffer` that is backed by `buffer`, caller owns.

```
6.161.3.20 static decaf::nio::ShortBuffer* de-
caf::internal::nio::BufferFactory::createShortBuffer
(short * buffer, int size, int offset, int length)
throw ( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException ) [static]
```

Wraps the passed buffer with a new `ShortBuffer`. The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The array that will back the new buffer.

size The size of the specified buffer.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new `ShortBuffer` that is backed by `buffer`, caller owns the returned pointer.

Exceptions:

NullPointerException if the buffer given is Null.

IndexOutOfBoundsException if the capacity specified is negative.

```
6.161.3.21 static decaf::nio::ShortBuffer* de-
caf::internal::nio::BufferFactory::createShortBuffer (int
capacity) throw ( decaf::lang::exceptions::IndexOutOfBoundsException
) [static]
```

Allocates a new short buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p. 144) buffer's capacity.

Returns:

a newly allocated ShortBuffer which the caller owns.

Exceptions:

IndexOutOfBoundsException if the capacity specified is negative.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/BufferFactory.h`

6.162 decaf::nio::BufferOverflowException Class Reference

#include <src/main/decaf/nio/BufferOverflowException.h> Inheritance diagram for decaf::nio::BufferOverflowException:

Public Member Functions

- **BufferOverflowException** () throw ()
Default Constructor.
- **BufferOverflowException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **BufferOverflowException** (const **BufferOverflowException** &ex) throw ()
Copy Constructor.
- **BufferOverflowException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **BufferOverflowException** (const std::exception *cause) throw ()
Constructor.
- **BufferOverflowException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **BufferOverflowException** * clone () const
Clones this exception.
- virtual ~**BufferOverflowException** () throw ()

6.162.1 Constructor & Destructor Documentation

6.162.1.1 decaf::nio::BufferOverflowException::BufferOverflowException () throw () [inline]

Default Constructor.

6.162.1.2 decaf::nio::BufferOverflowException::BufferOverflowException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.162.1.3 `decaf::nio::BufferOverflowException::BufferOverflowException (const BufferOverflowException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.162.1.4 `decaf::nio::BufferOverflowException::BufferOverflowException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.162.1.5 `decaf::nio::BufferOverflowException::BufferOverflowException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.162.1.6 `decaf::nio::BufferOverflowException::BufferOverflowException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.162.1.7 virtual decaf::nio::BufferOverflowException::~~BufferOverflowException
() throw () [inline, virtual]

6.162.2 Member Function Documentation

6.162.2.1 virtual BufferOverflowException* decaf::nio::BufferOverflowException::clone () const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**BufferOverflowException.h**

6.163 decaf::nio::BufferUnderflowException Class Reference

#include <src/main/decaf/nio/BufferUnderflowException.h> Inheritance diagram for decaf::nio::BufferUnderflowException:

Public Member Functions

- **BufferUnderflowException** () throw ()
Default Constructor.
- **BufferUnderflowException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **BufferUnderflowException** (const BufferUnderflowException &ex) throw ()
Copy Constructor.
- **BufferUnderflowException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **BufferUnderflowException** (const std::exception *cause) throw ()
Constructor.
- **BufferUnderflowException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **BufferUnderflowException** * clone () const
Clones this exception.
- virtual ~**BufferUnderflowException** () throw ()

6.163.1 Constructor & Destructor Documentation

6.163.1.1 decaf::nio::BufferUnderflowException::BufferUnderflowException () throw () [inline]

Default Constructor.

6.163.1.2 decaf::nio::BufferUnderflowException::BufferUnderflowException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.163.1.3 decaf::nio::BufferUnderflowException::BufferUnderflowException (const BufferUnderflowException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.163.1.4 decaf::nio::BufferUnderflowException::BufferUnderflowException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.163.1.5 decaf::nio::BufferUnderflowException::BufferUnderflowException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.163.1.6 decaf::nio::BufferUnderflowException::BufferUnderflowException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.163.1.7 **virtual**
decaf::nio::BufferUnderflowException::~~BufferUnderflowException ()
throw () [inline, virtual]

6.163.2 **Member Function Documentation**

6.163.2.1 **virtual BufferUnderflowException* de-**
caf::nio::BufferUnderflowException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/nio/BufferUnderflowException.h`

6.164 decaf::lang::Byte Class Reference

#include <src/main/decaf/lang/Byte.h> Inheritance diagram for decaf::lang::Byte:

Public Member Functions

- **Byte** (unsigned char value)
- **Byte** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Byte** ()
- virtual int **compareTo** (const **Byte** &c) const
*Compares this **Byte** (p. 960) instance with another.*
- virtual bool **operator==** (const **Byte** &c) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Byte** &c) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const unsigned char &c) const
*Compares this **Byte** (p. 960) instance with a char type.*
- virtual bool **operator==** (const unsigned char &c) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const unsigned char &c) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- bool **equals** (const **Byte** &c) const
- bool **equals** (const unsigned char &c) const
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const
Answers the long value which the receiver represents.

Static Public Member Functions

- static `std::string toString` (unsigned char value)
- static `Byte decode` (const `std::string &value`) throw (exceptions::NumberFormatException)
*Decodes a **String** (p. 3665) into a **Byte** (p. 960).*
- static unsigned char `parseByte` (const `std::string &s`, int radix) throw (exceptions::NumberFormatException)
Parses the string argument as a signed unsigned char in the radix specified by the second argument.
- static unsigned char `parseByte` (const `std::string &s`) throw (exceptions::NumberFormatException)
Parses the string argument as a signed decimal unsigned char.
- static `Byte valueOf` (unsigned char value)
*Returns a **Character** (p. 1100) instance representing the specified char value.*
- static `Byte valueOf` (const `std::string &value`) throw (exceptions::NumberFormatException)
*Returns a **Byte** (p. 960) object holding the value given by the specified `std::string`.*
- static `Byte valueOf` (const `std::string &value`, int radix) throw (exceptions::NumberFormatException)
*Returns a **Byte** (p. 960) object holding the value extracted from the specified `std::string` when parsed with the radix given by the second argument.*

Static Public Attributes

- static const unsigned char `MIN_VALUE` = 0x7F
The minimum value that a unsigned char can take on.
- static const unsigned char `MAX_VALUE` = 0x80
The maximum value that a unsigned char can take on.
- static const int `SIZE` = 8
The size of the primitive character in bits.

6.164.1 Constructor & Destructor Documentation

6.164.1.1 `decaf::lang::Byte::Byte` (unsigned char *value*)

Parameters:

value - the primitive value to wrap

6.164.1.2 decaf::lang::Byte::Byte (const std::string & *value*) throw (exceptions::NumberFormatException)

Parameters:

value - the string to convert to an unsigned char

Exceptions:

NumberFormatException

6.164.1.3 virtual decaf::lang::Byte::~~Byte () [inline, virtual]

6.164.2 Member Function Documentation

6.164.2.1 virtual unsigned char decaf::lang::Byte::byteValue () const [inline, virtual]

Answers the byte value which the receiver represents.

Returns:

byte the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2835).

6.164.2.2 virtual int decaf::lang::Byte::compareTo (const unsigned char & *c*) const [inline, virtual]

Compares this **Byte** (p. 960) instance with a char type.

Parameters:

c - the char instance to be compared

Returns:

zero if this object represents the same char value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements **decaf::lang::Comparable< unsigned char >** (p. 1214).

6.164.2.3 virtual int decaf::lang::Byte::compareTo (const Byte & *c*) const [inline, virtual]

Compares this **Byte** (p. 960) instance with another.

Parameters:

c - the **Byte** (p. 960) instance to be compared

Returns:

zero if this object represents the same char value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.164.2.4 static Byte decaf::lang::Byte::decode (const std::string & *value*) throw (exceptions::NumberFormatException) [static]

Decodes a **String** (p. 3665) into a **Byte** (p. 960). Accepts decimal, hexadecimal, and octal numbers given by the following grammar:

The sequence of characters following an (optional) negative sign and/or radix specifier ("0x", "0X", "#", or leading zero) is parsed as by the **Byte::parseByte** (p. 966) method with the indicated radix (10, 16, or 8). This sequence of characters must represent a positive value or a **NumberFormatException** will be thrown. The result is negated if first character of the specified **String** (p. 3665) is the minus sign. No whitespace characters are permitted in the string.

Parameters:

value - The string to decode

Returns:

a **Byte** (p. 960) object containing the decoded value

Exceptions:

NumberFormatException if the string is not formatted correctly.

6.164.2.5 virtual double decaf::lang::Byte::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.164.2.6 bool decaf::lang::Byte::equals (const unsigned char & *c*) const [inline, virtual]

Returns:

true if the two Bytes have the same value.

Implements **decaf::lang::Comparable< unsigned char >** (p. 1215).

6.164.2.7 bool decaf::lang::Byte::equals (const Byte & *c*) const [inline]

Returns:

true if the two **Byte** (p. 960) Objects have the same value.

6.164.2.8 virtual float decaf::lang::Byte::floatValue () const [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.164.2.9 virtual int decaf::lang::Byte::intValue () const [inline, virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.164.2.10 virtual long long decaf::lang::Byte::longValue () const [inline, virtual]

Answers the long value which the receiver represents.

Returns:

long long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.164.2.11 virtual bool decaf::lang::Byte::operator< (const unsigned char & c) const [inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable< unsigned char >** (p. 1215).

6.164.2.12 virtual bool decaf::lang::Byte::operator< (const Byte & c) const [inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.164.2.13 `virtual bool decaf::lang::Byte::operator==(const unsigned char & c)
const [inline, virtual]`

Compares equality between this object and the one passed.

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< unsigned char >` (p. 1215).

6.164.2.14 `virtual bool decaf::lang::Byte::operator==(const Byte & c) const
[inline, virtual]`

Compares equality between this object and the one passed.

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.164.2.15 `static unsigned char decaf::lang::Byte::parseByte (const std::string & s)
throw (exceptions::NumberFormatException) [static]`

Parses the string argument as a signed decimal unsigned char. The characters in the string must all be decimal digits, except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting unsigned char value is returned, exactly as if the argument and the radix 10 were given as arguments to the `parseByte(const std::string, int)` method.

Parameters:

s - `String` (p. 3665) to convert to a unsigned char

Returns:

the converted unsigned char value

Exceptions:

NumberFormatException if the string is not a unsigned char.

6.164.2.16 static unsigned char decaf::lang::Byte::parseByte (const std::string & *s*, int *radix*) throw (exceptions::NumberFormatException) [static]

Parses the string argument as a signed unsigned char in the radix specified by the second argument. The characters in the string must all be digits, of the specified radix (as determined by whether **Character.digit(char, int)** (p. 1103) returns a nonnegative value) except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting byte value is returned.

An exception of type `NumberFormatException` is thrown if any of the following situations occurs:
 * The first argument is null or is a string of length zero. * The radix is either smaller than **Character.MIN_RADIX** (p. 1107) or larger than **Character::MAX_RADIX** (p. 1106). * Any character of the string is not a digit of the specified radix, except that the first character may be a minus sign '-' provided that the string is longer than length 1. * The value represented by the string is not a value of type unsigned char.

Parameters:

s - the **String** (p. 3665) containing the unsigned char to be parsed

radix - the radix to be used while parsing *s*

Returns:

the unsigned char represented by the string argument in the specified radix.

Exceptions:

NumberFormatException - If **String** (p. 3665) does not contain a parsable unsigned char.

6.164.2.17 virtual short decaf::lang::Byte::shortValue () const [inline, virtual]

Answers the short value which the receiver represents.

Returns:

short the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2837).

6.164.2.18 static std::string decaf::lang::Byte::toString (unsigned char *value*) [static]

Returns:

a string representing the primitive value as Base 10

6.164.2.19 std::string decaf::lang::Byte::toString () const

Returns:

this **Byte** (p. 960) Object as a **String** (p. 3665) Representation

6.164.2.20 `static Byte decaf::lang::Byte::valueOf (const std::string & value, int radix) throw (exceptions::NumberFormatException) [static]`

Returns a **Byte** (p.960) object holding the value extracted from the specified `std::string` when parsed with the radix given by the second argument. The first argument is interpreted as representing a signed unsigned char in the radix specified by the second argument, exactly as if the argument were given to the `parseByte(std::string, int)` method. The result is a **Byte** (p.960) object that represents the unsigned char value specified by the string.

Parameters:

value - `std::string` to parse as base (*radix*)

radix - base of the string to parse.

Returns:

new **Byte** (p.960) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a valid unsigned char.

6.164.2.21 `static Byte decaf::lang::Byte::valueOf (const std::string & value) throw (exceptions::NumberFormatException) [static]`

Returns a **Byte** (p.960) object holding the value given by the specified `std::string`. The argument is interpreted as representing a signed decimal unsigned char, exactly as if the argument were given to the `parseByte(std::string)` method. The result is a **Byte** (p.960) object that represents the unsigned char value specified by the string.

Parameters:

value - `std::string` to parse as base 10

Returns:

new **Byte** (p.960) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a decimal unsigned char.

6.164.2.22 `static Byte decaf::lang::Byte::valueOf (unsigned char value) [inline, static]`

Returns a **Character** (p.1100) instance representing the specified char value.

Parameters:

value - the primitive char to wrap.

Returns:

a new **Character** (p.1100) instance that wraps this value.

6.164.3 Field Documentation

6.164.3.1 `const unsigned char decaf::lang::Byte::MAX_VALUE = 0x80` [static]

The maximum value that a unsigned char can take on.

6.164.3.2 `const unsigned char decaf::lang::Byte::MIN_VALUE = 0x7F` [static]

The minimum value that a unsigned char can take on.

6.164.3.3 `const int decaf::lang::Byte::SIZE = 8` [static]

The size of the primitive charactor in bits.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Byte.h`

6.165 decaf::internal::util::ByteArrayAdapter Class Reference

This class adapts primitive type arrays to a base byte array so that the classes can inter-operate on the same base byte array without copying data.

```
#include <src/main/decaf/internal/util/ByteArrayAdapter.h>
```

Data Structures

- union **Array**

Public Member Functions

- **ByteArrayAdapter** (int size) throw (decaf::lang::exceptions::IllegalArgumentException)
Creates a byte array object that is allocated internally and is then owned and deleted when this object is deleted.
- **ByteArrayAdapter** (unsigned char *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- **ByteArrayAdapter** (char *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- **ByteArrayAdapter** (double *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- **ByteArrayAdapter** (float *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- **ByteArrayAdapter** (long long *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- **ByteArrayAdapter** (int *array, int size, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.

- **ByteArrayAdapter** (short *array, int size, bool own=false)
throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Creates a byte array object that wraps the given array.
- virtual ~**ByteArrayAdapter** ()
- virtual int **getCapacity** () const
Gets the size of the underlying array.
- virtual int **getCharCapacity** () const
Gets the size of the underlying array as if it contains chars.
- virtual int **getDoubleCapacity** () const
Gets the size of the underlying array as if it contains doubles.
- virtual int **getFloatCapacity** () const
Gets the size of the underlying array as if it contains doubles.
- virtual int **getLongCapacity** () const
Gets the size of the underlying array as if it contains doubles.
- virtual int **getIntCapacity** () const
Gets the size of the underlying array as if it contains ints.
- virtual int **getShortCapacity** () const
Gets the size of the underlying array as if it contains shorts.
- virtual unsigned char * **getByteArray** ()
Gets the pointer to the array we are wrapping.
- virtual char * **getCharArray** ()
Gets the pointer to the array we are wrapping.
- virtual short * **getShortArray** ()
Gets the pointer to the array we are wrapping.
- virtual int * **getIntArray** ()
Gets the pointer to the array we are wrapping.
- virtual long long * **getLongArray** ()
Gets the pointer to the array we are wrapping.
- virtual double * **getDoubleArray** ()
Gets the pointer to the array we are wrapping.
- virtual float * **getFloatArray** ()
Gets the pointer to the array we are wrapping.
- virtual void **read** (unsigned char *buffer, int size, int offset, int length)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException, decaf::nio::BufferUnderflowException)

Reads from the Byte array starting at the specified offset and reading the specified length.

- virtual void **write** (unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException, decaf::nio::BufferOverflowException)

*Writes from the Byte array given, starting at the specified offset and writing the specified amount of data into this objects **internal** (p. 144) array.*

- virtual void **resize** (int size) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InvalidStateException)

Resizes the underlying array to the new given size, preserving all the Data that was previously in the array, unless the resize is smaller than the current size in which case only the data that will fit into the new array is preserved.

- virtual void **clear** () throw ()

Clear all data from that Array, setting the underlying bytes to zero.

- unsigned char & **operator[]** (int index) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

*Allows the **ByteArrayAdapter** (p. 969) to be indexed as a standard array.*

- const unsigned char & **operator[]** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

- virtual unsigned char **get** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

- virtual char **getChar** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads one byte at the given index and returns it.

- virtual double **getDouble** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads eight bytes at the given index and returns it.

- virtual double **getDoubleAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads eight bytes at the given byte index and returns it.

- virtual float **getFloat** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads four bytes at the given index and returns it.

- virtual float **getFloatAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads four bytes at the given byte index and returns it.

- virtual long long **getLong** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads eight bytes at the given index and returns it.

- virtual long long **getLongAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads eight bytes at the given byte index and returns it.
- virtual int **getInt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads four bytes at the given index and returns it.
- virtual int **getIntAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads four bytes at the given byte index and returns it.
- virtual short **getShort** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads two bytes at the given index and returns it.
- virtual short **getShortAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads two bytes at the given byte index and returns it.
- virtual **ByteArrayAdapter** & **put** (int index, unsigned char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes the given byte into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putChar** (int index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes one byte containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putDouble** (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes eight bytes containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putDoubleAt** (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes eight bytes containing the given value, into this buffer at the given byte index.
- virtual **ByteArrayAdapter** & **putFloat** (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes four bytes containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putFloatAt** (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes four bytes containing the given value, into this buffer at the given byte index.
- virtual **ByteArrayAdapter** & **putLong** (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes eight bytes containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putLongAt** (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes eight bytes containing the given value, into this buffer at the given byte index.

- virtual **ByteArrayAdapter** & **putInt** (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes four bytes containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putIntAt** (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes four bytes containing the given value, into this buffer at the given byte index.
- virtual **ByteArrayAdapter** & **putShort** (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes two bytes containing the given value, into this buffer at the given index.
- virtual **ByteArrayAdapter** & **putShortAt** (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Writes two bytes containing the given value, into this buffer at the given byte index.

6.165.1 Detailed Description

This class adapts primitive type arrays to a base byte array so that the classes can inter-operate on the same base byte array without copying data. All the array types are mapped down to a byte array and methods are supplied for accessing the data in any of the primitive type forms.

Methods in this class that do not return a specific value return a reference to this object so that calls can be chained.

Since:

1.0

6.165.2 Constructor & Destructor Documentation

6.165.2.1 decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter (int size) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a byte array object that is allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

Exceptions:

IllegalArgumentException if size is negative.

6.165.2.2 decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter (unsigned char * array, int size, bool own = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

- array* The physical array to wrap.
- size* The size of the array, this is the limit we read and write to.
- own* Indicates if this class is now the owner of the pointer.

Exceptions:

- NullPointerException* if buffer is NULL
- IndexOutOfBoundsException* if the size is negative.

6.165.2.3 decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter
(char * *array*, int *size*, bool *own* = false) throw
(decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

- array* The physical array to wrap.
- size* The size of the array, this is the limit we read and write to.
- own* Indicates if this class is now the owner of the pointer.

Exceptions:

- NullPointerException* if buffer is NULL
- IndexOutOfBoundsException* if the size is negative.

6.165.2.4 decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter
(double * *array*, int *size*, bool *own* = false)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

- array* The physical array to wrap.
- size* The size of the array, this is the limit we read and write to.
- own* Indicates if this class is now the owner of the pointer.

Exceptions:

- NullPointerException* if buffer is NULL
- IndexOutOfBoundsException* if the size is negative.

6.165.2.5 `decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter`
 (float * *array*, int *size*, bool *own* = false) throw
 (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The physical array to wrap.
size The size of the array, this is the limit we read and write to.
own Indicates if this class is now the owner of the pointer.

Exceptions:

NullPointerException if buffer is NULL
IndexOutOfBoundsException if the size is negative.

6.165.2.6 `decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter`
 (long long * *array*, int *size*, bool *own* = false)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The physical array to wrap.
size The size of the array, this is the limit we read and write to.
own Indicates if this class is now the owner of the pointer.

Exceptions:

NullPointerException if buffer is NULL
IndexOutOfBoundsException if the size is negative.

6.165.2.7 `decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter`
 (int * *array*, int *size*, bool *own* = false) throw
 (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The physical array to wrap.
size The size of the array, this is the limit we read and write to.

own Indicates if this class is now the owner of the pointer.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if the size is negative.

6.165.2.8 decaf::internal::util::ByteArrayAdapter::ByteArrayAdapter
(short * *array*, int *size*, bool *own* = false)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte array object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The physical array to wrap.

size The size of the array, this is the limit we read and write to.

own Indicates if this class is now the owner of the pointer.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if the size is negative.

6.165.2.9 virtual decaf::internal::util::ByteArrayAdapter::~~ByteArrayAdapter ()
[virtual]

6.165.3 Member Function Documentation

6.165.3.1 virtual void decaf::internal::util::ByteArrayAdapter::clear () throw ()
[virtual]

Clear all data from that Array, setting the underlying bytes to zero.

6.165.3.2 virtual unsigned char decaf::internal::util::ByteArrayAdapter::get (int
index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException
) [virtual]

Absolute get method. Reads the byte at the given index.

Parameters:

index The index in the Buffer where the byte is to be read.

Returns:

the byte that is located at the given index.

Exceptions:

IndexOutOfBoundsException If index is not smaller than the buffer's limit or is negative.

6.165.3.3 `virtual unsigned char* decaf::internal::util::ByteArrayAdapter::getByteArray ()`
[inline, virtual]

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an unsigned char* pointer to the array this object wraps.

6.165.3.4 `virtual int decaf::internal::util::ByteArrayAdapter::getCapacity () const`
[inline, virtual]

Gets the size of the underlying array.

Returns:

the size the array.

6.165.3.5 `virtual char decaf::internal::util::ByteArrayAdapter::getChar (int index)`
`const throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Reads one byte at the given index and returns it.

Parameters:

index The index in the Buffer where the byte is to be read.

Returns:

the byte that is located at the given index.

Exceptions:

IndexOutOfBoundsException If index is not smaller than the buffer's limit or is negative.

6.165.3.6 `virtual char* decaf::internal::util::ByteArrayAdapter::getCharArray ()`
[inline, virtual]

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an char* pointer to the array this object wraps.

6.165.3.7 `virtual int decaf::internal::util::ByteArrayAdapter::getCharCapacity ()`
`const [inline, virtual]`

Gets the size of the underlying array as if it contains chars.

Returns:

the size the array.

6.165.3.8 virtual double decaf::internal::util::ByteArrayAdapter::getDouble (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Reads eight bytes at the given index and returns it. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The index in the Buffer where the bytes are to be read.

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.9 virtual double* decaf::internal::util::ByteArrayAdapter::getDoubleArray () [inline, virtual]

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an double* pointer to the array this object wraps.

6.165.3.10 virtual double decaf::internal::util::ByteArrayAdapter::getDoubleAt (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Reads eight bytes at the given byte index and returns it.

Parameters:

index The index in the Buffer where the bytes are to be read

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.11 `virtual int decaf::internal::util::ByteArrayAdapter::getDoubleCapacity
() const [inline, virtual]`

Gets the size of the underlying array as if it contains doubles.

Returns:

the size the array.

6.165.3.12 `virtual float decaf::internal::util::ByteArrayAdapter::getFloat (int index)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]`

Reads four bytes at the given index and returns it. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The index in the Buffer where the bytes are to be read.

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.13 `virtual float* decaf::internal::util::ByteArrayAdapter::getFloatArray ()
[inline, virtual]`

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an float* pointer to the array this object wraps.

6.165.3.14 `virtual float decaf::internal::util::ByteArrayAdapter::getFloatAt (int in-
dex) const throw (decaf::lang::exceptions::IndexOutOfBoundsException
) [virtual]`

Reads four bytes at the given byte index and returns it.

Parameters:

index The index in the Buffer where the bytes are to be read

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.15 `virtual int decaf::internal::util::ByteArrayAdapter::getFloatCapacity ()`
 `const [inline, virtual]`

Gets the size of the underlying array as if it contains doubles.

Returns:

the size the array.

6.165.3.16 `virtual int decaf::internal::util::ByteArrayAdapter::getInt (int index)`
 `const throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
 `[virtual]`

Reads four bytes at the given index and returns it. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The index in the Buffer where the bytes are to be read.

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.17 `virtual int* decaf::internal::util::ByteArrayAdapter::getIntArray ()`
 `[inline, virtual]`

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p. 969) objects that point to this array.

Returns:

an int* pointer to the array this object wraps.

6.165.3.18 `virtual int decaf::internal::util::ByteArrayAdapter::getIntAt (int index)`
 `const throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
 `[virtual]`

Reads four bytes at the given byte index and returns it.

Parameters:

index The index in the Buffer where the bytes are to be read

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.19 `virtual int decaf::internal::util::ByteArrayAdapter::getIntCapacity ()
const [inline, virtual]`

Gets the size of the underlying array as if it contains ints.

Returns:

the size the array.

6.165.3.20 `virtual long long decaf::internal::util::ByteArrayAdapter::getLong
(int index) const throw (de-
cafe::lang::exceptions::IndexOutOfBoundsException)
[virtual]`

Reads eight bytes at the given index and returns it. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The index in the Buffer where the bytes are to be read.

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.21 `virtual long long* decaf::internal::util::ByteArrayAdapter::getLongArray
() [inline, virtual]`

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an long long* pointer to the array this object wraps.

6.165.3.22 `virtual long long decaf::internal::util::ByteArrayAdapter::getLongAt (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Reads eight bytes at the given byte index and returns it.

Parameters:

index The index in the Buffer where the bytes are to be read

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.23 `virtual int decaf::internal::util::ByteArrayAdapter::getLongCapacity () const [inline, virtual]`

Gets the size of the underlying array as if it contains doubles.

Returns:

the size the array.

6.165.3.24 `virtual short decaf::internal::util::ByteArrayAdapter::getShort (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Reads two bytes at the given index and returns it. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The index in the Buffer where the bytes are to be read.

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.25 `virtual short* decaf::internal::util::ByteArrayAdapter::getShortArray ()`
`[inline, virtual]`

Gets the pointer to the array we are wrapping. Changes to the data in this array are reflected by all **ByteArrayAdapter** (p.969) objects that point to this array.

Returns:

an short* pointer to the array this object wraps.

6.165.3.26 `virtual short decaf::internal::util::ByteArrayAdapter::getShortAt (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
`[virtual]`

Reads two bytes at the given byte index and returns it.

Parameters:

index The index in the Buffer where the bytes are to be read

Returns:

the value at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

6.165.3.27 `virtual int decaf::internal::util::ByteArrayAdapter::getShortCapacity ()`
`const [inline, virtual]`

Gets the size of the underlying array as if it contains shorts.

Returns:

the size the array.

6.165.3.28 `const unsigned char& decaf::internal::util::ByteArrayAdapter::operator[] (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)`

6.165.3.29 `unsigned char& decaf::internal::util::ByteArrayAdapter::operator[] (int index) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`

Allows the **ByteArrayAdapter** (p.969) to be indexed as a standard array. calling the non constant version allows the user to change the value at index

Parameters:

index The position in the array to access, if the value is negative or greater than the size of the underlying array an *IndexOutOfBoundsException* is thrown.

Exceptions:

IndexOutOfBoundsException if the preconditions of index are not met.

6.165.3.30 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::put (int *index*, unsigned char *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Writes the given byte into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.31 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putChar (int *index*, char *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Writes one byte containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.32 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putDouble (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes eight bytes containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.33 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putDoubleAt (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes eight bytes containing the given value, into this buffer at the given byte index.

Parameters:

index The position in the Buffer to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.34 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putFloat (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes four bytes containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.35 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putFloatAt (int *index*, float *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Writes four bytes containing the given value, into this buffer at the given byte index.

Parameters:

index The position in the Buffer to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.36 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putInt (int *index*, int *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Writes four bytes containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.37 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putIntAt (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes four bytes containing the given value, into this buffer at the given byte index.

Parameters:

index The position in the Buffer to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.38 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putLong (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes eight bytes containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array `index * sizeof(type)` if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.39 `virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putLongAt (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Writes eight bytes containing the given value, into this buffer at the given byte index.

Parameters:

index The position in the Buffer to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.40 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putShort (int *index*, short *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Writes two bytes containing the given value, into this buffer at the given index. The index is a relative to the size of the type to be read, in other words when accessing the element in the array index * sizeof(type) if the actual start index of the type to be read.

Parameters:

index The position in the Buffer to write the data.

value The value to write to the array.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.41 virtual ByteArrayAdapter& decaf::internal::util::ByteArrayAdapter::putShortAt (int *index*, short *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Writes two bytes containing the given value, into this buffer at the given byte index.

Parameters:

index The position in the Buffer to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

6.165.3.42 `virtual void decaf::internal::util::ByteArrayAdapter::read (unsigned char * buffer, int size, int offset, int length) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException, decaf::nio::BufferUnderflowException)` [virtual]

Reads from the Byte array starting at the specified offset and reading the specified length. If the length is greater than the size of this underlying byte array then an `BufferUnderflowException` is thrown.

Parameters:

buffer The buffer to read data from this array into.

size The size of the buffer passed.

offset The position in this array to start reading from.

length The amount of data to read from this array.

Exceptions:

IndexOutOfBoundsException if the offset + length exceeds the size.

NullPointerException if buffer is null

BufferUnderflowException if there is not enough data to read because the offset or the length is greater than the size of this array.

6.165.3.43 `virtual void decaf::internal::util::ByteArrayAdapter::resize (int size) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InvalidStateException)` [virtual]

Resizes the underlying array to the new given size, preserving all the Data that was previously in the array, unless the resize is smaller than the current size in which case only the data that will fit into the new array is preserved. A `ByteArrayAdapter` (p. 969) can only be resized when it owns the underlying array, if it does not then it will throw an `InvalidStateException`.

Parameters:

size The new size of the array.

Exceptions:

IllegalArgumentException if the size parameter is negative.

InvalidStateException if this object does not own the buffer.

6.165.3.44 `virtual void decaf::internal::util::ByteArrayAdapter::write (unsigned char * buffer, int size, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException, decaf::nio::BufferOverflowException)` [virtual]

Writes from the Byte array given, starting at the specified offset and writing the specified amount of data into this objects `internal` (p. 144) array. . If the length is greater than the size of this underlying byte array then an `BufferOverflowException` is thrown.

Parameters:

- buffer* The buffer to read data from this array into.
- size* The size of the buffer passed.
- offset* The position in this array to start reading from.
- length* The amount of data to read from this array.

Exceptions:

- IndexOutOfBoundsException* if the offset + length exceeds the size.
- NullPointerException* if buffer is null
- BufferOverflowException* if the amount of data to be written to this array or the offset given are larger than this array's size.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/ByteArrayAdapter.h`

6.166 decaf::internal::nio::ByteBuffer Class Reference

This class defines six categories of operations upon byte buffers:.

#include <src/main/decaf/internal/nio/ByteBuffer.h> Inheritance diagram for decaf::internal::nio::ByteBuffer:

Public Member Functions

- **ByteBuffer** (int capacity, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **ByteBuffer** (p. 991) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **ByteBuffer** (unsigned char *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **ByteBuffer** (p. 991) object that wraps the given array.*

- **ByteBuffer** (const decaf::lang::Pointer< **ByteArrayAdapter** > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a byte buffer that wraps the passed **ByteArrayAdapter** and start at the given offset.*

- **ByteBuffer** (const **ByteBuffer** &other)

*Create a **ByteBuffer** (p. 991) that mirrors this one, meaning it shares a reference to this buffers **ByteArrayAdapter** and when changes are made to that data it is reflected in both.*

- virtual ~**ByteBuffer** ()
- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only

- virtual unsigned char * **array** () throw (decaf::nio::ReadOnlyBufferException, decaf::lang::exceptions::UnsupportedOperationException)

Returns the byte array that backs this buffer.

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

*Invoke the **hasArray** method before invoking this method in order to ensure that this buffer has an accessible backing array.*

Returns:

The array that backs this buffer

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this buffer is backed by an array but is read-only
UnsupportedOperationException if this buffer is not backed by an accessible array*

- virtual int **arrayOffset** () const throw (decaf::nio::ReadOnlyBufferException, decaf::lang::exceptions::UnsupportedOperationException)

Returns the offset within this buffer's backing array of the first element of the buffer.
 If this buffer is backed by an array then buffer position p corresponds to array index $p + \text{arrayOffset}()$ (p. 1037).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset within this buffer's array of the first element of the buffer.

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is backed by an array but is read-only.
UnsupportedOperationException if this buffer is not backed by an accessible array.

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible byte array.

If this method returns true then the `array` and `arrayOffset` methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

- virtual decaf::nio::CharBuffer * **asCharBuffer** () const

Creates a view of this byte buffer as a char buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new Char **Buffer** (p. 928), which the caller then owns.

- virtual decaf::nio::DoubleBuffer * **asDoubleBuffer** () const

Creates a view of this byte buffer as a double buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new double **Buffer** (p. 928), which the caller then owns.

- virtual decaf::nio::FloatBuffer * **asFloatBuffer** () const

Creates a view of this byte buffer as a float buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new float **Buffer** (p. 928), which the caller then owns.

- virtual **decaf::nio::IntBuffer * asIntBuffer ()** const

Creates a view of this byte buffer as a int buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the new int **Buffer** (p. 928), which the caller then owns.*

- virtual **decaf::nio::LongBuffer * asLongBuffer ()** const

Creates a view of this byte buffer as a long buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the new long **Buffer** (p. 928), which the caller then owns.*

- virtual **decaf::nio::ShortBuffer * asShortBuffer ()** const

Creates a view of this byte buffer as a short buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by two, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the new short **Buffer** (p. 928), which the caller then owns.*

- virtual **ByteBuffer * asReadOnlyBuffer ()** const

Creates a new, read-only byte buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only byte buffer which the caller then owns.

- virtual **ByteBuffer & compact ()** throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this *ByteBuffer* (p. 1031).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer * duplicate ()**

Creates a new byte buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new *Byte Buffer* (p. 928) which the caller owns.

- virtual unsigned char **get ()** const throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the byte at this buffer's current position, and then increments the position.

Returns:

The byte at the buffer's current position.

Exceptions:

BufferUnderflowException (p. 957) if the buffer's current position is not smaller than its limit.

- virtual unsigned char **get (int index)** const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the byte at the given index.

Parameters:

index The index in the *Buffer* (p. 928) where the byte is to be read.

Returns:

the byte that is located at the given index.

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit, or *index* is negative.

- virtual char **getChar ()** throw (decaf::nio::BufferUnderflowException)

Reads the next byte at this buffer's current position, and then increments the position by one.

Returns:

the next char in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

- virtual char **getChar (int index)** const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads one byte at the given index and returns it.

Parameters:

index The index in the *Buffer* (p. 928) where the byte is to be read.

Returns:

the char at the given index in the buffer

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit, or *index* is negative.

- virtual double **getDouble** () throw (decaf::nio::BufferUnderflowException)

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next double in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

- virtual double **getDouble** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the double at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit, or *index* is negative.

- virtual float **getFloat** () throw (decaf::nio::BufferUnderflowException)

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next float in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

- virtual float **getFloat** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the float at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or *index* is negative.

- virtual long long **getLong** () throw (decaf::nio::BufferUnderflowException)

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next long long in the buffer.

Exceptions:

BufferUnderflowException (p. 957) *if there are no more bytes remaining in this buffer, meaning we have reached the set limit.*

- virtual long long **getLong** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the long long at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException *if there are not enough bytes remaining to fill the requested Data Type, or index is negative.*

- virtual int **getInt** () throw (decaf::nio::BufferUnderflowException)

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next int in the buffer.

Exceptions:

BufferUnderflowException (p. 957) *if there are no more bytes remaining in this buffer, meaning we have reached the set limit.*

- virtual int **getInt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the int at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException *if there are not enough bytes remaining to fill the requested Data Type, or index is negative.*

- virtual short **getShort** () throw (decaf::nio::BufferUnderflowException)

Reads the next two bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next short in the buffer.

Exceptions:

BufferUnderflowException (p. 957) *if there are no more bytes remaining in this buffer, meaning we have reached the set limit.*

- virtual short **getShort** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Reads two bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the short at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

- virtual **ByteBuffer** & **put** (unsigned char value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given byte into this buffer at the current position, and then increments the position.

Parameters:

value - the byte value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **put** (int index, unsigned char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given byte into this buffer at the given index.

Parameters:

index - position in the **Buffer** (p. 928) to write the data
value - the byte to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putChar** (char value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes one byte containing the given value, into this buffer at the current position, and then increments the position by one.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **ByteBuffer** & **putChar** (int index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes one byte containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **ByteBuffer** & **putDouble** (double value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **ByteBuffer** & **putDouble** (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putFloat** (float value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putFloat** (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putLong** (long long value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putLong** (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putInt** (int value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **ByteBuffer** & **putInt** (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index *The position in the **Buffer** (p. 928) to write the data.*
value *The value to write.*

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **ByteBuffer** & **putShort** (short value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes two bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value *The value to be written.*

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** & **putShort** (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes two bytes containing the given value, into this buffer at the given index.

Parameters:

index *The position in the **Buffer** (p. 928) to write the data*
value *The value to write.*

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ByteBuffer** * **slice** () const

Creates a new byte buffer whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the newly create **ByteBuffer** (p. 1031) which the caller owns.*

Protected Member Functions

- virtual void **setReadOnly** (bool value)

*Sets this **ByteBuffer** (p. 991) as Read-Only or not Read-Only.*

6.166.1 Detailed Description

This class defines six categories of operations upon byte buffers: 1. Absolute and relative get and put methods that read and write single bytes; 2. Relative bulk get methods that transfer contiguous sequences of bytes from this buffer into an array; 3. Relative bulk put methods that transfer contiguous sequences of bytes from a byte array or some other byte buffer into this buffer; 4. Absolute and relative get and put methods that read and write values of other primitive types, translating them to and from sequences of bytes in a particular byte order; 5. Methods for creating view buffers, which allow a byte buffer to be viewed as a buffer containing values of some other primitive type; and 6. Methods for compacting, duplicating, and slicing a byte buffer.

Byte buffers can be created either by allocation, which allocates space for the buffer's content, or by wrapping an existing byte array into a buffer.

Access to binary data:

This class defines methods for reading and writing values of all other primitive types, except boolean. Primitive values are translated to (or from) sequences of bytes according to the buffer's current byte order.

For access to heterogeneous binary data, that is, sequences of values of different types, this class defines a family of absolute and relative get and put methods for each type. For 32-bit floating-point values, for example, this class defines:

float **getFloat()** (p. 1010) float **getFloat(int index)** void **putFloat(float f)** (p. 1016) void **putFloat(int index, float f)** (p. 1015)

Corresponding methods are defined for the types char, short, int, long, and double. The index parameters of the absolute get and put methods are in terms of bytes rather than of the type being read or written.

For access to homogeneous binary data, that is, sequences of values of the same type, this class defines methods that can create views of a given byte buffer. A view buffer is simply another buffer whose content is backed by the byte buffer. Changes to the byte buffer's content will be visible in the view buffer, and vice versa; the two buffers' position, limit, and mark values are independent. The **asFloatBuffer** method, for example, creates an instance of the **FloatBuffer** class that is backed by the byte buffer upon which the method is invoked. Corresponding view-creation methods are defined for the types char, short, int, long, and double.

View buffers have two important advantages over the families of type-specific get and put methods described above:

A view buffer is indexed not in terms of bytes but rather in terms of the type-specific size of its values;

A view buffer provides relative bulk get and put methods that can transfer contiguous sequences of values between a buffer and an array or some other buffer of the same type; and

Since:

1.0

6.166.2 Constructor & Destructor Documentation

6.166.2.1 decaf::internal::nio::ByteBuffer::ByteBuffer (int *capacity*, bool *readOnly* = false) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a **ByteBuffer** (p. 991) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size of the array, this is the limit we read and write to.

readOnly Should this buffer be read-only, default as false

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.166.2.2 decaf::internal::nio::ByteBuffer::ByteBuffer (unsigned char * *array*, int *size*, int *offset*, int *length*, bool *readOnly* = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a **ByteBuffer** (p. 991) object that wraps the given array.

Parameters:

array The array to wrap.

size The size of the array passed.

offset The position that is this buffers start position.

length The size of the sub-array, this is the limit we read and write to.

readOnly Should this buffer be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if the preconditions of size, offset and length are violated.

6.166.2.3 `decaf::internal::nio::ByteBuffer::ByteBuffer`
 (const decaf::lang::Pointer< ByteBufferAdapter > &
array, int *offset*, int *length*, bool *readOnly* = false)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteBufferAdapter and start at the given offset. The capacity and limit of the new **ByteBuffer** (p. 991) will be that of the remaining capacity of the passed buffer.

Parameters:

array The ByteBufferAdapter to wrap
offset The offset into array where the buffer starts
length The length of the array we are wrapping or limit.
readOnly Boolean indicating if this a readOnly buffer.

Exceptions:

NullPointerException if array is NULL
IndexOutOfBoundsException if offset is greater than array capacity.

6.166.2.4 `decaf::internal::nio::ByteBuffer::ByteBuffer` (const
 ByteBuffer & *other*)

Create a **ByteBuffer** (p. 991) that mirrors this one, meaning it shares a reference to this buffers ByteBufferAdapter and when changes are made to that data it is reflected in both.

Parameters:

other The **ByteBuffer** (p. 991) this one is to mirror.

6.166.2.5 `virtual decaf::internal::nio::ByteBuffer::~~ByteBuffer` ()
 [virtual]

6.166.3 Member Function Documentation

6.166.3.1 `virtual unsigned char* decaf::internal::nio::ByteBuffer::array`
 () throw (decaf::nio::ReadOnlyBufferException,
 decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Returns the byte array that backs this buffer.

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The array that backs this buffer

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is backed by an array but is read-only
UnsupportedOperationException if this buffer is not backed by an accessible array

Implements **decaf::nio::ByteBuffer** (p.1037).

6.166.3.2 `virtual int decaf::internal::nio::ByteBuffer::arrayOffset
 () const throw (decaf::nio::ReadOnlyBufferException,
 decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer.

If this buffer is backed by an array then buffer position *p* corresponds to array index *p* + **array-Offset()** (p.1037).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset within this buffer's array of the first element of the buffer.

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is backed by an array but is read-only.
UnsupportedOperationException if this buffer is not backed by an accessible array.

Implements **decaf::nio::ByteBuffer** (p.1037).

6.166.3.3 `virtual decaf::nio::CharBuffer* de-
 caf::internal::nio::ByteBuffer::asCharBuffer () const
 [inline, virtual]`

Creates a view of this byte buffer as a char buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new **Char Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p.1037).

6.166.3.4 `virtual decaf::nio::DoubleBuffer* de-
 caf::internal::nio::ByteBuffer::asDoubleBuffer ()
 const [inline, virtual]`

Creates a view of this byte buffer as a double buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new double **Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1038).

6.166.3.5 **virtual decaf::nio::FloatBuffer* de-**
caf::internal::nio::ByteBuffer::asFloatBuffer () const
[inline, virtual]

Creates a view of this byte buffer as a float buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new float **Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1038).

6.166.3.6 **virtual decaf::nio::IntBuffer* de-**
caf::internal::nio::ByteBuffer::asIntBuffer () const
[inline, virtual]

Creates a view of this byte buffer as a int buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new int **Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1038).

6.166.3.7 `virtual decaf::nio::LongBuffer* decaf::internal::nio::ByteBuffer::asLongBuffer () const`
[inline, virtual]

Creates a view of this byte buffer as a long buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new long **Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1039).

6.166.3.8 `virtual ByteBuffer* decaf::internal::nio::ByteBuffer::asReadOnlyBuffer () const`
[virtual]

Creates a new, read-only byte buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only byte buffer which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1039).

6.166.3.9 `virtual decaf::nio::ShortBuffer* decaf::internal::nio::ByteBuffer::asShortBuffer () const`
[inline, virtual]

Creates a view of this byte buffer as a short buffer.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by two, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new short **Buffer** (p. 928), which the caller then owns.

Implements **decaf::nio::ByteBuffer** (p. 1039).

6.166.3.10 **virtual ByteBuffer& decaf::internal::nio::ByteBuffer::compact () throw (decaf::nio::ReadOnlyBufferException)** [virtual]

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **ByteBuffer** (p. 1031).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p. 1040).

6.166.3.11 **virtual ByteBuffer* decaf::internal::nio::ByteBuffer::duplicate ()** [virtual]

Creates a new byte buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new **Byte Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::ByteBuffer** (p. 1040).

6.166.3.12 **virtual unsigned char decaf::internal::nio::ByteBuffer::get (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)** [virtual]

Absolute get method.

Reads the byte at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the byte is to be read.

Returns:

the byte that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1040).

6.166.3.13 `virtual unsigned char decaf::internal::nio::ByteArrayBuffer::get () const
throw (decaf::nio::BufferUnderflowException) [virtual]`

Relative get method.

Reads the byte at this buffer's current position, and then increments the position.

Returns:

The byte at the buffer's current position.

Exceptions:

BufferUnderflowException (p. 957) if the buffer's current position is not smaller than its limit.

Implements **decaf::nio::ByteBuffer** (p. 1041).

6.166.3.14 `virtual char decaf::internal::nio::ByteArrayBuffer::getChar (int index)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[inline, virtual]`

Reads one byte at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the byte is to be read.

Returns:

the char at the given index in the buffer

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1042).

6.166.3.15 virtual char decaf::internal::nio::ByteArrayBuffer::getChar () throw (decaf::nio::BufferUnderflowException) [inline, virtual]

Reads the next byte at this buffer's current position, and then increments the position by one.

Returns:

the next char in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1042).

6.166.3.16 virtual double decaf::internal::nio::ByteArrayBuffer::getDouble (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the double at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1043).

6.166.3.17 virtual double decaf::internal::nio::ByteArrayBuffer::getDouble () throw (decaf::nio::BufferUnderflowException) [virtual]

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next double in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1043).

6.166.3.18 virtual float decaf::internal::nio::ByteBuffer::getFloat (int *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the float at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1043).

6.166.3.19 virtual float decaf::internal::nio::ByteBuffer::getFloat () throw (
decaf::nio::BufferUnderflowException) [virtual]

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next float in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1044).

6.166.3.20 virtual int decaf::internal::nio::ByteBuffer::getInt (int *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the int at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1044).

6.166.3.21 `virtual int decaf::internal::nio::ByteBuffer::getInt () throw (decaf::nio::BufferUnderflowException) [virtual]`

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next int in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1044).

6.166.3.22 `virtual long long decaf::internal::nio::ByteBuffer::getLong (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the long long at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1045).

6.166.3.23 `virtual long long decaf::internal::nio::ByteBuffer::getLong () throw (decaf::nio::BufferUnderflowException) [virtual]`

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next long long in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1045).

6.166.3.24 virtual short decaf::internal::nio::ByteBuffer::getShort (int *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Reads two bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the short at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implements **decaf::nio::ByteBuffer** (p. 1045).

6.166.3.25 virtual short decaf::internal::nio::ByteBuffer::getShort () throw (
decaf::nio::BufferUnderflowException) [virtual]

Reads the next two bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next short in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implements **decaf::nio::ByteBuffer** (p. 1046).

6.166.3.26 virtual bool decaf::internal::nio::ByteBuffer::hasArray () const
[inline, virtual]

Tells whether or not this buffer is backed by an accessible byte array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implements **decaf::nio::ByteBuffer** (p. 1046).

6.166.3.27 `virtual bool decaf::internal::nio::ByteBuffer::isReadOnly () const`
[inline, virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only

Implements `decaf::nio::ByteBuffer` (p. 1046).

6.166.3.28 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::put`
(int *index*, unsigned char *value*) throw (de-
caf::lang::exceptions::IndexOutOfBoundsException,
decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given byte into this buffer at the given index.

Parameters:

index - position in the **Buffer** (p. 928) to write the data

value - the byte to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements `decaf::nio::ByteBuffer` (p. 1046).

6.166.3.29 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::put`
(unsigned char *value*) throw (decaf::nio::BufferOverflowException,
decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given byte into this buffer at the current position, and then increments the position.

Parameters:

value - the byte value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements `decaf::nio::ByteBuffer` (p. 1047).

6.166.3.30 virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putChar (int *index*, char *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes one byte containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::ByteBuffer** (p. 1049).

6.166.3.31 virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putChar (char *value*) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes one byte containing the given value, into this buffer at the current position, and then increments the position by one.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::ByteBuffer** (p. 1049).

6.166.3.32 virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putDouble (int *index*, double *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p. 1050).

6.166.3.33 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putDouble (double value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::ByteBuffer** (p. 1050).

6.166.3.34 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putFloat (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p.1050).

6.166.3.35 virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putFloat (float *value*) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p.1051).

6.166.3.36 virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putInt (int *index*, int *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::ByteBuffer** (p.1051).

6.166.3.37 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putInt (int value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements `decaf::nio::ByteBuffer` (p. 1052).

6.166.3.38 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putLong (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements `decaf::nio::ByteBuffer` (p. 1052).

6.166.3.39 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putLong (long long value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p.1052).

6.166.3.40 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putShort (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)` [virtual]

Writes two bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p.928) to write the data

value The value to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p.1053).

6.166.3.41 `virtual ByteBuffer& decaf::internal::nio::ByteBuffer::putShort (short value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)` [virtual]

Writes two bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ByteBuffer** (p. 1053).

6.166.3.42 `virtual void decaf::internal::nio::ByteBuffer::setReadOnly (bool value) [inline, protected, virtual]`

Sets this **ByteBuffer** (p. 991) as Read-Only or not Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.166.3.43 `virtual ByteBuffer* decaf::internal::nio::ByteBuffer::slice () const [virtual]`

Creates a new byte buffer whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **ByteBuffer** (p. 1031) which the caller owns.

Implements **decaf::nio::ByteBuffer** (p. 1054).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/ByteBuffer.h`

6.167 decaf::io::ByteArrayInputStream Class Reference

A **ByteArrayInputStream** (p.1020) contains an **internal** (p.144) buffer that contains bytes that may be read from the stream.

#include <src/main/decaf/io/ByteArrayInputStream.h> Inheritance diagram for decaf::io::ByteArrayInputStream:

Public Member Functions

- **ByteArrayInputStream** ()
*Creates an **ByteArrayInputStream** (p.1020) with an empty input buffer, the buffer can be initialized with a call to **setByteArray**.*
- **ByteArrayInputStream** (const std::vector< unsigned char > &buffer)
*Creates the input stream and calls **setBuffer** with the specified buffer object.*
- **ByteArrayInputStream** (const unsigned char *buffer, int bufferSize, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
*Create an instance of the **ByteArrayInputStream** (p.1020) with the given buffer as the source of input for all read operations.*
- **ByteArrayInputStream** (const unsigned char *buffer, int bufferSize, int offset, int length, bool own=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
*Create an instance of the **ByteArrayInputStream** (p.1020) with the given buffer as the source of input for all read operations.*
- virtual ~**ByteArrayInputStream** ()
- virtual void **setByteArray** (const std::vector< unsigned char > &buffer)
*Sets the **internal** (p.144) buffer.*
- virtual void **setByteArray** (const unsigned char *buffer, int bufferSize) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Sets the data that this reader uses, replaces any existing data and resets to beginning of the buffer.
- virtual void **setByteArray** (const unsigned char *buffer, int bufferSize, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Sets the data that this reader uses, replaces any existing data and resets to beginning of the buffer.
- virtual int **available** () const throw (IOException)
*Indicates the number of bytes available.
The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data avaiable. The caller should view the result of this method as an absolute.
The default implementation of this method returns zero.*

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual long long **skip** (long long num) throw (io::IOException, lang::exceptions::UnsupportedOperationException)

Skips over and discards n bytes of data from this input stream.

*The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*

Parameters:

num *The number of bytes to skip.*

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

- virtual void **mark** (int readLimit)

Marks the current position in the stream. A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit *The max bytes read before marked position is invalid.*

- virtual void **reset** () throw (IOException)

Repositions this stream to the position at the time the mark method was last called on this input stream.

*If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.*

*If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.*

*The default implementation of this method throws an **IOException** (p. 2142).*

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual bool **markSupported** () const

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Protected Member Functions

- virtual int **doReadByte** () throw (IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.167.1 Detailed Description

A **ByteArrayInputStream** (p.1020) contains an **internal** (p.144) buffer that contains bytes that may be read from the stream. An **internal** (p.144) counter keeps track of the next byte to be supplied by the read method. The **ByteArrayInputStream** (p.1020) never copies the supplied buffers, only points to them, therefore the caller must ensure that the supplied buffer remain in scope, or is not deleted before this **ByteArrayInputStream** (p.1020) is freed. If the own argument of one of the constructors that accepts an array pointer is set to true than the **ByteArrayInputStream** (p.1020) instance will take ownership of the supplied pointer and delete it when that instance is destroyed.

Closing a **ByteArrayInputStream** (p.1020) has no effect. The methods in this class can be called after the stream has been closed without generating an **IOException** (p.2142).

Since:

1.0

6.167.2 Constructor & Destructor Documentation

6.167.2.1 decaf::io::ByteArrayInputStream::ByteArrayInputStream ()

Creates an **ByteArrayInputStream** (p.1020) with an empty input buffer, the buffer can be initialized with a call to **setByteArray**.

6.167.2.2 decaf::io::ByteArrayInputStream::ByteArrayInputStream (const std::vector< unsigned char > & *buffer*)

Creates the input stream and calls **setBuffer** with the specified buffer object.

Parameters:

buffer The buffer to be used.

6.167.2.3 `decaf::io::ByteArrayInputStream::ByteArrayInputStream (const unsigned char * buffer, int bufferSize, bool own = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)`

Create an instance of the **ByteArrayInputStream** (p. 1020) with the given buffer as the source of input for all read operations.

Parameters:

buffer The initial byte array to use to read from.

bufferSize The size of the buffer.

own Indicates if this object should take ownership of the array, default is false.

Exceptions:

NullPointerException if the buffer is Null.

IllegalArgumentException if the bufferSize is negative.

6.167.2.4 `decaf::io::ByteArrayInputStream::ByteArrayInputStream (const unsigned char * buffer, int bufferSize, int offset, int length, bool own = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)`

Create an instance of the **ByteArrayInputStream** (p. 1020) with the given buffer as the source of input for all read operations.

Parameters:

buffer The initial byte array to use to read from.

bufferSize The size of the buffer.

offset The offset into the buffer to begin reading from.

length The number of bytes to read past the offset.

own Indicates if this object should take ownership of the array, default is false.

Exceptions:

NullPointerException if the buffer is Null.

IllegalArgumentException if the bufferSize is negative.

6.167.2.5 `virtual decaf::io::ByteArrayInputStream::~~ByteArrayInputStream () [virtual]`

6.167.3 Member Function Documentation

6.167.3.1 `virtual int decaf::io::ByteArrayInputStream::available () const throw (IOException) [virtual]`

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.167.3.2 `virtual int decaf::io::ByteArrayInputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Reimplemented from **decaf::io::InputStream** (p. 2046).

6.167.3.3 `virtual int decaf::io::ByteArrayInputStream::doReadByte () throw (IOException)` [protected, virtual]

Implements **decaf::io::InputStream** (p. 2046).

6.167.3.4 `virtual void decaf::io::ByteArrayInputStream::mark (int readLimit)` [virtual]

Marks the current position in the stream A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Reimplemented from **decaf::io::InputStream** (p. 2046).

6.167.3.5 `virtual bool decaf::io::ByteArrayInputStream::markSupported () const` [inline, virtual]

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Reimplemented from **decaf::io::InputStream** (p. 2047).

6.167.3.6 virtual void decaf::io::ByteArrayInputStream::reset () throw (IOException) [virtual]

Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2049).

6.167.3.7 virtual void decaf::io::ByteArrayInputStream::setByteArray (const unsigned char * buffer, int bufferSize, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Sets the data that this reader uses, replaces any existing data and resets to beginning of the buffer.

Parameters:

buffer The initial byte array to use to read from.

bufferSize The size of the buffer.

offset The offset into the buffer to begin reading from.

length The number of bytes to read past the offset.

Exceptions:

NullPointerException if the buffer is Null.

IllegalArgumentException if the bufferSize is negative.

6.167.3.8 virtual void decaf::io::ByteArrayInputStream::setByteArray
(const unsigned char * *buffer*, int *bufferSize*)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException) [virtual]

Sets the data that this reader uses, replaces any existing data and resets to beginning of the buffer.

Parameters:

buffer The initial byte array to use to read from.

bufferSize The size of the buffer.

Exceptions:

NullPointerException if the buffer is Null.

IllegalArgumentException if the bufferSize is negative.

6.167.3.9 virtual void decaf::io::ByteArrayInputStream::setByteArray (const
std::vector< unsigned char > & *buffer*) [virtual]

Sets the **internal** (p.144) buffer. The input stream will wrap around this buffer and will perform all read operations on it. The position will be reinitialized to the beginning of the specified buffer. This class will not own the given buffer - it is the caller's responsibility to free the memory of the given buffer as appropriate.

Parameters:

buffer The buffer to be used.

6.167.3.10 virtual long long decaf::io::ByteArrayInputStream::skip
(long long *num*) throw (io::IOException,
lang::exceptions::UnsupportedOperationException)
[virtual]

Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p.2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from **decaf::io::InputStream** (p. 2050).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/ByteArrayInputStream.h`

6.168 decaf::io::ByteArrayOutputStream Class Reference

#include <src/main/decaf/io/ByteArrayOutputStream.h> Inheritance diagram for decaf::io::ByteArrayOutputStream:

Public Member Functions

- **ByteArrayOutputStream** ()
*Default Constructor - uses a default **internal** (p. 144) buffer of 32 bytes, the size increases as the need for more room arises.*
- **ByteArrayOutputStream** (int bufferSize) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **ByteArrayOutputStream** (p. 1028) with an **internal** (p. 144) buffer allocated with the given size.*
- virtual ~**ByteArrayOutputStream** ()
- std::pair< unsigned char *, int > **toByteArray** () const
Creates a newly allocated byte array.
- long long **size** () const
*Gets the current count of bytes written into this **ByteArrayOutputStream** (p. 1028).*
- virtual void **reset** () throw (IOException)
Clear current Stream contents.
- virtual std::string **toString** () const
Converts the bytes in the buffer into a standard C++ string.
- void **writeTo** (OutputStream *out) const throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
Writes the complete contents of this byte array output stream to the specified output stream argument, as if by calling the output stream's write method using out.write(buf, 0, count).

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.168.1 Constructor & Destructor Documentation

6.168.1.1 decaf::io::ByteArrayOutputStream::ByteArrayOutputStream ()

Default Constructor - uses a default **internal** (p. 144) buffer of 32 bytes, the size increases as the need for more room arises.

6.168.1.2 `decaf::io::ByteArrayOutputStream::ByteArrayOutputStream (int bufferSize) throw (decaf::lang::exceptions::IllegalArgumentException)`

Creates a `ByteArrayOutputStream` (p. 1028) with an `internal` (p. 144) buffer allocated with the given size.

Parameters:

bufferSize The size to use for the `internal` (p. 144) buffer.

Exceptions:

IllegalArgumentException if the size is less than or equal to zero.

6.168.1.3 `virtual decaf::io::ByteArrayOutputStream::~~ByteArrayOutputStream () [virtual]`

6.168.2 Member Function Documentation

6.168.2.1 `virtual void decaf::io::ByteArrayOutputStream::doWriteArrayBounded (const unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]`

Reimplemented from `decaf::io::OutputStream` (p. 2909).

6.168.2.2 `virtual void decaf::io::ByteArrayOutputStream::doWriteByte (unsigned char value) throw (decaf::io::IOException) [protected, virtual]`

Implements `decaf::io::OutputStream` (p. 2910).

6.168.2.3 `virtual void decaf::io::ByteArrayOutputStream::reset () throw (IOException) [virtual]`

Clear current Stream contents.

Exceptions:

IOException (p. 2142)

6.168.2.4 `long long decaf::io::ByteArrayOutputStream::size () const`

Gets the current count of bytes written into this `ByteArrayOutputStream` (p. 1028).

Returns:

the number of valid bytes contained in the `ByteArrayOutputStream` (p. 1028).

6.168.2.5 `std::pair<unsigned char*, int> decaf::io::ByteArrayOutputStream::toByteArray () const`

Creates a newly allocated byte array. Its size is the current size of this output stream and the valid contents of the buffer have been copied into it. The newly allocated array and its size are returned inside an STL pair structure, the caller is responsible for freeing the returned array.

Returns:

an STL pair containing the copied array and its size.

6.168.2.6 `virtual std::string decaf::io::ByteArrayOutputStream::toString () const [virtual]`

Converts the bytes in the buffer into a standard C++ string.

Returns:

a string containing the bytes in the buffer

Reimplemented from `decaf::io::OutputStream` (p. 2911).

6.168.2.7 `void decaf::io::ByteArrayOutputStream::writeTo (OutputStream * out) const throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)`

Writes the complete contents of this byte array output stream to the specified output stream argument, as if by calling the output stream's write method using `out.write(buf, 0, count)`.

The documentation for this class was generated from the following file:

- `src/main/decaf/io/ByteArrayOutputStream.h`

6.169 decaf::nio::ByteBuffer Class Reference

This class defines six categories of operations upon byte buffers:.

```
#include <src/main/decaf/nio/ByteBuffer.h> Inheritance diagram for decaf::nio::ByteBuffer:
```

Public Member Functions

- virtual **~ByteBuffer** ()
- virtual std::string **toString** () const
- **ByteBuffer** & **get** (std::vector< unsigned char > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **ByteBuffer** & **get** (unsigned char *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- **ByteBuffer** & **put** (**ByteBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)
This method transfers the bytes remaining in the given source buffer into this buffer.
- **ByteBuffer** & **put** (const unsigned char *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
This method transfers bytes into this buffer from the given source array.
- **ByteBuffer** & **put** (std::vector< unsigned char > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)
This method transfers the entire content of the given source byte array into this buffer.
- virtual bool **isReadOnly** () const =0
Tells whether or not this buffer is read-only.
- virtual unsigned char * **array** ()=0 throw (ReadOnlyBufferException, decaf::lang::exceptions::UnsupportedOperationException)
Returns the byte array that backs this buffer.
- virtual int **arrayOffset** () const =0 throw (ReadOnlyBufferException, decaf::lang::exceptions::UnsupportedOperationException)
Returns the offset within this buffer's backing array of the first element of the buffer.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible byte array.
- virtual **CharBuffer** * **asCharBuffer** () const =0

Creates a view of this byte buffer as a char buffer.

- virtual **DoubleBuffer** * **asDoubleBuffer** () const =0
Creates a view of this byte buffer as a double buffer.
- virtual **FloatBuffer** * **asFloatBuffer** () const =0
Creates a view of this byte buffer as a float buffer.
- virtual **IntBuffer** * **asIntBuffer** () const =0
Creates a view of this byte buffer as a int buffer.
- virtual **LongBuffer** * **asLongBuffer** () const =0
Creates a view of this byte buffer as a long buffer.
- virtual **ShortBuffer** * **asShortBuffer** () const =0
Creates a view of this byte buffer as a short buffer.
- virtual **ByteBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only byte buffer that shares this buffer's content.
- virtual **ByteBuffer** & **compact** ()=0 throw (**ReadOnlyBufferException**)
Compacts this buffer.
- virtual **ByteBuffer** * **duplicate** ()=0
Creates a new byte buffer that shares this buffer's content.
- virtual unsigned char **get** () const =0 throw (**BufferUnderflowException**)
Relative get method.
- virtual unsigned char **get** (int index) const =0 throw (**decaf::lang::exceptions::IndexOutOfBoundsException**)
Absolute get method.
- virtual char **getChar** ()=0 throw (**BufferUnderflowException**)
Reads the next byte at this buffer's current position, and then increments the position by one.
- virtual char **getChar** (int index) const =0 throw (**decaf::lang::exceptions::IndexOutOfBoundsException**)
Reads one byte at the given index and returns it.
- virtual double **getDouble** ()=0 throw (**BufferUnderflowException**)
Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.
- virtual double **getDouble** (int index) const =0 throw (**decaf::lang::exceptions::IndexOutOfBoundsException**)
Reads eight bytes at the given index and returns it.
- virtual float **getFloat** ()=0 throw (**BufferUnderflowException**)
Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

- virtual float **getFloat** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads four bytes at the given index and returns it.
- virtual long long **getLong** ()=0 throw (BufferUnderflowException)
Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.
- virtual long long **getLong** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads eight bytes at the given index and returns it.
- virtual int **getInt** ()=0 throw (BufferUnderflowException)
Reads the next four bytes at this buffer's current position, and then increments the position by that amount.
- virtual int **getInt** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads four bytes at the given index and returns it.
- virtual short **getShort** ()=0 throw (BufferUnderflowException)
Reads the next two bytes at this buffer's current position, and then increments the position by that amount.
- virtual short **getShort** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads two bytes at the given index and returns it.
- virtual **ByteBuffer** & **put** (unsigned char value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes the given byte into this buffer at the current position, and then increments the position.
- virtual **ByteBuffer** & **put** (int index, unsigned char value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes the given byte into this buffer at the given index.
- virtual **ByteBuffer** & **putChar** (char value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes one byte containing the given value, into this buffer at the current position, and then increments the position by one.
- virtual **ByteBuffer** & **putChar** (int index, char value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes one byte containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** & **putDouble** (double value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

- virtual **ByteBuffer** & **putDouble** (int index, double value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes eight bytes containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** & **putFloat** (float value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.
- virtual **ByteBuffer** & **putFloat** (int index, float value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes four bytes containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** & **putLong** (long long value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.
- virtual **ByteBuffer** & **putLong** (int index, long long value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes eight bytes containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** & **putInt** (int value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.
- virtual **ByteBuffer** & **putInt** (int index, int value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes four bytes containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** & **putShort** (short value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes two bytes containing the given value, into this buffer at the current position, and then increments the position by eight.
- virtual **ByteBuffer** & **putShort** (int index, short value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes two bytes containing the given value, into this buffer at the given index.
- virtual **ByteBuffer** * **slice** () const =0
Creates a new byte buffer whose content is a shared subsequence of this buffer's content.
- virtual int **compareTo** (const **ByteBuffer** &value) const
- virtual bool **equals** (const **ByteBuffer** &value) const
- virtual bool **operator==** (const **ByteBuffer** &value) const

- virtual bool **operator**< (const **ByteBuffer** &value) const

Static Public Member Functions

- static **ByteBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)
Allocates a new byte buffer whose position will be zero its limit will be its capacity and its mark is not set.
- static **ByteBuffer** * **wrap** (unsigned char *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
*Wraps the passed buffer with a new **ByteBuffer** (p. 1031).*
- static **ByteBuffer** * **wrap** (std::vector< unsigned char > &buffer)
*Wraps the passed STL Byte Vector in a **ByteBuffer** (p. 1031).*

Protected Member Functions

- **ByteBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **ByteBuffer** (p. 1031) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.169.1 Detailed Description

This class defines six categories of operations upon byte buffers:. 1. Absolute and relative get and put methods that read and write single bytes; 2. Relative bulk get methods that transfer contiguous sequences of bytes from this buffer into an array; 3. Relative bulk put methods that transfer contiguous sequences of bytes from a byte array or some other byte buffer into this buffer; 4. Absolute and relative get and put methods that read and write values of other primitive types, translating them to and from sequences of bytes in a particular byte order; 5. Methods for creating view buffers, which allow a byte buffer to be viewed as a buffer containing values of some other primitive type; and 6. Methods for compacting, duplicating, and slicing a byte buffer.

Byte buffers can be created either by allocation, which allocates space for the buffer's content, or by wrapping an existing byte array into a buffer.

Access to binary data:

This class defines methods for reading and writing values of all other primitive types, except boolean. Primitive values are translated to (or from) sequences of bytes according to the buffer's current byte order.

For access to heterogeneous binary data, that is, sequences of values of different types, this class defines a family of absolute and relative get and put methods for each type. For 32-bit floating-point values, for example, this class defines:

float **getFloat**() (p. 1044) float **getFloat**(int index) void **putFloat**(float f) (p. 1051) void **putFloat**(int index, float f) (p. 1050)

Corresponding methods are defined for the types char, short, int, long, and double. The index parameters of the absolute get and put methods are in terms of bytes rather than of the type being read or written.

For access to homogeneous binary data, that is, sequences of values of the same type, this class defines methods that can create views of a given byte buffer. A view buffer is simply another buffer whose content is backed by the byte buffer. Changes to the byte buffer's content will be visible in the view buffer, and vice versa; the two buffers' position, limit, and mark values are independent. The asFloatBuffer method, for example, creates an instance of the **FloatBuffer** (p.1925) class that is backed by the byte buffer upon which the method is invoked. Corresponding view-creation methods are defined for the types char, short, int, long, and double.

View buffers have two important advantages over the families of type-specific get and put methods described above:

A view buffer is indexed not in terms of bytes but rather in terms of the type-specific size of its values;

A view buffer provides relative bulk get and put methods that can transfer contiguous sequences of values between a buffer and an array or some other buffer of the same type; and

6.169.2 Constructor & Destructor Documentation

6.169.2.1 decaf::nio::ByteBuffer::ByteBuffer (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **ByteBuffer** (p.1031) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size of the array, this is the limit we read and write to.

Exceptions:

IllegalArgumentException if capacity is negative.

6.169.2.2 virtual decaf::nio::ByteBuffer::~~ByteBuffer () [inline, virtual]

6.169.3 Member Function Documentation

6.169.3.1 static ByteBuffer* decaf::nio::ByteBuffer::allocate (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new byte buffer whose position will be zero its limit will be its capacity and its mark is not set.

Parameters:

capacity The **internal** (p.144) buffer's capacity.

Returns:

a newly allocated **ByteBuffer** (p.1031) which the caller owns.

Exceptions:

IllegalArgumentException if capacity is negative.

6.169.3.2 `virtual unsigned char* decaf::nio::ByteBuffer::array
() throw (ReadOnlyBufferException, de-
caf::lang::exceptions::UnsupportedOperationException)
[pure virtual]`

Returns the byte array that backs this buffer. Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The array that backs this buffer

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is backed by an array but is read-only
UnsupportedOperationException if this buffer is not backed by an accessible array

Implemented in `decaf::internal::nio::ByteArrayBuffer` (p. 1003).

6.169.3.3 `virtual int decaf::nio::ByteBuffer::arrayOffset
() const throw (ReadOnlyBufferException,
decaf::lang::exceptions::UnsupportedOperationException) [pure
virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer. If this buffer is backed by an array then buffer position `p` corresponds to array index `p + arrayOffset()` (p. 1037).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset within this buffer's array of the first element of the buffer.

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is backed by an array but is read-only
UnsupportedOperationException if this buffer is not backed by an accessible array.

Implemented in `decaf::internal::nio::ByteArrayBuffer` (p. 1004).

6.169.3.4 `virtual CharBuffer* decaf::nio::ByteBuffer::asCharBuffer () const [pure
virtual]`

Creates a view of this byte buffer as a char buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new Char **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1004).

6.169.3.5 virtual DoubleBuffer* decaf::nio::ByteBuffer::asDoubleBuffer () const
[pure virtual]

Creates a view of this byte buffer as a double buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new double **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1004).

6.169.3.6 virtual FloatBuffer* decaf::nio::ByteBuffer::asFloatBuffer () const [pure virtual]

Creates a view of this byte buffer as a float buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new float **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1005).

6.169.3.7 virtual IntBuffer* decaf::nio::ByteBuffer::asIntBuffer () const [pure virtual]

Creates a view of this byte buffer as a int buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by four, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new int **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1005).

6.169.3.8 virtual LongBuffer* decaf::nio::ByteBuffer::asLongBuffer () const [pure virtual]

Creates a view of this byte buffer as a long buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by eight, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new long **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1006).

6.169.3.9 virtual ByteBuffer* decaf::nio::ByteBuffer::asReadOnlyBuffer () const [pure virtual]

Creates a new, read-only byte buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only byte buffer which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1006).

6.169.3.10 virtual ShortBuffer* decaf::nio::ByteBuffer::asShortBuffer () const [pure virtual]

Creates a view of this byte buffer as a short buffer. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer divided by two, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the new short **Buffer** (p. 928), which the caller then owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1006).

6.169.3.11 virtual ByteBuffer& decaf::nio::ByteBuffer::compact () throw (ReadOnlyBufferException) [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **ByteBuffer** (p. 1031).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1007).

6.169.3.12 virtual int decaf::nio::ByteBuffer::compareTo (const ByteBuffer & value) const [virtual]

6.169.3.13 virtual ByteBuffer* decaf::nio::ByteBuffer::duplicate () [pure virtual]

Creates a new byte buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new Byte **Buffer** (p. 928) which the caller owns.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1007).

6.169.3.14 virtual bool decaf::nio::ByteBuffer::equals (const ByteBuffer & value) const [virtual]

6.169.3.15 virtual unsigned char decaf::nio::ByteBuffer::get (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the byte at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the byte is to be read.

Returns:

the byte that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1007).

6.169.3.16 **virtual unsigned char decaf::nio::ByteBuffer::get () const throw (BufferUnderflowException)** [pure virtual]

Relative get method. Reads the byte at this buffer's current position, and then increments the position.

Returns:

The byte at the buffer's current position.

Exceptions:

BufferUnderflowException (p. 957) if the buffer's current position is not smaller than its limit.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1008).

6.169.3.17 **ByteBuffer& decaf::nio::ByteBuffer::get (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)**

Relative bulk get method. This method transfers bytes from this buffer into the given destination array. If there are fewer bytes remaining in the buffer than are required to satisfy the request, that is, if `length > remaining()` (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies `length` bytes from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by `length`.

Parameters:

buffer The pointer to an allocated buffer to fill.

size The size of the passed in **Buffer** (p. 928).

offset The position in the buffer to start filling.

length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

IndexOutOfBoundsException if the preconditions of `size`, `offset`, or `length` are not met.

BufferUnderflowException (p. 957) if there are fewer than length bytes remaining in this buffer.

NullPointerException if the passed buffer is null.

6.169.3.18 `ByteBuffer& decaf::nio::ByteBuffer::get (std::vector< unsigned char > buffer) throw (BufferUnderflowException)`

Relative bulk get method. This method transfers bytes from this buffer into the given destination vector. An invocation of this method of the form `src.get(a)` behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call `buffer.resize(N)` before calling this get method.

Returns:

a reference to this Byte **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length bytes remaining in this buffer

6.169.3.19 `virtual char decaf::nio::ByteBuffer::getChar (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Reads one byte at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the byte is to be read.

Returns:

the char at the given index in the buffer

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implemented in `decaf::internal::nio::ByteArrayBuffer` (p. 1008).

6.169.3.20 `virtual char decaf::nio::ByteBuffer::getChar () throw (BufferUnderflowException) [pure virtual]`

Reads the next byte at this buffer's current position, and then increments the position by one.

Returns:

the next char in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in `decaf::internal::nio::ByteArrayBuffer` (p. 1009).

6.169.3.21 `virtual double decaf::nio::ByteBuffer::getDouble (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the double at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1009).

6.169.3.22 `virtual double decaf::nio::ByteBuffer::getDouble () throw (BufferUnderflowException) [pure virtual]`

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next double in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1009).

6.169.3.23 `virtual float decaf::nio::ByteBuffer::getFloat (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the float at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1010).

6.169.3.24 virtual float decaf::nio::ByteBuffer::getFloat () throw (
BufferUnderflowException) [pure virtual]

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next float in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1010).

6.169.3.25 virtual int decaf::nio::ByteBuffer::getInt (int *index*) const throw (
decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Reads four bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the int at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1010).

6.169.3.26 virtual int decaf::nio::ByteBuffer::getInt () throw (
BufferUnderflowException) [pure virtual]

Reads the next four bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next int in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1011).

6.169.3.27 `virtual long long decaf::nio::ByteBuffer::getLong (int index) const
throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure
virtual]`

Reads eight bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the long long at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1011).

6.169.3.28 `virtual long long decaf::nio::ByteBuffer::getLong () throw (
BufferUnderflowException) [pure virtual]`

Reads the next eight bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next long long in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1011).

6.169.3.29 `virtual short decaf::nio::ByteBuffer::getShort (int index) const throw (
decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Reads two bytes at the given index and returns it.

Parameters:

index The index in the **Buffer** (p. 928) where the bytes are to be read.

Returns:

the short at the given index in the buffer.

Exceptions:

IndexOutOfBoundsException if there are not enough bytes remaining to fill the requested Data Type, or index is negative.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1012).

6.169.3.30 virtual short decaf::nio::ByteBuffer::getShort () throw (BufferUnderflowException) [pure virtual]

Reads the next two bytes at this buffer's current position, and then increments the position by that amount.

Returns:

the next short in the buffer.

Exceptions:

BufferUnderflowException (p. 957) if there are no more bytes remaining in this buffer, meaning we have reached the set limit.

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1012).

6.169.3.31 virtual bool decaf::nio::ByteBuffer::hasArray () const [pure virtual]

Tells whether or not this buffer is backed by an accessible byte array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1012).

6.169.3.32 virtual bool decaf::nio::ByteBuffer::isReadOnly () const [pure virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only

Implements **decaf::nio::Buffer** (p. 931).

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1013).

6.169.3.33 virtual bool decaf::nio::ByteBuffer::operator< (const ByteBuffer & value) const [virtual]**6.169.3.34 virtual bool decaf::nio::ByteBuffer::operator== (const ByteBuffer & value) const [virtual]****6.169.3.35 virtual ByteBuffer& decaf::nio::ByteBuffer::put (int index, unsigned char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]**

Writes the given byte into this buffer at the given index.

Parameters:

index - position in the **Buffer** (p. 928) to write the data

value - the byte to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1013).

6.169.3.36 `virtual ByteBuffer& decaf::nio::ByteBuffer::put (unsigned char value)
throw (BufferOverflowException, ReadOnlyBufferException) [pure
virtual]`

Writes the given byte into this buffer at the current position, and then increments the position.

Parameters:

value - the byte value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1013).

6.169.3.37 `ByteBuffer& decaf::nio::ByteBuffer::put (std::vector< unsigned char >
& buffer) throw (BufferOverflowException, ReadOnlyBufferException)`

This method transfers the entire content of the given source byte array into this buffer. This is the same as calling `put(&buffer[0], buffer.size(), 0, buffer.size())`

Parameters:

buffer The buffer whose contents are copied to this **ByteBuffer** (p. 1031).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.169.3.38 `ByteBuffer& decaf::nio::ByteBuffer::put (const unsigned char * buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)`

This method transfers bytes into this buffer from the given source array. If there are more bytes to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no bytes are transferred and a **`BufferOverflowException`** (p. 954) is thrown.

Otherwise, this method copies `length` bytes from the given array into this buffer, starting at the given offset in the array and at the current position of this buffer. The position of this buffer is then incremented by `length`.

Parameters:

buffer The array from which bytes are to be read.

size The size of the given array.

offset The offset within the array of the first byte to be read.

length The number of bytes to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

`BufferOverflowException` (p. 954) if there is insufficient space in this buffer.

`ReadOnlyBufferException` (p. 3169) if this buffer is read-only.

`NullPointerException` if the passed buffer is null.

`IndexOutOfBoundsException` if the preconditions of `size`, `offset`, or `length` are not met.

6.169.3.39 `ByteBuffer& decaf::nio::ByteBuffer::put (ByteBuffer & src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)`

This method transfers the bytes remaining in the given source buffer into this buffer. If there are more bytes remaining in the source buffer than in this buffer, that is, if `src.remaining() > remaining()` (p. 933), then no bytes are transferred and a **`BufferOverflowException`** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` bytes from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

src The buffer to take bytes from an place in this one.

Returns:

a reference to this buffer

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer for the remaining bytes in the source buffer

IllegalArgumentException if the source buffer is this buffer

ReadOnlyBufferException (p. 3169) if this buffer is read-only

6.169.3.40 `virtual ByteBuffer& decaf::nio::ByteBuffer::putChar (int index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)` [pure virtual]

Writes one byte containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1014).

6.169.3.41 `virtual ByteBuffer& decaf::nio::ByteBuffer::putChar (char value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes one byte containing the given value, into this buffer at the current position, and then increments the position by one.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1014).

6.169.3.42 virtual ByteBuffer& decaf::nio::ByteBuffer::putDouble (int *index*, double *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1014).

6.169.3.43 virtual ByteBuffer& decaf::nio::ByteBuffer::putDouble (double *value*) throw (BufferOverflowException, ReadOnlyBufferException) [pure virtual]

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1015).

6.169.3.44 virtual ByteBuffer& decaf::nio::ByteBuffer::putFloat (int *index*, float *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1015).

6.169.3.45 `virtual ByteBuffer& decaf::nio::ByteBuffer::putFloat (float value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1016).

6.169.3.46 `virtual ByteBuffer& decaf::nio::ByteBuffer::putInt (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)` [pure virtual]

Writes four bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in `decaf::internal::nio::ByteBuffer` (p. 1016).

6.169.3.47 virtual ByteBuffer& decaf::nio::ByteBuffer::putInt (int *value*) throw (BufferOverflowException, ReadOnlyBufferException) [pure virtual]

Writes four bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1017).

6.169.3.48 virtual ByteBuffer& decaf::nio::ByteBuffer::putLong (int *index*, long long *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes eight bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The value to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p. 1017).

6.169.3.49 virtual ByteBuffer& decaf::nio::ByteBuffer::putLong (long long *value*) throw (BufferOverflowException, ReadOnlyBufferException) [pure virtual]

Writes eight bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1017).

6.169.3.50 `virtual ByteBuffer& decaf::nio::ByteBuffer::putShort (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)` [pure virtual]

Writes two bytes containing the given value, into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data

value The value to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1018).

6.169.3.51 `virtual ByteBuffer& decaf::nio::ByteBuffer::putShort (short value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes two bytes containing the given value, into this buffer at the current position, and then increments the position by eight.

Parameters:

value The value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there are fewer than bytes remaining in this buffer than the size of the data to be written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ByteBuffer** (p. 1018).

6.169.3.52 virtual ByteBuffer* decaf::nio::ByteBuffer::slice () const [pure virtual]

Creates a new byte buffer whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **ByteBuffer** (p.1031) which the caller owns.

Implemented in **decaf::internal::nio::ByteArrayBuffer** (p.1019).

6.169.3.53 virtual std::string decaf::nio::ByteBuffer::toString () const [virtual]**Returns:**

a std::string describing this object

6.169.3.54 static ByteBuffer* decaf::nio::ByteBuffer::wrap (std::vector< unsigned char > & *buffer*) [static]

Wraps the passed STL Byte Vector in a **ByteBuffer** (p.1031). The new buffer will be backed by the given byte array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be buffer.size(), its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling vector.resize(N).

Returns:

a new **ByteBuffer** (p.1031) that is backed by buffer, caller owns.

6.169.3.55 static ByteBuffer* decaf::nio::ByteBuffer::wrap (unsigned char * *array*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Wraps the passed buffer with a new **ByteBuffer** (p.1031). The new buffer will be backed by the given byte array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be array.length, its position will be offset, its limit will be offset + length, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

array The array that will back the new buffer.

size The size of the provided array.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new **ByteBuffer** (p. 1031) that is backed by buffer, caller owns.

Exceptions:

NullPointerException if the array passed in is NULL.

IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**ByteBuffer.h**

6.170 cms::BytesMessage Class Reference

A **BytesMessage** (p.1056) object is used to send a message containing a stream of unsigned bytes.

#include <src/main/cms/BytesMessage.h> Inheritance diagram for cms::BytesMessage:

Public Member Functions

- virtual **~BytesMessage** ()
- virtual void **setBodyBytes** (const unsigned char *buffer, int numBytes)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
sets the bytes given to the message body.
- virtual unsigned char * **getBodyBytes** () const =0 throw (cms::MessageNotReadableException, cms::CMSEException)
Gets the bytes that are contained in this message and returns them in a newly allocated array that becomes the property of the caller.
- virtual int **getBodyLength** () const =0 throw (cms::MessageNotReadableException, cms::CMSEException)
Returns the number of bytes contained in the body of this message.
- virtual void **reset** ()=0 throw (cms::MessageFormatException, cms::CMSEException)
Puts the message body in read-only mode and repositions the stream of bytes to the beginning.
- virtual bool **readBoolean** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Boolean from the Bytes message stream.
- virtual void **writeBoolean** (bool value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a boolean to the bytes message stream as a 1-byte value.
- virtual unsigned char **readByte** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Byte from the Bytes message stream.
- virtual void **writeByte** (unsigned char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte to the bytes message stream as a 1-byte value.
- virtual int **readBytes** (std::vector< unsigned char > &value) const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a byte array from the bytes message stream.
- virtual void **writeBytes** (const std::vector< unsigned char > &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a byte array to the bytes message stream using the vector size as the number of bytes to write.

- virtual int **readBytes** (unsigned char *buffer, int length) const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a portion of the bytes message stream.

- virtual void **writeBytes** (const unsigned char *value, int offset, int length)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a portion of a byte array to the bytes message stream.

- virtual char **readChar** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a Char from the Bytes message stream.

- virtual void **writeChar** (char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a char to the bytes message stream as a 1-byte value.

- virtual float **readFloat** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 32 bit float from the Bytes message stream.

- virtual void **writeFloat** (float value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a float to the bytes message stream as a 4 byte value.

- virtual double **readDouble** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 64 bit double from the Bytes message stream.

- virtual void **writeDouble** (double value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a double to the bytes message stream as a 8 byte value.

- virtual short **readShort** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 16 bit signed short from the Bytes message stream.

- virtual void **writeShort** (short value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a signed short to the bytes message stream as a 2 byte value.

- virtual unsigned short **readUnsignedShort** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 16 bit unsigned short from the Bytes message stream.

- virtual void **writeUnsignedShort** (unsigned short value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a unsigned short to the bytes message stream as a 2 byte value.

- virtual int **readInt** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 32 bit signed integer from the Bytes message stream.
- virtual void **writeInt** (int value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a signed int to the bytes message stream as a 4 byte value.
- virtual long long **readLong** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads a 64 bit long from the Bytes message stream.
- virtual void **writeLong** (long long value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a long long to the bytes message stream as a 8 byte value.
- virtual std::string **readString** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
Reads an ASCII String from the Bytes message stream.
- virtual void **writeString** (const std::string &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes an ASCII String to the Bytes message stream.
- virtual std::string **readUTF** () const =0 throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSEException)
*Reads an UTF String from the **BytesMessage** (p. 1056) stream.*
- virtual void **writeUTF** (const std::string &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
*Writes an UTF String to the **BytesMessage** (p. 1056) stream.*
- virtual **BytesMessage** * **clone** () const =0
Clones this message.

6.170.1 Detailed Description

A **BytesMessage** (p.1056) object is used to send a message containing a stream of unsigned bytes. It inherits from the **Message** (p.2534) interface and adds a bytes message body. The receiver of the message supplies the interpretation of the bytes using the methods added by the **BytesMessage** (p. 1056) interface.

The **BytesMessage** (p.1056) methods are based largely on those found in **decaf.io.DataInputStream** (p. 1566) and **decaf.io.DataOutputStream** (p. 1579).

Although the CMS API allows the use of message properties with byte messages, they are typically not used, since the inclusion of properties may affect the format.

The primitive types can be written explicitly using methods for each type. Because the C++ language is more limited when dealing with primitive types the JMS equivalent generic read and write methods that take Java objects cannot be provided in the CMS API.

When the message is first created, and when `clearBody` is called, the body of the message is in write-only mode. After the first call to `reset` has been made, the message body is in read-only mode. After a message has been sent, the client that sent it can retain and modify it without affecting the message that has been sent. The same message object can be sent multiple times. When a message has been received, the provider has called `reset` so that the message body is in read-only mode for the client.

If `clearBody` is called on a message in read-only mode, the message body is cleared and the message is in write-only mode.

If a client attempts to read a message in write-only mode, a **MessageNotReadableException** (p. 2723) is thrown.

If a client attempts to write a message in read-only mode, a **MessageNotWriteableException** (p. 2724) is thrown.

Since:

1.0

6.170.2 Constructor & Destructor Documentation

6.170.2.1 `virtual cms::BytesMessage::~~BytesMessage () [inline, virtual]`

6.170.3 Member Function Documentation

6.170.3.1 `virtual BytesMessage* cms::BytesMessage::clone () const [pure virtual]`

Clones this message.

Returns:

a deep copy of this message.

Exceptions:

CMSException (p. 1160) - if an internal error occurs while cloning the **Message** (p. 2534).

Implements **cms::Message** (p. 2539).

Implemented in **activemq::commands::ActiveMQBytesMessage** (p. 236).

6.170.3.2 `virtual unsigned char* cms::BytesMessage::getBodyBytes () const throw (cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Gets the bytes that are contained in this message and returns them in a newly allocated array that becomes the property of the caller. This is a copy of the data contained in this message, changing the value contained in this array has no effect on the data contained in this message.

Returns:

pointer to a byte buffer that the call owns upon completion of this method.

Exceptions:

CMSException (p. 1160) - If an internal error occurs.

MessageNotReadableException (p. 2723) - If the message is in Write Only Mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 237).

6.170.3.3 `virtual int cms::BytesMessage::getBodyLength () const throw (cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Returns the number of bytes contained in the body of this message.

Returns:

number of bytes.

Exceptions:

CMSException (p. 1160) - If an internal error occurs.

MessageNotReadableException (p. 2723) - If the message is in Write Only Mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 238).

6.170.3.4 `virtual bool cms::BytesMessage::readBoolean () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a Boolean from the Bytes message stream.

Returns:

boolean value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 238).

6.170.3.5 `virtual unsigned char cms::BytesMessage::readByte () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a Byte from the Bytes message stream.

Returns:

unsigned char value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 239).

6.170.3.6 `virtual int cms::BytesMessage::readBytes (unsigned char *
buffer, int length) const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [pure
virtual]`

Reads a portion of the bytes message stream. If the length of array value is less than the number of bytes remaining to be read from the stream, the array should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of array value, the bytes should be read into the array. The return value of the total number of bytes read will be less than the length of the array, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

If length is negative, or length is greater than the length of the array value, then an `IndexOutOfBoundsException` is thrown. No bytes will be read from the stream for this exception case.

Parameters:

buffer the buffer into which the data is read

length the number of bytes to read; must be less than or equal to value.length

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 239).

6.170.3.7 `virtual int cms::BytesMessage::readBytes (std::vector< unsigned
char > & value) const throw (cms::MessageEOFException,
cms::MessageNotReadableException, cms::CMSEException) [pure
virtual]`

Reads a byte array from the bytes message stream. If the length of vector value is less than the number of bytes remaining to be read from the stream, the vector should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of vector value, the bytes should be read into the vector. The return value of the total number of bytes read will be less than the length of the vector, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

Parameters:

value buffer to place data in

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 240).

6.170.3.8 `virtual char cms::BytesMessage::readChar () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a Char from the Bytes message stream.

Returns:

char value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 240).

6.170.3.9 `virtual double cms::BytesMessage::readDouble () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 64 bit double from the Bytes message stream.

Returns:

double value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 240).

6.170.3.10 `virtual float cms::BytesMessage::readFloat () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 32 bit float from the Bytes message stream.

Returns:

double value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 241).

6.170.3.11 `virtual int cms::BytesMessage::readInt () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 32 bit signed integer from the Bytes message stream.

Returns:

int value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 241).

6.170.3.12 `virtual long long cms::BytesMessage::readLong () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 64 bit long from the Bytes message stream.

Returns:

long long value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 241).

6.170.3.13 virtual short cms::BytesMessage::readShort () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]

Reads a 16 bit signed short from the Bytes message stream.

Returns:

short value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in **activemq::commands::ActiveMQBytesMessage** (p. 242).

6.170.3.14 virtual std::string cms::BytesMessage::readString () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]

Reads an ASCII String from the Bytes message stream.

Returns:

String from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in **activemq::commands::ActiveMQBytesMessage** (p. 242).

6.170.3.15 virtual unsigned short cms::BytesMessage::readUnsignedShort () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]

Reads a 16 bit unsigned short from the Bytes message stream.

Returns:

unsigned short value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 243).

6.170.3.16 `virtual std::string cms::BytesMessage::readUTF () const throw (cms::MessageEOFException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads an UTF String from the `BytesMessage` (p. 1056) stream.

Returns:

String from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 243).

6.170.3.17 `virtual void cms::BytesMessage::reset () throw (cms::MessageFormatException, cms::CMSException) [pure virtual]`

Puts the message body in read-only mode and repositions the stream of bytes to the beginning.

Exceptions:

CMSException (p. 1160) - If the provider fails to perform the reset operation.

MessageFormatException (p. 2662) - If the `Message` (p. 2534) has an invalid format.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 243).

6.170.3.18 `virtual void cms::BytesMessage::setBodyBytes (const unsigned char * buffer, int numBytes) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

sets the bytes given to the message body.

Parameters:

buffer Byte Buffer to copy

numBytes Number of bytes in Buffer to copy

Exceptions:

CMSException (p. 1160) - If an internal error occurs.

MessageNotWriteableException (p. 2724) - if in Read Only Mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 244).

6.170.3.19 `virtual void cms::BytesMessage::writeBoolean (bool value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a boolean to the bytes message stream as a 1-byte value. The value true is written as the value (byte)1; the value false is written as the value (byte)0.

Parameters:

value boolean to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 244).

6.170.3.20 `virtual void cms::BytesMessage::writeByte (unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a byte to the bytes message stream as a 1-byte value.

Parameters:

value byte to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 244).

6.170.3.21 `virtual void cms::BytesMessage::writeBytes (const unsigned char * value, int offset, int length) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a portion of a byte array to the bytes message stream. size as the number of bytes to write.

Parameters:

value bytes to write to the stream

offset the initial offset within the byte array

length the number of bytes to use

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 245).

6.170.3.22 `virtual void cms::BytesMessage::writeBytes (const std::vector< unsigned char > & value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a byte array to the bytes message stream using the vector size as the number of bytes to write.

Parameters:

value bytes to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 245).

6.170.3.23 `virtual void cms::BytesMessage::writeChar (char value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a char to the bytes message stream as a 1-byte value.

Parameters:

value char to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 245).

6.170.3.24 `virtual void cms::BytesMessage::writeDouble (double value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a double to the bytes message stream as a 8 byte value.

Parameters:

value double to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 246).

6.170.3.25 `virtual void cms::BytesMessage::writeFloat (float value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a float to the bytes message stream as a 4 byte value.

Parameters:

value float to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 246).

6.170.3.26 `virtual void cms::BytesMessage::writeInt (int value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a signed int to the bytes message stream as a 4 byte value.

Parameters:

value signed int to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 246).

6.170.3.27 `virtual void cms::BytesMessage::writeLong (long long value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a long long to the bytes message stream as a 8 byte value.

Parameters:

value signed long long to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 247).

6.170.3.28 `virtual void cms::BytesMessage::writeShort (short value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a signed short to the bytes message stream as a 2 byte value.

Parameters:

value signed short to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 247).

6.170.3.29 `virtual void cms::BytesMessage::writeString (const std::string & value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes an ASCII String to the Bytes message stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 247).

6.170.3.30 `virtual void cms::BytesMessage::writeUnsignedShort (unsigned short value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a unsigned short to the bytes message stream as a 2 byte value.

Parameters:

value unsigned short to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 248).

6.170.3.31 `virtual void cms::BytesMessage::writeUTF (const std::string & value)
 throw (cms::MessageNotWriteableException, cms::CMSException)
 [pure virtual]`

Writes an UTF String to the **BytesMessage** (p. 1056) stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of bytes stream has been reached.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in **activemq::commands::ActiveMQBytesMessage** (p. 248).

The documentation for this class was generated from the following file:

- `src/main/cms/BytesMessage.h`

6.171 activemq::cmsutil::CachedConsumer Class Reference

A cached message consumer contained within a pooled session.

#include <src/main/activemq/cmsutil/CachedConsumer.h> Inheritance diagram for activemq::cmsutil::CachedConsumer:

Public Member Functions

- **CachedConsumer** (**cms::MessageConsumer** *consumer)
- virtual **~CachedConsumer** ()
- virtual void **close** () throw (cms::CMSEException)
Does nothing - the real producer resource will be closed by the lifecycle manager.
- virtual **cms::Message** * **receive** () throw (cms::CMSEException)
Synchronously Receive a Message.
- virtual **cms::Message** * **receive** (int millisecs) throw (cms::CMSEException)
Synchronously Receive a Message, time out after defined interval.
- virtual **cms::Message** * **receiveNoWait** () throw (cms::CMSEException)
Receive a Message, does not wait if there isn't a new message to read, returns NULL if nothing read.
- virtual void **setMessageListener** (**cms::MessageListener** *listener) throw (cms::CMSEException)
Sets the MessageListener that this class will send notifs on.
- virtual **cms::MessageListener** * **getMessageListener** () const throw (cms::CMSEException)
Gets the MessageListener that this class will send new Message notification events to.
- virtual std::string **getMessageSelector** () const throw (cms::CMSEException)
Gets this message consumer's message selector expression.

Protected Member Functions

- **CachedConsumer** (const **CachedConsumer** &)
- **CachedConsumer** & **operator=** (const **CachedConsumer** &)

6.171.1 Detailed Description

A cached message consumer contained within a pooled session.

6.171.2 Constructor & Destructor Documentation

- 6.171.2.1** `activemq::cmsutil::CachedConsumer::CachedConsumer (const CachedConsumer &) [inline, protected]`
- 6.171.2.2** `activemq::cmsutil::CachedConsumer::CachedConsumer (cms::MessageConsumer * consumer) [inline]`
- 6.171.2.3** `virtual activemq::cmsutil::CachedConsumer::~~CachedConsumer () [inline, virtual]`

6.171.3 Member Function Documentation

- 6.171.3.1** `virtual void activemq::cmsutil::CachedConsumer::close () throw (cms::CMSEException) [inline, virtual]`

Does nothing - the real producer resource will be closed by the lifecycle manager.

Implements **cms::Closeable** (p. 1148).

- 6.171.3.2** `virtual cms::MessageListener* activemq::cmsutil::CachedConsumer::getMessageListener () const throw (cms::CMSEException) [inline, virtual]`

Gets the MessageListener that this class will send new Message notification events to.

Returns:

The listener of messages received by this consumer

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::MessageConsumer** (p. 2590).

- 6.171.3.3** `virtual std::string activemq::cmsutil::CachedConsumer::getMessageSelector () const throw (cms::CMSEException) [inline, virtual]`

Gets this message consumer's message selector expression.

Returns:

This Consumer's selector expression or "".

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::MessageConsumer** (p. 2590).

6.171.3.4 `CachedConsumer& activemq::cmsutil::CachedConsumer::operator=`
`(const CachedConsumer &) [inline, protected]`

6.171.3.5 `virtual cms::Message* activemq::cmsutil::CachedConsumer::receive (int`
`milliseconds) throw (cms::CMSEException) [inline, virtual]`

Synchronously Receive a Message, time out after defined interval. Returns null if nothing read.

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException - If an internal error occurs.

Implements `cms::MessageConsumer` (p. 2590).

6.171.3.6 `virtual cms::Message* activemq::cmsutil::CachedConsumer::receive ()`
`throw (cms::CMSEException) [inline, virtual]`

Synchronously Receive a Message.

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException - If an internal error occurs.

Implements `cms::MessageConsumer` (p. 2591).

6.171.3.7 `virtual cms::Message* ac-`
`tivemq::cmsutil::CachedConsumer::receiveNoWait ()`
`throw (cms::CMSEException) [inline, virtual]`

Receive a Message, does not wait if there isn't a new message to read, returns NULL if nothing read.

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException - If an internal error occurs.

Implements `cms::MessageConsumer` (p. 2591).

6.171.3.8 `virtual void activemq::cmsutil::CachedConsumer::setMessageListener`
`(cms::MessageListener * listener) throw (cms::CMSEException)`
`[inline, virtual]`

Sets the MessageListener that this class will send notifis on.

Parameters:

listener The listener of messages received by this consumer.

Exceptions:

CMSException - If an internal error occurs.

Implements **cms::MessageConsumer** (p. 2591).

The documentation for this class was generated from the following file:

- src/main/activemq/cmsutil/**CachedConsumer.h**

6.172 activemq::cmsutil::CachedProducer Class Reference

A cached message producer contained within a pooled session.

#include <src/main/activemq/cmsutil/CachedProducer.h> Inheritance diagram for activemq::cmsutil::CachedProducer:

Public Member Functions

- **CachedProducer** (**cms::MessageProducer** *producer)
- virtual **~CachedProducer** ()
- virtual void **close** () throw (cms::CMSEException)
Does nothing - the real producer resource will be closed by the lifecycle manager.
- virtual void **send** (**cms::Message** *message) throw (cms::CMSEException)
Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (**cms::Message** *message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException)
Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (const **cms::Destination** *destination, **cms::Message** *message) throw (cms::CMSEException)
Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (const **cms::Destination** *destination, **cms::Message** *message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException)
Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **setDeliveryMode** (int mode) throw (cms::CMSEException)
Sets the delivery mode for this Producer.
- virtual int **getDeliveryMode** () const throw (cms::CMSEException)
Gets the delivery mode for this Producer.
- virtual void **setDisableMessageID** (bool value) throw (cms::CMSEException)
Sets if Message Ids are disabled for this Producer.
- virtual bool **getDisableMessageID** () const throw (cms::CMSEException)
Gets if Message Ids are disabled for this Producer.
- virtual void **setDisableMessageTimeStamp** (bool value) throw (cms::CMSEException)
Sets if Message Time Stamps are disabled for this Producer.
- virtual bool **getDisableMessageTimeStamp** () const throw (cms::CMSEException)

Gets if Message Time Stamps are disabled for this Producer.

- virtual void **setPriority** (int priority) throw (cms::CMSEException)
Sets the Priority that this Producers sends messages at.
- virtual int **getPriority** () const throw (cms::CMSEException)
Gets the Priority level that this producer sends messages at.
- virtual void **setTimeToLive** (long long time) throw (cms::CMSEException)
Sets the Time to Live that this Producers sends messages with.
- virtual long long **getTimeToLive** () const throw (cms::CMSEException)
Gets the Time to Live that this producer sends messages with.

Protected Member Functions

- **CachedProducer** (const **CachedProducer** &)
- **CachedProducer** & **operator=** (const **CachedProducer** &)

6.172.1 Detailed Description

A cached message producer contained within a pooled session.

6.172.2 Constructor & Destructor Documentation

- 6.172.2.1 **activemq::cmsutil::CachedProducer::CachedProducer** (const **CachedProducer** &) [inline, protected]
- 6.172.2.2 **activemq::cmsutil::CachedProducer::CachedProducer** (cms::MessageProducer * *producer*) [inline]
- 6.172.2.3 **virtual activemq::cmsutil::CachedProducer::~~CachedProducer** () [inline, virtual]

6.172.3 Member Function Documentation

- 6.172.3.1 **virtual void activemq::cmsutil::CachedProducer::close** () throw (cms::CMSEException) [inline, virtual]

Does nothing - the real producer resource will be closed by the lifecycle manager.

Implements **cms::Closeable** (p.1148).

- 6.172.3.2 **virtual int activemq::cmsutil::CachedProducer::getDeliveryMode** () const throw (cms::CMSEException) [inline, virtual]

Gets the delivery mode for this Producer.

Returns:

The DeliveryMode

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2726).

6.172.3.3 `virtual bool activemq::cmsutil::CachedProducer::getDisableMessageID () const throw (cms::CMSEException) [inline, virtual]`

Gets if Message Ids are disabled for this Producer.

Returns:

boolean indicating enable / disable (true / false)

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2727).

6.172.3.4 `virtual bool activemq::cmsutil::CachedProducer::getDisableMessageTimeStamp () const throw (cms::CMSEException) [inline, virtual]`

Gets if Message Time Stamps are disabled for this Producer.

Returns:

boolean indicating enable / disable (true / false)

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2727).

6.172.3.5 `virtual int activemq::cmsutil::CachedProducer::getPriority () const throw (cms::CMSEException) [inline, virtual]`

Gets the Priority level that this producer sends messages at.

Returns:

int based priority level

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2727).

6.172.3.6 `virtual long long activemq::cmsutil::CachedProducer::getTimeToLive ()
const throw (cms::CMSEException) [inline, virtual]`

Gets the Time to Live that this producer sends messages with.

Returns:

Time to live value in milliseconds

Exceptions:

CMSEException - if an internal error occurs.

Implements `cms::MessageProducer` (p. 2728).

6.172.3.7 `CachedProducer& activemq::cmsutil::CachedProducer::operator= (const
CachedProducer &) [inline, protected]`

6.172.3.8 `virtual void activemq::cmsutil::CachedProducer::send (const
cms::Destination * destination, cms::Message * message, int
deliveryMode, int priority, long long timeToLive) throw (
cms::CMSEException) [inline, virtual]`

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

destination The destination on which to send the message

message The message to be sent.

deliveryMode The delivery mode to be used.

priority The priority for this message.

timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSEException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements `cms::MessageProducer` (p. 2728).

6.172.3.9 `virtual void activemq::cmsutil::CachedProducer::send (const
cms::Destination * destination, cms::Message * message) throw (
cms::CMSEException) [inline, virtual]`

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

destination The destination on which to send the message

message the message to be sent.

Exceptions:

CMSEException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements **cms::MessageProducer** (p. 2728).

6.172.3.10 `virtual void activemq::cmsutil::CachedProducer::send (cms::Message * message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException)` [inline, virtual]

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

message The message to be sent.

deliveryMode The delivery mode to be used.

priority The priority for this message.

timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSEException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements **cms::MessageProducer** (p. 2729).

6.172.3.11 `virtual void activemq::cmsutil::CachedProducer::send (cms::Message * message) throw (cms::CMSEException)` [inline, virtual]

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

message The message to be sent.

Exceptions:

CMSEException - if an internal error occurs while sending the message.

MessageFormatException - if an Invalid Message is given.

InvalidDestinationException - if a client uses this method with a MessageProducer with an invalid destination.

UnsupportedOperationException - if a client uses this method with a MessageProducer that did not specify a destination at creation time.

Implements **cms::MessageProducer** (p. 2729).

6.172.3.12 `virtual void activemq::cmsutil::CachedProducer::setDeliveryMode (int mode) throw (cms::CMSEException) [inline, virtual]`

Sets the delivery mode for this Producer.

Parameters:

mode The DeliveryMode

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2730).

6.172.3.13 `virtual void activemq::cmsutil::CachedProducer::setDisableMessageID (bool value) throw (cms::CMSEException) [inline, virtual]`

Sets if Message Ids are disabled for this Producer.

Parameters:

value boolean indicating enable / disable (true / false)

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2730).

6.172.3.14 `virtual void activemq::cmsutil::CachedProducer::setDisableMessageTimeStamp (bool value) throw (cms::CMSEException) [inline, virtual]`

Sets if Message Time Stamps are disabled for this Producer.

Parameters:

value - boolean indicating enable / disable (true / false)

Exceptions:

CMSEException - if an internal error occurs.

Implements **cms::MessageProducer** (p. 2730).

6.172.3.15 `virtual void activemq::cmsutil::CachedProducer::setPriority (int priority) throw (cms::CMSEException)` [inline, virtual]

Sets the Priority that this Producers sends messages at.

Parameters:

priority int value for Priority level

Exceptions:

CMSEException - if an internal error occurs.

Implements `cms::MessageProducer` (p. 2731).

6.172.3.16 `virtual void activemq::cmsutil::CachedProducer::setTimeToLive (long long time) throw (cms::CMSEException)` [inline, virtual]

Sets the Time to Live that this Producers sends messages with. This value will be used if the time to live is not specified via the send method.

Parameters:

time default time to live value in milliseconds

Exceptions:

CMSEException - if an internal error occurs.

Implements `cms::MessageProducer` (p. 2731).

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CachedProducer.h`

6.173 decaf::util::concurrent::Callable< V > Class Template Reference

A task that returns a result and may throw an exception.

```
#include <src/main/decaf/util/concurrent/Callable.h>
```

Public Member Functions

- virtual `~Callable ()`
- virtual `V call ()=0 throw (decaf::lang::Exception)`
Computes a result, or throws an exception if unable to do so.

6.173.1 Detailed Description

```
template<typename V> class decaf::util::concurrent::Callable< V >
```

A task that returns a result and may throw an exception. Implementors define a single method with no arguments called `call`. This interface differs from the `Runnable` interface in that a **Callable** (p.1082) object can return a result and is allowed to throw an exceptions from its `call` method.

The `Executors` class contains utility methods to convert from other common forms to **Callable** (p.1082) classes.

Since:

1.0

6.173.2 Constructor & Destructor Documentation

6.173.2.1 `template<typename V > virtual decaf::util::concurrent::Callable< V >::~~Callable () [inline, virtual]`

6.173.3 Member Function Documentation

6.173.3.1 `template<typename V > virtual V decaf::util::concurrent::Callable< V >::call () throw (decaf::lang::Exception) [pure virtual]`

Computes a result, or throws an exception if unable to do so.

Returns:

Computed Result.

Exceptions:

Exception If unable to compute a result.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Callable.h`

6.174 decaf::util::concurrent::CancellationException Class Reference

#include <src/main/decaf/util/concurrent/CancellationException.h> Inheritance diagram for decaf::util::concurrent::CancellationException:

Public Member Functions

- **CancellationException** () throw ()
Default Constructor.
- **CancellationException** (const **decaf::lang::Exception** &ex) throw ()
Conversion Constructor from some other Exception.
- **CancellationException** (const **CancellationException** &ex) throw ()
Copy Constructor.
- **CancellationException** (const std::exception *cause) throw ()
Constructor.
- **CancellationException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **CancellationException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CancellationException** * clone () const
Clones this exception.
- virtual ~**CancellationException** () throw ()

6.174.1 Constructor & Destructor Documentation

6.174.1.1 decaf::util::concurrent::CancellationException::CancellationException () throw () [inline]

Default Constructor.

6.174.1.2 decaf::util::concurrent::CancellationException::CancellationException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.174.1.3 decaf::util::concurrent::CancellationException::CancellationException (const CancellationException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex - The Exception to copy in this new instance.

References decaf::lang::Exception::Exception().

6.174.1.4 decaf::util::concurrent::CancellationException::CancellationException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.174.1.5 decaf::util::concurrent::CancellationException::CancellationException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

msg - The message to report

... - list of primitives that are formatted into the message

6.174.1.6 decaf::util::concurrent::CancellationException::CancellationException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

cause - The exception that was the cause for this one to be thrown.

msg - The message to report

... - list of primitives that are formatted into the message

6.174.1.7 **virtual**
 decaf::util::concurrent::CancellationException::~~CancellationException ()
 throw () [inline, virtual]

6.174.2 Member Function Documentation

6.174.2.1 **virtual CancellationException* de-**
 caf::util::concurrent::CancellationException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

 a new instance of an exception that is a clone of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/CancellationException.h`

6.175 decaf::security::cert::Certificate Class Reference

Base interface for all identity certificates.

#include <src/main/decaf/security/cert/Certificate.h> Inheritance diagram for decaf::security::cert::Certificate:

Public Member Functions

- virtual **~Certificate** ()
- virtual bool **equals** (const **Certificate** &cert) const =0
Compares the encoded form of the two certificates.
- virtual void **getEncoded** (std::vector< unsigned char > &output) const =0 throw (CertificateEncodingException)
Provides the encoded form of this certificate.
- virtual std::string **getType** () const =0
Returns the type of this certificate.
- virtual **PublicKey** * **getPublicKey** ()=0
Gets the public key of this certificate.
- virtual const **PublicKey** * **getPublicKey** () const =0
Gets the public key of this certificate.
- virtual void **verify** (const **PublicKey** &publicKey) const =0 throw (NoSuchAlgorithmException, InvalidKeyException, NoSuchProviderException, SignatureException, CertificateException)
Verifies that this certificate was signed with the private key that corresponds to the specified public key.
- virtual void **verify** (const **PublicKey** &publicKey, const std::string &sigProvider) const =0 throw (NoSuchAlgorithmException, InvalidKeyException, NoSuchProviderException, SignatureException, CertificateException)
Verifies that this certificate was signed with the private key that corresponds to the specified public key.
- virtual std::string **toString** () const =0
Returns a string representation of this certificate.

6.175.1 Detailed Description

Base interface for all identity certificates.

6.175.2 Constructor & Destructor Documentation

6.175.2.1 `virtual decaf::security::cert::Certificate::~~Certificate () [inline, virtual]`

6.175.3 Member Function Documentation

6.175.3.1 `virtual bool decaf::security::cert::Certificate::equals (const Certificate & cert) const [pure virtual]`

Compares the encoded form of the two certificates.

Parameters:

cert (p. 167) The certificate to be tested for equality with this certificate.

Returns:

true if the given certificate is equal to this certificate.

6.175.3.2 `virtual void decaf::security::cert::Certificate::getEncoded (std::vector< unsigned char > & output) const throw (CertificateEncodingException) [pure virtual]`

Provides the encoded form of this certificate.

Parameters:

output Receives the encoded form of this certificate.

Exceptions:

CertificateEncodingException (p. 1090) if an encoding error occurs

6.175.3.3 `virtual const PublicKey* decaf::security::cert::Certificate::getPublicKey () const [pure virtual]`

Gets the public key of this certificate.

Returns:

the public key

6.175.3.4 `virtual PublicKey* decaf::security::cert::Certificate::getPublicKey () [pure virtual]`

Gets the public key of this certificate.

Returns:

the public key

6.175.3.5 `virtual std::string decaf::security::cert::Certificate::getType () const`
[pure virtual]

Returns the type of this certificate.

Returns:

the type of this certificate

6.175.3.6 `virtual std::string decaf::security::cert::Certificate::toString () const`
[pure virtual]

Returns a string representation of this certificate.

Returns:

a string representation of this certificate

6.175.3.7 `virtual void decaf::security::cert::Certificate::verify (const`
`PublicKey & publicKey, const std::string & sigProvider) const`
`throw (NoSuchAlgorithmException, InvalidKeyException,`
`NoSuchProviderException, SignatureException, CertificateException)`
[pure virtual]

Verifies that this certificate was signed with the private key that corresponds to the specified public key. Uses the verification engine of the specified provider.

Parameters:

publicKey The public key used to carry out the validation.

sigProvider The name of the signature provider

Exceptions:

NoSuchAlgorithmException (p. 2823) - on unsupported signature algorithms.

InvalidKeyException (p. 2132) - on incorrect key.

NoSuchProviderException (p. 2829) - if there's no default provider.

SignatureException (p. 3497) - on signature errors.

CertificateException (p. 1092) - on encoding errors.

6.175.3.8 `virtual void decaf::security::cert::Certificate::verify (const`
`PublicKey & publicKey) const throw (NoSuchAlgorithmException,`
`InvalidKeyException, NoSuchProviderException, SignatureException,`
`CertificateException)` [pure virtual]

Verifies that this certificate was signed with the private key that corresponds to the specified public key.

Parameters:

publicKey The public key used to carry out the validation.

Exceptions:

NoSuchAlgorithmException (p. 2823) - on unsupported signature algorithms.

InvalidKeyException (p. 2132) - on incorrect key.

NoSuchProviderException (p. 2829) - if there's no default provider.

SignatureException (p. 3497) - on signature errors.

CertificateException (p. 1092) - on encoding errors.

The documentation for this class was generated from the following file:

- src/main/decaf/security/cert/**Certificate.h**

6.176 decaf::security::cert::CertificateEncodingException Class Reference

#include <src/main/decaf/security/cert/CertificateEncodingException.h> Inheritance diagram for decaf::security::cert::CertificateEncodingException:

Public Member Functions

- **CertificateEncodingException** () throw ()
Default Constructor.
- **CertificateEncodingException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **CertificateEncodingException** (const **CertificateEncodingException** &ex) throw ()
Copy Constructor.
- **CertificateEncodingException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CertificateEncodingException** * clone () const
Clones this exception.
- virtual ~**CertificateEncodingException** () throw ()

6.176.1 Constructor & Destructor Documentation

6.176.1.1 decaf::security::cert::CertificateEncodingException::CertificateEncodingException () throw () [inline]

Default Constructor.

6.176.1.2 decaf::security::cert::CertificateEncodingException::CertificateEncodingException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.176.1.3 decaf::security::cert::CertificateEncodingException::CertificateEncodingException (const CertificateEncodingException & ex) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.176.1.4 `decaf::security::cert::CertificateEncodingException::CertificateEncodingException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.176.1.5 `virtual decaf::security::cert::CertificateEncodingException::~CertificateEncodingException () throw () [inline, virtual]`

6.176.2 Member Function Documentation

6.176.2.1 `virtual CertificateEncodingException* decaf::security::cert::CertificateEncodingException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::cert::CertificateException` (p.1093).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/cert/CertificateEncodingException.h`

6.177 decaf::security::cert::CertificateException Class Reference

#include <src/main/decaf/security/cert/CertificateException.h> Inheritance diagram for decaf::security::cert::CertificateException:

Public Member Functions

- **CertificateException** () throw ()
Default Constructor.
- **CertificateException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **CertificateException** (const **CertificateException** &ex) throw ()
Copy Constructor.
- **CertificateException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CertificateException** * **clone** () const
Clones this exception.
- virtual ~**CertificateException** () throw ()

6.177.1 Constructor & Destructor Documentation

6.177.1.1 decaf::security::cert::CertificateException::CertificateException () throw () [inline]

Default Constructor.

6.177.1.2 decaf::security::cert::CertificateException::CertificateException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.177.1.3 decaf::security::cert::CertificateException::CertificateException (const CertificateException & ex) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.177.1.4 `decaf::security::cert::CertificateException::CertificateException (const char * file, const int lineNumber, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.177.1.5 `virtual decaf::security::cert::CertificateException::~~CertificateException () throw ()` [inline, virtual]

6.177.2 Member Function Documentation

6.177.2.1 `virtual CertificateException* decaf::security::cert::CertificateException::clone () const` [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::GeneralSecurityException` (p. 1973).

Reimplemented in `decaf::security::cert::CertificateEncodingException` (p. 1091), `decaf::security::cert::CertificateExpiredException` (p. 1095), `decaf::security::cert::CertificateNotYetValidException` (p. 1097), and `decaf::security::cert::CertificateParsingException` (p. 1099).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/cert/CertificateException.h`

6.178 decaf::security::cert::CertificateExpiredException Class Reference

#include <src/main/decaf/security/cert/CertificateExpiredException.h> Inheritance diagram for decaf::security::cert::CertificateExpiredException:

Public Member Functions

- **CertificateExpiredException** () throw ()
Default Constructor.
- **CertificateExpiredException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **CertificateExpiredException** (const **CertificateExpiredException** &ex) throw ()
Copy Constructor.
- **CertificateExpiredException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CertificateExpiredException** * clone () const
Clones this exception.
- virtual ~**CertificateExpiredException** () throw ()

6.178.1 Constructor & Destructor Documentation

6.178.1.1 decaf::security::cert::CertificateExpiredException::CertificateExpiredException () throw () [inline]

Default Constructor.

6.178.1.2 decaf::security::cert::CertificateExpiredException::CertificateExpiredException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.178.1.3 decaf::security::cert::CertificateExpiredException::CertificateExpiredException (const CertificateExpiredException & ex) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.178.1.4 `decaf::security::cert::CertificateExpiredException::CertificateExpiredException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.178.1.5 `virtual decaf::security::cert::CertificateExpiredException::~~CertificateExpiredException () throw () [inline, virtual]`

6.178.2 Member Function Documentation

6.178.2.1 `virtual CertificateExpiredException* decaf::security::cert::CertificateExpiredException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::cert::CertificateException` (p.1093).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/cert/CertificateExpiredException.h`

6.179 decaf::security::cert::CertificateNotYetValidException Class Reference

#include <src/main/decaf/security/cert/CertificateNotYetValidException.h> Inheritance diagram for decaf::security::cert::CertificateNotYetValidException:

Public Member Functions

- **CertificateNotYetValidException** () throw ()
Default Constructor.
- **CertificateNotYetValidException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **CertificateNotYetValidException** (const **CertificateNotYetValidException** &ex) throw ()
Copy Constructor.
- **CertificateNotYetValidException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CertificateNotYetValidException** * clone () const
Clones this exception.
- virtual ~**CertificateNotYetValidException** () throw ()

6.179.1 Constructor & Destructor Documentation

6.179.1.1 decaf::security::cert::CertificateNotYetValidException::CertificateNotYetValidException () throw () [inline]

Default Constructor.

6.179.1.2 decaf::security::cert::CertificateNotYetValidException::CertificateNotYetValidException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.179.1.3 decaf::security::cert::CertificateNotYetValidException::CertificateNotYetValidException (const CertificateNotYetValidException & ex) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.179.1.4 `decaf::security::cert::CertificateNotYetValidException::CertificateNotYetValidException (const char * file, const int lineNumber, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.179.1.5 `virtual decaf::security::cert::CertificateNotYetValidException::~~CertificateNotYetValidException () throw ()` [inline, virtual]

6.179.2 Member Function Documentation

6.179.2.1 `virtual CertificateNotYetValidException* decaf::security::cert::CertificateNotYetValidException::clone () const` [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::cert::CertificateException` (p.1093).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/cert/CertificateNotYetValidException.h`

6.180 decaf::security::cert::CertificateParsingException Class Reference

#include <src/main/decaf/security/cert/CertificateParsingException.h>Inheritance diagram for decaf::security::cert::CertificateParsingException:

Public Member Functions

- **CertificateParsingException** () throw ()
Default Constructor.
- **CertificateParsingException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **CertificateParsingException** (const **CertificateParsingException** &ex) throw ()
Copy Constructor.
- **CertificateParsingException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **CertificateParsingException** * clone () const
Clones this exception.
- virtual ~**CertificateParsingException** () throw ()

6.180.1 Constructor & Destructor Documentation

6.180.1.1 decaf::security::cert::CertificateParsingException::CertificateParsingException () throw () [inline]

Default Constructor.

6.180.1.2 decaf::security::cert::CertificateParsingException::CertificateParsingException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.180.1.3 decaf::security::cert::CertificateParsingException::CertificateParsingException (const CertificateParsingException & ex) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.180.1.4 `decaf::security::cert::CertificateParsingException::CertificateParsingException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.180.1.5 `virtual decaf::security::cert::CertificateParsingException::~~CertificateParsingException () throw () [inline, virtual]`

6.180.2 Member Function Documentation

6.180.2.1 `virtual CertificateParsingException* decaf::security::cert::CertificateParsingException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::cert::CertificateException` (p.1093).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/cert/CertificateParsingException.h`

6.181 decaf::lang::Character Class Reference

#include <src/main/decaf/lang/Character.h> Inheritance diagram for decaf::lang::Character:

Public Member Functions

- **Character** (char value)
- virtual int **compareTo** (const **Character** &c) const
*Compares this **Character** (p. 1100) instance with another.*
- virtual bool **operator==** (const **Character** &c) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Character** &c) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const char &c) const
*Compares this **Character** (p. 1100) instance with a char type.*
- virtual bool **operator==** (const char &c) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const char &c) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- bool **equals** (const **Character** &c) const
- bool **equals** (const char &c) const
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const
Answers the long value which the receiver represents.

Static Public Member Functions

- static **Character valueOf** (char value)
*Returns a **Character** (p. 1100) instance representing the specified char value.*
- static bool **isWhitespace** (char c)
Indicates whether or not the given character is considered whitespace.
- static bool **isDigit** (char c)
Indicates whether or not the given character is a digit.
- static bool **isLowerCase** (char c)
Indicates whether or not the given character is a lower case character.
- static bool **isUpperCase** (char c)
Indicates whether or not the given character is a upper case character.
- static bool **isLetter** (char c)
Indicates whether or not the given character is a letter.
- static bool **isLetterOrDigit** (char c)
Indicates whether or not the given character is either a letter or a digit.
- static bool **isISOControl** (char c)
Answers whether the character is an ISO control character, which is a char that lays in the range of 0 to 1f and 7f to 9f.
- static int **digit** (char c, int radix)
Returns the numeric value of the character ch in the specified radix.

Static Public Attributes

- static const int **MIN_RADIX** = 2
The minimum radix available for conversion to and from strings.
- static const int **MAX_RADIX** = 36
The maximum radix available for conversion to and from strings.
- static const char **MIN_VALUE** = (char)0x7F
The minimum value that a signed char can take on.
- static const char **MAX_VALUE** = (char)0x80
The maximum value that a signed char can take on.
- static const int **SIZE** = 8
The size of the primitive charactor in bits.

6.181.1 Constructor & Destructor Documentation

6.181.1.1 decaf::lang::Character::Character (char *value*)

Parameters:

value - char to wrap.

6.181.2 Member Function Documentation

6.181.2.1 virtual unsigned char decaf::lang::Character::byteValue () const [inline, virtual]

Answers the byte value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2835).

6.181.2.2 virtual int decaf::lang::Character::compareTo (const char & *c*) const [inline, virtual]

Compares this **Character** (p. 1100) instance with a char type.

Parameters:

c - the char instance to be compared

Returns:

zero if this object represents the same char value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements **decaf::lang::Comparable< char >** (p. 1214).

6.181.2.3 virtual int decaf::lang::Character::compareTo (const Character & *c*) const [inline, virtual]

Compares this **Character** (p. 1100) instance with another.

Parameters:

c - the **Character** (p. 1100) instance to be compared

Returns:

zero if this object represents the same char value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.181.2.4 static int decaf::lang::Character::digit (char *c*, int *radix*) [static]

Returns the numeric value of the character *ch* in the specified radix. If the radix is not in the range `MIN_RADIX <= radix <= MAX_RADIX` or if the value of *ch* is not a valid digit in the specified radix, -1 is returned. A character is a valid digit if at least one of the following is true:

* The method `isDigit` is true of the character and the single-character decomposition is less than the specified radix. In this case the decimal digit value is returned. * The character is one of the uppercase Latin letters 'A' through 'Z' and its **code** (p. 1183) is less than `radix + 'A' - 10`. In this case, `ch - 'A' + 10` is returned. * The character is one of the lowercase Latin letters 'a' through 'z' and its **code** (p. 1183) is less than `radix + 'a' - 10`. In this case, `ch - 'a' + 10` is returned.

Parameters:

c - the char to be converted
radix - the radix of the number

Returns:

the numeric value of the number represented in the given radix

6.181.2.5 virtual double decaf::lang::Character::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.181.2.6 bool decaf::lang::Character::equals (const char & *c*) const [inline, virtual]**Returns:**

true if the two Characters have the same value.

Implements **decaf::lang::Comparable< char >** (p. 1215).

6.181.2.7 bool decaf::lang::Character::equals (const Character & *c*) const [inline]**Returns:**

true if the two **Character** (p. 1100) Objects have the same value.

6.181.2.8 virtual float decaf::lang::Character::floatValue () const [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.181.2.9 `virtual int decaf::lang::Character::intValue () const [inline, virtual]`

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.181.2.10 `static bool decaf::lang::Character::isDigit (char c) [inline, static]`

Indicates whether or not the given character is a digit.

6.181.2.11 `static bool decaf::lang::Character::isISOControl (char c) [inline, static]`

Answers whether the character is an ISO control character, which is a char that lays in the range of 0 to 1f and 7f to 9f.

Parameters:

c - the character, including supplementary characters

Returns:

true if the char is an ISO control character

6.181.2.12 `static bool decaf::lang::Character::isLetter (char c) [inline, static]`

Indicates whether or not the given character is a letter.

6.181.2.13 `static bool decaf::lang::Character::isLetterOrDigit (char c) [inline, static]`

Indicates whether or not the given character is either a letter or a digit.

6.181.2.14 `static bool decaf::lang::Character::isLowerCase (char c) [inline, static]`

Indicates whether or not the given character is a lower case character.

6.181.2.15 `static bool decaf::lang::Character::isUpperCase (char c) [inline, static]`

Indicates whether or not the given character is a upper case character.

6.181.2.16 `static bool decaf::lang::Character::isWhitespace (char c) [inline, static]`

Indicates whether or not the given character is considered whitespace.

6.181.2.17 `virtual long long decaf::lang::Character::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.181.2.18 `virtual bool decaf::lang::Character::operator< (const char & c) const [inline, virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable< char >** (p. 1215).

6.181.2.19 `virtual bool decaf::lang::Character::operator< (const Character & c) const [inline, virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.181.2.20 `virtual bool decaf::lang::Character::operator== (const char & c) const [inline, virtual]`

Compares equality between this object and the one passed.

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable< char >** (p. 1215).

6.181.2.21 `virtual bool decaf::lang::Character::operator==(const Character & c)
const [inline, virtual]`

Compares equality between this object and the one passed.

Parameters:

c - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.181.2.22 `virtual short decaf::lang::Character::shortValue () const [inline,
virtual]`

Answers the short value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2837).

6.181.2.23 `std::string decaf::lang::Character::toString () const`

Returns:

this **Character** (p. 1100) Object as a **String** (p. 3665) Representation

6.181.2.24 `static Character decaf::lang::Character::valueOf (char value) [inline,
static]`

Returns a **Character** (p. 1100) instance representing the specified char value.

Parameters:

value - the primitive char to wrap.

Returns:

a new Character instance that wraps this value.

6.181.3 Field Documentation

6.181.3.1 `const int decaf::lang::Character::MAX_RADIX = 36 [static]`

The maximum radix available for conversion to and from strings.

6.181.3.2 `const char decaf::lang::Character::MAX_VALUE = (char)0x80 [static]`

The maximum value that a signed char can take on.

6.181.3.3 `const int decaf::lang::Character::MIN_RADIX = 2` [static]

The minimum radix available for conversion to and from strings.

6.181.3.4 `const char decaf::lang::Character::MIN_VALUE = (char)0x7F` [static]

The minimum value that a signed char can take on.

6.181.3.5 `const int decaf::lang::Character::SIZE = 8` [static]

The size of the primitive character in bits.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Character.h`

6.182 decaf::internal::nio::CharArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/CharArrayBuffer.h> Inheritance diagram for decaf::internal::nio::CharArrayBuffer:

Public Member Functions

- **CharArrayBuffer** (int size, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **CharArrayBuffer** (p. 1108) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **CharArrayBuffer** (char *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **CharArrayBuffer** (p. 1108) object that wraps the given array.*

- **CharArrayBuffer** (const decaf::lang::Pointer< ByteArrayAdapter > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset.

- **CharArrayBuffer** (const CharArrayBuffer &other)

*Create a **CharArrayBuffer** (p. 1108) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.*

- virtual ~**CharArrayBuffer** ()
- virtual char * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the character array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

*the array that backs this **Buffer** (p. 928).*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual CharBuffer * **asReadOnlyBuffer** () const

Creates a new, read-only char buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only char buffer which the caller then owns.

- virtual CharBuffer & **compact** () throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

*a reference to this **CharBuffer** (p. 1119).*

Exceptions:

ReadOnlyBufferException (p. 3169) - If this buffer is read-only

- virtual CharBuffer * **duplicate** ()

Creates a new char buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*a new char **Buffer** (p. 928) which the caller owns.*

- virtual char **get** () throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the character at this buffer's current position, and then increments the position.

Returns:

the char at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return

- virtual char **get** (int index) const throw (lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the char at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the char is to be read.

Returns:

the char that is located at the given index.

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit or is negative.

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible char array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual CharBuffer & **put** (char value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given char into this buffer at the current position, and then increments the position.

Parameters:

value The char value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual CharBuffer & **put** (int index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given char into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The char to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if *index* greater than the buffer's limit minus the size of the type being written, or *index* is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual CharBuffer * **slice** () const

Creates a new **CharBuffer** (p. 1119) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **CharBuffer** (p. 1119) which the caller owns.

- virtual **lang::CharSequence * subSequence** (int start, int end) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a new character buffer that represents the specified subsequence of this buffer, relative to the current position.

The new buffer will share this buffer's content; that is, if the content of this buffer is mutable then modifications to one buffer will cause the other to be modified. The new buffer's capacity will be that of this buffer, its position will be **position()** (p. 932) + start, and its limit will be **position()** (p. 932) + end. The new **Buffer** (p. 928) will be read-only if, and only if, this buffer is read-only.

Parameters:

start The index, relative to the current position, of the first character in the subsequence; must be non-negative and no larger than **remaining()** (p. 933).

end The index, relative to the current position, of the character following the last character in the subsequence; must be no smaller than start and no larger than **remaining()** (p. 933).

Returns:

The new character buffer, caller owns.

Exceptions:

IndexOutOfBoundsException if the preconditions on start and end fail.

Protected Member Functions

- virtual void **setReadOnly** (bool value)

Sets this **CharArrayBuffer** (p. 1108) as Read-Only.

Protected Attributes

- bool **readOnly**
- decaf::lang::Pointer< ByteArrayAdapter > **_array**
- int **offset**
- int **length**

6.182.1 Constructor & Destructor Documentation

6.182.1.1 decaf::internal::nio::CharArrayBuffer::CharArrayBuffer (int *size*, bool *readOnly* = false) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a **CharArrayBuffer** (p.1108) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.182.1.2 decaf::internal::nio::CharArrayBuffer::CharArrayBuffer (char * *array*, int *size*, int *offset*, int *length*, bool *readOnly* = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a **CharArrayBuffer** (p.1108) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.182.1.3 decaf::internal::nio::CharArrayBuffer::CharArrayBuffer (const decaf::lang::Pointer< ByteArrayAdapter > & *array*, int *offset*, int *length*, bool *readOnly* = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset. The capacity and limit of the new **CharArrayBuffer** (p.1108) will be that of the remaining capacity of the passed buffer.

Parameters:

- array* The ByteBufferAdapter to wrap.
- offset* The position that is this buffers start position.
- length* The limit of how many bytes into the array this Buffer can write.
- readOnly* Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

- NullPointerException* if array is NULL
- IndexOutOfBoundsException* if offset + length is greater than array size.

6.182.1.4 decaf::internal::nio::CharArrayBuffer::CharArrayBuffer (const CharArrayBuffer & *other*)

Create a **CharArrayBuffer** (p. 1108) that mirrors this one, meaning it shares a reference to this buffers ByteBufferAdapter and when changes are made to that data it is reflected in both.

Parameters:

- other* The **CharArrayBuffer** (p. 1108) this one is to mirror.

6.182.1.5 virtual decaf::internal::nio::CharArrayBuffer::~~CharArrayBuffer () [virtual]

6.182.2 Member Function Documentation

6.182.2.1 virtual char* decaf::internal::nio::CharArrayBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException) [virtual]

Returns the character array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

- the array that backs this **Buffer** (p. 928).

Exceptions:

- ReadOnlyBufferException* (p. 3169) if this **Buffer** (p. 928) is read only.
- UnsupportedOperationException* if the underlying store has no array.

Implements **decaf::nio::CharBuffer** (p. 1124).

6.182.2.2 `virtual int decaf::internal::nio::CharArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::CharBuffer** (p. 1124).

6.182.2.3 `virtual CharBuffer* de-
caf::internal::nio::CharArrayBuffer::asReadOnlyBuffer ()
const [virtual]`

Creates a new, read-only char buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only char buffer which the caller then owns.

Implements **decaf::nio::CharBuffer** (p. 1125).

6.182.2.4 `virtual CharBuffer& decaf::internal::nio::CharArrayBuffer::compact ()
throw (decaf::nio::ReadOnlyBufferException) [virtual]`

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index `p = position()` (p. 932) is copied to index zero, the byte at index `p + 1` is copied to index one, and so forth until the byte at index `limit()` (p. 932) - 1 is copied to index `n = limit()` (p. 932) - 1 - `p`. The buffer's position is then set to `n+1` and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **CharBuffer** (p. 1119).

Exceptions:

ReadOnlyBufferException (p. 3169) - If this buffer is read-only

Implements **decaf::nio::CharBuffer** (p. 1125).

6.182.2.5 **virtual CharBuffer* decaf::internal::nio::CharArrayBuffer::duplicate ()** [virtual]

Creates a new char buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new char **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::CharBuffer** (p. 1126).

6.182.2.6 **virtual char decaf::internal::nio::CharArrayBuffer::get (int *index*) const** **throw (lang::exceptions::IndexOutOfBoundsException)** [virtual]

Absolute get method.

Reads the char at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the char is to be read.

Returns:

the char that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit or is negative.

Implements **decaf::nio::CharBuffer** (p. 1127).

6.182.2.7 **virtual char decaf::internal::nio::CharArrayBuffer::get () throw (** **decaf::nio::BufferUnderflowException)** [virtual]

Relative get method.

Reads the character at this buffer's current position, and then increments the position.

Returns:

the char at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return

Implements **decaf::nio::CharBuffer** (p. 1127).

6.182.2.8 virtual bool decaf::internal::nio::CharArrayBuffer::hasArray () const
[inline, virtual]

Tells whether or not this buffer is backed by an accessible char array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implements **decaf::nio::CharBuffer** (p. 1128).

6.182.2.9 virtual bool decaf::internal::nio::CharArrayBuffer::isReadOnly () const
[inline, virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.182.2.10 virtual CharBuffer& decaf::internal::nio::CharArrayBuffer::put
(int *index*, char *value*) throw (de-
caf::lang::exceptions::IndexOutOfBoundsException,
decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given char into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The char to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::CharBuffer** (p. 1129).

6.182.2.11 **virtual CharBuffer& decaf::internal::nio::CharArrayBuffer::put**
(char *value*) throw (decaf::nio::BufferOverflowException,
decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given char into this buffer at the current position, and then increments the position.

Parameters:

value The char value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its
limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::CharBuffer** (p. 1130).

6.182.2.12 **virtual void decaf::internal::nio::CharArrayBuffer::setReadOnly** (bool
value) [inline, protected, virtual]

Sets this **CharArrayBuffer** (p. 1108) as Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.182.2.13 **virtual CharBuffer* decaf::internal::nio::CharArrayBuffer::slice** () const
[virtual]

Creates a new **CharBuffer** (p. 1119) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **CharBuffer** (p. 1119) which the caller owns.

Implements **decaf::nio::CharBuffer** (p. 1132).

```

6.182.2.14  virtual lang::CharSequence* de-
             caf::internal::nio::CharArrayBuffer::subSequence (int start, int end)
             const throw ( decaf::lang::exceptions::IndexOutOfBoundsException )
             [virtual]

```

Creates a new character buffer that represents the specified subsequence of this buffer, relative to the current position.

The new buffer will share this buffer's content; that is, if the content of this buffer is mutable then modifications to one buffer will cause the other to be modified. The new buffer's capacity will be that of this buffer, its position will be **position()** (p. 932) + *start*, and its limit will be **position()** (p. 932) + *end*. The new **Buffer** (p. 928) will be read-only if, and only if, this buffer is read-only.

Parameters:

start The index, relative to the current position, of the first character in the subsequence; must be non-negative and no larger than **remaining()** (p. 933).

end The index, relative to the current position, of the character following the last character in the subsequence; must be no smaller than *start* and no larger than **remaining()** (p. 933).

Returns:

The new character buffer, caller owns.

Exceptions:

IndexOutOfBoundsException if the preconditions on *start* and *end* fail.

Implements **decaf::nio::CharBuffer** (p. 1132).

6.182.3 Field Documentation

```

6.182.3.1  decaf::lang::Pointer<ByteArrayAdapter>
             decaf::internal::nio::CharArrayBuffer::_array  [protected]

```

```

6.182.3.2  int decaf::internal::nio::CharArrayBuffer::length  [protected]

```

```

6.182.3.3  int decaf::internal::nio::CharArrayBuffer::offset  [protected]

```

```

6.182.3.4  bool decaf::internal::nio::CharArrayBuffer::readOnly  [protected]

```

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/CharArrayBuffer.h`

6.183 decaf::nio::CharBuffer Class Reference

This class defines four categories of operations upon character buffers:.

```
#include <src/main/decaf/nio/CharBuffer.h>
Inheritance diagram for decaf::nio::CharBuffer:
```

Public Member Functions

- virtual **~CharBuffer** ()
- virtual std::string **toString** () const
- **CharBuffer & append** (char value) throw (BufferOverflowException, ReadOnlyBufferException)
Appends the specified character to this buffer.
- **CharBuffer & append** (const lang::CharSequence *value) throw (BufferOverflowException, ReadOnlyBufferException)
Appends the specified character sequence to this buffer.
- **CharBuffer & append** (const lang::CharSequence *value, int start, int end) throw (decaf::lang::exceptions::IndexOutOfBoundsException, BufferOverflowException, ReadOnlyBufferException)
Appends a subsequence of the specified character sequence to this buffer If value is Null the the string "null" is appended to the buffer.
- virtual char * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the character array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **CharBuffer * asReadOnlyBuffer** () const =0
Creates a new, read-only char buffer that shares this buffer's content.
- char **charAt** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Reads the character at the given index relative to the current position.
- virtual **CharBuffer & compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **CharBuffer * duplicate** ()=0
Creates a new char buffer that shares this buffer's content.
- virtual char **get** ()=0 throw (BufferUnderflowException)
Relative get method.

- virtual char **get** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **CharBuffer** & **get** (std::vector< char > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **CharBuffer** & **get** (char *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible char array.
- int **length** () const
Returns the length of this character buffer.
- **CharBuffer** & **put** (**CharBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)
This method transfers the chars remaining in the given source buffer into this buffer.
- **CharBuffer** & **put** (const char *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
This method transfers chars into this buffer from the given source array.
- **CharBuffer** & **put** (std::vector< char > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)
This method transfers the entire content of the given source char array into this buffer.
- virtual **CharBuffer** & **put** (char value)=0 throw (BufferOverflowException, ReadOnlyBufferException)
Writes the given char into this buffer at the current position, and then increments the position.
- virtual **CharBuffer** & **put** (int index, char value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)
Writes the given char into this buffer at the given index.
- **CharBuffer** & **put** (std::string &src, int start, int end) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException)
Relative bulk put method (optional operation).
- **CharBuffer** & **put** (const std::string &src) throw (BufferOverflowException, ReadOnlyBufferException)
Relative bulk put method (optional operation).

- virtual int **read** (**CharBuffer** *target) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, ReadOnlyBufferException)

Attempts to read characters into the specified character buffer.

- virtual **lang::CharSequence** * **subSequence** (int start, int end) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a new character buffer that represents the specified subsequence of this buffer, relative to the current position.

- virtual **CharBuffer** * **slice** () const =0

*Creates a new **CharBuffer** (p. 1119) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **CharBuffer** &value) const

- virtual bool **equals** (const **CharBuffer** &value) const

- virtual bool **operator==** (const **CharBuffer** &value) const

- virtual bool **operator<** (const **CharBuffer** &value) const

Static Public Member Functions

- static **CharBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Allocates a new character buffer.

- static **CharBuffer** * **wrap** (char *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **CharBuffer** (p. 1119).*

- static **CharBuffer** * **wrap** (std::vector< char > &buffer)

*Wraps the passed STL char Vector in a **CharBuffer** (p. 1119).*

Protected Member Functions

- **CharBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **CharBuffer** (p. 1119) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.183.1 Detailed Description

This class defines four categories of operations upon character buffers:.

- o Absolute and relative get and put methods that read and write single characters;
- o Relative bulk get methods that transfer contiguous sequences of characters from this buffer into an array; and
- o Relative bulk put methods that transfer contiguous sequences of characters from a character array, a string, or some other character buffer into this buffer.
- o Methods for compacting, duplicating, and slicing a character buffer.

Character buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing character array or string into a buffer, or by creating a view of an existing byte buffer

This class implements the `CharSequence` interface so that character buffers may be used wherever character sequences are accepted, for example in the regular-expression package `decaf.util.regex`.

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained. The sequence of statements

```
cb.put("text/"); cb.put(subtype); cb.put("; charset="); cb.put(enc);
```

can, for example, be replaced by the single statement

```
cb.put("text/").put(subtype).put("; charset=").put(enc);
```

6.183.2 Constructor & Destructor Documentation

6.183.2.1 `decaf::nio::CharBuffer::CharBuffer (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)` [protected]

Creates a **CharBuffer** (p. 1119) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size of the array, this is the limit we read and write to.

Exceptions:

IllegalArgumentException if *capacity* is negative.

6.183.2.2 `virtual decaf::nio::CharBuffer::~~CharBuffer ()` [inline, virtual]

6.183.3 Member Function Documentation

6.183.3.1 `static CharBuffer* decaf::nio::CharBuffer::allocate (int capacity) throw (decaf::lang::exceptions::IndexOutOfBoundsException)` [static]

Allocates a new character buffer. The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Char buffer in chars (1 byte).

Returns:

the **CharBuffer** (p. 1119) that was allocated, caller owns.

Exceptions:

IndexOutOfBoundsException if capacity is negative.

6.183.3.2 CharBuffer& decaf::nio::CharBuffer::append (const lang::CharSequence * *value*, int *start*, int *end*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, BufferOverflowException, ReadOnlyBufferException) [virtual]

Appends a subsequence of the specified character sequence to this buffer If value is Null the the string "null" is appended to the buffer.

Parameters:

value The CharSequence to append.

start The index to start appending from.

end The index to append to.

Returns:

a reference to this modified **CharBuffer** (p. 1119).

Exceptions:

BufferOverflowException (p. 954) if there is no more space

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

IndexOutOfBoundsException if start > end, or > length of sequence.

Implements **decaf::lang::Appendable** (p. 726).

6.183.3.3 CharBuffer& decaf::nio::CharBuffer::append (const lang::CharSequence * *value*) throw (BufferOverflowException, ReadOnlyBufferException) [virtual]

Appends the specified character sequence to this buffer. If value is Null the the string "null" is appended to the buffer.

Parameters:

value The CharSequence to append.

Returns:

a reference to this modified **CharBuffer** (p. 1119)

Exceptions:

BufferOverflowException (p. 954) if there is no more space

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

Implements **decaf::lang::Appendable** (p. 726).

6.183.3.4 CharBuffer& decaf::nio::CharBuffer::append (char *value*) throw (BufferOverflowException, ReadOnlyBufferException) [virtual]

Appends the specified character to this buffer.

Parameters:

value The char to append.

Returns:

a reference to this modified **CharBuffer** (p. 1119).

Exceptions:

BufferOverflowException (p. 954) if there is no more space

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

Implements **decaf::lang::Appendable** (p. 726).

6.183.3.5 virtual char* decaf::nio::CharBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]

Returns the character array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1113).

6.183.3.6 virtual int decaf::nio::CharBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::CharArrayBuffer` (p. 1113).

6.183.3.7 `virtual CharBuffer* decaf::nio::CharBuffer::asReadOnlyBuffer () const` [pure virtual]

Creates a new, read-only char buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only char buffer which the caller then owns.

Implemented in `decaf::internal::nio::CharArrayBuffer` (p. 1114).

6.183.3.8 `char decaf::nio::CharBuffer::charAt (int index) const throw (` `decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Reads the character at the given index relative to the current position.

Parameters:

index - The index of the character to be read relative to position

Returns:

The character at index `position()` (p. 932) + index.

Exceptions:

IndexOutOfBoundsException if the index + the current position exceeds the size of the buffer or the index is negative.

Implements `decaf::lang::CharSequence` (p. 1135).

6.183.3.9 `virtual CharBuffer& decaf::nio::CharBuffer::compact () throw (` `ReadOnlyBufferException)` [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index `p = position()` (p. 932) is copied to index zero, the byte at index `p + 1` is copied to index one, and so forth until the byte at index `limit()` (p. 932) - 1 is copied to index `n = limit()` (p. 932) - 1 - `p`. The buffer's position is then set to `n+1` and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **CharBuffer** (p. 1119).

Exceptions:

ReadOnlyBufferException (p. 3169) - If this buffer is read-only

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1114).

6.183.3.10 `virtual int decaf::nio::CharBuffer::compareTo (const CharBuffer & value) const` [virtual]

6.183.3.11 `virtual CharBuffer* decaf::nio::CharBuffer::duplicate ()` [pure virtual]

Creates a new char buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new char **Buffer** (p. 928) which the caller owns.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1114).

6.183.3.12 `virtual bool decaf::nio::CharBuffer::equals (const CharBuffer & value) const` [virtual]

6.183.3.13 `CharBuffer& decaf::nio::CharBuffer::get (char * buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)`

Relative bulk get method. This method transfers chars from this buffer into the given destination array. If there are fewer chars remaining in the buffer than are required to satisfy the request, that is, if `length > remaining()` (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies `length` chars from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by `length`.

Parameters:

buffer The pointer to an allocated buffer to fill.

size The size of the buffer passed.

offset The position in the buffer to start filling.

length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length chars remaining in this buffer

NullPointerException if the passed buffer is null.

IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.183.3.14 CharBuffer& decaf::nio::CharBuffer::get (std::vector< char > *buffer*) throw (BufferUnderflowException)

Relative bulk get method. This method transfers chars from this buffer into the given destination vector. An invocation of this method of the form `src.get(a)` behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call `buffer.resize(N)` before calling this get method.

Returns:

a reference to this **CharBuffer** (p. 1119).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length chars remaining in this buffer.

6.183.3.15 virtual char decaf::nio::CharBuffer::get (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the char at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the char is to be read.

Returns:

the char that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit or is negative.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1115).

6.183.3.16 virtual char decaf::nio::CharBuffer::get () throw (BufferUnderflowException) [pure virtual]

Relative get method. Reads the character at this buffer's current position, and then increments the position.

Returns:

the char at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1115).

6.183.3.17 virtual bool decaf::nio::CharBuffer::hasArray () const [pure virtual]

Tells whether or not this buffer is backed by an accessible char array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1115).

6.183.3.18 int decaf::nio::CharBuffer::length () const [inline, virtual]

Returns the length of this character buffer.

Returns:

the length of this buffer from the position to the limit.

Implements **decaf::lang::CharSequence** (p. 1136).

6.183.3.19 virtual bool decaf::nio::CharBuffer::operator< (const CharBuffer & value) const [virtual]**6.183.3.20 virtual bool decaf::nio::CharBuffer::operator== (const CharBuffer & value) const [virtual]****6.183.3.21 CharBuffer& decaf::nio::CharBuffer::put (const std::string & src) throw (BufferOverflowException, ReadOnlyBufferException)**

Relative bulk put method (optional operation). This method transfers the entire content of the given source string into this buffer. An invocation of this method of the form dst.put(s) behaves in exactly the same way as the invocation.

Parameters:

src The string to copy from.

Returns:

a reference to this **CharBuffer** (p. 1119).

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.183.3.22 CharBuffer& decaf::nio::CharBuffer::put (std::string & *src*, int *start*, int *end*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException)

Relative bulk put method (optional operation). This method transfers characters from the given string into this buffer. If there are more characters to be copied from the string than remain in this buffer, that is, if *end* - *start* > **remaining()** (p. 933), then no characters are transferred and a **BufferOverflowException** (p. 954) is thrown.

Returns:

a reference to this buffer

Otherwise, this method copies *n* = *end* - *start* characters from the given string into this buffer, starting at the given *start* index and at the current position of this buffer. The position of this buffer is then incremented by *n*.

Parameters:

src The string to copy from.
start The position in *src* to start from.
end The position in *src* to stop at.

Returns:

a reference to this **CharBuffer** (p. 1119).

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not
IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.
ReadOnlyBufferException (p. 3169) if this buffer is read-only

6.183.3.23 virtual CharBuffer& decaf::nio::CharBuffer::put (int *index*, char *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes the given char into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The char to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1116).

6.183.3.24 virtual CharBuffer& decaf::nio::CharBuffer::put (char *value*) throw (BufferOverflowException, ReadOnlyBufferException) [pure virtual]

Writes the given char into this buffer at the current position, and then increments the position.

Parameters:

value The char value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1116).

6.183.3.25 CharBuffer& decaf::nio::CharBuffer::put (std::vector< char > & *buffer*) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source char array into this buffer. This is the same as calling `put(&buffer[0], 0, buffer.size())`.

Parameters:

buffer The buffer whose contents are copied to this **CharBuffer** (p. 1119).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.183.3.26 CharBuffer& decaf::nio::CharBuffer::put (const char * *buffer*, int *size*, int *offset*, int *length*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers chars into this buffer from the given source array. If there are more chars to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no chars are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `length` bytes from the given array into this buffer, starting at the given `offset` in the array and at the current position of this buffer. The position of this buffer is then incremented by `length`.

Parameters:

buffer The array from which chars are to be read.
size The size of the buffer passed.
offset The offset within the array of the first char to be read.
length The number of chars to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer
ReadOnlyBufferException (p. 3169) if this buffer is read-only
NullPointerException if the passed buffer is null.
IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.183.3.27 `CharBuffer& decaf::nio::CharBuffer::put (CharBuffer & src)
 throw (BufferOverflowException, ReadOnlyBufferException,
 decaf::lang::exceptions::IllegalArgumentException)`

This method transfers the chars remaining in the given source buffer into this buffer. If there are more chars remaining in the source buffer than in this buffer, that is, if `src.remaining() > remaining()` (p. 933), then no chars are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` chars from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

src - the buffer to take chars from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer for the remaining chars in the source buffer.
IllegalArgumentException if the source buffer is this buffer.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.183.3.28 `virtual int decaf::nio::CharBuffer::read (CharBuffer * target)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IllegalArgumentException,
 ReadOnlyBufferException) [virtual]`

Attempts to read characters into the specified character buffer. The buffer is used as a repository of characters as-is: the only changes made are the results of a put operation. No flipping or rewinding of the buffer is performed.

Parameters:

target The buffer to read characters into

Returns:

The number of characters added to the buffer, or string::npos if this source of characters is at its end

Exceptions:

NullPointerException if target is Null.

IllegalArgumentException if target is this **CharBuffer** (p. 1119).

ReadOnlyBufferException (p. 3169) if this buffer is in read-only mode.

6.183.3.29 virtual CharBuffer* decaf::nio::CharBuffer::slice () const [pure virtual]

Creates a new **CharBuffer** (p. 1119) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **CharBuffer** (p. 1119) which the caller owns.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p. 1117).

6.183.3.30 virtual lang::CharSequence* decaf::nio::CharBuffer::subSequence (int start, int end) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Creates a new character buffer that represents the specified subsequence of this buffer, relative to the current position. The new buffer will share this buffer's content; that is, if the content of this buffer is mutable then modifications to one buffer will cause the other to be modified. The new buffer's capacity will be that of this buffer, its position will be **position()** (p. 932) + start, and its limit will be **position()** (p. 932) + end. The new **Buffer** (p. 928) will be read-only if, and only if, this buffer is read-only.

Parameters:

start The index, relative to the current position, of the first character in the subsequence; must be non-negative and no larger than **remaining()** (p. 933).

end The index, relative to the current position, of the character following the last character in the subsequence; must be no smaller than start and no larger than **remaining()** (p. 933).

Returns:

The new character buffer, caller owns.

Exceptions:

IndexOutOfBoundsException if the preconditions on start and end fail.

Implements **decaf::lang::CharSequence** (p.1136).

Implemented in **decaf::internal::nio::CharArrayBuffer** (p.1117).

6.183.3.31 `virtual std::string decaf::nio::CharBuffer::toString () const` [virtual]**Returns:**

a `std::string` describing this object

Implements **decaf::lang::CharSequence** (p.1136).

6.183.3.32 `static CharBuffer* decaf::nio::CharBuffer::wrap (std::vector< char > &buffer)` [static]

Wraps the passed STL char Vector in a **CharBuffer** (p.1119). The new buffer will be backed by the given char array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new **CharBuffer** (p.1119) that is backed by *buffer*, caller owns.

6.183.3.33 `static CharBuffer* decaf::nio::CharBuffer::wrap (char * array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [static]

Wraps the passed buffer with a new **CharBuffer** (p.1119). The new buffer will be backed by the given char array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

array The array that will back the new buffer.

size The size of the array passed in.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new **CharBuffer** (p. 1119) that is backed by buffer, caller owns.

Exceptions:

NullPointerException if the array pointer is Null.

IndexOutOfBoundsException if capacity is negative.

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**CharBuffer.h**

6.184 decaf::lang::CharSequence Class Reference

A **CharSequence** (p. 1135) is a readable sequence of char values.

#include <src/main/decaf/lang/CharSequence.h> Inheritance diagram for decaf::lang::CharSequence:

Public Member Functions

- virtual **~CharSequence** ()
- virtual int **length** () const =0
- virtual char **charAt** (int index) const =0 throw (lang::exceptions::IndexOutOfBoundsException)
Returns the Char at the specified index so long as the index is not greater than the length of the sequence.
- virtual **CharSequence** * **subSequence** (int start, int end) const =0 throw (lang::exceptions::IndexOutOfBoundsException)
*Returns a new **CharSequence** (p. 1135) that is a subsequence of this sequence.*
- virtual std::string **toString** () const =0

6.184.1 Detailed Description

A **CharSequence** (p. 1135) is a readable sequence of char values. This interface provides uniform, read-only access to many different kinds of char sequences.

This interface does not define that a **CharSequence** (p. 1135) should implement comparable, it is therefore up to the dervied classes that implement this interface to define equality, which implies that comparison of two **CharSequences** does not have a contract on equality.

6.184.2 Constructor & Destructor Documentation

6.184.2.1 virtual decaf::lang::CharSequence::~~CharSequence () [inline, virtual]

6.184.3 Member Function Documentation

6.184.3.1 virtual char decaf::lang::CharSequence::charAt (int *index*) const throw (lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Returns the Char at the specified index so long as the index is not greater than the length of the sequence.

Parameters:

index - position to return the char at.

Returns:

the char at the given position

Exceptions:

IndexOutOfBoundsException if index is > than **length()** (p. 1136) or negative

Implemented in **decaf::lang::String** (p. 3666), and **decaf::nio::CharBuffer** (p. 1125).

6.184.3.2 virtual int decaf::lang::CharSequence::length () const [pure virtual]**Returns:**

the length of the underlying character sequence.

Implemented in **decaf::lang::String** (p. 3667), and **decaf::nio::CharBuffer** (p. 1128).

6.184.3.3 virtual CharSequence* decaf::lang::CharSequence::subSequence (int start, int end) const throw (lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Returns a new **CharSequence** (p. 1135) that is a subsequence of this sequence. The subsequence starts with the char value at the specified index and ends with the char value at index end - 1. The length (in chars) of the returned sequence is end - start, so if start == end then an empty sequence is returned.

Parameters:

start - the start index, inclusive

end - the end index, exclusive

Returns:

a new **CharSequence** (p. 1135)

Exceptions:

IndexOutOfBoundsException if start or end > **length()** (p.1136) or start or end are negative.

Implemented in **decaf::internal::nio::CharArrayBuffer** (p.1117), **decaf::lang::String** (p. 3667), and **decaf::nio::CharBuffer** (p. 1132).

6.184.3.4 virtual std::string decaf::lang::CharSequence::toString () const [pure virtual]**Returns:**

the string representation of this **CharSequence** (p. 1135)

Implemented in **decaf::lang::String** (p. 3667), and **decaf::nio::CharBuffer** (p. 1133).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**CharSequence.h**

6.185 decaf::util::zip::Checksum Class Reference

An implementation of a `FilterInputStream` that will maintain a **Checksum** (p. 1142) of the bytes read, the **Checksum** (p. 1142) can then be used to verify the integrity of the input stream.

#include <src/main/decaf/util/zip/Checksum.h> Inheritance diagram for decaf::util::zip::Checksum:

Public Member Functions

- **Checksum** (InputStream *inputStream, Checksum *sum, bool own=false)

Create a new instance of a **Checksum** (p. 1137).

- virtual ~Checksum ()
- Checksum * getChecksum () const

Returns a Pointer to the **Checksum** (p. 1142) that is in use by this **Checksum** (p. 1137).

- virtual long long skip (long long num) throw (decaf::io::IOException)

Skips over and discards *n* bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until *num* bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Protected Member Functions

- virtual int doReadByte () throw (decaf::io::IOException)
- virtual int doReadArrayBounded (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.185.1 Detailed Description

An implementation of a `FilterInputStream` that will maintain a **Checksum** (p. 1142) of the bytes read, the **Checksum** (p. 1142) can then be used to verify the integrity of the input stream.

Since:

1.0

6.185.2 Constructor & Destructor Documentation

6.185.2.1 decaf::util::zip::CheckedInputStream::CheckedInputStream (InputStream * *inputStream*, Checksum * *sum*, bool *own* = false)

Create a new instance of a **CheckedInputStream** (p. 1137).

Parameters:

inputStream The InputStream instance to Wrap.

sum The **Checksum** (p. 1142) instance to use (does not take ownership of the Pointer).

own Indicates if this filer should take ownership of the InputStream.

Exceptions:

NullPointerException if the **Checksum** (p. 1142) pointer is NULL.

6.185.2.2 virtual decaf::util::zip::CheckedInputStream::~~CheckedInputStream () [virtual]

6.185.3 Member Function Documentation

6.185.3.1 virtual int decaf::util::zip::CheckedInputStream::doReadArrayBounded (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.185.3.2 virtual int decaf::util::zip::CheckedInputStream::doReadByte () throw (decaf::io::IOException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.185.3.3 Checksum* decaf::util::zip::CheckedInputStream::getChecksum () const [inline]

Returns a Pointer to the **Checksum** (p. 1142) that is in use by this **CheckedInputStream** (p. 1137).

Returns:

the pointer to the **Checksum** (p. 1142) instance that is in use by this object.

6.185.3.4 `virtual long long decaf::util::zip::CheckedInputStream::skip (long long num) throw (decaf::io::IOException)` [virtual]

Skips over and discards *n* bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until *num* bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Adds the skipped bytes into the **Checksum** (p. 1142).

Reimplemented from **decaf::io::FilterInputStream** (p. 1899).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/CheckedInputStream.h`

6.186 decaf::util::zip::CheckedOutputStream Class Reference

An implementation of a `FilterOutputStream` that will maintain a **Checksum** (p.1142) of the bytes written, the **Checksum** (p.1142) can then be used to verify the integrity of the output stream.

#include <src/main/decaf/util/zip/CheckedOutputStream.h> Inheritance diagram for decaf::util::zip::CheckedOutputStream:

Public Member Functions

- **CheckedOutputStream** (decaf::io::OutputStream *outputStream, Checksum *sum, bool own=false)
*Create a new instance of a **CheckedOutputStream** (p. 1140).*
- virtual ~**CheckedOutputStream** ()
- **Checksum** * **getChecksum** () const

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.186.1 Detailed Description

An implementation of a `FilterOutputStream` that will maintain a **Checksum** (p.1142) of the bytes written, the **Checksum** (p.1142) can then be used to verify the integrity of the output stream.

Since:

1.0

6.186.2 Constructor & Destructor Documentation

- ##### 6.186.2.1 decaf::util::zip::CheckedOutputStream::CheckedOutputStream (decaf::io::OutputStream * outputStream, Checksum * sum, bool own = false)

Create a new instance of a **CheckedOutputStream** (p. 1140).

Parameters:

- outputStream* The `OutputStream` instance to Wrap.
- sum* The **Checksum** (p.1142) instance to use (does not take ownership of the Pointer).
- own* Indicates if this filer should take ownership of the `InputStream`.

Exceptions:

NullPointerException if the **Checksum** (p. 1142) pointer is NULL.

6.186.2.2 virtual decaf::util::zip::ChecksumOutputStream::~ChecksumOutputStream()
[virtual]

6.186.3 Member Function Documentation

6.186.3.1 virtual void decaf::util::zip::ChecksumOutputStream::doWriteArrayBounded (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.186.3.2 virtual void decaf::util::zip::ChecksumOutputStream::doWriteByte (unsigned char *value*) throw (decaf::io::IOException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.186.3.3 Checksum* decaf::util::zip::ChecksumOutputStream::getChecksum () const [inline]

Returns:

a pointer to the **Checksum** (p. 1142) instance in use by this object.

The documentation for this class was generated from the following file:

- src/main/decaf/util/zip/ChecksumOutputStream.h

6.187 decaf::util::zip::Checksum Class Reference

An interface used to represent **Checksum** (p.1142) values in the Zip package.

#include <src/main/decaf/util/zip/Checksum.h> Inheritance diagram for decaf::util::zip::Checksum:

Public Member Functions

- virtual **~Checksum** ()
- virtual long long **getValue** () const =0
- virtual void **reset** ()=0
Reset the checksum to its initial value.
- virtual void **update** (const std::vector< unsigned char > &buffer)=0
Updates the current checksum with the specified vector of bytes.
- virtual void **update** (const std::vector< unsigned char > &buffer, int offset, int length)=0
throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Updates the current checksum with the specified array of bytes.
- virtual void **update** (const unsigned char *buffer, int size, int offset, int length)=0 throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Updates the current checksum with the specified array of bytes.
- virtual void **update** (int byte)=0
Updates the current checksum with the specified byte value.

6.187.1 Detailed Description

An interface used to represent **Checksum** (p.1142) values in the Zip package.

Since:

1.0

6.187.2 Constructor & Destructor Documentation

6.187.2.1 virtual decaf::util::zip::Checksum::~~Checksum () [inline, virtual]

6.187.3 Member Function Documentation

6.187.3.1 virtual long long decaf::util::zip::Checksum::getValue () const [pure virtual]

Returns:

the current checksum value.

Implemented in **decaf::util::zip::Adler32** (p. 723), and **decaf::util::zip::CRC32** (p. 1525).

6.187.3.2 virtual void decaf::util::zip::Checksum::reset () [pure virtual]

Reset the checksum to its initial value.

Implemented in **decaf::util::zip::Adler32** (p. 723), and **decaf::util::zip::CRC32** (p. 1525).

6.187.3.3 virtual void decaf::util::zip::Checksum::update (int *byte*) [pure virtual]

Updates the current checksum with the specified byte value.

Parameters:

byte The byte value to update the current **Checksum** (p. 1142) with (0..255).

Implemented in **decaf::util::zip::Adler32** (p. 723), and **decaf::util::zip::CRC32** (p. 1525).

6.187.3.4 virtual void decaf::util::zip::Checksum::update (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

size The size of the passed buffer.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

NullPointerException if the passed buffer is NULL.

IndexOutOfBoundsException if $\text{offset} + \text{length} > \text{size of the buffer}$.

Implemented in **decaf::util::zip::Adler32** (p. 723), and **decaf::util::zip::CRC32** (p. 1525).

6.187.3.5 virtual void decaf::util::zip::Checksum::update (const std::vector< unsigned char > & *buffer*, int *offset*, int *length*) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

IndexOutOfBoundsException if $\text{offset} + \text{length} > \text{size of the buffer}$.

Implemented in **decaf::util::zip::Adler32** (p. 724), and **decaf::util::zip::CRC32** (p. 1526).

6.187.3.6 virtual void decaf::util::zip::Checksum::update (const std::vector< unsigned char > & *buffer*) [pure virtual]

Updates the current checksum with the specified vector of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

Implemented in **decaf::util::zip::Adler32** (p. 724), and **decaf::util::zip::CRC32** (p. 1526).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/Checksum.h`

6.188 decaf::lang::exceptions::ClassCastException Class Reference

#include <src/main/decaf/lang/exceptions/ClassCastException.h> Inheritance diagram for decaf::lang::exceptions::ClassCastException:

Public Member Functions

- **ClassCastException** () throw ()
Default Constructor.
- **ClassCastException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **ClassCastException** (const **ClassCastException** &ex) throw ()
Copy Constructor.
- **ClassCastException** (const std::exception *cause) throw ()
Constructor.
- **ClassCastException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ClassCastException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **ClassCastException** * clone () const
Clones this exception.
- virtual ~**ClassCastException** () throw ()

6.188.1 Constructor & Destructor Documentation

6.188.1.1 decaf::lang::exceptions::ClassCastException::ClassCastException () throw () [inline]

Default Constructor.

6.188.1.2 decaf::lang::exceptions::ClassCastException::ClassCastException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.188.1.3 decaf::lang::exceptions::ClassCastException::ClassCastException (const ClassCastException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.188.1.4 decaf::lang::exceptions::ClassCastException::ClassCastException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.188.1.5 decaf::lang::exceptions::ClassCastException::ClassCastException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.188.1.6 decaf::lang::exceptions::ClassCastException::ClassCastException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.188.1.7 `virtual decaf::lang::exceptions::ClassCastException::~~ClassCastException
() throw () [inline, virtual]`

6.188.2 Member Function Documentation

6.188.2.1 `virtual ClassCastException* de-
caf::lang::exceptions::ClassCastException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/ClassCastException.h`

6.189 cms::Closeable Class Reference

Interface for a class that implements the close method.

#include <src/main/cms/Closeable.h> Inheritance diagram for cms::Closeable:

Public Member Functions

- virtual `~Closeable ()`
- virtual void `close ()=0` throw (CMSEException)
Closes this object and deallocates the appropriate resources.

6.189.1 Detailed Description

Interface for a class that implements the close method. A class that implements this interface should release all resources upon the close call and should throw an exception from any methods that require those resources after they have been closed.

Since:

1.0

6.189.2 Constructor & Destructor Documentation

6.189.2.1 virtual cms::Closeable::~~Closeable () [inline, virtual]

6.189.3 Member Function Documentation

6.189.3.1 virtual void cms::Closeable::close () throw (CMSEException) [pure virtual]

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

CMSEException (p. 1160) - If an error occurs while the resource is being closed.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1072), `activemq::cmsutil::CachedProducer` (p. 1076), `activemq::cmsutil::PooledSession` (p. 2957), `activemq::commands::ActiveMQTempDestination` (p. 577), `activemq::core::ActiveMQConnection` (p. 279), `activemq::core::ActiveMQConsumer` (p. 313), `activemq::core::ActiveMQProducer` (p. 472), `activemq::core::ActiveMQQueueBrowser` (p. 488), `activemq::core::ActiveMQSession` (p. 520), `cms::Connection` (p. 1263), and `cms::Session` (p. 3368).

The documentation for this class was generated from the following file:

- `src/main/cms/Closeable.h`

6.190 decaf::io::Closeable Class Reference

Interface for a class that implements the close method.

#include <src/main/decaf/io/Closeable.h> Inheritance diagram for decaf::io::Closeable:

Public Member Functions

- virtual `~Closeable ()`
- virtual void `close ()=0 throw (io::IOException)`
Closes this object and deallocates the appropriate resources.

6.190.1 Detailed Description

Interface for a class that implements the close method.

6.190.2 Constructor & Destructor Documentation

6.190.2.1 virtual `decaf::io::Closeable::~~Closeable ()` [inline, virtual]

6.190.3 Member Function Documentation

6.190.3.1 virtual void `decaf::io::Closeable::close () throw (io::IOException)` [pure virtual]

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

Implemented in `activemq::transport::correlator::ResponseCorrelator` (p. 3292), `activemq::transport::failover::FailoverTransport` (p. 1876), `activemq::transport::inactivity::InactivityMonitor` (p. 2005), `activemq::transport::IOTransport` (p. 2147), `activemq::transport::mock::MockTransport` (p. 2770), `activemq::transport::tcp::TcpTransport` (p. 3753), `activemq::transport::TransportFilter` (p. 3893), `activemq::wireformat::openwire::OpenWireFormatNegotiator` (p. 2902), `decaf::internal::io::StandardErrorOutputStream` (p. 3580), `decaf::internal::io::StandardOutputStream` (p. 3584), `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2863), `decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream` (p. 2883), `decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream` (p. 2886), `decaf::internal::net::tcp::TcpSocketInputStream` (p. 3748), `decaf::internal::net::tcp::TcpSocketOutputStream` (p. 3751), `decaf::io::BlockingByteArrayInputStream` (p. 841), `decaf::io::BufferedInputStream` (p. 937), `decaf::io::FilterInputStream` (p. 1897), `decaf::io::FilterOutputStream` (p. 1901), `decaf::io::InputStream` (p. 2045), `decaf::io::InputStreamReader` (p. 2054),

decaf::io::OutputStream (p. 2909), **decaf::io::OutputStreamWriter** (p. 2916), **decaf::net::Socket** (p. 3509), **decaf::util::logging::ConsoleHandler** (p. 1399), **decaf::util::logging::StreamHandler** (p. 3650), **decaf::util::zip::DeflaterOutputStream** (p. 1718), and **decaf::util::zip::InflaterInputStream** (p. 2039).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/Closeable.h`

6.191 activemq::transport::failover::CloseTransportsTask Class Reference

#include <src/main/activemq/transport/failover/CloseTransportsTask.h> Inheritance diagram for activemq::transport::failover::CloseTransportsTask:

Public Member Functions

- **CloseTransportsTask** ()
- virtual **~CloseTransportsTask** ()
- void **add** (const **Pointer**< **Transport** > &transport)
*Add a new **Transport** (p. 3883) to close.*
- virtual bool **isPending** () const
This Task is pending if there are transports in the Queue that need to be closed.
- virtual bool **iterate** ()
Return true until all transports have been closed and removed from the queue.

6.191.1 Constructor & Destructor Documentation

- 6.191.1.1** **activemq::transport::failover::CloseTransportsTask::CloseTransportsTask** ()
- 6.191.1.2** **virtual**
activemq::transport::failover::CloseTransportsTask::~~CloseTransportsTask () [virtual]

6.191.2 Member Function Documentation

- 6.191.2.1** **void** **activemq::transport::failover::CloseTransportsTask::add** (const **Pointer**< **Transport** > & *transport*)

Add a new **Transport** (p. 3883) to close.

- 6.191.2.2** **virtual bool** **activemq::transport::failover::CloseTransportsTask::isPending** () const [virtual]

This Task is pending if there are transports in the Queue that need to be closed.

Returns:

true if there is a **transport** (p. 97) in the queue that needs closed.

Implements **activemq::threads::CompositeTask** (p. 1221).

6.191.2.3 virtual bool activemq::transport::failover::CloseTransportsTask::iterate () [virtual]

Return true until all transports have been closed and removed from the queue.

Implements **activemq::threads::Task** (p. 3734).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/failover/**CloseTransportsTask.h**

6.192 activemq::cmsutil::CmsAccessor Class Reference

Base class for **activemq.cmsutil.CmsTemplate** (p.1170) and other CMS-accessing gateway helpers, defining common properties such as the CMS **cms.ConnectionFactory** (p.1324) to operate on.

#include <src/main/activemq/cmsutil/CmsAccessor.h> Inheritance diagram for activemq::cmsutil::CmsAccessor:

Public Member Functions

- **CmsAccessor** ()
- virtual **~CmsAccessor** ()
- virtual **ResourceLifecycleManager** * **getResourceLifecycleManager** ()
- virtual const **ResourceLifecycleManager** * **getResourceLifecycleManager** () const
- virtual void **setConnectionFactory** (cms::ConnectionFactory *connectionFactory)
Set the ConnectionFactory to use for obtaining CMS Connections.
- virtual const cms::ConnectionFactory * **getConnectionFactory** () const
Return the ConnectionFactory that this accessor uses for obtaining CMS Connections.
- virtual cms::ConnectionFactory * **getConnectionFactory** ()
Return the ConnectionFactory that this accessor uses for obtaining CMS Connections.
- virtual void **setSessionAcknowledgeMode** (cms::Session::AcknowledgeMode sessionAcknowledgeMode)
Set the CMS acknowledgment mode that is used when creating a CMS Session to send a message.
- virtual cms::Session::AcknowledgeMode **getSessionAcknowledgeMode** () const
Return the acknowledgment mode for CMS sessions.

Protected Member Functions

- **CmsAccessor** (const **CmsAccessor** &)
- **CmsAccessor** & **operator=** (const **CmsAccessor** &)
- virtual void **init** () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)
Initializes this object and prepares it for use.
- virtual void **destroy** () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)
Shuts down this object and destroys any allocated resources.
- virtual cms::Connection * **createConnection** () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)
Create a CMS Connection via this template's ConnectionFactory.

- virtual **cms::Session** * **createSession** (**cms::Connection** *con) throw (**cms::CMSException**, **decaf::lang::exceptions::IllegalStateException**)
Create a CMS Session for the given Connection.
- virtual void **checkConnectionFactory** () throw (**decaf::lang::exceptions::IllegalStateException**)
Verifies that the connection factory is valid.

6.192.1 Detailed Description

Base class for **activemq.cmsutil.CmsTemplate** (p.1170) and other CMS-accessing gateway helpers, defining common properties such as the CMS **cms.ConnectionFactory** (p.1324) to operate on. The subclass **activemq.cmsutil.CmsDestinationAccessor** (p.1157) adds further, destination-related properties.

Not intended to be used directly.

See also:

activemq.cmsutil.CmsDestinationAccessor (p.1157)
activemq.cmsutil.CmsTemplate (p.1170)

6.192.2 Constructor & Destructor Documentation

- 6.192.2.1** **activemq::cmsutil::CmsAccessor::CmsAccessor** (const **CmsAccessor** &)
[inline, protected]
- 6.192.2.2** **activemq::cmsutil::CmsAccessor::CmsAccessor** ()
- 6.192.2.3** **virtual activemq::cmsutil::CmsAccessor::~~CmsAccessor** () [virtual]

6.192.3 Member Function Documentation

- 6.192.3.1** **virtual void activemq::cmsutil::CmsAccessor::checkConnectionFactory** () throw (**decaf::lang::exceptions::IllegalStateException**) [protected, virtual]

Verifies that the connection factory is valid.

- 6.192.3.2** **virtual cms::Connection* activemq::cmsutil::CmsAccessor::createConnection** () throw (**cms::CMSException**, **decaf::lang::exceptions::IllegalStateException**) [protected, virtual]

Create a CMS Connection via this template's ConnectionFactory.

Returns:

the new CMS Connection

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

6.192.3.3 `virtual cms::Session* activemq::cmsutil::CmsAccessor::createSession (cms::Connection * con) throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException) [protected, virtual]`

Create a CMS Session for the given Connection.

Parameters:

con the CMS Connection to create a Session for

Returns:

the new CMS Session

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

6.192.3.4 `virtual void activemq::cmsutil::CmsAccessor::destroy () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException) [inline, protected, virtual]`

Shuts down this object and destroys any allocated resources.

Reimplemented in `activemq::cmsutil::CmsDestinationAccessor` (p.1158), and `activemq::cmsutil::CmsTemplate` (p.1173).

6.192.3.5 `virtual cms::ConnectionFactory* activemq::cmsutil::CmsAccessor::getConnectionFactory () [inline, virtual]`

Return the ConnectionFactory that this accessor uses for obtaining CMS Connections.

6.192.3.6 `virtual const cms::ConnectionFactory* activemq::cmsutil::CmsAccessor::getConnectionFactory () const [inline, virtual]`

Return the ConnectionFactory that this accessor uses for obtaining CMS Connections.

6.192.3.7 `virtual const ResourceLifecycleManager* activemq::cmsutil::CmsAccessor::getResourceLifecycleManager () const [inline, virtual]`

6.192.3.8 `virtual ResourceLifecycleManager* activemq::cmsutil::CmsAccessor::getResourceLifecycleManager () [inline, virtual]`

6.192.3.9 `virtual cms::Session::AcknowledgeMode activemq::cmsutil::CmsAccessor::getSessionAcknowledgeMode () const [inline, virtual]`

Return the acknowledgment mode for CMS sessions.

Returns:

the acknowledgment mode applied by this accessor

6.192.3.10 `virtual void activemq::cmsutil::CmsAccessor::init () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException) [inline, protected, virtual]`

Initializes this object and prepares it for use. This should be called before any other methods are called. This version does nothing.

Reimplemented in `activemq::cmsutil::CmsDestinationAccessor` (p.1158), and `activemq::cmsutil::CmsTemplate` (p.1176).

6.192.3.11 `CmsAccessor& activemq::cmsutil::CmsAccessor::operator= (const CmsAccessor &) [inline, protected]`

Reimplemented in `activemq::cmsutil::CmsDestinationAccessor` (p.1159), and `activemq::cmsutil::CmsTemplate` (p.1176).

6.192.3.12 `virtual void activemq::cmsutil::CmsAccessor::setConnectionFactory (cms::ConnectionFactory * connectionFactory) [inline, virtual]`

Set the ConnectionFactory to use for obtaining CMS Connections.

6.192.3.13 `virtual void activemq::cmsutil::CmsAccessor::setSessionAcknowledgeMode (cms::Session::AcknowledgeMode sessionAcknowledgeMode) [inline, virtual]`

Set the CMS acknowledgment mode that is used when creating a CMS Session to send a message. Default is `AUTO_ACKNOWLEDGE`.

Parameters:

sessionAcknowledgeMode the acknowledgment mode

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsAccessor.h`

6.193 `activemq::cmsutil::CmsDestinationAccessor` Class Reference

Extends the `CmsAccessor` (p. 1153) to add support for resolving destination names.

`#include <src/main/activemq/cmsutil/CmsDestinationAccessor.h>` Inheritance diagram for `activemq::cmsutil::CmsDestinationAccessor`:

Public Member Functions

- `CmsDestinationAccessor ()`
- `virtual ~CmsDestinationAccessor ()`
- `virtual bool isPubSubDomain () const`
- `virtual void setPubSubDomain (bool pubSubDomain)`
- `virtual DestinationResolver * getDestinationResolver ()`
- `virtual const DestinationResolver * getDestinationResolver () const`
- `virtual void setDestinationResolver (DestinationResolver *destRes)`

Protected Member Functions

- `CmsDestinationAccessor (const CmsDestinationAccessor &)`
- `CmsDestinationAccessor & operator= (const CmsDestinationAccessor &)`
- `virtual void init () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
Initializes the destination resolver.
- `virtual void destroy () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
*Calls **destroy()** (p. 1158) on the destination resolver.*
- `virtual cms::Destination * resolveDestinationName (cms::Session *session, const std::string &destName) throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
*Resolves the destination via the *DestinationResolver* (p. 1756).*
- `virtual void checkDestinationResolver () throw (decaf::lang::exceptions::IllegalStateException)`
Verifies that the destination resolver is valid.

6.193.1 Detailed Description

Extends the `CmsAccessor` (p. 1153) to add support for resolving destination names. Not intended to be used directly.

See also:

`CmsTemplate` (p. 1170)
`CmsAccessor` (p. 1153)

6.193.2 Constructor & Destructor Documentation

- 6.193.2.1** `activemq::cmsutil::CmsDestinationAccessor::CmsDestinationAccessor (const CmsDestinationAccessor &) [inline, protected]`
- 6.193.2.2** `activemq::cmsutil::CmsDestinationAccessor::CmsDestinationAccessor ()`
- 6.193.2.3** `virtual
activemq::cmsutil::CmsDestinationAccessor::~~CmsDestinationAccessor ()
[virtual]`

6.193.3 Member Function Documentation

- 6.193.3.1** `virtual void activemq::cmsutil::CmsDestinationAccessor::checkDestinationResolver ()
throw (decaf::lang::exceptions::IllegalStateException) [protected,
virtual]`

Verifies that the destination resolver is valid.

- 6.193.3.2** `virtual void activemq::cmsutil::CmsDestinationAccessor::destroy () throw
(cms::CMSException, decaf::lang::exceptions::IllegalStateException)
[protected, virtual]`

Calls `destroy()` (p. 1158) on the destination resolver.

Reimplemented from `activemq::cmsutil::CmsAccessor` (p. 1155).

Reimplemented in `activemq::cmsutil::CmsTemplate` (p. 1173).

- 6.193.3.3** `virtual const DestinationResolver* ac-
tivemq::cmsutil::CmsDestinationAccessor::getDestinationResolver ()
const [inline, virtual]`

- 6.193.3.4** `virtual DestinationResolver* ac-
tivemq::cmsutil::CmsDestinationAccessor::getDestinationResolver ()
[inline, virtual]`

- 6.193.3.5** `virtual void activemq::cmsutil::CmsDestinationAccessor::init () throw
(cms::CMSException, decaf::lang::exceptions::IllegalStateException)
[protected, virtual]`

Initializes the destination resolver.

Reimplemented from `activemq::cmsutil::CmsAccessor` (p. 1156).

Reimplemented in `activemq::cmsutil::CmsTemplate` (p. 1176).

6.193.3.6 `virtual bool activemq::cmsutil::CmsDestinationAccessor::isPubSubDomain () const`
[inline, virtual]

6.193.3.7 `CmsDestinationAccessor& activemq::cmsutil::CmsDestinationAccessor::operator=`
`(const CmsDestinationAccessor &) [inline, protected]`

Reimplemented from `activemq::cmsutil::CmsAccessor` (p. 1156).

Reimplemented in `activemq::cmsutil::CmsTemplate` (p. 1176).

6.193.3.8 `virtual cms::Destination* activemq::cmsutil::CmsDestinationAccessor::resolveDestinationName`
`(cms::Session * session, const std::string & destName) throw (`
`cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
[protected, virtual]

Resolves the destination via the `DestinationResolver` (p. 1756).

Parameters:

session the session

destName the name of the destination.

Returns:

the destination

Exceptions:

cms::CMSException (p. 1160) if resolution failed.

decaf::lang::exceptions::IllegalStateException (p. 1998) if the destination resolver property is NULL.

6.193.3.9 `virtual void activemq::cmsutil::CmsDestinationAccessor::setDestinationResolver`
`(DestinationResolver * destRes) [inline, virtual]`

6.193.3.10 `virtual void activemq::cmsutil::CmsDestinationAccessor::setPubSubDomain (bool`
`pubSubDomain) [inline, virtual]`

Reimplemented in `activemq::cmsutil::CmsTemplate` (p. 1181).

Referenced by `activemq::cmsutil::CmsTemplate::setPubSubDomain()`.

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsDestinationAccessor.h`

6.194 cms::CMSException Class Reference

CMS API Exception that is the base for all exceptions thrown from CMS classes.

#include <src/main/cms/CMSException.h> Inheritance diagram for cms::CMSException:

Public Member Functions

- **CMSException** () throw ()
- **CMSException** (const **CMSException** &ex) throw ()
- **CMSException** (const std::string &message, const std::exception *cause) throw ()
- **CMSException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**CMSException** () throw ()
- virtual std::string **getMessage** () const
Gets the cause of the error.
- virtual const std::exception * **getCause** () const
Gets the exception that caused this one to be thrown, this allows for chaining of exceptions in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.
- virtual std::vector< std::pair< std::string, int > > **getStackTrace** () const
Provides the stack trace for every point where this exception was caught, marked, and rethrown.
- virtual void **setMark** (const char *file, const int lineNumber)
Adds a file/line number to the stack trace.
- virtual void **printStackTrace** () const
Prints the stack trace to std::err.
- virtual void **printStackTrace** (std::ostream &stream) const
Prints the stack trace to the given output stream.
- virtual std::string **getStackTraceString** () const
Gets the stack trace as one contiguous string.
- virtual const char * **what** () const throw ()
Overloads the std::exception what() (p. 1162) function to return the cause of the exception.

6.194.1 Detailed Description

CMS API Exception that is the base for all exceptions thrown from CMS classes. This class represents an error that has occurred in CMS, providers can wrap provider specific exceptions in this class by setting the cause to an instance of a provider specific exception provided it can be cast to an std::exception.

Since the contained cause exception is of type `std::exception` and the C++ exception class has no clone or copy method defined the contained exception can only be owned by one instance of an **CMSEException** (p. 1160). To that end the class hands off the exception to each successive copy so care must be taken when handling **CMSEException** (p. 1160) instances.

Since:

1.0

6.194.2 Constructor & Destructor Documentation

6.194.2.1 `cms::CMSEException::CMSEException () throw ()`

6.194.2.2 `cms::CMSEException::CMSEException (const CMSEException & ex) throw ()`

6.194.2.3 `cms::CMSEException::CMSEException (const std::string & message, const std::exception * cause) throw ()`

6.194.2.4 `cms::CMSEException::CMSEException (const std::string & message, const std::exception * cause, const std::vector< std::pair< std::string, int > > & stackTrace) throw ()`

6.194.2.5 `virtual cms::CMSEException::~~CMSEException () throw () [virtual]`

6.194.3 Member Function Documentation

6.194.3.1 `virtual const std::exception* cms::CMSEException::getCause () const [virtual]`

Gets the exception that caused this one to be thrown, this allows for chaining of exceptions in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.

Returns:

a const pointer reference to the causal exception, if there was no cause associated with this exception then NULL is returned.

6.194.3.2 `virtual std::string cms::CMSEException::getMessage () const [virtual]`

Gets the cause of the error.

Returns:

string errors message

6.194.3.3 `virtual std::vector< std::pair< std::string, int> > cms::CMSEException::getStackTrace () const [virtual]`

Provides the stack trace for every point where this exception was caught, marked, and rethrown.

Returns:

vector containing stack trace strings

6.194.3.4 virtual std::string cms::CMSException::getStackTraceString () const [virtual]

Gets the stack trace as one contiguous string.

Returns:

string with formatted stack trace data

6.194.3.5 virtual void cms::CMSException::printStackTrace (std::ostream & *stream*) const [virtual]

Prints the stack trace to the given output stream.

Parameters:

stream the target output stream.

6.194.3.6 virtual void cms::CMSException::printStackTrace () const [virtual]

Prints the stack trace to std::err.

6.194.3.7 virtual void cms::CMSException::setMark (const char * *file*, const int *lineNumber*) [virtual]

Adds a file/line number to the stack trace.

Parameters:

file The name of the file calling this method (use `__FILE__`).

lineNumber The line number in the calling file (use `__LINE__`).

6.194.3.8 virtual const char* cms::CMSException::what () const throw () [virtual]

Overloads the std::exception **what()** (p. 1162) function to return the cause of the exception.

Returns:

const char pointer to error message

The documentation for this class was generated from the following file:

- `src/main/cms/CMSException.h`

6.195 activemq::util::CMSExceptionSupport Class Reference

```
#include <src/main/activemq/util/CMSExceptionSupport.h>
```

Public Member Functions

- virtual `~CMSExceptionSupport()`

Static Public Member Functions

- static `cms::CMSException create (const std::string &msg, const decaf::lang::Exception &cause)`
- static `cms::CMSException create (const decaf::lang::Exception &cause)`
- static `cms::MessageEOFException createMessageEOFException (const decaf::lang::Exception &cause)`
- static `cms::MessageFormatException createMessageFormatException (const decaf::lang::Exception &cause)`

6.195.1 Constructor & Destructor Documentation

6.195.1.1 virtual `activemq::util::CMSExceptionSupport::~~CMSExceptionSupport()` [virtual]

6.195.2 Member Function Documentation

6.195.2.1 static `cms::CMSException activemq::util::CMSExceptionSupport::create (const decaf::lang::Exception & cause)` [static]

6.195.2.2 static `cms::CMSException activemq::util::CMSExceptionSupport::create (const std::string & msg, const decaf::lang::Exception & cause)` [static]

6.195.2.3 static `cms::MessageEOFException activemq::util::CMSExceptionSupport::createMessageEOFException (const decaf::lang::Exception & cause)` [static]

6.195.2.4 static `cms::MessageFormatException activemq::util::CMSExceptionSupport::createMessageFormatException (const decaf::lang::Exception & cause)` [static]

Referenced by `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getBooleanProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getByteProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getDoubleProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getFloatProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getIntProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getLongProperty()`, `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getShortProperty()`, and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::getStringProperty()`.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/CMSExceptionSupport.h`

6.196 cms::CMSProperties Class Reference

Interface for a Java-like properties object.

#include <src/main/cms/CMSProperties.h> Inheritance diagram for cms::CMSProperties:

Public Member Functions

- virtual **~CMSProperties** ()
- virtual bool **isEmpty** () const =0
Returns true if the properties object is empty.
- virtual const char * **getProperty** (const std::string &name) const =0
Looks up the value for the given property.
- virtual std::string **getProperty** (const std::string &name, const std::string &defaultValue) const =0
Looks up the value for the given property.
- virtual void **setProperty** (const std::string &name, const std::string &value)=0
Sets the value for a given property.
- virtual bool **hasProperty** (const std::string &name) const =0
Check to see if the Property exists in the set.
- virtual void **remove** (const std::string &name)=0
Removes the property with the given name.
- virtual std::vector< std::pair< std::string, std::string > > **toArray** () const =0
Method that serializes the contents of the property map to an array.
- virtual void **copy** (const **CMSProperties** *source)=0
Copies the contents of the given properties object to this one.
- virtual **CMSProperties** * **clone** () const =0
Clones this object.
- virtual void **clear** ()=0
Clears all properties from the map.
- virtual std::string **toString** () const =0
Formats the contents of the Properties Object into a string that can be logged, etc.

6.196.1 Detailed Description

Interface for a Java-like properties object. This is essentially a map of key-value string pairs.

Since:

1.1

6.196.2 Constructor & Destructor Documentation

6.196.2.1 `virtual cms::CMSProperties::~~CMSProperties () [inline, virtual]`

6.196.3 Member Function Documentation

6.196.3.1 `virtual void cms::CMSProperties::clear () [pure virtual]`

Clears all properties from the map.

Implemented in `activemq::util::ActiveMQProperties` (p. 479).

6.196.3.2 `virtual CMSProperties* cms::CMSProperties::clone () const [pure virtual]`

Clones this object.

Returns:

a replica of this object.

Implemented in `activemq::util::ActiveMQProperties` (p. 479).

6.196.3.3 `virtual void cms::CMSProperties::copy (const CMSProperties * source) [pure virtual]`

Copies the contents of the given properties object to this one.

Parameters:

source The source properties object.

6.196.3.4 `virtual std::string cms::CMSProperties::getProperty (const std::string & name, const std::string & defaultValue) const [pure virtual]`

Looks up the value for the given property.

Parameters:

name the name of the property to be looked up.

defaultValue The value to be returned if the given property does not exist.

Returns:

The value of the property specified by *name*, if it exists, otherwise the *defaultValue*.

Implemented in `activemq::util::ActiveMQProperties` (p. 480).

6.196.3.5 `virtual const char* cms::CMSProperties::getProperty (const std::string & name) const` [pure virtual]

Looks up the value for the given property.

Parameters:

name The name of the property to be looked up.

Returns:

the value of the property with the given name, if it exists. If it does not exist, returns NULL.

Implemented in `activemq::util::ActiveMQProperties` (p. 480).

6.196.3.6 `virtual bool cms::CMSProperties::hasProperty (const std::string & name) const` [pure virtual]

Check to see if the Property exists in the set.

Parameters:

name the name of the property to check

Returns:

true if property exists, false otherwise.

Implemented in `activemq::util::ActiveMQProperties` (p. 480).

6.196.3.7 `virtual bool cms::CMSProperties::isEmpty () const` [pure virtual]

Returns true if the properties object is empty.

Returns:

true if empty

Implemented in `activemq::util::ActiveMQProperties` (p. 481).

6.196.3.8 `virtual void cms::CMSProperties::remove (const std::string & name)` [pure virtual]

Removes the property with the given name.

Parameters:

name the name of the property to be removed.s

Implemented in `activemq::util::ActiveMQProperties` (p. 481).

6.196.3.9 `virtual void cms::CMSProperties::setProperty (const std::string & name,
const std::string & value) [pure virtual]`

Sets the value for a given property. If the property already exists, overwrites the value.

Parameters:

name The name of the value to be written.

value The value to be written.

Implemented in `activemq::util::ActiveMQProperties` (p. 481).

6.196.3.10 `virtual std::vector< std::pair< std::string, std::string > >
cms::CMSProperties::toArray () const [pure virtual]`

Method that serializes the contents of the property map to an array.

Returns:

list of pairs where the first is the name and the second is the value.

Implemented in `activemq::util::ActiveMQProperties` (p. 481).

6.196.3.11 `virtual std::string cms::CMSProperties::toString () const [pure
virtual]`

Formats the contents of the Properties Object into a string that can be logged, etc.

Returns:

string value of this object.

Implemented in `activemq::util::ActiveMQProperties` (p. 481).

The documentation for this class was generated from the following file:

- `src/main/cms/CMSProperties.h`

6.197 cms::CMSSecurityException Class Reference

This exception must be thrown when a provider rejects a user name/password submitted by a client.

#include <src/main/cms/CMSSecurityException.h> Inheritance diagram for cms::CMSSecurityException:

Public Member Functions

- **CMSSecurityException** () throw ()
- **CMSSecurityException** (const **CMSSecurityException** &ex) throw ()
- **CMSSecurityException** (const std::string &message, const std::exception *cause) throw ()
- **CMSSecurityException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**CMSSecurityException** () throw ()

6.197.1 Detailed Description

This exception must be thrown when a provider rejects a user name/password submitted by a client. It may also be thrown for any case where a security restriction prevents a method from completing.

Since:

1.3

6.197.2 Constructor & Destructor Documentation

6.197.2.1 cms::CMSSecurityException::CMSSecurityException () throw ()

6.197.2.2 cms::CMSSecurityException::CMSSecurityException (const CMSSecurityException & ex) throw ()

6.197.2.3 cms::CMSSecurityException::CMSSecurityException (const std::string & message, const std::exception * cause) throw ()

6.197.2.4 cms::CMSSecurityException::CMSSecurityException (const std::string & message, const std::exception * cause, const std::vector< std::pair< std::string, int > > & stackTrace) throw ()

6.197.2.5 virtual cms::CMSSecurityException::~CMSSecurityException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/CMSSecurityException.h

6.198 activemq::cmsutil::CmsTemplate Class Reference

CmsTemplate (p. 1170) simplifies performing synchronous CMS operations.

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate:

Data Structures

- class **ProducerExecutor**
- class **ReceiveExecutor**
- class **ResolveProducerExecutor**
- class **ResolveReceiveExecutor**
- class **SendExecutor**

Public Member Functions

- **CmsTemplate** ()
- **CmsTemplate** (cms::ConnectionFactory *connectionFactory)
- virtual ~**CmsTemplate** ()
- virtual void **setDefaultDestination** (cms::Destination *defaultDestination)
Sets the destination object to be used by default for send/receive operations.
- virtual const cms::Destination * **getDefaultDestination** () const
Retrieves the default destination to be used for send/receive operations.
- virtual cms::Destination * **getDefaultDestination** ()
Retrieves the default destination to be used for send/receive operations.
- virtual void **setDefaultDestinationName** (const std::string &defaultDestinationName)
Sets the name of the default destination to be used from send/receive operations.
- virtual const std::string **getDefaultDestinationName** () const
Gets the name of the default destination to be used for send/receive operations.
- virtual void **setPubSubDomain** (bool pubSubDomain)
Indicates whether the default destination is a topic (true) or a queue (false).
- virtual void **setMessageIdEnabled** (bool messageIdEnabled)
- virtual bool **isMessageIdEnabled** () const
- virtual void **setMessageTimestampEnabled** (bool messageTimestampEnabled)
- virtual bool **isMessageTimestampEnabled** () const
- virtual void **setNoLocal** (bool noLocal)
- virtual bool **isNoLocal** () const
- virtual void **setReceiveTimeout** (long long receiveTimeout)
- virtual long long **getReceiveTimeout** () const
- virtual void **setExplicitQosEnabled** (bool explicitQosEnabled)
Set if the QOS values (deliveryMode, priority, timeToLive) should be used for sending a message.

- virtual bool **isExplicitQosEnabled** () const
If "true", then the values of deliveryMode, priority, and timeToLive will be used when sending a message.
- virtual void **setDeliveryPersistent** (bool deliveryPersistent)
Set whether message delivery should be persistent or non-persistent, specified as boolean value ("true" or "false").
- virtual void **setDeliveryMode** (int deliveryMode)
Set the delivery mode to use when sending a message.
- virtual int **getDeliveryMode** () const
Return the delivery mode to use when sending a message.
- virtual void **setPriority** (int priority)
Set the priority of a message when sending.
- virtual int **getPriority** () const
Return the priority of a message when sending.
- virtual void **setTimeToLive** (long long timeToLive)
Set the time-to-live of the message when sending.
- virtual long long **getTimeToLive** () const
Return the time-to-live of the message when sending.
- virtual void **execute** (SessionCallback *action) throw (cms::CMSEException)
Executes the given action within a CMS Session.
- virtual void **execute** (ProducerCallback *action) throw (cms::CMSEException)
Executes the given action and provides it with a CMS Session and producer.
- virtual void **execute** (cms::Destination *dest, ProducerCallback *action) throw (cms::CMSEException)
Executes the given action and provides it with a CMS Session and producer.
- virtual void **execute** (const std::string &destinationName, ProducerCallback *action) throw (cms::CMSEException)
Executes the given action and provides it with a CMS Session and producer.
- virtual void **send** (MessageCreator *messageCreator) throw (cms::CMSEException)
Convenience method for sending a message to the default destination.
- virtual void **send** (cms::Destination *dest, MessageCreator *messageCreator) throw (cms::CMSEException)
Convenience method for sending a message to the specified destination.
- virtual void **send** (const std::string &destinationName, MessageCreator *messageCreator) throw (cms::CMSEException)

Convenience method for sending a message to the specified destination.

- virtual **cms::Message * receive** () throw (cms::CMSEException)
Performs a synchronous read from the default destination.
- virtual **cms::Message * receive** (cms::Destination *destination) throw (cms::CMSEException)
Performs a synchronous read from the specified destination.
- virtual **cms::Message * receive** (const std::string &destinationName) throw (cms::CMSEException)
Performs a synchronous read from the specified destination.
- virtual **cms::Message * receiveSelected** (const std::string &selector) throw (cms::CMSEException)
Performs a synchronous read consuming only messages identified by the given selector.
- virtual **cms::Message * receiveSelected** (cms::Destination *destination, const std::string &selector) throw (cms::CMSEException)
Performs a synchronous read from the specified destination, consuming only messages identified by the given selector.
- virtual **cms::Message * receiveSelected** (const std::string &destinationName, const std::string &selector) throw (cms::CMSEException)
Performs a synchronous read from the specified destination, consuming only messages identified by the given selector.

Static Public Attributes

- static const long long **RECEIVE_TIMEOUT_NO_WAIT**
Timeout value indicating that a receive operation should check if a message is immediately available without blocking.
- static const long long **RECEIVE_TIMEOUT_INDEFINITE_WAIT**
Timeout value indicating a blocking receive without timeout.
- static const int **DEFAULT_PRIORITY**
Default message priority.
- static const long long **DEFAULT_TIME_TO_LIVE**
My default, messages should live forever.

Protected Member Functions

- **CmsTemplate** (const **CmsTemplate** &)
- **CmsTemplate & operator=** (const **CmsTemplate** &)
- void **init** () throw (cms::CMSEException, decaf::lang::exceptions::IllegalStateException)
Initializes this object and prepares it for use.

- void **destroy** () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)

Clears all internal resources.

Friends

- class **ProducerExecutor**
- class **ResolveProducerExecutor**
- class **SendExecutor**
- class **ReceiveExecutor**
- class **ResolveReceiveExecutor**

6.198.1 Detailed Description

CmsTemplate (p. 1170) simplifies performing synchronous CMS operations. This class is intended to be for CMS what Spring's **JmsTemplate** is for JMS. Provided with a **CMS ConnectionFactory**, creates and manages all other CMS resources internally.

Before using **CmsTemplate** (p. 1170) the user must first set the destination (either by name or by setting the destination object directly) and then call **init** to initialize the object for use.

CmsTemplate (p. 1170) allows the user to get access to a **CMS Session** through a user-defined **SessionCallback** (p. 3378). Similarly, if the user wants direct access to a **CMS MessageProducer**, it can provide a **ProducerCallback** (p. 3064). As a convenience, the user can bypass having to provide callbacks altogether for sending messages, by calling one of the **send** methods.

See also:

SessionCallback (p. 3378)
ProducerCallback (p. 3064)
MessageCreator (p. 2593)

6.198.2 Constructor & Destructor Documentation

6.198.2.1 `activemq::cmsutil::CmsTemplate::CmsTemplate (const CmsTemplate &)`
[inline, protected]

6.198.2.2 `activemq::cmsutil::CmsTemplate::CmsTemplate ()`

6.198.2.3 `activemq::cmsutil::CmsTemplate::CmsTemplate (cms::ConnectionFactory * connectionFactory)`

6.198.2.4 `virtual activemq::cmsutil::CmsTemplate::~~CmsTemplate ()` [virtual]

6.198.3 Member Function Documentation

6.198.3.1 `void activemq::cmsutil::CmsTemplate::destroy () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
[protected, virtual]

Clears all internal resources.

Reimplemented from `activemq::cmsutil::CmsDestinationAccessor` (p. 1158).

6.198.3.2 `virtual void activemq::cmsutil::CmsTemplate::execute (const std::string & destinationName, ProducerCallback * action) throw (cms::CMSException)` [virtual]

Executes the given action and provides it with a CMS Session and producer.

Parameters:

destinationName the name of the destination to send messages to (to internally be resolved to an actual destination)

action the action to perform

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.3 `virtual void activemq::cmsutil::CmsTemplate::execute (cms::Destination * dest, ProducerCallback * action) throw (cms::CMSException)`
[virtual]

Executes the given action and provides it with a CMS Session and producer.

Parameters:

dest the destination to send messages to

action the action to perform

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.4 **virtual void activemq::cmsutil::CmsTemplate::execute (ProducerCallback * *action*) throw (cms::CMSException) [virtual]**

Executes the given action and provides it with a CMS Session and producer.

Parameters:

action the action to perform

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.5 **virtual void activemq::cmsutil::CmsTemplate::execute (SessionCallback * *action*) throw (cms::CMSException) [virtual]**

Executes the given action within a CMS Session.

Parameters:

action the action to perform within a CMS Session

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.6 **virtual cms::Destination* activemq::cmsutil::CmsTemplate::getDefaultDestination () [inline, virtual]**

Retrieves the default destination to be used for send/receive operations.

Returns:

the default destination. Non-const version of this method.

6.198.3.7 **virtual const cms::Destination* activemq::cmsutil::CmsTemplate::getDefaultDestination () const [inline, virtual]**

Retrieves the default destination to be used for send/receive operations.

Returns:

the default destination. Const version of this method.

6.198.3.8 **virtual const std::string activemq::cmsutil::CmsTemplate::getDefaultDestinationName () const [inline, virtual]**

Gets the name of the default destination to be used for send/receive operations. The destination type (topic/queue) is determined by the `pubSubDomain` property.

Returns:

the default name of the destination for send/receive operations.

6.198.3.9 `virtual int activemq::cmsutil::CmsTemplate::getDeliveryMode () const`
[inline, virtual]

Return the delivery mode to use when sending a message.

6.198.3.10 `virtual int activemq::cmsutil::CmsTemplate::getPriority () const`
[inline, virtual]

Return the priority of a message when sending.

6.198.3.11 `virtual long long activemq::cmsutil::CmsTemplate::getReceiveTimeout () const` [inline, virtual]

6.198.3.12 `virtual long long activemq::cmsutil::CmsTemplate::getTimeToLive () const` [inline, virtual]

Return the time-to-live of the message when sending.

6.198.3.13 `void activemq::cmsutil::CmsTemplate::init () throw (cms::CMSException, decaf::lang::exceptions::IllegalStateException)`
[protected, virtual]

Initializes this object and prepares it for use. This should be called before any other methods are called.

Reimplemented from `activemq::cmsutil::CmsDestinationAccessor` (p. 1158).

6.198.3.14 `virtual bool activemq::cmsutil::CmsTemplate::isExplicitQosEnabled () const` [inline, virtual]

If "true", then the values of deliveryMode, priority, and timeToLive will be used when sending a message. Otherwise, the default values, that may be set administratively, will be used.

Returns:

true if overriding default values of QOS parameters (deliveryMode, priority, and timeToLive)

See also:

`setDeliveryMode` (p. 1180)
`setPriority` (p. 1181)
`setTimeToLive` (p. 1181)

6.198.3.15 `virtual bool activemq::cmsutil::CmsTemplate::isMessageIdEnabled () const [inline, virtual]`

6.198.3.16 `virtual bool activemq::cmsutil::CmsTemplate::isMessageTimestampEnabled () const [inline, virtual]`

6.198.3.17 `virtual bool activemq::cmsutil::CmsTemplate::isNoLocal () const [inline, virtual]`

6.198.3.18 `CmsTemplate& activemq::cmsutil::CmsTemplate::operator= (const CmsTemplate &) [inline, protected]`

Reimplemented from `activemq::cmsutil::CmsDestinationAccessor` (p. 1159).

6.198.3.19 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receive (const std::string & destinationName) throw (cms::CMSException) [virtual]`

Performs a synchronous read from the specified destination.

Parameters:

destinationName the name of the destination to receive on (will be resolved to destination internally).

Returns:

the message

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs

6.198.3.20 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receive (cms::Destination * destination) throw (cms::CMSException) [virtual]`

Performs a synchronous read from the specified destination.

Parameters:

destination the destination to receive on

Returns:

the message

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs

6.198.3.21 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receive () throw (cms::CMSEException) [virtual]`

Performs a synchronous read from the default destination.

Returns:

the message

Exceptions:

cms::CMSEException (p. 1160) thrown if an error occurs

6.198.3.22 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receiveSelected (const std::string & destinationName, const std::string & selector) throw (cms::CMSEException) [virtual]`

Performs a synchronous read from the specified destination, consuming only messages identified by the given selector.

Parameters:

destinationName the name of the destination to receive on (will be resolved to destination internally).

selector the selector expression.

Returns:

the message

Exceptions:

cms::CMSEException (p. 1160) thrown if an error occurs

6.198.3.23 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receiveSelected (cms::Destination * destination, const std::string & selector) throw (cms::CMSEException) [virtual]`

Performs a synchronous read from the specified destination, consuming only messages identified by the given selector.

Parameters:

destination the destination to receive on.

selector the selector expression.

Returns:

the message

Exceptions:

cms::CMSEException (p. 1160) thrown if an error occurs

6.198.3.24 `virtual cms::Message* activemq::cmsutil::CmsTemplate::receiveSelected (const std::string & selector) throw (cms::CMSException) [virtual]`

Performs a synchronous read consuming only messages identified by the given selector.

Parameters:

selector the selector expression.

Returns:

the message

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs

6.198.3.25 `virtual void activemq::cmsutil::CmsTemplate::send (const std::string & destinationName, MessageCreator * messageCreator) throw (cms::CMSException) [virtual]`

Convenience method for sending a message to the specified destination.

Parameters:

destinationName The name of the destination to send to.

messageCreator Responsible for creating the message to be sent

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.26 `virtual void activemq::cmsutil::CmsTemplate::send (cms::Destination * dest, MessageCreator * messageCreator) throw (cms::CMSException) [virtual]`

Convenience method for sending a message to the specified destination.

Parameters:

dest The destination to send to

messageCreator Responsible for creating the message to be sent

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.27 `virtual void activemq::cmsutil::CmsTemplate::send (MessageCreator * messageCreator) throw (cms::CMSException) [virtual]`

Convenience method for sending a message to the default destination.

Parameters:

messageCreator Responsible for creating the message to be sent

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.198.3.28 virtual void activemq::cmsutil::CmsTemplate::setDefaultDestination (cms::Destination * *defaultDestination*) [inline, virtual]

Sets the destination object to be used by default for send/receive operations. If no default destination is provided, the `defaultDestinationName` property is used to resolve this default destination for send/receive operations.

Parameters:

defaultDestination the default destination

6.198.3.29 virtual void activemq::cmsutil::CmsTemplate::setDefaultDestinationName (const std::string & *defaultDestinationName*) [inline, virtual]

Sets the name of the default destination to be used from send/receive operations. Calling this method will set the `defaultDestination` property to NULL. The destination type (topic/queue) is determined by the `pubSubDomain` property.

Parameters:

defaultDestinationName the name of the destination for send/receive to by default.

6.198.3.30 virtual void activemq::cmsutil::CmsTemplate::setDeliveryMode (int *deliveryMode*) [inline, virtual]

Set the delivery mode to use when sending a message. Default is the Message default: "PERSISTENT".

Since a default value may be defined administratively, this is only used when "isExplicitQosEnabled" equals "true".

Parameters:

deliveryMode the delivery mode to use

See also:

`isExplicitQosEnabled` (p. 1176)

6.198.3.31 **virtual void activemq::cmsutil::CmsTemplate::setDeliveryPersistent**
(bool *deliveryPersistent*) [inline, virtual]

Set whether message delivery should be persistent or non-persistent, specified as boolean value ("true" or "false"). This will set the delivery mode accordingly, to either "PERSISTENT" or "NON_PERSISTENT".

Default it "true" aka delivery mode "PERSISTENT".

See also:

setDeliveryMode(int) (p. 1180)

6.198.3.32 **virtual void activemq::cmsutil::CmsTemplate::setExplicitQosEnabled**
(bool *explicitQosEnabled*) [inline, virtual]

Set if the QOS values (deliveryMode, priority, timeToLive) should be used for sending a message.

See also:

setDeliveryMode (p. 1180)

setPriority (p. 1181)

setTimeToLive (p. 1181)

6.198.3.33 **virtual void activemq::cmsutil::CmsTemplate::setMessageIdEnabled**
(bool *messageIdEnabled*) [inline, virtual]

6.198.3.34 **virtual void activemq::cmsutil::CmsTemplate::setMessageTimestampEnabled** (bool
messageTimestampEnabled) [inline, virtual]

6.198.3.35 **virtual void activemq::cmsutil::CmsTemplate::setNoLocal** (bool *noLocal*)
[inline, virtual]

6.198.3.36 **virtual void activemq::cmsutil::CmsTemplate::setPriority** (int *priority*)
[inline, virtual]

Set the priority of a message when sending. Since a default value may be defined administratively, this is only used when "isExplicitQosEnabled" equals "true".

See also:

isExplicitQosEnabled (p. 1176)

6.198.3.37 **virtual void activemq::cmsutil::CmsTemplate::setPubSubDomain** (bool
pubSubDomain) [inline, virtual]

Indicates whether the default destination is a topic (true) or a queue (false). Calling this method will set the defaultDestination property to NULL.

Parameters:

pubSubDomain indicates whether to use pub-sub messaging (topics).

Reimplemented from **activemq::cmsutil::CmsDestinationAccessor** (p. 1159).

References **activemq::cmsutil::CmsDestinationAccessor::setPubSubDomain()**.

6.198.3.38 **virtual void activemq::cmsutil::CmsTemplate::setReceiveTimeout** (long long *receiveTimeout*) [inline, virtual]

6.198.3.39 **virtual void activemq::cmsutil::CmsTemplate::setTimeToLive** (long long *timeToLive*) [inline, virtual]

Set the time-to-live of the message when sending. Since a default value may be defined administratively, this is only used when "isExplicitQosEnabled" equals "true".

Parameters:

timeToLive the message's lifetime (in milliseconds)

See also:

isExplicitQosEnabled (p. 1176)

6.198.4 Friends And Related Function Documentation

6.198.4.1 friend class **ProducerExecutor** [friend]

6.198.4.2 friend class **ReceiveExecutor** [friend]

6.198.4.3 friend class **ResolveProducerExecutor** [friend]

6.198.4.4 friend class **ResolveReceiveExecutor** [friend]

6.198.4.5 friend class **SendExecutor** [friend]

6.198.5 Field Documentation

6.198.5.1 **const int activemq::cmsutil::CmsTemplate::DEFAULT_PRIORITY** [static]

Default message priority.

6.198.5.2 **const long long activemq::cmsutil::CmsTemplate::DEFAULT_TIME_TO_LIVE** [static]

My default, messages should live forever.

6.198.5.3 **const long long activemq::cmsutil::CmsTemplate::RECEIVE_TIMEOUT_INDEFINITE_WAIT** [static]

Timeout value indicating a blocking receive without timeout.

6.198.5.4 `const long long activemq::cmsutil::CmsTemplate::RECEIVE_ - TIMEOUT_NO_WAIT [static]`

Timeout value indicating that a receive operation should check if a message is immediately available without blocking.

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsTemplate.h`

6.199 code Struct Reference

```
#include <src/main/decaf/internal/util/zip/inftrees.h>
```

Data Fields

- unsigned char **op**
- unsigned char **bits**
- unsigned short **val**

6.199.1 Field Documentation

6.199.1.1 unsigned char code::bits

6.199.1.2 unsigned char code::op

6.199.1.3 unsigned short code::val

The documentation for this struct was generated from the following file:

- `src/main/decaf/internal/util/zip/inftrees.h`

6.200 decaf::util::Collection< E > Class Template Reference

The root interface in the collection hierarchy.

```
#include <src/main/decaf/util/Collection.h>Inheritance          diagram          for
decaf::util::Collection< E >:
```

Public Member Functions

- virtual **~Collection** ()
- virtual bool **add** (const E &value)=0 throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Returns true if this collection changed as a result of the call.
- virtual bool **addAll** (const **Collection**< E > &collection)=0 throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Adds all of the elements in the specified collection to this collection.
- virtual void **clear** ()=0 throw (lang::exceptions::UnsupportedOperationException)
Removes all of the elements from this collection (optional operation).
- virtual bool **contains** (const E &value) const =0 throw (lang::Exception)
Returns true if this collection contains the specified element.
- virtual bool **containsAll** (const **Collection**< E > &collection) const =0 throw (lang::Exception)
Returns true if this collection contains all of the elements in the specified collection.
- virtual bool **equals** (const **Collection**< E > &value) const =0
Compares the passed collection to this one, if they contain the same elements, i.e.
- virtual bool **isEmpty** () const =0
- virtual bool **remove** (const E &value)=0 throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes a single instance of the specified element from the collection.
- virtual bool **removeAll** (const **Collection**< E > &collection)=0 throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes all this collection's elements that are also contained in the specified collection (optional operation).
- virtual bool **retainAll** (const **Collection**< E > &collection)=0 throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Retains only the elements in this collection that are contained in the specified collection (optional operation).

- virtual std::size_t **size** () const =0

Returns the number of elements in this collection.

- virtual std::vector< E > **toArray** () const =0

Returns an array containing all of the elements in this collection.

6.200.1 Detailed Description

template<typename E> class decaf::util::Collection< E >

The root interface in the collection hierarchy. A collection represents a group of objects, known as its elements. Some collections allow duplicate elements and others do not. Some are ordered and others unordered. This interface is typically used to pass collections around and manipulate them where maximum generality is desired.

All general-purpose **Collection** (p. 1184) implementation classes (which typically implement **Collection** (p. 1184) indirectly through one of its subinterfaces) should provide two "standard" constructors: a void (no arguments) constructor, which creates an empty collection, and a constructor with a single argument of type **Collection** (p. 1184), which creates a new collection with the same elements as its argument. In effect, the latter constructor allows the user to copy any collection, producing an equivalent collection of the desired implementation type. There is no way to enforce this convention (as interfaces cannot contain constructors) but all of the general-purpose **Collection** (p. 1184) implementations in the Decaf platform libraries comply.

The "destructive" methods contained in this interface, that is, the methods that modify the collection on which they operate, are specified to throw UnsupportedOperationException if this collection does not support the operation. If this is the case, these methods may, but are not required to, throw an UnsupportedOperationException if the invocation would have no effect on the collection. For example, invoking the addAll(Collection) method on an unmodifiable collection may, but is not required to, throw the exception if the collection to be added is empty.

Many methods in Collections Framework interfaces are defined in terms of the equals method. For example, the specification for the contains(Object o) method says: returns true if and only if this collection contains at least one element e such that (o==null ? e==null : o.equals(e)).

Since:

1.0

6.200.2 Constructor & Destructor Documentation

6.200.2.1 `template<typename E> virtual decaf::util::Collection< E >::~~Collection
() [inline, virtual]`

6.200.3 Member Function Documentation

6.200.3.1 `template<typename E> virtual bool decaf::util::Collection<
E >::add (const E & value) throw (
lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException,
lang::exceptions::IllegalStateException) [pure
virtual]`

Returns true if this collection changed as a result of the call. (Returns false if this collection does not permit duplicates and already contains the specified element.)

Collections that support this operation may place limitations on what elements may be added to this collection. In particular, some collections will refuse to add null elements, and others will impose restrictions on the type of elements that may be added. **Collection** (p.1184) classes should clearly specify in their documentation any restrictions on what elements may be added.

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

For non-pointer values, i.e. class instances or string's the object will be copied into the collection, thus the object must support being copied, must not hide the copy constructor and assignment operator.

Parameters:

value - reference to the element to add.

Returns:

true if the element was added

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

Implemented in `decaf::util::AbstractQueue< E >` (p.195), `decaf::util::PriorityQueue< E >` (p.3031), `decaf::util::StlList< E >` (p.3594), `decaf::util::StlSet< E >` (p.3625), `decaf::util::StlList< cms::MessageConsumer * >` (p.3594), `decaf::util::StlList< CompositeTask * >` (p.3594), `decaf::util::StlList< URI >` (p.3594), `decaf::util::StlList< Pointer< DestinationInfo > >` (p.3594), `decaf::util::StlList< PrimitiveValueNode >` (p.3594), `decaf::util::StlList< Pointer< Command > >` (p.3594), `decaf::util::StlList< Pointer< BackupTransport > >` (p.3594), `decaf::util::StlList< cms::MessageProducer * >` (p.3594), `decaf::util::StlList< cms::Destination * >` (p.3594), `decaf::util::StlList< cms::Session * >` (p.3594), `decaf::util::StlList< cms::Connection * >` (p.3594), `decaf::util::StlSet< transport::TransportListener * >` (p.3625), `decaf::util::StlSet< Pointer< Synchronization > >` (p.3625), `decaf::util::StlSet< Resource * >` (p.3625), and `decaf::util::StlSet< ActiveMQSession * >` (p.3625).

```

6.200.3.2  template<typename E> virtual bool decaf::util::Collection<
           E >::addAll (const Collection< E > & collection) throw
           ( lang::exceptions::UnsupportedOperationException,
           lang::exceptions::IllegalArgumentException,
           lang::exceptions::IllegalStateException ) [pure
           virtual]

```

Adds all of the elements in the specified collection to this collection. The behavior of this operation is undefined if the specified collection is modified while the operation is in progress. (This implies that the behavior of this call is undefined if the specified collection is this collection, and this collection is nonempty.)

Parameters:

collection - **Collection** (p. 1184) whose elements are added to this one.

Returns:

true if this collection changed as a result of the call

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

```

6.200.3.3  template<typename E> virtual void decaf::util::Collection< E >::clear
           () throw ( lang::exceptions::UnsupportedOperationException ) [pure
           virtual]

```

Removes all of the elements from this collection (optional operation). This collection will be empty after this method returns unless it throws an exception.

Exceptions:

UnsupportedOperationException

Implemented in **decaf::util::AbstractCollection< E >** (p. 183), **decaf::util::AbstractQueue< E >** (p. 196), **decaf::util::concurrent::SynchronousQueue< E >** (p. 3718), **decaf::util::PriorityQueue< E >** (p. 3031), **decaf::util::StlList< E >** (p. 3596), **decaf::util::StlSet< E >** (p. 3626), **decaf::util::AbstractCollection< transport::TransportListener * >** (p. 183), **decaf::util::AbstractCollection< Pointer< Synchronization > >** (p. 183), **decaf::util::AbstractCollection< Resource * >** (p. 183), **decaf::util::AbstractCollection< cms::MessageConsumer * >** (p. 183), **decaf::util::AbstractCollection< CompositeTask * >** (p. 183), **decaf::util::AbstractCollection< URI >** (p. 183), **decaf::util::AbstractCollection< ActiveMQSession * >** (p. 183), **decaf::util::AbstractCollection< Pointer< DestinationInfo > >** (p. 183), **decaf::util::AbstractCollection< PrimitiveValueNode >** (p. 183), **decaf::util::AbstractCollection< Pointer< Command > >** (p. 183), **decaf::util::AbstractCollection< Pointer< BackupTransport > >** (p. 183), **decaf::util::AbstractCollection< cms::MessageProducer * >** (p. 183), **decaf::util::AbstractCollection< cms::Destination * >**

(p. 183), `decaf::util::AbstractCollection< cms::Session * >` (p. 183), `decaf::util::AbstractCollection< cms::Connection * >` (p. 183), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3596), `decaf::util::StlList< CompositeTask * >` (p. 3596), `decaf::util::StlList< URI >` (p. 3596), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3596), `decaf::util::StlList< PrimitiveValueNode >` (p. 3596), `decaf::util::StlList< Pointer< Command > >` (p. 3596), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3596), `decaf::util::StlList< cms::MessageProducer * >` (p. 3596), `decaf::util::StlList< cms::Destination * >` (p. 3596), `decaf::util::StlList< cms::Session * >` (p. 3596), `decaf::util::StlList< cms::Connection * >` (p. 3596), `decaf::util::StlSet< transport::TransportListener * >` (p. 3626), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3626), `decaf::util::StlSet< Resource * >` (p. 3626), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3626).

6.200.3.4 `template<typename E> virtual bool decaf::util::Collection< E >::contains (const E & value) const throw (lang::Exception) [pure virtual]`

Returns true if this collection contains the specified element. More formally, returns true if and only if this collection contains at least one element *e* such that (*o*==null ? *e*==null : *o*.equals(*e*)).

Parameters:

value - value to check for presence in the collection

Returns:

true if there is at least one of the elements in the collection

Exceptions:

Exception

Implemented in `decaf::util::AbstractCollection< E >` (p. 184), `decaf::util::StlList< E >` (p. 3596), `decaf::util::StlSet< E >` (p. 3627), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 184), `decaf::util::AbstractCollection< Pointer< Synchronization > >` (p. 184), `decaf::util::AbstractCollection< Resource * >` (p. 184), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 184), `decaf::util::AbstractCollection< CompositeTask * >` (p. 184), `decaf::util::AbstractCollection< URI >` (p. 184), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 184), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 184), `decaf::util::AbstractCollection< PrimitiveValueNode >` (p. 184), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 184), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 184), `decaf::util::AbstractCollection< cms::MessageProducer * >` (p. 184), `decaf::util::AbstractCollection< cms::Destination * >` (p. 184), `decaf::util::AbstractCollection< cms::Session * >` (p. 184), `decaf::util::AbstractCollection< cms::Connection * >` (p. 184), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3596), `decaf::util::StlList< CompositeTask * >` (p. 3596), `decaf::util::StlList< URI >` (p. 3596), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3596), `decaf::util::StlList< PrimitiveValueNode >` (p. 3596), `decaf::util::StlList< Pointer< Command > >` (p. 3596), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3596), `decaf::util::StlList< cms::MessageProducer * >` (p. 3596), `decaf::util::StlList< cms::Destination * >` (p. 3596), `decaf::util::StlList< cms::Session * >` (p. 3596), `decaf::util::StlList< cms::Connection * >` (p. 3596), `decaf::util::StlSet< transport::TransportListener * >` (p. 3627), `decaf::util::StlSet<`

Pointer< Synchronization > > (p. 3627), **decaf::util::StlSet< Resource * >** (p. 3627), and **decaf::util::StlSet< ActiveMQSession * >** (p. 3627).

6.200.3.5 `template<typename E> virtual bool decaf::util::Collection< E >::containsAll (const Collection< E > & collection) const throw (lang::Exception) [pure virtual]`

Returns true if this collection contains all of the elements in the specified collection.

Parameters:

collection - **Collection** (p. 1184) to compare to this one.

Exceptions:

Exception

6.200.3.6 `template<typename E> virtual bool decaf::util::Collection< E >::equals (const Collection< E > & value) const [pure virtual]`

Compares the passed collection to this one, if they contain the same elements, i.e. all their elements are equivalent, then it returns true.

Returns:

true if the Collections contain the same elements.

Implemented in **decaf::util::StlList< E >** (p. 3597), and **decaf::util::StlSet< E >** (p. 3627).

6.200.3.7 `template<typename E> virtual bool decaf::util::Collection< E >::isEmpty () const [pure virtual]`

Returns:

true if this collection contains no elements.

Implemented in **decaf::util::AbstractCollection< E >** (p. 186), **decaf::util::concurrent::SynchronousQueue< E >** (p. 3721), **decaf::util::StlList< E >** (p. 3598), **decaf::util::StlSet< E >** (p. 3627), **decaf::util::AbstractCollection< transport::TransportListener * >** (p. 186), **decaf::util::AbstractCollection< Pointer< Synchronization > >** (p. 186), **decaf::util::AbstractCollection< Resource * >** (p. 186), **decaf::util::AbstractCollection< cms::MessageConsumer * >** (p. 186), **decaf::util::AbstractCollection< CompositeTask * >** (p. 186), **decaf::util::AbstractCollection< URI >** (p. 186), **decaf::util::AbstractCollection< ActiveMQSession * >** (p. 186), **decaf::util::AbstractCollection< Pointer< DestinationInfo > >** (p. 186), **decaf::util::AbstractCollection< PrimitiveValueNode >** (p. 186), **decaf::util::AbstractCollection< Pointer< Command > >** (p. 186), **decaf::util::AbstractCollection< Pointer< BackupTransport > >** (p. 186), **decaf::util::AbstractCollection< cms::MessageProducer * >** (p. 186), **decaf::util::AbstractCollection< cms::Destination * >** (p. 186), **decaf::util::AbstractCollection< cms::Session * >** (p. 186), **decaf::util::AbstractCollection< cms::Connection * >** (p. 186), **decaf::util::StlList<**

`cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), `decaf::util::StlList< cms::Connection * >` (p. 3598), `decaf::util::StlSet< transport::TransportListener * >` (p. 3627), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3627), `decaf::util::StlSet< Resource * >` (p. 3627), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3627).

6.200.3.8 `template<typename E> virtual bool decaf::util::Collection< E >::remove (const E & value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException) [pure virtual]`

Removes a single instance of the specified element from the collection. More formally, removes an element *e* such that (`o==null ? e==null : o.equals(e)`), if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

Parameters:

value - reference to the element to remove.

Returns:

true if the collection was changed

Exceptions:

UnsupportedOperationException

IllegalArgumentException

Implemented in `decaf::util::AbstractCollection< E >` (p. 187), `decaf::util::PriorityQueue< E >` (p. 3034), `decaf::util::StlList< E >` (p. 3600), `decaf::util::StlSet< E >` (p. 3628), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 187), `decaf::util::AbstractCollection< Pointer< Synchronization > >` (p. 187), `decaf::util::AbstractCollection< Resource * >` (p. 187), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 187), `decaf::util::AbstractCollection< CompositeTask * >` (p. 187), `decaf::util::AbstractCollection< URI >` (p. 187), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 187), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 187), `decaf::util::AbstractCollection< PrimitiveValueNode >` (p. 187), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 187), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 187), `decaf::util::AbstractCollection< cms::MessageProducer * >` (p. 187), `decaf::util::AbstractCollection< cms::Destination * >` (p. 187), `decaf::util::AbstractCollection< cms::Session * >` (p. 187), `decaf::util::AbstractCollection< cms::Connection * >` (p. 187), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3600), `decaf::util::StlList< CompositeTask * >` (p. 3600), `decaf::util::StlList< URI >` (p. 3600), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3600), `decaf::util::StlList< PrimitiveValueNode >` (p. 3600), `decaf::util::StlList< Pointer< Command > >` (p. 3600), `decaf::util::StlList< Pointer<`

BackupTransport > > (p. 3600), decaf::util::StlList< cms::MessageProducer * > (p. 3600), decaf::util::StlList< cms::Destination * > (p. 3600), decaf::util::StlList< cms::Session * > (p. 3600), decaf::util::StlList< cms::Connection * > (p. 3600), decaf::util::StlSet< transport::TransportListener * > (p. 3628), decaf::util::StlSet< Pointer< Synchronization > > (p. 3628), decaf::util::StlSet< Resource * > (p. 3628), and decaf::util::StlSet< ActiveMQSession * > (p. 3628).

6.200.3.9 template<typename E> virtual bool decaf::util::Collection< E >::removeAll (const Collection< E > & *collection*)
 throw (lang::exceptions::UnsupportedOperationException,
 lang::exceptions::IllegalArgumentException) [pure virtual]

Removes all this collection's elements that are also contained in the specified collection (optional operation). After this call returns, this collection will contain no elements in common with the specified collection.

Parameters:

collection - The **Collection** (p. 1184) whose elements are to be removed

Returns:

true if the collection changed as a result of this call

Exceptions:

UnsupportedOperationException

IllegalArgumentException

6.200.3.10 template<typename E> virtual bool decaf::util::Collection< E >::retainAll (const Collection< E > & *collection*)
 throw (lang::exceptions::UnsupportedOperationException,
 lang::exceptions::IllegalArgumentException) [pure virtual]

Retains only the elements in this collection that are contained in the specified collection (optional operation). In other words, removes from this collection all of its elements that are not contained in the specified collection.

Parameters:

collection - The **Collection** (p. 1184) whose elements are to be retained

Returns:

true if the collection changed as a result of this call

Exceptions:

UnsupportedOperationException

IllegalArgumentException

6.200.3.11 `template<typename E> virtual std::size_t decaf::util::Collection< E >::size () const [pure virtual]`

Returns the number of elements in this collection. If this collection contains more than Integer.MAX_VALUE elements, returns Integer.MAX_VALUE.

Returns:

the number of elements in this collection

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3724), `decaf::util::PriorityQueue< E >` (p. 3034), `decaf::util::StlList< E >` (p. 3601), `decaf::util::StlSet< E >` (p. 3628), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3601), `decaf::util::StlList< CompositeTask * >` (p. 3601), `decaf::util::StlList< URI >` (p. 3601), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3601), `decaf::util::StlList< PrimitiveValueNode >` (p. 3601), `decaf::util::StlList< Pointer< Command > >` (p. 3601), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3601), `decaf::util::StlList< cms::MessageProducer * >` (p. 3601), `decaf::util::StlList< cms::Destination * >` (p. 3601), `decaf::util::StlList< cms::Session * >` (p. 3601), `decaf::util::StlList< cms::Connection * >` (p. 3601), `decaf::util::StlSet< transport::TransportListener * >` (p. 3628), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3628), `decaf::util::StlSet< Resource * >` (p. 3628), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3628).

Referenced by `decaf::util::AbstractCollection< cms::Connection * >::equals()`, `decaf::util::AbstractCollection< cms::Connection * >::isEmpty()`, `decaf::util::AbstractSet< ActiveMQSession * >::removeAll()`, and `decaf::util::AbstractCollection< cms::Connection * >::toArray()`.

6.200.3.12 `template<typename E> virtual std::vector<E> decaf::util::Collection< E >::toArray () const [pure virtual]`

Returns an array containing all of the elements in this collection. If the collection makes any guarantees as to what order its elements are returned by its iterator, this method must return the elements in the same order.

This method acts as bridge between array-based and collection-based APIs.

Returns:

an array of the elements in this collection.

Implemented in `decaf::util::AbstractCollection< E >` (p. 189), `decaf::util::concurrent::SynchronousQueue< E >` (p. 3724), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 189), `decaf::util::AbstractCollection< Pointer< Synchronization > >` (p. 189), `decaf::util::AbstractCollection< Resource * >` (p. 189), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 189), `decaf::util::AbstractCollection< CompositeTask * >` (p. 189), `decaf::util::AbstractCollection< URI >` (p. 189), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 189), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 189), `decaf::util::AbstractCollection< PrimitiveValueNode >` (p. 189), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 189), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 189), and `decaf::util::AbstractCollection< cms::MessageProducer`

* > (p. 189), `decaf::util::AbstractCollection< cms::Destination * >` (p. 189), `decaf::util::AbstractCollection< cms::Session * >` (p. 189), and `decaf::util::AbstractCollection< cms::Connection * >` (p. 189).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Collection.h`

6.201 activemq::commands::Command Class Reference

#include <src/main/activemq/commands/Command.h> Inheritance diagram for activemq::commands::Command:

Public Member Functions

- virtual **~Command** ()
- virtual void **setCommandId** (int id)=0
*Sets the **Command** (p. 1194) Id of this **Message** (p. 2516).*
- virtual int **getCommandId** () const =0
*Gets the **Command** (p. 1194) Id of this **Message** (p. 2516).*
- virtual void **setResponseRequired** (const bool required)=0
*Set if this **Message** (p. 2516) requires a **Response** (p. 3285).*
- virtual bool **isResponseRequired** () const =0
*Is a **Response** (p. 3285) required for this **Command** (p. 1194).*
- virtual std::string **toString** () const =0
Returns a provider-specific string that provides information about the contents of the command.
- virtual **decaf::lang::Pointer**< **commands::Command** > **visit** (**activemq::state::CommandVisitor** *visitor)=0 throw (**exceptions::ActiveMQException**)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.
- virtual bool **isConnectionInfo** () const =0
- virtual bool **isConsumerInfo** () const =0
- virtual bool **isBrokerInfo** () const =0
- virtual bool **isKeepAliveInfo** () const =0
- virtual bool **isMessage** () const =0
- virtual bool **isMessageAck** () const =0
- virtual bool **isMessageDispatch** () const =0
- virtual bool **isMessageDispatchNotification** () const =0
- virtual bool **isProducerAck** () const =0
- virtual bool **isProducerInfo** () const =0
- virtual bool **isResponse** () const =0
- virtual bool **isRemoveInfo** () const =0
- virtual bool **isRemoveSubscriptionInfo** () const =0
- virtual bool **isShutdownInfo** () const =0
- virtual bool **isTransactionInfo** () const =0
- virtual bool **isWireFormatInfo** () const =0

6.201.1 Constructor & Destructor Documentation

6.201.1.1 virtual `activemq::commands::Command::~~Command ()` [inline, virtual]

6.201.2 Member Function Documentation

6.201.2.1 virtual `int activemq::commands::Command::getCommandId ()` const [pure virtual]

Gets the **Command** (p. 1194) Id of this **Message** (p. 2516).

Returns:

Command (p. 1194) Id

Implemented in `activemq::commands::BaseCommand` (p. 760).

6.201.2.2 virtual `bool activemq::commands::Command::isBrokerInfo ()` const [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 760), and `activemq::commands::BrokerInfo` (p. 900).

6.201.2.3 virtual `bool activemq::commands::Command::isConnectionInfo ()` const [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::ConnectionInfo` (p. 1358).

6.201.2.4 virtual `bool activemq::commands::Command::isConsumerInfo ()` const [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::ConsumerInfo` (p. 1463).

6.201.2.5 virtual `bool activemq::commands::Command::isKeepAliveInfo ()` const [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::KeepAliveInfo` (p. 2268).

6.201.2.6 virtual `bool activemq::commands::Command::isMessage ()` const [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::Message` (p. 2527).

6.201.2.7 `virtual bool activemq::commands::Command::isMessageAck () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::MessageAck` (p. 2562).

6.201.2.8 `virtual bool activemq::commands::Command::isMessageDispatch () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::MessageDispatch` (p. 2596).

6.201.2.9 `virtual bool activemq::commands::Command::isMessageDispatchNotification () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 761), and `activemq::commands::MessageDispatchNotification` (p. 2632).

6.201.2.10 `virtual bool activemq::commands::Command::isProducerAck () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 762), and `activemq::commands::ProducerAck` (p. 3038).

6.201.2.11 `virtual bool activemq::commands::Command::isProducerInfo () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 762), and `activemq::commands::ProducerInfo` (p. 3098).

6.201.2.12 `virtual bool activemq::commands::Command::isRemoveInfo () const`
[pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 762), and `activemq::commands::RemoveInfo` (p. 3196).

6.201.2.13 `virtual bool activemq::commands::Command::isRemoveSubscriptionInfo () const` [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 762), and `activemq::commands::RemoveSubscriptionInfo` (p. 3224).

6.201.2.14 `virtual bool activemq::commands::Command::isResponse () const` [pure virtual]

Implemented in `activemq::commands::BaseCommand` (p. 762), and `activemq::commands::Response` (p. 3287).

6.201.2.15 `virtual bool activemq::commands::Command::isResponseRequired () const [pure virtual]`

Is a **Response** (p. 3285) required for this **Command** (p. 1194).

Returns:

true if a response is required.

Implemented in **activemq::commands::BaseCommand** (p. 762).

6.201.2.16 `virtual bool activemq::commands::Command::isShutdownInfo () const [pure virtual]`

Implemented in **activemq::commands::BaseCommand** (p. 762), and **activemq::commands::ShutdownInfo** (p. 3472).

6.201.2.17 `virtual bool activemq::commands::Command::isTransactionInfo () const [pure virtual]`

Implemented in **activemq::commands::BaseCommand** (p. 763), and **activemq::commands::TransactionInfo** (p. 3849).

6.201.2.18 `virtual bool activemq::commands::Command::isWireFormatInfo () const [pure virtual]`

Implemented in **activemq::commands::BaseCommand** (p. 763), and **activemq::commands::WireFormatInfo** (p. 3989).

6.201.2.19 `virtual void activemq::commands::Command::setCommandId (int id) [pure virtual]`

Sets the **Command** (p. 1194) Id of this **Message** (p. 2516).

Parameters:

id **Command** (p. 1194) Id

Implemented in **activemq::commands::BaseCommand** (p. 763).

6.201.2.20 `virtual void activemq::commands::Command::setResponseRequired (const bool required) [pure virtual]`

Set if this **Message** (p. 2516) requires a **Response** (p. 3285).

Parameters:

required true if response is required

Implemented in **activemq::commands::BaseCommand** (p. 763).

6.201.2.21 `virtual std::string activemq::commands::Command::toString () const`
`[pure virtual]`

Returns a provider-specific string that provides information about the contents of the command.

Reimplemented from `activemq::commands::BaseDataStructure` (p. 833).

Implemented in `activemq::commands::ActiveMQBlobMessage` (p. 208), `activemq::commands::ActiveMQBytesMessage` (p. 244), `activemq::commands::ActiveMQMapMessage` (p. 372), `activemq::commands::ActiveMQMessage` (p. 400), `activemq::commands::ActiveMQObjectMessage` (p. 445), `activemq::commands::ActiveMQStreamMessage` (p. 547), `activemq::commands::ActiveMQTextMessage` (p. 666), `activemq::commands::BaseCommand` (p. 763), `activemq::commands::BrokerInfo` (p. 901), `activemq::commands::ConnectionControl` (p. 1270), `activemq::commands::ConnectionError` (p. 1298), `activemq::commands::ConnectionInfo` (p. 1359), `activemq::commands::ConsumerControl` (p. 1404), `activemq::commands::ConsumerInfo` (p. 1464), `activemq::commands::ControlCommand` (p. 1495), `activemq::commands::DataArrayResponse` (p. 1530), `activemq::commands::DataResponse` (p. 1585), `activemq::commands::DestinationInfo` (p. 1730), `activemq::commands::ExceptionResponse` (p. 1841), `activemq::commands::FlushCommand` (p. 1939), `activemq::commands::IntegerResponse` (p. 2093), `activemq::commands::KeepAliveInfo` (p. 2268), `activemq::commands::Message` (p. 2530), `activemq::commands::MessageAck` (p. 2563), `activemq::commands::MessageDispatch` (p. 2597), `activemq::commands::MessageDispatchNotification` (p. 2633), `activemq::commands::MessagePull` (p. 2742), `activemq::commands::ProducerAck` (p. 3038), `activemq::commands::ProducerInfo` (p. 3099), `activemq::commands::RemoveInfo` (p. 3196), `activemq::commands::RemoveSubscriptionInfo` (p. 3225), `activemq::commands::ReplayCommand` (p. 3253), `activemq::commands::Response` (p. 3287), `activemq::commands::SessionInfo` (p. 3409), `activemq::commands::ShutdownInfo` (p. 3472), `activemq::commands::TransactionInfo` (p. 3849), and `activemq::commands::WireFormatInfo` (p. 3991).

6.201.2.22 `virtual decaf::lang::Pointer<commands::Command> activemq::commands::Command::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` `[pure virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implemented in `activemq::commands::BrokerError` (p. 866), `activemq::commands::BrokerInfo` (p. 902), `activemq::commands::ConnectionControl` (p. 1271), `activemq::commands::ConnectionError` (p. 1298), `activemq::commands::ConnectionInfo` (p. 1359), `activemq::commands::ConsumerControl` (p. 1405), `activemq::commands::ConsumerInfo` (p. 1465), `activemq::commands::ControlCommand` (p. 1495), `activemq::commands::DestinationInfo` (p. 1730), `activemq::commands::FlushCommand` (p. 1939), `activemq::commands::KeepAliveInfo` (p. 2268), `activemq::commands::Message` (p. 2531), `activemq::commands::MessageAck` (p. 2563), `activemq::commands::MessageDispatch`

(p. 2597), **activemq::commands::MessageDispatchNotification**
(p. 2633), **activemq::commands::MessagePull** (p. 2742), **ac-**
tivemq::commands::ProducerAck (p. 3038), **activemq::commands::ProducerInfo**
(p. 3099), **activemq::commands::RemoveInfo** (p. 3196), **ac-**
tivemq::commands::RemoveSubscriptionInfo (p. 3225), **ac-**
tivemq::commands::ReplayCommand (p. 3253), **activemq::commands::Response**
(p. 3287), **activemq::commands::SessionInfo** (p. 3409), **ac-**
tivemq::commands::ShutdownInfo (p. 3472), **activemq::commands::TransactionInfo**
(p. 3850), and **activemq::commands::WireFormatInfo** (p. 3991).

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/Command.h`

6.202 activemq::state::CommandVisitor Class Reference

Interface for an Object that can visit the various Command Objects that are sent from and to this client.

#include <src/main/activemq/state/CommandVisitor.h> Inheritance diagram for activemq::state::CommandVisitor:

Public Member Functions

- virtual `~CommandVisitor ()`
- virtual `decaf::lang::Pointer< commands::Command > processTransactionInfo (commands::TransactionInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveInfo (commands::RemoveInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processConnectionInfo (commands::ConnectionInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processSessionInfo (commands::SessionInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processProducerInfo (commands::ProducerInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processConsumerInfo (commands::ConsumerInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveConnection (commands::ConnectionId *id)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveSession (commands::SessionId *id)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveProducer (commands::ProducerId *id)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveConsumer (commands::ConsumerId *id)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processDestinationInfo (commands::DestinationInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveDestination (commands::DestinationInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processRemoveSubscriptionInfo (commands::RemoveSubscriptionInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processMessage (commands::Message *send)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processMessageAck (commands::MessageAck *ack)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processMessagePull (commands::MessagePull *pull)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processBeginTransaction (commands::TransactionInfo *info)=0` throw (exceptions::ActiveMQException)
- virtual `decaf::lang::Pointer< commands::Command > processPrepareTransaction (commands::TransactionInfo *info)=0` throw (exceptions::ActiveMQException)

- virtual **decaf::lang::Pointer< commands::Command > processCommitTransactionOnePhase** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processCommitTransactionTwoPhase** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRollbackTransaction** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processWireFormat** (commands::WireFormatInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processKeepAliveInfo** (commands::KeepAliveInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processShutdownInfo** (commands::ShutdownInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processFlushCommand** (commands::FlushCommand *command)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processBrokerInfo** (commands::BrokerInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRecoverTransactions** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processForgetTransaction** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processEndTransaction** (commands::TransactionInfo *info)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processMessageDispatchNotification** (commands::MessageDispatchNotification *notification)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processProducerAck** (commands::ProducerAck *ack)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processMessageDispatch** (commands::MessageDispatch *dispatch)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processControlCommand** (commands::ControlCommand *command)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processConnectionError** (commands::ConnectionError *error)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processConnectionControl** (commands::ConnectionControl *control)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processConsumerControl** (commands::ConsumerControl *control)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processBrokerError** (commands::BrokerError *error)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processReplayCommand** (commands::ReplayCommand *replay)=0 throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processResponse** (commands::Response *response)=0 throw (exceptions::ActiveMQException)

6.202.1 Detailed Description

Interface for an Object that can visit the various Command Objects that are sent from and to this client. The Commands themselves implement a **visit** method that is called with an instance of this interface and each one then call the appropriate **processXXX** method.

Since:

3.0

6.202.2 Constructor & Destructor Documentation

6.202.2.1 `virtual activemq::state::CommandVisitor::~~CommandVisitor ()` [inline, virtual]

6.202.3 Member Function Documentation

6.202.3.1 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processBeginTransaction
(commands::TransactionInfo * info) throw (exceptions::ActiveMQException)` [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1394).

6.202.3.2 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processBrokerError
(commands::BrokerError * error) throw (exceptions::ActiveMQException)` [pure virtual]

6.202.3.3 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processBrokerInfo
(commands::BrokerInfo * info) throw (exceptions::ActiveMQException)` [pure virtual]

6.202.3.4 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processCommitTransactionOnePhase
(commands::TransactionInfo * info) throw (exceptions::ActiveMQException)` [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1394).

6.202.3.5 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processCommitTransactionTwoPhase
(commands::TransactionInfo * info) throw (exceptions::ActiveMQException)` [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.6** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processConnectionControl
(commands::ConnectionControl * *control*) throw (
exceptions::ActiveMQException) [pure virtual]
- 6.202.3.7** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processConnectionError
(commands::ConnectionError * *error*) throw (
exceptions::ActiveMQException) [pure virtual]
- 6.202.3.8** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processConnectionInfo
(commands::ConnectionInfo * *info*) throw (
exceptions::ActiveMQException) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.9** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processConsumerControl
(commands::ConsumerControl * *control*) throw (
exceptions::ActiveMQException) [pure virtual]
- 6.202.3.10** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processConsumerInfo
(commands::ConsumerInfo * *info*) throw (
exceptions::ActiveMQException) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.11** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processControlCommand
(commands::ControlCommand * *command*) throw (
exceptions::ActiveMQException) [pure virtual]
- 6.202.3.12** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processDestinationInfo
(commands::DestinationInfo * *info*) throw (
exceptions::ActiveMQException) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.13** virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processEndTransaction
(commands::TransactionInfo * *info*) throw (
exceptions::ActiveMQException) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.14 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processFlushCommand
(commands::FlushCommand * command) throw (
exceptions::ActiveMQException) [pure virtual]`
- 6.202.3.15 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processForgetTransaction
(commands::TransactionInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`
- 6.202.3.16 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processKeepAliveInfo
(commands::KeepAliveInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`
- 6.202.3.17 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processMessage (commands::Message
* send) throw (exceptions::ActiveMQException) [pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.18 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processMessageAck
(commands::MessageAck * ack) throw (exceptions::ActiveMQException
) [pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1395).

- 6.202.3.19 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processMessageDispatch
(commands::MessageDispatch * dispatch) throw (
exceptions::ActiveMQException) [pure virtual]`
- 6.202.3.20 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processMessageDispatchNotification
(commands::MessageDispatchNotification * notification) throw (
exceptions::ActiveMQException) [pure virtual]`
- 6.202.3.21 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processMessagePull
(commands::MessagePull * pull) throw (exceptions::ActiveMQException
) [pure virtual]`
- 6.202.3.22 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processPrepareTransaction
(commands::TransactionInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.23 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processProducerAck
(commands::ProducerAck * *ack*) throw (exceptions::ActiveMQException
) [pure virtual]

6.202.3.24 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processProducerInfo (com-
mands::ProducerInfo * *info*) throw (exceptions::ActiveMQException)
[pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.25 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRecoverTransactions
(commands::TransactionInfo * *info*) throw (exceptions::ActiveMQException) [pure virtual]

6.202.3.26 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveConnection
(commands::ConnectionId * *id*) throw (exceptions::ActiveMQException
) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.27 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveConsumer
(commands::ConsumerId * *id*) throw (exceptions::ActiveMQException
) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.28 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveDestination
(commands::DestinationInfo * *info*) throw (exceptions::ActiveMQException) [pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.29 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveInfo
(commands::RemoveInfo * *info*) throw (exceptions::ActiveMQException
) [pure virtual]

Implemented in `activemq::state::CommandVisitorAdapter` (p. 1211).

6.202.3.30 virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveProducer
(commands::ProducerId * *id*) throw (exceptions::ActiveMQException)
[pure virtual]

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.31 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveSession
(commands::SessionId * id) throw (exceptions::ActiveMQException)
[pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1396).

6.202.3.32 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRemoveSubscriptionInfo
(commands::RemoveSubscriptionInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`

6.202.3.33 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processReplayCommand
(commands::ReplayCommand * replay) throw (
exceptions::ActiveMQException) [pure virtual]`

6.202.3.34 `virtual decaf::lang::Pointer<commands::Command> ac-
tivemq::state::CommandVisitor::processResponse (commands::Response
* response) throw (exceptions::ActiveMQException) [pure virtual]`

6.202.3.35 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processRollbackTransaction
(commands::TransactionInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1397).

6.202.3.36 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processSessionInfo
(commands::SessionInfo * info) throw (exceptions::ActiveMQException
) [pure virtual]`

Implemented in `activemq::state::ConnectionStateTracker` (p. 1397).

6.202.3.37 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processShutdownInfo (com-
mands::ShutdownInfo * info) throw (exceptions::ActiveMQException)
[pure virtual]`

6.202.3.38 `virtual decaf::lang::Pointer<commands::Command>
activemq::state::CommandVisitor::processTransactionInfo
(commands::TransactionInfo * info) throw (
exceptions::ActiveMQException) [pure virtual]`

Implemented in `activemq::state::CommandVisitorAdapter` (p. 1212).

6.202.3.39 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitor::processWireFormat
 (commands::WireFormatInfo * *info*) throw (
 exceptions::ActiveMQException) [pure virtual]

The documentation for this class was generated from the following file:

- src/main/activemq/state/CommandVisitor.h

6.203 activemq::state::CommandVisitorAdapter Class Reference

Default Implementation of a **CommandVisitor** (p.1200) that returns NULL for all calls.

#include <src/main/activemq/state/CommandVisitorAdapter.h> Inheritance diagram for activemq::state::CommandVisitorAdapter:

Public Member Functions

- virtual **~CommandVisitorAdapter** ()
- virtual **decaf::lang::Pointer< commands::Command > processRemoveConnection** (**commands::ConnectionId** *id AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRemoveSession** (**commands::SessionId** *id AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRemoveProducer** (**commands::ProducerId** *id AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRemoveConsumer** (**commands::ConsumerId** *id AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processDestinationInfo** (**commands::DestinationInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRemoveDestination** (**commands::DestinationInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processRemoveSubscriptionInfo** (**commands::RemoveSubscriptionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processMessage** (**commands::Message** *send AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processMessageAck** (**commands::MessageAck** *ack AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processMessagePull** (**commands::MessagePull** *pull AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processBeginTransaction** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processPrepareTransaction** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer< commands::Command > processCommitTransactionOnePhase** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)

- virtual **decaf::lang::Pointer**< **commands::Command** > **processCommitTransactionTwoPhase** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processRollbackTransaction** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processWireFormat** (**commands::WireFormatInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processKeepAliveInfo** (**commands::KeepAliveInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processShutdownInfo** (**commands::ShutdownInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processFlushCommand** (**commands::FlushCommand** *command AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processBrokerInfo** (**commands::BrokerInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processRecoverTransactions** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processForgetTransaction** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processEndTransaction** (**commands::TransactionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processMessageDispatchNotification** (**commands::MessageDispatchNotification** *notification AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processProducerAck** (**commands::ProducerAck** *ack AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processMessageDispatch** (**commands::MessageDispatch** *dispatch AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processControlCommand** (**commands::ControlCommand** *command AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processConnectionError** (**commands::ConnectionError** *error AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processConnectionControl** (**commands::ConnectionControl** *control AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processConsumerControl** (**commands::ConsumerControl** *control AMQCPP_UNUSED) throw (exceptions::ActiveMQException)

- virtual **decaf::lang::Pointer**< **commands::Command** > **processBrokerError** (**commands::BrokerError** *error AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processReplayCommand** (**commands::ReplayCommand** *replay AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processResponse** (**commands::Response** *response AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processConnectionInfo** (**commands::ConnectionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processSessionInfo** (**commands::SessionInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processProducerInfo** (**commands::ProducerInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processConsumerInfo** (**commands::ConsumerInfo** *info AMQCPP_UNUSED) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processTransactionInfo** (**commands::TransactionInfo** *info) throw (exceptions::ActiveMQException)
- virtual **decaf::lang::Pointer**< **commands::Command** > **processRemoveInfo** (**commands::RemoveInfo** *info) throw (exceptions::ActiveMQException)

6.203.1 Detailed Description

Default Implementation of a **CommandVisitor** (p. 1200) that returns NULL for all calls.

Since:

3.0

6.203.2 Constructor & Destructor Documentation

- 6.203.2.1 virtual
 activemq::state::CommandVisitorAdapter::~~CommandVisitorAdapter ()
 [inline, virtual]

6.203.3 Member Function Documentation

- 6.203.3.1 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processBeginTransaction
 (commands::TransactionInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.2 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processBrokerError
 (commands::BrokerError *error *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.3 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processBrokerInfo
 (commands::BrokerInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.4 virtual decaf::lang::Pointer<commands::Command> ac-
 tivemq::state::CommandVisitorAdapter::processCommitTransactionOnePhase
 (commands::TransactionInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.5 virtual decaf::lang::Pointer<commands::Command> ac-
 tivemq::state::CommandVisitorAdapter::processCommitTransactionTwoPhase
 (commands::TransactionInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.6 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processConnectionControl
 (commands::ConnectionControl *control *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.7 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processConnectionError
 (commands::ConnectionError *error *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.8 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processConnectionInfo
 (commands::ConnectionInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.9 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processConsumerControl
 (commands::ConsumerControl *control *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]
- 6.203.3.10 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processConsumerInfo
 (commands::ConsumerInfo *info *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]

Generated on Wed Nov 10 22:23:45 2010 for Activemqcpp43MQCPP by Doxygen 1.8.1

- 6.203.3.11 virtual decaf::lang::Pointer<commands::Command>
 activemq::state::CommandVisitorAdapter::processControlCommand
 (commands::ControlCommand *command *AMQCPP_UNUSED*) throw (
 exceptions::ActiveMQException) [inline, virtual]

References `activemq::commands::ConnectionId::ID_CONNECTIONID`, `activemq::commands::ConsumerId::ID_CONSUMERID`, `activemq::commands::ProducerId::ID_PRODUCERID`, and `activemq::commands::SessionId::ID_SESSIONID`.

- 6.203.3.30 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processRemoveProducer`
`(commands::ProducerId *id AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.31 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processRemoveSession`
`(commands::SessionId *id AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.32 `virtual decaf::lang::Pointer<commands::Command> ac-`
`tivemq::state::CommandVisitorAdapter::processRemoveSubscriptionInfo`
`(commands::RemoveSubscriptionInfo *info AMQCPP_UNUSED)`
`throw (exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.33 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processReplayCommand`
`(commands::ReplayCommand *replay AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.34 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processResponse`
`(commands::Response *response AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.35 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processRollbackTransaction`
`(commands::TransactionInfo *info AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.36 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processSessionInfo`
`(commands::SessionInfo *info AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.37 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processShutdownInfo`
`(commands::ShutdownInfo *info AMQCPP_UNUSED) throw (`
`exceptions::ActiveMQException) [inline, virtual]`
- 6.203.3.38 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::state::CommandVisitorAdapter::processTransactionInfo`
`(commands::TransactionInfo * info) throw (`
`exceptions::ActiveMQException) [inline, virtual]`

Implements `activemq::state::CommandVisitor` (p. 1206).

References `activemq::core::ActiveMQConstants::TRANSACTION_STATE_BEGIN`,
`activemq::core::ActiveMQConstants::TRANSACTION_STATE_`

```

COMMITONEPHASE,      activemq::core::ActiveMQConstants::TRANSACTION_STATE_-
COMMITTWOPHASE,      activemq::core::ActiveMQConstants::TRANSACTION_-
STATE_END,           activemq::core::ActiveMQConstants::TRANSACTION_STATE_-
FORGET,              activemq::core::ActiveMQConstants::TRANSACTION_STATE_PREPARE,
activemq::core::ActiveMQConstants::TRANSACTION_STATE_RECOVER,      and
activemq::core::ActiveMQConstants::TRANSACTION_STATE_ROLLBACK.

```

```

6.203.3.39  virtual decaf::lang::Pointer<commands::Command>
               activemq::state::CommandVisitorAdapter::processWireFormat
               (commands::WireFormatInfo *info AMQCPP_UNUSED) throw (
               exceptions::ActiveMQException ) [inline, virtual]

```

The documentation for this class was generated from the following file:

- src/main/activemq/state/CommandVisitorAdapter.h

6.204 decaf::lang::Comparable< T > Class Template Reference

This interface imposes a total ordering on the objects of each class that implements it.

```
#include <src/main/decaf/lang/Comparable.h>
```

Public Member Functions

- virtual **~Comparable** ()
- virtual int **compareTo** (const T &value) const =0
Compares this object with the specified object for order.
- virtual bool **equals** (const T &value) const =0
- virtual bool **operator==** (const T &value) const =0
Compares equality between this object and the one passed.
- virtual bool **operator<** (const T &value) const =0
Compares this object to another and returns true if this object is considered to be less than the one passed.

6.204.1 Detailed Description

```
template<typename T> class decaf::lang::Comparable< T >
```

This interface imposes a total ordering on the objects of each class that implements it. This ordering is referred to as the class's natural ordering, and the class's compareTo method is referred to as its natural comparison method.

6.204.2 Constructor & Destructor Documentation

6.204.2.1 `template<typename T> virtual decaf::lang::Comparable< T >::~~Comparable () [inline, virtual]`

6.204.3 Member Function Documentation

6.204.3.1 `template<typename T> virtual int decaf::lang::Comparable< T >::compareTo (const T & value) const [pure virtual]`

Compares this object with the specified object for order. Returns a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than the specified object.

In the foregoing description, the notation `sgn(expression)` designates the mathematical signum function, which is defined to return one of -1, 0, or 1 according to whether the value of expression is negative, zero or positive. The implementor must ensure `sgn(x.compareTo(y)) == -sgn(y.compareTo(x))` for all x and y. (This implies that `x.compareTo(y)` must throw an exception iff `y.compareTo(x)` throws an exception.)

The implementor must also ensure that the relation is transitive: `(x.compareTo(y)>0 && y.compareTo(z)>0)` implies `x.compareTo(z)>0`.

Finally, the implementer must ensure that `x.compareTo(y)==0` implies that `sgn(x.compareTo(z)) == sgn(y.compareTo(z))`, for all `z`.

It is strongly recommended, but not strictly required that `(x.compareTo(y)==0) == (x.equals(y))`. Generally speaking, any class that implements the **Comparable** (p. 1214) interface and violates this condition should clearly indicate this fact. The recommended language is "Note: this class has a natural ordering that is inconsistent with equals."

Parameters:

value - the Object to be compared.

Returns:

a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than the specified object.

Implemented in `decaf::lang::Boolean` (p. 851), `decaf::lang::Byte` (p. 962), `decaf::lang::Character` (p. 1102), `decaf::lang::Double` (p. 1791), `decaf::lang::Float` (p. 1907), `decaf::lang::Integer` (p. 2080), `decaf::lang::Long` (p. 2423), and `decaf::lang::Short` (p. 3442).

6.204.3.2 `template<typename T> virtual bool decaf::lang::Comparable< T >::equals (const T & value) const` [pure virtual]

Returns:

true if this value is considered equal to the passed value.

Implemented in `decaf::lang::Boolean` (p. 852), `decaf::lang::Byte` (p. 963), `decaf::lang::Character` (p. 1103), `decaf::lang::Double` (p. 1793), `decaf::lang::Float` (p. 1908), `decaf::lang::Integer` (p. 2081), `decaf::lang::Long` (p. 2424), and `decaf::lang::Short` (p. 3443).

6.204.3.3 `template<typename T> virtual bool decaf::lang::Comparable< T >::operator< (const T & value) const` [pure virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implemented in `decaf::lang::Boolean` (p. 852), `decaf::lang::Byte` (p. 964), `decaf::lang::Character` (p. 1105), `decaf::lang::Double` (p. 1795), `decaf::lang::Float` (p. 1910), `decaf::lang::Integer` (p. 2084), `decaf::lang::Long` (p. 2427), and `decaf::lang::Short` (p. 3444).

6.204.3.4 `template<typename T> virtual bool decaf::lang::Comparable< T
>::operator==(const T & value) const` [pure virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implemented in `decaf::lang::Boolean` (p. 853), `decaf::lang::Byte` (p. 965), `decaf::lang::Character` (p. 1105), `decaf::lang::Double` (p. 1795), `decaf::lang::Float` (p. 1911), `decaf::lang::Integer` (p. 2084), `decaf::lang::Long` (p. 2427), and `decaf::lang::Short` (p. 3445).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Comparable.h`

6.205 decaf::util::Comparator< T > Class Template Reference

A comparison function, which imposes a total ordering on some collection of objects.

```
#include <src/main/decaf/util/Comparator.h>
```

Public Member Functions

- virtual **~Comparator** ()
- virtual bool **operator**() (const T &left, const T &right) const =0
*Implementation of the Binary function interface as a means of allowing a **Comparator** (p. 1217) to be passed to an STL **Map** (p. 2459) for use as the sorting criteria.*
- virtual int **compare** (const T &o1, const T &o2) const =0
Compares its two arguments for order.

6.205.1 Detailed Description

```
template<typename T> class decaf::util::Comparator< T >
```

A comparison function, which imposes a total ordering on some collection of objects. Comparators can be passed to a sort method (such as Collections.sort) to allow precise control over the sort order. Comparators can also be used to control the order of certain data structures.

The ordering imposed by a **Comparator** (p. 1217) c on a set of elements S is said to be consistent with equals if and only if (compare(e1, e2) == 0) has the same boolean value as (e1 == e2) for every e1 and e2 in S.

6.205.2 Constructor & Destructor Documentation

6.205.2.1 template<typename T> virtual decaf::util::Comparator< T
 >::~Comparator () [inline, virtual]

6.205.3 Member Function Documentation

6.205.3.1 template<typename T> virtual int decaf::util::Comparator< T
 >::compare (const T & o1, const T & o2) const [pure virtual]

Compares its two arguments for order. Returns a negative integer, zero, or a positive integer as the first argument is less than, equal to, or greater than the second.

The implementor must ensure that `sgn(compare(x, y)) == -sgn(compare(y, x))` for all x and y. (This implies that `compare(x, y)` must throw an exception if and only if `compare(y, x)` throws an exception.)

The implementor must also ensure that the relation is transitive: `((compare(x, y)>0) && (compare(y, z)>0)) implies compare(x, z)>0`.

Finally, the implementer must ensure that `compare(x, y)==0` implies that `sgn(compare(x, z))==sgn(compare(y, z))` for all z.

It is generally the case, but not strictly required that `(compare(x, y)==0) == (x == y)`. Generally speaking, any comparator that violates this condition should clearly indicate this fact. The recommended language is "Note: this comparator imposes orderings that are inconsistent with equals."

Parameters:

- o1* - the first object to be compared
- o2* - the second object to be compared

Returns:

a negative integer, zero, or a positive integer as the first argument is less than, equal to, or greater than the second.

Implemented in **decaf::util::comparators::Less< E >** (p. 2328).

6.205.3.2 `template<typename T> virtual bool decaf::util::Comparator< T >::operator() (const T & left, const T & right) const` [pure virtual]

Implementation of the Binary function interface as a means of allowing a **Comparator** (p. 1217) to be passed to an STL **Map** (p. 2459) for use as the sorting criteria.

Parameters:

- left* - the Left hand side operand.
- right* - the Right hand side operand.

Returns:

true if the value of left is less than the value of right.

Implemented in **decaf::util::comparators::Less< E >** (p. 2329).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Comparator.h`

6.206 activemq::util::CompositeData Class Reference

Represents a Composite URI.

```
#include <src/main/activemq/util/CompositeData.h>
```

Public Member Functions

- **CompositeData** ()
- virtual **~CompositeData** ()
- **StlList< URI > & getComponents** ()
- const **StlList< URI > & getComponents** () const
- void **setComponents** (const **StlList< URI > &components**)
- std::string **getFragment** () const
- void **setFragment** (const std::string &fragment)
- const **Properties & getParameters** () const
- void **setParameters** (const **Properties ¶meters**)
- std::string **getScheme** () const
- void **setScheme** (const std::string &scheme)
- std::string **getPath** () const
- void **setPath** (const std::string &path)
- std::string **getHost** () const
- void **setHost** (const std::string &host)
- **URI toURI** () const throw (decaf::net::URISyntaxException)

6.206.1 Detailed Description

Represents a Composite URI.

Since:

3.0

6.206.2 Constructor & Destructor Documentation

6.206.2.1 `activemq::util::CompositeData::CompositeData ()`

6.206.2.2 `virtual activemq::util::CompositeData::~~CompositeData ()` [virtual]

6.206.3 Member Function Documentation

6.206.3.1 `const StlList<URI>& activemq::util::CompositeData::getComponents ()`
const [inline]

6.206.3.2 `StlList<URI>& activemq::util::CompositeData::getComponents ()`
[inline]

6.206.3.3 `std::string activemq::util::CompositeData::getFragment ()` const
[inline]

6.206.3.4 `std::string activemq::util::CompositeData::getHost ()` const [inline]

6.206.3.5 `const Properties& activemq::util::CompositeData::getParameters ()`
const [inline]

6.206.3.6 `std::string activemq::util::CompositeData::getPath ()` const [inline]

6.206.3.7 `std::string activemq::util::CompositeData::getScheme ()` const [inline]

6.206.3.8 `void activemq::util::CompositeData::setComponents (const StlList< URI`
> & *components*) [inline]

6.206.3.9 `void activemq::util::CompositeData::setFragment (const std::string &`
fragment) [inline]

6.206.3.10 `void activemq::util::CompositeData::setHost (const std::string & host)`
[inline]

6.206.3.11 `void activemq::util::CompositeData::setParameters (const Properties &`
parameters) [inline]

6.206.3.12 `void activemq::util::CompositeData::setPath (const std::string & path)`
[inline]

6.206.3.13 `void activemq::util::CompositeData::setScheme (const std::string &`
scheme) [inline]

6.206.3.14 `URI activemq::util::CompositeData::toURI ()` const throw (
`decaf::net::URISyntaxException`)

The documentation for this class was generated from the following file:

- `src/main/activemq/util/CompositeData.h`

6.207 activemq::threads::CompositeTask Class Reference

Represents a single task that can be part of a set of Tasks that are contained in a CompositeTaskRunner (p.1223).

#include <src/main/activemq/threads/CompositeTask.h>Inheritance diagram for activemq::threads::CompositeTask:

Public Member Functions

- virtual `~CompositeTask ()`
- virtual `bool isPending () const =0`

*Indicates whether this task has any pending work that needs to be done, if not then it is skipped and the next **Task** (p.3734) in the CompositeTaskRunner's list of tasks is checked, if none of the tasks have any pending work to do, then the runner can go to sleep until it awakened by a call to **wakeup**.*

6.207.1 Detailed Description

Represents a single task that can be part of a set of Tasks that are contained in a CompositeTaskRunner (p.1223).

Since:

3.0

6.207.2 Constructor & Destructor Documentation

6.207.2.1 `virtual activemq::threads::CompositeTask::~~CompositeTask () [inline, virtual]`

6.207.3 Member Function Documentation

6.207.3.1 `virtual bool activemq::threads::CompositeTask::isPending () const [pure virtual]`

Indicates whether this task has any pending work that needs to be done, if not then it is skipped and the next **Task** (p.3734) in the CompositeTaskRunner's list of tasks is checked, if none of the tasks have any pending work to do, then the runner can go to sleep until it awakened by a call to **wakeup**.

Since:

3.0

Implemented in `activemq::transport::failover::BackupTransportPool` (p.757), `activemq::transport::failover::CloseTransportsTask` (p.1151), and `activemq::transport::failover::FailoverTransport` (p.1879).

The documentation for this class was generated from the following file:

- `src/main/activemq/threads/CompositeTask.h`

6.208 activemq::threads::CompositeTaskRunner Class Reference

A **Task** (p. 3734) Runner that can contain one or more CompositeTasks that are each checked for pending work and run if any is present in the order that the tasks were added.

#include <src/main/activemq/threads/CompositeTaskRunner.h> Inheritance diagram for activemq::threads::CompositeTaskRunner:

Public Member Functions

- **CompositeTaskRunner** ()
- virtual **~CompositeTaskRunner** ()
- void **addTask** (CompositeTask *task)
*Adds a new **CompositeTask** (p. 1221) to the Set of Tasks that this class manages.*
- void **removeTask** (CompositeTask *task)
*Removes a **CompositeTask** (p. 1221) that was added previously.*
- virtual void **shutdown** (unsigned int timeout)
Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.
- virtual void **shutdown** ()
Shutdown once the task has finished and the TaskRunner's thread has exited.
- virtual void **wakeup** ()
*Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.*

Protected Member Functions

- virtual void **run** ()
Run method - called by the Thread class in the context of the thread.
- virtual bool **iterate** ()
Perform one iteration of work, returns true if the task needs to run again to complete or false to indicate that the task is now complete.

6.208.1 Detailed Description

A **Task** (p. 3734) Runner that can contain one or more CompositeTasks that are each checked for pending work and run if any is present in the order that the tasks were added.

Since:

3.0

6.208.2 Constructor & Destructor Documentation

6.208.2.1 `activemq::threads::CompositeTaskRunner::CompositeTaskRunner ()`

6.208.2.2 `virtual
activemq::threads::CompositeTaskRunner::~~CompositeTaskRunner ()
[virtual]`

6.208.3 Member Function Documentation

6.208.3.1 `void activemq::threads::CompositeTaskRunner::addTask (CompositeTask * task)`

Adds a new **CompositeTask** (p. 1221) to the Set of Tasks that this class manages.

Parameters:

task - Pointer to a **CompositeTask** (p. 1221) instance.

6.208.3.2 `virtual bool activemq::threads::CompositeTaskRunner::iterate ()
[protected, virtual]`

Perform one iteration of work, returns true if the task needs to run again to complete or false to indicate that the task is now complete.

Returns:

true if the task should be run again or false if the task has completed and the runner should wait for a wakeup call.

Implements **activemq::threads::Task** (p. 3734).

6.208.3.3 `void activemq::threads::CompositeTaskRunner::removeTask
(CompositeTask * task)`

Removes a **CompositeTask** (p. 1221) that was added previously.

Parameters:

task - Pointer to a **CompositeTask** (p. 1221) instance.

6.208.3.4 `virtual void activemq::threads::CompositeTaskRunner::run ()
[protected, virtual]`

Run method - called by the Thread class in the context of the thread.

Implements **decaf::lang::Runnable** (p. 3325).

6.208.3.5 `virtual void activemq::threads::CompositeTaskRunner::shutdown ()
[virtual]`

Shutdown once the task has finished and the TaskRunner's thread has exited.

Implements **activemq::threads::TaskRunner** (p. 3736).

6.208.3.6 virtual void activemq::threads::CompositeTaskRunner::shutdown (unsigned int *timeout*) [virtual]

Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.

Parameters:

timeout - Time in Milliseconds to wait for the task to stop.

Implements **activemq::threads::TaskRunner** (p. 3736).

6.208.3.7 virtual void activemq::threads::CompositeTaskRunner::wakeup () [virtual]

Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.

Implements **activemq::threads::TaskRunner** (p. 3737).

The documentation for this class was generated from the following file:

- src/main/activemq/threads/**CompositeTaskRunner.h**

6.209 activemq::transport::CompositeTransport Class Reference

A Composite **Transport** (p. 3883) is a **Transport** (p. 3883) implementation that is composed of several Transports.

#include <src/main/activemq/transport/CompositeTransport.h> Inheritance diagram for activemq::transport::CompositeTransport:

Public Member Functions

- virtual **~CompositeTransport** ()
- virtual void **addURI** (const **List**< **URI** > &uris)=0
*Add a URI to the list of URI's that will represent the set of Transports that this **Transport** (p. 3883) is a composite of.*
- virtual void **removeURI** (const **List**< **URI** > &uris)=0
*Remove a URI from the set of URI's that represents the set of Transports that this **Transport** (p. 3883) is composed of, removing a URI for which the composite has created a connected **Transport** (p. 3883) should result in that **Transport** (p. 3883) being disposed of.*

6.209.1 Detailed Description

A Composite **Transport** (p. 3883) is a **Transport** (p. 3883) implementation that is composed of several Transports. The composition could be such that only one **Transport** (p. 3883) exists for each URI that is composed or there could be many active Transports working at once.

Since:

3.0

6.209.2 Constructor & Destructor Documentation

- 6.209.2.1** virtual **activemq::transport::CompositeTransport::~~CompositeTransport** () [inline, virtual]

6.209.3 Member Function Documentation

- 6.209.3.1** virtual void **activemq::transport::CompositeTransport::addURI** (const **List**< **URI** > & *uris*) [pure virtual]

Add a URI to the list of URI's that will represent the set of Transports that this **Transport** (p. 3883) is a composite of.

Parameters:

uris The new URI set to add to the set this composite maintains.

Implemented in **activemq::transport::failover::FailoverTransport** (p. 1876).

6.209.3.2 virtual void activemq::transport::CompositeTransport::removeURI (const List< URI > & *uris*) [pure virtual]

Remove a URI from the set of URI's that represents the set of Transports that this **Transport** (p. 3883) is composed of, removing a URI for which the composite has created a connected **Transport** (p. 3883) should result in that **Transport** (p. 3883) being disposed of.

Parameters:

uris The new URI set to remove to the set this composite maintains.

Implemented in **activemq::transport::failover::FailoverTransport** (p. 1881).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/**CompositeTransport.h**

6.210 decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR > Class Template Reference

Interface for a **Map** (p. 2459) type that provides additional **atomic** (p. 173) `putIfAbsent`, `remove`, and `replace` methods alongside the already available **Map** (p. 2459) interface.

#include <src/main/decaf/util/concurrent/ConcurrentMap.h> Inheritance diagram for `decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >`:

Public Member Functions

- virtual `~ConcurrentMap()`
- virtual `bool putIfAbsent (const K &key, const V &value)=0` throw (`decaf::lang::exceptions::UnsupportedOperationException`)

If the specified key is not already associated with a value, associate it with the given value.

- virtual `bool remove (const K &key, const V &value)=0`

Remove entry for key only if currently mapped to given value.

- virtual `bool replace (const K &key, const V &oldValue, const V &newValue)=0`

Replace entry for key only if currently mapped to given value.

- virtual `V replace (const K &key, const V &value)=0` throw (`decaf::lang::exceptions::NoSuchElementException`)

Replace entry for key only if currently mapped to some value.

6.210.1 Detailed Description

```
template<typename K, typename V, typename COMPARATOR> class
decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >
```

Interface for a **Map** (p. 2459) type that provides additional **atomic** (p. 173) `putIfAbsent`, `remove`, and `replace` methods alongside the already available **Map** (p. 2459) interface.

Since:

1.0

6.210.2 Constructor & Destructor Documentation

6.210.2.1 `template<typename K, typename V, typename COMPARATOR>
virtual decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR
>::~ConcurrentMap () [inline, virtual]`

6.210.3 Member Function Documentation

6.210.3.1 `template<typename K, typename V, typename COMPARATOR>
virtual bool decaf::util::concurrent::ConcurrentMap< K, V,
COMPARATOR >::putIfAbsent (const K & key, const V & value)
throw (decaf::lang::exceptions::UnsupportedOperationException) [pure
virtual]`

If the specified key is not already associated with a value, associate it with the given value. This is equivalent to

```
if( !map.containsKey( key ) ) {
    map.put( key, value );
    return true;
} else {
    return false;
}
```

except that the action is performed atomically.

Parameters:

key The key to map the value to.

value The value to map to the given key.

Returns:

true if the put operation was performed otherwise return false which indicates there was a value previously mapped to the key.

Exceptions:

UnsupportedOperationException if the put operation is not supported by this map

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p.1243), and `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p.1243).

6.210.3.2 `template<typename K, typename V, typename COMPARATOR> virtual bool decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >::remove (const K & key, const V & value) [pure virtual]`

Remove entry for key only if currently mapped to given value. Acts as

```
if( ( map.containsKey( key ) && ( map.get( key ) == value ) ) ) {
    map.remove( key );
    return true;
} else {
    return false;
}
```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

value value associated with the specified key.

Returns:

true if the value was removed, false otherwise

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p.1243), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p.1243), and `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p.1243).

6.210.3.3 `template<typename K, typename V, typename COMPARATOR> virtual V decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >::replace (const K & key, const V & value) throw (decaf::lang::exceptions::NoSuchElementException) [pure virtual]`

Replace entry for key only if currently mapped to some value. Acts as

```
if( ( map.containsKey( key ) ) ) {
    return map.put( key, value );
} else {
    throw NoSuchElementException(...);
};
```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

value value to be associated with the specified key.

Returns:

copy of the previous value associated with specified key, or throws an NoSuchElementException if there was no mapping for key.

Exceptions:

NoSuchElementException if there was no previous mapping.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p.1244), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p.1244), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p.1244), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p.1244), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p.1244), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p.1244), and decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p.1244).

6.210.3.4 template<typename K, typename V, typename COMPARATOR> virtual
 bool decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR
 >::replace (const K & *key*, const V & *oldValue*, const V & *newValue*)
 [pure virtual]

Replace entry for key only if currently mapped to given value. Acts as

```
if( ( map.containsKey( key ) && ( map.get( key ) == oldValue ) ) ) {
    map.put( key, newValue );
    return true;
} else {
    return false;
}
```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

oldValue value expected to be associated with the specified key.

newValue value to be associated with the specified key.

Returns:

true if the value was replaced

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p.1245), `decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >` (p.1245), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p.1245), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p.1245), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p.1245), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p.1245), and `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p.1245).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/ConcurrentMap.h`

6.211 decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > Class Template Reference

Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map.

#include <src/main/decaf/util/concurrent/ConcurrentStlMap.h> Inheritance diagram for decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >:

Public Member Functions

- **ConcurrentStlMap** ()
Default constructor - does nothing.
- **ConcurrentStlMap** (const **ConcurrentStlMap** &source)
Copy constructor - copies the content of the given map into this one.
- **ConcurrentStlMap** (const **Map**< K, V, COMPARATOR > &source)
Copy constructor - copies the content of the given map into this one.
- virtual ~**ConcurrentStlMap** ()
- virtual bool **equals** (const **ConcurrentStlMap** &source) const
Comparison, equality is dependent on the method of determining if the element are equal.
Parameters:
source - **Map** (p. 2459) to compare to this one.
Returns:
*true if the **Map** (p. 2459) passed is equal in value to this one.*
- virtual bool **equals** (const **Map**< K, V, COMPARATOR > &source) const
- virtual void **copy** (const **ConcurrentStlMap** &source)
Copies the content of the source map into this map.
Erases all existing data in this map.
Parameters:
source The source object to copy from.
- virtual void **copy** (const **Map**< K, V, COMPARATOR > &source)
- virtual void **clear** () throw (decaf::lang::exceptions::UnsupportedOperationException)
Removes all keys and values from this map.
Exceptions:
UnsupportedOperationException if this map is unmodifiable.
- virtual bool **containsKey** (const K &key) const
Indicates whether or this map contains a value for the given key.
Parameters:
key The key to look up.
Returns:
true if this map contains the value, otherwise false.

- virtual bool **containsValue** (const V &value) const
Indicates whether or this map contains a value for the given value, i.e. they are equal, this is done by operator== so the types must pass equivalence testing in this manner.
Parameters:
value The Value to look up.
Returns:
true if this map contains the value, otherwise false.
- virtual bool **isEmpty** () const
Returns:
*if the **Map** (p. 2459) contains any element or not, TRUE or FALSE*
- virtual std::size_t **size** () const
Returns:
The number of elements (key/value pairs) in this map.
- virtual V & **get** (const K &key) throw (lang::exceptions::NoSuchElementException)
*Gets the value mapped to the specified key in the **Map** (p. 2459).
If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.*
Parameters:
key The search key.
Returns:
A reference to the value for the given key.
Exceptions:
***NoSuchElementException** if the key requests doesn't exist in the **Map** (p. 2459).*
- virtual const V & **get** (const K &key) const throw (lang::exceptions::NoSuchElementException)
*Gets the value mapped to the specified key in the **Map** (p. 2459).
If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.*
Parameters:
key The search key.
Returns:
A {const} reference to the value for the given key.
Exceptions:
***NoSuchElementException** if the key requests doesn't exist in the **Map** (p. 2459).*
- virtual void **put** (const K &key, const V &value) throw (decaf::lang::exceptions::UnsupportedOperationException)
Sets the value for the specified key.
Parameters:
key The target key.
value The value to be set.
Exceptions:
***UnsupportedOperationException** if this map is unmodifiable.*

- virtual void **putAll** (const **ConcurrentStlMap**< K, V, COMPARATOR > &other) throw (decaf::lang::exceptions::UnsupportedOperationException)

*Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.*

Parameters:

*other A **Map** (p. 2459) instance whose elements are to all be inserted in this **Map** (p. 2459).*

Exceptions:

UnsupportedOperationException *If the implementing class does not support the putAll operation.*

- virtual void **putAll** (const **Map**< K, V, COMPARATOR > &other) throw (decaf::lang::exceptions::UnsupportedOperationException)

- virtual V **remove** (const K &key) throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)

Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.

Parameters:

key The search key.

Returns:

a copy of the element that was previously mapped to the given key

Exceptions:

NoSuchElementException *if this key is not in the **Map** (p. 2459).*
UnsupportedOperationException *if this map is unmodifiable.*

- virtual std::vector< K > **keySet** () const

*Returns a **Set** (p. 3439) view of the mappings contained in this map.*

*The set is backed by the map, so changes to the map are reflected in the set, and vice-versa. If the map is modified while an iteration over the set is in progress (except through the iterator's own remove operation, or through the setValue operation on a map entry returned by the iterator) the results of the iteration are undefined. The set supports element removal, which removes the corresponding mapping from the map, via the **Iterator.remove** (p. 2155), **Set.remove** (p. 187), **removeAll**, **retainAll** and **clear** operations. It does not support the **add** or **addAll** operations.*

Returns:

the entire set of keys in this map as a std::vector.

- virtual std::vector< V > **values** () const

Returns:

the entire set of values in this map as a std::vector.

- bool **putIfAbsent** (const K &key, const V &value) throw (decaf::lang::exceptions::UnsupportedOperationException)

If the specified key is not already associated with a value, associate it with the given value.

- bool **remove** (const K &key, const V &value)

Remove entry for key only if currently mapped to given value.

- bool **replace** (const K &key, const V &oldValue, const V &newValue)

Replace entry for key only if currently mapped to given value.

- V **replace** (const K &key, const V &value) throw (decaf::lang::exceptions::NoSuchElementException)

Replace entry for key only if currently mapped to some value.

- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)

Locks the object.

- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)

*Attempts to **Lock** (p. 2375) the object, if the lock is already held by another thread than this method returns false.*

- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)

Unlocks the object.

- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentOutOfRangeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals a waiter on this object that it can now wake up and continue.

- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals the waiters on this object that it can now wake up and continue.

6.211.1 Detailed Description

```
template<typename K, typename V, typename COMPARATOR = std::less<K>>
class decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >
```

Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map. This version of **Map** (p. 2459) extends the **ConcurrentMap** (p. 1228) interface and implements all the methods defined in that interface. Unlike a Java ConcurrentHashMap this implementations synchronizes all methods such that any call to this class will block if another thread is already holding a lock, much like the Java HashTable.

Since:

1.0

6.211.2 Constructor & Destructor Documentation

6.211.2.1 `template<typename K, typename V, typename COMPARATOR
 = std::less<K>> decaf::util::concurrent::ConcurrentStlMap< K, V,
 COMPARATOR >::ConcurrentStlMap () [inline]`

Default constructor - does nothing.

6.211.2.2 `template<typename K, typename V, typename COMPARATOR
 = std::less<K>> decaf::util::concurrent::ConcurrentStlMap< K, V,
 COMPARATOR >::ConcurrentStlMap (const ConcurrentStlMap< K, V,
 COMPARATOR > & source) [inline]`

Copy constructor - copies the content of the given map into this one.

Parameters:

source The source map.

6.211.2.3 `template<typename K, typename V, typename COMPARATOR
 = std::less<K>> decaf::util::concurrent::ConcurrentStlMap< K,
 V, COMPARATOR >::ConcurrentStlMap (const Map< K, V,
 COMPARATOR > & source) [inline]`

Copy constructor - copies the content of the given map into this one.

Parameters:

source The source map.

6.211.2.4 `template<typename K, typename V, typename COMPARATOR =
 std::less<K>> virtual decaf::util::concurrent::ConcurrentStlMap< K, V,
 COMPARATOR >::~~ConcurrentStlMap () [inline, virtual]`

6.211.3 Member Function Documentation

6.211.3.1 `template<typename K, typename V, typename COMPARATOR =
 std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap<
 K, V, COMPARATOR >::clear () throw (de-
 caf::lang::exceptions::UnsupportedOperationException) [inline,
 virtual]`

Removes all keys and values from this map.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2460).

Referenced by **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** >::copy().

6.211.3.2 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::containsKey (const K & key) const [inline,
virtual]`

Indicates whether or this map contains a value for the given key.

Parameters:

key The key to look up.

Returns:

true if this map contains the value, otherwise false.

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2461).

Referenced by **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** >::equals(), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** >::putIfAbsent(), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** >::remove(), and **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** >::replace().

6.211.3.3 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::containsValue (const V & value) const
[inline, virtual]`

Indicates whether or this map contains a value for the given value, i.e.

they are equal, this is done by operator== so the types must pass equivalence testing in this manner.

Parameters:

value The Value to look up.

Returns:

true if this map contains the value, otherwise false.

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2462).

6.211.3.4 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::copy (const Map< K, V, COMPARATOR > & source) [inline, virtual]`

6.211.3.5 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::copy (const ConcurrentStlMap< K, V, COMPARATOR > & source) [inline, virtual]`

Copies the content of the source map into this map.

Erases all existing data in this map.

Parameters:

source The source object to copy from.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2463).

Referenced by `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::ConcurrentStlMap()`.

6.211.3.6 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::equals (const Map< K, V, COMPARATOR > & source) const [inline, virtual]`

6.211.3.7 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::equals (const ConcurrentStlMap< K, V, COMPARATOR > & source) const [inline, virtual]`

Comparison, equality is dependent on the method of determining if the element are equal.

Parameters:

source - `Map` (p. 2459) to compare to this one.

Returns:

true if the `Map` (p. 2459) passed is equal in value to this one.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2463).

6.211.3.8 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual const V& decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::get (const K & key) const throw (lang::exceptions::NoSuchElementException) [inline, virtual]`

Gets the value mapped to the specified key in the `Map` (p. 2459).

If there is no element in the map whose key is equivalent to the key provided then a `NoSuchElementException` is thrown.

Parameters:

key The search key.

Returns:

A {const} reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2463).

```
6.211.3.9  template<typename K, typename V, typename COMPARATOR =
           std::less<K>> virtual V& decaf::util::concurrent::ConcurrentStlMap<
           K, V, COMPARATOR >::get (const K & key) throw (
           lang::exceptions::NoSuchElementException ) [inline, virtual]
```

Gets the value mapped to the specified key in the **Map** (p. 2459).

If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.

Parameters:

key The search key.

Returns:

A reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2464).

```
6.211.3.10 template<typename K, typename V, typename COMPARATOR =
           std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap<
           K, V, COMPARATOR >::isEmpty () const [inline, virtual]
```

Returns:

if the **Map** (p. 2459) contains any element or not, TRUE or FALSE

Implements **decaf::util::Map**< **K**, **V**, **COMPARATOR** > (p. 2465).

```
6.211.3.11 template<typename K, typename V, typename
           COMPARATOR = std::less<K>> virtual std::vector<K>
           decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
           >::keySet () const [inline, virtual]
```

Returns a **Set** (p. 3439) view of the mappings contained in this map.

The set is backed by the map, so changes to the map are reflected in the set, and vice-versa. If the map is modified while an iteration over the set is in progress (except through the iterator's own remove operation, or through the setValue operation on a map entry returned by the iterator) the results of the iteration are undefined. The set supports element removal, which removes the corresponding mapping from the map, via the **Iterator.remove** (p. 2155), **Set.remove** (p. 187), **removeAll**, **retainAll** and **clear** operations. It does not support the **add** or **addAll** operations.

Returns:

the entire set of keys in this map as a std::vector.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2466).

6.211.3.12 `template<typename K, typename V, typename
 COMPARATOR = std::less<K>> virtual void
 decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
 >::lock () throw (decaf::lang::exceptions::RuntimeException) [inline,
 virtual]`

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3701).

6.211.3.13 `template<typename K, typename V, typename
 COMPARATOR = std::less<K>> virtual void
 decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
 >::notify () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [inline,
 virtual]`

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3702).

6.211.3.14 `template<typename K, typename V, typename
 COMPARATOR = std::less<K>> virtual void
 decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
 >::notifyAll () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [inline,
 virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.211.3.15 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::put (const K & key, const V & value) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Sets the value for the specified key.

Parameters:

key The target key.

value The value to be set.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2467).

Referenced by `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::putAll()`, `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::putIfAbsent()`, and `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::replace()`.

6.211.3.16 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::putAll (const Map< K, V, COMPARATOR > & other) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

6.211.3.17 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::putAll (const ConcurrentStlMap< K, V, COMPARATOR > & other) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.

Parameters:

other A **Map** (p. 2459) instance whose elements are to all be inserted in this **Map** (p. 2459).

Exceptions:

UnsupportedOperationException If the implementing class does not support the putAll operation.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2468).

Referenced by **decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::copy()**.

6.211.3.18 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> bool decaf::util::concurrent::ConcurrentStlMap< K, V,
COMPARATOR >::putIfAbsent (const K & key, const V & value)
throw (decaf::lang::exceptions::UnsupportedOperationException)
[inline, virtual]`

If the specified key is not already associated with a value, associate it with the given value. This is equivalent to

```
if( !map.containsKey( key ) ) {  
    map.put( key, value );  
    return true;  
} else {  
    return false;  
}
```

except that the action is performed atomically.

Parameters:

key The key to map the value to.

value The value to map to the given key.

Returns:

true if the put operation was performed otherwise return false which indicates there was a value previously mapped to the key.

Exceptions:

UnsupportedOperationException if the put operation is not supported by this map

Implements **decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >** (p. 1229).

6.211.3.19 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> bool decaf::util::concurrent::ConcurrentStlMap< K, V,
COMPARATOR >::remove (const K & key, const V & value) [inline,
virtual]`

Remove entry for key only if currently mapped to given value. Acts as

```
if( map.containsKey( key ) && ( map.get( key ) == value ) ) {
```

```

    map.remove( key );
    return true;
} else {
    return false;
}

```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

value value associated with the specified key.

Returns:

true if the value was removed, false otherwise

Implements **decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >** (p. 1230).

6.211.3.20 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual V decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::remove (const K & key) throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.

Parameters:

key The search key.

Returns:

a copy of the element that was previously mapped to the given key

Exceptions:

NoSuchElementException if this key is not in the **Map** (p. 2459).

UnsupportedOperationException if this map is unmodifiable.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2468).

6.211.3.21 `template<typename K, typename V, typename COMPARATOR = std::less<K>> V decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::replace (const K & key, const V & value) throw (decaf::lang::exceptions::NoSuchElementException) [inline, virtual]`

Replace entry for key only if currently mapped to some value. Acts as

```
if( map.containsKey( key ) ) {
    return map.put( key, value );
} else {
    throw NoSuchElementException(...);
};
```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

value value to be associated with the specified key.

Returns:

copy of the previous value associated with specified key, or throws an NoSuchElementException if there was no mapping for key.

Exceptions:

NoSuchElementException if there was no previous mapping.

Implements `decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >` (p. 1230).

6.211.3.22 `template<typename K, typename V, typename COMPARATOR = std::less<K>> bool decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >::replace (const K & key, const V & oldValue, const V & newValue) [inline, virtual]`

Replace entry for key only if currently mapped to given value. Acts as

```
if( map.containsKey( key ) && ( map.get( key ) == oldValue ) ) {
    map.put( key, newValue );
    return true;
} else {
    return false;
}
```

except that the action is performed atomically.

Parameters:

key key with which the specified value is associated.

oldValue value expected to be associated with the specified key.

newValue value to be associated with the specified key.

Returns:

true if the value was replaced

Implements `decaf::util::concurrent::ConcurrentMap< K, V, COMPARATOR >` (p. 1231).

6.211.3.23 `template<typename K, typename V, typename
COMPARATOR = std::less<K>> virtual std::size_t
decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
>::size () const [inline, virtual]`

Returns:

The number of elements (key/value pairs) in this map.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2469).

6.211.3.24 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual bool decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::tryLock () throw (
decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to **Lock** (p. 2375) the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3704).

6.211.3.25 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::unlock () throw (
decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3705).

6.211.3.26 `template<typename K, typename V, typename
COMPARATOR = std::less<K>> virtual std::vector<V>
decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
>::values () const [inline, virtual]`

Returns:

the entire set of values in this map as a `std::vector`.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2470).

Referenced by `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::values()`.

6.211.3.27 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::wait (long long millisecs, int
nanos) throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE
nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]
RuntimeException if an error occurs while waiting on the object.
InterruptedException if the wait is interrupted before it completes.
IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.211.3.28 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::concurrent::ConcurrentStlMap<
K, V, COMPARATOR >::wait (long long millisecs)
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.
InterruptedException if the wait is interrupted before it completes.
IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

```
6.211.3.29  template<typename K, typename V, typename
            COMPARATOR = std::less<K>> virtual void
            decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR
            >::wait () throw ( decaf::lang::exceptions::RuntimeException,
            decaf::lang::exceptions::IllegalMonitorStateException,
            decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/**ConcurrentStlMap.h**

6.212 decaf::util::concurrent::locks::Condition Class Reference

Condition (p. 1249) factors out the **Mutex** (p. 2782) monitor methods (wait, notify and notifyAll) into distinct objects to give the effect of having multiple wait-sets per object, by combining them with the use of arbitrary **Lock** (p. 2377) implementations.

```
#include <src/main/decaf/util/concurrent/locks/Condition.h>
```

Public Member Functions

- virtual `~Condition()`
- virtual void **await** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException)
Causes the current thread to wait until it is signaled or interrupted.
- virtual void **awaitUninterruptibly** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Causes the current thread to wait until it is signalled.
- virtual long long **awaitNanos** (long long nanosTimeout)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException)
Causes the current thread to wait until it is signaled or interrupted, or the specified waiting time elapses.
- virtual bool **await** (long long time, const **TimeUnit** &unit)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException)
Causes the current thread to wait until it is signaled or interrupted, or the specified waiting time elapses.
- virtual bool **awaitUntil** (const **Date** &deadline)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException)
- virtual void **signal** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Wakes up one waiting thread.
- virtual void **signalAll** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Wakes up all waiting threads.

6.212.1 Detailed Description

Condition (p. 1249) factors out the **Mutex** (p. 2782) monitor methods (wait, notify and notifyAll) into distinct objects to give the effect of having multiple wait-sets per object, by combining them with the use of arbitrary **Lock** (p. 2377) implementations. Where a **Lock** (p. 2377) replaces the use of synchronized statements, a **Condition** (p. 1249) replaces the use of the Object monitor methods.

Conditions (also known as condition queues or condition variables) provide a means for one thread to suspend execution (to "wait") until notified by another thread that some state condition may now be true. Because access to this shared state information occurs in different threads, it must be protected, so a lock of some form is associated with the condition. The key property that waiting for a condition provides is that it atomically releases the associated lock and suspends the current thread.

A **Condition** (p. 1249) instance is intrinsically bound to a lock. To obtain a **Condition** (p. 1249) instance for a particular **Lock** (p. 2377) instance use its `newCondition()` method.

As an example, suppose we have a bounded buffer which supports put and take methods. If a take is attempted on an empty buffer, then the thread will block until an item becomes available; if a put is attempted on a full buffer, then the thread will block until a space becomes available. We would like to keep waiting put threads and take threads in separate wait-sets so that we can use the optimization of only notifying a single thread at a time when items or spaces become available in the buffer. This can be achieved using two **Condition** (p. 1249) instances.

```
class BoundedBuffer { Lock* lock = new ReentrantLock(); Condition* notFull = lock->newCondition(); Condition* notEmpty = lock->newCondition();
```

```
Object* items = new Object[100]; int putptr, takeptr, count;
```

```
public void put( Object* x ) throw( InterruptedException ) { lock->lock(); try { while( count == 100 ) notFull->await() (p. 1251); items[putptr] = x; if ( ++putptr == 100 ) putptr = 0; ++count; notEmpty->signal() (p. 1254); } catch(...) { lock->unlock(); } }
```

```
public Object take() throw( InterruptedException ) { lock->lock(); try { while(count == 0) notEmpty->await() (p. 1251); Object x = items[takeptr]; if ( ++takeptr == 100 ) takeptr = 0; --count; notFull->signal() (p. 1254); return x; } catch(...) { lock->unlock(); } }
```

(The `ArrayBlockingQueue` class provides this functionality, so there is no reason to implement this sample usage class.)

Implementation Considerations

When waiting upon a **Condition** (p. 1249), a "spurious wakeup" is permitted to occur, in general, as a concession to the underlying platform semantics. This has little practical impact on most application programs as a **Condition** (p. 1249) should always be waited upon in a loop, testing the state predicate that is being waited for. An implementation is free to remove the possibility of spurious wakeups but it is recommended that applications programmers always assume that they can occur and so always wait in a loop.

The three forms of condition waiting (interruptible, non-interruptible, and timed) may differ in their ease of implementation on some platforms and in their performance characteristics. In particular, it may be difficult to provide these features and maintain specific semantics such as ordering guarantees. Further, the ability to interrupt the actual suspension of the thread may not always be feasible to implement on all platforms.

Consequently, an implementation is not required to define exactly the same guarantees or semantics for all three forms of waiting, nor is it required to support interruption of the actual suspension of the thread.

An implementation is required to clearly document the semantics and guarantees provided by each of the waiting methods, and when an implementation does support interruption of thread suspension then it must obey the interruption semantics as defined in this interface.

As interruption generally implies cancellation, and checks for interruption are often infrequent, an implementation can favor responding to an interrupt over normal method return. This is true even if it can be shown that the interrupt occurred after another action may have unblocked the thread. An implementation should document this behavior.

Since:

1.0

6.212.2 Constructor & Destructor Documentation

6.212.2.1 virtual decaf::util::concurrent::locks::Condition::~~Condition () [inline, virtual]

6.212.3 Member Function Documentation

6.212.3.1 virtual bool decaf::util::concurrent::locks::Condition::await (long long *time*, const TimeUnit & *unit*) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException) [pure virtual]

Causes the current thread to wait until it is signaled or interrupted, or the specified waiting time elapses. This method is behaviorally equivalent to:

```
awaitNanos(unit.toNanos(time)) > 0
```

Parameters:

time - the maximum time to wait

unit - the time unit of the time argument

Returns:

false if the waiting time detectably elapsed before return from the method, else true

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p. 1249).

InterruptedException if the current thread is interrupted (and interruption of thread suspension is supported)

IllegalMonitorStateException if the caller is not the lock owner.

6.212.3.2 virtual void decaf::util::concurrent::locks::Condition::await () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException) [pure virtual]

Causes the current thread to wait until it is signaled or interrupted. The lock associated with this **Condition** (p. 1249) is atomically released and the current thread becomes disabled for thread scheduling purposes and lies dormant until one of four things happens:

- * Some other thread invokes the **signal()** (p. 1254) method for this **Condition** (p. 1249) and the current thread happens to be chosen as the thread to be awakened; or
- * Some other thread invokes the **signalAll()** (p. 1254) method for this **Condition** (p. 1249); or
- * Some other thread interrupts the current thread, and interruption of thread suspension is supported; or
- * A "spurious wakeup" occurs.

In all cases, before this method can return the current thread must re-acquire the lock associated with this condition. When the thread returns it is guaranteed to hold this lock.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting and interruption of thread suspension is supported,

then `InterruptedException` is thrown and the current thread's interrupted status is cleared. It is not specified, in the first case, whether or not the test for interruption occurs before the lock is released.

Implementation Considerations

The current thread is assumed to hold the lock associated with this **Condition** (p. 1249) when this method is called. It is up to the implementation to determine if this is the case and if not, how to respond. Typically, an exception will be thrown (such as `IllegalMonitorStateException`) and the implementation must document that fact.

An implementation can favor responding to an interrupt over normal method return in response to a signal. In that case the implementation must ensure that the signal is redirected to another waiting thread, if there is one.

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p. 1249).

InterruptedException if the current thread is interrupted (and interruption of thread suspension is supported)

IllegalMonitorStateException if the caller is not the lock owner.

```
6.212.3.3  virtual long long decaf::util::concurrent::locks::Condition::awaitNanos
            (long long nanosTimeout) throw ( de-
            caf::lang::exceptions::RuntimeException,
            decaf::lang::exceptions::InterruptedException, de-
            caf::lang::exceptions::IllegalMonitorStateException ) [pure
            virtual]
```

Causes the current thread to wait until it is signaled or interrupted, or the specified waiting time elapses. The lock associated with this condition is atomically released and the current thread becomes disabled for thread scheduling purposes and lies dormant until one of five things happens:

* Some other thread invokes the **signal()** (p. 1254) method for this **Condition** (p. 1249) and the current thread happens to be chosen as the thread to be awakened; or * Some other thread invokes the **signalAll()** (p. 1254) method for this **Condition** (p. 1249); or * Some other thread interrupts the current thread, and interruption of thread suspension is supported; or * The specified waiting time elapses; or * A "spurious wakeup" occurs.

In all cases, before this method can return the current thread must re-acquire the lock associated with this condition. When the thread returns it is guaranteed to hold this lock.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting and interruption of thread suspension is supported,

then `InterruptedException` is thrown and the current thread's interrupted status is cleared. It is not specified, in the first case, whether or not the test for interruption occurs before the lock is released.

The method returns an estimate of the number of nanoseconds remaining to wait given the supplied `nanosTimeout` value upon return, or a value less than or equal to zero if it timed out. This value can be used to determine whether and how long to re-wait in cases where the wait returns but an awaited condition still does not hold. Typical uses of this method take the following form:

```
synchronized boolean aMethod( long timeout, const TimeUnit& unit ) { long nanosTimeout =
unit.toNanos(timeout); while (!conditionBeingWaitedFor) { if (nanosTimeout > 0) nanosTimeout =
theCondition->awaitNanos(nanosTimeout); else return false; } // ... }
```

Design note: This method requires a nanosecond argument so as to avoid truncation errors in reporting remaining times. Such precision loss would make it difficult for programmers to ensure that total waiting times are not systematically shorter than specified when re-waits occur.

Implementation Considerations

The current thread is assumed to hold the lock associated with this **Condition** (p.1249) when this method is called. It is up to the implementation to determine if this is the case and if not, how to respond. Typically, an exception will be thrown (such as `IllegalMonitorStateException`) and the implementation must document that fact.

An implementation can favor responding to an interrupt over normal method return in response to a signal, or over indicating the elapse of the specified waiting time. In either case the implementation must ensure that the signal is redirected to another waiting thread, if there is one.

Parameters:

nanosTimeout - the maximum time to wait, in nanoseconds

Returns:

an estimate of the `nanosTimeout` value minus the time spent waiting upon return from this method. A positive value may be used as the argument to a subsequent call to this method to finish waiting out the desired time. A value less than or equal to zero indicates that no time remains.

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p.1249).

InterruptedException if the current thread is interrupted (and interruption of thread suspension is supported)

IllegalMonitorStateException if the caller is not the lock owner.

6.212.3.4 virtual void decaf::util::concurrent::locks::Condition::awaitUninterruptibly() throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalMonitorStateException`) [pure virtual]

Causes the current thread to wait until it is signalled. The lock associated with this condition is atomically released and the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

* Some other thread invokes the **signal()** (p.1254) method for this **Condition** (p.1249) and the current thread happens to be chosen as the thread to be awakened; or * Some other thread invokes the **signalAll()** (p.1254) method for this **Condition** (p.1249); or * A "spurious wakeup" occurs.

In all cases, before this method can return the current thread must re-acquire the lock associated with this condition. When the thread returns it is guaranteed to hold this lock.

If the current thread's interrupted status is set when it enters this method, or it is interrupted while waiting, it will continue to wait until signalled. When it finally returns from this method its interrupted status will still be set.

Implementation Considerations

The current thread is assumed to hold the lock associated with this **Condition** (p. 1249) when this method is called. It is up to the implementation to determine if this is the case and if not, how to respond. Typically, an exception will be thrown (such as `IllegalMonitorStateException`) and the implementation must document that fact.

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p. 1249).

IllegalMonitorStateException if the caller is not the lock owner.

6.212.3.5 `virtual bool decaf::util::concurrent::locks::Condition::awaitUntil (const Date & deadline) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalMonitorStateException)` [pure virtual]

6.212.3.6 `virtual void decaf::util::concurrent::locks::Condition::signal () throw (decaf::lang::exceptions::RuntimeException)` [pure virtual]

Wakes up one waiting thread. If any threads are waiting on this condition then one is selected for waking up. That thread must then re-acquire the lock before returning from await.

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p. 1249).

6.212.3.7 `virtual void decaf::util::concurrent::locks::Condition::signalAll () throw (decaf::lang::exceptions::RuntimeException)` [pure virtual]

Wakes up all waiting threads. If any threads are waiting on this condition then they are all woken up. Each thread must re-acquire the lock before it can return from await.

Exceptions:

RuntimeException if an unexpected error occurs while trying to wait on the **Condition** (p. 1249).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/locks/Condition.h`

6.213 decaf::util::concurrent::ConditionHandle Class Reference

```
#include <src/main/decaf/internal/util/concurrent/unix/ConditionHandle.h>
```

Public Member Functions

- **ConditionHandle** ()
- **~ConditionHandle** ()
- **ConditionHandle** ()
- **~ConditionHandle** ()

Data Fields

- pthread_cond_t **condition**
- MutexHandle * **mutex**
- HANDLE semaphore
- CRITICAL_SECTION **criticalSection**
- volatile unsigned int **numWaiting**
- volatile unsigned int **numWake**
- volatile unsigned int **generation**

6.213.1 Constructor & Destructor Documentation

6.213.1.1 decaf::util::concurrent::ConditionHandle::ConditionHandle () [inline]

6.213.1.2 decaf::util::concurrent::ConditionHandle::~~ConditionHandle () [inline]

6.213.1.3 decaf::util::concurrent::ConditionHandle::ConditionHandle () [inline]

6.213.1.4 decaf::util::concurrent::ConditionHandle::~~ConditionHandle () [inline]

6.213.2 Field Documentation

6.213.2.1 pthread_cond_t decaf::util::concurrent::ConditionHandle::condition

6.213.2.2 CRITICAL_SECTION decaf::util::concurrent::ConditionHandle::criticalSection

6.213.2.3 volatile unsigned int decaf::util::concurrent::ConditionHandle::generation

6.213.2.4 MutexHandle * decaf::util::concurrent::ConditionHandle::mutex

6.213.2.5 volatile unsigned int decaf::util::concurrent::ConditionHandle::numWaiting

6.213.2.6 volatile unsigned int decaf::util::concurrent::ConditionHandle::numWake

6.213.2.7 HANDLE decaf::util::concurrent::ConditionHandle::semaphore

The documentation for this class was generated from the following files:

- `src/main/decaf/internal/util/concurrent/unix/ConditionHandle.h`
- `src/main/decaf/internal/util/concurrent/windows/ConditionHandle.h`

6.214 decaf::internal::util::concurrent::ConditionImpl Class Reference

```
#include <src/main/decaf/internal/util/concurrent/ConditionImpl.h>
```

Static Public Member Functions

- static **decaf::util::concurrent::ConditionHandle** * **create** (decaf::util::concurrent::MutexHandle *mutex)
Creates the Condition object and attaches it to the given MutexHandle.
- static void **destroy** (decaf::util::concurrent::ConditionHandle *handle)
Destroy a previously create Condition instance.
- static void **wait** (decaf::util::concurrent::ConditionHandle *condition)
Waits for the condition to be signaled.
- static void **wait** (decaf::util::concurrent::ConditionHandle *condition, long long mills, long long nanos)
Waits for the condition to be signaled or for the time specified to ellapse.
- static void **notify** (decaf::util::concurrent::ConditionHandle *condition)
Signals one Thread that is waiting on this condition to wake up.
- static void **notifyAll** (decaf::util::concurrent::ConditionHandle *condition)
Signals all Threads that is waiting on this condition to wake up.

6.214.1 Member Function Documentation

6.214.1.1 static **decaf::util::concurrent::ConditionHandle***
decaf::internal::util::concurrent::ConditionImpl::create
(decaf::util::concurrent::MutexHandle * *mutex*) [static]

Creates the Condition object and attaches it to the given MutexHandle.

Parameters:

mutex the Mutex handle that this Condition is attached to.

Returns:

a newly constructed Condition handle that is attached to the given handle.

6.214.1.2 static void **decaf::internal::util::concurrent::ConditionImpl::destroy**
(decaf::util::concurrent::ConditionHandle * *handle*) [static]

Destroy a previously create Condition instance.

Parameters:

handle The Condition handle to be destroyed.

6.214.1.3 `static void decaf::internal::util::concurrent::ConditionImpl::notify`
(`decaf::util::concurrent::ConditionHandle * condition`) [static]

Signals one Thread that is waiting on this condition to wake up.

Parameters:

condition the handle to the condition to wait on.

6.214.1.4 `static void decaf::internal::util::concurrent::ConditionImpl::notifyAll`
(`decaf::util::concurrent::ConditionHandle * condition`) [static]

Signals all Threads that is waiting on this condition to wake up.

Parameters:

condition the handle to the condition to wait on.

6.214.1.5 `static void decaf::internal::util::concurrent::ConditionImpl::wait`
(`decaf::util::concurrent::ConditionHandle * condition, long long mills,
long long nanos`) [static]

Waits for the condition to be signaled or for the time specified to elapse.

Parameters:

condition the handle to the condition to wait on.

mills the time in milliseconds to wait for the condition to be signaled.

nanos additional time in nanoseconds to wait for the thread to be signaled.

6.214.1.6 `static void decaf::internal::util::concurrent::ConditionImpl::wait`
(`decaf::util::concurrent::ConditionHandle * condition`) [static]

Waits for the condition to be signaled.

Parameters:

condition the handle to the condition to wait on.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/concurrent/ConditionImpl.h`

6.215 decaf::net::ConnectException Class Reference

#include <src/main/decaf/net/ConnectException.h> Inheritance diagram for decaf::net::ConnectException:

Public Member Functions

- **ConnectException** () throw ()
Default Constructor.
- **ConnectException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **ConnectException** (const **ConnectException** &ex) throw ()
Copy Constructor.
- **ConnectException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ConnectException** (const std::exception *cause) throw ()
Constructor.
- **ConnectException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **ConnectException** * **clone** () const
Clones this exception.
- virtual ~**ConnectException** () throw ()

6.215.1 Constructor & Destructor Documentation

6.215.1.1 decaf::net::ConnectException::ConnectException () throw () [inline]

Default Constructor.

6.215.1.2 decaf::net::ConnectException::ConnectException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.215.1.3 `decaf::net::ConnectException::ConnectException (const ConnectException & ex) throw ()` [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.215.1.4 `decaf::net::ConnectException::ConnectException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.215.1.5 `decaf::net::ConnectException::ConnectException (const std::exception * cause) throw ()` [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.215.1.6 `decaf::net::ConnectException::ConnectException (const char * file, const int lineNumber, const char * msg, ...) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.215.1.7 virtual decaf::net::ConnectException::~~ConnectException () throw ()
[inline, virtual]

6.215.2 Member Function Documentation

6.215.2.1 virtual ConnectException* decaf::net::ConnectException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::net::SocketException** (p. 3522).

The documentation for this class was generated from the following file:

- src/main/decaf/net/**ConnectException.h**

6.216 cms::Connection Class Reference

The client's connection to its provider.

#include <src/main/cms/Connection.h> Inheritance diagram for cms::Connection:

Public Member Functions

- virtual **~Connection** ()
- virtual void **close** ()=0 throw (CMSEException)
Closes this connection as well as any Sessions created from it (and those Sessions' consumers and producers).
- virtual const **ConnectionMetaData** * **getMetaData** () const =0 throw (CMSEException)
Gets the metadata for this connection.
- virtual **Session** * **createSession** ()=0 throw (CMSEException)
Creates an AUTO_ACKNOWLEDGE Session (p. 3365).
- virtual **Session** * **createSession** (Session::AcknowledgeMode ackMode)=0 throw (CMSEException)
Creates a new Session (p. 3365) to work for this Connection (p. 1262) using the specified acknowledgment mode.
- virtual std::string **getClientID** () const =0
Get the Client Id for this session, the client Id is provider specific and is either assigned by the connection factory or set using the setClientID method.
- virtual void **setClientID** (const std::string &clientID)=0
Sets the client identifier for this connection.
- virtual **ExceptionListener** * **getExceptionListener** () const =0
Gets the registered Exception Listener for this connection.
- virtual void **setExceptionListener** (ExceptionListener *listener)=0
Sets the registered Exception Listener for this connection.

6.216.1 Detailed Description

The client's connection to its provider. Connections support concurrent use.

A connection serves several purposes:

- It encapsulates an open connection with a JMS provider. It typically represents an open TCP/IP socket between a client and the service provider software.
- Its creation is where client authentication takes place.

- It can specify a unique client identifier.
- It provides a **ConnectionMetaData** (p. 1385) object.
- It supports an optional **ExceptionListener** (p. 1838) object.

Because the creation of a connection involves setting up authentication and communication, a connection is a relatively heavy-weight object. Most clients will do all their messaging with a single connection. Other more advanced applications may use several connections. The CMS API does not architect a reason for using multiple connections; however, there may be operational reasons for doing so.

A CMS client typically creates a connection, one or more sessions, and a number of message producers and consumers. When a connection is created, it is in stopped mode. That means that no messages are being delivered.

It is typical to leave the connection in stopped mode until setup is complete (that is, until all message consumers have been created). At that point, the client calls the connection's start method, and messages begin arriving at the connection's consumers. This setup convention minimizes any client confusion that may result from asynchronous message delivery while the client is still in the process of setting itself up.

A connection can be started immediately, and the setup can be done afterwards. Clients that do this must be prepared to handle asynchronous message delivery while they are still in the process of setting up.

A message producer can send messages while a connection is stopped.

Since:

1.0

6.216.2 Constructor & Destructor Documentation

6.216.2.1 virtual cms::Connection::~~Connection () [inline, virtual]

6.216.3 Member Function Documentation

6.216.3.1 virtual void cms::Connection::close () throw (CMSException) [pure virtual]

Closes this connection as well as any Sessions created from it (and those Sessions' consumers and producers).

Exceptions:

CMSException (p. 1160)

Implements cms::Closeable (p. 1148).

Implemented in **activemq::core::ActiveMQConnection** (p. 279).

6.216.3.2 `virtual Session* cms::Connection::createSession
(Session::AcknowledgeMode ackMode) throw (CMSException) [pure
virtual]`

Creates a new **Session** (p. 3365) to work for this **Connection** (p. 1262) using the specified acknowledgment mode.

Parameters:

ackMode the Acknowledgment Mode to use.

Exceptions:

CMSException (p. 1160)

Implemented in **activemq::core::ActiveMQConnection** (p. 279).

6.216.3.3 `virtual Session* cms::Connection::createSession () throw (CMSException
) [pure virtual]`

Creates an AUTO_ACKNOWLEDGE **Session** (p. 3365).

Exceptions:

CMSException (p. 1160)

Implemented in **activemq::core::ActiveMQConnection** (p. 279).

6.216.3.4 `virtual std::string cms::Connection::getClientID () const [pure virtual]`

Get the Client Id for this session, the client Id is provider specific and is either assigned by the connection factory or set using the setClientID method.

Returns:

Client Id String for this **Connection** (p. 1262).

Exceptions:

CMSException (p. 1160) if the provider fails to return the client id or an internal error occurs.

Implemented in **activemq::core::ActiveMQConnection** (p. 281).

6.216.3.5 `virtual ExceptionListener* cms::Connection::getExceptionListener ()
const [pure virtual]`

Gets the registered Exception Listener for this connection.

Returns:

pointer to an exception listener or NULL

Implemented in **activemq::core::ActiveMQConnection** (p. 281).

6.216.3.6 virtual const ConnectionMetaData* cms::Connection::getMetaData () const throw (CMSEException) [pure virtual]

Gets the metadata for this connection.

Returns:

the connection MetaData pointer (caller does not own it).

Exceptions:

CMSEException (p. 1160) if the provider fails to get the connection metadata for this connection.

See also:

ConnectionMetaData (p. 1385)

Since:

2.0

Implemented in **activemq::core::ActiveMQConnection** (p. 282).

6.216.3.7 virtual void cms::Connection::setClientID (const std::string & clientID) [pure virtual]

Sets the client identifier for this connection. The preferred way to assign a CMS client's client identifier is for it to be configured in a client-specific **ConnectionFactory** (p. 1324) object and transparently assigned to the **Connection** (p. 1262) object it creates.

If a client sets the client identifier explicitly, it must do so immediately after it creates the connection and before any other action on the connection is taken. After this point, setting the client identifier is a programming error that should throw an **IllegalStateException** (p. 1997).

Parameters:

clientID The unique client identifier to assign to the **Connection** (p. 1262).

Exceptions:

CMSEException (p. 1160) if the provider fails to set the client id due to some internal error.

InvalidClientIDException if the id given is somehow invalid or is a duplicate.

IllegalStateException (p. 1997) if the client tries to set the id after a **Connection** (p. 1262) method has been called.

Implemented in **activemq::core::ActiveMQConnection** (p. 287).

6.216.3.8 virtual void cms::Connection::setExceptionListener (ExceptionListener * listener) [pure virtual]

Sets the registered Exception Listener for this connection.

Parameters:

listener pointer to and ExceptionListener (p. 1838)

Implemented in **activemq::core::ActiveMQConnection** (p. 288).

The documentation for this class was generated from the following file:

- `src/main/cms/Connection.h`

6.217 activemq::commands::ConnectionControl Class Reference

#include <src/main/activemq/commands/ConnectionControl.h> Inheritance diagram for activemq::commands::ConnectionControl:

Public Member Functions

- **ConnectionControl** ()
- virtual **~ConnectionControl** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConnectionControl** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual bool **isClose** () const
- virtual void **setClose** (bool close)
- virtual bool **isExit** () const
- virtual void **setExit** (bool exit)
- virtual bool **isFaultTolerant** () const
- virtual void **setFaultTolerant** (bool faultTolerant)
- virtual bool **isResume** () const
- virtual void **setResume** (bool resume)
- virtual bool **isSuspend** () const
- virtual void **setSuspend** (bool suspend)
- virtual const std::string & **getConnectedBrokers** () const
- virtual std::string & **getConnectedBrokers** ()
- virtual void **setConnectedBrokers** (const std::string &connectedBrokers)
- virtual const std::string & **getReconnectTo** () const
- virtual std::string & **getReconnectTo** ()
- virtual void **setReconnectTo** (const std::string &reconnectTo)
- virtual bool **isRebalanceConnection** () const
- virtual void **setRebalanceConnection** (bool rebalanceConnection)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_CONNECTIONCONTROL** = 18

Protected Attributes

- bool **close**
- bool **exit**
- bool **faultTolerant**
- bool **resume**
- bool **suspend**
- std::string **connectedBrokers**
- std::string **reconnectTo**
- bool **rebalanceConnection**

6.217.1 Constructor & Destructor Documentation

6.217.1.1 `activemq::commands::ConnectionControl::ConnectionControl ()`

6.217.1.2 `virtual activemq::commands::ConnectionControl::~~ConnectionControl ()`
[virtual]

6.217.2 Member Function Documentation

6.217.2.1 `virtual ConnectionControl* activemq::commands::ConnectionControl::cloneDataStructure () const`
[virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.217.2.2 `virtual void activemq::commands::ConnectionControl::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.217.2.3 virtual bool activemq::commands::ConnectionControl::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.217.2.4 virtual std::string& activemq::commands::ConnectionControl::getConnectedBrokers () [virtual]

6.217.2.5 virtual const std::string& activemq::commands::ConnectionControl::getConnectedBrokers () const [virtual]

6.217.2.6 virtual unsigned char activemq::commands::ConnectionControl::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.217.2.7 `virtual std::string& activemq::commands::ConnectionControl::getReconnectTo ()`
[virtual]
- 6.217.2.8 `virtual const std::string& activemq::commands::ConnectionControl::getReconnectTo ()`
`const` [virtual]
- 6.217.2.9 `virtual bool activemq::commands::ConnectionControl::isClose () const`
[virtual]
- 6.217.2.10 `virtual bool activemq::commands::ConnectionControl::isExit () const`
[virtual]
- 6.217.2.11 `virtual bool activemq::commands::ConnectionControl::isFaultTolerant () const` [virtual]
- 6.217.2.12 `virtual bool activemq::commands::ConnectionControl::isRebalanceConnection () const`
[virtual]
- 6.217.2.13 `virtual bool activemq::commands::ConnectionControl::isResume ()`
`const` [virtual]
- 6.217.2.14 `virtual bool activemq::commands::ConnectionControl::isSuspend ()`
`const` [virtual]
- 6.217.2.15 `virtual void activemq::commands::ConnectionControl::setClose (bool`
`close)` [virtual]
- 6.217.2.16 `virtual void activemq::commands::ConnectionControl::setConnectedBrokers (const`
`std::string & connectedBrokers)` [virtual]
- 6.217.2.17 `virtual void activemq::commands::ConnectionControl::setExit (bool`
`exit)` [virtual]
- 6.217.2.18 `virtual void activemq::commands::ConnectionControl::setFaultTolerant`
`(bool faultTolerant)` [virtual]
- 6.217.2.19 `virtual void activemq::commands::ConnectionControl::setRebalanceConnection (bool`
`rebalanceConnection)` [virtual]
- 6.217.2.20 `virtual void activemq::commands::ConnectionControl::setReconnectTo`
`(const std::string & reconnectTo)` [virtual]
- 6.217.2.21 `virtual void activemq::commands::ConnectionControl::setResume (bool`
`resume)` [virtual]
- 6.217.2.22 `virtual void activemq::commands::ConnectionControl::setSuspend (bool`
`suspend)` [virtual]
- 6.217.2.23 `virtual std::string activemq::commands::ConnectionControl::toString ()`
`const` [virtual]

Generated on Wed Nov 10 22:25:45 2010 for activemq-cpp-3.2.3 by Doxygen

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

```
6.217.2.24 virtual Pointer<Command> ac-
    tivemq::commands::ConnectionControl::visit
    (activemq::state::CommandVisitor * visitor) throw (
    exceptions::ActiveMQException ) [virtual]
```

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements `activemq::commands::Command` (p. 1198).

6.217.3 Field Documentation

- 6.217.3.1** `bool activemq::commands::ConnectionControl::close` [protected]
- 6.217.3.2** `std::string activemq::commands::ConnectionControl::connectedBrokers` [protected]
- 6.217.3.3** `bool activemq::commands::ConnectionControl::exit` [protected]
- 6.217.3.4** `bool activemq::commands::ConnectionControl::faultTolerant` [protected]
- 6.217.3.5** `const unsigned char activemq::commands::ConnectionControl::ID_ - CONNECTIONCONTROL = 18` [static]
- 6.217.3.6** `bool activemq::commands::ConnectionControl::rebalanceConnection` [protected]
- 6.217.3.7** `std::string activemq::commands::ConnectionControl::reconnectTo` [protected]
- 6.217.3.8** `bool activemq::commands::ConnectionControl::resume` [protected]
- 6.217.3.9** `bool activemq::commands::ConnectionControl::suspend` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ConnectionControl.h`

6.218 activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1272).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConnectionControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller:

Public Member Functions

- **ConnectionControlMarshaller** ()
- virtual **~ConnectionControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.218.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1272).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.218.2 Constructor & Destructor Documentation

6.218.2.1 `activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::ConnectionControlMarshaller()` [inline]

6.218.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` [inline, virtual]

6.218.3 Member Function Documentation

6.218.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.218.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.218.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.218.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.218.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.218.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.218.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConnectionControlMarshaller.h

6.219 activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1276).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConnectionControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller:

Public Member Functions

- **ConnectionControlMarshaller** ()
- virtual **~ConnectionControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.219.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1276).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.219.2 Constructor & Destructor Documentation

6.219.2.1 `activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::ConnectionControlMarshaller()` `[inline]`

6.219.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` `[inline, virtual]`

6.219.3 Member Function Documentation

6.219.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.219.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.219.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.219.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.219.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.219.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.219.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConnectionControlMarshaller.h

6.220 activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1280).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller:

Public Member Functions

- **ConnectionControlMarshaller** ()
- virtual **~ConnectionControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.220.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **ConnectionControlMarshaller** (p. 1280).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.220.2 Constructor & Destructor Documentation

6.220.2.1 `activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::ConnectionControlMarshaller()` [inline]

6.220.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` [inline, virtual]

6.220.3 Member Function Documentation

6.220.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.220.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.220.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.220.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.220.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.220.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.220.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h

6.221 activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1284).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConnectionControlMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller`:

Public Member Functions

- `ConnectionControlMarshaller ()`
- `virtual ~ConnectionControlMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.221.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1284).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.221.2 Constructor & Destructor Documentation

6.221.2.1 `activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::ConnectionControlMarshaller()` [inline]

6.221.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` [inline, virtual]

6.221.3 Member Function Documentation

6.221.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.221.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.221.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.221.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.221.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.221.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.221.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConnectionControlMarshaller.h

6.222 activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1288).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConnectionControlMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller`:

Public Member Functions

- `ConnectionControlMarshaller ()`
- `virtual ~ConnectionControlMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.222.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1288).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.222.2 Constructor & Destructor Documentation

6.222.2.1 `activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::ConnectionControlMarshaller()` [inline]

6.222.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` [inline, virtual]

6.222.3 Member Function Documentation

6.222.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.222.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.222.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.222.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.222.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.222.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.222.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConnectionControlMarshaller.h

6.223 activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1292).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConnectionControlMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller`:

Public Member Functions

- `ConnectionControlMarshaller ()`
- `virtual ~ConnectionControlMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.223.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `ConnectionControlMarshaller` (p. 1292).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.223.2 Constructor & Destructor Documentation

6.223.2.1 `activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::ConnectionControlMarshaller()` [inline]

6.223.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::~~ConnectionControlMarshaller()` [inline, virtual]

6.223.3 Member Function Documentation

6.223.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.223.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.223.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.223.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.223.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.223.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.223.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConnectionControlMarshaller.h

6.224 activemq::commands::ConnectionError Class Reference

#include <src/main/activemq/commands/ConnectionError.h> Inheritance diagram for activemq::commands::ConnectionError:

Public Member Functions

- **ConnectionError** ()
- virtual **~ConnectionError** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConnectionError** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **BrokerError** > & **getException** () const
- virtual **Pointer**< **BrokerError** > & **getException** ()
- virtual void **setException** (const **Pointer**< **BrokerError** > &exception)
- virtual const **Pointer**< **ConnectionId** > & **getConnectionId** () const
- virtual **Pointer**< **ConnectionId** > & **getConnectionId** ()
- virtual void **setConnectionId** (const **Pointer**< **ConnectionId** > &connectionId)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_CONNECTIONERROR** = 16

Protected Attributes

- **Pointer**< **BrokerError** > exception
- **Pointer**< **ConnectionId** > connectionId

6.224.1 Constructor & Destructor Documentation

6.224.1.1 `activemq::commands::ConnectionError::ConnectionError ()`

6.224.1.2 `virtual activemq::commands::ConnectionError::~~ConnectionError ()`
[virtual]

6.224.2 Member Function Documentation

6.224.2.1 `virtual ConnectionError* activemq::commands::ConnectionError::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.224.2.2 `virtual void activemq::commands::ConnectionError::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.224.2.3 `virtual bool activemq::commands::ConnectionError::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.224.2.4 `virtual Pointer<ConnectionId>& activemq::commands::ConnectionError::getConnectionId ()`
[virtual]
- 6.224.2.5 `virtual const Pointer<ConnectionId>& activemq::commands::ConnectionError::getConnectionId ()`
`const` [virtual]
- 6.224.2.6 `virtual unsigned char activemq::commands::ConnectionError::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.224.2.7 `virtual Pointer<BrokerError>& activemq::commands::ConnectionError::getException ()`
[virtual]
- 6.224.2.8 `virtual const Pointer<BrokerError>& activemq::commands::ConnectionError::getException ()`
`const` [virtual]
- 6.224.2.9 `virtual void activemq::commands::ConnectionError::setConnectionId`
`(const Pointer< ConnectionId > & connectionId)` [virtual]
- 6.224.2.10 `virtual void activemq::commands::ConnectionError::setException (const`
`Pointer< BrokerError > & exception)` [virtual]
- 6.224.2.11 `virtual std::string activemq::commands::ConnectionError::toString ()`
`const` [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.224.2.12 `virtual Pointer<Command> activemq::commands::ConnectionError::visit`
`(activemq::state::CommandVisitor * visitor) throw (`
`exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

- a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.224.3 Field Documentation

6.224.3.1 **Pointer<ConnectionId>** **activemq::commands::ConnectionError::connectionId**
[protected]

6.224.3.2 **Pointer<BrokerError>** **activemq::commands::ConnectionError::exception**
[protected]

6.224.3.3 **const unsigned char** **activemq::commands::ConnectionError::ID_ - CONNECTIONERROR = 16** [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ConnectionError.h`

6.225 activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1300).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.225.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1300).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.225.2 Constructor & Destructor Documentation

6.225.2.1 `activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.225.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.225.3 Member Function Documentation

6.225.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.225.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.225.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.225.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.225.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.225.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.225.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h

6.226 activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1304).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.226.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1304).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.226.2 Constructor & Destructor Documentation

6.226.2.1 `activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.226.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.226.3 Member Function Documentation

6.226.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.226.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.226.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.226.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.226.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.226.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.226.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConnectionErrorMarshaller.h

6.227 activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1308).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.227.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1308).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.227.2 Constructor & Destructor Documentation

6.227.2.1 `activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.227.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.227.3 Member Function Documentation

6.227.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.227.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.227.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.227.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.227.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.227.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.227.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h

6.228 activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1312).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.228.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1312).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.228.2 Constructor & Destructor Documentation

6.228.2.1 `activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.228.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.228.3 Member Function Documentation

6.228.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.228.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.228.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.228.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.228.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.228.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.228.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionErrorMarshaller.h

6.229 activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1316).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.229.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1316).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.229.2 Constructor & Destructor Documentation

6.229.2.1 `activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.229.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.229.3 Member Function Documentation

6.229.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.229.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.229.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.229.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.229.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.229.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.229.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConnectionErrorMarshaller.h

6.230 activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1320).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConnectionErrorMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller:

Public Member Functions

- **ConnectionErrorMarshaller** ()
- virtual **~ConnectionErrorMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.230.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1320).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.230.2 Constructor & Destructor Documentation

6.230.2.1 `activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::ConnectionErrorMarshaller()` [inline]

6.230.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::~~ConnectionErrorMarshaller()` [inline, virtual]

6.230.3 Member Function Documentation

6.230.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.230.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.230.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.230.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.230.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.230.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.230.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConnectionErrorMarshaller.h

6.231 cms::ConnectionFactory Class Reference

Defines the interface for a factory that creates connection objects, the **Connection** (p.1262) objects returned implement the CMS **Connection** (p.1262) interface and hide the CMS Provider specific implementation details behind that interface.

#include <src/main/cms/ConnectionFactory.h> Inheritance diagram for cms::ConnectionFactory:

Public Member Functions

- virtual **~ConnectionFactory** ()
- virtual **Connection * createConnection** ()=0 throw (CMSEException)
Creates a connection with the default user identity.
- virtual **cms::Connection * createConnection** (const std::string &username, const std::string &password)=0 throw (cms::CMSEException)
Creates a connection with the default specified identity.
- virtual **cms::Connection * createConnection** (const std::string &username, const std::string &password, const std::string &clientId)=0 throw (cms::CMSEException)
Creates a connection with the specified user identity.

Static Public Member Functions

- static **ConnectionFactory * createCMSConnectionFactory** (const std::string &brokerURI) throw (cms::CMSEException)
Static method that is used to create a provider specific connection factory.

6.231.1 Detailed Description

Defines the interface for a factory that creates connection objects, the **Connection** (p.1262) objects returned implement the CMS **Connection** (p.1262) interface and hide the CMS Provider specific implementation details behind that interface. A Client creates a new **ConnectionFactory** (p.1324) either directly by instantiating the provider specific implementation of the factory or by using the static method **createCMSConnectionFactory** which all providers are required to implement.

Since:

1.0

6.231.2 Constructor & Destructor Documentation

6.231.2.1 `virtual cms::ConnectionFactory::~~ConnectionFactory () [inline, virtual]`

6.231.3 Member Function Documentation

6.231.3.1 `static ConnectionFactory* cms::ConnectionFactory::createCMSConnectionFactory (const std::string & brokerURI) throw (cms::CMSException) [static]`

Static method that is used to create a provider specific connection factory. The provider implements this method in their library and returns an instance of a **ConnectionFactory** (p.1324) derived object. Clients can use this method to remain abstracted from the specific CMS implementation being used.

Parameters:

brokerURI The remote address to use to connect to the Provider.

Returns:

A pointer to a provider specific implementation of the **ConnectionFactory** (p.1324) interface, the caller is responsible for deleting this resource.

Exceptions:

CMSException (p. 1160) if an internal error occurs while creating the **ConnectionFactory** (p.1324).

6.231.3.2 `virtual cms::Connection* cms::ConnectionFactory::createConnection (const std::string & username, const std::string & password, const std::string & clientId) throw (cms::CMSException) [pure virtual]`

Creates a connection with the specified user identity. The connection is created in stopped mode. No messages will be delivered until the **Connection.start** (p. 3586) method is explicitly called. The user name and password values passed here do not change the defaults, subsequent calls to the parameterless createConnection will continue to use the default values that were set in the Constructor.

Parameters:

username The user name used to authenticate with the Provider.

password The password used to authenticate with the Provider.

clientId The Client Id assigned to connection. If the id is the empty string ("") then a random client Id is created for this connection.

Returns:

A pointer to a connection object, caller owns the pointer and is responsible for closing the connection and deleting the instance.

Exceptions:

CMSException (p. 1160) if an internal error occurs while creating the **Connection** (p.1262).

Implemented in **activemq::core::ActiveMQConnectionFactory** (p. 295).

6.231.3.3 **virtual cms::Connection* cms::ConnectionFactory::createConnection**
(const std::string & *username*, const std::string & *password*) throw (
cms::CMSException) [pure virtual]

Creates a connection with the default specified identity. The connection is created in stopped mode. No messages will be delivered until the **Connection.start** (p. 3586) method is explicitly called. The username and password values passed here do not change the defaults, subsequent calls to the parameterless createConnection will continue to use the default values that were set in the Constructor.

Parameters:

username The user name used to authenticate with the Provider.

password The password used to authenticate with the Provider.

Returns:

A pointer to a connection object, caller owns the pointer and is responsible for closing the connection and deleting the instance.

Exceptions:

CMSException (p. 1160) if an internal error occurs while creating the **Connection** (p. 1262).

Implemented in **activemq::core::ActiveMQConnectionFactory** (p. 296).

6.231.3.4 **virtual Connection* cms::ConnectionFactory::createConnection ()** throw
(CMSException) [pure virtual]

Creates a connection with the default user identity. The connection is created in stopped mode. No messages will be delivered until the **Connection.start** (p. 3586) method is explicitly called.

Returns:

A pointer to a connection object, caller owns the pointer and is responsible for closing the connection and deleting the instance.

Exceptions:

CMSException (p. 1160) if an internal error occurs while creating the **Connection** (p. 1262).

Implemented in **activemq::core::ActiveMQConnectionFactory** (p. 296).

The documentation for this class was generated from the following file:

- src/main/cms/ConnectionFactory.h

6.232 activemq::commands::ConnectionId Class Reference

#include <src/main/activemq/commands/ConnectionId.h> Inheritance diagram for activemq::commands::ConnectionId:

Public Types

- typedef decaf::lang::PointerComparator< ConnectionId > COMPARATOR

Public Member Functions

- **ConnectionId** ()
- **ConnectionId** (const **ConnectionId** &other)
- **ConnectionId** (const **SessionId** *sessionId)
- **ConnectionId** (const **ProducerId** *producerId)
- **ConnectionId** (const **ConsumerId** *consumerId)
- virtual ~**ConnectionId** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConnectionId** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getValue** () const
- virtual std::string & **getValue** ()
- virtual void **setValue** (const std::string &value)
- virtual int **compareTo** (const **ConnectionId** &value) const
- virtual bool **equals** (const **ConnectionId** &value) const
- virtual bool **operator==** (const **ConnectionId** &value) const
- virtual bool **operator<** (const **ConnectionId** &value) const
- **ConnectionId** & **operator=** (const **ConnectionId** &other)

Static Public Attributes

- static const unsigned char **ID_CONNECTIONID** = 120

Protected Attributes

- `std::string value`

6.232.1 Member Typedef Documentation

6.232.1.1 `typedef decaf::lang::PointerComparator<ConnectionId>
activemq::commands::ConnectionId::COMPARATOR`

6.232.2 Constructor & Destructor Documentation

6.232.2.1 `activemq::commands::ConnectionId::ConnectionId ()`

6.232.2.2 `activemq::commands::ConnectionId::ConnectionId (const ConnectionId
& other)`

6.232.2.3 `activemq::commands::ConnectionId::ConnectionId (const SessionId *
sessionId)`

6.232.2.4 `activemq::commands::ConnectionId::ConnectionId (const ProducerId *
producerId)`

6.232.2.5 `activemq::commands::ConnectionId::ConnectionId (const ConsumerId *
consumerId)`

6.232.2.6 `virtual activemq::commands::ConnectionId::~~ConnectionId () [virtual]`

6.232.3 Member Function Documentation

6.232.3.1 `virtual ConnectionId* ac-
tivemq::commands::ConnectionId::cloneDataStructure ()
const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.232.3.2 `virtual int activemq::commands::ConnectionId::compareTo (const
ConnectionId & value) const [virtual]`

6.232.3.3 `virtual void activemq::commands::ConnectionId::copyDataStructure
(const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.232.3.4 virtual bool activemq::commands::ConnectionId::equals (const ConnectionId & *value*) const [virtual]

6.232.3.5 virtual bool activemq::commands::ConnectionId::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.232.3.6 virtual unsigned char activemq::commands::ConnectionId::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.232.3.7 virtual std::string& activemq::commands::ConnectionId::getValue () [virtual]

6.232.3.8 virtual const std::string& activemq::commands::ConnectionId::getValue () const [virtual]

6.232.3.9 virtual bool activemq::commands::ConnectionId::operator< (const ConnectionId & *value*) const [virtual]

6.232.3.10 ConnectionId& activemq::commands::ConnectionId::operator= (const ConnectionId & *other*)

6.232.3.11 virtual bool activemq::commands::ConnectionId::operator== (const ConnectionId & *value*) const [virtual]

6.232.3.12 virtual void activemq::commands::ConnectionId::setValue (const std::string & *value*) [virtual]

6.232.3.13 virtual std::string activemq::commands::ConnectionId::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p. 833).

6.232.4 Field Documentation

6.232.4.1 `const unsigned char activemq::commands::ConnectionId::ID_ - CONNECTIONID = 120` [static]

Referenced by `activemq::state::CommandVisitorAdapter::processRemoveInfo()`.

6.232.4.2 `std::string activemq::commands::ConnectionId::value` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ConnectionId.h`

6.233 activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1331).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.233.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1331).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.233.2 Constructor & Destructor Documentation

6.233.2.1 `activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.233.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.233.3 Member Function Documentation

6.233.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.233.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.233.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.233.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.233.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.233.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.233.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConnectionIdMarshaller.h

6.234 activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1335).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.234.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1335).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.234.2 Constructor & Destructor Documentation

6.234.2.1 `activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.234.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.234.3 Member Function Documentation

6.234.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.234.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.234.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.234.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.234.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.234.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.234.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConnectionIdMarshaller.h

6.235 activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1339).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.235.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1339).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.235.2 Constructor & Destructor Documentation

6.235.2.1 `activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.235.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.235.3 Member Function Documentation

6.235.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.235.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.235.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.235.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.235.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.235.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.235.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConnectionIdMarshaller.h

6.236 activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1343).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.236.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1343).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.236.2 Constructor & Destructor Documentation

6.236.2.1 `activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.236.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.236.3 Member Function Documentation

6.236.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.236.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.236.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.236.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.236.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.236.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.236.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h

6.237 activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1347).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.237.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1347).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.237.2 Constructor & Destructor Documentation

6.237.2.1 `activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.237.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.237.3 Member Function Documentation

6.237.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.237.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.237.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.237.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.237.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.237.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.237.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConnectionIdMarshaller.h

6.238 activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1351).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConnectionIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller:

Public Member Functions

- **ConnectionIdMarshaller** ()
- virtual **~ConnectionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.238.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionIdMarshaller** (p.1351).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.238.2 Constructor & Destructor Documentation

6.238.2.1 `activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::ConnectionIdMarshaller()` [inline]

6.238.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::~~ConnectionIdMarshaller()` [inline, virtual]

6.238.3 Member Function Documentation

6.238.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.238.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.238.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.238.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.238.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.238.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.238.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConnectionIdMarshaller.h

6.239 activemq::commands::ConnectionInfo Class Reference

#include <src/main/activemq/commands/ConnectionInfo.h> Inheritance diagram for activemq::commands::ConnectionInfo:

Public Member Functions

- **ConnectionInfo** ()
- virtual **~ConnectionInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConnectionInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- **Pointer< RemoveInfo > createRemoveCommand** () const
- virtual const **Pointer< ConnectionId > & getConnectionId** () const
- virtual **Pointer< ConnectionId > & getConnectionId** ()
- virtual void **setConnectionId** (const **Pointer< ConnectionId > &connectionId**)
- virtual const std::string & **getClientId** () const
- virtual std::string & **getClientId** ()
- virtual void **setClientId** (const std::string &clientId)
- virtual const std::string & **getPassword** () const
- virtual std::string & **getPassword** ()
- virtual void **setPassword** (const std::string &password)
- virtual const std::string & **getUserName** () const
- virtual std::string & **getUserName** ()
- virtual void **setUserName** (const std::string &userName)
- virtual const std::vector< **decaf::lang::Pointer< BrokerId > > & getBrokerPath** () const
- virtual std::vector< **decaf::lang::Pointer< BrokerId > > & getBrokerPath** ()
- virtual void **setBrokerPath** (const std::vector< **decaf::lang::Pointer< BrokerId > > &brokerPath**)
- virtual bool **isBrokerMasterConnector** () const
- virtual void **setBrokerMasterConnector** (bool brokerMasterConnector)
- virtual bool **isManageable** () const
- virtual void **setManageable** (bool manageable)

- virtual bool **isClientMaster** () const
- virtual void **setClientMaster** (bool **clientMaster**)
- virtual bool **isFaultTolerant** () const
- virtual void **setFaultTolerant** (bool **faultTolerant**)
- virtual bool **isConnectionInfo** () const
- virtual **Pointer< Command > visit** (**activemq::state::CommandVisitor** *visitor) throw (exceptions::ActiveMQException)

Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID _ CONNECTIONINFO** = 3

Protected Attributes

- **Pointer< ConnectionId > connectionId**
- std::string **clientId**
- std::string **password**
- std::string **userName**
- std::vector< **decaf::lang::Pointer< BrokerId > > brokerPath**
- bool **brokerMasterConnector**
- bool **manageable**
- bool **clientMaster**
- bool **faultTolerant**

6.239.1 Constructor & Destructor Documentation

6.239.1.1 **activemq::commands::ConnectionInfo::ConnectionInfo** ()

6.239.1.2 **virtual activemq::commands::ConnectionInfo::~~ConnectionInfo** ()
[virtual]

6.239.2 Member Function Documentation

6.239.2.1 **virtual ConnectionInfo* activemq::commands::ConnectionInfo::cloneDataStructure** ()
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.239.2.2 virtual void activemq::commands::ConnectionInfo::copyDataStructure (const DataStructure * *src*) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.239.2.3 Pointer<RemoveInfo> activemq::commands::ConnectionInfo::createRemoveCommand () const

6.239.2.4 virtual bool activemq::commands::ConnectionInfo::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.239.2.5 virtual std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ConnectionInfo::getBrokerPath () [virtual]

6.239.2.6 virtual const std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ConnectionInfo::getBrokerPath () const [virtual]

6.239.2.7 virtual std::string& activemq::commands::ConnectionInfo::getClientId () [virtual]

6.239.2.8 virtual const std::string& activemq::commands::ConnectionInfo::getClientId () const [virtual]

6.239.2.9 virtual Pointer<ConnectionId>& activemq::commands::ConnectionInfo::getConnectionId () [virtual]

6.239.2.10 virtual const Pointer<ConnectionId>& activemq::commands::ConnectionInfo::getConnectionId () const [virtual]

6.239.2.11 virtual unsigned char activemq::commands::ConnectionInfo::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSet** (p. 1660) type copy.

Implements **activemq::commands::DataSet** (p. 1662).

6.239.2.12 `virtual std::string& activemq::commands::ConnectionInfo::getPassword()
() [virtual]`

6.239.2.13 `virtual const std::string& activemq::commands::ConnectionInfo::getPassword()
() const [virtual]`

6.239.2.14 `virtual std::string& activemq::commands::ConnectionInfo::getUserName()
() [virtual]`

6.239.2.15 `virtual const std::string& activemq::commands::ConnectionInfo::getUserName()
() const [virtual]`

6.239.2.16 `virtual bool activemq::commands::ConnectionInfo::isBrokerMasterConnector()
() const [virtual]`

6.239.2.17 `virtual bool activemq::commands::ConnectionInfo::isClientMaster()
() const [virtual]`

6.239.2.18 `virtual bool activemq::commands::ConnectionInfo::isConnectionInfo()
() const [inline, virtual]`

Returns:

an answer of true to the **isConnectionInfo()** (p. 1358) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 761).

- 6.239.2.19 virtual bool activemq::commands::ConnectionInfo::isFaultTolerant ()
const [virtual]
- 6.239.2.20 virtual bool activemq::commands::ConnectionInfo::isManageable ()
const [virtual]
- 6.239.2.21 virtual void activemq::commands::ConnectionInfo::setBrokerMasterConnector (bool
brokerMasterConnector) [virtual]
- 6.239.2.22 virtual void activemq::commands::ConnectionInfo::setBrokerPath
(const std::vector< decaf::lang::Pointer< BrokerId > > & *brokerPath*)
[virtual]
- 6.239.2.23 virtual void activemq::commands::ConnectionInfo::setClientId (const
std::string & *clientId*) [virtual]
- 6.239.2.24 virtual void activemq::commands::ConnectionInfo::setClientMaster
(bool *clientMaster*) [virtual]
- 6.239.2.25 virtual void activemq::commands::ConnectionInfo::setConnectionId
(const Pointer< ConnectionId > & *connectionId*) [virtual]
- 6.239.2.26 virtual void activemq::commands::ConnectionInfo::setFaultTolerant
(bool *faultTolerant*) [virtual]
- 6.239.2.27 virtual void activemq::commands::ConnectionInfo::setManageable (bool
manageable) [virtual]
- 6.239.2.28 virtual void activemq::commands::ConnectionInfo::setPassword (const
std::string & *password*) [virtual]
- 6.239.2.29 virtual void activemq::commands::ConnectionInfo::setUserName (const
std::string & *userName*) [virtual]
- 6.239.2.30 virtual std::string activemq::commands::ConnectionInfo::toString ()
const [virtual]

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.239.2.31 virtual Pointer<Command> activemq::commands::ConnectionInfo::visit
(activemq::state::CommandVisitor * *visitor*) throw (
exceptions::ActiveMQException) [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.239.3 Field Documentation

- 6.239.3.1** **bool** **activemq::commands::ConnectionInfo::brokerMasterConnector** [protected]
- 6.239.3.2** **std::vector< decaf::lang::Pointer<BrokerId> >**
activemq::commands::ConnectionInfo::brokerPath [protected]
- 6.239.3.3** **std::string** **activemq::commands::ConnectionInfo::clientId** [protected]
- 6.239.3.4** **bool** **activemq::commands::ConnectionInfo::clientMaster** [protected]
- 6.239.3.5** **Pointer<ConnectionId>** **activemq::commands::ConnectionInfo::connectionId** [protected]
- 6.239.3.6** **bool** **activemq::commands::ConnectionInfo::faultTolerant** [protected]
- 6.239.3.7** **const unsigned char** **activemq::commands::ConnectionInfo::ID_ - CONNECTIONINFO = 3** [static]
- 6.239.3.8** **bool** **activemq::commands::ConnectionInfo::manageable** [protected]
- 6.239.3.9** **std::string** **activemq::commands::ConnectionInfo::password** [protected]
- 6.239.3.10** **std::string** **activemq::commands::ConnectionInfo::userName** [protected]

The documentation for this class was generated from the following file:

- **src/main/activemq/commands/ConnectionInfo.h**

6.240 activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1361).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.240.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1361).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.240.2 Constructor & Destructor Documentation

6.240.2.1 `activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::ConnectionInfoM
() [inline]`

6.240.2.2 `virtual
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::~~ConnectionInfo
() [inline, virtual]`

6.240.3 Member Function Documentation

6.240.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.240.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::getDataStructureT
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.240.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.240.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.240.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.240.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.240.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConnectionInfoMarshaller.h

6.241 activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1365).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.241.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1365).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.241.2 Constructor & Destructor Documentation

6.241.2.1 `activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::ConnectionInfoMarshaller()` [inline]

6.241.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::~~ConnectionInfoMarshaller()` [inline, virtual]

6.241.3 Member Function Documentation

6.241.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.241.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.241.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.241.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.241.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.241.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.241.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConnectionInfoMarshaller.h

6.242 activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1369).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.242.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1369).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.242.2 Constructor & Destructor Documentation

6.242.2.1 `activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::ConnectionInfoM
() [inline]`

6.242.2.2 `virtual
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::~~ConnectionInfo
() [inline, virtual]`

6.242.3 Member Function Documentation

6.242.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.242.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::getDataStructureT
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.242.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.242.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.242.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.242.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.242.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConnectionInfoMarshaller.h

6.243 activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1373).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.243.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1373).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.243.2 Constructor & Destructor Documentation

6.243.2.1 `activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::ConnectionInfoMarshaller()` [inline]

6.243.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::~~ConnectionInfoMarshaller()` [inline, virtual]

6.243.3 Member Function Documentation

6.243.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.243.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.243.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.243.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.243.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.243.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.243.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h

6.244 activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1377).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.244.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1377).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.244.2 Constructor & Destructor Documentation

6.244.2.1 `activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::ConnectionInfoM
() [inline]`

6.244.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::~~ConnectionInfo
() [inline, virtual]`

6.244.3 Member Function Documentation

6.244.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.244.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::getDataStructureT
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.244.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.244.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.244.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.244.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.244.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConnectionInfoMarshaller.h

6.245 activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1381).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConnectionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller:

Public Member Functions

- **ConnectionInfoMarshaller** ()
- virtual **~ConnectionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.245.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1381).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.245.2 Constructor & Destructor Documentation

6.245.2.1 `activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::ConnectionInfoM
() [inline]`

6.245.2.2 `virtual
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::~~ConnectionInfo
() [inline, virtual]`

6.245.3 Member Function Documentation

6.245.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.245.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::getDataStructureT
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.245.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.245.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.245.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.245.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.245.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConnectionInfoMarshaller.h

6.246 cms::ConnectionMetaData Class Reference

A **ConnectionMetaData** (p.1385) object provides information describing the **Connection** (p.1262) object.

#include <src/main/cms/ConnectionMetaData.h> Inheritance diagram for cms::ConnectionMetaData:

Public Member Functions

- virtual **~ConnectionMetaData** ()
- virtual std::string **getCMSVersion** () const =0 throw (cms::CMSEException)
Gets the CMS API version.
- virtual int **getCMSMajorVersion** () const =0 throw (cms::CMSEException)
Gets the CMS major version number.
- virtual int **getCMSMinorVersion** () const =0 throw (cms::CMSEException)
Gets the CMS minor version number.
- virtual std::string **getCMSProviderName** () const =0 throw (cms::CMSEException)
Gets the CMS provider name.
- virtual std::string **getProviderVersion** () const =0 throw (cms::CMSEException)
Gets the CMS provider version.
- virtual int **getProviderMajorVersion** () const =0 throw (cms::CMSEException)
Gets the CMS provider major version number.
- virtual int **getProviderMinorVersion** () const =0 throw (cms::CMSEException)
Gets the CMS provider minor version number.
- virtual std::vector< std::string > **getCMSXPropertyNames** () const =0 throw (cms::CMSEException)
Gets an Vector of the CMSX property names.

6.246.1 Detailed Description

A **ConnectionMetaData** (p.1385) object provides information describing the **Connection** (p.1262) object.

Since:

1.3

6.246.2 Constructor & Destructor Documentation

6.246.2.1 `virtual cms::ConnectionMetaData::~~ConnectionMetaData () [inline, virtual]`

6.246.3 Member Function Documentation

6.246.3.1 `virtual int cms::ConnectionMetaData::getCMSMajorVersion () const throw (cms::CMSEException) [pure virtual]`

Gets the CMS major version number.

Returns:

the CMS API major version number

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 304).

6.246.3.2 `virtual int cms::ConnectionMetaData::getCMSMinorVersion () const throw (cms::CMSEException) [pure virtual]`

Gets the CMS minor version number.

Returns:

the CMS API minor version number

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 304).

6.246.3.3 `virtual std::string cms::ConnectionMetaData::getCMSProviderName () const throw (cms::CMSEException) [pure virtual]`

Gets the CMS provider name.

Returns:

the CMS provider name

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 304).

6.246.3.4 `virtual std::string cms::ConnectionMetaData::getCMSVersion () const
throw (cms::CMSEException) [pure virtual]`

Gets the CMS API version.

Returns:

the CMS API Version in String form.

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 305).

6.246.3.5 `virtual std::vector<std::string>
cms::ConnectionMetaData::getCMSXPropertyNames ()
const throw (cms::CMSEException) [pure virtual]`

Gets an Vector of the CMSX property names.

Returns:

an Vector of CMSX property names

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 305).

6.246.3.6 `virtual int cms::ConnectionMetaData::getProviderMajorVersion () const
throw (cms::CMSEException) [pure virtual]`

Gets the CMS provider major version number.

Returns:

the CMS provider major version number

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in `activemq::core::ActiveMQConnectionMetaData` (p. 305).

6.246.3.7 `virtual int cms::ConnectionMetaData::getProviderMinorVersion () const
throw (cms::CMSEException) [pure virtual]`

Gets the CMS provider minor version number.

Returns:

the CMS provider minor version number

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in **activemq::core::ActiveMQConnectionMetaData** (p. 306).

6.246.3.8 `virtual std::string cms::ConnectionMetaData::getProviderVersion ()
const throw (cms::CMSEException) [pure virtual]`

Gets the CMS provider version.

Returns:

the CMS provider version

Exceptions:

CMSEException (p. 1160) If the CMS Provider fails to retrieve the metadata due to some internal error.

Implemented in **activemq::core::ActiveMQConnectionMetaData** (p. 306).

The documentation for this class was generated from the following file:

- `src/main/cms/ConnectionMetaData.h`

6.247 activemq::state::ConnectionState Class Reference

```
#include <src/main/activemq/state/ConnectionState.h>
```

Public Member Functions

- **ConnectionState** (const **Pointer**< **ConnectionInfo** > &info)
- virtual **~ConnectionState** ()
- std::string **toString** () const
- const **Pointer**< **commands::ConnectionInfo** > & **getInfo** () const
- void **checkShutdown** () const
- void **shutdown** ()
- void **reset** (const **Pointer**< **ConnectionInfo** > &info)
- void **addTempDestination** (const **Pointer**< **DestinationInfo** > &info)
- void **removeTempDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- void **addTransactionState** (const **Pointer**< **TransactionId** > &id)
- const **Pointer**< **TransactionState** > & **getTransactionState** (const **Pointer**< **TransactionId** > &id) const
- std::vector< **Pointer**< **TransactionState** > > **getTransactionStates** () const
- **Pointer**< **TransactionState** > **removeTransactionState** (const **Pointer**< **TransactionId** > &id)
- void **addSession** (const **Pointer**< **SessionInfo** > &info)
- **Pointer**< **SessionState** > **removeSession** (const **Pointer**< **SessionId** > &id)
- const **Pointer**< **SessionState** > & **getSessionState** (const **Pointer**< **SessionId** > &id) const
- const **StlList**< **Pointer**< **DestinationInfo** > > & **getTempDesinations** () const
- std::vector< **Pointer**< **SessionState** > > **getSessionStates** () const
- **StlMap**< **Pointer**< **ConsumerId** >, **Pointer**< **ConsumerInfo** >, **ConsumerId::COMPARATOR** > **getRecoveringPullConsumers** ()
- void **setConnectionInterruptProcessingComplete** (bool connectionInterruptProcessingComplete)
- bool **isConnectionInterruptProcessingComplete** ()

6.247.1 Constructor & Destructor Documentation

- 6.247.1.1 `activemq::state::ConnectionState::ConnectionState (const Pointer< ConnectionInfo > & info)`
- 6.247.1.2 `virtual activemq::state::ConnectionState::~~ConnectionState ()` [virtual]

6.247.2 Member Function Documentation

- 6.247.2.1 `void activemq::state::ConnectionState::addSession (const Pointer< SessionInfo > & info)` [inline]
- 6.247.2.2 `void activemq::state::ConnectionState::addTempDestination (const Pointer< DestinationInfo > & info)` [inline]
- 6.247.2.3 `void activemq::state::ConnectionState::addTransactionState (const Pointer< TransactionId > & id)` [inline]
- 6.247.2.4 `void activemq::state::ConnectionState::checkShutdown ()` const
- 6.247.2.5 `const Pointer<commands::ConnectionInfo>& activemq::state::ConnectionState::getInfo ()` const [inline]
- 6.247.2.6 `StlMap< Pointer<ConsumerId>, Pointer<ConsumerInfo>, ConsumerId::COMPARATOR > & activemq::state::ConnectionState::getRecoveringPullConsumers ()` [inline]
- 6.247.2.7 `const Pointer<SessionState>& activemq::state::ConnectionState::getSessionState (const Pointer< SessionId > & id)` const [inline]
- 6.247.2.8 `std::vector< Pointer<SessionState> > & activemq::state::ConnectionState::getSessionStates ()` const [inline]
- 6.247.2.9 `const StlList< Pointer<DestinationInfo> >& activemq::state::ConnectionState::getTempDesinations ()` const [inline]
- 6.247.2.10 `const Pointer<TransactionState>& activemq::state::ConnectionState::getTransactionState (const Pointer< TransactionId > & id)` const [inline]

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

- 6.247.2.11 `std::vector< Pointer<TransactionState> > activemq::state::ConnectionState::getTransactionStates () const` [inline]
- 6.247.2.12 `bool activemq::state::ConnectionState::isConnectionInterruptProcessingComplete ()` [inline]
- 6.247.2.13 `Pointer<SessionState> activemq::state::ConnectionState::removeSession (const Pointer< SessionId > & id)` [inline]
- 6.247.2.14 `void activemq::state::ConnectionState::removeTempDestination (const Pointer< ActiveMQDestination > & destination)` [inline]

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

- 6.247.2.15 `Pointer<TransactionState> activemq::state::ConnectionState::removeTransactionState (const Pointer< TransactionId > & id)` [inline]
- 6.247.2.16 `void activemq::state::ConnectionState::reset (const Pointer< ConnectionInfo > & info)`
- 6.247.2.17 `void activemq::state::ConnectionState::setConnectionInterruptProcessingComplete (bool connectionInterruptProcessingComplete)` [inline]
- 6.247.2.18 `void activemq::state::ConnectionState::shutdown ()`
- 6.247.2.19 `std::string activemq::state::ConnectionState::toString () const`

The documentation for this class was generated from the following file:

- `src/main/activemq/state/ConnectionState.h`

6.248 activemq::state::ConnectionStateTracker Class Reference

#include <src/main/activemq/state/ConnectionStateTracker.h> Inheritance diagram for activemq::state::ConnectionStateTracker:

Public Member Functions

- **ConnectionStateTracker** ()
- virtual **~ConnectionStateTracker** ()
- **Pointer< Tracked > track** (const **Pointer< Command >** &command) throw (decaf::io::IOException)
- void **trackBack** (const **Pointer< Command >** &command)
- void **restore** (const **Pointer< transport::Transport >** &transport) throw (decaf::io::IOException)
- void **connectionInterruptProcessingComplete** (transport::Transport *transport, const **Pointer< ConnectionId >** &connectionId)
- void **transportInterrupted** ()
- virtual **Pointer< Command > processDestinationInfo** (DestinationInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRemoveDestination** (DestinationInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processProducerInfo** (ProducerInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRemoveProducer** (ProducerId *id) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processConsumerInfo** (ConsumerInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRemoveConsumer** (ConsumerId *id) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processSessionInfo** (SessionInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRemoveSession** (SessionId *id) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processConnectionInfo** (ConnectionInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRemoveConnection** (ConnectionId *id) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processMessage** (Message *message) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processMessageAck** (MessageAck *ack) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processBeginTransaction** (TransactionInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processPrepareTransaction** (TransactionInfo *info) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processCommitTransactionOnePhase** (TransactionInfo *info) throw (exceptions::ActiveMQException)

- virtual **Pointer< Command > processCommitTransactionTwoPhase** (**TransactionInfo *info**) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processRollbackTransaction** (**TransactionInfo *info**) throw (exceptions::ActiveMQException)
- virtual **Pointer< Command > processEndTransaction** (**TransactionInfo *info**) throw (exceptions::ActiveMQException)
- bool **isRestoreConsumers** () const
- void **setRestoreConsumers** (bool restoreConsumers)
- bool **isRestoreProducers** () const
- void **setRestoreProducers** (bool restoreProducers)
- bool **isRestoreSessions** () const
- void **setRestoreSessions** (bool restoreSessions)
- bool **isTrackTransactions** () const
- void **setTrackTransactions** (bool trackTransactions)
- bool **isRestoreTransaction** () const
- void **setRestoreTransaction** (bool restoreTransaction)
- bool **isTrackMessages** () const
- void **setTrackMessages** (bool trackMessages)
- int **getMaxCacheSize** () const
- void **setMaxCacheSize** (int maxCacheSize)
- bool **isTrackTransactionProducers** () const
- void **setTrackTransactionProducers** (bool trackTransactionProducers)

Friends

- class **RemoveTransactionAction**

6.248.1 Constructor & Destructor Documentation

6.248.1.1 `activemq::state::ConnectionStateTracker::ConnectionStateTracker ()`

6.248.1.2 `virtual
activemq::state::ConnectionStateTracker::~~ConnectionStateTracker ()
[virtual]`

6.248.2 Member Function Documentation

6.248.2.1 `void ac-
tivemq::state::ConnectionStateTracker::connectionInterruptProcessingComplete
(transport::Transport * transport, const Pointer< ConnectionId > &
connectionId)`

6.248.2.2 `int activemq::state::ConnectionStateTracker::getMaxCacheSize () const
[inline]`

6.248.2.3 `bool activemq::state::ConnectionStateTracker::isRestoreConsumers ()
const [inline]`

6.248.2.4 `bool activemq::state::ConnectionStateTracker::isRestoreProducers ()
const [inline]`

6.248.2.5 `bool activemq::state::ConnectionStateTracker::isRestoreSessions () const
[inline]`

6.248.2.6 `bool activemq::state::ConnectionStateTracker::isRestoreTransaction ()
const [inline]`

6.248.2.7 `bool activemq::state::ConnectionStateTracker::isTrackMessages () const
[inline]`

6.248.2.8 `bool ac-
tivemq::state::ConnectionStateTracker::isTrackTransactionProducers ()
const [inline]`

6.248.2.9 `bool activemq::state::ConnectionStateTracker::isTrackTransactions ()
const [inline]`

6.248.2.10 `virtual Pointer<Command> ac-
tivemq::state::ConnectionStateTracker::processBeginTransaction
(TransactionInfo * info) throw (exceptions::ActiveMQException)
[virtual]`

Implements `activemq::state::CommandVisitor` (p. 1202).

6.248.2.11 `virtual Pointer<Command> ac-
tivemq::state::ConnectionStateTracker::processCommitTransactionOnePhase
(TransactionInfo * info) throw (exceptions::ActiveMQException)
[virtual]`

Implements `activemq::state::CommandVisitor` (p. 1202).

6.248.2.12 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processCommitTransactionTwoPhase (TransactionInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1202).

6.248.2.13 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processConnectionInfo (ConnectionInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1203).

6.248.2.14 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processConsumerInfo (ConsumerInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1203).

6.248.2.15 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processDestinationInfo (DestinationInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1203).

6.248.2.16 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processEndTransaction (TransactionInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1203).

6.248.2.17 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processMessage (Message * *message*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1204).

6.248.2.18 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processMessageAck (MessageAck * *ack*) throw (exceptions::ActiveMQException)
[virtual]

Implements activemq::state::CommandVisitor (p. 1204).

6.248.2.19 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processPrepareTransaction (TransactionInfo * info) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1204).

6.248.2.20 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processProducerInfo (ProducerInfo * info) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1205).

6.248.2.21 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRemoveConnection (ConnectionId * id) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1205).

6.248.2.22 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRemoveConsumer (ConsumerId * id) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1205).

6.248.2.23 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRemoveDestination (DestinationInfo * info) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1205).

6.248.2.24 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRemoveProducer (ProducerId * id) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1205).

6.248.2.25 `virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRemoveSession (SessionId * id) throw (exceptions::ActiveMQException)` [virtual]

Implements `activemq::state::CommandVisitor` (p. 1206).

6.248.2.26 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processRollbackTransaction (TransactionInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements **activemq::state::CommandVisitor** (p. 1206).

6.248.2.27 virtual Pointer<Command> activemq::state::ConnectionStateTracker::processSessionInfo (SessionInfo * *info*) throw (exceptions::ActiveMQException)
[virtual]

Implements **activemq::state::CommandVisitor** (p. 1206).

- 6.248.2.28 `void activemq::state::ConnectionStateTracker::restore (const Pointer< transport::Transport > & transport) throw (decaf::io::IOException)`
- 6.248.2.29 `void activemq::state::ConnectionStateTracker::setMaxCacheSize (int maxCacheSize) [inline]`
- 6.248.2.30 `void activemq::state::ConnectionStateTracker::setRestoreConsumers (bool restoreConsumers) [inline]`
- 6.248.2.31 `void activemq::state::ConnectionStateTracker::setRestoreProducers (bool restoreProducers) [inline]`
- 6.248.2.32 `void activemq::state::ConnectionStateTracker::setRestoreSessions (bool restoreSessions) [inline]`
- 6.248.2.33 `void activemq::state::ConnectionStateTracker::setRestoreTransaction (bool restoreTransaction) [inline]`
- 6.248.2.34 `void activemq::state::ConnectionStateTracker::setTrackMessages (bool trackMessages) [inline]`
- 6.248.2.35 `void activemq::state::ConnectionStateTracker::setTrackTransactionProducers (bool trackTransactionProducers) [inline]`
- 6.248.2.36 `void activemq::state::ConnectionStateTracker::setTrackTransactions (bool trackTransactions) [inline]`
- 6.248.2.37 `Pointer<Tracked> activemq::state::ConnectionStateTracker::track (const Pointer< Command > & command) throw (decaf::io::IOException)`
- 6.248.2.38 `void activemq::state::ConnectionStateTracker::trackBack (const Pointer< Command > & command)`
- 6.248.2.39 `void activemq::state::ConnectionStateTracker::transportInterrupted ()`

6.248.3 Friends And Related Function Documentation

- 6.248.3.1 `friend class RemoveTransactionAction [friend]`

The documentation for this class was generated from the following file:

- `src/main/activemq/state/ConnectionStateTracker.h`

6.249 decaf::util::logging::ConsoleHandler Class Reference

This **Handler** (p. 1978) publishes log records to System.err.

#include <src/main/decaf/util/logging/ConsoleHandler.h> Inheritance diagram for decaf::util::logging::ConsoleHandler:

Public Member Functions

- **ConsoleHandler** ()
- virtual **~ConsoleHandler** ()
- virtual void **close** () throw (decaf::io::IOException)
Close the current output stream.
- virtual void **publish** (const **LogRecord** &record)
*Publish the Log Record to this **Handler** (p. 1978).*

6.249.1 Detailed Description

This **Handler** (p. 1978) publishes log records to System.err. By default the **SimpleFormatter** (p. 3500) is used to generate brief summaries.

Configuration: By default each **ConsoleHandler** (p. 1399) is initialized using the following **LogManager** (p. 2406) configuration properties. If properties are not defined (or have invalid values) then the specified default values are used.

ConsoleHandler.level specifies the default level for the **Handler** (p. 1978) (defaults to **Level.INFO** (p. 2336)). ConsoleHandler.filter specifies the name of a **Filter** (p. 1893) class to use (defaults to no **Filter** (p. 1893)). ConsoleHandler.formatter specifies the name of a **Formatter** (p. 1964) class to use (defaults to **SimpleFormatter** (p. 3500)).

Since:

1.0

6.249.2 Constructor & Destructor Documentation

6.249.2.1 decaf::util::logging::ConsoleHandler::ConsoleHandler ()

6.249.2.2 virtual decaf::util::logging::ConsoleHandler::~~ConsoleHandler ()
[inline, virtual]

6.249.3 Member Function Documentation

6.249.3.1 virtual void decaf::util::logging::ConsoleHandler::close () throw (decaf::io::IOException) [virtual]

Close the current output stream. Override the **StreamHandler** (p. 3649) close to flush the Std Err stream but doesn't close.

Exceptions:***IOException***

Reimplemented from **decaf::util::logging::StreamHandler** (p. 3650).

6.249.3.2 virtual void decaf::util::logging::ConsoleHandler::publish (const LogRecord & *record*) [virtual]

Publish the Log Record to this **Handler** (p. 1978).

Parameters:

record The LogRecord (p. 2413) to Publish

Reimplemented from **decaf::util::logging::StreamHandler** (p. 3651).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/ConsoleHandler.h`

6.250 activemq::commands::ConsumerControl Class Reference

#include <src/main/activemq/commands/ConsumerControl.h> Inheritance diagram for activemq::commands::ConsumerControl:

Public Member Functions

- **ConsumerControl** ()
- virtual **~ConsumerControl** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConsumerControl** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual bool **isClose** () const
- virtual void **setClose** (bool close)
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual int **getPrefetch** () const
- virtual void **setPrefetch** (int prefetch)
- virtual bool **isFlush** () const
- virtual void **setFlush** (bool flush)
- virtual bool **isStart** () const
- virtual void **setStart** (bool start)
- virtual bool **isStop** () const
- virtual void **setStop** (bool stop)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_CONSUMERCONTROL** = 17

Protected Attributes

- **Pointer**< **ActiveMQDestination** > **destination**
- bool **close**
- **Pointer**< **ConsumerId** > **consumerId**
- int **prefetch**
- bool **flush**
- bool **start**
- bool **stop**

6.250.1 Constructor & Destructor Documentation

6.250.1.1 **activemq::commands::ConsumerControl::ConsumerControl** ()

6.250.1.2 **virtual activemq::commands::ConsumerControl::~~ConsumerControl** ()
[virtual]

6.250.2 Member Function Documentation

6.250.2.1 **virtual ConsumerControl* activemq::commands::ConsumerControl::cloneDataStructure**
() const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.250.2.2 **virtual void activemq::commands::ConsumerControl::copyDataStructure**
(const **DataStructure** * *src*) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.250.2.3 **virtual bool activemq::commands::ConsumerControl::equals** (const
DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.250.2.4 virtual Pointer<ConsumerId>& activemq::commands::ConsumerControl::getConsumerId ()
[virtual]

6.250.2.5 virtual const Pointer<ConsumerId>& activemq::commands::ConsumerControl::getConsumerId ()
const [virtual]

6.250.2.6 virtual unsigned char activemq::commands::ConsumerControl::getDataStructureType () const
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.250.2.7 `virtual Pointer<ActiveMQDestination>& activemq::commands::ConsumerControl::getDestination ()`
[virtual]
- 6.250.2.8 `virtual const Pointer<ActiveMQDestination>& activemq::commands::ConsumerControl::getDestination () const`
[virtual]
- 6.250.2.9 `virtual int activemq::commands::ConsumerControl::getPrefetch () const`
[virtual]
- 6.250.2.10 `virtual bool activemq::commands::ConsumerControl::isClose () const`
[virtual]
- 6.250.2.11 `virtual bool activemq::commands::ConsumerControl::isFlush () const`
[virtual]
- 6.250.2.12 `virtual bool activemq::commands::ConsumerControl::isStart () const`
[virtual]
- 6.250.2.13 `virtual bool activemq::commands::ConsumerControl::isStop () const`
[virtual]
- 6.250.2.14 `virtual void activemq::commands::ConsumerControl::setClose (bool close)` [virtual]
- 6.250.2.15 `virtual void activemq::commands::ConsumerControl::setConsumerId (const Pointer< ConsumerId > & consumerId)` [virtual]
- 6.250.2.16 `virtual void activemq::commands::ConsumerControl::setDestination (const Pointer< ActiveMQDestination > & destination)` [virtual]
- 6.250.2.17 `virtual void activemq::commands::ConsumerControl::setFlush (bool flush)` [virtual]
- 6.250.2.18 `virtual void activemq::commands::ConsumerControl::setPrefetch (int prefetch)` [virtual]
- 6.250.2.19 `virtual void activemq::commands::ConsumerControl::setStart (bool start)` [virtual]
- 6.250.2.20 `virtual void activemq::commands::ConsumerControl::setStop (bool stop)` [virtual]
- 6.250.2.21 `virtual std::string activemq::commands::ConsumerControl::toString () const` [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

6.250.2.22 `virtual Pointer<Command> activemq::commands::ConsumerControl::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements `activemq::commands::Command` (p. 1198).

6.250.3 Field Documentation

6.250.3.1 `bool activemq::commands::ConsumerControl::close [protected]`

6.250.3.2 `Pointer<ConsumerId> activemq::commands::ConsumerControl::consumerId [protected]`

6.250.3.3 `Pointer<ActiveMQDestination> activemq::commands::ConsumerControl::destination [protected]`

6.250.3.4 `bool activemq::commands::ConsumerControl::flush [protected]`

6.250.3.5 `const unsigned char activemq::commands::ConsumerControl::ID_CONSUMERCONTROL = 17 [static]`

6.250.3.6 `int activemq::commands::ConsumerControl::prefetch [protected]`

6.250.3.7 `bool activemq::commands::ConsumerControl::start [protected]`

6.250.3.8 `bool activemq::commands::ConsumerControl::stop [protected]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ConsumerControl.h`

6.251 activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1406).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.251.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1406).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.251.2 Constructor & Destructor Documentation

6.251.2.1 `activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::ConsumerControlMarshaller()` [inline]

6.251.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::~~ConsumerControlMarshaller()` [inline, virtual]

6.251.3 Member Function Documentation

6.251.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.251.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.251.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.251.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.251.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.251.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.251.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConsumerControlMarshaller.h

6.252 activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1410).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.252.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1410).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.252.2 Constructor & Destructor Documentation

6.252.2.1 `activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::ConsumerControlMarshaller()` [inline]

6.252.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::~~ConsumerControlMarshaller()` [inline, virtual]

6.252.3 Member Function Documentation

6.252.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.252.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.252.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.252.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.252.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.252.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.252.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConsumerControlMarshaller.h

6.253 activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1414).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.253.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1414).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.253.2 Constructor & Destructor Documentation

6.253.2.1 `activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::ConsumerControlMarshaller()` [inline]

6.253.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::~~ConsumerControlMarshaller()` [inline, virtual]

6.253.3 Member Function Documentation

6.253.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.253.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.253.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.253.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.253.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.253.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.253.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConsumerControlMarshaller.h

6.254 activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1418).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.254.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1418).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.254.2 Constructor & Destructor Documentation

6.254.2.1 **activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::ConsumerControlMarshaller()** [inline]

6.254.2.2 **virtual activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::~~ConsumerControlMarshaller()** [inline, virtual]

6.254.3 Member Function Documentation

6.254.3.1 **virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::createObject()** const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1611).

6.254.3.2 **virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::getDataStructureType()** const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1617).

6.254.3.3 **virtual void activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)** [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.254.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.254.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.254.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.254.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConsumerControlMarshaller.h

6.255 activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1422).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.255.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1422).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.255.2 Constructor & Destructor Documentation

6.255.2.1 `activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::ConsumerControlMarshaller()` [inline]

6.255.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::~~ConsumerControlMarshaller()` [inline, virtual]

6.255.3 Member Function Documentation

6.255.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.255.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.255.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.255.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.255.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.255.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.255.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConsumerControlMarshaller.h

6.256 activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1426).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConsumerControlMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller:

Public Member Functions

- **ConsumerControlMarshaller** ()
- virtual **~ConsumerControlMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.256.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1426).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.256.2 Constructor & Destructor Documentation

6.256.2.1 `activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::ConsumerControlMarshaller()` [inline]

6.256.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::~~ConsumerControlMarshaller()` [inline, virtual]

6.256.3 Member Function Documentation

6.256.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.256.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.256.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.256.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.256.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.256.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.256.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConsumerControlMarshaller.h

6.257 activemq::commands::ConsumerId Class Reference

#include <src/main/activemq/commands/ConsumerId.h> Inheritance diagram for activemq::commands::ConsumerId:

Public Types

- typedef decaf::lang::PointerComparator< ConsumerId > COMPARATOR

Public Member Functions

- **ConsumerId** ()
- **ConsumerId** (const **ConsumerId** &other)
- **ConsumerId** (const **SessionId** &sessionId, long long consumerId)
- virtual ~**ConsumerId** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConsumerId** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- const **Pointer**< **SessionId** > & **getParentId** () const
- virtual const std::string & **getConnectionId** () const
- virtual std::string & **getConnectionId** ()
- virtual void **setConnectionId** (const std::string &connectionId)
- virtual long long **getSessionId** () const
- virtual void **setSessionId** (long long sessionId)
- virtual long long **getValue** () const
- virtual void **setValue** (long long value)
- virtual int **compareTo** (const **ConsumerId** &value) const
- virtual bool **equals** (const **ConsumerId** &value) const
- virtual bool **operator==** (const **ConsumerId** &value) const
- virtual bool **operator<** (const **ConsumerId** &value) const
- **ConsumerId** & **operator=** (const **ConsumerId** &other)

Static Public Attributes

- static const unsigned char **ID_ CONSUMERID** = 122

Protected Attributes

- std::string **connectionId**
- long long **sessionId**
- long long **value**

6.257.1 Member Typedef Documentation

- 6.257.1.1** `typedef decaf::lang::PointerComparator<ConsumerId>
activemq::commands::ConsumerId::COMPARATOR`

6.257.2 Constructor & Destructor Documentation

- 6.257.2.1** `activemq::commands::ConsumerId::ConsumerId ()`
- 6.257.2.2** `activemq::commands::ConsumerId::ConsumerId (const ConsumerId &
other)`
- 6.257.2.3** `activemq::commands::ConsumerId::ConsumerId (const SessionId &
sessionId, long long consumerId)`
- 6.257.2.4** `virtual activemq::commands::ConsumerId::~~ConsumerId ()` [virtual]

6.257.3 Member Function Documentation

- 6.257.3.1** `virtual ConsumerId* ac-
tivemq::commands::ConsumerId::cloneDataStructure ()
const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p.1660).

- 6.257.3.2** `virtual int activemq::commands::ConsumerId::compareTo (const
ConsumerId & value) const` [virtual]

- 6.257.3.3** `virtual void activemq::commands::ConsumerId::copyDataStructure
(const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.257.3.4 virtual bool activemq::commands::ConsumerId::equals (const ConsumerId & *value*) const [virtual]

6.257.3.5 virtual bool activemq::commands::ConsumerId::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.257.3.6 virtual std::string& activemq::commands::ConsumerId::getConnectionId () [virtual]

6.257.3.7 virtual const std::string& activemq::commands::ConsumerId::getConnectionId () const [virtual]

6.257.3.8 virtual unsigned char activemq::commands::ConsumerId::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.257.3.9 `const Pointer<SessionId>& activemq::commands::ConsumerId::getParentId () const`
- 6.257.3.10 `virtual long long activemq::commands::ConsumerId::getSessionId () const [virtual]`
- 6.257.3.11 `virtual long long activemq::commands::ConsumerId::getValue () const [virtual]`
- 6.257.3.12 `virtual bool activemq::commands::ConsumerId::operator< (const ConsumerId & value) const [virtual]`
- 6.257.3.13 `ConsumerId& activemq::commands::ConsumerId::operator= (const ConsumerId & other)`
- 6.257.3.14 `virtual bool activemq::commands::ConsumerId::operator== (const ConsumerId & value) const [virtual]`
- 6.257.3.15 `virtual void activemq::commands::ConsumerId::setConnectionId (const std::string & connectionId) [virtual]`
- 6.257.3.16 `virtual void activemq::commands::ConsumerId::setSessionId (long long sessionId) [virtual]`
- 6.257.3.17 `virtual void activemq::commands::ConsumerId::setValue (long long value) [virtual]`
- 6.257.3.18 `virtual std::string activemq::commands::ConsumerId::toString () const [virtual]`

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataSet** (p.833).

6.257.4 Field Documentation

- 6.257.4.1 `std::string activemq::commands::ConsumerId::connectionId [protected]`
- 6.257.4.2 `const unsigned char activemq::commands::ConsumerId::ID _ - CONSUMERID = 122 [static]`

Referenced by `activemq::state::CommandVisitorAdapter::processRemoveInfo()`.

6.257.4.3 `long long activemq::commands::ConsumerId::sessionId` [protected]

6.257.4.4 `long long activemq::commands::ConsumerId::value` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ConsumerId.h`

6.258 activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1435).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConsumerIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.258.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1435).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.258.2 Constructor & Destructor Documentation

6.258.2.1 `activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.258.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.258.3 Member Function Documentation

6.258.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.258.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.258.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.258.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.258.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.258.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.258.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConsumerIdMarshaller.h

6.259 activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1439).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConsumerIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.259.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1439).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.259.2 Constructor & Destructor Documentation

6.259.2.1 `activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.259.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.259.3 Member Function Documentation

6.259.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.259.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.259.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.259.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.259.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.259.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.259.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConsumerIdMarshaller.h

6.260 activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1443).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.260.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1443).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.260.2 Constructor & Destructor Documentation

6.260.2.1 `activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.260.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.260.3 Member Function Documentation

6.260.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.260.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.260.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.260.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.260.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.260.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.260.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h

6.261 activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1447).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConsumerIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.261.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1447).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.261.2 Constructor & Destructor Documentation

6.261.2.1 `activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.261.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.261.3 Member Function Documentation

6.261.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.261.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.261.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.261.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.261.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.261.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.261.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ConsumerIdMarshaller.h

6.262 activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1451).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConsumerIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.262.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1451).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.262.2 Constructor & Destructor Documentation

6.262.2.1 `activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.262.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.262.3 Member Function Documentation

6.262.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.262.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.262.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.262.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.262.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.262.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.262.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConsumerIdMarshaller.h

6.263 activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1455).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConsumerIdMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller:

Public Member Functions

- **ConsumerIdMarshaller** ()
- virtual **~ConsumerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.263.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerIdMarshaller** (p.1455).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.263.2 Constructor & Destructor Documentation

6.263.2.1 `activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::ConsumerIdMarshaller()` [inline]

6.263.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::~~ConsumerIdMarshaller()` [inline, virtual]

6.263.3 Member Function Documentation

6.263.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.263.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.263.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.263.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.263.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.263.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.263.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConsumerIdMarshaller.h

6.264 activemq::commands::ConsumerInfo Class Reference

#include <src/main/activemq/commands/ConsumerInfo.h> Inheritance diagram for activemq::commands::ConsumerInfo:

Public Member Functions

- **ConsumerInfo** ()
- virtual **~ConsumerInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ConsumerInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- **Pointer**< **RemoveInfo** > **createRemoveCommand** () const
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual bool **isBrowser** () const
- virtual void **setBrowser** (bool browser)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual int **getPrefetchSize** () const
- virtual void **setPrefetchSize** (int prefetchSize)
- virtual int **getMaximumPendingMessageLimit** () const
- virtual void **setMaximumPendingMessageLimit** (int maximumPendingMessageLimit)
- virtual bool **isDispatchAsync** () const
- virtual void **setDispatchAsync** (bool dispatchAsync)
- virtual const std::string & **getSelector** () const
- virtual std::string & **getSelector** ()
- virtual void **setSelector** (const std::string &selector)
- virtual const std::string & **getSubscriptionName** () const
- virtual std::string & **getSubscriptionName** ()
- virtual void **setSubscriptionName** (const std::string &subscriptionName)

- virtual bool **isNoLocal** () const
- virtual void **setNoLocal** (bool **noLocal**)
- virtual bool **isExclusive** () const
- virtual void **setExclusive** (bool **exclusive**)
- virtual bool **isRetroactive** () const
- virtual void **setRetroactive** (bool **retroactive**)
- virtual unsigned char **getPriority** () const
- virtual void **setPriority** (unsigned char **priority**)
- virtual const std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** () const
- virtual std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** ()
- virtual void **setBrokerPath** (const std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **brokerPath**)
- virtual const **Pointer**< **BooleanExpression** > & **getAdditionalPredicate** () const
- virtual **Pointer**< **BooleanExpression** > & **getAdditionalPredicate** ()
- virtual void **setAdditionalPredicate** (const **Pointer**< **BooleanExpression** > & **additionalPredicate**)
- virtual bool **isNetworkSubscription** () const
- virtual void **setNetworkSubscription** (bool **networkSubscription**)
- virtual bool **isOptimizedAcknowledge** () const
- virtual void **setOptimizedAcknowledge** (bool **optimizedAcknowledge**)
- virtual bool **isNoRangeAcks** () const
- virtual void **setNoRangeAcks** (bool **noRangeAcks**)
- virtual const std::vector< **decaf::lang::Pointer**< **ConsumerId** > > & **getNetworkConsumerPath** () const
- virtual std::vector< **decaf::lang::Pointer**< **ConsumerId** > > & **getNetworkConsumerPath** ()
- virtual void **setNetworkConsumerPath** (const std::vector< **decaf::lang::Pointer**< **ConsumerId** > > & **networkConsumerPath**)
- virtual bool **isConsumerInfo** () const
- virtual **Pointer**< **Command** > **visit** (**activemq::state::CommandVisitor** *visitor) throw (exceptions::ActiveMQException)

Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID _CONSUMERINFO** = 5

Protected Attributes

- **Pointer**< **ConsumerId** > **consumerId**
- bool **browser**
- **Pointer**< **ActiveMQDestination** > **destination**
- int **prefetchSize**
- int **maximumPendingMessageLimit**
- bool **dispatchAsync**
- std::string **selector**
- std::string **subscriptionName**

- bool **noLocal**
- bool **exclusive**
- bool **retroactive**
- unsigned char **priority**
- std::vector< decaf::lang::Pointer< BrokerId > > **brokerPath**
- Pointer< BooleanExpression > **additionalPredicate**
- bool **networkSubscription**
- bool **optimizedAcknowledge**
- bool **noRangeAcks**
- std::vector< decaf::lang::Pointer< ConsumerId > > **networkConsumerPath**

6.264.1 Constructor & Destructor Documentation

- 6.264.1.1** `activemq::commands::ConsumerInfo::ConsumerInfo ()`
- 6.264.1.2** `virtual activemq::commands::ConsumerInfo::~~ConsumerInfo ()`
[virtual]

6.264.2 Member Function Documentation

- 6.264.2.1** `virtual ConsumerInfo* activemq::commands::ConsumerInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

- 6.264.2.2** `virtual void activemq::commands::ConsumerInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.264.2.3** `Pointer<RemoveInfo> activemq::commands::ConsumerInfo::createRemoveCommand ()`
`const`

- 6.264.2.4** `virtual bool activemq::commands::ConsumerInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.264.2.5 `virtual Pointer<BooleanExpression>& activemq::commands::ConsumerInfo::getAdditionalPredicate () [virtual]`
- 6.264.2.6 `virtual const Pointer<BooleanExpression>& activemq::commands::ConsumerInfo::getAdditionalPredicate () const [virtual]`
- 6.264.2.7 `virtual std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ConsumerInfo::getBrokerPath () [virtual]`
- 6.264.2.8 `virtual const std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ConsumerInfo::getBrokerPath () const [virtual]`
- 6.264.2.9 `virtual Pointer<ConsumerId>& activemq::commands::ConsumerInfo::getConsumerId () [virtual]`
- 6.264.2.10 `virtual const Pointer<ConsumerId>& activemq::commands::ConsumerInfo::getConsumerId () const [virtual]`
- 6.264.2.11 `virtual unsigned char activemq::commands::ConsumerInfo::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.264.2.12 `virtual Pointer<ActiveMQDestination>& activemq::commands::ConsumerInfo::getDestination ()` [virtual]
- 6.264.2.13 `virtual const Pointer<ActiveMQDestination>& activemq::commands::ConsumerInfo::getDestination () const` [virtual]
- 6.264.2.14 `virtual int activemq::commands::ConsumerInfo::getMaximumPendingMessageLimit () const` [virtual]
- 6.264.2.15 `virtual std::vector< decaf::lang::Pointer<ConsumerId> >& activemq::commands::ConsumerInfo::getNetworkConsumerPath ()` [virtual]
- 6.264.2.16 `virtual const std::vector< decaf::lang::Pointer<ConsumerId> >& activemq::commands::ConsumerInfo::getNetworkConsumerPath () const` [virtual]
- 6.264.2.17 `virtual int activemq::commands::ConsumerInfo::getPrefetchSize () const` [virtual]
- 6.264.2.18 `virtual unsigned char activemq::commands::ConsumerInfo::getPriority () const` [virtual]
- 6.264.2.19 `virtual std::string& activemq::commands::ConsumerInfo::getSelector ()` [virtual]
- 6.264.2.20 `virtual const std::string& activemq::commands::ConsumerInfo::getSelector () const` [virtual]
- 6.264.2.21 `virtual std::string& activemq::commands::ConsumerInfo::getSubscriptionName ()` [virtual]
- 6.264.2.22 `virtual const std::string& activemq::commands::ConsumerInfo::getSubscriptionName () const` [virtual]
- 6.264.2.23 `virtual bool activemq::commands::ConsumerInfo::isBrowser () const` [virtual]
- 6.264.2.24 `virtual bool activemq::commands::ConsumerInfo::isConsumerInfo () const` [inline, virtual]

Returns:

an answer of true to the `isConsumerInfo()` (p. 1463) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 761).

- 6.264.2.25 virtual bool activemq::commands::ConsumerInfo::isDispatchAsync ()
const [virtual]
- 6.264.2.26 virtual bool activemq::commands::ConsumerInfo::isExclusive () const
[virtual]
- 6.264.2.27 virtual bool activemq::commands::ConsumerInfo::isNetworkSubscription
() const [virtual]
- 6.264.2.28 virtual bool activemq::commands::ConsumerInfo::isNoLocal () const
[virtual]
- 6.264.2.29 virtual bool activemq::commands::ConsumerInfo::isNoRangeAcks ()
const [virtual]
- 6.264.2.30 virtual bool ac-
tivismq::commands::ConsumerInfo::isOptimizedAcknowledge () const
[virtual]
- 6.264.2.31 virtual bool activemq::commands::ConsumerInfo::isRetroactive () const
[virtual]
- 6.264.2.32 virtual void activemq::commands::ConsumerInfo::setAdditionalPredicate
(const Pointer< BooleanExpression > & *additionalPredicate*) [virtual]
- 6.264.2.33 virtual void activemq::commands::ConsumerInfo::setBrokerPath
(const std::vector< decaf::lang::Pointer< BrokerId > > & *brokerPath*)
[virtual]
- 6.264.2.34 virtual void activemq::commands::ConsumerInfo::setBrowser (bool
browser) [virtual]
- 6.264.2.35 virtual void activemq::commands::ConsumerInfo::setConsumerId (const
Pointer< ConsumerId > & *consumerId*) [virtual]
- 6.264.2.36 virtual void activemq::commands::ConsumerInfo::setDestination (const
Pointer< ActiveMQDestination > & *destination*) [virtual]
- 6.264.2.37 virtual void activemq::commands::ConsumerInfo::setDispatchAsync
(bool *dispatchAsync*) [virtual]
- 6.264.2.38 virtual void activemq::commands::ConsumerInfo::setExclusive (bool
exclusive) [virtual]
- 6.264.2.39 virtual void ac-
tivismq::commands::ConsumerInfo::setMaximumPendingMessageLimit
(int *maximumPendingMessageLimit*) [virtual]
- 6.264.2.40 virtual void ac-
tivismq::commands::ConsumerInfo::setNetworkConsumerPath
(const std::vector< decaf::lang::Pointer< ConsumerId > > &
networkConsumerPath) [virtual]
- 6.264.2.41 virtual void ac-
tivismq::commands::ConsumerInfo::setNetworkSubscription (bool
networkSubscription) [virtual]

Copyright © 2010-2011 by Doxygen

- 6.264.2.42 virtual void activemq::commands::ConsumerInfo::setNoLocal (bool
noLocal) [virtual]

- 6.264.2.43 virtual void activemq::commands::ConsumerInfo::setNoRangeAcks
(bool *noRangeAcks*) [virtual]

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.264.2.51 `virtual Pointer<Command> activemq::commands::ConsumerInfo::visit
(activemq::state::CommandVisitor * visitor) throw (
exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.264.3 Field Documentation

- 6.264.3.1 `Pointer<BooleanExpression> activemq::commands::ConsumerInfo::additionalPredicate`
[protected]
- 6.264.3.2 `std::vector< decaf::lang::Pointer<BrokerId> > activemq::commands::ConsumerInfo::brokerPath` [protected]
- 6.264.3.3 `bool activemq::commands::ConsumerInfo::browser` [protected]
- 6.264.3.4 `Pointer<ConsumerId> activemq::commands::ConsumerInfo::consumerId`
[protected]
- 6.264.3.5 `Pointer<ActiveMQDestination> activemq::commands::ConsumerInfo::destination`
[protected]
- 6.264.3.6 `bool activemq::commands::ConsumerInfo::dispatchAsync` [protected]
- 6.264.3.7 `bool activemq::commands::ConsumerInfo::exclusive` [protected]
- 6.264.3.8 `const unsigned char activemq::commands::ConsumerInfo::ID_ - CONSUMERINFO = 5` [static]
- 6.264.3.9 `int activemq::commands::ConsumerInfo::maximumPendingMessageLimit`
[protected]
- 6.264.3.10 `std::vector< decaf::lang::Pointer<ConsumerId> > activemq::commands::ConsumerInfo::networkConsumerPath`
[protected]
- 6.264.3.11 `bool activemq::commands::ConsumerInfo::networkSubscription`
[protected]
- 6.264.3.12 `bool activemq::commands::ConsumerInfo::noLocal` [protected]
- 6.264.3.13 `bool activemq::commands::ConsumerInfo::noRangeAcks` [protected]
- 6.264.3.14 `bool activemq::commands::ConsumerInfo::optimizedAcknowledge`
[protected]
- 6.264.3.15 `int activemq::commands::ConsumerInfo::prefetchSize` [protected]
- 6.264.3.16 `unsigned char activemq::commands::ConsumerInfo::priority`
[protected]
- 6.264.3.17 `bool activemq::commands::ConsumerInfo::retroactive` [protected]
- 6.264.3.18 `std::string activemq::commands::ConsumerInfo::selector` [protected]
- 6.264.3.19 `std::string activemq::commands::ConsumerInfo::subscriptionName`
[protected]

The documentation for this class was generated from the following file:

Generated on Wed Nov 10 22:25:45 2010 for activemq-cpp-3.2.3 by Doxygen

- `src/main/activemq/commands/ConsumerInfo.h`

6.265 activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1468).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ConsumerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.265.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1468).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.265.2 Constructor & Destructor Documentation

6.265.2.1 `activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::ConsumerInfoMarshaller()` [inline]

6.265.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::~~ConsumerInfoMarshaller()` [inline, virtual]

6.265.3 Member Function Documentation

6.265.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.265.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.265.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.265.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.265.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.265.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.265.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ConsumerInfoMarshaller.h

6.266 activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1472).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ConsumerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.266.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1472).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.266.2 Constructor & Destructor Documentation

6.266.2.1 `activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::ConsumerInfoMarshaller()` [inline]

6.266.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::~~ConsumerInfoMarshaller()` [inline, virtual]

6.266.3 Member Function Documentation

6.266.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.266.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.266.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.266.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.266.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.266.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.266.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ConsumerInfoMarshaller.h

6.267 activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1476).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.267.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1476).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.267.2 Constructor & Destructor Documentation

6.267.2.1 `activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::ConsumerInfoMar
() [inline]`

6.267.2.2 `virtual
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::~~ConsumerInfoMar
() [inline, virtual]`

6.267.3 Member Function Documentation

6.267.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.267.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.267.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.267.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.267.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.267.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.267.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h

6.268 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1480).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.268.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1480).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.268.2 Constructor & Destructor Documentation

6.268.2.1 `activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::ConsumerInfoMarshaller()` [inline]

6.268.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::~~ConsumerInfoMarshaller()` [inline, virtual]

6.268.3 Member Function Documentation

6.268.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.268.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.268.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.268.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.268.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.268.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.268.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ConsumerInfoMarshaller.h**

6.269 activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1484).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ConsumerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.269.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1484).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.269.2 Constructor & Destructor Documentation

6.269.2.1 `activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::ConsumerInfoMarshaller()` [inline]

6.269.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::~~ConsumerInfoMarshaller()` [inline, virtual]

6.269.3 Member Function Documentation

6.269.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.269.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.269.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.269.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.269.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.269.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.269.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ConsumerInfoMarshaller.h

6.270 activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1488).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ConsumerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller:

Public Member Functions

- **ConsumerInfoMarshaller** ()
- virtual **~ConsumerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.270.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ConsumerInfoMarshaller** (p.1488).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.270.2 Constructor & Destructor Documentation

6.270.2.1 `activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::ConsumerInfoMarshaller()` [inline]

6.270.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::~~ConsumerInfoMarshaller()` [inline, virtual]

6.270.3 Member Function Documentation

6.270.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.270.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.270.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.270.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.270.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.270.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.270.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ConsumerInfoMarshaller.h

6.271 activemq::state::ConsumerState Class Reference

```
#include <src/main/activemq/state/ConsumerState.h>
```

Public Member Functions

- **ConsumerState** (const **Pointer**< **ConsumerInfo** > &info)
- virtual **~ConsumerState** ()
- std::string **toString** () const
- const **Pointer**< **ConsumerInfo** > & **getInfo** () const

6.271.1 Constructor & Destructor Documentation

6.271.1.1 **activemq::state::ConsumerState::ConsumerState** (const **Pointer**< **ConsumerInfo** > & *info*)

6.271.1.2 virtual **activemq::state::ConsumerState::~~ConsumerState** () [virtual]

6.271.2 Member Function Documentation

6.271.2.1 const **Pointer**<**ConsumerInfo**>& **activemq::state::ConsumerState::getInfo** () const [inline]

6.271.2.2 std::string **activemq::state::ConsumerState::toString** () const

The documentation for this class was generated from the following file:

- src/main/activemq/state/**ConsumerState.h**

6.272 activemq::commands::ControlCommand Class Reference

#include <src/main/activemq/commands/ControlCommand.h> Inheritance diagram for activemq::commands::ControlCommand:

Public Member Functions

- **ControlCommand** ()
- virtual **~ControlCommand** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ControlCommand * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getCommand** () const
- virtual std::string & **getCommand** ()
- virtual void **setCommand** (const std::string &command)
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID _CONTROLCOMMAND** = 14

Protected Attributes

- std::string **command**

6.272.1 Constructor & Destructor Documentation

6.272.1.1 `activemq::commands::ControlCommand::ControlCommand ()`

6.272.1.2 `virtual activemq::commands::ControlCommand::~~ControlCommand ()`
[virtual]

6.272.2 Member Function Documentation

6.272.2.1 `virtual ControlCommand* activemq::commands::ControlCommand::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.272.2.2 `virtual void activemq::commands::ControlCommand::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.272.2.3 `virtual bool activemq::commands::ControlCommand::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.272.2.4** `virtual std::string& activemq::commands::ControlCommand::getCommand ()`
[virtual]
- 6.272.2.5** `virtual const std::string& activemq::commands::ControlCommand::getCommand ()`
`const` [virtual]
- 6.272.2.6** `virtual unsigned char activemq::commands::ControlCommand::getDataSetType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSet** (p. 1660) type copy.

Implements **activemq::commands::DataSet** (p. 1662).

- 6.272.2.7** `virtual void activemq::commands::ControlCommand::setCommand (const std::string & command)` [virtual]
- 6.272.2.8** `virtual std::string activemq::commands::ControlCommand::toString ()`
`const` [virtual]

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.272.2.9** `virtual Pointer<Command> activemq::commands::ControlCommand::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.272.3 Field Documentation

6.272.3.1 `std::string activemq::commands::ControlCommand::command`
[protected]

6.272.3.2 `const unsigned char activemq::commands::ControlCommand::ID_ -
CONTROLCOMMAND = 14` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ControlCommand.h`

6.273 activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1497).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.273.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1497).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.273.2 Constructor & Destructor Documentation

6.273.2.1 `activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::ControlComm`
`() [inline]`

6.273.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::~~ControlComm`
`() [inline, virtual]`

6.273.3 Member Function Documentation

6.273.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::createObject`
`() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.273.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::getDataStructur`
`() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.273.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.273.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.273.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.273.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.273.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ControlCommandMarshaller.h

6.274 activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1501).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.274.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1501).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.274.2 Constructor & Destructor Documentation

6.274.2.1 `activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::ControlComm`
`() [inline]`

6.274.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::~~ControlComm`
`() [inline, virtual]`

6.274.3 Member Function Documentation

6.274.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::createObject`
`() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.274.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::getDataStructur`
`() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.274.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.274.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.274.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.274.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.274.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ControlCommandMarshaller.h

6.275 activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1505).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.275.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1505).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.275.2 Constructor & Destructor Documentation

6.275.2.1 `activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::ControlComm`
`() [inline]`

6.275.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::~~ControlComm`
`() [inline, virtual]`

6.275.3 Member Function Documentation

6.275.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::createObject`
`() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.275.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::getDataStructur`
`() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.275.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure *`
`dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.275.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.275.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.275.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.275.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ControlCommandMarshaller.h

6.276 activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1509).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.276.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1509).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.276.2 Constructor & Destructor Documentation

6.276.2.1 `activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::ControlComm`
`() [inline]`

6.276.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::~~ControlComm`
`() [inline, virtual]`

6.276.3 Member Function Documentation

6.276.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::createObject`
`() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.276.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::getDataStructur`
`() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.276.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

6.276.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

6.276.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

6.276.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.276.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h

6.277 activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1513).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.277.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1513).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.277.2 Constructor & Destructor Documentation

6.277.2.1 `activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::ControlComm`
`() [inline]`

6.277.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::~~ControlComm`
`() [inline, virtual]`

6.277.3 Member Function Documentation

6.277.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::createObject`
`() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.277.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::getDataStructur`
`() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.277.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.277.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.277.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.277.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.277.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ControlCommandMarshaller.h

6.278 activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1517).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ControlCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller:

Public Member Functions

- **ControlCommandMarshaller** ()
- virtual **~ControlCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.278.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1517).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.278.2 Constructor & Destructor Documentation

6.278.2.1 `activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::ControlComm`
`()` [inline]

6.278.2.2 `virtual`
`activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::~~ControlComm`
`()` [inline, virtual]

6.278.3 Member Function Documentation

6.278.3.1 `virtual commands::DataStructure* ac-`
`tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::createObject`
`() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.278.3.2 `virtual unsigned char ac-`
`tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::getDataStructur`
`() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.278.3.3 `virtual void ac-`
`tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::looseMarshal`
`(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (`
`decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.278.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.278.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.278.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.278.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ControlCommandMarshaller.h

6.279 decaf::util::concurrent::CountDownLatch Class Reference

```
#include <src/main/decaf/util/concurrent/CountDownLatch.h>
```

Public Member Functions

- **CountDownLatch** (int count)

Constructor.

- virtual **~CountDownLatch** ()
- virtual void **await** () throw (decaf::lang::exceptions::InterruptedException, decaf::lang::Exception)

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted.

- virtual bool **await** (long long timeout) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::Exception)

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted, or the specified waiting time elapses.

- virtual bool **await** (long long timeout, const **TimeUnit** &unit) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::Exception)

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted, or the specified waiting time elapses.

- virtual void **countDown** ()

Counts down the latch, releasing all waiting threads when the count hits zero.

- virtual int **getCount** () const

Gets the current count.

6.279.1 Constructor & Destructor Documentation

6.279.1.1 decaf::util::concurrent::CountDownLatch::CountDownLatch (int count)

Constructor.

Parameters:

count - number to count down from.

6.279.1.2 `virtual decaf::util::concurrent::CountDownLatch::~~CountDownLatch ()`
[virtual]

6.279.2 Member Function Documentation

6.279.2.1 `virtual bool decaf::util::concurrent::CountDownLatch::await`
(long long *timeout*, const TimeUnit & *unit*) throw (
decaf::lang::exceptions::InterruptedException, decaf::lang::Exception)
[virtual]

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted, or the specified waiting time elapses. If the current count is zero then this method returns immediately with the value true.

If the current count is greater than zero then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happen:

* The count reaches zero due to invocations of the **countDown()** (p.1523) method; or * Some other thread interrupts the current thread; or * The specified waiting time elapses.

If the count reaches zero then the method returns with the value true.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting,

then InterruptedException is thrown and the current thread's interrupted status is cleared.

If the specified waiting time elapses then the value false is returned. If the time is less than or equal to zero, the method will not wait at all.

Parameters:

timeout - Time to wait for the count to reach zero.

unit - The units that the timeout specifies.

Exceptions:

InterruptedException - if the current thread is interrupted while waiting.

Exception - if any other error occurs.

6.279.2.2 `virtual bool decaf::util::concurrent::CountDownLatch::await` (long
long *timeOut*) throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::Exception) [virtual]

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted, or the specified waiting time elapses. If the current count is zero then this method returns immediately with the value true.

If the current count is greater than zero then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happen:

* The count reaches zero due to invocations of the **countDown()** (p.1523) method; or * Some other thread interrupts the current thread; or * The specified waiting time elapses.

If the count reaches zero then the method returns with the value true.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting, then InterruptedException is thrown and the current thread's interrupted status is cleared. If the specified waiting time elapses then the value false is returned. If the time is less than or equal to zero, the method will not wait at all.

Parameters:

timeout - Time in milliseconds to wait for the count to reach zero.

Exceptions:

InterruptedException - if the current thread is interrupted while waiting.

Exception - if any other error occurs.

6.279.2.3 virtual void decaf::util::concurrent::CountDownLatch::await () throw (decaf::lang::exceptions::InterruptedException, decaf::lang::Exception)
[virtual]

Causes the current thread to wait until the latch has counted down to zero, unless the thread is interrupted. If the current count is zero then this method returns immediately.

If the current count is greater than zero then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of two things happen:

* The count reaches zero due to invocations of the **countDown()** (p. 1523) method; or * Some other thread interrupts the current thread.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting, then InterruptedException is thrown and the current thread's interrupted status is cleared.

Exceptions:

InterruptedException - if the current thread is interrupted while waiting.

Exception - if any other error occurs.

6.279.2.4 virtual void decaf::util::concurrent::CountDownLatch::countDown ()
[virtual]

Counts down the latch, releasing all waiting threads when the count hits zero.

6.279.2.5 virtual int decaf::util::concurrent::CountDownLatch::getCount () const
[inline, virtual]

Gets the current count.

Returns:

int count value

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/CountDownLatch.h

6.280 decaf::util::zip::CRC32 Class Reference

Class that can be used to compute a CRC-32 checksum for a data stream.

```
#include <src/main/decaf/util/zip/CRC32.h>Inheritance diagram for de-  
caf::util::zip::CRC32:
```

Public Member Functions

- **CRC32** ()
- virtual **~CRC32** ()
- virtual long long **getValue** () const
- virtual void **reset** ()
Reset the checksum to its initial value.
- virtual void **update** (const std::vector< unsigned char > &buffer)
Updates the current checksum with the specified vector of bytes.
- virtual void **update** (const std::vector< unsigned char > &buffer, int offset, int length)
throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Updates the current checksum with the specified array of bytes.
- virtual void **update** (const unsigned char *buffer, int size, int off-
set, int length) throw (decaf::lang::exceptions::NullPointerException, de-
caf::lang::exceptions::IndexOutOfBoundsException)
Updates the current checksum with the specified array of bytes.
- virtual void **update** (int byte)
Updates the current checksum with the specified byte value.

6.280.1 Detailed Description

Class that can be used to compute a CRC-32 checksum for a data stream.

Since:

1.0

6.280.2 Constructor & Destructor Documentation

6.280.2.1 decaf::util::zip::CRC32::CRC32 ()

6.280.2.2 virtual decaf::util::zip::CRC32::~~CRC32 () [virtual]

6.280.3 Member Function Documentation

6.280.3.1 virtual long long decaf::util::zip::CRC32::getValue () const [virtual]

Returns:

the current checksum value.

Implements **decaf::util::zip::Checksum** (p. 1142).

6.280.3.2 virtual void decaf::util::zip::CRC32::reset () [virtual]

Reset the checksum to its initial value.

Implements **decaf::util::zip::Checksum** (p. 1143).

6.280.3.3 virtual void decaf::util::zip::CRC32::update (int *byte*) [virtual]

Updates the current checksum with the specified byte value.

Parameters:

byte The byte value to update the current **Checksum** (p. 1142) with (0..255).

Implements **decaf::util::zip::Checksum** (p. 1143).

6.280.3.4 virtual void decaf::util::zip::CRC32::update (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

size The size of the passed buffer.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

NullPointerException if the passed buffer is NULL.

IndexOutOfBoundsException if offset + length > size of the buffer.

Implements **decaf::util::zip::Checksum** (p. 1143).

6.280.3.5 virtual void decaf::util::zip::CRC32::update (const std::vector< unsigned char > & *buffer*, int *offset*, int *length*) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Updates the current checksum with the specified array of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

offset The position in the buffer to start reading.

length The amount of data to read from the byte buffer.

Exceptions:

IndexOutOfBoundsException if $\text{offset} + \text{length} > \text{size of the buffer}$.

Implements **decaf::util::zip::Checksum** (p. 1143).

6.280.3.6 virtual void decaf::util::zip::CRC32::update (const std::vector< unsigned char > & *buffer*) [virtual]

Updates the current checksum with the specified vector of bytes.

Parameters:

buffer The buffer to read the updated bytes from.

Implements **decaf::util::zip::Checksum** (p. 1144).

The documentation for this class was generated from the following file:

- src/main/decaf/util/zip/**CRC32.h**

6.281 ct_data_s Struct Reference

```
#include <src/main/decaf/internal/util/zip/deflate.h>
```

Data Fields

- union {
 ush freq
 ush code
} fc
- union {
 ush dad
 ush len
} dl

6.281.1 Field Documentation

6.281.1.1 ush ct_data_s::code

6.281.1.2 ush ct_data_s::dad

6.281.1.3 union { ... } ct_data_s::dl

6.281.1.4 union { ... } ct_data_s::fc

6.281.1.5 ush ct_data_s::freq

6.281.1.6 ush ct_data_s::len

The documentation for this struct was generated from the following file:

- src/main/decaf/internal/util/zip/**deflate.h**

6.282 activemq::commands::DataArrayResponse Class Reference

#include <src/main/activemq/commands/DataArrayResponse.h> Inheritance diagram for activemq::commands::DataArrayResponse:

Public Member Functions

- **DataArrayResponse** ()
- virtual **~DataArrayResponse** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **DataArrayResponse * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::vector< **decaf::lang::Pointer**< **DataStructure** > & **getData** () const
- virtual std::vector< **decaf::lang::Pointer**< **DataStructure** > & **getData** ()
- virtual void **setData** (const std::vector< **decaf::lang::Pointer**< **DataStructure** > > &data)

Static Public Attributes

- static const unsigned char **ID_DATAARRAYRESPONSE** = 33

Protected Attributes

- std::vector< **decaf::lang::Pointer**< **DataStructure** > > **data**

6.282.1 Constructor & Destructor Documentation

6.282.1.1 `activemq::commands::DataArrayResponse::DataArrayResponse ()`

6.282.1.2 `virtual activemq::commands::DataArrayResponse::~~DataArrayResponse () [virtual]`

6.282.2 Member Function Documentation

6.282.2.1 `virtual DataArrayResponse* activemq::commands::DataArrayResponse::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.282.2.2 `virtual void activemq::commands::DataArrayResponse::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::Response` (p. 3286).

6.282.2.3 `virtual bool activemq::commands::DataArrayResponse::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::Response` (p. 3286).

- 6.282.2.4** `virtual std::vector< decaf::lang::Pointer<DataStructure> >& activemq::commands::DataArrayResponse::getData () [virtual]`
- 6.282.2.5** `virtual const std::vector< decaf::lang::Pointer<DataStructure> >& activemq::commands::DataArrayResponse::getData () const [virtual]`
- 6.282.2.6** `virtual unsigned char activemq::commands::DataArrayResponse::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Response** (p. 3287).

- 6.282.2.7** `virtual void activemq::commands::DataArrayResponse::setData (const std::vector< decaf::lang::Pointer< DataStructure > > & data) [virtual]`
- 6.282.2.8** `virtual std::string activemq::commands::DataArrayResponse::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Response** (p. 3287).

6.282.3 Field Documentation

- 6.282.3.1** `std::vector< decaf::lang::Pointer<DataStructure> > activemq::commands::DataArrayResponse::data [protected]`
- 6.282.3.2** `const unsigned char activemq::commands::DataArrayResponse::ID__ - DATAARRAYRESPONSE = 33 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/DataArrayResponse.h`

6.283 activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1531).

#include <src/main/activemq/wireformat/openwire/marshal/v2/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.283.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1531). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.283.2 Constructor & Destructor Documentation

6.283.2.1 `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::DataArrayResponseMarshaller()` [inline]

6.283.2.2 `virtual activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::~DataArrayResponseMarshaller()` [inline, virtual]

6.283.3 Member Function Documentation

6.283.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.283.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.283.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.283.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.283.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.283.3.6 virtual void activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3303).

6.283.3.7 virtual void activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3304).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**DataArrayResponseMarshaller.h**

6.284 activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1535).

#include <src/main/activemq/wireformat/openwire/marshal/v3/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.284.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1535). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.284.2 Constructor & Destructor Documentation

6.284.2.1 `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::DataArrayResponseMarshaller()` [inline]

6.284.2.2 `virtual activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::~DataArrayResponseMarshaller()` [inline, virtual]

6.284.3 Member Function Documentation

6.284.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.284.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.284.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.284.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.284.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.284.3.6 virtual void activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p. 3313).

6.284.3.7 virtual void activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p. 3314).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**DataArrayResponseMarshaller.h**

6.285 activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1539).

#include <src/main/activemq/wireformat/openwire/marshal/v4/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.285.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1539). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.285.2 Constructor & Destructor Documentation

6.285.2.1 `activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::DataArrayResponseMarshaller()` [inline]

6.285.2.2 `virtual activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::~DataArrayResponseMarshaller()` [inline, virtual]

6.285.3 Member Function Documentation

6.285.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.285.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.285.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.285.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.285.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.285.3.6 virtual void activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3298).

6.285.3.7 virtual void activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3299).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**DataArrayResponseMarshaller.h**

6.286 activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1543).

#include <src/main/activemq/wireformat/openwire/marshal/v1/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.286.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1543). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.286.2 Constructor & Destructor Documentation

6.286.2.1 `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::DataArrayResponseMarshaller()` [inline]

6.286.2.2 `virtual activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::~DataArrayResponseMarshaller()` [inline, virtual]

6.286.3 Member Function Documentation

6.286.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.286.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.286.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3316).

6.286.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::looseUnmarsh
(**OpenWireFormat** * *wireFormat*, **commands::DataStructure**
* *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3317).

6.286.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::tightMarshal
(**OpenWireFormat** * *wireFormat*, **commands::DataStructure** *
dataStructure, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3317).

6.286.3.6 virtual void activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p.3318).

6.286.3.7 virtual void activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p.3319).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**DataArrayResponseMarshaller.h**

6.287 activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1547).

#include <src/main/activemq/wireformat/openwire/marshal/v5/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.287.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1547). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.287.2 Constructor & Destructor Documentation

6.287.2.1 `activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::DataArrayR
() [inline]`

6.287.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::~~DataArray
() [inline, virtual]`

6.287.3 Member Function Documentation

6.287.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.287.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::getDataStruct
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.287.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.287.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.287.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.287.3.6 virtual void activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3308).

6.287.3.7 virtual void activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3309).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**DataArrayResponseMarshaller.h**

6.288 activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1551).

#include <src/main/activemq/wireformat/openwire/marshal/v6/DataArrayResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller:

Public Member Functions

- **DataArrayResponseMarshaller** ()
- virtual **~DataArrayResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.288.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **DataArrayResponseMarshaller** (p.1551). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.288.2 Constructor & Destructor Documentation

6.288.2.1 `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::DataArrayResponseMarshaller()` [inline]

6.288.2.2 `virtual activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::~DataArrayResponseMarshaller()` [inline, virtual]

6.288.3 Member Function Documentation

6.288.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.288.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.288.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.288.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.288.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.288.3.6 virtual void activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3323).

6.288.3.7 virtual void activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3324).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**DataArrayResponseMarshaller.h**

6.289 decaf::util::zip::DataFormatException Class Reference

#include <src/main/decaf/util/zip/DataFormatException.h> Inheritance diagram for decaf::util::zip::DataFormatException:

Public Member Functions

- **DataFormatException** () throw ()
Default Constructor.
- **DataFormatException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **DataFormatException** (const DataFormatException &ex) throw ()
Copy Constructor.
- **DataFormatException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **DataFormatException** (const std::exception *cause) throw ()
Constructor.
- **DataFormatException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **DataFormatException** * clone () const
Clones this exception.
- virtual ~**DataFormatException** () throw ()

6.289.1 Constructor & Destructor Documentation

6.289.1.1 decaf::util::zip::DataFormatException::DataFormatException () throw () [inline]

Default Constructor.

6.289.1.2 decaf::util::zip::DataFormatException::DataFormatException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.289.1.3 `decaf::util::zip::DataFormatException::DataFormatException (const DataFormatException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.289.1.4 `decaf::util::zip::DataFormatException::DataFormatException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.289.1.5 `decaf::util::zip::DataFormatException::DataFormatException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.289.1.6 `decaf::util::zip::DataFormatException::DataFormatException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.289.1.7 virtual decaf::util::zip::DataFormatException::~DataFormatException ()
throw () [inline, virtual]

6.289.2 Member Function Documentation

6.289.2.1 virtual DataFormatException* decaf::util::zip::DataFormatException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an Exception that is a copy of this instance.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- src/main/decaf/util/zip/**DataFormatException.h**

6.290 decaf::io::DataInput Class Reference

The **DataInput** (p.1558) interface provides for reading bytes from a binary stream and reconstructing from them data in any of the C++ primitive types.

```
#include <src/main/decaf/io/DataInput.h>
```

Public Member Functions

- virtual **~DataInput** ()
- virtual bool **readBoolean** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads in one byte and returns true if that byte is nonzero, false if that byte is zero.
- virtual char **readByte** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads and returns one input byte.
- virtual unsigned char **readUnsignedByte** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads one input byte, zero-extends it to type int, and returns the result, which is therefore in the range 0 through 255.
- virtual char **readChar** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads an input char and returns the char value.
- virtual double **readDouble** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads eight input bytes and returns a double value.
- virtual float **readFloat** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads four input bytes and returns a float value.
- virtual int **readInt** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads four input bytes and returns an int value.
- virtual long long **readLong** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads eight input bytes and returns a long value.
- virtual short **readShort** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads two input bytes and returns a short value.
- virtual unsigned short **readUnsignedShort** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads two input bytes and returns an int value in the range 0 through 65535.
- virtual std::string **readString** ()=0 throw (decaf::io::IOException, decaf::io::EOFException)
Reads an NULL terminated ASCII string to the stream and returns the string to the caller.
- virtual std::string **readLine** ()=0 throw (decaf::io::IOException)
Reads the next line of text from the input stream.

- virtual std::string **readUTF** ()=0 throw (decaf::io::IOException, decaf::io::EOFException, decaf::io::UTFDataFormatException)

Reads a modified UTF-8 encoded string in ASCII format and returns it, this is only useful if you know for sure that the string that is to be read was a string that contained all ASCII values (0-255), if so this method will throw a UTFFormatException.

- virtual void **readFully** (unsigned char *buffer, int size)=0 throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::IndexOutOfBoundsException)

Reads some bytes from an input stream and stores them into the buffer array buffer.

- virtual void **readFully** (unsigned char *buffer, int size, int offset, int length)=0 throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Reads length bytes from an input stream.

- virtual long long **skipBytes** (long long num)=0 throw (io::IOException)

Makes an attempt to skip over n bytes of data from the input stream, discarding the skipped bytes.

6.290.1 Detailed Description

The **DataInput** (p. 1558) interface provides for reading bytes from a binary stream and reconstructing from them data in any of the C++ primitive types. There is also a facility for reconstructing Strings from data in the Java standard modified UTF-8 format.

It is generally true of all the reading routines in this interface that if end of file is reached before the desired number of bytes has been read, an **EOFException** (p. 1825) is thrown. If any byte cannot be read for any reason other than end of file, an **IOException** (p. 2142) other than **EOFException** (p. 1825) is thrown. for example, an **IOException** (p. 2142) may be thrown if the underlying input stream has been closed.

See also:

DataOutput (p. 1574)

DataInputStream (p. 1566)

Since:

1.0

6.290.2 Constructor & Destructor Documentation

- 6.290.2.1 virtual decaf::io::DataInput::~~DataInput () [inline, virtual]

6.290.3 Member Function Documentation

- 6.290.3.1 virtual bool decaf::io::DataInput::readBoolean () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads in one byte and returns true if that byte is nonzero, false if that byte is zero.

Returns:

the boolean value of the read in byte (0=false, 1=true).

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.2 virtual char decaf::io::DataInput::readByte () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads and returns one input byte. The byte is treated as a signed value in the range -128 through 127, inclusive.

Returns:

the 8-bit value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.3 virtual char decaf::io::DataInput::readChar () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads an input char and returns the char value. A ascii char is made up of one bytes. This returns the same result as `readByte`

Returns:

the 8 bit char read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.4 virtual double decaf::io::DataInput::readDouble () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads eight input bytes and returns a double value. It does this by first constructing a long long value in exactly the manner of the `readLong` method, then converting this long value to a double in exactly the manner of the method `Double::longBitsToDouble`.

Returns:

the double value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.5 virtual float decaf::io::DataInput::readFloat () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads four input bytes and returns a float value. It does this by first constructing an int value in exactly the manner of the readInt method, then converting this int value to a float in exactly the manner of the method Float::intBitsToFloat.

Returns:

the float value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.6 virtual void decaf::io::DataInput::readFully (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Reads length bytes from an input stream. This method blocks until one of the following conditions occurs: * length bytes of input data are available, in which case a normal return is made. * End of file is detected, in which case an **EOFException** (p. 1825) is thrown. * An I/O error occurs, in which case an **IOException** (p. 2142) other than **EOFException** (p. 1825) is thrown.

If buffer is NULL, a NullPointerException is thrown. If offset+length is greater than the length of the array buffer, then an IndexOutOfBoundsException is thrown. If length is zero, then no bytes are read. Otherwise, the first byte read is stored into element buffer[off], the next one into buffer[offset+1], and so on. The number of bytes read is, at most, equal to length.

Parameters:

buffer The byte array to insert read data into.

size The size in bytes of the given byte buffer.

offset The location in buffer to start writing.

length The number of bytes to read from the buffer.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

NullPointerException if the buffer is NULL.

IndexOutOfBoundsException if the offset + length > size, or an int param is negative.

6.290.3.7 virtual void decaf::io::DataInput::readFully (unsigned char * *buffer*, int *size*) throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Reads some bytes from an input stream and stores them into the buffer array buffer. The number of bytes read is equal to the length of buffer.

This method blocks until one of the following conditions occurs: * buffer's size bytes of input data are available, in which case a normal return is made. * End of file is detected, in which case an **EOFException** (p. 1825) is thrown. * An I/O error occurs, in which case an **IOException** (p. 2142) other than **EOFException** (p. 1825) is thrown.

If buffer size is zero, then no bytes are read. Otherwise, the first byte read is stored into element b[0], the next one into buffer[1], and so on. If an exception is thrown from this method, then it may be that some but not all bytes of buffer have been updated with data from the input stream.

Parameters:

buffer The byte array to insert read data into.

size The size in bytes of the given byte buffer.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

IndexOutOfBoundsException if the size value is negative.

6.290.3.8 virtual int decaf::io::DataInput::readInt () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads four input bytes and returns an int value. Let a be the first byte read, b be the second byte, c be the third byte, and d be the fourth byte. The value returned is:

$((a \& 0xff) \ll 24) | ((b \& 0xff) \ll 16) | ((c \& 0xff) \ll 8) | (d \& 0xff)$

Returns:

the int value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.9 virtual std::string decaf::io::DataInput::readLine () throw (decaf::io::IOException) [pure virtual]

Reads the next line of text from the input stream. It reads successive bytes, converting each byte to an ASCII char separately, until it encounters a line terminator or end of file; the characters read are then returned as a standard String. Note that because this method processes bytes, it does not support input of the full Unicode character set.

If end of file is encountered before even one byte can be read, then an empty string is returned. Otherwise, each byte that is read is converted to type char. If the character ' is

' is encountered, it is discarded and reading ceases. If the character " is encountered, it is discarded and, if the following byte converts to the character ' is

', then that is discarded also; reading then ceases. If end of file is encountered before either of the characters ' and " is encountered, reading ceases. Once reading has ceased, a String is returned that contains all the characters read and not discarded, taken in order.

Returns:

the next line of text read from the input stream or empty string if at EOF.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

6.290.3.10 virtual long long decaf::io::DataInput::readLong () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads eight input bytes and returns a long value. Let a be the first byte read, b be the second byte, c be the third byte, d be the fourth byte, e be the fifth byte, f be the sixth byte, g be the seventh byte, and h be the eighth byte. The value returned is:

$$(((\text{long})(a \& 0\text{xff}) << 56) | ((\text{long})(b \& 0\text{xff}) << 48) | ((\text{long})(c \& 0\text{xff}) << 40) | ((\text{long})(d \& 0\text{xff}) << 32) | ((\text{long})(e \& 0\text{xff}) << 24) | ((\text{long})(f \& 0\text{xff}) << 16) | ((\text{long})(g \& 0\text{xff}) << 8) | ((\text{long})(h \& 0\text{xff})))$$
Returns:

the 64 bit long long read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.11 virtual short decaf::io::DataInput::readShort () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads two input bytes and returns a short value. Let a be the first byte read and b be the second byte. The value returned is:

$$(\text{short})((a << 8) | (b \& 0\text{xff}))$$
Returns:

the 16 bit short value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.12 virtual std::string decaf::io::DataInput::readString () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]

Reads an NULL terminated ASCII string to the stream and returns the string to the caller.

Returns:

string object containing the string read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.13 `virtual unsigned char decaf::io::DataInput::readUnsignedByte () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]`

Reads one input byte, zero-extends it to type int, and returns the result, which is therefore in the range 0 through 255.

Returns:

the 8 bit unsigned value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.14 `virtual unsigned short decaf::io::DataInput::readUnsignedShort () throw (decaf::io::IOException, decaf::io::EOFException) [pure virtual]`

Reads two input bytes and returns an int value in the range 0 through 65535. Let a be the first byte read and b be the second byte. The value returned is:

$((a \& 0xff) \ll 8) \mid (b \& 0xff)$

Returns:

the 16 bit unsigned short read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.290.3.15 `virtual std::string decaf::io::DataInput::readUTF ()
throw (decaf::io::IOException, decaf::io::EOFException,
decaf::io::UTFDataFormatException) [pure virtual]`

Reads a modified UTF-8 encoded string in ASCII format and returns it, this is only useful if you know for sure that the string that is to be read was a string that contained all ASCII values (0-255), if so this method will throw a UTFFormatException. This method reads String value written from a Java **DataOutputStream** (p. 1579) and assumes that the length prefix the precedes the encoded UTF-8 bytes is an unsigned short, which implies that the String will be no longer than 65535 characters.

Returns:

The decoded string read from stream.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

UTFDataFormatException (p. 3966) if the bytes are not valid modified UTF-8 values.

6.290.3.16 virtual long long decaf::io::DataInput::skipBytes (long long *num*) throw (io::IOException) [pure virtual]

Makes an attempt to skip over *n* bytes of data from the input stream, discarding the skipped bytes. However, it may skip over some smaller number of bytes, possibly zero. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. This method never throws an **EOFException** (p. 1825). The actual number of bytes skipped is returned.

Parameters:

num The number of bytes to skip over.

Returns:

the total number of bytes skipped.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

The documentation for this class was generated from the following file:

- src/main/decaf/io/**DataInput.h**

6.291 decaf::io::DataInputStream Class Reference

A data input stream lets an application read primitive Java data types from an underlying input stream in a machine-independent way.

#include <src/main/decaf/io/DataInputStream.h> Inheritance diagram for decaf::io::DataInputStream:

Public Member Functions

- **DataInputStream** (**InputStream** ***inputStream**, bool **own**=false)
*Creates a **DataInputStream** (p. 1566) that uses the specified underlying **InputStream** (p. 2043).*
- virtual ~**DataInputStream** ()
- virtual bool **readBoolean** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads in one byte and returns true if that byte is nonzero, false if that byte is zero.
- virtual char **readByte** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads and returns one input byte.
- virtual unsigned char **readUnsignedByte** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads one input byte, zero-extends it to type int, and returns the result, which is therefore in the range 0 through 255.
- virtual char **readChar** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads an input char and returns the char value.
- virtual double **readDouble** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads eight input bytes and returns a double value.
- virtual float **readFloat** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads four input bytes and returns a float value.
- virtual int **readInt** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads four input bytes and returns an int value.
- virtual long long **readLong** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads eight input bytes and returns a long value.
- virtual short **readShort** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads two input bytes and returns a short value.
- virtual unsigned short **readUnsignedShort** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads two input bytes and returns an int value in the range 0 through 65535.

- virtual std::string **readString** () throw (decaf::io::IOException, decaf::io::EOFException)
Reads an NULL terminated ASCII string to the stream and returns the string to the caller.
- virtual std::string **readLine** () throw (decaf::io::IOException)
Reads the next line of text from the input stream.
- virtual std::string **readUTF** () throw (decaf::io::IOException, decaf::io::EOFException, decaf::io::UTFDataFormatException)
Reads a modified UTF-8 encoded string in ASCII format and returns it, this is only useful if you know for sure that the string that is to be read was a string that contained all ASCII values (0-255), if so this method will throw a UTFFormatException.
- virtual void **readFully** (unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::IndexOutOfBoundsException)
Reads some bytes from an input stream and stores them into the buffer array buffer.
- virtual void **readFully** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Reads length bytes from an input stream.
- virtual long long **skipBytes** (long long num) throw (io::IOException)
Makes an attempt to skip over n bytes of data from the input stream, discarding the skipped bytes.

6.291.1 Detailed Description

A data input stream lets an application read primitive Java data types from an underlying input stream in a machine-independent way. An application uses a data output stream to write data that can later be read by a data input stream.

Due to the lack of garbage collection in C++ a design decision was made to add a boolean parameter to the constructor indicating if the wrapped **InputStream** (p.2043) is owned by this object. That way creation of the underlying stream can occur in a Java like way. Ex:

```
DataInputStream (p.1566) os = new DataInputStream (p.1566)( new InputStream()
(p.2045), true )
```

Since:

1.0

6.291.2 Constructor & Destructor Documentation

6.291.2.1 decaf::io::DataInputStream::DataInputStream (InputStream * inputStream, bool own = false)

Creates a **DataInputStream** (p.1566) that uses the specified underlying **InputStream** (p.2043).

Parameters:

inputStream the **InputStream** (p.2043) instance to wrap.

own indicates if this class owns the wrapped string defaults to false.

6.291.2.2 **virtual decaf::io::DataInputStream::~~DataInputStream ()** [virtual]

6.291.3 Member Function Documentation

6.291.3.1 **virtual bool decaf::io::DataInputStream::readBoolean () throw (**
 decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads in one byte and returns true if that byte is nonzero, false if that byte is zero.

Returns:

the boolean value of the read in byte (0=false, 1=true).

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.2 **virtual char decaf::io::DataInputStream::readByte () throw (**
 decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads and returns one input byte. The byte is treated as a signed value in the range -128 through 127, inclusive.

Returns:

the 8-bit value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.3 **virtual char decaf::io::DataInputStream::readChar () throw (**
 decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads an input char and returns the char value. A ascii char is made up of one bytes. This returns the same result as `readByte`

Returns:

the 8 bit char read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.4 virtual double decaf::io::DataInputStream::readDouble () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads eight input bytes and returns a double value. It does this by first constructing a long long value in exactly the manner of the readlong method, then converting this long value to a double in exactly the manner of the method Double::longBitsToDouble.

Returns:

the double value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.5 virtual float decaf::io::DataInputStream::readFloat () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads four input bytes and returns a float value. It does this by first constructing an int value in exactly the manner of the readInt method, then converting this int value to a float in exactly the manner of the method Float::intBitsToFloat.

Returns:

the float value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.6 virtual void decaf::io::DataInputStream::readFully (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::io::EOFException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Reads length bytes from an input stream. This method blocks until one of the following conditions occurs: * length bytes of input data are available, in which case a normal return is made. * End of file is detected, in which case an **EOFException** (p. 1825) is thrown. * An I/O error occurs, in which case an **IOException** (p. 2142) other than **EOFException** (p. 1825) is thrown.

If buffer is NULL, a NullPointerException is thrown. If offset+length is greater than the length of the array buffer, then an IndexOutOfBoundsException is thrown. If length is zero, then no bytes are read. Otherwise, the first byte read is stored into element buffer[offset], the next one into buffer[offset+1], and so on. The number of bytes read is, at most, equal to length.

Parameters:

buffer The byte array to insert read data into.

size The size in bytes of the given byte buffer.

offset The location in buffer to start writing.

length The number of bytes to read from the buffer.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

NullPointerException if the buffer is NULL.

IndexOutOfBoundsException if the offset + length > size.

6.291.3.7 **virtual void decaf::io::DataInputStream::readFully (unsigned char *
buffer, int size) throw (decaf::io::IOException, decaf::io::EOFException,
decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]**

Reads some bytes from an input stream and stores them into the buffer array buffer. The number of bytes read is equal to the length of buffer.

This method blocks until one of the following conditions occurs: * buffer's size bytes of input data are available, in which case a normal return is made. * End of file is detected, in which case an ***EOFException*** (p. 1825) is thrown. * An I/O error occurs, in which case an ***IOException*** (p. 2142) other than ***EOFException*** (p. 1825) is thrown.

If buffer size is zero, then no bytes are read. Otherwise, the first byte read is stored into element b[0], the next one into buffer[1], and so on. If an exception is thrown from this method, then it may be that some but not all bytes of buffer have been updated with data from the input stream.

Parameters:

buffer The byte array to insert read data into.

size The size in bytes of the given byte buffer.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

IndexOutOfBoundsException if the size value is negative.

6.291.3.8 **virtual int decaf::io::DataInputStream::readInt () throw (
decaf::io::IOException, decaf::io::EOFException) [virtual]**

Reads four input bytes and returns an int value. Let a be the first byte read, b be the second byte, c be the third byte, and d be the fourth byte. The value returned is:

$((a \& 0xff) << 24) | ((b \& 0xff) << 16) | ((c \& 0xff) << 8) | (d \& 0xff)$

Returns:

the int value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.9 virtual std::string decaf::io::DataInputStream::readLine () throw (decaf::io::IOException) [virtual]

Reads the next line of text from the input stream. It reads successive bytes, converting each byte to an ASCII char separately, until it encounters a line terminator or end of file; the characters read are then returned as a standard String. Note that because this method processes bytes, it does not support input of the full Unicode character set.

If end of file is encountered before even one byte can be read, then an empty string is returned. Otherwise, each byte that is read is converted to type char. If the character ' ' is encountered, it is discarded and reading ceases. If the character " " is encountered, it is discarded and, if the following byte converts to the character ' ' , then that is discarded also; reading then ceases. If end of file is encountered before either of the characters ' ' and " " is encountered, reading ceases. Once reading has ceased, a String is returned that contains all the characters read and not discarded, taken in order.

' is encountered, it is discarded and reading ceases. If the character " " is encountered, it is discarded and, if the following byte converts to the character ' ' , then that is discarded also; reading then ceases. If end of file is encountered before either of the characters ' ' and " " is encountered, reading ceases. Once reading has ceased, a String is returned that contains all the characters read and not discarded, taken in order.

' , then that is discarded also; reading then ceases. If end of file is encountered before either of the characters ' ' and " " is encountered, reading ceases. Once reading has ceased, a String is returned that contains all the characters read and not discarded, taken in order.

' and " " is encountered, reading ceases. Once reading has ceased, a String is returned that contains all the characters read and not discarded, taken in order.

Returns:

the next line of text read from the input stream or empty string if at EOF.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

6.291.3.10 virtual long long decaf::io::DataInputStream::readLong () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads eight input bytes and returns a long value. Let a be the first byte read, b be the second byte, c be the third byte, d be the fourth byte, e be the fifth byte, f be the sixth byte, g be the seventh byte, and h be the eighth byte. The value returned is:

$$(((\text{long})(a \& 0\text{xff}) << 56) | ((\text{long})(b \& 0\text{xff}) << 48) | ((\text{long})(c \& 0\text{xff}) << 40) | ((\text{long})(d \& 0\text{xff}) << 32) | ((\text{long})(e \& 0\text{xff}) << 24) | ((\text{long})(f \& 0\text{xff}) << 16) | ((\text{long})(g \& 0\text{xff}) << 8) | ((\text{long})(h \& 0\text{xff})))$$

Returns:

the 64 bit long long read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.11 virtual short decaf::io::DataInputStream::readShort () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads two input bytes and returns a short value. Let a be the first byte read and b be the second byte. The value returned is:

$$(\text{short})((a << 8) | (b \& 0\text{xff}))$$

Returns:

the 16 bit short value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.12 virtual std::string decaf::io::DataInputStream::readString () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads an NULL terminated ASCII string to the stream and returns the string to the caller.

Returns:

string object containing the string read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.13 virtual unsigned char decaf::io::DataInputStream::readUnsignedByte () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads one input byte, zero-extends it to type int, and returns the result, which is therefore in the range 0 through 255.

Returns:

the 8 bit unsigned value read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.14 virtual unsigned short decaf::io::DataInputStream::readUnsignedShort () throw (decaf::io::IOException, decaf::io::EOFException) [virtual]

Reads two input bytes and returns an int value in the range 0 through 65535. Let a be the first byte read and b be the second byte. The value returned is:

$((a \& 0xff) \ll 8) | (b \& 0xff)$

Returns:

the 16 bit unsigned short read.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

6.291.3.15 **virtual std::string decaf::io::DataInputStream::readUTF ()**
 throw (decaf::io::IOException, decaf::io::EOFException,
 decaf::io::UTFDataFormatException) [virtual]

Reads a modified UTF-8 encoded string in ASCII format and returns it, this is only useful if you know for sure that the string that is to be read was a string that contained all ASCII values (0-255), if so this method will throw a **UTFFormatException**. This method reads String value written from a Java **DataOutputStream** (p. 1579) and assumes that the length prefix the precedes the encoded UTF-8 bytes is an unsigned short, which implies that the String will be no longer than 65535 characters.

Returns:

The decoded string read from stream.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

EOFException (p. 1825) if the end of input is reached.

UTFDataFormatException (p. 3966) if the bytes are not valid modified UTF-8 values.

6.291.3.16 **virtual long long decaf::io::DataInputStream::skipBytes (long long num)**
 throw (io::IOException) [virtual]

Makes an attempt to skip over n bytes of data from the input stream, discarding the skipped bytes. However, it may skip over some smaller number of bytes, possibly zero. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. This method never throws an **EOFException** (p. 1825). The actual number of bytes skipped is returned.

Parameters:

num The number of bytes to skip over.

Returns:

the total number of bytes skipped.

Exceptions:

IOException (p. 2142) if an I/O Error occurs.

The documentation for this class was generated from the following file:

- src/main/decaf/io/**DataInputStream.h**

6.292 decaf::io::DataOutput Class Reference

The **DataOutput** (p. 1574) interface provides for converting data from any of the C++ primitive types to a series of bytes and writing these bytes to a binary stream.

```
#include <src/main/decaf/io/DataOutput.h>
```

Public Member Functions

- virtual **~DataOutput** ()
- virtual void **writeBoolean** (bool value)=0 throw (decaf::io::IOException)
Writes a boolean to the underlying output stream as a 1-byte value.
- virtual void **writeByte** (unsigned char value)=0 throw (decaf::io::IOException)
Writes out a byte to the underlying output stream as a 1-byte value.
- virtual void **writeShort** (short value)=0 throw (decaf::io::IOException)
Writes a short to the underlying output stream as two bytes, high byte first.
- virtual void **writeUnsignedShort** (unsigned short value)=0 throw (decaf::io::IOException)
Writes a unsigned short to the bytes message stream as a 2 byte value.
- virtual void **writeChar** (char value)=0 throw (decaf::io::IOException)
Writes out a char to the underlying output stream as a one byte value If no exception is thrown, the counter written is incremented by 1.
- virtual void **writeInt** (int value)=0 throw (decaf::io::IOException)
Writes an int to the underlying output stream as four bytes, high byte first.
- virtual void **writeLong** (long long value)=0 throw (decaf::io::IOException)
Writes an 64 bit long to the underlying output stream as eight bytes, high byte first.
- virtual void **writeFloat** (float value)=0 throw (decaf::io::IOException)
Converts the float argument to an int using the floatToIntBits method in class Float, and then writes that int value to the underlying output stream as a 4-byte quantity, high byte first.
- virtual void **writeDouble** (double value)=0 throw (decaf::io::IOException)
Converts the double argument to a long using the doubleToLongBits method in class Double, and then writes that long value to the underlying output stream as an 8-byte quantity, high byte first.
- virtual void **writeBytes** (const std::string &value)=0 throw (decaf::io::IOException)
Writes out the string to the underlying output stream as a sequence of bytes.
- virtual void **writeChars** (const std::string &value)=0 throw (decaf::io::IOException)
Writes a string to the underlying output stream as a sequence of characters.
- virtual void **writeUTF** (const std::string &value)=0 throw (decaf::io::IOException, decaf::io::UTFDataFormatException)
Writes out the string to the underlying output stream as a modeified UTF-8 encoded sequence of bytes.

6.292.1 Detailed Description

The **DataOutput** (p. 1574) interface provides for converting data from any of the C++ primitive types to a series of bytes and writing these bytes to a binary stream. There is also a facility for converting Strings into the Java standard modified UTF-8 format and writing the resulting series of bytes.

If a method in this interface encounters an error while writing it will throw an **IOException** (p. 2142).

See also:

DataInput (p. 1558)

DataOutputStream (p. 1579)

Since:

1.0

6.292.2 Constructor & Destructor Documentation

6.292.2.1 virtual decaf::io::DataOutput::~~DataOutput () [inline, virtual]

6.292.3 Member Function Documentation

6.292.3.1 virtual void decaf::io::DataOutput::writeBoolean (bool *value*) throw (decaf::io::IOException) [pure virtual]

Writes a boolean to the underlying output stream as a 1-byte value. The value true is written out as the value (byte)1; the value false is written out as the value (byte)0. If no exception is thrown, the counter written is incremented by 1.

Parameters:

value The boolean to write as a byte (1=true, 0=false).

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.2 virtual void decaf::io::DataOutput::writeByte (unsigned char *value*) throw (decaf::io::IOException) [pure virtual]

Writes out a byte to the underlying output stream as a 1-byte value. If no exception is thrown, the counter written is incremented by 1.

Parameters:

value The unsigned char value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.3 virtual void decaf::io::DataOutput::writeBytes (const std::string & *value*) throw (decaf::io::IOException) [pure virtual]

Writes out the string to the underlying output stream as a sequence of bytes. Each character in the string is written out, in sequence, by discarding its high eight bits. If no exception is thrown, the counter written is incremented by the length of value. The value written does not include a trailing null as that is not part of the sequence of bytes, if the null is needed, then use the writeChars method.

Parameters:

value The vector of bytes to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.4 virtual void decaf::io::DataOutput::writeChar (char *value*) throw (decaf::io::IOException) [pure virtual]

Writes out a char to the underlying output stream as a one byte value. If no exception is thrown, the counter written is incremented by 1.

Parameters:

value The signed char value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.5 virtual void decaf::io::DataOutput::writeChars (const std::string & *value*) throw (decaf::io::IOException) [pure virtual]

Writes a string to the underlying output stream as a sequence of characters. Each character is written to the data output stream as if by the writeChar method. If no exception is thrown, the counter written is incremented by the length of value. The trailing NULL character is written by this method.

Parameters:

value The string value to write as raw bytes.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.6 virtual void decaf::io::DataOutput::writeDouble (double *value*) throw (decaf::io::IOException) [pure virtual]

Converts the double argument to a long using the doubleToLongBits method in class Double, and then writes that long value to the underlying output stream as an 8-byte quantity, high byte first. If no exception is thrown, the counter written is incremented by 8.

Parameters:

value The 64bit double value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.7 virtual void decaf::io::DataOutput::writeFloat (float *value*) throw (decaf::io::IOException) [pure virtual]

Converts the float argument to an int using the floatToIntBits method in class Float, and then writes that int value to the underlying output stream as a 4-byte quantity, high byte first. If no exception is thrown, the counter written is incremented by 4.

Parameters:

value The 32bit floating point value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.8 virtual void decaf::io::DataOutput::writeInt (int *value*) throw (decaf::io::IOException) [pure virtual]

Writes an int to the underlying output stream as four bytes, high byte first. If no exception is thrown, the counter written is incremented by 4.

Parameters:

value The signed integer value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.9 virtual void decaf::io::DataOutput::writeLong (long long *value*) throw (decaf::io::IOException) [pure virtual]

Writes an 64 bit long to the underlying output stream as eight bytes, high byte first. If no exception is thrown, the counter written is incremented by 8.

Parameters:

value The signed 64bit long value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.10 `virtual void decaf::io::DataOutput::writeShort (short value) throw (decaf::io::IOException)` [pure virtual]

Writes a short to the underlying output stream as two bytes, high byte first. If no exception is thrown, the counter written is incremented by 2.

Parameters:

value The signed short value to write.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.11 `virtual void decaf::io::DataOutput::writeUnsignedShort (unsigned short value) throw (decaf::io::IOException)` [pure virtual]

Writes a unsigned short to the bytes message stream as a 2 byte value.

Parameters:

value The unsigned short to write to the stream.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

6.292.3.12 `virtual void decaf::io::DataOutput::writeUTF (const std::string & value) throw (decaf::io::IOException, decaf::io::UTFDataFormatException)` [pure virtual]

Writes out the string to the underlying output stream as a modeified UTF-8 encoded sequence of bytes. The first two bytes written are indicate its encoded length followed by the rest of the string's characters encoded as modified UTF-8. The length represent the encoded length of the data not the actual length of the string.

Parameters:

value The string value value to write as modified UTF-8.

Exceptions:

IOException (p. 2142) if an I/O error is encountered.

UTFDataFormatException (p. 3966) if the encoded size if greater than 65535

The documentation for this class was generated from the following file:

- `src/main/decaf/io/DataOutput.h`

6.293 decaf::io::DataOutputStream Class Reference

A data output stream lets an application write primitive Java data types to an output stream in a portable way.

#include <src/main/decaf/io/DataOutputStream.h> Inheritance diagram for decaf::io::DataOutputStream:

Public Member Functions

- **DataOutputStream** (**OutputStream** ***outputStream**, bool **own**=false)
Creates a new data output stream to write data to the specified underlying output stream.
- virtual ~**DataOutputStream** ()
- virtual long long **size** () const
Returns the current value of the counter written, the number of bytes written to this data output stream so far.
- virtual void **writeBoolean** (bool value) throw (**IOException**)
- virtual void **writeByte** (unsigned char value) throw (**IOException**)
- virtual void **writeShort** (short value) throw (**IOException**)
- virtual void **writeUnsignedShort** (unsigned short value) throw (**IOException**)
- virtual void **writeChar** (char value) throw (**IOException**)
- virtual void **writeInt** (int value) throw (**IOException**)
- virtual void **writeLong** (long long value) throw (**IOException**)
- virtual void **writeFloat** (float value) throw (**IOException**)
- virtual void **writeDouble** (double value) throw (**IOException**)
- virtual void **writeBytes** (const std::string &value) throw (**IOException**)

- virtual void **writeChars** (const std::string &value) throw (IOException)
- virtual void **writeUTF** (const std::string &value) throw (IOException, UTFDataFormatException)

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char ***buffer**, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Protected Attributes

- long long **written**
- unsigned char **buffer** [8]

6.293.1 Detailed Description

A data output stream lets an application write primitive Java data types to an output stream in a portable way. An application can then use a data input stream to read the data back in.

6.293.2 Constructor & Destructor Documentation

6.293.2.1 decaf::io::DataOutputStream::DataOutputStream (OutputStream * *outputStream*, bool *own* = false)

Creates a new data output stream to write data to the specified underlying output stream.

Parameters:

outputStream a stream to wrap with this one.

own true if this objects owns the stream that it wraps.

6.293.2.2 virtual decaf::io::DataOutputStream::~~DataOutputStream () [virtual]

6.293.3 Member Function Documentation

6.293.3.1 virtual void decaf::io::DataOutputStream::doWriteArrayBounded (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.293.3.2 virtual void decaf::io::DataOutputStream::doWriteByte (unsigned char *value*) throw (decaf::io::IOException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.293.3.3 virtual long long decaf::io::DataOutputStream::size () const [inline, virtual]

Returns the current value of the counter written, the number of bytes written to this data output stream so far. If the counter overflows, it will be wrapped to **decaf::lang::Long::MAX_VALUE** (p. 2433).

Returns:

the value of the written field.

- 6.293.3.4 virtual void decaf::io::DataOutputStream::writeBoolean (bool *value*)
throw (IOException) [virtual]
- 6.293.3.5 virtual void decaf::io::DataOutputStream::writeByte (unsigned char
value) throw (IOException) [virtual]
- 6.293.3.6 virtual void decaf::io::DataOutputStream::writeBytes (const std::string &
value) throw (IOException) [virtual]
- 6.293.3.7 virtual void decaf::io::DataOutputStream::writeChar (char *value*) throw (
IOException) [virtual]
- 6.293.3.8 virtual void decaf::io::DataOutputStream::writeChars (const std::string
& *value*) throw (IOException) [virtual]
- 6.293.3.9 virtual void decaf::io::DataOutputStream::writeDouble (double *value*)
throw (IOException) [virtual]
- 6.293.3.10 virtual void decaf::io::DataOutputStream::writeFloat (float *value*) throw
(IOException) [virtual]
- 6.293.3.11 virtual void decaf::io::DataOutputStream::writeInt (int *value*) throw (
IOException) [virtual]
- 6.293.3.12 virtual void decaf::io::DataOutputStream::writeLong (long long *value*)
throw (IOException) [virtual]
- 6.293.3.13 virtual void decaf::io::DataOutputStream::writeShort (short *value*)
throw (IOException) [virtual]
- 6.293.3.14 virtual void decaf::io::DataOutputStream::writeUnsignedShort
(unsigned short *value*) throw (IOException) [virtual]
- 6.293.3.15 virtual void decaf::io::DataOutputStream::writeUTF (const std::string
& *value*) throw (IOException, UTFDataFormatException) [virtual]

6.293.4 Field Documentation

- 6.293.4.1 unsigned char decaf::io::DataOutputStream::buffer[8] [protected]
- 6.293.4.2 long long decaf::io::DataOutputStream::written [protected]

The documentation for this class was generated from the following file:

- src/main/decaf/io/**DataOutputStream.h**

6.294 activemq::commands::DataResponse Class Reference

#include <src/main/activemq/commands/DataResponse.h> Inheritance diagram for activemq::commands::DataResponse:

Public Member Functions

- **DataResponse** ()
- virtual **~DataResponse** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **DataResponse * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **DataStructure** > &**getData** () const
- virtual **Pointer**< **DataStructure** > &**getData** ()
- virtual void **setData** (const **Pointer**< **DataStructure** > &data)

Static Public Attributes

- static const unsigned char **ID_DATARESPONSE** = 32

Protected Attributes

- **Pointer**< **DataStructure** > data

6.294.1 Constructor & Destructor Documentation

6.294.1.1 `activemq::commands::DataResponse::DataResponse ()`

6.294.1.2 `virtual activemq::commands::DataResponse::~~DataResponse ()`
[virtual]

6.294.2 Member Function Documentation

6.294.2.1 `virtual DataResponse* activemq::commands::DataResponse::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.294.2.2 `virtual void activemq::commands::DataResponse::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::Response` (p. 3286).

6.294.2.3 `virtual bool activemq::commands::DataResponse::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::Response` (p. 3286).

- 6.294.2.4** `virtual Pointer<DataStructure>& activemq::commands::DataResponse::getData ()`
[virtual]
- 6.294.2.5** `virtual const Pointer<DataStructure>& activemq::commands::DataResponse::getData () const`
[virtual]
- 6.294.2.6** `virtual unsigned char activemq::commands::DataResponse::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Response** (p. 3287).

- 6.294.2.7** `virtual void activemq::commands::DataResponse::setData (const Pointer< DataStructure > & data)` [virtual]
- 6.294.2.8** `virtual std::string activemq::commands::DataResponse::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Response** (p. 3287).

6.294.3 Field Documentation

- 6.294.3.1** `Pointer<DataStructure> activemq::commands::DataResponse::data`
[protected]
- 6.294.3.2** `const unsigned char activemq::commands::DataResponse::ID_ - DATARESPONSE = 32` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/DataResponse.h`

6.295 activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1586).

#include <src/main/activemq/wireformat/openwire/marshal/v5/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.295.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1586).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.295.2 Constructor & Destructor Documentation

6.295.2.1 `activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::DataResponseMar
() [inline]`

6.295.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::~~DataResponseM
() [inline, virtual]`

6.295.3 Member Function Documentation

6.295.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller`
(p. 3306).

6.295.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller`
(p. 3306).

6.295.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.295.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.295.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.295.3.6 virtual void activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3308).

6.295.3.7 virtual void activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3309).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**DataResponseMarshaller.h**

6.296 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1590).

#include <src/main/activemq/wireformat/openwire/marshal/v6/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.296.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1590).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.296.2 Constructor & Destructor Documentation

6.296.2.1 `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::DataResponseMarshaller()` [inline]

6.296.2.2 `virtual activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::~~DataResponseMarshaller()` [inline, virtual]

6.296.3 Member Function Documentation

6.296.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.296.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.296.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.296.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.296.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.296.3.6 virtual void activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3323).

6.296.3.7 virtual void activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3324).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**DataResponseMarshaller.h**

6.297 activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1594).

#include <src/main/activemq/wireformat/openwire/marshal/v2/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.297.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1594).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.297.2 Constructor & Destructor Documentation

6.297.2.1 `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::DataResponseMarshaller()` [inline]

6.297.2.2 `virtual activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::~~DataResponseMarshaller()` [inline, virtual]

6.297.3 Member Function Documentation

6.297.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.297.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.297.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.297.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.297.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.297.3.6 virtual void activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3303).

6.297.3.7 virtual void activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3304).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**DataResponseMarshaller.h**

6.298 activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1598).

#include <src/main/activemq/wireformat/openwire/marshal/v3/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.298.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1598).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.298.2 Constructor & Destructor Documentation

6.298.2.1 `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::DataResponseMarshaller()` [inline]

6.298.2.2 `virtual activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::~~DataResponseMarshaller()` [inline, virtual]

6.298.3 Member Function Documentation

6.298.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.298.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.298.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.298.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.298.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.298.3.6 virtual void activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p.3313).

6.298.3.7 virtual void activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p.3314).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**DataResponseMarshaller.h**

6.299 activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1602).

#include <src/main/activemq/wireformat/openwire/marshal/v4/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.299.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1602).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.299.2 Constructor & Destructor Documentation

6.299.2.1 `activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::DataResponseMarshaller()` [inline]

6.299.2.2 `virtual activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::~~DataResponseMarshaller()` [inline, virtual]

6.299.3 Member Function Documentation

6.299.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.299.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.299.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.299.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.299.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.299.3.6 virtual void activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p.3298).

6.299.3.7 virtual void activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p.3299).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**DataResponseMarshaller.h**

6.300 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1606).

#include <src/main/activemq/wireformat/openwire/marshal/v1/DataResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller:

Public Member Functions

- **DataResponseMarshaller** ()
- virtual **~DataResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.300.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DataResponseMarshaller** (p.1606).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.300.2 Constructor & Destructor Documentation

6.300.2.1 `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::DataResponseMar
() [inline]`

6.300.2.2 `virtual
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::~~DataResponseM
() [inline, virtual]`

6.300.3 Member Function Documentation

6.300.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller`
(p. 3316).

6.300.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller`
(p. 3316).

6.300.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.300.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.300.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.300.3.6 virtual void activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3318).

6.300.3.7 virtual void activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3319).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**DataResponseMarshaller.h**

6.301 activemq::wireformat::openwire::marshal::DataStreamMarshaller Class Reference

Base class for all classes that **marshal** (p.107) **commands** (p. 87) for Openwire.

#include <src/main/activemq/wireformat/openwire/marshal/DataStreamMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::DataStreamMarshaller:

Public Member Functions

- virtual **~DataStreamMarshaller** ()
- virtual unsigned char **getDataStructureType** () const =0
Gets the DataStructureType that this class marshals/unmarshals.
- virtual **commands::DataStructure * createObject** () const =0
Creates a new instance of the class that this class is a marshaling director for.
- virtual int **tightMarshal1** (**OpenWireFormat *format**, **commands::DataStructure *command**, **utils::BooleanStream *bs**)=0 throw (**decaf::io::IOException**)
Tight Marhsal to the given stream.
- virtual void **tightMarshal2** (**OpenWireFormat *format**, **commands::DataStructure *command**, **decaf::io::DataOutputStream *ds**, **utils::BooleanStream *bs**)=0 throw (**decaf::io::IOException**)
Tight Marhsal to the given stream.
- virtual void **tightUnmarshal** (**OpenWireFormat *format**, **commands::DataStructure *command**, **decaf::io::DataInputStream *dis**, **utils::BooleanStream *bs**)=0 throw (**decaf::io::IOException**)
Tight Un-marhsal to the given stream.
- virtual void **looseMarshal** (**OpenWireFormat *format**, **commands::DataStructure *command**, **decaf::io::DataOutputStream *ds**)=0 throw (**decaf::io::IOException**)
Tight Marhsal to the given stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *format**, **commands::DataStructure *command**, **decaf::io::DataInputStream *dis**)=0 throw (**decaf::io::IOException**)
Loose Un-marhsal to the given stream.

6.301.1 Detailed Description

Base class for all classes that **marshal** (p.107) **commands** (p. 87) for Openwire.

6.301.2 Constructor & Destructor Documentation

6.301.2.1 virtual
activemq::wireformat::openwire::marshal::DataStreamMarshaller::~~DataStreamMarshaller
() [inline, virtual]

6.301.3 Member Function Documentation

6.301.3.1 virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::DataStreamMarshaller::createObject
() const [pure virtual]

Creates a new instance of the class that this class is a marshaling director for.

Returns:

newly allocated Command

Implemented in activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller (p. 214), activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller (p. 254), activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller (p. 379), activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller (p. 406), activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller (p. 451), activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller (p. 496), activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller (p. 557), activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller (p. 614), activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller (p. 647), activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller (p. 676), activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller (p. 704), activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller (p. 881), activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller (p. 913), activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller (p. 1281), activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller (p. 1313), activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller (p. 1344), activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller (p. 1374), activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (p. 1419), activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (p. 1448), activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1481), activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1510), activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1544), activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1607), activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1745), activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (p. 1779), activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1863), activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1957), activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2111), activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (p. 2180), activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (p. 2209), activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (p. 2232), activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (p. 2263), activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2290), activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller (p. 2325), activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller (p. 2372), activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller

(p. 2582), `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller`
 (p. 2623), `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller`
 (p. 2652), `activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller` (p. 2689),
`activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller` (p. 2761), `ac-`
`tivemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller` (p. 2817),
`activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2943),
`activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller` (p. 3061),
`activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller` (p. 3093),
`activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller` (p. 3110),
`activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller` (p. 3211), `ac-`
`tivemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller`
 (p. 3228), `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller`
 (p. 3259), `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316),
`activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller` (p. 3404), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller` (p. 3420), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller` (p. 3482), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller` (p. 3681),
`activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller` (p. 3856),
`activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller` (p. 4009),
`activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller` (p. 4049),
`activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller`
 (p. 222), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller`
 (p. 270), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller`
 (p. 391), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller`
 (p. 418), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller`
 (p. 463), `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller`
 (p. 508), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller`
 (p. 569), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller`
 (p. 626), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller`
 (p. 655), `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller`
 (p. 688), `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller`
 (p. 716), `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller` (p. 893),
`activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 925), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1293),
`activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1301),
`activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller` (p. 1332),
`activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1362),
`activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1407),
`activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller` (p. 1436),
`activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1469), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1498), `ac-`
`tivemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1532),
`activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1595),
`activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1733),
`activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller` (p. 1767), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1847),
`activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1945),
`activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2099),
`activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller` (p. 2164),
`activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller` (p. 2193),
`activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller` (p. 2216), `ac-`
`tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller` (p. 2247),
`activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2274),
`activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller`

(p. 2313), activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller (p. 2356),
 activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller (p. 2570),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller (p. 2607),
 activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller (p. 2640),
 activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller (p. 2669),
 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2745),
 activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller (p. 2797),
 activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller (p. 2927),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3041),
 activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller (p. 3073),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3106),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3199),
 activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller (p. 3236),
 activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller (p. 3263),
 activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3301),
 activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller (p. 3384),
 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3428),
 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3478),
 activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller (p. 3697),
 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3872),
 activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (p. 4001),
 activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (p. 4041),
 activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller (p. 210),
 activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller (p. 250),
 activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller (p. 375),
 activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller (p. 402),
 activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller (p. 447),
 activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller (p. 492),
 activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller (p. 553),
 activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller (p. 610),
 activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller (p. 639),
 activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller (p. 668),
 activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller (p. 696),
 activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (p. 873),
 activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (p. 905),
 activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (p. 1273),
 activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (p. 1305),
 activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (p. 1336),
 activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (p. 1366),
 activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1411),
 activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (p. 1440),
 activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1473),
 activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1502),
 activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1536),
 activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1599),
 activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1737),
 activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (p. 1771),
 activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1851),
 activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1949),
 activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2103),
 activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (p. 2172),
 activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (p. 2197),
 activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (p. 2220),
 activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (p. 2251),

activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2278),
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller
(p. 2309), activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller
(p. 2360), activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller
(p. 2574), activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller
(p. 2611), activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller
(p. 2644), activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (p. 2681),
activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2753), ac-
tivemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (p. 2809),
activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (p. 2935),
activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3049),
activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (p. 3081),
activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3118),
activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3207), ac-
tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller
(p. 3232), activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller
(p. 3267), activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3311),
activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller (p. 3400), ac-
tivemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3424), ac-
tivemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3490), ac-
tivemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller (p. 3677),
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3860),
activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller (p. 4013),
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller (p. 4053),
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller
(p. 218), activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller
(p. 258), activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller
(p. 383), activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller
(p. 410), activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller
(p. 455), activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller
(p. 500), activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller
(p. 561), activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller
(p. 618), activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller
(p. 643), activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller
(p. 672), activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller
(p. 700), activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (p. 877),
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (p. 909), ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (p. 1277),
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (p. 1309),
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (p. 1340),
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (p. 1370),
activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1415),
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (p. 1444),
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1477), ac-
tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1506), ac-
tivemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1540),
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1603),
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1741),
activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (p. 1775), ac-
tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1859),
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1953),
activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2107),
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (p. 2176),
activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (p. 2205),

activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (p. 2228), activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (p. 2259), activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2282), activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller (p. 2321), activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller (p. 2368), activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (p. 2578), activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (p. 2619), activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller (p. 2648), activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (p. 2673), activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2757), activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (p. 2813), activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2939), activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3045), activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3077), activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3102), activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3219), activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller (p. 3248), activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller (p. 3255), activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3296), activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3388), activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3432), activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3494), activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3689), activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3868), activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4005), activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4045), activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller (p. 226), activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller (p. 262), activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller (p. 387), activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller (p. 414), activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller (p. 459), activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMessageMarshaller (p. 504), activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller (p. 565), activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller (p. 622), activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller (p. 651), activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller (p. 680), activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller (p. 708), activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller (p. 885), activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller (p. 917), activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (p. 1285), activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (p. 1317), activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller (p. 1348), activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (p. 1378), activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (p. 1423), activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller (p. 1452), activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (p. 1485), activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (p. 1514), activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (p. 1548), activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1587), activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1753), activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller (p. 1783), activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1855), activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1961), activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2115),

activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller (p. 2168),
activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller (p. 2189),
activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller (p. 2236),
activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller (p. 2255),
activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2286),
activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller
(p. 2317), activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller
(p. 2364), activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller
(p. 2586), activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
(p. 2615), activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
(p. 2656), activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller (p. 2677),
activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2749),
activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller (p. 2805),
activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller (p. 2931),
activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3053),
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller (p. 3085),
activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3114),
activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3215),
activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
(p. 3244), activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
(p. 3275), activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3306),
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller (p. 3396),
activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3416),
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3486),
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (p. 3685),
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3852),
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (p. 3993),
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (p. 4057),
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller
(p. 230), activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller
(p. 266), activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller
(p. 395), activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller
(p. 422), activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller
(p. 467), activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller
(p. 512), activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller
(p. 573), activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller
(p. 630), activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller
(p. 659), activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller
(p. 684), activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller
(p. 712), activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (p. 889),
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (p. 921),
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (p. 1289),
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (p. 1321),
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (p. 1352),
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (p. 1382),
activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1427),
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (p. 1456),
activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1489),
activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1518),
activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1552),
activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1591),
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1749),
activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (p. 1763),
activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1843),

activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1941),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2095),
 activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (p. 2160),
 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (p. 2201),
 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (p. 2224),
 activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (p. 2243),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2270),
 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller
 (p. 2305), activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller
 (p. 2352), activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller
 (p. 2566), activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller
 (p. 2627), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
 (p. 2636), activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (p. 2685),
 activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2765),
 activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (p. 2801),
 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (p. 2923),
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3057),
 activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (p. 3089),
 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3122),
 activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3203),
 activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller
 (p. 3240), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller
 (p. 3271), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3321),
 activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller (p. 3392),
 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3412),
 activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3474),
 activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (p. 3693),
 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3864),
 activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (p. 3997), and
 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (p. 4037).

6.301.3.2 virtual unsigned char ac-

tivemq::wireformat::openwire::marshal::DataStreamMarshaller::getDataStructureType
 () const [pure virtual]

Gets the DataStructureType that this class marshals/unmarshals.

Returns:

byte Id of this classes DataStructureType

Implemented in activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller
 (p. 214), activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller
 (p. 254), activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller
 (p. 379), activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller
 (p. 406), activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller
 (p. 451), activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller
 (p. 496), activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller
 (p. 557), activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller
 (p. 614), activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller
 (p. 647), activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller
 (p. 676), activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller
 (p. 704), activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller (p. 881),

activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller (p. 913),
 activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller (p. 1281),
 activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller (p. 1313),
 activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller (p. 1344),
 activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller (p. 1374),
 activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (p. 1419),
 activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (p. 1448),
 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1481),
 activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1510),
 activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1544),
 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1607),
 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1745),
 activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (p. 1779),
 activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1863),
 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1957),
 activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2111),
 activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (p. 2180),
 activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (p. 2209),
 activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (p. 2232),
 activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (p. 2263),
 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2290),
 activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller
 (p. 2325),
 activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller
 (p. 2372),
 activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller
 (p. 2582),
 activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller
 (p. 2623),
 activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller
 (p. 2652),
 activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller (p. 2689),
 activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2761),
 activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller (p. 2817),
 activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller (p. 2943),
 activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3061),
 activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller (p. 3093),
 activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3110),
 activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3211),
 activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller
 (p. 3228),
 activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller
 (p. 3259),
 activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3316),
 activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller (p. 3404),
 activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3420),
 activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3482),
 activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller (p. 3681),
 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3856),
 activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (p. 4009),
 activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (p. 4049),
 activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller
 (p. 222),
 activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller
 (p. 270),
 activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller
 (p. 391),
 activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller
 (p. 418),
 activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller
 (p. 463),
 activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller
 (p. 508),
 activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller
 (p. 569),
 activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller
 (p. 626),
 activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller
 (p. 655),
 activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller

(p. 688), `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller`
(p. 716), `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller` (p. 893),
`activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 925), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1293),
`activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1301),
`activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller` (p. 1332),
`activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1362),
`activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1407),
`activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller` (p. 1436),
`activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1469), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1498), `ac-`
`tivemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1532),
`activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1595),
`activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1733),
`activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller` (p. 1767), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1847),
`activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1945),
`activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2099),
`activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller` (p. 2164),
`activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller` (p. 2193),
`activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller` (p. 2216), `ac-`
`tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller` (p. 2247),
`activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2274),
`activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller`
(p. 2313), `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller`
(p. 2356), `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller`
(p. 2570), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller`
(p. 2607), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller`
(p. 2640), `activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller` (p. 2669),
`activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller` (p. 2745), `ac-`
`tivemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller` (p. 2797),
`activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2927),
`activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller` (p. 3041),
`activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller` (p. 3073),
`activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller` (p. 3106),
`activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller` (p. 3199), `ac-`
`tivemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller`
(p. 3236), `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller`
(p. 3263), `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301),
`activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller` (p. 3384), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller` (p. 3428), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller` (p. 3478), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller` (p. 3697),
`activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller` (p. 3872),
`activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller` (p. 4001),
`activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller` (p. 4041),
`activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller`
(p. 210), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller`
(p. 250), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller`
(p. 375), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller`
(p. 402), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller`
(p. 447), `activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller`
(p. 492), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller`
(p. 553), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller`

(p. 610), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller`
 (p. 639), `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller`
 (p. 668), `activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller`
 (p. 696), `activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller` (p. 873),
`activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller` (p. 905), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller` (p. 1273),
`activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller` (p. 1305),
`activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller` (p. 1336),
`activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller` (p. 1366),
`activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller` (p. 1411),
`activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller` (p. 1440),
`activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller` (p. 1473), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller` (p. 1502), `ac-`
`tivemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1536),
`activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1599),
`activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller` (p. 1737),
`activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller` (p. 1771), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1851),
`activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller` (p. 1949),
`activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2103),
`activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller` (p. 2172),
`activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller` (p. 2197),
`activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller` (p. 2220), `ac-`
`tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller` (p. 2251),
`activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller` (p. 2278),
`activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller`
 (p. 2309), `activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller`
 (p. 2360), `activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller`
 (p. 2574), `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller`
 (p. 2611), `activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller`
 (p. 2644), `activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller` (p. 2681),
`activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller` (p. 2753), `ac-`
`tivemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller` (p. 2809),
`activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2935),
`activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller` (p. 3049),
`activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller` (p. 3081),
`activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller` (p. 3118),
`activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller` (p. 3207), `ac-`
`tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller`
 (p. 3232), `activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller`
 (p. 3267), `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311),
`activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller` (p. 3400), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller` (p. 3424), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller` (p. 3490), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller` (p. 3677),
`activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller` (p. 3860),
`activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller` (p. 4013),
`activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller` (p. 4053),
`activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller`
 (p. 218), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller`
 (p. 258), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller`
 (p. 383), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller`
 (p. 410), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller`
 (p. 455), `activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller`

(p. 500), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller`
 (p. 561), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller`
 (p. 618), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller`
 (p. 643), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller`
 (p. 672), `activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller`
 (p. 700), `activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller` (p. 877),
`activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller` (p. 909), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller` (p. 1277),
`activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller` (p. 1309),
`activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller` (p. 1340),
`activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller` (p. 1370),
`activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller` (p. 1415),
`activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller` (p. 1444),
`activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller` (p. 1477), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller` (p. 1506), `ac-`
`tivemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1540),
`activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller` (p. 1603),
`activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller` (p. 1741),
`activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller` (p. 1775), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller` (p. 1859),
`activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller` (p. 1953),
`activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller` (p. 2107),
`activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller` (p. 2176),
`activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller` (p. 2205),
`activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller` (p. 2228), `ac-`
`tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller` (p. 2259),
`activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller` (p. 2282),
`activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller`
 (p. 2321), `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller`
 (p. 2368), `activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller`
 (p. 2578), `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller`
 (p. 2619), `activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller`
 (p. 2648), `activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller` (p. 2673),
`activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller` (p. 2757), `ac-`
`tivemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller` (p. 2813),
`activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2939),
`activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller` (p. 3045),
`activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller` (p. 3077),
`activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller` (p. 3102),
`activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller` (p. 3219), `ac-`
`tivemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller`
 (p. 3248), `activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller`
 (p. 3255), `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296),
`activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller` (p. 3388), `ac-`
`tivemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller` (p. 3432), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller` (p. 3494), `ac-`
`tivemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller` (p. 3689),
`activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller` (p. 3868),
`activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller` (p. 4005),
`activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller` (p. 4045),
`activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller`
 (p. 226), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller`
 (p. 262), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller`
 (p. 387), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller`

(p. 414), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller`
 (p. 459), `activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller`
 (p. 504), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller`
 (p. 565), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller`
 (p. 622), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller`
 (p. 651), `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller`
 (p. 680), `activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller`
 (p. 708), `activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller` (p. 885),
`activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller` (p. 917), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller` (p. 1285),
`activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller` (p. 1317),
`activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller` (p. 1348),
`activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller` (p. 1378),
`activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller` (p. 1423),
`activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller` (p. 1452),
`activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller` (p. 1485), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller` (p. 1514), `ac-`
`tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1548),
`activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1587),
`activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller` (p. 1753),
`activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller` (p. 1783), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1855),
`activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller` (p. 1961),
`activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2115),
`activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller` (p. 2168),
`activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller` (p. 2189),
`activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller` (p. 2236), `ac-`
`tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller` (p. 2255),
`activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller` (p. 2286),
`activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller`
 (p. 2317), `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller`
 (p. 2364), `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller`
 (p. 2586), `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller`
 (p. 2615), `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller`
 (p. 2656), `activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller` (p. 2677),
`activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller` (p. 2749), `ac-`
`tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller` (p. 2805),
`activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2931),
`activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller` (p. 3053),
`activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller` (p. 3085),
`activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller` (p. 3114),
`activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller` (p. 3215), `ac-`
`tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller`
 (p. 3244), `activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller`
 (p. 3275), `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306),
`activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller` (p. 3396), `ac-`
`tivemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller` (p. 3416), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller` (p. 3486), `ac-`
`tivemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller` (p. 3685),
`activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller` (p. 3852),
`activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller` (p. 3993),
`activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller` (p. 4057),
`activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller`
 (p. 230), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller`

(p. 266), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller`
 (p. 395), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller`
 (p. 422), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller`
 (p. 467), `activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller`
 (p. 512), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller`
 (p. 573), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller`
 (p. 630), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller`
 (p. 659), `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller`
 (p. 684), `activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller`
 (p. 712), `activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller` (p. 889),
`activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller` (p. 921), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller` (p. 1289),
`activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller` (p. 1321),
`activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller` (p. 1352),
`activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller` (p. 1382),
`activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller` (p. 1427),
`activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller` (p. 1456),
`activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller` (p. 1489), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller` (p. 1518), `ac-`
`tivemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1552),
`activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1591),
`activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller` (p. 1749),
`activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller` (p. 1763), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1843),
`activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller` (p. 1941),
`activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2095),
`activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller` (p. 2160),
`activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller` (p. 2201),
`activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller` (p. 2224), `ac-`
`tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller` (p. 2243),
`activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller` (p. 2270),
`activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller`
 (p. 2305), `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller`
 (p. 2352), `activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller`
 (p. 2566), `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller`
 (p. 2627), `activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller`
 (p. 2636), `activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller` (p. 2685),
`activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller` (p. 2765), `ac-`
`tivemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller` (p. 2801),
`activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2923),
`activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller` (p. 3057),
`activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller` (p. 3089),
`activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller` (p. 3122),
`activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller` (p. 3203), `ac-`
`tivemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller`
 (p. 3240), `activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller`
 (p. 3271), `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321),
`activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller` (p. 3392), `ac-`
`tivemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller` (p. 3412), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller` (p. 3474), `ac-`
`tivemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller` (p. 3693),
`activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller` (p. 3864), `ac-`
`tivemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller` (p. 3997), and
`activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller` (p. 4037).

6.301.3.3 virtual void activemq::wireformat::openwire::marshal::DataStreamMarshaller::looseMarshal (OpenWireFormat * *format*, commands::DataStructure * *command*, decaf::io::DataOutputStream * *ds*) throw (decaf::io::IOException)
[pure virtual]

Tight Marshal to the given stream.

Parameters:

format - The OpenWireFormat properties
command - the object to Marshal
ds - DataOutputStream to **marshal** (p.107) to

Exceptions:

IOException if an error occurs.

Implemented in activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller (p. 214), activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller (p. 254), activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller (p. 338), activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller (p. 379), activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller (p. 406), activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller (p. 451), activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller (p. 496), activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller (p. 557), activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller (p. 585), activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller (p. 614), activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller (p. 647), activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller (p. 676), activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller (p. 704), activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller (p. 780), activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller (p. 881), activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller (p. 913), activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller (p. 1281), activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller (p. 1313), activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller (p. 1344), activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller (p. 1374), activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (p. 1419), activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (p. 1448), activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1481), activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1510), activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1544), activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1607), activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1745), activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (p. 1779), activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1863), activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1957), activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2111), activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (p. 2180), activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (p. 2209), activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (p. 2232), activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (p. 2263), activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2290),

activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller (p. 2325),
activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller (p. 2372),
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller (p. 2582),
activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller (p. 2623),
activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller (p. 2652),
activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller (p. 2689),
activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2714),
activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2761),
activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller (p. 2817),
activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller (p. 2943),
activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3061),
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller (p. 3093),
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3110),
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3211),
activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller (p. 3228),
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller (p. 3259),
activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3316),
activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller (p. 3404),
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3420),
activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3482),
activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller (p. 3681),
activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller (p. 3828),
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3856),
activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (p. 4009),
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (p. 4049),
activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller (p. 222),
activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller (p. 270),
activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller (p. 350),
activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller (p. 391),
activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller (p. 418),
activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller (p. 463),
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller (p. 508),
activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller (p. 569),
activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller (p. 597),
activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller (p. 626),
activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller (p. 655),
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller (p. 688),
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller (p. 716),
activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller (p. 801),
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller (p. 893),
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller (p. 925),
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller (p. 1293),
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller (p. 1301),
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller (p. 1332),
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller (p. 1362),
activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller (p. 1407),
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller (p. 1436),
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller (p. 1469),
activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller (p. 1498),
activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller (p. 1532),
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (p. 1595),
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (p. 1733),
activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller (p. 1767),
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (p. 1847),

activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (p. 1945),
 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (p. 2099),
 activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller (p. 2164),
 activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller (p. 2193),
 activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller (p. 2216),
 activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller (p. 2247),
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (p. 2274),
 activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller
 (p. 2313), activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller
 (p. 2356), activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller
 (p. 2570), activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller
 (p. 2607), activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
 (p. 2640), activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller (p. 2669),
 activemq::wireformat::openwire::marshal::v2::MessageMarshaller (p. 2704),
 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2745),
 activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller (p. 2797),
 activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller (p. 2927),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3041),
 activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller (p. 3073),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3106),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3199),
 activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller
 (p. 3236), activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller
 (p. 3263), activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3301),
 activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller (p. 3384),
 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3428),
 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3478),
 activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller (p. 3697),
 activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller (p. 3832),
 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3872),
 activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (p. 4001),
 activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (p. 4041),
 activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller
 (p. 210), activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller
 (p. 250), activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller
 (p. 334), activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller
 (p. 375), activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller
 (p. 402), activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller
 (p. 447), activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller
 (p. 492), activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller
 (p. 553), activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller
 (p. 581), activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller
 (p. 610), activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller
 (p. 639), activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller
 (p. 668), activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller
 (p. 696), activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller
 (p. 766), activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (p. 873),
 activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (p. 905),
 activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (p. 1273),
 activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (p. 1305),
 activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (p. 1336),
 activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (p. 1366),
 activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1411),
 activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (p. 1440),

activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1473),
activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1502),
activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1536),
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1599),
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1737),
activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (p. 1771),
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1851),
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1949),
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2103),
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (p. 2172),
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (p. 2197),
activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (p. 2220),
activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (p. 2251),
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2278),
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller
(p. 2309), activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller
(p. 2360), activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller
(p. 2574), activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller
(p. 2611), activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller
(p. 2644), activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (p. 2681),
activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2699),
activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2753),
activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (p. 2809),
activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (p. 2935),
activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3049),
activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (p. 3081),
activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3118),
activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3207),
activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller
(p. 3232), activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller
(p. 3267), activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3311),
activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller (p. 3400),
activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3424),
activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3490),
activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller (p. 3677),
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller (p. 3836),
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3860),
activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller (p. 4013),
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller (p. 4053),
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller
(p. 218), activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller
(p. 258), activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller
(p. 342), activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller
(p. 383), activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller
(p. 410), activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller
(p. 455), activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller
(p. 500), activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller
(p. 561), activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller
(p. 589), activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller
(p. 618), activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller
(p. 643), activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller
(p. 672), activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller
(p. 700), activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller
(p. 773), activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (p. 877),

activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (p. 909),
 activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (p. 1277),
 activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (p. 1309),
 activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (p. 1340),
 activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (p. 1370),
 activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1415),
 activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (p. 1444),
 activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1477),
 activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1506),
 activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1540),
 activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1603),
 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1741),
 activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (p. 1775),
 activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1859),
 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1953),
 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2107),
 activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (p. 2176),
 activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (p. 2205),
 activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (p. 2228),
 activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (p. 2259),
 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2282),
 activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller (p. 2321),
 activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller (p. 2368),
 activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (p. 2578),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (p. 2619),
 activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller (p. 2648),
 activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (p. 2673),
 activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2709),
 activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2757),
 activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (p. 2813),
 activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2939),
 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3045),
 activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3077),
 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3102),
 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3219),
 activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller (p. 3248),
 activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller (p. 3255),
 activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3296),
 activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3388),
 activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3432),
 activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3494),
 activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3689),
 activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (p. 3840),
 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3868),
 activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4005),
 activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4045),
 activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller (p. 226),
 activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller (p. 262),
 activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller (p. 346),
 activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller (p. 387),
 activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller (p. 414),
 activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller (p. 459),
 activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller (p. 504),
 activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller

(p. 565), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller`
 (p. 593), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller`
 (p. 622), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller`
 (p. 651), `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller`
 (p. 680), `activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller`
 (p. 708), `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller`
 (p. 787), `activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller` (p. 885),
`activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller` (p. 917), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller` (p. 1285),
`activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller` (p. 1317),
`activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller` (p. 1348),
`activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller` (p. 1378),
`activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller` (p. 1423),
`activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller` (p. 1452),
`activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller` (p. 1485), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller` (p. 1514), `ac-`
`tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1548),
`activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1587),
`activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller` (p. 1753),
`activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller` (p. 1783), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1855),
`activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller` (p. 1961),
`activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2115),
`activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller` (p. 2168),
`activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller` (p. 2189),
`activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller` (p. 2236), `ac-`
`tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller` (p. 2255),
`activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller` (p. 2286),
`activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller`
 (p. 2317), `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller`
 (p. 2364), `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller`
 (p. 2586), `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller`
 (p. 2615), `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller`
 (p. 2656), `activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller` (p. 2677),
`activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694), `ac-`
`tivemq::wireformat::openwire::marshal::v5::MessagePullMarshaller` (p. 2749), `ac-`
`tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller` (p. 2805),
`activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2931),
`activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller` (p. 3053),
`activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller` (p. 3085),
`activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller` (p. 3114),
`activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller` (p. 3215), `ac-`
`tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller`
 (p. 3244), `activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller`
 (p. 3275), `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306),
`activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller` (p. 3396), `ac-`
`tivemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller` (p. 3416), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller` (p. 3486), `ac-`
`tivemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller` (p. 3685),
`activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller` (p. 3824),
`activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller` (p. 3852),
`activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller` (p. 3993),
`activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller` (p. 4057),
`activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller`

(p. 230), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller`
 (p. 266), `activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller`
 (p. 354), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller`
 (p. 395), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller`
 (p. 422), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller`
 (p. 467), `activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller`
 (p. 512), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller`
 (p. 573), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller`
 (p. 601), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller`
 (p. 630), `activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller`
 (p. 659), `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller`
 (p. 684), `activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller`
 (p. 712), `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller`
 (p. 794), `activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller` (p. 889),
`activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller` (p. 921), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller` (p. 1289),
`activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller` (p. 1321),
`activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller` (p. 1352),
`activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller` (p. 1382),
`activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller` (p. 1427),
`activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller` (p. 1456),
`activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller` (p. 1489), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller` (p. 1518), `ac-`
`tivemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1552),
`activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1591),
`activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller` (p. 1749),
`activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller` (p. 1763), `ac-`
`tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1843),
`activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller` (p. 1941),
`activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2095),
`activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller` (p. 2160),
`activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller` (p. 2201),
`activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller` (p. 2224), `ac-`
`tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller` (p. 2243),
`activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller` (p. 2270),
`activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller`
 (p. 2305), `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller`
 (p. 2352), `activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller`
 (p. 2566), `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller`
 (p. 2627), `activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller`
 (p. 2636), `activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller` (p. 2685),
`activemq::wireformat::openwire::marshal::v6::MessageMarshaller` (p. 2719), `ac-`
`tivemq::wireformat::openwire::marshal::v6::MessagePullMarshaller` (p. 2765), `ac-`
`tivemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller` (p. 2801),
`activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2923),
`activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller` (p. 3057),
`activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller` (p. 3089),
`activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller` (p. 3122),
`activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller` (p. 3203), `ac-`
`tivemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller`
 (p. 3240), `activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller`
 (p. 3271), `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321),
`activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller` (p. 3392), `ac-`
`tivemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller` (p. 3412), `ac-`

tivemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3474), activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (p. 3693), activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller (p. 3844), activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3864), activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (p. 3997), and activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (p. 4037).

6.301.3.4 virtual void activemq::wireformat::openwire::marshal::DataStreamMarshaller::looseUnmarshal (OpenWireFormat * *format*, commands::DataStructure * *command*, decaf::io::DataInputStream * *dis*) throw (decaf::io::IOException) [pure virtual]

Loose Un-marhsal to the given stream.

Parameters:

format - The OpenWireFormat properties
command - the object to Un-Marshal
dis - the DataInputStream to Un-Marshal from

Exceptions:

IOException if an error occurs.

Implemented in activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller (p. 215), activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller (p. 255), activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller (p. 338), activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller (p. 380), activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller (p. 407), activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller (p. 452), activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller (p. 497), activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller (p. 558), activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller (p. 585), activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller (p. 615), activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller (p. 648), activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller (p. 677), activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller (p. 705), activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller (p. 781), activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller (p. 882), activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller (p. 914), activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller (p. 1282), activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller (p. 1314), activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller (p. 1345), activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller (p. 1375), activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller (p. 1420), activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (p. 1449), activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1482), activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1511), activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1545), activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1608), activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1746), activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (p. 1780), activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1864),

activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1958),
 activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2112),
 activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (p. 2181),
 activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (p. 2210),
 activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (p. 2233),
 activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (p. 2264),
 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2291),
 activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller
 (p. 2326), activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller
 (p. 2373), activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller
 (p. 2583), activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller
 (p. 2624), activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller
 (p. 2653), activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller (p. 2690),
 activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2714),
 activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2762),
 activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller (p. 2818),
 activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller (p. 2944),
 activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3062),
 activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller (p. 3094),
 activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3111),
 activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3212),
 activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller
 (p. 3229), activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller
 (p. 3260), activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3317),
 activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller (p. 3405),
 activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3421),
 activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3483),
 activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller (p. 3682),
 activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller (p. 3828),
 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3857),
 activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (p. 4010),
 activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (p. 4050),
 activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller
 (p. 223), activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller
 (p. 271), activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller
 (p. 350), activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller
 (p. 392), activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller
 (p. 419), activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller
 (p. 464), activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller
 (p. 509), activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller
 (p. 570), activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller
 (p. 597), activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller
 (p. 627), activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller
 (p. 656), activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller
 (p. 689), activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller
 (p. 717), activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller
 (p. 802), activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller (p. 894),
 activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller (p. 926),
 activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller (p. 1294),
 activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller (p. 1302),
 activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller (p. 1333),
 activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller (p. 1363),
 activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller (p. 1408),
 activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller (p. 1437),

activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller (p. 1470),
 activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller (p. 1499),
 activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller (p. 1533),
 activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (p. 1596),
 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (p. 1734),
 activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller (p. 1768),
 activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (p. 1848),
 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (p. 1946),
 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (p. 2100),
 activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller (p. 2165),
 activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller (p. 2194),
 activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller (p. 2217),
 activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller (p. 2248),
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (p. 2275),
 activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller
 (p. 2314), activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller
 (p. 2357), activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller
 (p. 2571), activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller
 (p. 2608), activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
 (p. 2641), activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller (p. 2670),
 activemq::wireformat::openwire::marshal::v2::MessageMarshaller (p. 2704),
 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2746),
 activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller (p. 2798),
 activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller (p. 2928),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3042),
 activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller (p. 3074),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3107),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3200),
 activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller
 (p. 3237), activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller
 (p. 3264), activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3302),
 activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller (p. 3385),
 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3429),
 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3479),
 activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller (p. 3698),
 activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller (p. 3832),
 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3873),
 activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (p. 4002),
 activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (p. 4042),
 activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller
 (p. 211), activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller
 (p. 251), activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller
 (p. 334), activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller
 (p. 376), activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller
 (p. 403), activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller
 (p. 448), activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller
 (p. 493), activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller
 (p. 554), activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller
 (p. 581), activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller
 (p. 611), activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller
 (p. 640), activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller
 (p. 669), activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller
 (p. 697), activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller
 (p. 767), activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (p. 874),

activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (p. 906),
 activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (p. 1274),
 activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (p. 1306),
 activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (p. 1337),
 activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (p. 1367),
 activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1412),
 activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (p. 1441),
 activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1474),
 activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1503),
 activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1537),
 activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1600),
 activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1738),
 activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (p. 1772),
 activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1852),
 activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1950),
 activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2104),
 activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (p. 2173),
 activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (p. 2198),
 activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (p. 2221),
 activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (p. 2252),
 activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2279),
 activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller (p. 2310),
 activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller (p. 2361),
 activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (p. 2575),
 activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller (p. 2612),
 activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller (p. 2645),
 activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (p. 2682),
 activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2699),
 activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2754),
 activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (p. 2810),
 activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (p. 2936),
 activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3050),
 activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (p. 3082),
 activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3119),
 activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3208),
 activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller (p. 3233),
 activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller (p. 3268),
 activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3312),
 activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller (p. 3401),
 activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3425),
 activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3491),
 activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller (p. 3678),
 activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller (p. 3836),
 activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3861),
 activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller (p. 4014),
 activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller (p. 4054),
 activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller (p. 219),
 activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller (p. 259),
 activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller (p. 342),
 activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller (p. 384),
 activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller (p. 411),
 activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller (p. 456),
 activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller (p. 501),
 activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller

(p. 562), activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller
(p. 589), activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller
(p. 619), activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller
(p. 644), activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller
(p. 673), activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller
(p. 701), activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller
(p. 774), activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (p. 878),
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (p. 910), ac-
tivemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (p. 1278),
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (p. 1310),
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (p. 1341),
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (p. 1371),
activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1416),
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (p. 1445),
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1478), ac-
tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1507), ac-
tivemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1541),
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1604),
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1742),
activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (p. 1776), ac-
tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1860),
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1954),
activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2108),
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (p. 2177),
activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (p. 2206),
activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (p. 2229), ac-
tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (p. 2260),
activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2283),
activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller
(p. 2322), activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller
(p. 2369), activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller
(p. 2579), activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller
(p. 2620), activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller
(p. 2649), activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (p. 2674),
activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2709), ac-
tivemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2758), ac-
tivemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (p. 2814),
activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2940),
activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3046),
activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3078),
activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3103),
activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3220), ac-
tivemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller
(p. 3249), activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller
(p. 3256), activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3297),
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3389), ac-
tivemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3433), ac-
tivemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3495), ac-
tivemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3690),
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (p. 3840),
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3869),
activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4006),
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4046),
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller

(p. 227), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller`
 (p. 263), `activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller`
 (p. 346), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller`
 (p. 388), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller`
 (p. 415), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller`
 (p. 460), `activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller`
 (p. 505), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller`
 (p. 566), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller`
 (p. 593), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller`
 (p. 623), `activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller`
 (p. 652), `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller`
 (p. 681), `activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller`
 (p. 709), `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller`
 (p. 788), `activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller` (p. 886),
`activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller` (p. 918), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller` (p. 1286),
`activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller` (p. 1318),
`activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller` (p. 1349),
`activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller` (p. 1379),
`activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller` (p. 1424),
`activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller` (p. 1453),
`activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller` (p. 1486), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller` (p. 1515), `ac-`
`tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1549),
`activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1588),
`activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller` (p. 1754),
`activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller` (p. 1784), `ac-`
`tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1856),
`activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller` (p. 1962),
`activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2116),
`activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller` (p. 2169),
`activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller` (p. 2190),
`activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller` (p. 2237), `ac-`
`tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller` (p. 2256),
`activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller` (p. 2287),
`activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller`
 (p. 2318), `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller`
 (p. 2365), `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller`
 (p. 2587), `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller`
 (p. 2616), `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller`
 (p. 2657), `activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller` (p. 2678),
`activemq::wireformat::openwire::marshal::v5::MessageMarshaller` (p. 2694), `ac-`
`tivemq::wireformat::openwire::marshal::v5::MessagePullMarshaller` (p. 2750), `ac-`
`tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller` (p. 2806),
`activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2932),
`activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller` (p. 3054),
`activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller` (p. 3086),
`activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller` (p. 3115),
`activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller` (p. 3216), `ac-`
`tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller`
 (p. 3245), `activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller`
 (p. 3276), `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307),
`activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller` (p. 3397), `ac-`
`tivemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller` (p. 3417), `ac-`

tivemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3487),
 tivemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (p. 3686),
 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller (p. 3824),
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3853),
 activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (p. 3994),
 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (p. 4058),
 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller
 (p. 231), activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller
 (p. 267), activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller
 (p. 354), activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller
 (p. 396), activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller
 (p. 423), activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller
 (p. 468), activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller
 (p. 513), activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller
 (p. 574), activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller
 (p. 601), activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller
 (p. 631), activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller
 (p. 660), activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller
 (p. 685), activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller
 (p. 713), activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller
 (p. 795), activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (p. 890),
 activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (p. 922),
 tivemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (p. 1290),
 activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (p. 1322),
 activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (p. 1353),
 activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (p. 1383),
 activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1428),
 activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (p. 1457),
 activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1490),
 tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1519),
 tivemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1553),
 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1592),
 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1750),
 activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (p. 1764),
 tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1844),
 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1942),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2096),
 activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (p. 2161),
 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (p. 2202),
 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (p. 2225),
 tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (p. 2244),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2271),
 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller
 (p. 2306), activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller
 (p. 2353), activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller
 (p. 2567), activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller
 (p. 2628), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
 (p. 2637), activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (p. 2686),
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2719),
 tivemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766),
 tivemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (p. 2802),
 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (p. 2924),
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058),
 activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (p. 3090),

`activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller` (p. 3123),
`activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller` (p. 3204), `activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller` (p. 3241),
`activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller` (p. 3272), `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322),
`activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller` (p. 3393), `activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller` (p. 3413), `activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller` (p. 3475), `activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller` (p. 3694),
`activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3844), `activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller` (p. 3865), `activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller` (p. 3998), and
`activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller` (p. 4038).

6.301.3.5 `virtual int activemq::wireformat::openwire::marshal::DataStreamMarshaller::tightMarshal1 (OpenWireFormat * format, commands::DataStructure * command, utils::BooleanStream * bs) throw (decaf::io::IOException)` [pure virtual]

Tight Marshal to the given stream.

Parameters:

format - The OpenWireFormat properties
command - the object to Marshal
bs - boolean stream to `marshal` (p. 107) to.

Exceptions:

IOException if an error occurs.

Implemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 215), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 255), `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller` (p. 339), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 380), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 407), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 452), `activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller` (p. 497), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 558), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller` (p. 586), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller` (p. 615), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller` (p. 648), `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 677), `activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller` (p. 705), `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782), `activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller` (p. 882), `activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 914), `activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1282), `activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1314), `activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller` (p. 1345), `activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1375), `activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1420),

activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller (p. 1449),
 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller (p. 1482), ac-
 tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller (p. 1511), ac-
 tivemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller (p. 1545),
 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller (p. 1608),
 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller (p. 1746),
 activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller (p. 1780), ac-
 tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller (p. 1864),
 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller (p. 1958),
 activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller (p. 2112),
 activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller (p. 2181),
 activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller (p. 2210),
 activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller (p. 2233), ac-
 tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller (p. 2264),
 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller (p. 2291),
 activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller
 (p. 2326), activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller
 (p. 2373), activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller
 (p. 2583), activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller
 (p. 2624), activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller
 (p. 2653), activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller (p. 2690),
 activemq::wireformat::openwire::marshal::v1::MessageMarshaller (p. 2715), ac-
 tivemq::wireformat::openwire::marshal::v1::MessagePullMarshaller (p. 2762), ac-
 tivemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller (p. 2818),
 activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller (p. 2944),
 activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller (p. 3062),
 activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller (p. 3094),
 activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller (p. 3111),
 activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller (p. 3212), ac-
 tivemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller
 (p. 3229), activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller
 (p. 3260), activemq::wireformat::openwire::marshal::v1::ResponseMarshaller (p. 3317),
 activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller (p. 3405), ac-
 tivemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller (p. 3421), ac-
 tivemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller (p. 3483), ac-
 tivemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller (p. 3682),
 activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller (p. 3829),
 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3857),
 activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (p. 4010),
 activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (p. 4050),
 activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller
 (p. 223), activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller
 (p. 271), activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller
 (p. 351), activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller
 (p. 392), activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller
 (p. 419), activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller
 (p. 464), activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller
 (p. 509), activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller
 (p. 570), activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller
 (p. 598), activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller
 (p. 627), activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller
 (p. 656), activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller
 (p. 689), activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller
 (p. 717), activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller

(p. 803), `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller` (p. 894),
`activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 926), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1294),
`activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1302),
`activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller` (p. 1333),
`activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1363),
`activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1408),
`activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller` (p. 1437),
`activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1470), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1499), `ac-`
`tivemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1533),
`activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1596),
`activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1734),
`activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller` (p. 1768), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1848),
`activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1946),
`activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2100),
`activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller` (p. 2165),
`activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller` (p. 2194),
`activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller` (p. 2217), `ac-`
`tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller` (p. 2248),
`activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2275),
`activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller`
(p. 2314), `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller`
(p. 2357), `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller`
(p. 2571), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller`
(p. 2608), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller`
(p. 2641), `activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller` (p. 2670),
`activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2705), `ac-`
`tivemq::wireformat::openwire::marshal::v2::MessagePullMarshaller` (p. 2746), `ac-`
`tivemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller` (p. 2798),
`activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2928),
`activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller` (p. 3042),
`activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller` (p. 3074),
`activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller` (p. 3107),
`activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller` (p. 3200), `ac-`
`tivemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller`
(p. 3237), `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller`
(p. 3264), `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302),
`activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller` (p. 3385), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller` (p. 3429), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller` (p. 3479), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller` (p. 3698),
`activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3833),
`activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller` (p. 3873),
`activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller` (p. 4002),
`activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller` (p. 4042),
`activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller`
(p. 211), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller`
(p. 251), `activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller`
(p. 335), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller`
(p. 376), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller`
(p. 403), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller`
(p. 448), `activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller`

(p. 493), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller`
 (p. 554), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller`
 (p. 582), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller`
 (p. 611), `activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller`
 (p. 640), `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller`
 (p. 669), `activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller`
 (p. 697), `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller`
 (p. 768), `activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller` (p. 874),
`activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller` (p. 906), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller` (p. 1274),
`activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller` (p. 1306),
`activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller` (p. 1337),
`activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller` (p. 1367),
`activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller` (p. 1412),
`activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller` (p. 1441),
`activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller` (p. 1474), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller` (p. 1503), `ac-`
`tivemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1537),
`activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1600),
`activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller` (p. 1738),
`activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller` (p. 1772), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1852),
`activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller` (p. 1950),
`activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2104),
`activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller` (p. 2173),
`activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller` (p. 2198),
`activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller` (p. 2221), `ac-`
`tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller` (p. 2252),
`activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller` (p. 2279),
`activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller`
 (p. 2310), `activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller`
 (p. 2361), `activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller`
 (p. 2575), `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller`
 (p. 2612), `activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller`
 (p. 2645), `activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller` (p. 2682),
`activemq::wireformat::openwire::marshal::v3::MessageMarshaller` (p. 2700), `ac-`
`tivemq::wireformat::openwire::marshal::v3::MessagePullMarshaller` (p. 2754), `ac-`
`tivemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller` (p. 2810),
`activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2936),
`activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller` (p. 3050),
`activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller` (p. 3082),
`activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller` (p. 3119),
`activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller` (p. 3208), `ac-`
`tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller`
 (p. 3233), `activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller`
 (p. 3268), `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312),
`activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller` (p. 3401), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller` (p. 3425), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller` (p. 3491), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller` (p. 3678),
`activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3837),
`activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller` (p. 3861),
`activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller` (p. 4014),
`activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller` (p. 4054),

activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller
 (p. 219), activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller
 (p. 259), activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller
 (p. 343), activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller
 (p. 384), activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller
 (p. 411), activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller
 (p. 456), activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller
 (p. 501), activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller
 (p. 562), activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller
 (p. 590), activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller
 (p. 619), activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller
 (p. 644), activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller
 (p. 673), activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller
 (p. 701), activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller
 (p. 775), activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (p. 878),
 activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (p. 910), ac-
 tivemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (p. 1278),
 activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (p. 1310),
 activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (p. 1341),
 activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (p. 1371),
 activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1416),
 activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (p. 1445),
 activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1478), ac-
 tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1507), ac-
 tivemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1541),
 activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1604),
 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1742),
 activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (p. 1776), ac-
 tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1860),
 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1954),
 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2108),
 activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (p. 2177),
 activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (p. 2206),
 activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (p. 2229), ac-
 tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (p. 2260),
 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2283),
 activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller
 (p. 2322), activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller
 (p. 2369), activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller
 (p. 2579), activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller
 (p. 2620), activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller
 (p. 2649), activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (p. 2674),
 activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2710), ac-
 tivemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2758), ac-
 tivemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (p. 2814),
 activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2940),
 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3046),
 activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3078),
 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3103),
 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3220), ac-
 tivemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller
 (p. 3249), activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller
 (p. 3256), activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3297),
 activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3389), ac-

tivemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3433),
 tivemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3495),
 tivemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3690),
 activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (p. 3841),
 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3869),
 activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4006),
 activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4046),
 activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller
 (p. 227), activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller
 (p. 263), activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller
 (p. 347), activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller
 (p. 388), activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller
 (p. 415), activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller
 (p. 460), activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller
 (p. 505), activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller
 (p. 566), activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller
 (p. 594), activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller
 (p. 623), activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller
 (p. 652), activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller
 (p. 681), activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller
 (p. 709), activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller
 (p. 789), activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller (p. 886),
 activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller (p. 918),
 tivemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (p. 1286),
 activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (p. 1318),
 activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller (p. 1349),
 activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (p. 1379),
 activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (p. 1424),
 activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller (p. 1453),
 activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (p. 1486),
 tivemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (p. 1515),
 tivemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (p. 1549),
 activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1588),
 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1754),
 activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller (p. 1784),
 tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1856),
 activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1962),
 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2116),
 activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller (p. 2169),
 activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller (p. 2190),
 activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller (p. 2237),
 tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller (p. 2256),
 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2287),
 activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller
 (p. 2318), activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller
 (p. 2365), activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller
 (p. 2587), activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
 (p. 2616), activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
 (p. 2657), activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller (p. 2678),
 activemq::wireformat::openwire::marshal::v5::MessageMarshaller (p. 2695),
 tivemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2750),
 tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller (p. 2806),
 activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller (p. 2932),
 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3054),

activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller (p. 3086),
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3115),
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3216),
 activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
 (p. 3245),
 activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
 (p. 3276),
 activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3307),
 activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller (p. 3397),
 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3417),
 activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3487),
 activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (p. 3686),
 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller (p. 3825),
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3853),
 activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (p. 3994),
 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (p. 4058),
 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller
 (p. 231),
 activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller
 (p. 267),
 activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller
 (p. 355),
 activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller
 (p. 396),
 activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller
 (p. 423),
 activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller
 (p. 468),
 activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller
 (p. 513),
 activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller
 (p. 574),
 activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller
 (p. 602),
 activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller
 (p. 631),
 activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller
 (p. 660),
 activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller
 (p. 685),
 activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller
 (p. 713),
 activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller
 (p. 796),
 activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (p. 890),
 activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (p. 922),
 activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (p. 1290),
 activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (p. 1322),
 activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (p. 1353),
 activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (p. 1383),
 activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1428),
 activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (p. 1457),
 activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1490),
 activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1519),
 activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1553),
 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1592),
 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1750),
 activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (p. 1764),
 activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1844),
 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1942),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2096),
 activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (p. 2161),
 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (p. 2202),
 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (p. 2225),
 activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (p. 2244),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2271),
 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller
 (p. 2306),
 activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller
 (p. 2353),
 activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller
 (p. 2567),
 activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller

(p. 2628), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller (p. 2637), activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (p. 2686), activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2720), activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766), activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (p. 2802), activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (p. 2924), activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058), activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (p. 3090), activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3123), activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3204), activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller (p. 3241), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller (p. 3272), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3322), activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller (p. 3393), activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3413), activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3475), activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (p. 3694), activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller (p. 3845), activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3865), activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (p. 3998), and activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (p. 4038).

6.301.3.6 virtual void activemq::wireformat::openwire::marshal::DataStreamMarshaller::tightMarshal2 (OpenWireFormat * *format*, commands::DataStructure * *command*, decaf::io::DataOutputStream * *ds*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [pure virtual]

Tight Marshal to the given stream.

Parameters:

format - The OpenWireFormat properties
command - the object to Marshal
ds - the DataOutputStream to Marshal to
bs - boolean stream to **marshal** (p. 107) to.

Exceptions:

IOException if an error occurs.

Implemented in activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller (p. 215), activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller (p. 255), activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller (p. 339), activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller (p. 380), activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller (p. 407), activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller (p. 452), activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller (p. 497), activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller (p. 558), activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller (p. 586), activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller (p. 615), activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller (p. 648), activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller

(p. 677), `activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller`
 (p. 705), `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller`
 (p. 783), `activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller` (p. 882),
`activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 914), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1282),
`activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1314),
`activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller` (p. 1345),
`activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1375),
`activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1420),
`activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller` (p. 1449),
`activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller` (p. 1482), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller` (p. 1511), `ac-`
`tivemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1546),
`activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1609),
`activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller` (p. 1746),
`activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller` (p. 1780), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1865),
`activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller` (p. 1958),
`activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2113),
`activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller` (p. 2181),
`activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller` (p. 2210),
`activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller` (p. 2233), `ac-`
`tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller` (p. 2264),
`activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller` (p. 2291),
`activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller`
 (p. 2327), `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller`
 (p. 2373), `activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller`
 (p. 2583), `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller`
 (p. 2624), `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller`
 (p. 2653), `activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller` (p. 2690),
`activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2716), `ac-`
`tivemq::wireformat::openwire::marshal::v1::MessagePullMarshaller` (p. 2762), `ac-`
`tivemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller` (p. 2818),
`activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2945),
`activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller` (p. 3062),
`activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller` (p. 3094),
`activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller` (p. 3111),
`activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller` (p. 3212), `ac-`
`tivemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller`
 (p. 3229), `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller`
 (p. 3260), `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3318),
`activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller` (p. 3405), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller` (p. 3421), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller` (p. 3483), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller` (p. 3682),
`activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3829),
`activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller` (p. 3857),
`activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller` (p. 4010),
`activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller` (p. 4050),
`activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller`
 (p. 223), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller`
 (p. 271), `activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller`
 (p. 351), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller`
 (p. 392), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller`

(p. 419), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller`
 (p. 464), `activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller`
 (p. 509), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller`
 (p. 570), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller`
 (p. 598), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller`
 (p. 627), `activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller`
 (p. 656), `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller`
 (p. 689), `activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller`
 (p. 717), `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller`
 (p. 804), `activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller` (p. 894),
`activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller` (p. 926), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller` (p. 1294),
`activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller` (p. 1302),
`activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller` (p. 1333),
`activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller` (p. 1363),
`activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller` (p. 1408),
`activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller` (p. 1437),
`activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller` (p. 1470), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller` (p. 1499), `ac-`
`tivemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1534),
`activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1597),
`activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller` (p. 1734),
`activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller` (p. 1768), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1849),
`activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller` (p. 1946),
`activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2101),
`activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller` (p. 2165),
`activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller` (p. 2194),
`activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller` (p. 2217), `ac-`
`tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller` (p. 2248),
`activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller` (p. 2275),
`activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller`
 (p. 2315), `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller`
 (p. 2357), `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller`
 (p. 2571), `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller`
 (p. 2608), `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller`
 (p. 2641), `activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller` (p. 2670),
`activemq::wireformat::openwire::marshal::v2::MessageMarshaller` (p. 2706), `ac-`
`tivemq::wireformat::openwire::marshal::v2::MessagePullMarshaller` (p. 2746), `ac-`
`tivemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller` (p. 2798),
`activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2929),
`activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller` (p. 3042),
`activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller` (p. 3074),
`activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller` (p. 3107),
`activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller` (p. 3200), `ac-`
`tivemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller`
 (p. 3237), `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller`
 (p. 3264), `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3303),
`activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller` (p. 3385), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller` (p. 3429), `ac-`
`tivemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller` (p. 3479), `ac-`
`tivemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller` (p. 3698),
`activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3833),
`activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller` (p. 3873),

activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (p. 4002),
 activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (p. 4042),
 activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller
 (p. 211), activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller
 (p. 251), activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller
 (p. 335), activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller
 (p. 376), activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller
 (p. 403), activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller
 (p. 448), activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller
 (p. 493), activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller
 (p. 554), activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller
 (p. 582), activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller
 (p. 611), activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller
 (p. 640), activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller
 (p. 669), activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller
 (p. 697), activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller
 (p. 769), activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (p. 874),
 activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (p. 906), ac-
 tivemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (p. 1274),
 activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (p. 1306),
 activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (p. 1337),
 activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (p. 1367),
 activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1412),
 activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (p. 1441),
 activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1474), ac-
 tivemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1503), ac-
 tivemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1538),
 activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1601),
 activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1738),
 activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (p. 1772), ac-
 tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1853),
 activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1950),
 activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2105),
 activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (p. 2173),
 activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (p. 2198),
 activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (p. 2221), ac-
 tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (p. 2252),
 activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2279),
 activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller
 (p. 2311), activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller
 (p. 2361), activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller
 (p. 2575), activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller
 (p. 2612), activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller
 (p. 2645), activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (p. 2682),
 activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2701), ac-
 tivemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2754), ac-
 tivemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (p. 2810),
 activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (p. 2937),
 activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3050),
 activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (p. 3082),
 activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3119),
 activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3208), ac-
 tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller
 (p. 3233), activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller

(p. 3268), `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3313),
`activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller` (p. 3401), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller` (p. 3425), `ac-`
`tivemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller` (p. 3491), `ac-`
`tivemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller` (p. 3678),
`activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3837),
`activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller` (p. 3861),
`activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller` (p. 4014),
`activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller` (p. 4054),
`activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller`
(p. 219), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller`
(p. 259), `activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller`
(p. 343), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller`
(p. 384), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller`
(p. 411), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller`
(p. 456), `activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller`
(p. 501), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller`
(p. 562), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller`
(p. 590), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller`
(p. 619), `activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller`
(p. 644), `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller`
(p. 673), `activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller`
(p. 701), `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller`
(p. 776), `activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller` (p. 878),
`activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller` (p. 910), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller` (p. 1278),
`activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller` (p. 1310),
`activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller` (p. 1341),
`activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller` (p. 1371),
`activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller` (p. 1416),
`activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller` (p. 1445),
`activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller` (p. 1478), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller` (p. 1507), `ac-`
`tivemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1542),
`activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller` (p. 1605),
`activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller` (p. 1742),
`activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller` (p. 1776), `ac-`
`tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller` (p. 1861),
`activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller` (p. 1954),
`activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller` (p. 2109),
`activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller` (p. 2177),
`activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller` (p. 2206),
`activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller` (p. 2229), `ac-`
`tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller` (p. 2260),
`activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller` (p. 2283),
`activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller`
(p. 2323), `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller`
(p. 2369), `activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller`
(p. 2579), `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller`
(p. 2620), `activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller`
(p. 2649), `activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller` (p. 2674),
`activemq::wireformat::openwire::marshal::v4::MessageMarshaller` (p. 2711), `ac-`
`tivemq::wireformat::openwire::marshal::v4::MessagePullMarshaller` (p. 2758), `ac-`
`tivemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller` (p. 2814),

activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2941),
 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3046),
 activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3078),
 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3103),
 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3220),
 activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller
 (p. 3249),
 activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller
 (p. 3256),
 activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3298),
 activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3389),
 activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3433),
 activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3495),
 activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3690),
 activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (p. 3841),
 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3869),
 activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4006),
 activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4046),
 activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller
 (p. 227),
 activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller
 (p. 263),
 activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller
 (p. 347),
 activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller
 (p. 388),
 activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller
 (p. 415),
 activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller
 (p. 460),
 activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller
 (p. 505),
 activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller
 (p. 566),
 activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller
 (p. 594),
 activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller
 (p. 623),
 activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller
 (p. 652),
 activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller
 (p. 681),
 activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller
 (p. 709),
 activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller
 (p. 790),
 activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller (p. 886),
 activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller (p. 918),
 activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (p. 1286),
 activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (p. 1318),
 activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller (p. 1349),
 activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (p. 1379),
 activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (p. 1424),
 activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller (p. 1453),
 activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (p. 1486),
 activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (p. 1515),
 activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (p. 1550),
 activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1589),
 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1754),
 activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller (p. 1784),
 activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1857),
 activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1962),
 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2117),
 activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller (p. 2169),
 activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller (p. 2190),
 activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller (p. 2237),
 activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller (p. 2256),
 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2287),
 activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller
 (p. 2319),
 activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller

(p. 2365), activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller
 (p. 2587), activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
 (p. 2616), activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
 (p. 2657), activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller (p. 2678),
 activemq::wireformat::openwire::marshal::v5::MessageMarshaller (p. 2696), ac-
 tivemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2750), ac-
 tivemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller (p. 2806),
 activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller (p. 2933),
 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3054),
 activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller (p. 3086),
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3115),
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3216), ac-
 tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
 (p. 3245), activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
 (p. 3276), activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3308),
 activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller (p. 3397), ac-
 tivemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3417), ac-
 tivemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3487), ac-
 tivemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (p. 3686),
 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller (p. 3825),
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3853),
 activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (p. 3994),
 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (p. 4058),
 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller
 (p. 231), activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller
 (p. 267), activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller
 (p. 355), activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller
 (p. 396), activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller
 (p. 423), activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller
 (p. 468), activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller
 (p. 513), activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller
 (p. 574), activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller
 (p. 602), activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller
 (p. 631), activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller
 (p. 660), activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller
 (p. 685), activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller
 (p. 713), activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller
 (p. 797), activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (p. 890),
 activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (p. 922), ac-
 tivemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (p. 1290),
 activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (p. 1322),
 activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (p. 1353),
 activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (p. 1383),
 activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1428),
 activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (p. 1457),
 activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1490), ac-
 tivemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1519), ac-
 tivemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1554),
 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1593),
 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1750),
 activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (p. 1764), ac-
 tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1845),
 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1942),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2097),

activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (p. 2161),
 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (p. 2202),
 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (p. 2225),
 activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (p. 2244),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2271),
 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller
 (p. 2307), activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller
 (p. 2353), activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller
 (p. 2567), activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller
 (p. 2628), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
 (p. 2637), activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (p. 2686),
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2721),
 activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2766),
 activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (p. 2802),
 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (p. 2925),
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3058),
 activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (p. 3090),
 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3123),
 activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3204),
 activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller
 (p. 3241), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller
 (p. 3272), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3323),
 activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller (p. 3393),
 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3413),
 activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3475),
 activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (p. 3694),
 activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller (p. 3845),
 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3865),
 activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (p. 3998), and
 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (p. 4038).

6.301.3.7 virtual void ac-
tivemq::wireformat::openwire::marshal::DataStreamMarshaller::tightUnmarshal
(OpenWireFormat * *format*, commands::DataStructure * *command*,
decaf::io::DataInputStream * *dis*, utils::BooleanStream * *bs*) throw (
decaf::io::IOException) [pure virtual]

Tight Un-marhsal to the given stream.

Parameters:

format - The OpenWireFormat properties
command - the object to Un-Marshal
dis - the DataInputStream to Un-Marshal from
bs - boolean stream to unmarshal from.

Exceptions:

IOException if an error occurs.

Implemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller`
 (p. 216), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller`
 (p. 256), `activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller`

(p. 340), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller`
 (p. 381), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller`
 (p. 408), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller`
 (p. 453), `activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller`
 (p. 498), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller`
 (p. 559), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller`
 (p. 587), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller`
 (p. 616), `activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller`
 (p. 649), `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller`
 (p. 678), `activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller`
 (p. 706), `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller`
 (p. 784), `activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller` (p. 883),
`activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller` (p. 915), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller` (p. 1283),
`activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller` (p. 1315),
`activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller` (p. 1346),
`activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller` (p. 1376),
`activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller` (p. 1421),
`activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller` (p. 1450),
`activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller` (p. 1483), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller` (p. 1512), `ac-`
`tivemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1546),
`activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1609),
`activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller` (p. 1747),
`activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller` (p. 1781), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1865),
`activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller` (p. 1959),
`activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2113),
`activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller` (p. 2182),
`activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller` (p. 2211),
`activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller` (p. 2234), `ac-`
`tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller` (p. 2265),
`activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller` (p. 2292),
`activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller`
 (p. 2327), `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller`
 (p. 2374), `activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller`
 (p. 2584), `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller`
 (p. 2625), `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller`
 (p. 2654), `activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller` (p. 2691),
`activemq::wireformat::openwire::marshal::v1::MessageMarshaller` (p. 2716), `ac-`
`tivemq::wireformat::openwire::marshal::v1::MessagePullMarshaller` (p. 2763), `ac-`
`tivemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller` (p. 2819),
`activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2945),
`activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller` (p. 3063),
`activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller` (p. 3095),
`activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller` (p. 3112),
`activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller` (p. 3213), `ac-`
`tivemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller`
 (p. 3230), `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller`
 (p. 3261), `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3319),
`activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller` (p. 3406), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller` (p. 3422), `ac-`
`tivemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller` (p. 3484), `ac-`
`tivemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller` (p. 3683),

activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller (p. 3830),
 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller (p. 3858),
 activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller (p. 4011),
 activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller (p. 4051),
 activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller
 (p. 224), activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller
 (p. 272), activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller
 (p. 352), activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller
 (p. 393), activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller
 (p. 420), activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller
 (p. 465), activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller
 (p. 510), activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller
 (p. 571), activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller
 (p. 599), activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller
 (p. 628), activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller
 (p. 657), activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller
 (p. 690), activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller
 (p. 718), activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller
 (p. 805), activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller (p. 895),
 activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller (p. 927), ac-
 tivemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller (p. 1295),
 activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller (p. 1303),
 activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller (p. 1334),
 activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller (p. 1364),
 activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller (p. 1409),
 activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller (p. 1438),
 activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller (p. 1471), ac-
 tivemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller (p. 1500), ac-
 tivemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller (p. 1534),
 activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller (p. 1597),
 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller (p. 1735),
 activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller (p. 1769), ac-
 tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller (p. 1849),
 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller (p. 1947),
 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller (p. 2101),
 activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller (p. 2166),
 activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller (p. 2195),
 activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller (p. 2218), ac-
 tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller (p. 2249),
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller (p. 2276),
 activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller
 (p. 2315), activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller
 (p. 2358), activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller
 (p. 2572), activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller
 (p. 2609), activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
 (p. 2642), activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller (p. 2671),
 activemq::wireformat::openwire::marshal::v2::MessageMarshaller (p. 2706), ac-
 tivemq::wireformat::openwire::marshal::v2::MessagePullMarshaller (p. 2747), ac-
 tivemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller (p. 2799),
 activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller (p. 2929),
 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller (p. 3043),
 activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller (p. 3075),
 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller (p. 3108),
 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller (p. 3201), ac-

tivemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller (p. 3238),
activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller (p. 3265),
activemq::wireformat::openwire::marshal::v2::ResponseMarshaller (p. 3304),
activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller (p. 3386),
activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller (p. 3430),
activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller (p. 3480),
activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller (p. 3699),
activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller (p. 3834),
activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller (p. 3874),
activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller (p. 4003),
activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller (p. 4043),
activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller (p. 212),
activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller (p. 252),
activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller (p. 336),
activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller (p. 377),
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller (p. 404),
activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller (p. 449),
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller (p. 494),
activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller (p. 555),
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller (p. 583),
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller (p. 612),
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller (p. 641),
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller (p. 670),
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller (p. 698),
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller (p. 770),
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller (p. 875),
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller (p. 907),
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller (p. 1275),
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller (p. 1307),
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller (p. 1338),
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller (p. 1368),
activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller (p. 1413),
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller (p. 1442),
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller (p. 1475),
activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller (p. 1504),
activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller (p. 1538),
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller (p. 1601),
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller (p. 1739),
activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller (p. 1773),
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller (p. 1853),
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller (p. 1951),
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller (p. 2105),
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller (p. 2174),
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller (p. 2199),
activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller (p. 2222),
activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller (p. 2253),
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller (p. 2280),
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller (p. 2311),
activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller (p. 2362),
activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller (p. 2576),
activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller (p. 2613),
activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller (p. 2646),
activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller (p. 2683),
activemq::wireformat::openwire::marshal::v3::MessageMarshaller (p. 2701), ac-

activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller (p. 2755),
 activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller (p. 2811),
 activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller (p. 2937),
 activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller (p. 3051),
 activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller (p. 3083),
 activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller (p. 3120),
 activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller (p. 3209),
 activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller
 (p. 3234),
 activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller
 (p. 3269),
 activemq::wireformat::openwire::marshal::v3::ResponseMarshaller (p. 3314),
 activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller (p. 3402),
 activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller (p. 3426),
 activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller (p. 3492),
 activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller (p. 3679),
 activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller (p. 3838),
 activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller (p. 3862),
 activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller (p. 4015),
 activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller (p. 4055),
 activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller
 (p. 220),
 activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller
 (p. 260),
 activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller
 (p. 344),
 activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller
 (p. 385),
 activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller
 (p. 412),
 activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller
 (p. 457),
 activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller
 (p. 502),
 activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller
 (p. 563),
 activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller
 (p. 591),
 activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller
 (p. 620),
 activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller
 (p. 645),
 activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller
 (p. 674),
 activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller
 (p. 702),
 activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller
 (p. 777),
 activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller (p. 879),
 activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller (p. 911),
 activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller (p. 1279),
 activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller (p. 1311),
 activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller (p. 1342),
 activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller (p. 1372),
 activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller (p. 1417),
 activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller (p. 1446),
 activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller (p. 1479),
 activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller (p. 1508),
 activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller (p. 1542),
 activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller (p. 1605),
 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller (p. 1743),
 activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller (p. 1777),
 activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller (p. 1861),
 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller (p. 1955),
 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller (p. 2109),
 activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller (p. 2178),
 activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller (p. 2207),
 activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller (p. 2230),
 activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller (p. 2261),
 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller (p. 2284),

activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller (p. 2323),
activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller (p. 2370),
activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller (p. 2580),
activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller (p. 2621),
activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller (p. 2650),
activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller (p. 2675),
activemq::wireformat::openwire::marshal::v4::MessageMarshaller (p. 2711),
activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller (p. 2759),
activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller (p. 2815),
activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller (p. 2941),
activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller (p. 3047),
activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller (p. 3079),
activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller (p. 3104),
activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller (p. 3221),
activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller (p. 3250),
activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller (p. 3257),
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller (p. 3299),
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller (p. 3390),
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller (p. 3434),
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller (p. 3496),
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller (p. 3691),
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller (p. 3842),
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller (p. 3870),
activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller (p. 4007),
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller (p. 4047),
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller (p. 228),
activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller (p. 264),
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller (p. 348),
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller (p. 389),
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller (p. 416),
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller (p. 461),
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller (p. 506),
activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller (p. 567),
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller (p. 595),
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller (p. 624),
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller (p. 653),
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller (p. 682),
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller (p. 710),
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller (p. 791),
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller (p. 887),
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller (p. 919),
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller (p. 1287),
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller (p. 1319),
activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller (p. 1350),
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller (p. 1380),
activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller (p. 1425),
activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller (p. 1454),
activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller (p. 1487),
activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller (p. 1516),
activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller (p. 1550),
activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller (p. 1589),
activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller (p. 1755),
activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller (p. 1785),
activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller (p. 1857),

activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller (p. 1963),
 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller (p. 2117),
 activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller (p. 2170),
 activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller (p. 2191),
 activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller (p. 2238),
 activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller (p. 2257),
 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller (p. 2288),
 activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller
 (p. 2319), activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller
 (p. 2366), activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller
 (p. 2588), activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
 (p. 2617), activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
 (p. 2658), activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller (p. 2679),
 activemq::wireformat::openwire::marshal::v5::MessageMarshaller (p. 2696),
 activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller (p. 2751),
 activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller (p. 2807),
 activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller (p. 2933),
 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller (p. 3055),
 activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller (p. 3087),
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller (p. 3116),
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller (p. 3217),
 activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller
 (p. 3246), activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
 (p. 3277), activemq::wireformat::openwire::marshal::v5::ResponseMarshaller (p. 3309),
 activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller (p. 3398),
 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller (p. 3418),
 activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller (p. 3488),
 activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller (p. 3687),
 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller (p. 3826),
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller (p. 3854),
 activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller (p. 3995),
 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller (p. 4059),
 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller
 (p. 232), activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller
 (p. 268), activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller
 (p. 356), activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller
 (p. 397), activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller
 (p. 424), activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller
 (p. 469), activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller
 (p. 514), activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller
 (p. 575), activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller
 (p. 603), activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller
 (p. 632), activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller
 (p. 661), activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller
 (p. 686), activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller
 (p. 714), activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller
 (p. 798), activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller (p. 891),
 activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller (p. 923),
 activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller (p. 1291),
 activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller (p. 1323),
 activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller (p. 1354),
 activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller (p. 1384),
 activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller (p. 1429),
 activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller (p. 1458),

activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller (p. 1491),
 activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller (p. 1520),
 activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller (p. 1554),
 activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller (p. 1593),
 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller (p. 1751),
 activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller (p. 1765),
 activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller (p. 1845),
 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller (p. 1943),
 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller (p. 2097),
 activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller (p. 2162),
 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller (p. 2203),
 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller (p. 2226),
 activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller (p. 2245),
 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller (p. 2272),
 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller
 (p. 2307), activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller
 (p. 2354), activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller
 (p. 2568), activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller
 (p. 2629), activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
 (p. 2638), activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller (p. 2687),
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller (p. 2721),
 activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller (p. 2767),
 activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller (p. 2803),
 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller (p. 2925),
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller (p. 3059),
 activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller (p. 3091),
 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller (p. 3124),
 activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller (p. 3205),
 activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller
 (p. 3242), activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller
 (p. 3273), activemq::wireformat::openwire::marshal::v6::ResponseMarshaller (p. 3324),
 activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller (p. 3394),
 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller (p. 3414),
 activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller (p. 3476),
 activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller (p. 3695),
 activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller (p. 3846),
 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller (p. 3866),
 activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller (p. 3999), and
 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller (p. 4039).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/DataStreamMarshaller.h`

6.302 activemq::commands::DataStructure Class Reference

#include <src/main/activemq/commands/DataStructure.h> Inheritance diagram for activemq::commands::DataStructure:

Public Member Functions

- virtual **~DataStructure** ()
- virtual unsigned char **getDataStructureType** () const =0
*Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.*
- virtual **DataStructure** * **cloneDataStructure** () const =0
Clone this obbject and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)=0
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const =0
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const =0
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

6.302.1 Constructor & Destructor Documentation

6.302.1.1 virtual activemq::commands::DataStructure::~~DataStructure ()
 [inline, virtual]

6.302.2 Member Function Documentation

6.302.2.1 virtual **DataStructure*** **activemq::commands::DataStructure::cloneDataStructure** ()
 const [pure virtual]

Clone this obbject and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implemented in **activemq::commands::ActiveMQBlobMessage** (p. 205), **activemq::commands::ActiveMQBytesMessage** (p. 236), **activemq::commands::ActiveMQDestination** (p. 324), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage**

(p. 444), `activemq::commands::ActiveMQQueue` (p. 484), `ac-`
`tivemq::commands::ActiveMQStreamMessage` (p. 540), `ac-`
`tivemq::commands::ActiveMQTempDestination` (p. 577), `ac-`
`tivemq::commands::ActiveMQTempQueue` (p. 605), `ac-`
`tivemq::commands::ActiveMQTempTopic` (p. 634), `activemq::commands::ActiveMQTextMessage`
(p. 664), `activemq::commands::ActiveMQTopic` (p. 692), `ac-`
`tivemq::commands::BooleanExpression` (p. 855), `activemq::commands::BrokerError`
(p. 864), `activemq::commands::BrokerId` (p. 870), `activemq::commands::BrokerInfo`
(p. 897), `activemq::commands::ConnectionControl` (p. 1268), `ac-`
`tivemq::commands::ConnectionError` (p. 1297), `activemq::commands::ConnectionId`
(p. 1328), `activemq::commands::ConnectionInfo` (p. 1356), `ac-`
`tivemq::commands::ConsumerControl` (p. 1402), `activemq::commands::ConsumerId`
(p. 1431), `activemq::commands::ConsumerInfo` (p. 1461), `ac-`
`tivemq::commands::ControlCommand` (p. 1494), `activemq::commands::DataArrayResponse`
(p. 1529), `activemq::commands::DataResponse` (p. 1584), `ac-`
`tivemq::commands::DestinationInfo` (p. 1728), `activemq::commands::DiscoveryEvent`
(p. 1759), `activemq::commands::ExceptionResponse` (p. 1840), `ac-`
`tivemq::commands::FlushCommand` (p. 1938), `activemq::commands::IntegerResponse`
(p. 2092), `activemq::commands::JournalQueueAck` (p. 2157), `ac-`
`tivemq::commands::JournalTopicAck` (p. 2184), `activemq::commands::JournalTrace`
(p. 2213), `activemq::commands::JournalTransaction` (p. 2240), `ac-`
`tivemq::commands::KeepAliveInfo` (p. 2267), `activemq::commands::LastPartialCommand`
(p. 2301), `activemq::commands::LocalTransactionId` (p. 2348), `ac-`
`tivemq::commands::Message` (p. 2520), `activemq::commands::MessageAck`
(p. 2560), `activemq::commands::MessageDispatch` (p. 2595), `ac-`
`tivemq::commands::MessageDispatchNotification` (p. 2631), `ac-`
`tivemq::commands::MessageId` (p. 2664), `activemq::commands::MessagePull`
(p. 2740), `activemq::commands::NetworkBridgeFilter` (p. 2794), `ac-`
`tivemq::commands::PartialCommand` (p. 2919), `activemq::commands::ProducerAck`
(p. 3037), `activemq::commands::ProducerId` (p. 3068), `ac-`
`tivemq::commands::ProducerInfo` (p. 3097), `activemq::commands::RemoveInfo`
(p. 3195), `activemq::commands::RemoveSubscriptionInfo` (p. 3223), `ac-`
`tivemq::commands::ReplayCommand` (p. 3252), `activemq::commands::Response`
(p. 3286), `activemq::commands::SessionId` (p. 3380), `ac-`
`tivemq::commands::SessionInfo` (p. 3408), `activemq::commands::ShutdownInfo`
(p. 3471), `activemq::commands::SubscriptionInfo` (p. 3672), `ac-`
`tivemq::commands::TransactionId` (p. 3820), `activemq::commands::TransactionInfo`
(p. 3848), `activemq::commands::WireFormatInfo` (p. 3985), and `ac-`
`tivemq::commands::XATransactionId` (p. 4032).

6.302.2.2 virtual void `activemq::commands::DataStructure::copyDataStructure` (const `DataStructure * src`) [pure virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

6.302.2.3 virtual bool activemq::commands::DataStructure::equals (const DataStructure * *value*) const [pure virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.302.2.4 virtual unsigned char activemq::commands::DataStructure::getDataStructureType () const [pure virtual]

Get the **DataStructure** (p. 1660) Type as defined in CommandTypes.h.

Returns:

The type of the data structure

Implemented in **activemq::commands::ActiveMQBlobMessage** (p. 206), **activemq::commands::ActiveMQBytesMessage** (p. 238), **activemq::commands::ActiveMQDestination** (p. 326), **activemq::commands::ActiveMQMapMessage** (p. 366), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage** (p. 445), **activemq::commands::ActiveMQQueue** (p. 485), **activemq::commands::ActiveMQStreamMessage** (p. 541), **activemq::commands::ActiveMQTempDestination** (p. 578), **activemq::commands::ActiveMQTempQueue** (p. 607), **activemq::commands::ActiveMQTempTopic** (p. 636), **activemq::commands::ActiveMQTextMessage** (p. 664), **activemq::commands::ActiveMQTopic** (p. 693), **activemq::commands::BrokerError** (p. 865), **activemq::commands::BrokerId** (p. 871), **activemq::commands::BrokerInfo** (p. 899), **activemq::commands::ConnectionControl** (p. 1269), **activemq::commands::ConnectionError** (p. 1298), **activemq::commands::ConnectionId** (p. 1329), **activemq::commands::ConnectionInfo** (p. 1357), **activemq::commands::ConsumerControl** (p. 1403), **activemq::commands::ConsumerId** (p. 1432), **activemq::commands::ConsumerInfo** (p. 1462), **activemq::commands::ControlCommand** (p. 1495), **activemq::commands::DataArrayResponse** (p. 1530), **activemq::commands::DataResponse** (p. 1585), **activemq::commands::DestinationInfo** (p. 1729), **activemq::commands::DiscoveryEvent** (p. 1760), **activemq::commands::ExceptionResponse** (p. 1840), **activemq::commands::FlushCommand** (p. 1938), **activemq::commands::IntegerResponse** (p. 2092), **activemq::commands::JournalQueueAck** (p. 2157), **activemq::commands::JournalTopicAck** (p. 2185), **activemq::commands::JournalTrace** (p. 2213), **activemq::commands::JournalTransaction** (p. 2240), **activemq::commands::KeepAliveInfo** (p. 2267), **activemq::commands::LastPartialCommand** (p. 2302), **activemq::commands::LocalTransactionId** (p. 2349), **activemq::commands::Message** (p. 2523), **activemq::commands::MessageAck** (p. 2561), **activemq::commands::MessageDispatch** (p. 2596), **activemq::commands::MessageDispatchNotification** (p. 2632), **activemq::commands::MessageId** (p. 2665), **activemq::commands::MessagePull**

(p. 2741), **activemq::commands::NetworkBridgeFilter** (p. 2794), **activemq::commands::PartialCommand** (p. 2920), **activemq::commands::ProducerAck** (p. 3037), **activemq::commands::ProducerId** (p. 3069), **activemq::commands::ProducerInfo** (p. 3098), **activemq::commands::RemoveInfo** (p. 3195), **activemq::commands::RemoveSubscriptionInfo** (p. 3224), **activemq::commands::ReplayCommand** (p. 3252), **activemq::commands::Response** (p. 3287), **activemq::commands::SessionId** (p. 3381), **activemq::commands::SessionInfo** (p. 3409), **activemq::commands::ShutdownInfo** (p. 3471), **activemq::commands::SubscriptionInfo** (p. 3673), **activemq::commands::TransactionId** (p. 3821), **activemq::commands::TransactionInfo** (p. 3849), **activemq::commands::WireFormatInfo** (p. 3986), and **activemq::commands::XATransactionId** (p. 4033).

6.302.2.5 virtual std::string activemq::commands::DataStructure::toString () const [pure virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Implemented in **activemq::commands::ActiveMQBlobMessage** (p. 208), **activemq::commands::ActiveMQBytesMessage** (p. 244), **activemq::commands::ActiveMQDestination** (p. 330), **activemq::commands::ActiveMQMapMessage** (p. 372), **activemq::commands::ActiveMQMessage** (p. 400), **activemq::commands::ActiveMQObjectMessage** (p. 445), **activemq::commands::ActiveMQQueue** (p. 486), **activemq::commands::ActiveMQStreamMessage** (p. 547), **activemq::commands::ActiveMQTempDestination** (p. 578), **activemq::commands::ActiveMQTempQueue** (p. 607), **activemq::commands::ActiveMQTempTopic** (p. 636), **activemq::commands::ActiveMQTextMessage** (p. 666), **activemq::commands::ActiveMQTopic** (p. 694), **activemq::commands::BaseCommand** (p. 763), **activemq::commands::BaseDataStructure** (p. 833), **activemq::commands::BooleanExpression** (p. 856), **activemq::commands::BrokerId** (p. 871), **activemq::commands::BrokerInfo** (p. 901), **activemq::commands::Command** (p. 1198), **activemq::commands::ConnectionControl** (p. 1270), **activemq::commands::ConnectionError** (p. 1298), **activemq::commands::ConnectionId** (p. 1329), **activemq::commands::ConnectionInfo** (p. 1359), **activemq::commands::ConsumerControl** (p. 1404), **activemq::commands::ConsumerId** (p. 1433), **activemq::commands::ConsumerInfo** (p. 1464), **activemq::commands::ControlCommand** (p. 1495), **activemq::commands::DataArrayResponse** (p. 1530), **activemq::commands::DataResponse** (p. 1585), **activemq::commands::DestinationInfo** (p. 1730), **activemq::commands::DiscoveryEvent** (p. 1760), **activemq::commands::ExceptionResponse** (p. 1841), **activemq::commands::FlushCommand** (p. 1939), **activemq::commands::IntegerResponse** (p. 2093), **activemq::commands::JournalQueueAck** (p. 2158), **activemq::commands::JournalTopicAck** (p. 2186), **activemq::commands::JournalTrace** (p. 2214), **activemq::commands::JournalTransaction** (p. 2241), **activemq::commands::KeepAliveInfo** (p. 2268), **activemq::commands::LastPartialCommand** (p. 2302), **activemq::commands::LocalTransactionId** (p. 2350), **activemq::commands::Message** (p. 2530), **activemq::commands::MessageAck**

(p. 2563), `activemq::commands::MessageDispatch` (p. 2597), `activemq::commands::MessageDispatchNotification` (p. 2633), `activemq::commands::MessageId` (p. 2666), `activemq::commands::MessagePull` (p. 2742), `activemq::commands::NetworkBridgeFilter` (p. 2795), `activemq::commands::PartialCommand` (p. 2920), `activemq::commands::ProducerAck` (p. 3038), `activemq::commands::ProducerId` (p. 3070), `activemq::commands::ProducerInfo` (p. 3099), `activemq::commands::RemoveInfo` (p. 3196), `activemq::commands::RemoveSubscriptionInfo` (p. 3225), `activemq::commands::ReplayCommand` (p. 3253), `activemq::commands::Response` (p. 3287), `activemq::commands::SessionId` (p. 3382), `activemq::commands::SessionInfo` (p. 3409), `activemq::commands::ShutdownInfo` (p. 3472), `activemq::commands::SubscriptionInfo` (p. 3674), `activemq::commands::TransactionId` (p. 3821), `activemq::commands::TransactionInfo` (p. 3849), `activemq::commands::WireFormatInfo` (p. 3991), and `activemq::commands::XATransactionId` (p. 4034).

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/DataStructure.h`

6.303 decaf::util::Date Class Reference

Wrapper class around a time value in milliseconds.

#include <src/main/decaf/util/Date.h> Inheritance diagram for decaf::util::Date:

Public Member Functions

- **Date** ()
Default constructor - sets time to the current System time, rounded to the nearest millisecond.
- **Date** (long long milliseconds)
Constructs the date with a given time value.
- **Date** (const **Date** &source)
Copy constructor.
- **Date** & **operator=** (const **Date** &value)
*Assigns the value of one **Date** (p. 1665) object to another.*
- virtual ~**Date** ()
- long long **getTime** () const
Gets the underlying time.
- void **setTime** (long long milliseconds)
Sets the underlying time.
- bool **after** (const **Date** &when) const
Determines whether or not this date falls after the specified time.
- bool **before** (const **Date** &when) const
Determines whether or not this date falls before the specified time.
- std::string **toString** () const
*Converts this **Date** (p. 1665) object to a String of the form:.*
- virtual int **compareTo** (const **Date** &value) const
Compares this Data object to the one given.
- virtual bool **equals** (const **Date** &value) const
- virtual bool **operator==** (const **Date** &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Date** &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.

6.303.1 Detailed Description

Wrapper class around a time value in milliseconds. This class is comparable to Java's `java.util.Date` class.

Since:

1.0

6.303.2 Constructor & Destructor Documentation

6.303.2.1 `decaf::util::Date::Date ()`

Default constructor - sets time to the current System time, rounded to the nearest millisecond.

6.303.2.2 `decaf::util::Date::Date (long long milliseconds)`

Constructs the date with a given time value.

Parameters:

milliseconds The time in milliseconds;

6.303.2.3 `decaf::util::Date::Date (const Date & source)`

Copy constructor.

Parameters:

source The **Date** (p. 1665) instance to copy into this one.

6.303.2.4 `virtual decaf::util::Date::~~Date ()` [virtual]

6.303.3 Member Function Documentation

6.303.3.1 `bool decaf::util::Date::after (const Date & when) const`

Determines whether or not this date falls after the specified time.

Parameters:

when The date to compare

Returns:

true if this date falls after when.

6.303.3.2 `bool decaf::util::Date::before (const Date & when) const`

Determines whether or not this date falls before the specified time.

Parameters:

when The date to compare

Returns:

true if this date falls before when.

6.303.3.3 virtual int decaf::util::Date::compareTo (const Date & *value*) const
[virtual]

Compares this Date object to the one given.

Parameters:

value The **Date** (p. 1665) value to compare to this one.

Returns:

zero if the **Date** (p. 1665) values are equal, a value less than zero if this Date value is earlier than argument value, and a value greater than zero if this **Date** (p. 1665) object is later than the argument **Date** (p. 1665) value.

6.303.3.4 virtual bool decaf::util::Date::equals (const Date & *value*) const
[virtual]**Returns:**

true if this value is considered equal to the passed value.

6.303.3.5 long long decaf::util::Date::getTime () const

Gets the underlying time.

Returns:

The underlying time value in milliseconds.

6.303.3.6 virtual bool decaf::util::Date::operator< (const Date & *value*) const
[virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.303.3.7 Date& decaf::util::Date::operator= (const Date & *value*)

Assigns the value of one **Date** (p. 1665) object to another.

Parameters:

value The value to be copied into this **Date** (p. 1665) object.

Returns:

reference to this object with the newly assigned value.

6.303.3.8 virtual bool decaf::util::Date::operator== (const Date & *value*) const
[virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.303.3.9 void decaf::util::Date::setTime (long long *milliseconds*)

Sets the underlying time.

Parameters:

milliseconds The underlying time value in milliseconds.

6.303.3.10 std::string decaf::util::Date::toString () const

Converts this **Date** (p. 1665) object to a String of the form: . dow mon dd hh:mm:ss zzz yyyy where:

- dow is the day of the week (Sun, Mon, Tue, Wed, Thu, Fri, Sat).
- mon is the month (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, Dec).
- dd is the day of the month (01 through 31), as two decimal digits.
- hh is the hour of the day (00 through 23), as two decimal digits.
- mm is the minute within the hour (00 through 59), as two decimal digits.
- ss is the second within the minute (00 through 61, as two decimal digits.
- zzz is the time zone (and may reflect daylight saving time). Standard time zone abbreviations include those recognized by the method parse. If time zone information is not available, then zzz is empty - that is, it consists of no characters at all.

- yyyy is the year, as four decimal digits.

Returns:

the String representation of the **Date** (p. 1665) object.

The documentation for this class was generated from the following file:

- src/main/decaf/util/**Date.h**

6.304 decaf::internal::DecafRuntime Class Reference

Handles APR initialization and termination.

#include <src/main/decaf/internal/DecafRuntime.h> Inheritance diagram for decaf::internal::DecafRuntime:

Public Member Functions

- **DecafRuntime ()**
Initializes the APR Runtime for a library.
- virtual **~DecafRuntime ()**
Terminates the APR Runtime for a library.
- apr_pool_t * **getGlobalPool () const**
Grants access to the Global APR Pool instance that should be used when creating new threads.

6.304.1 Detailed Description

Handles APR initialization and termination.

6.304.2 Constructor & Destructor Documentation

6.304.2.1 decaf::internal::DecafRuntime::DecafRuntime ()

Initializes the APR Runtime for a library.

6.304.2.2 virtual decaf::internal::DecafRuntime::~~DecafRuntime () [virtual]

Terminates the APR Runtime for a library.

6.304.3 Member Function Documentation

6.304.3.1 apr_pool_t* decaf::internal::DecafRuntime::getGlobalPool () const

Grants access to the Global APR Pool instance that should be used when creating new threads.

The documentation for this class was generated from the following file:

- src/main/decaf/internal/**DecafRuntime.h**

6.305 activemq::threads::DedicatedTaskRunner Class Reference

#include <src/main/activemq/threads/DedicatedTaskRunner.h> Inheritance diagram for activemq::threads::DedicatedTaskRunner:

Public Member Functions

- **DedicatedTaskRunner** (**Task** *task)
- virtual **~DedicatedTaskRunner** ()
- virtual void **shutdown** (unsigned int timeout)

Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.

- virtual void **shutdown** ()

Shutdown once the task has finished and the TaskRunner's thread has exited.

- virtual void **wakeup** ()

*Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.*

Protected Member Functions

- virtual void **run** ()

Run method - called by the Thread class in the context of the thread.

6.305.1 Constructor & Destructor Documentation

6.305.1.1 **activemq::threads::DedicatedTaskRunner::DedicatedTaskRunner** (**Task** *task)

6.305.1.2 **virtual activemq::threads::DedicatedTaskRunner::~~DedicatedTaskRunner** () [virtual]

6.305.2 Member Function Documentation

6.305.2.1 **virtual void activemq::threads::DedicatedTaskRunner::run** () [protected, virtual]

Run method - called by the Thread class in the context of the thread.

Implements **decaf::lang::Runnable** (p. 3325).

6.305.2.2 virtual void activemq::threads::DedicatedTaskRunner::shutdown ()
[virtual]

Shutdown once the task has finished and the TaskRunner's thread has exited.

Implements **activemq::threads::TaskRunner** (p. 3736).

6.305.2.3 virtual void activemq::threads::DedicatedTaskRunner::shutdown
(unsigned int *timeout*) [virtual]

Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.

Parameters:

timeout - Time in Milliseconds to wait for the task to stop.

Implements **activemq::threads::TaskRunner** (p. 3736).

6.305.2.4 virtual void activemq::threads::DedicatedTaskRunner::wakeup ()
[virtual]

Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.

Implements **activemq::threads::TaskRunner** (p. 3737).

The documentation for this class was generated from the following file:

- src/main/activemq/threads/**DedicatedTaskRunner.h**

6.306 activemq::core::policies::DefaultPrefetchPolicy Class Reference

#include <src/main/activemq/core/policies/DefaultPrefetchPolicy.h> Inheritance diagram for activemq::core::policies::DefaultPrefetchPolicy:

Public Member Functions

- **DefaultPrefetchPolicy** ()
- virtual **~DefaultPrefetchPolicy** ()
- virtual void **setDurableTopicPrefetch** (int value)
Sets the amount of prefetched messages for a Durable Topic.
- virtual int **getDurableTopicPrefetch** () const
Gets the amount of messages to prefetch for a Durable Topic.
- virtual void **setQueuePrefetch** (int value)
Sets the amount of prefetched messages for a Queue.
- virtual int **getQueuePrefetch** () const
Gets the amount of messages to prefetch for a Queue.
- virtual void **setQueueBrowserPrefetch** (int value)
Sets the amount of prefetched messages for a Queue Browser.
- virtual int **getQueueBrowserPrefetch** () const
Gets the amount of messages to prefetch for a Queue Browser.
- virtual void **setTopicPrefetch** (int value)
Sets the amount of prefetched messages for a Topic.
- virtual int **getTopicPrefetch** () const
Gets the amount of messages to prefetch for a Topic.
- virtual int **getMaxPrefetchLimit** (int value) const
Given a requested value for a new prefetch limit, compare it against some max prefetch value and return either the requested value or the maximum allowable value for prefetch.
- virtual **PrefetchPolicy** * **clone** () const
Clone the Policy and return a new pointer to that clone.

Static Public Attributes

- static int **MAX_PREFETCH_SIZE**
- static int **DEFAULT_DURABLE_TOPIC_PREFETCH**
- static int **DEFAULT_QUEUE_PREFETCH**
- static int **DEFAULT_QUEUE_BROWSER_PREFETCH**
- static int **DEFAULT_TOPIC_PREFETCH**

6.306.1 Constructor & Destructor Documentation

6.306.1.1 `activemq::core::policies::DefaultPrefetchPolicy::DefaultPrefetchPolicy ()`

6.306.1.2 `virtual
activemq::core::policies::DefaultPrefetchPolicy::~~DefaultPrefetchPolicy
() [virtual]`

6.306.2 Member Function Documentation

6.306.2.1 `virtual PrefetchPolicy* ac-
tivemq::core::policies::DefaultPrefetchPolicy::clone ()
const [virtual]`

Clone the Policy and return a new pointer to that clone.

Returns:

pointer to a new **PrefetchPolicy** (p. 2976) instance that is a clone of this one.

Implements `activemq::core::PrefetchPolicy` (p. 2977).

6.306.2.2 `virtual int ac-
tivemq::core::policies::DefaultPrefetchPolicy::getDurableTopicPrefetch ()
const [inline, virtual]`

Gets the amount of messages to prefetch for a Durable Topic.

Returns:

value of the number of messages to prefetch.

Implements `activemq::core::PrefetchPolicy` (p. 2978).

6.306.2.3 `virtual int ac-
tivemq::core::policies::DefaultPrefetchPolicy::getMaxPrefetchLimit (int
value) const [inline, virtual]`

Given a requested value for a new prefetch limit, compare it against some max prefetch value and return either the requested value or the maximum allowable value for prefetch.

Returns:

the allowable value for a prefetch limit, either requested or the max.

Implements `activemq::core::PrefetchPolicy` (p. 2978).

6.306.2.4 `virtual int ac-
tivemq::core::policies::DefaultPrefetchPolicy::getQueueBrowserPrefetch
() const [inline, virtual]`

Gets the amount of messages to prefetch for a Queue Browser.

Returns:

value of the number of messages to prefetch.

Implements **activemq::core::PrefetchPolicy** (p. 2978).

6.306.2.5 `virtual int activemq::core::policies::DefaultPrefetchPolicy::getQueuePrefetch () const [inline, virtual]`

Gets the amount of messages to prefetch for a Queue.

Returns:

value of the number of messages to prefetch.

Implements **activemq::core::PrefetchPolicy** (p. 2978).

6.306.2.6 `virtual int activemq::core::policies::DefaultPrefetchPolicy::getTopicPrefetch () const [inline, virtual]`

Gets the amount of messages to prefetch for a Topic.

Returns:

value of the number of messages to prefetch.

Implements **activemq::core::PrefetchPolicy** (p. 2978).

6.306.2.7 `virtual void activemq::core::policies::DefaultPrefetchPolicy::setDurableTopicPrefetch (int value) [inline, virtual]`

Sets the amount of prefetched messages for a Durable Topic.

Parameters:

value The number of messages to prefetch.

Implements **activemq::core::PrefetchPolicy** (p. 2979).

6.306.2.8 `virtual void activemq::core::policies::DefaultPrefetchPolicy::setQueueBrowserPrefetch (int value) [inline, virtual]`

Sets the amount of prefetched messages for a Queue Browser.

Parameters:

value The number of messages to prefetch.

Implements **activemq::core::PrefetchPolicy** (p. 2979).

6.306.2.9 `virtual void activemq::core::policies::DefaultPrefetchPolicy::setQueuePrefetch (int value)` [inline, virtual]

Sets the amount of prefetched messages for a Queue.

Parameters:

value The number of messages to prefetch.

Implements `activemq::core::PrefetchPolicy` (p. 2979).

6.306.2.10 `virtual void activemq::core::policies::DefaultPrefetchPolicy::setTopicPrefetch (int value)` [inline, virtual]

Sets the amount of prefetched messages for a Topic.

Parameters:

value The number of messages to prefetch.

Implements `activemq::core::PrefetchPolicy` (p. 2979).

6.306.3 Field Documentation

6.306.3.1 `int activemq::core::policies::DefaultPrefetchPolicy::DEFAULT_DURABLE_TOPIC_PREFETCH` [static]

6.306.3.2 `int activemq::core::policies::DefaultPrefetchPolicy::DEFAULT_QUEUE_BROWSER_PREFETCH` [static]

6.306.3.3 `int activemq::core::policies::DefaultPrefetchPolicy::DEFAULT_QUEUE_PREFETCH` [static]

6.306.3.4 `int activemq::core::policies::DefaultPrefetchPolicy::DEFAULT_TOPIC_PREFETCH` [static]

6.306.3.5 `int activemq::core::policies::DefaultPrefetchPolicy::MAX_PREFETCH_SIZE` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/core/policies/DefaultPrefetchPolicy.h`

6.307 activemq::core::policies::DefaultRedeliveryPolicy Class Reference

#include <src/main/activemq/core/policies/DefaultRedeliveryPolicy.h>Inheritance diagram for activemq::core::policies::DefaultRedeliveryPolicy:

Public Member Functions

- **DefaultRedeliveryPolicy** ()
- virtual **~DefaultRedeliveryPolicy** ()
- virtual double **getBackOffMultiplier** () const
- virtual void **setBackOffMultiplier** (double value)
Sets the Back-Off Multiplier for Message Redelivery.
- virtual short **getCollisionAvoidancePercent** () const
- virtual void **setCollisionAvoidancePercent** (short value)
- virtual long long **getInitialRedeliveryDelay** () const
Gets the initial time that redelivery of messages is delayed.
- virtual void **setInitialRedeliveryDelay** (long long value)
Sets the initial time that redelivery will be delayed.
- virtual int **getMaximumRedeliveries** () const
Gets the Maximum number of allowed redeliveries for a message before it will be discarded by the consumer.
- virtual void **setMaximumRedeliveries** (int value)
Sets the Maximum allowable redeliveries for a Message.
- virtual bool **isUseCollisionAvoidance** () const
- virtual void **setUseCollisionAvoidance** (bool value)
- virtual bool **isUseExponentialBackOff** () const
- virtual void **setUseExponentialBackOff** (bool value)
- virtual long long **getRedeliveryDelay** (long long previousDelay)
Given the last used redelivery delay calculate the next value of the delay based on the settings in this Policy instance.
- virtual **RedeliveryPolicy** * **clone** () const
Create a copy of this Policy and return it.

6.307.1 Constructor & Destructor Documentation

6.307.1.1 `activemq::core::policies::DefaultRedeliveryPolicy::DefaultRedeliveryPolicy()`

6.307.1.2 `virtual
activemq::core::policies::DefaultRedeliveryPolicy::~~DefaultRedeliveryPolicy()
[virtual]`

6.307.2 Member Function Documentation

6.307.2.1 `virtual RedeliveryPolicy* ac-
tivemq::core::policies::DefaultRedeliveryPolicy::clone ()
const [virtual]`

Create a copy of this Policy and return it.

Returns:

pointer to a new **RedeliveryPolicy** (p. 3177) that is a copy of this one.

Implements **activemq::core::RedeliveryPolicy** (p. 3178).

6.307.2.2 `virtual double ac-
tivemq::core::policies::DefaultRedeliveryPolicy::getBackOffMultiplier ()
const [inline, virtual]`

Returns:

The value of the Back-Off Multiplier for Message Redelivery.

Implements **activemq::core::RedeliveryPolicy** (p. 3179).

6.307.2.3 `virtual short ac-
tivemq::core::policies::DefaultRedeliveryPolicy::getCollisionAvoidancePercent
() const [virtual]`

Returns:

the currently set Collision Avoidance percentage.

Implements **activemq::core::RedeliveryPolicy** (p. 3179).

6.307.2.4 `virtual long long ac-
tivemq::core::policies::DefaultRedeliveryPolicy::getInitialRedeliveryDelay
() const [inline, virtual]`

Gets the initial time that redelivery of messages is delayed.

Returns:

the time in milliseconds that redelivery is delayed initially.

Implements **activemq::core::RedeliveryPolicy** (p. 3179).

6.307.2.5 `virtual int activemq::core::policies::DefaultRedeliveryPolicy::getMaximumRedeliveries() const [inline, virtual]`

Gets the Maximum number of allowed redeliveries for a message before it will be discarded by the consumer.

Returns:

maximum allowed redeliveries for a message.

Implements `activemq::core::RedeliveryPolicy` (p. 3179).

6.307.2.6 `virtual long long activemq::core::policies::DefaultRedeliveryPolicy::getRedeliveryDelay(long long previousDelay) [virtual]`

Given the last used redelivery delay calculate the next value of the delay based on the settings in this Policy instance.

Parameters:

previousDelay The last delay that was used between message redeliveries.

Returns:

the new delay to use before attempting another redelivery.

Implements `activemq::core::RedeliveryPolicy` (p. 3179).

6.307.2.7 `virtual bool activemq::core::policies::DefaultRedeliveryPolicy::isUseCollisionAvoidance() const [inline, virtual]`

Returns:

whether or not collision avoidance is enabled for this Policy.

Implements `activemq::core::RedeliveryPolicy` (p. 3180).

6.307.2.8 `virtual bool activemq::core::policies::DefaultRedeliveryPolicy::isUseExponentialBackOff() const [inline, virtual]`

Returns:

whether or not the exponential back off option is enabled.

Implements `activemq::core::RedeliveryPolicy` (p. 3180).

6.307.2.9 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setBackOffMultiplier(double value) [inline, virtual]`

Sets the Back-Off Multiplier for Message Redelivery.

Parameters:

value The new value for the back-off multiplier.

Implements **activemq::core::RedeliveryPolicy** (p. 3180).

6.307.2.10 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setCollisionAvoidancePercent(short value) [virtual]`

Parameters:

value The collision avoidance percentage setting.

Implements **activemq::core::RedeliveryPolicy** (p. 3180).

6.307.2.11 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setInitialRedeliveryDelay(long long value) [inline, virtual]`

Sets the initial time that redelivery will be delayed.

Parameters:

value Time in Milliseconds to wait before starting redelivery.

Implements **activemq::core::RedeliveryPolicy** (p. 3180).

6.307.2.12 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setMaximumRedeliveries(int maximumRedeliveries) [inline, virtual]`

Sets the Maximum allowable redeliveries for a Message.

Parameters:

maximumRedeliveries The maximum number of times that a message will be redelivered.

Implements **activemq::core::RedeliveryPolicy** (p. 3181).

6.307.2.13 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setUseCollisionAvoidance(bool value) [inline, virtual]`

Parameters:

value Enable or Disable collision avoidance for this Policy.

Implements **activemq::core::RedeliveryPolicy** (p. 3181).

6.307.2.14 `virtual void activemq::core::policies::DefaultRedeliveryPolicy::setUseExponentialBackOff (bool value)` [inline, virtual]

Parameters:

value Enable or Disable the exponential back off multiplier option.

Implements **activemq::core::RedeliveryPolicy** (p. 3181).

The documentation for this class was generated from the following file:

- `src/main/activemq/core/policies/DefaultRedeliveryPolicy.h`

6.308 decaf::internal::net::DefaultServerSocketFactory Class Reference

Default implementation of the Decaf ServerSocketFactory, creates ServerSocket objects with supplied options.

#include <src/main/decaf/internal/net/DefaultServerSocketFactory.h> Inheritance diagram for decaf::internal::net::DefaultServerSocketFactory:

Public Member Functions

- **DefaultServerSocketFactory** ()
- virtual **~DefaultServerSocketFactory** ()
- virtual **decaf::net::ServerSocket * createServerSocket** ()

Create a new **ServerSocket** (p. 3352) that is unbound.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.
- virtual **decaf::net::ServerSocket * createServerSocket** (int port)

Create a new **ServerSocket** (p. 3352) that is bound to the given port.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.
- virtual **decaf::net::ServerSocket * createServerSocket** (int port, int backlog)

Create a new **ServerSocket** (p. 3352) that is bound to the given port.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.
- virtual **decaf::net::ServerSocket * createServerSocket** (int port, int backlog, const **decaf::net::InetAddress** *address)

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is **NULL** than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.
address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

6.308.1 Detailed Description

Default implementation of the Decaf ServerSocketFactory, creates ServerSocket objects with supplied options.

Since:

1.0

6.308.2 Constructor & Destructor Documentation

6.308.2.1 decaf::internal::net::DefaultServerSocketFactory::DefaultServerSocketFactory()
 ()

6.308.2.2 virtual decaf::internal::net::DefaultServerSocketFactory::~~DefaultServerSocketFactory()
 () [virtual]

6.308.3 Member Function Documentation

6.308.3.1 virtual decaf::net::ServerSocket* decaf::internal::net::DefaultServerSocketFactory::createServerSocket (int *port*, int *backlog*, const decaf::net::InetAddress * *address*) [virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is **NULL** than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.
address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.308.3.2 `virtual decaf::net::ServerSocket* decaf::internal::net::DefaultServerSocketFactory::createServerSocket (int port, int backlog) [virtual]`

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.308.3.3 `virtual decaf::net::ServerSocket* decaf::internal::net::DefaultServerSocketFactory::createServerSocket (int port) [virtual]`

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3363).

6.308.3.4 virtual decaf::net::ServerSocket* decaf::internal::net::DefaultServerSocketFactory::createServerSocket ()
[virtual]

Create a new **ServerSocket** (p. 3352) that is unbound.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Reimplemented from **decaf::net::ServerSocketFactory** (p. 3363).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/net/**DefaultServerSocketFactory.h**

6.309 decaf::internal::net::DefaultSocketFactory Class Reference

SocketFactory implementation that is used to create Sockets.

#include <src/main/decaf/internal/net/DefaultSocketFactory.h>Inheritance diagram for decaf::internal::net::DefaultSocketFactory:

Public Member Functions

- **DefaultSocketFactory** ()
- virtual **~DefaultSocketFactory** ()
- virtual **decaf::net::Socket * createSocket** () throw (decaf::io::IOException)
*Creates an unconnected **Socket** (p. 3503) object.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if the **Socket** (p. 3503) cannot be created.*
- virtual **decaf::net::Socket * createSocket** (const **decaf::net::InetAddress** *host, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.*
***UnknownHostException** (p. 3907) if the host name is not known.*
- virtual **decaf::net::Socket * createSocket** (const **decaf::net::InetAddress** *host, int port, const **decaf::net::InetAddress** *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
*The **Socket** (p. 3503) will be bound to the specified local address and port.*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
*ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.*
*localPort The local port to bind the **Socket** (p. 3503) to.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.*
***UnknownHostException** (p. 3907) if the host name is not known.*

- virtual **decaf::net::Socket** * **createSocket** (const std::string &name, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.
port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.

- virtual **decaf::net::Socket** * **createSocket** (const std::string &name, int port, const **decaf::net::InetAddress** *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.
port The port on the remote host to connect to.
ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.
localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.

6.309.1 Detailed Description

SocketFactory implementation that is used to create Sockets.

Since:

1.0

6.309.2 Constructor & Destructor Documentation

6.309.2.1 `decaf::internal::net::DefaultSocketFactory::DefaultSocketFactory ()`

6.309.2.2 `virtual decaf::internal::net::DefaultSocketFactory::~~DefaultSocketFactory ()` [virtual]

6.309.3 Member Function Documentation

6.309.3.1 `virtual decaf::net::Socket* decaf::internal::net::DefaultSocketFactory::createSocket (const std::string & name, int port, const decaf::net::InetAddress * ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)` [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.309.3.2 `virtual decaf::net::Socket* decaf::internal::net::DefaultSocketFactory::createSocket (const std::string & name, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)` [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.309.3.3 virtual decaf::net::Socket* decaf::internal::net::DefaultSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*, const decaf::net::InetAddress * *ifAddress*, int *localPort*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

The **Socket** (p. 3503) will be bound to the specified local address and port.

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.309.3.4 virtual decaf::net::Socket* decaf::internal::net::DefaultSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.309.3.5 `virtual decaf::net::Socket* decaf::internal::net::DefaultSocketFactory::createSocket ()
throw (decaf::io::IOException) [virtual]`

Creates an unconnected **Socket** (p. 3503) object.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if the **Socket** (p. 3503) cannot be created.

Reimplemented from **decaf::net::SocketFactory** (p. 3527).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/DefaultSocketFactory.h`

6.310 decaf::internal::net::ssl::DefaultSSLContext Class Reference

Default SSLContext manager for the Decaf library.

```
#include <src/main/decaf/internal/net/ssl/DefaultSSLContext.h>
```

Public Member Functions

- virtual `~DefaultSSLContext ()`

Static Public Member Functions

- static `decaf::net::ssl::SSLContext * getContext ()`

Protected Member Functions

- `DefaultSSLContext ()`

6.310.1 Detailed Description

Default SSLContext manager for the Decaf library. If the user doesn't supply or specify the SSLContext that they wish to use then we load the Decaf library's default SSLContext using whatever SSL provider is enabled an preferred.

Since:

1.0

6.310.2 Constructor & Destructor Documentation

6.310.2.1 `decaf::internal::net::ssl::DefaultSSLContext::DefaultSSLContext ()`
[protected]

6.310.2.2 `virtual decaf::internal::net::ssl::DefaultSSLContext::~~DefaultSSLContext ()` [virtual]

6.310.3 Member Function Documentation

6.310.3.1 `static decaf::net::ssl::SSLContext* decaf::internal::net::ssl::DefaultSSLContext::getContext ()`
[static]

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/DefaultSSLContext.h`

6.311 decaf::internal::net::ssl::DefaultSSLServerSocketFactory Class Reference

Default implementation of the SSLServerSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

#include <src/main/decaf/internal/net/ssl/DefaultSSLServerSocketFactory.h> Inheritance diagram for decaf::internal::net::ssl::DefaultSSLServerSocketFactory:

Public Member Functions

- **DefaultSSLServerSocketFactory** (const std::string &errorMessage)
- virtual ~**DefaultSSLServerSocketFactory** ()
- virtual **decaf::net::ServerSocket * createServerSocket** ()

*Create a new **ServerSocket** (p. 3352) that is unbound.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.*

Returns:

*new **ServerSocket** (p. 3352) pointer that is owned by the caller.*

Exceptions:

*IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.*
- virtual **decaf::net::ServerSocket * createServerSocket** (int port)

*Create a new **ServerSocket** (p. 3352) that is bound to the given port.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.*

Parameters:

*port The port to bind the **ServerSocket** (p. 3352) to.*

Returns:

*new **ServerSocket** (p. 3352) pointer that is owned by the caller.*

Exceptions:

*IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.*
- virtual **decaf::net::ServerSocket * createServerSocket** (int port, int backlog)

*Create a new **ServerSocket** (p. 3352) that is bound to the given port.
The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.*

Parameters:

*port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.*

Returns:

*new **ServerSocket** (p. 3352) pointer that is owned by the caller.*

Exceptions:

*IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.*
- virtual **decaf::net::ServerSocket * createServerSocket** (int port, int backlog, const **decaf::net::InetAddress** *address)

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is *NULL* than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.
address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

- virtual std::vector< std::string > **getDefaultCipherSuites** ()

Returns the list of cipher suites which are enabled by default. Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

getSupportedCipherSuites() (p. 3561)

- virtual std::vector< std::string > **getSupportedCipherSuites** ()

Returns the names of the cipher suites which could be enabled for use on an SSL connection. Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

getDefaultCipherSuites() (p. 3561)

6.311.1 Detailed Description

Default implementation of the SSLServerSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

Since:

1.0

6.311.2 Constructor & Destructor Documentation

6.311.2.1 `decaf::internal::net::ssl::DefaultSSLServerSocketFactory::DefaultSSLServerSocketFactory(const std::string & errorMessage)`

6.311.2.2 `virtual decaf::internal::net::ssl::DefaultSSLServerSocketFactory::~DefaultSSLServerSocketFactory() [virtual]`

6.311.3 Member Function Documentation

6.311.3.1 `virtual decaf::net::ServerSocket* decaf::internal::net::ssl::DefaultSSLServerSocketFactory::createServerSocket(int port, int backlog, const decaf::net::InetAddress * address) [virtual]`

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is NULL than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.311.3.2 `virtual decaf::net::ServerSocket* decaf::internal::net::ssl::DefaultSSLServerSocketFactory::createServerSocket(int port, int backlog) [virtual]`

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.311.3.3 **virtual decaf::net::ServerSocket* decaf::internal::net::ssl::DefaultSSLServerSocketFactory::createServerSocket(int port) [virtual]**

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3363).

6.311.3.4 **virtual decaf::net::ServerSocket* decaf::internal::net::ssl::DefaultSSLServerSocketFactory::createServerSocket() [virtual]**

Create a new **ServerSocket** (p. 3352) that is unbound.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Reimplemented from **decaf::net::ServerSocketFactory** (p. 3363).

6.311.3.5 **virtual std::vector<std::string> decaf::internal::net::ssl::DefaultSSLServerSocketFactory::getDefaultCipherSuites() [virtual]**

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

`getSupportedCipherSuites()` (p. 3561)

Implements `decaf::net::ssl::SSLServerSocketFactory` (p. 3561).

6.311.3.6 `virtual std::vector<std::string> decaf::internal::net::ssl::DefaultSSLServerSocketFactory::getSupportedCipherSuites()` [virtual]

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

`getDefaultCipherSuites()` (p. 3561)

Implements `decaf::net::ssl::SSLServerSocketFactory` (p. 3561).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/DefaultSSLServerSocketFactory.h`

6.312 decaf::internal::net::ssl::DefaultSSLSocketFactory Class Reference

Default implementation of the SSLSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

#include <src/main/decaf/internal/net/ssl/DefaultSSLSocketFactory.h>Inheritance diagram for decaf::internal::net::ssl::DefaultSSLSocketFactory:

Public Member Functions

- **DefaultSSLSocketFactory** (const std::string &errorMessage)
- virtual ~**DefaultSSLSocketFactory** ()
- virtual **decaf::net::Socket** * **createSocket** () throw (decaf::io::IOException)
*Creates an unconnected **Socket** (p. 3503) object.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
*IOException if the **Socket** (p. 3503) cannot be created.*
- virtual **decaf::net::Socket** * **createSocket** (const **decaf::net::InetAddress** *host, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
*IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.*
UnknownHostException (p. 3907) if the host name is not known.
- virtual **decaf::net::Socket** * **createSocket** (const **decaf::net::InetAddress** *host, int port, const **decaf::net::InetAddress** *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
*The **Socket** (p. 3503) will be bound to the specified local address and port.*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
*ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.*
*localPort The local port to bind the **Socket** (p. 3503) to.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
*IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.*

UnknownHostException (p. 3907) if the host name is not known.

- virtual **decaf::net::Socket * createSocket** (const std::string &name, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)

*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*

Parameters:

***host** The host name or IP address to connect the socket to.
port The port on the remote host to connect to.*

Returns:

*a new **Socket** (p. 3503) object, caller must free this object when done.*

Exceptions:

***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.*

- virtual **decaf::net::Socket * createSocket** (const std::string &name, int port, const decaf::net::InetAddress *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)

*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*

Parameters:

***host** The host name or IP address to connect the socket to.
port The port on the remote host to connect to.
ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.
localPort The local port to bind the **Socket** (p. 3503) to.*

Returns:

*a new **Socket** (p. 3503) object, caller must free this object when done.*

Exceptions:

***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.*

- virtual std::vector< std::string > **getDefaultCipherSuites** ()

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

***getSupportedCipherSuites()** (p. 3573)*

- virtual std::vector< std::string > **getSupportedCipherSuites** ()

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

***getDefaultCipherSuites()** (p. 3573)*

- virtual **decaf::net::Socket * createSocket** (**decaf::net::Socket *socket**, **std::string host**, **int port**, **bool autoClose**)

Returns a socket layered over an existing socket connected to the named host, at the given port. This constructor can be used when tunneling SSL through a proxy or when negotiating the use of SSL over an existing socket. The host and port refer to the logical peer destination. This socket is configured using the socket options established for this factory.

Parameters:

socket The existing socket to layer over.
host The server host the original **Socket** (p. 3503) is connected to.
port The server port the original **Socket** (p. 3503) is connected to.
autoClose Should the layered over **Socket** (p. 3503) be closed when the topmost socket is closed.

Returns:

a new **Socket** (p. 3503) instance that wraps the given **Socket** (p. 3503).

Exceptions:

IOException if an I/O exception occurs while performing this operation.
UnknownHostException (p. 3907) if the host is unknown.

6.312.1 Detailed Description

Default implementation of the SSLSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

Since:

1.0

6.312.2 Constructor & Destructor Documentation

6.312.2.1 **decaf::internal::net::ssl::DefaultSSLSocketFactory::DefaultSSLSocketFactory** (**const std::string & errorMessage**)

6.312.2.2 **virtual**
decaf::internal::net::ssl::DefaultSSLSocketFactory::~DefaultSSLSocketFactory
 () [virtual]

6.312.3 Member Function Documentation

6.312.3.1 **virtual decaf::net::Socket* de-**
caf::internal::net::ssl::DefaultSSLSocketFactory::createSocket
 (**decaf::net::Socket * socket**, **std::string host**, **int port**, **bool autoClose**)
 [virtual]

Returns a socket layered over an existing socket connected to the named host, at the given port.

This constructor can be used when tunneling SSL through a proxy or when negotiating the use of SSL over an existing socket. The host and port refer to the logical peer destination. This socket is configured using the socket options established for this factory.

Parameters:

socket The existing socket to layer over.

host The server host the original **Socket** (p. 3503) is connected to.

port The server port the original **Socket** (p. 3503) is connected to.

autoClose Should the layered over **Socket** (p. 3503) be closed when the topmost socket is closed.

Returns:

a new **Socket** (p. 3503) instance that wraps the given **Socket** (p. 3503).

Exceptions:

IOException if an I/O exception occurs while performing this operation.

UnknownHostException (p. 3907) if the host is unknown.

Implements **decaf::net::ssl::SSLSocketFactory** (p. 3572).

6.312.3.2 virtual **decaf::net::Socket*** **decaf::internal::net::ssl::DefaultSSLSocketFactory::createSocket** (const **std::string** & *name*, int *port*, const **decaf::net::InetAddress** * *ifAddress*, int *localPort*) throw (**decaf::io::IOException**, **decaf::net::UnknownHostException**) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.312.3.3 virtual **decaf::net::Socket*** **decaf::internal::net::ssl::DefaultSSLSocketFactory::createSocket** (const **std::string** & *name*, int *port*) throw (**decaf::io::IOException**, **decaf::net::UnknownHostException**) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.312.3.4 virtual decaf::net::Socket* decaf::internal::net::ssl::DefaultSSLSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*, const decaf::net::InetAddress * *ifAddress*, int *localPort*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

The **Socket** (p. 3503) will be bound to the specified local address and port.

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.312.3.5 virtual decaf::net::Socket* decaf::internal::net::ssl::DefaultSSLSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.312.3.6 `virtual decaf::net::Socket* decaf::internal::net::ssl::DefaultSSLSocketFactory::createSocket () throw (decaf::io::IOException) [virtual]`

Creates an unconnected **Socket** (p. 3503) object.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if the **Socket** (p. 3503) cannot be created.

Reimplemented from **decaf::net::SocketFactory** (p. 3527).

6.312.3.7 `virtual std::vector<std::string> decaf::internal::net::ssl::DefaultSSLSocketFactory::getDefaultCipherSuites () [virtual]`

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

getSupportedCipherSuites() (p. 3573)

Implements **decaf::net::ssl::SSLSocketFactory** (p. 3573).

6.312.3.8 virtual std::vector<std::string> decaf::internal::net::ssl::DefaultSSLSocketFactory::getSupportedCipherSuites() [virtual]

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

[getDefaultCipherSuites\(\)](#) (p. 3573)

Implements [decaf::net::ssl::SSLSocketFactory](#) (p. 3573).

The documentation for this class was generated from the following file:

- [src/main/decaf/internal/net/ssl/DefaultSSLSocketFactory.h](#)

6.313 activemq::transport::DefaultTransportListener Class Reference

#include <src/main/activemq/transport/DefaultTransportListener.h> Inheritance diagram for activemq::transport::DefaultTransportListener:

Public Member Functions

- virtual **~DefaultTransportListener** ()
- virtual void **onCommand** (const **Pointer**< **Command** > &command *AMQCPP_*-*UNUSED*)
Event handler for the receipt of a command.
- virtual void **onException** (const **decaf::lang::Exception** &ex *AMQCPP_*-*UNUSED*)
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **transportInterrupted** ()
*The **transport** (p. 97) has suffered an interruption from which it hopes to recover.*
- virtual void **transportResumed** ()
*The **transport** (p. 97) has resumed after an interruption.*

6.313.1 Constructor & Destructor Documentation

- 6.313.1.1** virtual **activemq::transport::DefaultTransportListener::~~DefaultTransportListener** () [inline, virtual]

6.313.2 Member Function Documentation

- 6.313.2.1** virtual void **activemq::transport::DefaultTransportListener::onCommand** (const **Pointer**< **Command** > &command *AMQCPP_*-*UNUSED*) [inline, virtual]

Event handler for the receipt of a command. The **transport** (p. 97) passes off all received **commands** (p. 87) to its listeners, the listener then owns the Object. If there is no registered listener the **Transport** (p. 3883) deletes the command upon receipt.

Parameters:

command the received command object.

- 6.313.2.2** virtual void **activemq::transport::DefaultTransportListener::onException** (const **decaf::lang::Exception** &ex *AMQCPP_*-*UNUSED*) [inline, virtual]

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception.

6.313.2.3 virtual void activemq::transport::DefaultTransportListener::transportInterrupted ()
[inline, virtual]

The **transport** (p.97) has suffered an interruption from which it hopes to recover.

Implements **activemq::transport::TransportListener** (p.3901).

6.313.2.4 virtual void activemq::transport::DefaultTransportListener::transportResumed ()
[inline, virtual]

The **transport** (p.97) has resumed after an interruption.

Implements **activemq::transport::TransportListener** (p.3901).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/**DefaultTransportListener.h**

6.314 decaf::util::zip::Deflater Class Reference

This class compresses data using the *DEFLATE* algorithm (see [specification](#)).

```
#include <src/main/decaf/util/zip/Deflater.h>
```

Public Member Functions

- **Deflater** (int level, bool nowrap=false)
Creates a new compressor using the specified compression level.
- **Deflater** ()
Creates a new compressor with the default compression level.
- virtual **~Deflater** ()
- void **setInput** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets input data for compression.
- void **setInput** (const std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets input data for compression.
- void **setInput** (const std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException)
Sets input data for compression.
- void **setDictionary** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets preset dictionary for compression.
- void **setDictionary** (const std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets preset dictionary for compression.
- void **setDictionary** (const std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException)
Sets preset dictionary for compression.
- void **setStrategy** (int strategy) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Sets the compression strategy to the specified value.
- void **setLevel** (int level) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Sets the compression level to the specified value.

- bool **needsInput** () const
- void **finish** ()

When called, indicates that compression should end with the current contents of the input buffer.

- bool **finished** () const
- int **deflate** (unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data.

- int **deflate** (std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data.

- int **deflate** (std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data.

- long long **getAdler** () const throw (decaf::lang::exceptions::IllegalStateException)
- long long **getBytesRead** () const throw (decaf::lang::exceptions::IllegalStateException)
- long long **getBytesWritten** () const throw (decaf::lang::exceptions::IllegalStateException)
- void **reset** () throw (decaf::lang::exceptions::IllegalStateException)

Resets deflater so that a new set of input data can be processed.

- void **end** ()

Closes the compressor and discards any unprocessed input.

Static Public Attributes

- static const int **BEST_SPEED**
Compression level for fastest compression.
- static const int **BEST_COMPRESSION**
Compression level for best compression.
- static const int **DEFAULT_COMPRESSION**
Default compression level.
- static const int **DEFLATED**
Compression method for the deflate algorithm (the only one currently supported).
- static const int **NO_COMPRESSION**
Compression level for no compression.

- static const int **FILTERED**

Compression strategy best used for data consisting mostly of small values with a somewhat random distribution.

- static const int **HUFFMAN_ONLY**

Compression strategy for Huffman coding only.

- static const int **DEFAULT_STRATEGY**

Default compression strategy.

6.314.1 Detailed Description

This class compresses data using the *DEFLATE* algorithm (see [specification](#)). Basically this class is part of the API to the stream based ZLIB compression library and is used as such by **DeflaterOutputStream** (p. 1716) and its descendants.

The typical usage of a **Deflater** (p. 1706) instance outside this package consists of a specific call to one of its constructors before being passed to an instance of **DeflaterOutputStream** (p. 1716).

See also:

DeflaterOutputStream (p. 1716)

Inflater (p. 2027)

Since:

1.0

6.314.2 Constructor & Destructor Documentation

6.314.2.1 `decaf::util::zip::Deflater::Deflater (int level, bool nowrap = false)`

Creates a new compressor using the specified compression level. If 'nowrap' is true then the ZLIB header and checksum fields will not be used in order to support the compression format used in both GZIP and PKZIP.

Parameters:

level The compression level to use (0-9).

nowrap If true uses GZip compatible compression (defaults to false).

6.314.2.2 `decaf::util::zip::Deflater::Deflater ()`

Creates a new compressor with the default compression level. Compressed data will be generated in ZLIB format.

6.314.2.3 virtual decaf::util::zip::Deflater::~~Deflater () [virtual]

6.314.3 Member Function Documentation

6.314.3.1 int decaf::util::zip::Deflater::deflate (std::vector< unsigned char > & *buffer*) throw (decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data. Returns actual number of bytes of compressed data. A return value of 0 indicates that **needsInput()** (p. 1711) should be called in order to determine if more input data is required.

Parameters:

buffer The Buffer to write the compressed data to.

Returns:

the actual number of bytes of compressed data.

Exceptions:

IllegalStateException if in the end state.

6.314.3.2 int decaf::util::zip::Deflater::deflate (std::vector< unsigned char > & *buffer*, int *offset*, int *length*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data. Returns actual number of bytes of compressed data. A return value of 0 indicates that **needsInput()** (p. 1711) should be called in order to determine if more input data is required.

Parameters:

buffer The Buffer to write the compressed data to.

offset The position in the Buffer to start writing at.

length The maximum number of byte of data to write.

Returns:

the actual number of bytes of compressed data.

Exceptions:

IndexOutOfBoundsException if the offset + length > size of the buffer.

IllegalStateException if in the end state.

6.314.3.3 int decaf::util::zip::Deflater::deflate (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Fills specified buffer with compressed data. Returns actual number of bytes of compressed data. A return value of 0 indicates that **needsInput()** (p. 1711) should be called in order to determine if more input data is required.

Parameters:

buffer The Buffer to write the compressed data to.
size The size of the passed buffer.
offset The position in the Buffer to start writing at.
length The maximum number of byte of data to write.

Returns:

the actual number of bytes of compressed data.

Exceptions:

NullPointerException if buffer is NULL.
IndexOutOfBoundsException if the offset + length > size of the buffer.
IllegalStateException if in the end state.

6.314.3.4 void decaf::util::zip::Deflater::end ()

Closes the compressor and discards any unprocessed input. This method should be called when the compressor is no longer being used, but will also be called automatically by the destructor. Once this method is called, the behavior of the **Deflater** (p. 1706) object is undefined.

6.314.3.5 void decaf::util::zip::Deflater::finish ()

When called, indicates that compression should end with the current contents of the input buffer.

6.314.3.6 bool decaf::util::zip::Deflater::finished () const**Returns:**

true if the end of the compressed data output stream has been reached.

6.314.3.7 long long decaf::util::zip::Deflater::getAdler () const throw (decaf::lang::exceptions::IllegalStateException)**Returns:**

the ADLER-32 value of the uncompressed data.

Exceptions:

IllegalStateException if in the end state.

6.314.3.8 long long decaf::util::zip::Deflater::getBytesRead () const throw (decaf::lang::exceptions::IllegalStateException)**Returns:**

the total number of uncompressed bytes input so far.

Exceptions:

IllegalStateException if in the end state.

6.314.3.9 `long long decaf::util::zip::Deflater::getBytesWritten () const throw (decaf::lang::exceptions::IllegalStateException)`

Returns:

the total number of compressed bytes output so far.

Exceptions:

IllegalStateException if in the end state.

6.314.3.10 `bool decaf::util::zip::Deflater::needsInput () const`

Returns:

true if the input data buffer is empty and `setInput()` (p. 1713) should be called in order to provide more input

6.314.3.11 `void decaf::util::zip::Deflater::reset () throw (decaf::lang::exceptions::IllegalStateException)`

Resets deflater so that a new set of input data can be processed. Keeps current compression level and strategy settings.

Exceptions:

IllegalStateException if in the end state.

6.314.3.12 `void decaf::util::zip::Deflater::setDictionary (const std::vector< unsigned char > & buffer) throw (decaf::lang::exceptions::IllegalStateException)`

Sets preset dictionary for compression. A preset dictionary is used when the history buffer can be predetermined. When the data is later uncompressed with `Inflater.inflate()` (p. 2031), `Inflater.getAdler()` (p. 2029) can be called in order to get the Adler-32 value of the dictionary required for decompression.

Parameters:

buffer The buffer containing the preset dictionary.

Exceptions:

IllegalStateException if in the end state.

6.314.3.13 `void decaf::util::zip::Deflater::setDictionary (const std::vector< unsigned char > & buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)`

Sets preset dictionary for compression. A preset dictionary is used when the history buffer can be predetermined. When the data is later uncompressed with **Inflater.inflate()** (p. 2031), **Inflater.getAdler()** (p. 2029) can be called in order to get the Adler-32 value of the dictionary required for decompression.

Parameters:

buffer The buffer containing the preset dictionary.
offset The position in the Buffer to start reading from.
length The number of bytes to read from the input buffer.

Exceptions:

IndexOutOfBoundsException if the offset + length > size of the buffer.
IllegalStateException if in the end state.

6.314.3.14 `void decaf::util::zip::Deflater::setDictionary (const unsigned char * buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)`

Sets preset dictionary for compression. A preset dictionary is used when the history buffer can be predetermined. When the data is later uncompressed with **Inflater.inflate()** (p. 2031), **Inflater.getAdler()** (p. 2029) can be called in order to get the Adler-32 value of the dictionary required for decompression.

Parameters:

buffer The buffer containing the preset dictionary.
size The size of the passed dictionary buffer.
offset The position in the Buffer to start reading from.
length The number of bytes to read from the input buffer.

Exceptions:

NullPointerException if buffer is NULL.
IndexOutOfBoundsException if the offset + length > size of the buffer.
IllegalStateException if in the end state.

6.314.3.15 `void decaf::util::zip::Deflater::setInput (const std::vector< unsigned char > & buffer) throw (decaf::lang::exceptions::IllegalStateException)`

Sets input data for compression. This should be called whenever **needsInput()** (p. 1711) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for compression.

Exceptions:

IllegalStateException if in the end state.

6.314.3.16 void decaf::util::zip::Deflater::setInput (const std::vector< unsigned char > & *buffer*, int *offset*, int *length*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Sets input data for compression. This should be called whenever **needsInput()** (p. 1711) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for compression.

offset The position in the Buffer to start reading from.

length The number of bytes to read from the input buffer.

Exceptions:

IndexOutOfBoundsException if the offset + length > size of the buffer.

IllegalStateException if in the end state.

6.314.3.17 void decaf::util::zip::Deflater::setInput (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Sets input data for compression. This should be called whenever **needsInput()** (p. 1711) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for compression.

size The size in bytes of the buffer passed.

offset The position in the Buffer to start reading from.

length The number of bytes to read from the input buffer.

Exceptions:

NullPointerException if buffer is NULL.

IndexOutOfBoundsException if the offset + length > size of the buffer.

IllegalStateException if in the end state.

6.314.3.18 `void decaf::util::zip::Deflater::setLevel (int level) throw
 (decaf::lang::exceptions::IllegalArgumentException,
 decaf::lang::exceptions::IllegalStateException)`

Sets the compression level to the specified value.

Parameters:

level The new Compression level to use.

Exceptions:

IllegalArgumentException if the level value is invalid.

IllegalStateException if in the end state.

6.314.3.19 `void decaf::util::zip::Deflater::setStrategy (int strategy)
 throw (decaf::lang::exceptions::IllegalArgumentException,
 decaf::lang::exceptions::IllegalStateException)`

Sets the compression strategy to the specified value.

Parameters:

strategy The new Compression strategy to use.

Exceptions:

IllegalArgumentException if the strategy value is invalid.

IllegalStateException if in the end state.

6.314.4 Field Documentation

6.314.4.1 `const int decaf::util::zip::Deflater::BEST_COMPRESSION [static]`

Compression level for best compression.

6.314.4.2 `const int decaf::util::zip::Deflater::BEST_SPEED [static]`

Compression level for fastest compression.

6.314.4.3 `const int decaf::util::zip::Deflater::DEFAULT_COMPRESSION
 [static]`

Default compression level.

6.314.4.4 `const int decaf::util::zip::Deflater::DEFAULT_STRATEGY [static]`

Default compression strategy.

6.314.4.5 const int decaf::util::zip::Deflater::DEFLATED [static]

Compression method for the deflate algorithm (the only one currently supported).

6.314.4.6 const int decaf::util::zip::Deflater::FILTERED [static]

Compression strategy best used for data consisting mostly of small values with a somewhat random distribution. Forces more Huffman coding and less string matching.

6.314.4.7 const int decaf::util::zip::Deflater::HUFFMAN_ONLY [static]

Compression strategy for Huffman coding only.

6.314.4.8 const int decaf::util::zip::Deflater::NO_COMPRESSION [static]

Compression level for no compression.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/Deflater.h`

6.315 decaf::util::zip::DeflaterOutputStream Class Reference

Provides a FilterOutputStream instance that compresses the data before writing it to the wrapped OutputStream.

#include <src/main/decaf/util/zip/DeflaterOutputStream.h> Inheritance diagram for decaf::util::zip::DeflaterOutputStream:

Public Member Functions

- **DeflaterOutputStream** (decaf::io::OutputStream *outputStream, bool own=false)

*Creates a new DeflateOutputStream with a Default **Deflater** (p. 1706) and buffer size.*

- **DeflaterOutputStream** (decaf::io::OutputStream *outputStream, Deflater *deflater, bool own=false)

*Creates a new DeflateOutputStream with a user supplied **Deflater** (p. 1706) and a default buffer size.*

- **DeflaterOutputStream** (decaf::io::OutputStream *outputStream, Deflater *deflater, int bufferSize, bool own=false)

*Creates a new DeflateOutputStream with a user supplied **Deflater** (p. 1706) and specified buffer size.*

- virtual ~**DeflaterOutputStream** ()
- virtual void **finish** () throw (decaf::io::IOException)

Finishes writing any remaining data to the wrapped OutputStream but does not close it upon completion.

- virtual void **close** () throw (decaf::io::IOException)

*Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.*

Exceptions:

***IOException** (p. 2142) if an error occurs while closing.*

The default implementation of this method does nothing.

*The close method of **FilterOutputStream** (p. 1900) calls its flush method, and then calls the close method of its underlying output stream.*

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual void **deflate** () throw (decaf::io::IOException)

Writes a buffers worth of compressed data to the wrapped OutputStream.

Protected Attributes

- **Deflater * deflater**
*The **Deflater** (p. 1706) for this stream.*
- `std::vector< unsigned char > buf`
*The **Buffer** to use for.*
- `bool ownDeflater`
- `bool isDone`

Static Protected Attributes

- `static const std::size_t DEFAULT_BUFFER_SIZE`

6.315.1 Detailed Description

Provides a FilterOutputStream instance that compresses the data before writing it to the wrapped OutputStream.

Since:

1.0

6.315.2 Constructor & Destructor Documentation

6.315.2.1 decaf::util::zip::DeflaterOutputStream::DeflaterOutputStream (decaf::io::OutputStream * *outputStream*, bool *own* = false)

Creates a new DeflateOutputStream with a Default **Deflater** (p. 1706) and buffer size.

Parameters:

outputStream The OutputStream instance to wrap.

own Should this filter take ownership of the OutputStream pointer (default is false).

6.315.2.2 decaf::util::zip::DeflaterOutputStream::DeflaterOutputStream (decaf::io::OutputStream * *outputStream*, Deflater * *deflater*, bool *own* = false)

Creates a new DeflateOutputStream with a user supplied **Deflater** (p. 1706) and a default buffer size. When the user supplied a **Deflater** (p. 1706) instance the DeflaterOutpotStream does not take ownership of the **Deflater** (p. 1706) pointer, the caller is still responsible for deleting the **Deflater** (p. 1706).

Parameters:

outputStream The OutputStream instance to wrap.

deflater The user supplied **Deflater** (p. 1706) to use for compression. (

own Should this filter take ownership of the OutputStream pointer (default is false).

Exceptions:

NullPointerException if the **Deflater** (p.1706) given is NULL.

6.315.2.3 **decaf::util::zip::DeflaterOutputStream::DeflaterOutputStream** (**decaf::io::OutputStream** * *outputStream*, **Deflater** * *deflater*, **int** *bufferSize*, **bool** *own* = false)

Creates a new DeflateOutputStream with a user supplied **Deflater** (p.1706) and specified buffer size. When the user supplied a **Deflater** (p.1706) instance the DeflaterOutpotStream does not take ownership of the **Deflater** (p.1706) pointer, the caller is still responsible for deleting the **Deflater** (p.1706).

Parameters:

outputStream The OutputStream instance to wrap.

deflater The user supplied **Deflater** (p.1706) to use for compression.

bufferSize The size of the input buffer.

own Should this filter take ownership of the OutputStream pointer (default is false).

Exceptions:

NullPointerException if the **Deflater** (p.1706) given is NULL.

IllegalArgumentException if bufferSize is 0.

6.315.2.4 **virtual decaf::util::zip::DeflaterOutputStream::~~DeflaterOutputStream ()** [virtual]

6.315.3 Member Function Documentation

6.315.3.1 **virtual void decaf::util::zip::DeflaterOutputStream::close () throw (** **decaf::io::IOException)** [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing.

The close method of **FilterOutputStream** (p.1900) calls its flush method, and then calls the close method of its underlying output stream. Finishes writing any remaining data to the OutputStream then closes the stream.

Reimplemented from **decaf::io::FilterOutputStream** (p.1901).

6.315.3.2 **virtual void decaf::util::zip::DeflaterOutputStream::deflate () throw (** **decaf::io::IOException)** [protected, virtual]

Writes a buffers worth of compressed data to the wrapped OutputStream.

6.315.3.3 virtual void decaf::util::zip::DeflaterOutputStream::doWriteArrayBounded (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.315.3.4 virtual void decaf::util::zip::DeflaterOutputStream::doWriteByte (unsigned char *value*) throw (decaf::io::IOException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.315.3.5 virtual void decaf::util::zip::DeflaterOutputStream::finish () throw (decaf::io::IOException) [virtual]

Finishes writing any remaining data to the wrapped OutputStream but does not close it upon completion.

Exceptions:

IOException if an I/O error occurs.

6.315.4 Field Documentation

6.315.4.1 std::vector<unsigned char> decaf::util::zip::DeflaterOutputStream::buf [protected]

The Buffer to use for.

6.315.4.2 const std::size_t decaf::util::zip::DeflaterOutputStream::DEFAULT_BUFFER_SIZE [static, protected]

6.315.4.3 Deflater* decaf::util::zip::DeflaterOutputStream::deflater [protected]

The Deflater (p. 1706) for this stream.

6.315.4.4 bool decaf::util::zip::DeflaterOutputStream::isDone [protected]

6.315.4.5 bool decaf::util::zip::DeflaterOutputStream::ownDeflater [protected]

The documentation for this class was generated from the following file:

- src/main/decaf/util/zip/DeflaterOutputStream.h

6.316 decaf::util::concurrent::Delayed Class Reference

A mix-in style interface for marking objects that should be acted upon after a given delay.

#include <src/main/decaf/util/concurrent/Delayed.h> Inheritance diagram for decaf::util::concurrent::Delayed:

Public Member Functions

- virtual `~Delayed()`
- virtual long long `getDelay` (const `TimeUnit` &unit)=0

Returns the remaining delay associated with this object, in the given time unit.

6.316.1 Detailed Description

A mix-in style interface for marking objects that should be acted upon after a given delay. An implementation of this interface must define a `Comparable` methods that provides an ordering consistent with its `getDelay` method.

6.316.2 Constructor & Destructor Documentation

6.316.2.1 virtual `decaf::util::concurrent::Delayed::~~Delayed()` [`inline`, `virtual`]

6.316.3 Member Function Documentation

6.316.3.1 virtual long long `decaf::util::concurrent::Delayed::getDelay` (const `TimeUnit` & *unit*) [`pure virtual`]

Returns the remaining delay associated with this object, in the given time unit.

Parameters:

unit The time unit

Returns:

the remaining delay; zero or negative values indicate that the delay has already elapsed

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Delayed.h`

6.317 cms::DeliveryMode Class Reference

This is an Abstract class whose purpose is to provide a container for the delivery mode enumeration for CMS messages.

```
#include <src/main/cms/DeliveryMode.h>
```

Public Types

- enum **DELIVERY_MODE** { **PERSISTENT** = 0, **NON_PERSISTENT** = 1 }

*Enumeration values for **Message** (p. 2534) Delivery Mode.*

Public Member Functions

- virtual **~DeliveryMode** ()

6.317.1 Detailed Description

This is an Abstract class whose purpose is to provide a container for the delivery mode enumeration for CMS messages. When a client sends a **cms::Message** (p. 2534) it can mark the **Message** (p. 2534) as either Persistent or Non-Persistent. If the client feels that the **Message** (p. 2534) cannot be lost in transit it should mark it as Persistent, otherwise if it is allowable for a **Message** (p. 2534) to occasionally be lost it can mark it as Non-Persistent. This allows the Provider to balance make tradeoffs between balance and **Message** (p. 2534) throughput.

The **DeliveryMode** (p. 1721) covers only the transport of the **Message** (p. 2534) for sending client to its destination and doesn't apply to the receiving **Message** (p. 2534) consumer. The receiving Consumer can drop Message's based on configuration such as memory limits or **Message** (p. 2534) filtering.

A message is guaranteed to be delivered once and only once by a CMS provider if the delivery mode of the message is PERSISTENT and the configuration of the **Message** (p. 2534) consumer allows for it.

Since:

1.0

6.317.2 Member Enumeration Documentation

6.317.2.1 enum cms::DeliveryMode::DELIVERY_MODE

Enumeration values for **Message** (p. 2534) Delivery Mode.

Enumerator:

PERSISTENT

NON_PERSISTENT

6.317.3 Constructor & Destructor Documentation

6.317.3.1 `virtual cms::DeliveryMode::~~DeliveryMode ()` [inline, virtual]

The documentation for this class was generated from the following file:

- `src/main/cms/DeliveryMode.h`

6.318 cms::Destination Class Reference

A **Destination** (p. 1723) object encapsulates a provider-specific address.

#include <src/main/cms/Destination.h> Inheritance diagram for cms::Destination:

Public Types

- enum **DestinationType** { **TOPIC**, **QUEUE**, **TEMPORARY_TOPIC**, **TEMPORARY_QUEUE** }

Public Member Functions

- virtual **~Destination** ()
- virtual **DestinationType** **getDestinationType** () const =0
*Retrieve the **Destination** (p. 1723) Type for this **Destination** (p. 1723).*
- virtual **cms::Destination * clone** () const =0
Creates a new instance of this destination type that is a copy of this one, and returns it.
- virtual void **copy** (const **cms::Destination** &source)=0
*Copies the contents of the given **Destination** (p. 1723) object to this one.*
- virtual const **CMSProperties** & **getCMSProperties** () const =0
Retrieve any properties that might be part of the destination that was specified.

6.318.1 Detailed Description

A **Destination** (p. 1723) object encapsulates a provider-specific address. There is no standard definition of a **Destination** (p. 1723) address, each provider can provide its own definition and there can be configuration data attached to the **Destination** (p. 1723) address.

All CMS **Destination** (p. 1723) objects support concurrent use.

Since:

1.0

6.318.2 Member Enumeration Documentation

6.318.2.1 enum cms::Destination::DestinationType

Enumerator:

TOPIC
QUEUE
TEMPORARY_TOPIC
TEMPORARY_QUEUE

6.318.3 Constructor & Destructor Documentation

6.318.3.1 `virtual cms::Destination::~~Destination () [inline, virtual]`

6.318.4 Member Function Documentation

6.318.4.1 `virtual cms::Destination* cms::Destination::clone () const [pure virtual]`

Creates a new instance of this destination type that is a copy of this one, and returns it.

Returns:

cloned copy of this object

Implemented in `activemq::commands::ActiveMQQueue` (p. 484),
`activemq::commands::ActiveMQTempQueue` (p. 605), `ac-`
`tivemq::commands::ActiveMQTempTopic` (p. 634), and `ac-`
`tivemq::commands::ActiveMQTopic` (p. 692).

6.318.4.2 `virtual void cms::Destination::copy (const cms::Destination & source) [pure virtual]`

Copies the contents of the given **Destination** (p. 1723) object to this one.

Parameters:

source The source **Destination** (p. 1723) object.

6.318.4.3 `virtual const CMSProperties& cms::Destination::getCMSProperties () const [pure virtual]`

Retrieve any properties that might be part of the destination that was specified. This is a deviation from the JMS spec but necessary due to C++ restrictions.

Returns:

A {const} reference to a **CMSProperties** (p. 1165) object.

Implemented in `activemq::commands::ActiveMQQueue` (p. 485),
`activemq::commands::ActiveMQTempQueue` (p. 606), `ac-`
`tivemq::commands::ActiveMQTempTopic` (p. 635), and `ac-`
`tivemq::commands::ActiveMQTopic` (p. 693).

6.318.4.4 `virtual DestinationType cms::Destination::getDestinationType () const [pure virtual]`

Retrieve the **Destination** (p. 1723) Type for this **Destination** (p. 1723).

Returns:

The **Destination** (p. 1723) Type

Implemented in `activemq::commands::ActiveMQQueue` (p. 485),
`activemq::commands::ActiveMQTempQueue` (p. 607), `ac-`
`tivemq::commands::ActiveMQTempTopic` (p. 636), and `ac-`
`tivemq::commands::ActiveMQTopic` (p. 693).

The documentation for this class was generated from the following file:

- `src/main/cms/Destination.h`

6.319 activemq::commands::ActiveMQDestination::DestinationFilter Struct Reference

```
#include <src/main/activemq/commands/ActiveMQDestination.h>
```

Static Public Attributes

- static const std::string **ANY_CHILD**
- static const std::string **ANY_DESCENDENT**

6.319.1 Field Documentation

6.319.1.1 const std::string
activemq::commands::ActiveMQDestination::DestinationFilter::ANY_
CHILD [static]

6.319.1.2 const std::string
activemq::commands::ActiveMQDestination::DestinationFilter::ANY_
DESCENDENT [static]

The documentation for this struct was generated from the following file:

- src/main/activemq/commands/**ActiveMQDestination.h**

6.320 activemq::commands::DestinationInfo Class Reference

#include <src/main/activemq/commands/DestinationInfo.h> Inheritance diagram for activemq::commands::DestinationInfo:

Public Member Functions

- **DestinationInfo** ()
- virtual **~DestinationInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **DestinationInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConnectionId** > & **getConnectionId** () const
- virtual **Pointer**< **ConnectionId** > & **getConnectionId** ()
- virtual void **setConnectionId** (const **Pointer**< **ConnectionId** > &connectionId)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual unsigned char **getOperationType** () const
- virtual void **setOperationType** (unsigned char operationType)
- virtual long long **getTimeout** () const
- virtual void **setTimeout** (long long timeout)
- virtual const std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** () const
- virtual std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** ()
- virtual void **setBrokerPath** (const std::vector< **decaf::lang::Pointer**< **BrokerId** > > &brokerPath)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_DESTINATIONINFO** = 8

Protected Attributes

- **Pointer< ConnectionId > connectionId**
- **Pointer< ActiveMQDestination > destination**
- unsigned char **operationType**
- long long **timeout**
- **std::vector< decaf::lang::Pointer< BrokerId > > brokerPath**

6.320.1 Constructor & Destructor Documentation

6.320.1.1 **activemq::commands::DestinationInfo::DestinationInfo ()**

6.320.1.2 **virtual activemq::commands::DestinationInfo::~~DestinationInfo ()**
[virtual]

6.320.2 Member Function Documentation

6.320.2.1 **virtual DestinationInfo* activemq::commands::DestinationInfo::cloneDataStructure ()**
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.320.2.2 **virtual void activemq::commands::DestinationInfo::copyDataStructure (const DataStructure * src)** [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.320.2.3 **virtual bool activemq::commands::DestinationInfo::equals (const DataStructure * value) const** [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

- 6.320.2.4 **virtual std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::DestinationInfo::getBrokerPath ()** [virtual]
- 6.320.2.5 **virtual const std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::DestinationInfo::getBrokerPath () const** [virtual]
- 6.320.2.6 **virtual Pointer<ConnectionId>& activemq::commands::DestinationInfo::getConnectionId ()** [virtual]
- 6.320.2.7 **virtual const Pointer<ConnectionId>& activemq::commands::DestinationInfo::getConnectionId () const** [virtual]
- 6.320.2.8 **virtual unsigned char activemq::commands::DestinationInfo::getDataStructureType () const** [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.320.2.9 `virtual Pointer<ActiveMQDestination>& activemq::commands::DestinationInfo::getDestination ()`
[virtual]
- 6.320.2.10 `virtual const Pointer<ActiveMQDestination>& activemq::commands::DestinationInfo::getDestination () const`
[virtual]
- 6.320.2.11 `virtual unsigned char activemq::commands::DestinationInfo::getOperationType ()`
const [virtual]
- 6.320.2.12 `virtual long long activemq::commands::DestinationInfo::getTimeout ()`
const [virtual]
- 6.320.2.13 `virtual void activemq::commands::DestinationInfo::setBrokerPath (const std::vector< decaf::lang::Pointer< BrokerId > > & brokerPath)`
[virtual]
- 6.320.2.14 `virtual void activemq::commands::DestinationInfo::setConnectionId (const Pointer< ConnectionId > & connectionId)` [virtual]
- 6.320.2.15 `virtual void activemq::commands::DestinationInfo::setDestination (const Pointer< ActiveMQDestination > & destination)` [virtual]
- 6.320.2.16 `virtual void activemq::commands::DestinationInfo::setOperationType (unsigned char operationType)` [virtual]
- 6.320.2.17 `virtual void activemq::commands::DestinationInfo::setTimeout (long long timeout)` [virtual]
- 6.320.2.18 `virtual std::string activemq::commands::DestinationInfo::toString ()`
const [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

- 6.320.2.19 `virtual Pointer<Command> activemq::commands::DestinationInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.320.3 Field Documentation

- 6.320.3.1** `std::vector< decaf::lang::Pointer<BrokerId> >`
`activemq::commands::DestinationInfo::brokerPath` [protected]
- 6.320.3.2** `Pointer<ConnectionId>` `activemq::commands::DestinationInfo::connectionId`
[protected]
- 6.320.3.3** `Pointer<ActiveMQDestination>` `activemq::commands::DestinationInfo::destination`
[protected]
- 6.320.3.4** `const unsigned char` `activemq::commands::DestinationInfo::ID_DESTINATIONINFO = 8` [static]
- 6.320.3.5** `unsigned char` `activemq::commands::DestinationInfo::operationType`
[protected]
- 6.320.3.6** `long long` `activemq::commands::DestinationInfo::timeout` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/DestinationInfo.h`

6.321 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1732).

#include <src/main/activemq/wireformat/openwire/marshal/v2/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual **~DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.321.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1732).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.321.2 Constructor & Destructor Documentation

6.321.2.1 `activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.321.2.2 `virtual activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.321.3 Member Function Documentation

6.321.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.321.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.321.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.321.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.321.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.321.3.6 virtual void activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.321.3.7 virtual void activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**DestinationInfoMarshaller.h**

6.322 activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1736).

#include <src/main/activemq/wireformat/openwire/marshal/v3/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual **~DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.322.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1736).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.322.2 Constructor & Destructor Documentation

6.322.2.1 `activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.322.2.2 `virtual activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.322.3 Member Function Documentation

6.322.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.322.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.322.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.322.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.322.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.322.3.6 virtual void activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.322.3.7 virtual void activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**DestinationInfoMarshaller.h**

6.323 activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1740).

#include <src/main/activemq/wireformat/openwire/marshal/v4/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual **~DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.323.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1740).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.323.2 Constructor & Destructor Documentation

6.323.2.1 `activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.323.2.2 `virtual activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.323.3 Member Function Documentation

6.323.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.323.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.323.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.323.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.323.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.323.3.6 virtual void activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.323.3.7 virtual void activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**DestinationInfoMarshaller.h**

6.324 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1744).

#include <src/main/activemq/wireformat/openwire/marshal/v1/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual **~DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.324.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1744).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.324.2 Constructor & Destructor Documentation

6.324.2.1 `activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.324.2.2 `virtual activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.324.3 Member Function Documentation

6.324.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.324.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.324.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.324.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.324.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.324.3.6 virtual void activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.324.3.7 virtual void activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**DestinationInfoMarshaller.h**

6.325 activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1748).

#include <src/main/activemq/wireformat/openwire/marshal/v6/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual **~DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.325.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1748).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.325.2 Constructor & Destructor Documentation

6.325.2.1 `activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.325.2.2 `virtual activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.325.3 Member Function Documentation

6.325.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.325.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.325.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.325.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.325.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.325.3.6 virtual void activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.325.3.7 virtual void activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**DestinationInfoMarshaller.h**

6.326 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DestinationInfoMarshaller** (p.1752).

#include <src/main/activemq/wireformat/openwire/marshal/v5/DestinationInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller:

Public Member Functions

- **DestinationInfoMarshaller** ()
- virtual ~**DestinationInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.326.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DestinationInfoMarshaller** (p.1752).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.326.2 Constructor & Destructor Documentation

6.326.2.1 `activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::DestinationInfoMarshaller()` [inline]

6.326.2.2 `virtual activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::~~DestinationInfoMarshaller()` [inline, virtual]

6.326.3 Member Function Documentation

6.326.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.326.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.326.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.326.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.326.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.326.3.6 virtual void activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.326.3.7 virtual void activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**DestinationInfoMarshaller.h**

6.327 activemq::cmsutil::DestinationResolver Class Reference

Resolves a CMS destination name to a `Destination`.

#include <src/main/activemq/cmsutil/DestinationResolver.h> Inheritance diagram for `activemq::cmsutil::DestinationResolver`:

Public Member Functions

- virtual `~DestinationResolver()`
- virtual void `init(ResourceLifecycleManager *mgr)=0`
Initializes this destination resolver for use.
- virtual void `destroy()`=0
Destroys any allocated resources.
- virtual `cms::Destination * resolveDestinationName(cms::Session *session, const std::string &destName, bool pubSubDomain)=0` throw (`cms::CMSException`)
Resolves the given name to a destination.

6.327.1 Detailed Description

Resolves a CMS destination name to a `Destination`.

6.327.2 Constructor & Destructor Documentation

6.327.2.1 virtual `activemq::cmsutil::DestinationResolver::~~DestinationResolver()` [inline, virtual]

6.327.3 Member Function Documentation

6.327.3.1 virtual void `activemq::cmsutil::DestinationResolver::destroy()` [pure virtual]

Destroys any allocated resources.

Implemented in `activemq::cmsutil::DynamicDestinationResolver` (p. 1822).

6.327.3.2 virtual void `activemq::cmsutil::DestinationResolver::init(ResourceLifecycleManager *mgr)` [pure virtual]

Initializes this destination resolver for use. Ensures that any previously allocated resources are first destroyed (e.g. calls `destroy()` (p. 1756)).

Parameters:

mgr the resource lifecycle manager.

Implemented in **activemq::cmsutil::DynamicDestinationResolver** (p. 1822).

6.327.3.3 `virtual cms::Destination* activemq::cmsutil::DestinationResolver::resolveDestinationName (cms::Session * session, const std::string & destName, bool pubSubDomain) throw (cms::CMSException) [pure virtual]`

Resolves the given name to a destination. If *pubSubDomain* is true, a topic will be returned, otherwise a queue will be returned.

Parameters:

session the session for which to retrieve resolve the destination.

destName the name to be resolved.

pubSubDomain If true, the name will be resolved to a Topic, otherwise a Queue.

Returns:

the resolved destination

Exceptions:

cms::CMSException (p. 1160) if resolution failed.

Implemented in **activemq::cmsutil::DynamicDestinationResolver** (p. 1822).

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/DestinationResolver.h`

6.328 activemq::commands::DiscoveryEvent Class Reference

#include <src/main/activemq/commands/DiscoveryEvent.h> Inheritance diagram for activemq::commands::DiscoveryEvent:

Public Member Functions

- **DiscoveryEvent** ()
- virtual **~DiscoveryEvent** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **DiscoveryEvent** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getServiceName** () const
- virtual std::string & **getServiceName** ()
- virtual void **setServiceName** (const std::string &serviceName)
- virtual const std::string & **getBrokerName** () const
- virtual std::string & **getBrokerName** ()
- virtual void **setBrokerName** (const std::string &brokerName)

Static Public Attributes

- static const unsigned char **ID_DISCOVERYEVENT** = 40

Protected Attributes

- std::string **serviceName**
- std::string **brokerName**

6.328.1 Constructor & Destructor Documentation

6.328.1.1 `activemq::commands::DiscoveryEvent::DiscoveryEvent ()`

6.328.1.2 `virtual activemq::commands::DiscoveryEvent::~~DiscoveryEvent ()`
[virtual]

6.328.2 Member Function Documentation

6.328.2.1 `virtual DiscoveryEvent* activemq::commands::DiscoveryEvent::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.328.2.2 `virtual void activemq::commands::DiscoveryEvent::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.328.2.3 `virtual bool activemq::commands::DiscoveryEvent::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

- 6.328.2.4 `virtual std::string& activemq::commands::DiscoveryEvent::getBrokerName ()`
[virtual]
- 6.328.2.5 `virtual const std::string& activemq::commands::DiscoveryEvent::getBrokerName ()`
`const` [virtual]
- 6.328.2.6 `virtual unsigned char activemq::commands::DiscoveryEvent::getDataSetType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSet** (p. 1660) type copy.

Implements **activemq::commands::DataSet** (p. 1662).

- 6.328.2.7 `virtual std::string& activemq::commands::DiscoveryEvent::getServiceName ()`
[virtual]
- 6.328.2.8 `virtual const std::string& activemq::commands::DiscoveryEvent::getServiceName ()`
`const` [virtual]
- 6.328.2.9 `virtual void activemq::commands::DiscoveryEvent::setBrokerName`
`(const std::string & brokerName)` [virtual]
- 6.328.2.10 `virtual void activemq::commands::DiscoveryEvent::setServiceName`
`(const std::string & serviceName)` [virtual]
- 6.328.2.11 `virtual std::string activemq::commands::DiscoveryEvent::toString ()`
`const` [virtual]

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataSet** (p. 833).

6.328.3 Field Documentation

- 6.328.3.1 `std::string activemq::commands::DiscoveryEvent::brokerName`
[protected]
- 6.328.3.2 `const unsigned char activemq::commands::DiscoveryEvent::ID_ -
DISCOVERYEVENT = 40` [static]
- 6.328.3.3 `std::string activemq::commands::DiscoveryEvent::serviceName`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/DiscoveryEvent.h`

6.329 activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1762).

#include <src/main/activemq/wireformat/openwire/marshal/v6/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.329.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1762).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.329.2 Constructor & Destructor Documentation

6.329.2.1 `activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` [inline]

6.329.2.2 `virtual activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` [inline, virtual]

6.329.3 Member Function Documentation

6.329.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.329.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.329.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.329.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.329.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.329.3.6 virtual void activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.329.3.7 virtual void activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/DiscoveryEventMarshaller.h

6.330 activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1766).

#include <src/main/activemq/wireformat/openwire/marshal/v2/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.330.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1766).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.330.2 Constructor & Destructor Documentation

6.330.2.1 `activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` `[inline]`

6.330.2.2 `virtual activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` `[inline, virtual]`

6.330.3 Member Function Documentation

6.330.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.330.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.330.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.330.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.330.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.330.3.6 virtual void activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.330.3.7 virtual void activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/DiscoveryEventMarshaller.h

6.331 activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1770).

#include <src/main/activemq/wireformat/openwire/marshal/v3/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.331.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1770).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.331.2 Constructor & Destructor Documentation

6.331.2.1 `activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` [inline]

6.331.2.2 `virtual activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` [inline, virtual]

6.331.3 Member Function Documentation

6.331.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.331.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.331.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.331.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.331.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.331.3.6 virtual void activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.331.3.7 virtual void activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/DiscoveryEventMarshaller.h

6.332 activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1774).

#include <src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.332.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1774).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.332.2 Constructor & Destructor Documentation

6.332.2.1 `activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` `[inline]`

6.332.2.2 `virtual activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` `[inline, virtual]`

6.332.3 Member Function Documentation

6.332.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.332.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.332.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.332.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.332.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.332.3.6 virtual void activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.332.3.7 virtual void activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryEventMarshaller.h

6.333 activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1778).

#include <src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.333.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1778).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.333.2 Constructor & Destructor Documentation

6.333.2.1 `activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` [inline]

6.333.2.2 `virtual activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` [inline, virtual]

6.333.3 Member Function Documentation

6.333.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.333.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.333.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.333.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.333.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.333.3.6 virtual void activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.333.3.7 virtual void activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryEventMarshaller.h

6.334 activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1782).

#include <src/main/activemq/wireformat/openwire/marshal/v5/DiscoveryEventMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller:

Public Member Functions

- **DiscoveryEventMarshaller** ()
- virtual **~DiscoveryEventMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.334.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **DiscoveryEventMarshaller** (p.1782).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.334.2 Constructor & Destructor Documentation

6.334.2.1 `activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::DiscoveryEventMarshaller()` [inline]

6.334.2.2 `virtual activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::~~DiscoveryEventMarshaller()` [inline, virtual]

6.334.3 Member Function Documentation

6.334.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.334.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.334.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.334.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.334.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.334.3.6 virtual void activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.334.3.7 virtual void activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/DiscoveryEventMarshaller.h

6.335 activemq::core::DispatchData Class Reference

Simple POCO that contains the information necessary to route a message to a specified consumer.

```
#include <src/main/activemq/core/DispatchData.h>
```

Public Member Functions

- **DispatchData** ()
- **DispatchData** (const decaf::lang::Pointer< commands::ConsumerId > &consumer, const decaf::lang::Pointer< commands::Message > &message)
- const decaf::lang::Pointer< commands::ConsumerId > & **getConsumerId** ()
- const decaf::lang::Pointer< commands::Message > & **getMessage** ()

6.335.1 Detailed Description

Simple POCO that contains the information necessary to route a message to a specified consumer.

6.335.2 Constructor & Destructor Documentation

6.335.2.1 **activemq::core::DispatchData::DispatchData** () [inline]

6.335.2.2 **activemq::core::DispatchData::DispatchData** (const decaf::lang::Pointer< commands::ConsumerId > & *consumer*, const decaf::lang::Pointer< commands::Message > & *message*) [inline]

6.335.3 Member Function Documentation

6.335.3.1 const decaf::lang::Pointer<commands::ConsumerId>& **activemq::core::DispatchData::getConsumerId** () [inline]

6.335.3.2 const decaf::lang::Pointer<commands::Message>& **activemq::core::DispatchData::getMessage** () [inline]

The documentation for this class was generated from the following file:

- src/main/activemq/core/**DispatchData.h**

6.336 activemq::core::Dispatcher Class Reference

Interface for an object responsible for dispatching messages to consumers.

#include <src/main/activemq/core/Dispatcher.h> Inheritance diagram for activemq::core::Dispatcher:

Public Member Functions

- virtual `~Dispatcher()`
- virtual void **dispatch** (const `Pointer< MessageDispatch >` &message)=0
Dispatches a message to a particular consumer.

6.336.1 Detailed Description

Interface for an object responsible for dispatching messages to consumers.

6.336.2 Constructor & Destructor Documentation

6.336.2.1 virtual `activemq::core::Dispatcher::~~Dispatcher()` [inline, virtual]

6.336.3 Member Function Documentation

6.336.3.1 virtual void `activemq::core::Dispatcher::dispatch` (const `Pointer< MessageDispatch >` & *message*) [pure virtual]

Dispatches a message to a particular consumer.

Parameters:

message - the message to be dispatched.

Implemented in `activemq::core::ActiveMQConsumer` (p. 314), and `activemq::core::ActiveMQSession` (p. 526).

The documentation for this class was generated from the following file:

- `src/main/activemq/core/Dispatcher.h`

6.337 decaf::lang::Double Class Reference

#include <src/main/decaf/lang/Double.h> Inheritance diagram for decaf::lang::Double:

Public Member Functions

- **Double** (double value)
- **Double** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Double** ()
- virtual int **compareTo** (const **Double** &d) const
*Compares this **Double** (p. 1788) instance with another.*
- bool **equals** (const **Double** &d) const
- virtual bool **operator==** (const **Double** &d) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Double** &d) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const double &d) const
*Compares this **Double** (p. 1788) instance with another.*
- bool **equals** (const double &d) const
- virtual bool **operator==** (const double &d) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const double &d) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const

Answers the long value which the receiver represents.

- bool **isInfinite** () const
- bool **isNaN** () const

Static Public Member Functions

- static int **compare** (double d1, double d2)
Compares the two specified double values.
- static long long **doubleToLongBits** (double value)
Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "double format" bit layout.
- static long long **doubleToRawLongBits** (double value)
Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "double format" bit layout, preserving Not-a-Number (NaN) values.
- static bool **isInfinite** (double value)
- static bool **isNaN** (double value)
- static double **longBitsToDouble** (long long bits)
Returns the double value corresponding to a given bit representation.
- static double **parseDouble** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a new double initialized to the value represented by the specified string, as performed by the valueOf method of class **Double** (p. 1788).*
- static std::string **toHexString** (double value)
Returns a hexadecimal string representation of the double argument.
- static std::string **toString** (double value)
Returns a string representation of the double argument.
- static **Double** **valueOf** (double value)
*Returns a **Double** (p. 1788) instance representing the specified double value.*
- static **Double** **valueOf** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a **Double** (p. 1788) instance that wraps a primitive double which is parsed from the string value passed.*

Static Public Attributes

- static const int **SIZE** = 64
The size in bits of the primitive int type.
- static const double **MAX_VALUE**
The maximum value that the primitive type can hold.

- static const double **MIN_VALUE**
The minimum value that the primitive type can hold.
- static const double **NaN**
*Constant for the Not a **Number** (p. 2835) Value.*
- static const double **POSITIVE_INFINITY**
Constant for Positive Infinity.
- static const double **NEGATIVE_INFINITY**
Constant for Negative Infinity.

6.337.1 Constructor & Destructor Documentation

6.337.1.1 `decaf::lang::Double::Double (double value)`

Parameters:

value - the primitive type to wrap

6.337.1.2 `decaf::lang::Double::Double (const std::string & value) throw (exceptions::NumberFormatException)`

Parameters:

value - the string to convert to a primitive type to wrap

6.337.1.3 `virtual decaf::lang::Double::~~Double () [inline, virtual]`

6.337.2 Member Function Documentation

6.337.2.1 `virtual unsigned char decaf::lang::Double::byteValue () const [inline, virtual]`

Answers the byte value which the receiver represents.

Returns:

byte the value of the receiver.

Reimplemented from `decaf::lang::Number` (p. 2835).

6.337.2.2 `static int decaf::lang::Double::compare (double d1, double d2) [static]`

Compares the two specified double values. The sign of the integer value returned is the same as that of the integer that would be returned by the call: `new Double(d1).compareTo(new Double(d2))`

Parameters:

d1 - the first double to compare
d2 - the second double to compare

Returns:

the value 0 if d1 is numerically equal to d2; a value less than 0 if d1 is numerically less than d2; and a value greater than 0 if d1 is numerically greater than d2.

6.337.2.3 virtual int decaf::lang::Double::compareTo (const double & d) const
[virtual]

Compares this **Double** (p. 1788) instance with another.

Parameters:

d - the **Double** (p. 1788) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements **decaf::lang::Comparable**< double > (p. 1214).

6.337.2.4 virtual int decaf::lang::Double::compareTo (const Double & d) const
[virtual]

Compares this **Double** (p. 1788) instance with another.

Parameters:

d - the **Double** (p. 1788) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.337.2.5 static long long decaf::lang::Double::doubleToLongBits (double value)
[static]

Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "double format" bit layout. Bit 63 (the bit that is selected by the mask 0x8000000000000000L) represents the sign of the floating-point number. Bits 62-52 (the bits that are selected by the mask 0x7ff0000000000000L) represent the exponent. Bits 51-0 (the bits that are selected by the mask 0x000fffffffffffffL) represent the significand (sometimes called the mantissa) of the floating-point number.

If the argument is positive infinity, the result is 0x7ff0000000000000L. If the argument is negative infinity, the result is 0xfff0000000000000L. If the argument is NaN, the result is 0x7ff8000000000000L.

In all cases, the result is a long integer that, when given to the `longBitsToDouble(long)` method, will produce a floating-point value the same as the argument to `doubleToLongBits` (except all NaN values are collapsed to a single "canonical" NaN value).

Parameters:

value - double to be converted

Returns:

the long long bits that make up the double

6.337.2.6 `static long long decaf::lang::Double::doubleToRawLongBits (double value) [static]`

Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "double format" bit layout, preserving Not-a-Number (NaN) values. Bit 63 (the bit that is selected by the mask 0x8000000000000000LL) represents the sign of the floating-point number. Bits 62-52 (the bits that are selected by the mask 0x7ff0000000000000L) represent the exponent. Bits 51-0 (the bits that are selected by the mask 0x000fffffffffffL) represent the significand (sometimes called the mantissa) of the floating-point number.

If the argument is positive infinity, the result is 0x7ff0000000000000LL. If the argument is negative infinity, the result is 0xfff0000000000000LL. If the argument is NaN, the result is the long integer representing the actual NaN value. Unlike the `doubleToLongBits` method, `doubleToRawLongBits` does not collapse all the bit patterns encoding a NaN to a single "canonical" NaN value.

In all cases, the result is a long integer that, when given to the `longBitsToDouble(long)` method, will produce a floating-point value the same as the argument to `doubleToRawLongBits`.

Parameters:

value - double to be converted

Returns:

the long long bits that make up the double

6.337.2.7 `virtual double decaf::lang::Double::doubleValue () const [inline, virtual]`

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements `decaf::lang::Number` (p. 2836).

6.337.2.8 `bool decaf::lang::Double::equals (const double & d) const` [inline, virtual]

Parameters:

d - the **Double** (p. 1788) object to compare against.

Returns:

true if the two **Double** (p. 1788) Objects have the same value.

Implements **decaf::lang::Comparable< double >** (p. 1215).

6.337.2.9 `bool decaf::lang::Double::equals (const Double & d) const` [inline]

Parameters:

d - the **Double** (p. 1788) object to compare against.

Returns:

true if the two **Double** (p. 1788) Objects have the same value.

6.337.2.10 `virtual float decaf::lang::Double::floatValue () const` [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.337.2.11 `virtual int decaf::lang::Double::intValue () const` [inline, virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.337.2.12 `static bool decaf::lang::Double::isInfinite (double value)` [static]

Parameters:

value - The double to check.

Returns:

true if the double is equal to infinity.

6.337.2.13 `bool decaf::lang::Double::isInfinite () const`**Returns:**

true if the double is equal to positive infinity.

6.337.2.14 `static bool decaf::lang::Double::isNaN (double value) [static]`**Parameters:**

value - The double to check.

Returns:

true if the double is equal to NaN.

6.337.2.15 `bool decaf::lang::Double::isNaN () const`**Returns:**

true if the double is equal to NaN.

6.337.2.16 `static double decaf::lang::Double::longBitsToDouble (long long bits) [static]`

Returns the double value corresponding to a given bit representation. The argument is considered to be a representation of a floating-point value according to the IEEE 754 floating-point "double format" bit layout.

If the argument is 0x7ff0000000000000L, the result is positive infinity. If the argument is 0xfff0000000000000L, the result is negative infinity. If the argument is any value in the range 0x7ff0000000000001L through 0x7fffffffffffffffL or in the range 0xfff0000000000001L through 0xfffffffffffffffL, the result is a NaN. No IEEE 754 floating-point operation provided by C++ can distinguish between two NaN values of the same type with different bit patterns. Distinct values of NaN are only distinguishable by use of the **Double.doubleToRawLongBits** (p. 1792) method.

Parameters:

bits - the long long bits to convert to double

Returns:

the double converted from the bits

6.337.2.17 `virtual long long decaf::lang::Double::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.337.2.18 `virtual bool decaf::lang::Double::operator< (const double & d) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

d - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< double >` (p.1215).

6.337.2.19 `virtual bool decaf::lang::Double::operator< (const Double & d) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

d - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.337.2.20 `virtual bool decaf::lang::Double::operator== (const double & d) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

d - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< double >` (p.1215).

6.337.2.21 `virtual bool decaf::lang::Double::operator== (const Double & d) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

d - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.337.2.22 `static double decaf::lang::Double::parseDouble (const std::string value)
throw (exceptions::NumberFormatException) [static]`

Returns a new double initialized to the value represented by the specified string, as performed by the `valueOf` method of class **Double** (p.1788).

Parameters:

value - The string to parse to an double

Returns:

a double parsed from the passed string

Exceptions:

NumberFormatException

6.337.2.23 `virtual short decaf::lang::Double::shortValue () const [inline, virtual]`

Answers the short value which the receiver represents.

Returns:

short the value of the receiver.

Reimplemented from `decaf::lang::Number` (p.2837).

6.337.2.24 `static std::string decaf::lang::Double::toHexString (double value)
[static]`

Returns a hexadecimal string representation of the double argument. All characters mentioned below are ASCII characters.

* If the argument is NaN, the result is the string "NaN". * Otherwise, the result is a string that represents the sign and magnitude (absolute value) of the argument. If the sign is negative, the first character of the result is '-'; if the sign is positive, no sign character appears in the result. As for the magnitude m: o If m is infinity, it is represented by the string "Infinity"; thus, positive infinity produces the result "Infinity" and negative infinity produces the result "-Infinity". o If m is zero, it is represented by the string "0x0.0p0"; thus, negative zero produces the result "-0x0.0p0" and positive zero produces the result "0x0.0p0". o If m is a double value with a normalized representation, substrings are used to represent the significand and exponent fields. The significand is represented by the characters "0x1." followed by a lowercase hexadecimal representation of the rest of the significand as a fraction. Trailing zeros in the hexadecimal representation are removed unless all the digits are zero, in which case a single zero is used. Next, the exponent is represented by "p" followed by a decimal string of the unbiased exponent as if produced by a call to **Integer.toString** (p.2089) on the exponent value. o If m is a double value with a subnormal representation, the significand is represented by the characters "0x0." followed by a hexadecimal representation of the rest of the significand as a fraction. Trailing zeros in the hexadecimal representation are removed. Next, the exponent is represented by "p-126". Note that there must be at least one nonzero digit in a subnormal significand.

Parameters:

value - The double to convert to a string

Returns:

the Hex formatted double string.

6.337.2.25 static std::string decaf::lang::Double::toString (double *value*) [static]

Returns a string representation of the double argument. All characters mentioned below are ASCII characters.

If the argument is NaN, the result is the string "NaN". Otherwise, the result is a string that represents the sign and magnitude (absolute value) of the argument. If the sign is negative, the first character of the result is '-'; if the sign is positive, no sign character appears in the result. As for the magnitude *m*:
 o If *m* is infinity, it is represented by the characters "Infinity"; thus, positive infinity produces the result "Infinity" and negative infinity produces the result "-Infinity".
 o If *m* is zero, it is represented by the characters "0.0"; thus, negative zero produces the result "-0.0" and positive zero produces the result "0.0".
 o If *m* is greater than or equal to 10⁻³ but less than 10⁷, then it is represented as the integer part of *m*, in decimal form with no leading zeroes, followed by '.', followed by one or more decimal digits representing the fractional part of *m*.
 o If *m* is less than 10⁻³ or greater than or equal to 10⁷, then it is represented in so-called "computerized scientific notation." Let *n* be the unique integer such that 10^{*n*} ≤ *m* < 10^{*n*+1}; then let *a* be the mathematically exact quotient of *m* and 10^{*n*} so that 1 ≤ *a* < 10. The magnitude is then represented as the integer part of *a*, as a single decimal digit, followed by '.', followed by decimal digits representing the fractional part of *a*, followed by the letter 'E', followed by a representation of *n* as a decimal integer, as produced by the method **Integer.toString(int)** (p. 2089).

Parameters:

value - The double to convert to a string

Returns:

the formatted double string.

6.337.2.26 std::string decaf::lang::Double::toString () const**Returns:**

this **Double** (p. 1788) Object as a **String** (p. 3665) Representation

6.337.2.27 static Double decaf::lang::Double::valueOf (const std::string & *value*) throw (exceptions::NumberFormatException) [static]

Returns a **Double** (p. 1788) instance that wraps a primitive double which is parsed from the string value passed.

Parameters:

value - the string to parse

Returns:

a new **Double** (p. 1788) instance wrapping the double parsed from value

Exceptions:

NumberFormatException on error.

6.337.2.28 `static Double decaf::lang::Double::valueOf (double value)` [static]

Returns a **Double** (p. 1788) instance representing the specified double value.

Parameters:

value - double to wrap

Returns:

new **Double** (p. 1788) instance wrapping the primitive value

6.337.3 **Field Documentation****6.337.3.1** `const double decaf::lang::Double::MAX_VALUE` [static]

The maximum value that the primitive type can hold.

6.337.3.2 `const double decaf::lang::Double::MIN_VALUE` [static]

The minimum value that the primitive type can hold.

6.337.3.3 `const double decaf::lang::Double::NaN` [static]

Constant for the Not a **Number** (p. 2835) Value.

6.337.3.4 `const double decaf::lang::Double::NEGATIVE_INFINITY` [static]

Constant for Negative Infinity.

6.337.3.5 `const double decaf::lang::Double::POSITIVE_INFINITY` [static]

Constant for Positive Infinity.

6.337.3.6 `const int decaf::lang::Double::SIZE = 64` [static]

The size in bits of the primitive int type.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Double.h`

6.338 decaf::internal::nio::DoubleArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/DoubleArrayBuffer.h> Inheritance diagram for decaf::internal::nio::DoubleArrayBuffer:

Public Member Functions

- **DoubleArrayBuffer** (int capacity, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **DoubleArrayBuffer** (p. 1799) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **DoubleArrayBuffer** (double *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **DoubleArrayBuffer** (p. 1799) object that wraps the given array.*

- **DoubleArrayBuffer** (const decaf::lang::Pointer< **ByteArrayAdapter** > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a byte buffer that wraps the passed **ByteArrayAdapter** and start at the given offset.*

- **DoubleArrayBuffer** (const **DoubleArrayBuffer** &other)

*Create a **DoubleArrayBuffer** (p. 1799) that mirrors this one, meaning it shares a reference to this buffers **ByteArrayAdapter** and when changes are made to that data it is reflected in both.*

- virtual ~**DoubleArrayBuffer** ()
- virtual double * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the double array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

*Invoke the **hasArray** method before invoking this method in order to ensure that this buffer has an accessible backing array.*

Returns:

*the array that backs this **Buffer** (p. 928).*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

*Invoke the **hasArray** method before invoking this method in order to ensure that this buffer has an accessible backing array.*

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual **DoubleBuffer * asReadOnlyBuffer () const**

Creates a new, read-only double buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only double buffer which the caller then owns.

- virtual **DoubleBuffer & compact () throw (decaf::nio::ReadOnlyBufferException)**

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

*a reference to this **DoubleBuffer** (p. 1809).*

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **DoubleBuffer * duplicate ()**

Creates a new double buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*a new double **Buffer** (p. 928) which the caller owns.*

- virtual double **get () throw (decaf::nio::BufferUnderflowException)**

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the double at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

- virtual double **get** (int index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the double is to be read.

Returns:

the double that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible double array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual DoubleBuffer & **put** (double value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given doubles into this buffer at the current position, and then increments the position.

Parameters:

value The doubles value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual DoubleBuffer & **put** (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given doubles into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The doubles to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or the index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual `DoubleBuffer * slice () const`

*Creates a new **DoubleBuffer** (p. 1809) whose content is a shared subsequence of this buffer's content.*

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the newly create **DoubleBuffer** (p. 1809) which the caller owns.*

Protected Member Functions

- virtual void `setReadOnly (bool value)`

*Sets this **DoubleArrayBuffer** (p. 1799) as Read-Only or not Read-Only.*

6.338.1 Constructor & Destructor Documentation

6.338.1.1 `decaf::internal::nio::DoubleArrayBuffer::DoubleArrayBuffer (int capacity, bool readOnly = false) throw (decaf::lang::exceptions::IllegalArgumentException)`

Creates a **DoubleArrayBuffer** (p. 1799) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.338.1.2 `decaf::internal::nio::DoubleArrayBuffer::DoubleArrayBuffer (double * array, int size, int offset, int length, bool readOnly = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)`

Creates a **DoubleArrayBuffer** (p. 1799) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.338.1.3 decaf::internal::nio::DoubleArrayBuffer::DoubleArrayBuffer (const decaf::lang::Pointer< ByteArrayAdapter > & array, int offset, int length, bool readOnly = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset. The capacity and limit of the new **DoubleArrayBuffer** (p.1799) will be that of the remaining capacity of the passed buffer.

Parameters:

array The ByteArrayAdapter to wrap.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if array is NULL

IndexOutOfBoundsException if offset + length is greater than array size.

6.338.1.4 decaf::internal::nio::DoubleArrayBuffer::DoubleArrayBuffer (const DoubleArrayBuffer & other)

Create a **DoubleArrayBuffer** (p.1799) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.

Parameters:

other The **DoubleArrayBuffer** (p.1799) this one is to mirror.

6.338.1.5 virtual decaf::internal::nio::DoubleArrayBuffer::~~DoubleArrayBuffer () [virtual]

6.338.2 Member Function Documentation

6.338.2.1 virtual double* decaf::internal::nio::DoubleArrayBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException) [virtual]

Returns the double array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::DoubleBuffer** (p. 1812).

6.338.2.2 `virtual int decaf::internal::nio::DoubleArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::DoubleBuffer** (p. 1812).

6.338.2.3 `virtual DoubleBuffer* decaf::internal::nio::DoubleArrayBuffer::asReadOnlyBuffer ()
const [virtual]`

Creates a new, read-only double buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only double buffer which the caller then owns.

Implements **decaf::nio::DoubleBuffer** (p. 1813).

**6.338.2.4 virtual DoubleBuffer& decaf::internal::nio::DoubleArrayBuffer::compact
() throw (decaf::nio::ReadOnlyBufferException) [virtual]**

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **DoubleBuffer** (p. 1809).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::DoubleBuffer** (p. 1813).

**6.338.2.5 virtual DoubleBuffer* decaf::internal::nio::DoubleArrayBuffer::duplicate
() [virtual]**

Creates a new double buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new double **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::DoubleBuffer** (p. 1813).

**6.338.2.6 virtual double decaf::internal::nio::DoubleArrayBuffer::get (int *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]**

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the double is to be read.

Returns:

the double that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

Implements **decaf::nio::DoubleBuffer** (p. 1815).

6.338.2.7 virtual double decaf::internal::nio::DoubleArrayBuffer::get () throw (decaf::nio::BufferUnderflowException) [virtual]

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the double at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implements **decaf::nio::DoubleBuffer** (p. 1815).

6.338.2.8 virtual bool decaf::internal::nio::DoubleArrayBuffer::hasArray () const [inline, virtual]

Tells whether or not this buffer is backed by an accessible double array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implements **decaf::nio::DoubleBuffer** (p. 1815).

6.338.2.9 virtual bool decaf::internal::nio::DoubleArrayBuffer::isReadOnly () const [inline, virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.338.2.10 virtual DoubleBuffer& decaf::internal::nio::DoubleArrayBuffer::put (int *index*, double *value*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given doubles into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The doubles to write.

Returns:

a reference to this buffer

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or the index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::DoubleBuffer** (p. 1816).

6.338.2.11 `virtual DoubleBuffer& decaf::internal::nio::DoubleArrayBuffer::put (double value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes the given doubles into this buffer at the current position, and then increments the position.

Parameters:

value The doubles value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::DoubleBuffer** (p. 1816).

6.338.2.12 `virtual void decaf::internal::nio::DoubleArrayBuffer::setReadOnly (bool value) [inline, protected, virtual]`

Sets this **DoubleArrayBuffer** (p. 1799) as Read-Only or not Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.338.2.13 `virtual DoubleBuffer* decaf::internal::nio::DoubleArrayBuffer::slice () const [virtual]`

Creates a new **DoubleBuffer** (p. 1809) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **DoubleBuffer** (p. 1809) which the caller owns.

Implements **decaf::nio::DoubleBuffer** (p. 1818).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/DoubleArrayBuffer.h`

6.339 decaf::nio::DoubleBuffer Class Reference

This class defines four categories of operations upon double buffers:

#include <src/main/decaf/nio/DoubleBuffer.h> Inheritance diagram for decaf::nio::DoubleBuffer:

Public Member Functions

- virtual **~DoubleBuffer** ()
- virtual std::string **toString** () const
- virtual double * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the double array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **DoubleBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only double buffer that shares this buffer's content.
- virtual **DoubleBuffer** & **compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **DoubleBuffer** * **duplicate** ()=0
Creates a new double buffer that shares this buffer's content.
- virtual double **get** ()=0 throw (BufferUnderflowException)
Relative get method.
- virtual double **get** (int index) const =0 throw (lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **DoubleBuffer** & **get** (std::vector< double > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **DoubleBuffer** & **get** (double *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible double array.
- **DoubleBuffer** & **put** (**DoubleBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the doubles remaining in the given source buffer into this buffer.

- **DoubleBuffer** & **put** (const double *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers doubles into this buffer from the given source array.

- **DoubleBuffer** & **put** (std::vector< double > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source doubles array into this buffer.

- virtual **DoubleBuffer** & **put** (double value)=0 throw (BufferOverflowException, ReadOnlyBufferException)

Writes the given doubles into this buffer at the current position, and then increments the position.

- virtual **DoubleBuffer** & **put** (int index, double value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)

Writes the given doubles into this buffer at the given index.

- virtual **DoubleBuffer** * **slice** () const =0

*Creates a new **DoubleBuffer** (p. 1809) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **DoubleBuffer** &value) const

- virtual bool **equals** (const **DoubleBuffer** &value) const

- virtual bool **operator==** (const **DoubleBuffer** &value) const

- virtual bool **operator<** (const **DoubleBuffer** &value) const

Static Public Member Functions

- static **DoubleBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

*Allocates a new **DoubleBuffer** (p. 1809).*

- static **DoubleBuffer** * **wrap** (double *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **DoubleBuffer** (p. 1809).*

- static **DoubleBuffer** * **wrap** (std::vector< double > &buffer)

*Wraps the passed STL double Vector in a **DoubleBuffer** (p. 1809).*

Protected Member Functions

- **DoubleBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **DoubleBuffer** (p. 1809) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.339.1 Detailed Description

This class defines four categories of operations upon double buffers:

- o Absolute and relative get and put methods that read and write single doubles;
- o Relative bulk get methods that transfer contiguous sequences of doubles from this buffer into an array; and
- o Relative bulk put methods that transfer contiguous sequences of doubles from a double array or some other double buffer into this buffer

 o Methods for compacting, duplicating, and slicing a double buffer.

Double buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing double array into a buffer, or by creating a view of an existing byte buffer

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained.

Since:

1.0

6.339.2 Constructor & Destructor Documentation

6.339.2.1 decaf::nio::DoubleBuffer::DoubleBuffer (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **DoubleBuffer** (p. 1809) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size and limit of the **Buffer** (p. 928) in doubles

Exceptions:

IllegalArgumentException if capacity is negative.

6.339.2.2 virtual decaf::nio::DoubleBuffer::~~DoubleBuffer () [inline, virtual]

6.339.3 Member Function Documentation

6.339.3.1 static DoubleBuffer* decaf::nio::DoubleBuffer::allocate (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new **DoubleBuffer** (p. 1809). The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Double buffer in doubles.

Returns:

the **DoubleBuffer** (p. 1809) that was allocated, caller owns.

Exceptions:

IllegalArgumentException is the capacity value is negative.

6.339.3.2 `virtual double* decaf::nio::DoubleBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the double array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::DoubleArrayBuffer` (p. 1803).

6.339.3.3 `virtual int decaf::nio::DoubleBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::DoubleArrayBuffer` (p. 1804).

6.339.3.4 virtual DoubleBuffer* decaf::nio::DoubleBuffer::asReadOnlyBuffer () const [pure virtual]

Creates a new, read-only double buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only double buffer which the caller then owns.

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1804).

6.339.3.5 virtual DoubleBuffer& decaf::nio::DoubleBuffer::compact () throw (ReadOnlyBufferException) [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **DoubleBuffer** (p. 1809).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1805).

6.339.3.6 virtual int decaf::nio::DoubleBuffer::compareTo (const DoubleBuffer & value) const [virtual]

6.339.3.7 virtual DoubleBuffer* decaf::nio::DoubleBuffer::duplicate () [pure virtual]

Creates a new double buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new double **Buffer** (p. 928) which the caller owns.

Implemented in `decaf::internal::nio::DoubleArrayBuffer` (p. 1805).

6.339.3.8 `virtual bool decaf::nio::DoubleBuffer::equals (const DoubleBuffer & value) const` [virtual]

6.339.3.9 `DoubleBuffer& decaf::nio::DoubleBuffer::get (double * buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)`

Relative bulk get method. This method transfers doubles from this buffer into the given destination array. If there are fewer doubles remaining in the buffer than are required to satisfy the request, that is, if `length > remaining()` (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies `length` doubles from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by `length`.

Parameters:

buffer The pointer to an allocated buffer to fill.
size The size of the buffer passed.
offset The position in the buffer to start filling.
length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than `length` doubles remaining in this buffer
NullPointerException if the passed buffer is null.
IndexOutOfBoundsException if the preconditions of `size`, `offset`, or `length` are not met.

6.339.3.10 `DoubleBuffer& decaf::nio::DoubleBuffer::get (std::vector< double > buffer) throw (BufferUnderflowException)`

Relative bulk get method. This method transfers values from this buffer into the given destination vector. An invocation of this method of the form `src.get(a)` behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call `buffer.resize(N)` before calling this get method.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than `length` doubles remaining in this buffer

6.339.3.11 virtual double decaf::nio::DoubleBuffer::get (int *index*) const throw (lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the double is to be read.

Returns:

the double that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1805).

6.339.3.12 virtual double decaf::nio::DoubleBuffer::get () throw (BufferUnderflowException) [pure virtual]

Relative get method. Reads the value at this buffer's current position, and then increments the position.

Returns:

the double at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1806).

6.339.3.13 virtual bool decaf::nio::DoubleBuffer::hasArray () const [pure virtual]

Tells whether or not this buffer is backed by an accessible double array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1806).

- 6.339.3.14** `virtual bool decaf::nio::DoubleBuffer::operator< (const DoubleBuffer & value) const` [virtual]
- 6.339.3.15** `virtual bool decaf::nio::DoubleBuffer::operator== (const DoubleBuffer & value) const` [virtual]
- 6.339.3.16** `virtual DoubleBuffer& decaf::nio::DoubleBuffer::put (int index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)` [pure virtual]

Writes the given doubles into this buffer at the given index.

Parameters:

- index* The position in the **Buffer** (p. 928) to write the data.
- value* The doubles to write.

Returns:

a reference to this buffer

Exceptions:

- IndexOutOfBoundsException* if index greater than the buffer's limit minus the size of the type being written, or the index is negative.
- ReadOnlyBufferException* (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::DoubleArrayBuffer` (p. 1806).

- 6.339.3.17** `virtual DoubleBuffer& decaf::nio::DoubleBuffer::put (double value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes the given doubles into this buffer at the current position, and then increments the position.

Parameters:

- value* The doubles value to be written.

Returns:

a reference to this buffer.

Exceptions:

- BufferOverflowException* (p. 954) if this buffer's current position is not smaller than its limit.
- ReadOnlyBufferException* (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::DoubleArrayBuffer` (p. 1807).

- 6.339.3.18** `DoubleBuffer& decaf::nio::DoubleBuffer::put (std::vector< double > & buffer) throw (BufferOverflowException, ReadOnlyBufferException)`

This method transfers the entire content of the given source doubles array into this buffer. This is the same as calling `put(&buffer[0], 0, buffer.size())`.

Parameters:

buffer The buffer whose contents are copied to this **DoubleBuffer** (p. 1809).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.339.3.19 DoubleBuffer& decaf::nio::DoubleBuffer::put (const double * *buffer*, int *size*, int *offset*, int *length*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers doubles into this buffer from the given source array. If there are more doubles to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no doubles are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `length` bytes from the given array into this buffer, starting at the given `offset` in the array and at the current position of this buffer. The position of this buffer is then incremented by `length`.

Parameters:

buffer The array from which doubles are to be read.

size The size of the buffer passed.

offset The offset within the array of the first char to be read.

length The number of doubles to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer

ReadOnlyBufferException (p. 3169) if this buffer is read-only

NullPointerException if the passed buffer is null.

IndexOutOfBoundsException if the preconditions of `size`, `offset`, or `length` are not met.

6.339.3.20 DoubleBuffer& decaf::nio::DoubleBuffer::put (DoubleBuffer & *src*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the doubles remaining in the given source buffer into this buffer. If there are more doubles remaining in the source buffer than in this buffer, that is, if `src.remaining() >`

remaining() (p. 933), then no doubles are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies $n = \text{src.remaining}()$ doubles from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by n .

Parameters:

src The buffer to take doubles from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer for the remaining doubles in the source buffer

IllegalArgumentException if the source buffer is this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.339.3.21 `virtual DoubleBuffer* decaf::nio::DoubleBuffer::slice () const` [pure virtual]

Creates a new **DoubleBuffer** (p. 1809) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **DoubleBuffer** (p. 1809) which the caller owns.

Implemented in **decaf::internal::nio::DoubleArrayBuffer** (p. 1807).

6.339.3.22 `virtual std::string decaf::nio::DoubleBuffer::toString () const` [virtual]

Returns:

a `std::string` describing this object

6.339.3.23 `static DoubleBuffer* decaf::nio::DoubleBuffer::wrap (std::vector< double > & buffer)` [static]

Wraps the passed STL double Vector in a **DoubleBuffer** (p. 1809). The new buffer will be backed by the given double array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new **DoubleBuffer** (p.1809) that is backed by *buffer*, caller owns.

6.339.3.24 `static DoubleBuffer* decaf::nio::DoubleBuffer::wrap
(double * array, int size, int offset, int length)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Wraps the passed buffer with a new **DoubleBuffer** (p.1809). The new buffer will be backed by the given double array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

array The array that will back the new buffer.

size The size of the passed in array.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new **DoubleBuffer** (p.1809) that is backed by *buffer*, caller owns.

Exceptions:

NullPointerException if the array pointer is NULL.

IndexOutOfBoundsException if the preconditions of *size*, *offset*, or *length* are not met.

The documentation for this class was generated from the following file:

- `src/main/decaf/nio/DoubleBuffer.h`

6.340 decaf::lang::DYNAMIC_CAST_TOKEN Struct Reference

```
#include <src/main/decaf/lang/Pointer.h>
```

The documentation for this struct was generated from the following file:

- `src/main/decaf/lang/Pointer.h`

6.341 activemq::cmsutil::DynamicDestinationResolver Class Reference

Resolves a CMS destination name to a `Destination`.

`#include <src/main/activemq/cmsutil/DynamicDestinationResolver.h>` Inheritance diagram for `activemq::cmsutil::DynamicDestinationResolver`:

Data Structures

- class `SessionResolver`

Manages maps of names to topics and queues for a single session.

Public Member Functions

- `DynamicDestinationResolver ()`
- `virtual ~DynamicDestinationResolver ()`
- `virtual void init (ResourceLifecycleManager *mgr)`

Initializes this destination resolver for use.

- `virtual void destroy ()`

Destroys any allocated resources.

- `virtual cms::Destination * resolveDestinationName (cms::Session *session, const std::string &destName, bool pubSubDomain) throw (cms::CMSEException)`

Resolves the given name to a destination.

Protected Member Functions

- `DynamicDestinationResolver (const DynamicDestinationResolver &)`
- `DynamicDestinationResolver & operator= (const DynamicDestinationResolver &)`

6.341.1 Detailed Description

Resolves a CMS destination name to a `Destination`.

6.341.2 Constructor & Destructor Documentation

- 6.341.2.1** `activemq::cmsutil::DynamicDestinationResolver::DynamicDestinationResolver (const DynamicDestinationResolver &) [inline, protected]`
- 6.341.2.2** `activemq::cmsutil::DynamicDestinationResolver::DynamicDestinationResolver ()`
- 6.341.2.3** `virtual
activemq::cmsutil::DynamicDestinationResolver::~~DynamicDestinationResolver
() [virtual]`

6.341.3 Member Function Documentation

- 6.341.3.1** `virtual void activemq::cmsutil::DynamicDestinationResolver::destroy () [virtual]`

Destroys any allocated resources.

Implements `activemq::cmsutil::DestinationResolver` (p. 1756).

- 6.341.3.2** `virtual void activemq::cmsutil::DynamicDestinationResolver::init (ResourceLifecycleManager * mgr) [inline, virtual]`

Initializes this destination resolver for use. Ensures that any previously allocated resources are first destroyed (e.g. calls `destroy()` (p. 1822)).

Parameters:

mgr the resource lifecycle manager.

Implements `activemq::cmsutil::DestinationResolver` (p. 1756).

- 6.341.3.3** `DynamicDestinationResolver& activemq::cmsutil::DynamicDestinationResolver::operator= (const DynamicDestinationResolver &) [inline, protected]`

- 6.341.3.4** `virtual cms::Destination* activemq::cmsutil::DynamicDestinationResolver::resolveDestinationName (cms::Session * session, const std::string & destName, bool pubSubDomain) throw (cms::CMSException) [virtual]`

Resolves the given name to a destination. If `pubSubDomain` is true, a topic will be returned, otherwise a queue will be returned.

Parameters:

session the session for which to retrieve resolve the destination.

destName the name to be resolved.

pubSubDomain If true, the name will be resolved to a Topic, otherwise a Queue.

Returns:

the resolved destination

Exceptions:

cms::CMSException (p. 1160) if resolution failed.

Implements **activemq::cmsutil::DestinationResolver** (p. 1757).

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/DynamicDestinationResolver.h`

6.342 decaf::util::Map< K, V, COMPARATOR >::Entry Class Reference

```
#include <src/main/decaf/util/Map.h>
```

Public Member Functions

- **Entry** ()
- virtual **~Entry** ()
- virtual const K & **getKey** () const =0
- virtual const V & **getValue** () const =0
- virtual void **setValue** (const V &value)=0

```
template<typename K, typename V, typename COMPARATOR = std::less<K>>
class decaf::util::Map< K, V, COMPARATOR >::Entry
```

6.342.1 Constructor & Destructor Documentation

6.342.1.1 `template<typename K, typename V, typename COMPARATOR = std::less<K>> decaf::util::Map< K, V, COMPARATOR >::Entry::Entry () [inline]`

6.342.1.2 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual decaf::util::Map< K, V, COMPARATOR >::Entry::~~Entry () [inline, virtual]`

6.342.2 Member Function Documentation

6.342.2.1 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual const K& decaf::util::Map< K, V, COMPARATOR >::Entry::getKey () const [pure virtual]`

6.342.2.2 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual const V& decaf::util::Map< K, V, COMPARATOR >::Entry::getValue () const [pure virtual]`

6.342.2.3 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::Map< K, V, COMPARATOR >::Entry::setValue (const V & value) [pure virtual]`

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Map.h`

6.343 decaf::io::EOFException Class Reference

#include <src/main/decaf/io/EOFException.h> Inheritance diagram for decaf::io::EOFException:

Public Member Functions

- **EOFException** () throw ()
Default Constructor.
- **EOFException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **EOFException** (const EOFException &ex) throw ()
Copy Constructor.
- **EOFException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **EOFException** (const std::exception *cause) throw ()
Constructor.
- **EOFException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **EOFException** * clone () const
Clones this exception.
- virtual ~**EOFException** () throw ()

6.343.1 Constructor & Destructor Documentation

6.343.1.1 decaf::io::EOFException::EOFException () throw () [inline]

Default Constructor.

6.343.1.2 decaf::io::EOFException::EOFException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.343.1.3 `decaf::io::EOFException::EOFException (const EOFException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.343.1.4 `decaf::io::EOFException::EOFException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.343.1.5 `decaf::io::EOFException::EOFException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.343.1.6 `decaf::io::EOFException::EOFException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.343.1.7 `virtual decaf::io::EOFException::~~EOFException () throw () [inline, virtual]`

6.343.2 Member Function Documentation

6.343.2.1 `virtual EOFException* decaf::io::EOFException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an Exception that is a copy of this one.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/EOFException.h`

6.344 decaf::util::logging::ErrorManager Class Reference

ErrorManager (p. 1828) objects can be attached to Handlers to process any error that occur on a **Handler** (p. 1978) during Logging.

```
#include <src/main/decaf/util/logging/ErrorManager.h>
```

Public Member Functions

- **ErrorManager** ()
- virtual **~ErrorManager** ()
- virtual void **error** (const std::string &message, **decaf::lang::Exception** *ex, int code)

*The error method is called when a **Handler** (p. 1978) failure occurs.*

Static Public Attributes

- static const int **GENERIC_FAILURE**
GENERIC_FAILURE is used for failure that don't fit into one of the other categories.
- static const int **WRITE_FAILURE**
WRITE_FAILURE is used when a write to an output stream fails.
- static const int **FLUSH_FAILURE**
FLUSH_FAILURE is used when a flush to an output stream fails.
- static const int **CLOSE_FAILURE**
CLOSE_FAILURE is used when a close of an output stream fails.
- static const int **OPEN_FAILURE**
OPEN_FAILURE is used when an open of an output stream fails.
- static const int **FORMAT_FAILURE**
FORMAT_FAILURE is used when formatting fails for any reason.

6.344.1 Detailed Description

ErrorManager (p. 1828) objects can be attached to Handlers to process any error that occur on a **Handler** (p. 1978) during Logging. When processing **logging** (p. 175) output, if a **Handler** (p. 1978) encounters problems then rather than throwing an Exception back to the issuer of the **logging** (p. 175) call (who is unlikely to be interested) the **Handler** (p. 1978) should call its associated **ErrorManager** (p. 1828).

Since:

1.0

6.344.2 Constructor & Destructor Documentation

6.344.2.1 `decaf::util::logging::ErrorManager::ErrorManager ()`

6.344.2.2 `virtual decaf::util::logging::ErrorManager::~~ErrorManager ()` [virtual]

6.344.3 Member Function Documentation

6.344.3.1 `virtual void decaf::util::logging::ErrorManager::error (const std::string & message, decaf::lang::Exception * ex, int code)` [virtual]

The error method is called when a **Handler** (p.1978) failure occurs. This method may be overridden in subclasses. The default behavior in this base class is that the first call is reported to System.err, and subsequent calls are ignored.

Parameters:

msg - a descriptive string (may be empty)

ex - an exception (may be NULL)

code (p. 1183) - an error **code** (p.1183) defined in **ErrorManager** (p.1828)

6.344.4 Field Documentation

6.344.4.1 `const int decaf::util::logging::ErrorManager::CLOSE_FAILURE`
[static]

CLOSE_FAILURE is used when a close of an output stream fails.

6.344.4.2 `const int decaf::util::logging::ErrorManager::FLUSH_FAILURE`
[static]

FLUSH_FAILURE is used when a flush to an output stream fails.

6.344.4.3 `const int decaf::util::logging::ErrorManager::FORMAT_FAILURE`
[static]

FORMAT_FAILURE is used when formatting fails for any reason.

6.344.4.4 `const int decaf::util::logging::ErrorManager::GENERIC_FAILURE`
[static]

GENERIC_FAILURE is used for failure that don't fit into one of the other categories.

6.344.4.5 `const int decaf::util::logging::ErrorManager::OPEN_FAILURE` [static]

OPEN_FAILURE is used when an open of an output stream fails.

6.344.4.6 `const int decaf::util::logging::ErrorManager::WRITE_FAILURE` [static]

WRITE_FAILURE is used when a write to an output stream fails.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/ErrorMessage.h`

6.345 decaf::lang::Exception Class Reference

#include <src/main/decaf/lang/Exception.h> Inheritance diagram for decaf::lang::Exception:

Public Member Functions

- **Exception** () throw ()
Default Constructor.
- **Exception** (const **Exception** &ex) throw ()
Copy Constructor.
- **Exception** (const std::exception ***cause**) throw ()
Constructor.
- **Exception** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **Exception** (const char *file, const int lineNumber, const std::exception ***cause**, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual ~**Exception** () throw ()
- virtual std::string **getMessage** () const
Gets the message for this exception.
- virtual const std::exception * **getCause** () const
*Gets the exception that caused this one to be thrown, this allows for chaining of **exceptions** (p. 159) in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.*
- virtual void **initCause** (const std::exception ***cause**)
Initializes the contained cause exception with the one given.
- virtual const char * **what** () const throw ()
Implement method from std::exception.
- virtual void **setMessage** (const char *msg,...)
Sets the cause for this exception.
- virtual void **setMark** (const char *file, const int lineNumber)
Adds a file/line number to the stack trace.
- virtual **Exception** * **clone** () const
Clones this exception.

- virtual `std::vector< std::pair< std::string, int > > getStackTrace () const`
Provides the stack trace for every point where this exception was caught, marked, and rethrown.
- virtual void `printStackTrace () const`
Prints the stack trace to `std::err`.
- virtual void `printStackTrace (std::ostream &stream) const`
Prints the stack trace to the given output stream.
- virtual `std::string getStackTraceString () const`
Gets the stack trace as one contiguous string.
- `Exception & operator= (const Exception &ex)`
Assignment operator.

Protected Member Functions

- virtual void `setStackTrace (const std::vector< std::pair< std::string, int > > &trace)`
- virtual void `buildMessage (const char *format, va_list &args)`

Protected Attributes

- `std::string message`
The cause of this exception.
- `std::exception * cause`
*The **Exception** (p. 1831) that caused this one to be thrown.*
- `std::vector< std::pair< std::string, int > > stackTrace`
The stack trace.

6.345.1 Constructor & Destructor Documentation

6.345.1.1 `decaf::lang::Exception::Exception () throw ()`

Default Constructor.

Referenced by `decaf::util::concurrent::BrokenBarrierException::BrokenBarrierException()`,
`decaf::util::concurrent::CancellationException::CancellationException()`,
`decaf::util::concurrent::ExecutionException::ExecutionException()`,
`decaf::net::HttpRetryException::HttpRetryException()`, `decaf::net::MalformedURLException::MalformedURLException()`,
`decaf::net::ProtocolException::ProtocolException()`, `decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException()`,
`decaf::net::SocketTimeoutException::SocketTimeoutException()`,
`decaf::util::concurrent::TimeoutException::TimeoutException()`,
`decaf::net::UnknownHostException::UnknownHostException()`, and `decaf::net::UnknownServiceException::UnknownServiceException()`.

6.345.1.2 decaf::lang::Exception::Exception (const Exception & *ex*) throw ()

Copy Constructor.

Parameters:

ex The Exception (p.1831) instance to copy.

6.345.1.3 decaf::lang::Exception::Exception (const std::exception * *cause*) throw ()

Constructor.

Parameters:

cause **Pointer** (p.2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.345.1.4 decaf::lang::Exception::Exception (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.345.1.5 decaf::lang::Exception::Exception (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw ()

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.345.1.6 virtual `decaf::lang::Exception::~~Exception () throw ()` [virtual]

6.345.2 Member Function Documentation

6.345.2.1 virtual void `decaf::lang::Exception::buildMessage (const char * format, va_list & vargs)` [protected, virtual]

Referenced by `decaf::lang::exceptions::NumberFormatException::NumberFormatException()`.

6.345.2.2 virtual `Exception* decaf::lang::Exception::clone () const` [virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

Copy of this **Exception** (p.1831) object

Implements **decaf::lang::Throwable** (p. 3784).

Reimplemented in **activemq::exceptions::ActiveMQException** (p. 358), **activemq::exceptions::BrokerException** (p. 867), **decaf::internal::net::ssl::openssl::OpenSSLSocketException** (p. 2873), **decaf::io::EOFException** (p. 1827), **decaf::io::InterruptedIOException** (p. 2129), **decaf::io::IOException** (p. 2144), **decaf::io::UnsupportedEncodingException** (p. 3915), **decaf::io::UTFDataFormatException** (p. 3968), **decaf::lang::exceptions::ClassCastException** (p. 1147), **decaf::lang::exceptions::IllegalArgumentException** (p. 1993), **decaf::lang::exceptions::IllegalMonitorStateException** (p. 1996), **decaf::lang::exceptions::IllegalStateException** (p. 2000), **decaf::lang::exceptions::IllegalThreadStateException** (p. 2003), **decaf::lang::exceptions::IndexOutOfBoundsException** (p. 2010), **decaf::lang::exceptions::InterruptedException** (p. 2126), **decaf::lang::exceptions::InvalidStateException** (p. 2141), **decaf::lang::exceptions::NoSuchElementException** (p. 2828), **decaf::lang::exceptions::NullPointerException** (p. 2834), **decaf::lang::exceptions::NumberFormatException** (p. 2840), **decaf::lang::exceptions::RuntimeException** (p. 3330), **decaf::lang::exceptions::UnsupportedOperationException** (p. 3918), **decaf::net::BindException** (p. 838), **decaf::net::ConnectException** (p. 1261), **decaf::net::HttpRetryException** (p. 1988), **decaf::net::MalformedURLException** (p. 2458), **decaf::net::NoRouteToHostException** (p. 2822), **decaf::net::PortUnreachableException** (p. 2975), **decaf::net::ProtocolException** (p. 3139), **decaf::net::SocketException** (p. 3522), **decaf::net::SocketTimeoutException** (p. 3544), **decaf::net::UnknownHostException** (p. 3909), **decaf::net::UnknownServiceException** (p. 3912), **decaf::net::URISyntaxException** (p. 3950), **decaf::nio::BufferOverflowException** (p. 956), **decaf::nio::BufferUnderflowException** (p. 959), **decaf::nio::InvalidMarkException** (p. 2137), **decaf::nio::ReadOnlyBufferException** (p. 3171), **decaf::security::cert::CertificateEncodingException** (p. 1091), **decaf::security::cert::CertificateException** (p. 1093), **decaf::security::cert::CertificateExpiredException** (p. 1095), **decaf::security::cert::CertificateNotYetValidException** (p. 1097), **decaf::security::cert::CertificateParsingException** (p. 1099), **decaf::security::GeneralSecurityException** (p. 1973), **de-**

caf::security::InvalidKeyException (p. 2134), **decaf::security::KeyException** (p. 2297),
decaf::security::KeyManagementException (p. 2300),
decaf::security::NoSuchAlgorithmException (p. 2825), **decaf::security::NoSuchProviderException** (p. 2831),
decaf::security::SignatureException (p. 3499), **decaf::util::concurrent::BrokenBarrierException** (p. 862),
decaf::util::concurrent::CancellationException (p. 1085), **decaf::util::concurrent::ExecutionException** (p. 1868),
decaf::util::concurrent::RejectedExecutionException (p. 3191),
decaf::util::concurrent::TimeoutException (p. 3789), **decaf::util::zip::DataFormatException** (p. 1557), and **decaf::util::zip::ZipException** (p. 4066).

6.345.2.3 virtual const std::exception* decaf::lang::Exception::getCause () const [inline, virtual]

Gets the exception that caused this one to be thrown, this allows for chaining of **exceptions** (p. 159) in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.

Returns:

a const pointer reference to the causal exception, if there was no cause associated with this exception then NULL is returned.

Implements **decaf::lang::Throwable** (p. 3785).

6.345.2.4 virtual std::string decaf::lang::Exception::getMessage () const [inline, virtual]

Gets the message for this exception.

Returns:

Text formatted error message

Implements **decaf::lang::Throwable** (p. 3785).

6.345.2.5 virtual std::vector< std::pair< std::string, int> > decaf::lang::Exception::getStackTrace () const [virtual]

Provides the stack trace for every point where this exception was caught, marked, and rethrown. The first item in the returned vector is the first point where the mark was set (e.g. where the exception was created).

Returns:

the stack trace.

Implements **decaf::lang::Throwable** (p. 3785).

6.345.2.6 `virtual std::string decaf::lang::Exception::getStackTraceString () const` [virtual]

Gets the stack trace as one contiguous string.

Returns:

string with formatted stack trace data

Implements **decaf::lang::Throwable** (p. 3786).

6.345.2.7 `virtual void decaf::lang::Exception::initCause (const std::exception * cause)` [virtual]

Initializes the contained cause exception with the one given. A copy is made to avoid ownership issues.

Parameters:

cause The exception that was the cause of this one.

Implements **decaf::lang::Throwable** (p. 3786).

6.345.2.8 `Exception& decaf::lang::Exception::operator= (const Exception & ex)`

Assignment operator.

Parameters:

ex const reference to another **Exception** (p. 1831)

6.345.2.9 `virtual void decaf::lang::Exception::printStackTrace (std::ostream & stream) const` [virtual]

Prints the stack trace to the given output stream.

Parameters:

stream the target output stream.

Implements **decaf::lang::Throwable** (p. 3786).

6.345.2.10 `virtual void decaf::lang::Exception::printStackTrace () const` [virtual]

Prints the stack trace to std::err.

Implements **decaf::lang::Throwable** (p. 3786).

6.345.2.11 `virtual void decaf::lang::Exception::setMark (const char * file, const int lineNumber)` [virtual]

Adds a file/line number to the stack trace.

Parameters:

file The name of the file calling this method (use `__FILE__`).

lineNumber The line number in the calling file (use `__LINE__`).

Implements **decaf::lang::Throwable** (p. 3786).

Referenced by `activemq::exceptions::BrokerException::BrokerException()`, and `decaf::lang::exceptions::NumberFormatException::NumberFormatException()`.

6.345.2.12 **virtual void decaf::lang::Exception::setMessage (const char * *msg*, ...)** [virtual]

Sets the cause for this exception.

Parameters:

msg the format string for the msg.

... params to format into the string

Referenced by `activemq::exceptions::BrokerException::BrokerException()`.

6.345.2.13 **virtual void decaf::lang::Exception::setStackTrace (const std::vector< std::pair< std::string, int > > & *trace*)** [protected, virtual]

6.345.2.14 **virtual const char* decaf::lang::Exception::what () const throw ()** [inline, virtual]

Implement method from `std::exception`.

Returns:

the const char* of `getMessage()` (p. 1835).

6.345.3 Field Documentation

6.345.3.1 **std::exception* decaf::lang::Exception::cause** [protected]

The **Exception** (p. 1831) that caused this one to be thrown.

6.345.3.2 **std::string decaf::lang::Exception::message** [protected]

The cause of this exception.

6.345.3.3 **std::vector< std::pair< std::string, int> > decaf::lang::Exception::stackTrace** [protected]

The stack trace.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Exception.h`

6.346 cms::ExceptionListener Class Reference

If a CMS provider detects a serious problem, it notifies the client application through an `ExceptionListener` (p. 1838) that is registered with the `Connection` (p. 1262).

```
#include <src/main/cms/ExceptionListener.h>
```

Public Member Functions

- virtual `~ExceptionListener ()`
- virtual void `onException (const cms::CMSException &ex)=0`
Called when an exception occurs.

6.346.1 Detailed Description

If a CMS provider detects a serious problem, it notifies the client application through an `ExceptionListener` (p. 1838) that is registered with the `Connection` (p. 1262). An exception listener allows a client to be notified of a problem asynchronously. Some connections only consume messages via the asynchronous event mechanism so they would have no other way to learn that their connection has failed.

Since:

1.0

6.346.2 Constructor & Destructor Documentation

6.346.2.1 virtual `cms::ExceptionListener::~ExceptionListener ()` [inline, virtual]

6.346.3 Member Function Documentation

6.346.3.1 virtual void `cms::ExceptionListener::onException (const cms::CMSException & ex)` [pure virtual]

Called when an exception occurs. Once notified of an exception the caller should no longer use the resource that generated the exception.

Parameters:

ex Exception Object that occurred.

The documentation for this class was generated from the following file:

- `src/main/cms/ExceptionListener.h`

6.347 activemq::commands::ExceptionResponse Class Reference

#include <src/main/activemq/commands/ExceptionResponse.h> Inheritance diagram for activemq::commands::ExceptionResponse:

Public Member Functions

- **ExceptionResponse** ()
- virtual **~ExceptionResponse** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ExceptionResponse * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **BrokerError** > & **getException** () const
- virtual **Pointer**< **BrokerError** > & **getException** ()
- virtual void **setException** (const **Pointer**< **BrokerError** > &exception)

Static Public Attributes

- static const unsigned char **ID_EXCEPTIONRESPONSE** = 31

Protected Attributes

- **Pointer**< **BrokerError** > **exception**

6.347.1 Constructor & Destructor Documentation

6.347.1.1 `activemq::commands::ExceptionResponse::ExceptionResponse ()`

6.347.1.2 `virtual activemq::commands::ExceptionResponse::~~ExceptionResponse () [virtual]`

6.347.2 Member Function Documentation

6.347.2.1 `virtual ExceptionResponse* activemq::commands::ExceptionResponse::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.347.2.2 `virtual void activemq::commands::ExceptionResponse::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::Response` (p. 3286).

6.347.2.3 `virtual bool activemq::commands::ExceptionResponse::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.347.2.4 `virtual unsigned char activemq::commands::ExceptionResponse::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from **activemq::commands::Response** (p. 3287).

6.347.2.5 `virtual Pointer<BrokerError>& activemq::commands::ExceptionResponse::getException ()`
[virtual]

6.347.2.6 `virtual const Pointer<BrokerError>& activemq::commands::ExceptionResponse::getException ()`
const [virtual]

6.347.2.7 `virtual void activemq::commands::ExceptionResponse::setException (const Pointer< BrokerError > & exception)` [virtual]

6.347.2.8 `virtual std::string activemq::commands::ExceptionResponse::toString ()`
const [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::Response** (p. 3287).

6.347.3 Field Documentation

6.347.3.1 `Pointer<BrokerError> activemq::commands::ExceptionResponse::exception`
[protected]

6.347.3.2 `const unsigned char activemq::commands::ExceptionResponse::ID_ - EXCEPTIONRESPONSE = 31` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ExceptionResponse.h`

6.348 activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1842).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.348.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1842).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.348.2 Constructor & Destructor Documentation

6.348.2.1 `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.348.2.2 `virtual
activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.348.3 Member Function Documentation

6.348.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller`
(p. 3321).

6.348.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller`
(p. 3321).

6.348.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.348.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.348.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.348.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3323).

6.348.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3324).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ExceptionResponseMarshaller.h

6.349 activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1846).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.349.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1846).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.349.2 Constructor & Destructor Documentation

6.349.2.1 `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.349.2.2 `virtual
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.349.3 Member Function Documentation

6.349.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller`
(p. 3301).

6.349.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller`
(p. 3301).

6.349.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.349.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.349.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.349.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3303).

6.349.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3304).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ExceptionResponseMarshaller.h

6.350 activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1850).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.350.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1850).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.350.2 Constructor & Destructor Documentation

6.350.2.1 `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.350.2.2 `virtual
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.350.3 Member Function Documentation

6.350.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller`
(p. 3311).

6.350.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller`
(p. 3311).

6.350.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.350.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.350.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.350.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p. 3313).

6.350.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p. 3314).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ExceptionResponseMarshaller.h

6.351 activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1854).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.351.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1854).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.351.2 Constructor & Destructor Documentation

6.351.2.1 `activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.351.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.351.3 Member Function Documentation

6.351.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller`
(p. 3306).

6.351.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller`
(p. 3306).

6.351.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.351.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.351.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.351.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3308).

6.351.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3309).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ExceptionResponseMarshaller.h**

6.352 activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1858).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.352.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1858).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.352.2 Constructor & Destructor Documentation

6.352.2.1 `activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.352.2.2 `virtual
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.352.3 Member Function Documentation

6.352.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller`
(p. 3296).

6.352.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller`
(p. 3296).

6.352.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.352.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.352.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.352.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3298).

6.352.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3299).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ExceptionResponseMarshaller.h

6.353 activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1862).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ExceptionResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller:

Public Member Functions

- **ExceptionResponseMarshaller** ()
- virtual **~ExceptionResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.353.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1862).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.353.2 Constructor & Destructor Documentation

6.353.2.1 `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::ExceptionRe
() [inline]`

6.353.2.2 `virtual
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::~~ExceptionR
() [inline, virtual]`

6.353.3 Member Function Documentation

6.353.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller`
(p. 3316).

6.353.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller`
(p. 3316).

6.353.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.353.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.353.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.353.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3318).

6.353.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3319).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/ExceptionResponseMarshaller.h

6.354 decaf::util::concurrent::ExecutionException Class Reference

#include <src/main/decaf/util/concurrent/ExecutionException.h> Inheritance diagram for decaf::util::concurrent::ExecutionException:

Public Member Functions

- **ExecutionException** () throw ()
Default Constructor.
- **ExecutionException** (const **decaf::lang::Exception** &ex) throw ()
Conversion Constructor from some other Exception.
- **ExecutionException** (const **ExecutionException** &ex) throw ()
Copy Constructor.
- **ExecutionException** (const std::exception *cause) throw ()
Constructor.
- **ExecutionException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ExecutionException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **ExecutionException** * clone () const
Clones this exception.
- virtual ~**ExecutionException** () throw ()

6.354.1 Constructor & Destructor Documentation

6.354.1.1 decaf::util::concurrent::ExecutionException::ExecutionException () throw () [inline]

Default Constructor.

6.354.1.2 decaf::util::concurrent::ExecutionException::ExecutionException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex - An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.354.1.3 decaf::util::concurrent::ExecutionException::ExecutionException (const ExecutionException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex - The Exception to copy in this new instance.

References decaf::lang::Exception::Exception().

6.354.1.4 decaf::util::concurrent::ExecutionException::ExecutionException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.354.1.5 decaf::util::concurrent::ExecutionException::ExecutionException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

msg - The message to report

... - The list of primitives that are formatted into the message

6.354.1.6 decaf::util::concurrent::ExecutionException::ExecutionException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

cause - The exception that was the cause for this one to be thrown.

msg - The message to report

... - list of primitives that are formatted into the message

6.354.1.7 `virtual decaf::util::concurrent::ExecutionException::~~ExecutionException
() throw () [inline, virtual]`

6.354.2 Member Function Documentation

6.354.2.1 `virtual ExecutionException* de-
caf::util::concurrent::ExecutionException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an exception that is a clone of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/ExecutionException.h`

6.355 decaf::util::concurrent::Executor Class Reference

An object that executes submitted **decaf.lang Runnable** (p. 3325) tasks.

#include <src/main/decaf/util/concurrent/Executor.h> Inheritance diagram for decaf::util::concurrent::Executor:

Public Member Functions

- virtual **~Executor** ()
- virtual void **execute** (Runnable *command)=0 throw (decaf::util::concurrent::RejectedExecutionException, decaf::lang::exceptions::NullPointerException)

Executes the given command at some time in the future.

6.355.1 Detailed Description

An object that executes submitted **decaf.lang Runnable** (p. 3325) tasks. This interface provides a way of decoupling task submission from the mechanics of how each task will be run, including details of thread use, scheduling, etc. An **Executor** (p. 1869) is normally used instead of explicitly creating threads. For example, rather than invoking `new Thread(new RunnableTask()).start()` for each of a set of tasks, you might use:

```
Executor (p.1869) executor = anExecutor;
executor->execute( new RunnableTask1() );
executor->execute( new RunnableTask2() );
...
```

However, the **Executor** (p. 1869) interface does not strictly require that execution be asynchronous. In the simplest case, an executor can run the submitted task immediately in the caller's thread:

```
class DirectExecutor : public Executor (p.1869) {
public:

    void execute( Runnable* r ) (p.1870) {
        r->run();
    }

}
```

More typically, tasks are executed in some thread other than the caller's thread. The executor below spawns a new thread for each task.

```
class ThreadPerTaskExecutor : public Executor (p.1869) {
public:
    std::vector<Thread*gt; threads;
```

```

void execute( Runnable* r ) (p.1870) {
    threads.push_back( new Thread( r ) );
    threads.rbegin()->start();
}

}

```

The `Executor` (p.1869) implementations provided in this package implement **decaf.util.concurrent.ExecutorService** (p.1871), which is a more extensive interface. The **decaf.util.concurrent.ThreadPoolExecutor** (p.??) class provides an extensible thread pool implementation. The **decaf.util.concurrent.Executor** (p.??) class provides convenient factory methods for these Executors.

Since:

1.0

6.355.2 Constructor & Destructor Documentation

6.355.2.1 `virtual decaf::util::concurrent::Executor::~~Executor ()` [inline, virtual]

6.355.3 Member Function Documentation

6.355.3.1 `virtual void decaf::util::concurrent::Executor::execute (Runnable * command) throw (decaf::util::concurrent::RejectedExecutionException, decaf::lang::exceptions::NullPointerException)` [pure virtual]

Executes the given command at some time in the future. The command may execute in a new thread, in a pooled thread, or in the calling thread, at the discretion of the `Executor` (p.1869) implementation.

Parameters:

command the runnable task

Exceptions:

RejectedExecutionException (p. 3189) if this task cannot be accepted for execution.

NullPointerException if command is null

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Executor.h`

6.356 decaf::util::concurrent::ExecutorService Class Reference

An **Executor** (p.1869) that provides methods to manage termination and methods that can produce a **Future** (p.1966) for tracking progress of one or more asynchronous tasks.

#include <src/main/decaf/util/concurrent/ExecutorService.h> Inheritance diagram for decaf::util::concurrent::ExecutorService:

Public Member Functions

- virtual \sim **ExecutorService** ()
- bool **awaitTermination** (long long timeout, const **TimeUnit** &unit)=0 throw (decaf::lang::exceptions::InterruptedException)

Blocks until all tasks have completed execution after a shutdown request, or the timeout occurs, or the current thread is interrupted, whichever happens first.

6.356.1 Detailed Description

An **Executor** (p.1869) that provides methods to manage termination and methods that can produce a **Future** (p.1966) for tracking progress of one or more asynchronous tasks. An **ExecutorService** (p.1871) can be shut down, which will cause it to reject new tasks. Two different methods are provided for shutting down an **ExecutorService** (p.1871). The shutdown() method will allow previously submitted tasks to execute before terminating, while the shutdownNow() method prevents waiting tasks from starting and attempts to stop currently executing tasks. Upon termination, an executor has no tasks actively executing, no tasks awaiting execution, and no new tasks can be submitted. An unused **ExecutorService** (p.1871) should be shut down to allow reclamation of its resources.

Method submit extends base method **Executor.execute** (p.1870)(**decaf.lang Runnable** (p.3325)) by creating and returning a **Future** (p.1966) that can be used to cancel execution and/or wait for completion. Methods invokeAny and invokeAll perform the most commonly useful forms of bulk execution, executing a collection of tasks and then waiting for at least one, or all, to complete. (Class ExecutorCompletionService can be used to write customized variants of these methods.)

The Executors class provides factory methods for the executor services provided in this package.

Since:

1.0

6.356.2 Constructor & Destructor Documentation

6.356.2.1 `virtual decaf::util::concurrent::ExecutorService::~~ExecutorService ()`
[inline, virtual]

6.356.3 Member Function Documentation

6.356.3.1 `bool decaf::util::concurrent::ExecutorService::awaitTermination`
(long long *timeout*, const TimeUnit & *unit*) throw (
decaf::lang::exceptions::InterruptedException) [pure virtual]

Blocks until all tasks have completed execution after a shutdown request, or the timeout occurs, or the current thread is interrupted, whichever happens first.

Parameters:

timeout The amount of time to wait before timing out the Wait operation.

unit The Units that comprise the timeout value.

Returns:

true if the executor terminated before the given timeout value elapsed.

Exceptions:

InterruptedException - if interrupted while waiting.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/ExecutorService.h`

6.357 activemq::transport::failover::FailoverTransport Class Reference

#include <src/main/activemq/transport/failover/FailoverTransport.h> Inheritance diagram for activemq::transport::failover::FailoverTransport:

Public Member Functions

- **FailoverTransport** ()
- virtual **~FailoverTransport** ()
- void **reconnect** ()
*Indicates that the **Transport** (p. 3883) needs to reconnect to another URI in its list.*
- void **add** (const std::string &uri)
*Adds a New URI to the List of URIs this **transport** (p. 97) can Connect to.*
- virtual void **addURI** (const **List**< **URI** > &uris)
*Add a URI to the list of URI's that will represent the set of Transports that this **Transport** (p. 3883) is a composite of.*
- virtual void **removeURI** (const **List**< **URI** > &uris)
*Remove a URI from the set of URI's that represents the set of Transports that this **Transport** (p. 3883) is composed of, removing a URI for which the composite has created a connected **Transport** (p. 3883) should result in that **Transport** (p. 3883) being disposed of.*
- virtual void **start** () throw (decaf::io::IOException)
*Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87).*
- virtual void **stop** () throw (decaf::io::IOException)
*Stop the **Transport** (p. 3883).*
- virtual void **close** () throw (decaf::io::IOException)
Stops the polling thread and closes the streams.
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.

- virtual void **setWireFormat** (const **Pointer**< **wireformat::WireFormat** > &wireFormat AMQCPP_UNUSED)
Sets the WireFormat instance to use.
- virtual void **setTransportListener** (**TransportListener** *listener)
*Sets the observer of asynchronous events from this **transport** (p. 97).*
- virtual **TransportListener** * **getTransportListener** () const
*Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual bool **isFaultTolerant** () const
*Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.*
- virtual bool **isConnected** () const
*Is the **Transport** (p. 3883) Connected to its Broker.*
- virtual bool **isClosed** () const
*Has the **Transport** (p. 3883) been shutdown and no longer usable.*
- bool **isInitialized** () const
*Returns true if the **Transport** (p. 3883) has been initialized by a BrokerInfo command.*
- void **setInitialized** (bool value)
*Sets the initialized **state** (p. 95) of this **Transport** (p. 3883) to true.*
- virtual **Transport** * **narrow** (const std::type_info &typeId)
*Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.*
- virtual std::string **getRemoteAddress** () const
- virtual bool **isPending** () const
- virtual bool **iterate** ()
*Performs the actual Reconnect operation for the **FailoverTransport** (p. 1873), when a connection is made this method returns false to indicate it doesn't need to run again, otherwise it returns true to indicate its still trying to connect.*
- virtual void **reconnect** (const **decaf::net::URI** &uri) throw (**decaf::io::IOException**)
reconnect to another location
- long long **getTimeout** () const
- void **setTimeout** (long long value)
- long long **getInitialReconnectDelay** () const
- void **setInitialReconnectDelay** (long long value)
- long long **getMaxReconnectDelay** () const
- void **setMaxReconnectDelay** (long long value)
- long long **getBackOffMultiplier** () const
- void **setBackOffMultiplier** (long long value)
- bool **isUseExponentialBackOff** () const
- void **setUseExponentialBackOff** (bool value)
- bool **isRandomize** () const

- void **setRandomize** (bool value)
- int **getMaxReconnectAttempts** () const
- void **setMaxReconnectAttempts** (int value)
- int **getStartupMaxReconnectAttempts** () const
- void **setStartupMaxReconnectAttempts** (int value)
- long long **getReconnectDelay** () const
- void **setReconnectDelay** (long long value)
- bool **isBackup** () const
- void **setBackup** (bool value)
- int **getBackupPoolSize** () const
- void **setBackupPoolSize** (int value)
- bool **isTrackMessages** () const
- void **setTrackMessages** (bool value)
- bool **isTrackTransactionProducers** () const
- void **setTrackTransactionProducers** (bool value)
- int **getMaxCacheSize** () const
- void **setMaxCacheSize** (int value)
- void **setConnectionInterruptProcessingComplete** (const **Pointer**< **commands::ConnectionId** > &connectionId)

Protected Member Functions

- void **restoreTransport** (const **Pointer**< **Transport** > &transport) throw (**decaf::io::IOException**)
*Given a **Transport** (p. 3883) restore the **state** (p. 95) of the Client's connection to the Broker using the data accumulated in the State Tracker.*
- void **handleTransportFailure** (const **decaf::lang::Exception** &error) throw (**decaf::lang::Exception**)
*Called when this class' **TransportListener** (p. 3900) is notified of a Failure.*

Friends

- class **FailoverTransportListener**

6.357.1 Constructor & Destructor Documentation

6.357.1.1 **activemq::transport::failover::FailoverTransport::FailoverTransport** ()

6.357.1.2 **virtual**
activemq::transport::failover::FailoverTransport::~~FailoverTransport ()
 [virtual]

6.357.2 Member Function Documentation

6.357.2.1 **void** **activemq::transport::failover::FailoverTransport::add** (const **std::string** & *uri*)

Adds a New URI to the List of URIs this **transport** (p. 97) can Connect to.

Parameters:

uri A String version of a URI to add to the URIs to **failover** (p. 99) to.

**6.357.2.2 virtual void activemq::transport::failover::FailoverTransport::addURI
(const List< URI > & *uris*) [virtual]**

Add a URI to the list of URI's that will represent the set of Transports that this **Transport** (p. 3883) is a composite of.

Parameters:

uris The new URIs to add to the set this composite maintains.

Implements **activemq::transport::CompositeTransport** (p. 1226).

**6.357.2.3 virtual void activemq::transport::failover::FailoverTransport::close ()
throw (decaf::io::IOException) [virtual]**

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if errors occur.

Implements **decaf::io::Closeable** (p. 1149).

- 6.357.2.4** `long long activemq::transport::failover::FailoverTransport::getBackOffMultiplier () const [inline]`
- 6.357.2.5** `int activemq::transport::failover::FailoverTransport::getBackupPoolSize () const [inline]`
- 6.357.2.6** `long long activemq::transport::failover::FailoverTransport::getInitialReconnectDelay () const [inline]`
- 6.357.2.7** `int activemq::transport::failover::FailoverTransport::getMaxCacheSize () const [inline]`
- 6.357.2.8** `int activemq::transport::failover::FailoverTransport::getMaxReconnectAttempts () const [inline]`
- 6.357.2.9** `long long activemq::transport::failover::FailoverTransport::getMaxReconnectDelay () const [inline]`
- 6.357.2.10** `long long activemq::transport::failover::FailoverTransport::getReconnectDelay () const [inline]`
- 6.357.2.11** `virtual std::string activemq::transport::failover::FailoverTransport::getRemoteAddress () const [virtual]`

Returns:

the remote address for this connection

Implements **activemq::transport::Transport** (p. 3884).

- 6.357.2.12** `int activemq::transport::failover::FailoverTransport::getStartupMaxReconnectAttempts () const [inline]`
- 6.357.2.13** `long long activemq::transport::failover::FailoverTransport::getTimeout () const [inline]`
- 6.357.2.14** `virtual TransportListener* activemq::transport::failover::FailoverTransport::getTransportListener () const [virtual]`

Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).

Returns:

The listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3884).

6.357.2.15 `void activemq::transport::failover::FailoverTransport::handleTransportFailure (const decaf::lang::Exception & error) throw (decaf::lang::Exception) [protected]`

Called when this class' **TransportListener** (p. 3900) is notified of a Failure.

Parameters:

error - The CMS Exception that was thrown.

Exceptions:

Exception if an error occurs.

6.357.2.16 `bool activemq::transport::failover::FailoverTransport::isBackup () const [inline]`

6.357.2.17 `virtual bool activemq::transport::failover::FailoverTransport::isClosed () const [inline, virtual]`

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

Implements **activemq::transport::Transport** (p. 3885).

6.357.2.18 `virtual bool activemq::transport::failover::FailoverTransport::isConnected () const [inline, virtual]`

Is the **Transport** (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Implements **activemq::transport::Transport** (p. 3885).

6.357.2.19 `virtual bool activemq::transport::failover::FailoverTransport::isFaultTolerant () const [inline, virtual]`

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Implements **activemq::transport::Transport** (p. 3885).

6.357.2.20 `bool activemq::transport::failover::FailoverTransport::isInitialized () const [inline]`

Returns true if the **Transport** (p. 3883) has been initialized by a **BrokerInfo** command.

Returns:

true if the **Transport** (p. 3883) has been initialized by a **BrokerInfo** command.

6.357.2.21 `virtual bool activemq::transport::failover::FailoverTransport::isPending () const [virtual]`

Returns:

true if there is a need for the **iterate** method to be called by this classes task runner.

Implements **activemq::threads::CompositeTask** (p. 1221).

6.357.2.22 `bool activemq::transport::failover::FailoverTransport::isRandomize () const [inline]`

6.357.2.23 `bool activemq::transport::failover::FailoverTransport::isTrackMessages () const [inline]`

6.357.2.24 `bool activemq::transport::failover::FailoverTransport::isTrackTransactionProducers () const [inline]`

6.357.2.25 `bool activemq::transport::failover::FailoverTransport::isUseExponentialBackOff () const [inline]`

6.357.2.26 `virtual bool activemq::transport::failover::FailoverTransport::iterate () [virtual]`

Performs the actual **Reconnect** operation for the **FailoverTransport** (p. 1873), when a connection is made this method returns false to indicate it doesn't need to run again, otherwise it returns true to indicate its still trying to connect.

Returns:

false to indicate a connection, true to indicate it needs to try again.

Implements **activemq::threads::Task** (p. 3734).

6.357.2.27 `virtual Transport* activemq::transport::failover::FailoverTransport::narrow (const std::type_info & typeId) [inline, virtual]`

Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.

Parameters:

typeId - The type_info of the Object we are searching for.

Returns:

the requested Object. or NULL if its not in this chain.

Implements **activemq::transport::Transport** (p.3885).

References **activemq::transport::Transport::narrow()**.

6.357.2.28 **virtual void activemq::transport::failover::FailoverTransport::oneway**
(const Pointer< Command > & command)
throw (decaf::io::IOException, de-
cafe::lang::exceptions::UnsupportedOperationException)
[virtual]

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport**
 (p. 97).

Implements **activemq::transport::Transport** (p.3886).

6.357.2.29 **virtual void activemq::transport::failover::FailoverTransport::reconnect**
(const decaf::net::URI & uri) throw (decaf::io::IOException)
[virtual]

reconnect to another location

Parameters:

uri

Exceptions:

IOException on failure of if not supported

Implements **activemq::transport::Transport** (p.3886).

6.357.2.30 **void activemq::transport::failover::FailoverTransport::reconnect ()**

Indicates that the **Transport** (p.3883) needs to reconnect to another URI in its list.

6.357.2.31 virtual void activemq::transport::failover::FailoverTransport::removeURI (const List< URI > & *uris*) [virtual]

Remove a URI from the set of URI's that represents the set of Transports that this **Transport** (p. 3883) is composed of, removing a URI for which the composite has created a connected **Transport** (p. 3883) should result in that **Transport** (p. 3883) being disposed of.

Parameters:

uris The new URIs to remove to the set this composite maintains.

Implements **activemq::transport::CompositeTransport** (p. 1227).

6.357.2.32 virtual Pointer<Response> activemq::transport::failover::FailoverTransport::request (const Pointer< Command > & *command*, unsigned int *timeout*) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Sends the given command to the broker and then waits for the response.

Parameters:

command - The command to be sent.

timeout - The time to wait for this response.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3886).

6.357.2.33 virtual Pointer<Response> activemq::transport::failover::FailoverTransport::request (const Pointer< Command > & *command*) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Sends the given command to the broker and then waits for the response.

Parameters:

command the command to be sent.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3887).

6.357.2.34 `void activemq::transport::failover::FailoverTransport::restoreTransport (const Pointer< Transport > & transport) throw (decaf::io::IOException) [protected]`

Given a **Transport** (p. 3883) restore the **state** (p. 95) of the Client's connection to the Broker using the data accumulated in the State Tracker.

Parameters:

transport (p. 97) The new **Transport** (p. 3883) connected to the Broker.

Exceptions:

IOException if an errors occurs while restoring the old **state** (p. 95).

6.357.2.35 `void activemq::transport::failover::FailoverTransport::setBackOffMultiplier (long long value) [inline]`

6.357.2.36 `void activemq::transport::failover::FailoverTransport::setBackup (bool value) [inline]`

6.357.2.37 `void activemq::transport::failover::FailoverTransport::setBackupPoolSize (int value) [inline]`

6.357.2.38 `void activemq::transport::failover::FailoverTransport::setConnectionInterruptProcessingComplete (const Pointer< commands::ConnectionId > & connectionId)`

6.357.2.39 `void activemq::transport::failover::FailoverTransport::setInitialized (bool value) [inline]`

Sets the initialized **state** (p. 95) of this **Transport** (p. 3883) to true.

Parameters:

value - true if this **Transport** (p. 3883) has been initialized.

- 6.357.2.40 void `activemq::transport::failover::FailoverTransport::setInitialReconnectDelay` (long long *value*) [inline]
- 6.357.2.41 void `activemq::transport::failover::FailoverTransport::setMaxCacheSize` (int *value*) [inline]
- 6.357.2.42 void `activemq::transport::failover::FailoverTransport::setMaxReconnectAttempts` (int *value*) [inline]
- 6.357.2.43 void `activemq::transport::failover::FailoverTransport::setMaxReconnectDelay` (long long *value*) [inline]
- 6.357.2.44 void `activemq::transport::failover::FailoverTransport::setRandomize` (bool *value*) [inline]
- 6.357.2.45 void `activemq::transport::failover::FailoverTransport::setReconnectDelay` (long long *value*) [inline]
- 6.357.2.46 void `activemq::transport::failover::FailoverTransport::setStartupMaxReconnectAttempts` (int *value*) [inline]
- 6.357.2.47 void `activemq::transport::failover::FailoverTransport::setTimeout` (long long *value*) [inline]
- 6.357.2.48 void `activemq::transport::failover::FailoverTransport::setTrackMessages` (bool *value*) [inline]
- 6.357.2.49 void `activemq::transport::failover::FailoverTransport::setTrackTransactionProducers` (bool *value*) [inline]
- 6.357.2.50 virtual void `activemq::transport::failover::FailoverTransport::setTransportListener` (TransportListener * *listener*) [virtual]

Sets the observer of asynchronous events from this **transport** (p. 97).

Parameters:

listener the listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3887).

6.357.2.51 void activemq::transport::failover::FailoverTransport::setUseExponentialBackOff (bool *value*) [inline]

6.357.2.52 virtual void activemq::transport::failover::FailoverTransport::setWireFormat (const Pointer< wireformat::WireFormat > &wireFormat *AMQCPP_UNUSED*) [inline, virtual]

Sets the WireFormat instance to use.

Parameters:

wireFormat The WireFormat the object used to encode / decode **commands** (p.87).

6.357.2.53 virtual void activemq::transport::failover::FailoverTransport::start () throw (decaf::io::IOException) [virtual]

Starts this **transport** (p.97) object and creates the thread for polling on the input stream for **commands** (p.87). If this object has been closed, throws an exception. Before calling start, the caller must set the IO streams and the reader and writer objects.

Exceptions:

IOException if an error occurs or if this **transport** (p.97) has already been closed.

Implements **activemq::transport::Transport** (p.3888).

6.357.2.54 virtual void activemq::transport::failover::FailoverTransport::stop () throw (decaf::io::IOException) [virtual]

Stop the **Transport** (p.3883).

Exceptions:

IOException if an error occurs while stopping the **Transport** (p.3883).

Implements **activemq::transport::Transport** (p.3888).

6.357.3 Friends And Related Function Documentation

6.357.3.1 friend class FailoverTransportListener [friend]

The documentation for this class was generated from the following file:

- src/main/activemq/transport/failover/**FailoverTransport.h**

6.358 activemq::transport::failover::FailoverTransportFactory Class Reference

Creates an instance of a **FailoverTransport** (p.1873).

#include <src/main/activemq/transport/failover/FailoverTransportFactory.h> Inheritance diagram for activemq::transport::failover::FailoverTransportFactory:

Public Member Functions

- virtual **~FailoverTransportFactory** ()
- virtual **Pointer< Transport > create** (const **decaf::net::URI** &location) throw (exceptions::ActiveMQException)

*Creates a fully configured **Transport** (p.3883) instance which could be a chain of filters and transports.*

- virtual **Pointer< Transport > createComposite** (const **decaf::net::URI** &location) throw (exceptions::ActiveMQException)

*Creates a slimmed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.*

Protected Member Functions

- virtual **Pointer< Transport > doCreateComposite** (const **decaf::net::URI** &location, const **decaf::util::Properties** &properties) throw (exceptions::ActiveMQException)

*Creates a slimmed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.*

6.358.1 Detailed Description

Creates an instance of a **FailoverTransport** (p.1873).

Since:

3.0

6.358.2 Constructor & Destructor Documentation

6.358.2.1 `virtual
activemq::transport::failover::FailoverTransportFactory::~~FailoverTransportFactory
() [inline, virtual]`

6.358.3 Member Function Documentation

6.358.3.1 `virtual Pointer<Transport> ac-
tivismq::transport::failover::FailoverTransportFactory::create (const
decaf::net::URI & location) throw (exceptions::ActiveMQException)
[virtual]`

Creates a fully configured **Transport** (p.3883) instance which could be a chain of filters and transports.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3889).

6.358.3.2 `virtual Pointer<Transport> ac-
tivismq::transport::failover::FailoverTransportFactory::createComposite
(const decaf::net::URI & location) throw (excep-
tions::ActiveMQException) [virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3890).

6.358.3.3 `virtual Pointer<Transport> ac-
tivismq::transport::failover::FailoverTransportFactory::doCreateComposite
(const decaf::net::URI & location, const decaf::util::Properties &
properties) throw (exceptions::ActiveMQException) [protected,
virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to.

properties - Properties to apply to the **transport** (p. 97).

Returns:

Pointer to a new **FailoverTransport** (p. 1873) instance.

Exceptions:

ActiveMQException if an error occurs

The documentation for this class was generated from the following file:

- src/main/activemq/transport/failover/**FailoverTransportFactory.h**

6.359 activemq::transport::failover::FailoverTransportListener Class Reference

Utility class used by the **Transport** (p. 3883) to perform the work of responding to events from the active **Transport** (p. 3883).

#include <src/main/activemq/transport/failover/FailoverTransportListener.h> Inheritance diagram for activemq::transport::failover::FailoverTransportListener:

Public Member Functions

- **FailoverTransportListener** (**FailoverTransport** *parent)
- virtual ~**FailoverTransportListener** ()
- virtual void **onCommand** (const **Pointer**< **Command** > &command)

Event handler for the receipt of a command.

- virtual void **onException** (const **decaf::lang::Exception** &ex)

*Event handler for an exception from a command **transport** (p. 97).*

- virtual void **transportInterrupted** ()

*The **transport** (p. 97) has suffered an interruption from which it hopes to recover.*

- virtual void **transportResumed** ()

*The **transport** (p. 97) has resumed after an interruption.*

6.359.1 Detailed Description

Utility class used by the **Transport** (p. 3883) to perform the work of responding to events from the active **Transport** (p. 3883).

Since:

3.0

6.359.2 Constructor & Destructor Documentation

6.359.2.1 `activemq::transport::failover::FailoverTransportListener::FailoverTransportListener(FailoverTransport * parent)`

6.359.2.2 `virtual
activemq::transport::failover::FailoverTransportListener::~~FailoverTransportListener()
()` [virtual]

6.359.3 Member Function Documentation

6.359.3.1 `virtual void ac-
tivemq::transport::failover::FailoverTransportListener::onCommand
(const Pointer< Command > & command)` [virtual]

Event handler for the receipt of a command. The **transport** (p. 97) passes off all received **commands** (p. 87) to its listeners, the listener then owns the Object. If there is no registered listener the **Transport** (p. 3883) deletes the command upon receipt.

Parameters:

command the received command object.

Implements **activemq::transport::TransportListener** (p. 3900).

6.359.3.2 `virtual void ac-
tivemq::transport::failover::FailoverTransportListener::onException
(const decaf::lang::Exception & ex)` [virtual]

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception.

Implements **activemq::transport::TransportListener** (p. 3901).

6.359.3.3 `virtual void ac-
tivemq::transport::failover::FailoverTransportListener::transportInterrupted
()` [virtual]

The **transport** (p. 97) has suffered an interruption from which it hopes to recover.

Implements **activemq::transport::TransportListener** (p. 3901).

6.359.3.4 `virtual void ac-
tivemq::transport::failover::FailoverTransportListener::transportResumed
()` [virtual]

The **transport** (p. 97) has resumed after an interruption.

Implements **activemq::transport::TransportListener** (p. 3901).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/failover/FailoverTransportListener.h`

6.360 decaf::io::FileDescriptor Class Reference

This class servers as an opaque wrapper around an underlying OS level resource that can be used as a source / sink for byte level data such as sockets and files.

#include <src/main/decaf/io/FileDescriptor.h>Inheritance diagram for decaf::io::FileDescriptor:

Public Member Functions

- **FileDescriptor** ()
- virtual **~FileDescriptor** ()
- void **sync** ()
*Force any/all buffered data for this **FileDescriptor** (p. 1891) to be flushed to the underlying device.*
- bool **valid** ()
Indicates whether the File Descriptor is valid.

Static Public Attributes

- static **FileDescriptor in**
A handle to the standard input stream.
- static **FileDescriptor out**
A handle to the standard output stream.
- static **FileDescriptor err**
A handle to the standard error stream.

Protected Member Functions

- **FileDescriptor** (long value, bool **readonly**)

Protected Attributes

- long **descriptor**
- bool **readonly**

6.360.1 Detailed Description

This class servers as an opaque wrapper around an underlying OS level resource that can be used as a source / sink for byte level data such as sockets and files.

Since:

1.0

6.360.2 Constructor & Destructor Documentation

6.360.2.1 `decaf::io::FileDescriptor::FileDescriptor (long value, bool readonly)` [protected]

6.360.2.2 `decaf::io::FileDescriptor::FileDescriptor ()`

6.360.2.3 `virtual decaf::io::FileDescriptor::~~FileDescriptor ()` [virtual]

6.360.3 Member Function Documentation

6.360.3.1 `void decaf::io::FileDescriptor::sync ()`

Force any/all buffered data for this **FileDescriptor** (p.1891) to be flushed to the underlying device. This method blocks until all data is flushed to the underlying device and is used to place the device into a known state. In the case of data that is buffered at a higher level such as a **BufferedOutputStream** (p.940) the stream must first be flushed before this method can force the data to be sent to the output device.

6.360.3.2 `bool decaf::io::FileDescriptor::valid ()`

Indicates whether the File Descriptor is valid.

Returns:

true for a valid descriptor such as open socket or file, false otherwise.

6.360.4 Field Documentation

6.360.4.1 `long decaf::io::FileDescriptor::descriptor` [protected]

6.360.4.2 `FileDescriptor decaf::io::FileDescriptor::err` [static]

A handle to the standard error stream. Usually, this file descriptor is not used directly, but rather via the output stream known as `System::err`.

6.360.4.3 `FileDescriptor decaf::io::FileDescriptor::in` [static]

A handle to the standard input stream. Usually, this file descriptor is not used directly, but rather via the input stream known as `System::in`.

6.360.4.4 `FileDescriptor decaf::io::FileDescriptor::out` [static]

A handle to the standard output stream. Usually, this file descriptor is not used directly, but rather via the output stream known as `System::out`.

6.360.4.5 `bool decaf::io::FileDescriptor::readonly` [protected]

The documentation for this class was generated from the following file:

- `src/main/decaf/io/FileDescriptor.h`

6.361 decaf::util::logging::Filter Class Reference

A **Filter** (p. 1893) can be used to provide fine grain control over what is logged, beyond the control provided by log levels.

```
#include <src/main/decaf/util/logging/Filter.h>
```

Public Member Functions

- virtual **~Filter** ()
- virtual bool **isLoggable** (const **LogRecord** &record) const =0

Check if a given log record should be published.

6.361.1 Detailed Description

A **Filter** (p.1893) can be used to provide fine grain control over what is logged, beyond the control provided by log levels. Each **Logger** (p.2386) and each **Handler** (p.1978) can have a filter associated with it. The **Logger** (p.2386) or **Handler** (p.1978) will call the **isLoggable** method to check if a given **LogRecord** (p.2413) should be published. If **isLoggable** returns false, the **LogRecord** (p.2413) will be discarded.

6.361.2 Constructor & Destructor Documentation

6.361.2.1 virtual decaf::util::logging::Filter::~Filter () [inline, virtual]

6.361.3 Member Function Documentation

6.361.3.1 virtual bool decaf::util::logging::Filter::isLoggable (const **LogRecord** &*record*) const [pure virtual]

Check if a given log record should be published.

Parameters:

record the **LogRecord** (p.2413) to check.

Returns:

true if the record is loggable.

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**Filter.h**

6.362 decaf::io::FilterInputStream Class Reference

A **FilterInputStream** (p.1894) contains some other input stream, which it uses as its basic source of data, possibly transforming the data along the way or providing additional functionality.

#include <src/main/decaf/io/FilterInputStream.h> Inheritance diagram for decaf::io::FilterInputStream:

Public Member Functions

- **FilterInputStream** (**InputStream** *inputStream, bool own=false)

*Constructor to create a wrapped **InputStream** (p. 2043).*

- virtual ~**FilterInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

***IOException** (p. 2142) if an I/O error occurs.*

- virtual void **close** () throw (decaf::io::IOException)

*Closes the **InputStream** (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.*

The default implementation of this method does nothing.

- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Skips over and discards n bytes of data from this input stream.

*The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

***IOException** (p. 2142) if an I/O error occurs.*

***UnsupportedOperationException** if the concrete stream class does not support skipping bytes.*

- virtual void **mark** (int readLimit)

Marks the current position in the stream. A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit *The max bytes read before marked position is invalid.*

- virtual void **reset** () throw (decaf::io::IOException)

Repositions this stream to the position at the time the mark method was last called on this input stream.

*If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset. If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.*

*The default implementation of this method throws an **IOException** (p. 2142).*

Exceptions:

IOException (p. 2142) *if an I/O error occurs.*

- virtual bool **markSupported** () const

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Protected Member Functions

- virtual int **doReadByte** () throw (decaf::io::IOException)
- virtual int **doReadArray** (unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
- virtual bool **isClosed** () const

Protected Attributes

- **InputStream * inputStream**

- bool **own**
- volatile bool **closed**

6.362.1 Detailed Description

A **FilterInputStream** (p. 1894) contains some other input stream, which it uses as its basic source of data, possibly transforming the data along the way or providing additional functionality. The class **FilterInputStream** (p. 1894) itself simply overrides all methods of **InputStream** (p. 2043) with versions that pass all requests to the contained input stream. Subclasses of **FilterInputStream** (p. 1894) may further override some of these methods and may also provide additional methods and fields.

6.362.2 Constructor & Destructor Documentation

6.362.2.1 `decaf::io::FilterInputStream::FilterInputStream (InputStream * inputStream, bool own = false)`

Constructor to create a wrapped **InputStream** (p. 2043).

Parameters:

- inputStream* The stream to wrap and filter.
- own* Indicates if we own the stream object, defaults to false.

6.362.2.2 `virtual decaf::io::FilterInputStream::~~FilterInputStream ()` [virtual]

6.362.3 Member Function Documentation

6.362.3.1 `virtual int decaf::io::FilterInputStream::available () const throw (decaf::io::IOException)` [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

- the number of bytes available on this input stream.

Exceptions:

- IOException* (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2045).

Reimplemented in **decaf::io::BufferedInputStream** (p. 936), **decaf::io::PushbackInputStream** (p. 3143), and **decaf::util::zip::InflaterInputStream** (p. 2038).

6.362.3.2 virtual void decaf::io::FilterInputStream::close () throw (decaf::io::IOException) [virtual]

Closes the **InputStream** (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.

The default implementation of this method does nothing.

Reimplemented from **decaf::io::InputStream** (p. 2045).

Reimplemented in **decaf::io::BufferedInputStream** (p. 937), and **decaf::util::zip::InflaterInputStream** (p. 2039).

6.362.3.3 virtual int decaf::io::FilterInputStream::doReadArray (unsigned char * *buffer*, int *size*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.362.3.4 virtual int decaf::io::FilterInputStream::doReadArrayBounded (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::InputStream** (p. 2046).

Reimplemented in **activemq::io::LoggingInputStream** (p. 2399), **decaf::io::BufferedInputStream** (p. 937), **decaf::io::PushbackInputStream** (p. 3144), **decaf::util::zip::CheckedInputStream** (p. 1138), and **decaf::util::zip::InflaterInputStream** (p. 2039).

6.362.3.5 virtual int decaf::io::FilterInputStream::doReadByte () throw (decaf::io::IOException) [protected, virtual]

Implements **decaf::io::InputStream** (p. 2046).

Reimplemented in **activemq::io::LoggingInputStream** (p. 2400), **decaf::io::BufferedInputStream** (p. 937), **decaf::io::PushbackInputStream** (p. 3144), **decaf::util::zip::CheckedInputStream** (p. 1138), and **decaf::util::zip::InflaterInputStream** (p. 2039).

6.362.3.6 virtual bool decaf::io::FilterInputStream::isClosed () const [protected, virtual]

Returns:

true if this stream has been closed.

6.362.3.7 virtual void decaf::io::FilterInputStream::mark (int *readLimit*) [virtual]

Marks the current position in the stream A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the `reset` method is called so long the `readLimit` is not reached.

Calling `mark` on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Reimplemented from **`decaf::io::InputStream`** (p. 2046).

Reimplemented in **`decaf::io::BufferedInputStream`** (p. 937), **`decaf::io::PushbackInputStream`** (p. 3144), and **`decaf::util::zip::InflaterInputStream`** (p. 2039).

6.362.3.8 **`virtual bool decaf::io::FilterInputStream::markSupported () const`** [virtual]

Determines if this input stream supports the `mark` and `reset` methods.

Whether or not `mark` and `reset` are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns `false`.

Returns:

`true` if this stream instance supports marks

Reimplemented from **`decaf::io::InputStream`** (p. 2047).

Reimplemented in **`decaf::io::BufferedInputStream`** (p. 937), **`decaf::io::PushbackInputStream`** (p. 3144), and **`decaf::util::zip::InflaterInputStream`** (p. 2040).

6.362.3.9 **`virtual void decaf::io::FilterInputStream::reset () throw (decaf::io::IOException)`** [virtual]

Repositions this stream to the position at the time the `mark` method was last called on this input stream.

If the method `markSupported` returns `true`, then: * If the method `mark` has not been called since the stream was created, or the number of bytes read from the stream since `mark` was last called is larger than the argument to `mark` at that last call, then an **`IOException`** (p. 2142) might be thrown. * If such an **`IOException`** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to `mark` (or since the start of the file, if `mark` has not been called) will be resupplied to subsequent callers of the `read` method, followed by any bytes that otherwise would have been the next input data as of the time of the call to `reset`.

If the method `markSupported` returns `false`, then: * The call to `reset` may throw an **`IOException`** (p. 2142). * If an **`IOException`** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the `read` method depend on the particular type of the input stream.

The default implementation of this method throws an **`IOException`** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2049).

Reimplemented in **decaf::io::BufferedInputStream** (p. 938), **decaf::io::PushbackInputStream** (p. 3145), and **decaf::util::zip::InflaterInputStream** (p. 2040).

**6.362.3.10 virtual long long decaf::io::FilterInputStream::skip
(long long num) throw (decaf::io::IOException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]**

Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from **decaf::io::InputStream** (p. 2050).

Reimplemented in **decaf::io::BufferedInputStream** (p. 938), **decaf::io::PushbackInputStream** (p. 3145), **decaf::util::zip::CheckedInputStream** (p. 1139), and **decaf::util::zip::InflaterInputStream** (p. 2041).

6.362.4 Field Documentation

6.362.4.1 volatile bool decaf::io::FilterInputStream::closed [protected]

6.362.4.2 InputStream* decaf::io::FilterInputStream::inputStream [protected]

6.362.4.3 bool decaf::io::FilterInputStream::own [protected]

The documentation for this class was generated from the following file:

- src/main/decaf/io/**FilterInputStream.h**

6.363 decaf::io::FilterOutputStream Class Reference

This class is the superclass of all classes that filter output streams.

#include <src/main/decaf/io/FilterOutputStream.h> Inheritance diagram for decaf::io::FilterOutputStream:

Public Member Functions

- **FilterOutputStream (OutputStream *outputStream, bool own=false)**
Constructor, creates a wrapped output stream.
- virtual **~FilterOutputStream ()**
- virtual void **flush ()** throw (decaf::io::IOException)
Flushes this stream by writing any buffered output to the underlying stream.
Exceptions:
IOException (p. 2142) if an I/O error occurs.
The default implementation of this method does nothing.
- virtual void **close ()** throw (decaf::io::IOException)
Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.
Exceptions:
IOException (p. 2142) if an error occurs while closing.
The default implementation of this method does nothing.
- virtual std::string **toString ()** const
Output a String representation of this object.
The default version of this method just prints the Class Name.
Returns:
a string representation of the object.

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArray** (const unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual bool **isClosed ()** const

Protected Attributes

- **OutputStream * outputStream**
- **bool own**
- **volatile bool closed**

6.363.1 Detailed Description

This class is the superclass of all classes that filter output streams. These streams sit on top of an already existing output stream (the underlying output stream) which it uses as its basic sink of data, but possibly transforming the data along the way or providing additional functionality.

The class **FilterOutputStream** (p. 1900) itself simply overrides all methods of **OutputStream** (p. 2907) with versions that pass all requests to the underlying output stream. Subclasses of **FilterOutputStream** (p. 1900) may further override some of these methods as well as provide additional methods and fields.

Due to the lack of garbage collection in C++ a design decision was made to add a boolean parameter to the constructor indicating if the wrapped **InputStream** (p. 2043) is owned by this object. That way creation of the underlying stream can occur in a Java like way. Ex:

```
DataOutputStream (p. 1579) os = new DataOutputStream (p. 1579)( new Output-Stream() (p. 2909), true )
```

6.363.2 Constructor & Destructor Documentation

6.363.2.1 decaf::io::FilterOutputStream::FilterOutputStream (OutputStream * *outputStream*, bool *own* = false)

Constructor, creates a wrapped output stream.

Parameters:

outputStream the **OutputStream** (p. 2907) to wrap

own If true, this object will control the lifetime of the output stream that it encapsulates.

6.363.2.2 virtual decaf::io::FilterOutputStream::~~FilterOutputStream () [virtual]

6.363.3 Member Function Documentation

6.363.3.1 virtual void decaf::io::FilterOutputStream::close () throw (decaf::io::IOException) [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing. The close method of **FilterOutputStream** (p. 1900) calls its flush method, and then calls the close method of its underlying output stream.

Reimplemented from **decaf::io::OutputStream** (p. 2909).

Reimplemented in **decaf::util::zip::DeflaterOutputStream** (p. 1718).

6.363.3.2 `virtual void decaf::io::FilterOutputStream::doWriteArray (const unsigned char * buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [protected, virtual]

Reimplemented from `decaf::io::OutputStream` (p. 2909).

Reimplemented in `decaf::io::BufferedOutputStream` (p. 941).

6.363.3.3 `virtual void decaf::io::FilterOutputStream::doWriteArrayBounded (const unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [protected, virtual]

Reimplemented from `decaf::io::OutputStream` (p. 2909).

Reimplemented in `activemq::io::LoggingOutputStream` (p. 2401), `decaf::io::BufferedOutputStream` (p. 941), `decaf::io::DataOutputStream` (p. 1580), `decaf::util::zip::CheckedOutputStream` (p. 1141), and `decaf::util::zip::DeflaterOutputStream` (p. 1719).

6.363.3.4 `virtual void decaf::io::FilterOutputStream::doWriteByte (unsigned char value) throw (decaf::io::IOException)` [protected, virtual]

Implements `decaf::io::OutputStream` (p. 2910).

Reimplemented in `activemq::io::LoggingOutputStream` (p. 2402), `decaf::io::BufferedOutputStream` (p. 941), `decaf::io::DataOutputStream` (p. 1581), `decaf::util::zip::CheckedOutputStream` (p. 1141), and `decaf::util::zip::DeflaterOutputStream` (p. 1719).

6.363.3.5 `virtual void decaf::io::FilterOutputStream::flush () throw (decaf::io::IOException)` [virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The default implementation of this method does nothing. The flush method of **FilterOutputStream** (p. 1900) calls the flush method of its underlying output stream.

Reimplemented from `decaf::io::OutputStream` (p. 2910).

Reimplemented in `decaf::io::BufferedOutputStream` (p. 941).

6.363.3.6 `virtual bool decaf::io::FilterOutputStream::isClosed () const` [protected, virtual]

Returns:

true if this stream has been closed.

6.363.3.7 virtual std::string decaf::io::FilterOutputStream::toString () const [virtual]

Output a String representation of this object.

The default version of this method just prints the Class Name.

Returns:

a string representation of the object.

The toString method of **FilterOutputStream** (p. 1900) calls the toString method of its underlying output stream.

Reimplemented from **decaf::io::OutputStream** (p. 2911).

6.363.4 Field Documentation

6.363.4.1 volatile bool decaf::io::FilterOutputStream::closed [protected]

6.363.4.2 OutputStream* decaf::io::FilterOutputStream::outputStream [protected]

6.363.4.3 bool decaf::io::FilterOutputStream::own [protected]

The documentation for this class was generated from the following file:

- src/main/decaf/io/**FilterOutputStream.h**

6.364 decaf::lang::Float Class Reference

#include <src/main/decaf/lang/Float.h> Inheritance diagram for decaf::lang::Float:

Public Member Functions

- **Float** (float value)
- **Float** (double value)
- **Float** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Float** ()
- virtual int **compareTo** (const **Float** &f) const
*Compares this **Float** (p. 1904) instance with another.*
- bool **equals** (const **Float** &f) const
- virtual bool **operator==** (const **Float** &f) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Float** &f) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const float &f) const
*Compares this **Float** (p. 1904) instance with another.*
- bool **equals** (const float &f) const
- virtual bool **operator==** (const float &f) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const float &f) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.

- virtual long long **longValue** () const
Answers the long value which the receiver represents.
- bool **isInfinite** () const
- bool **isNaN** () const

Static Public Member Functions

- static int **compare** (float f1, float f2)
Compares the two specified double values.
- static int **floatToIntBits** (float value)
Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "single format" bit layout.
- static int **floatToRawIntBits** (float value)
Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "single format" bit layout, preserving Not-a-Number (NaN) values.
- static float **intBitsToFloat** (int bits)
Returns the float value corresponding to a given bit representation.
- static bool **isInfinite** (float value)
- static bool **isNaN** (float value)
- static float **parseFloat** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a new float initialized to the value represented by the specified string, as performed by the valueOf method of class **Float** (p. 1904).*
- static std::string **toHexString** (float value)
Returns a hexadecimal string representation of the float argument.
- static std::string **toString** (float value)
Returns a string representation of the float argument.
- static **Float** **valueOf** (float value)
*Returns a **Float** (p. 1904) instance representing the specified float value.*
- static **Float** **valueOf** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a **Float** (p. 1904) instance that wraps a primitive float which is parsed from the string value passed.*

Static Public Attributes

- static const int **SIZE** = 32
The size in bits of the primitive int type.
- static const float **MAX_VALUE**

The maximum value that the primitive type can hold.

- static const float **MIN_VALUE**

The minimum value that the primitive type can hold.

- static const float **NaN**

*Constant for the Not a **Number** (p. 2835) Value.*

- static const float **POSITIVE_INFINITY**

Constant for Positive Infinity.

- static const float **NEGATIVE_INFINITY**

Constant for Negative Infinity.

6.364.1 Constructor & Destructor Documentation

6.364.1.1 `decaf::lang::Float::Float (float value)`

Parameters:

value - the primitive type to wrap

6.364.1.2 `decaf::lang::Float::Float (double value)`

Parameters:

value - the primitive type to wrap

6.364.1.3 `decaf::lang::Float::Float (const std::string & value) throw (exceptions::NumberFormatException)`

Parameters:

value - the string to convert to a primitive type to wrap

6.364.1.4 `virtual decaf::lang::Float::~~Float () [inline, virtual]`

6.364.2 Member Function Documentation

6.364.2.1 `virtual unsigned char decaf::lang::Float::byteValue () const [inline, virtual]`

Answers the byte value which the receiver represents.

Returns:

byte the value of the receiver.

Reimplemented from `decaf::lang::Number` (p. 2835).

6.364.2.2 static int decaf::lang::Float::compare (float *f1*, float *f2*) [static]

Compares the two specified double values. The sign of the integer value returned is the same as that of the integer that would be returned by the call: `Float(f1).compareTo(Float(f2))`

Parameters:

f1 - the first double to compare

f2 - the second double to compare

Returns:

the value 0 if *d1* is numerically equal to *f2*; a value less than 0 if *f1* is numerically less than *f2*; and a value greater than 0 if *f1* is numerically greater than *f2*.

6.364.2.3 virtual int decaf::lang::Float::compareTo (const float & *f*) const [virtual]

Compares this **Float** (p. 1904) instance with another.

Parameters:

f - the **Float** (p. 1904) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements **decaf::lang::Comparable**< float > (p. 1214).

6.364.2.4 virtual int decaf::lang::Float::compareTo (const Float & *f*) const [virtual]

Compares this **Float** (p. 1904) instance with another.

Parameters:

f - the **Float** (p. 1904) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.364.2.5 virtual double decaf::lang::Float::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.364.2.6 `bool decaf::lang::Float::equals (const float & f) const` [inline, virtual]

Parameters:

f - the **Float** (p. 1904) object to compare against.

Returns:

true if the two **Float** (p. 1904) Objects have the same value.

Implements **decaf::lang::Comparable**< **float** > (p. 1215).

6.364.2.7 `bool decaf::lang::Float::equals (const Float & f) const` [inline]

Parameters:

f - the **Float** (p. 1904) object to compare against.

Returns:

true if the two **Float** (p. 1904) Objects have the same value.

6.364.2.8 `static int decaf::lang::Float::floatToIntBits (float value)` [static]

Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "single format" bit layout. Bit 31 (the bit that is selected by the mask 0x80000000) represents the sign of the floating-point number. Bits 30-23 (the bits that are selected by the mask 0x7f800000) represent the exponent. Bits 22-0 (the bits that are selected by the mask 0x007fffff) represent the significand (sometimes called the mantissa) of the floating-point number.

If the argument is positive infinity, the result is 0x7f800000. If the argument is negative infinity, the result is 0xff800000. If the argument is NaN, the result is 0x7c000000.

In all cases, the result is an integer that, when given to the **intBitsToFloat(int)** (p. 1909) method, will produce a floating-point value the same as the argument to **floatToIntBits** (except all NaN values are collapsed to a single "canonical" NaN value).

Parameters:

value - the float to convert to int bits

Returns:

the int that holds the float's value

6.364.2.9 `static int decaf::lang::Float::floatToRawIntBits (float value)` [static]

Returns a representation of the specified floating-point value according to the IEEE 754 floating-point "single format" bit layout, preserving Not-a-Number (NaN) values. Bit 31 (the bit that is selected by the mask 0x80000000) represents the sign of the floating-point number. Bits 30-23 (the bits that are selected by the mask 0x7f800000) represent the exponent. Bits 22-0 (the bits that are selected by the mask 0x007fffff) represent the significand (sometimes called the mantissa) of the floating-point number.

If the argument is positive infinity, the result is 0x7f800000. If the argument is negative infinity, the result is 0xff800000. If the argument is NaN, the result is the integer representing the actual NaN value. Unlike the `floatToIntBits` method, `intToRawIntBits` does not collapse all the bit patterns encoding a NaN to a single "canonical" NaN value.

In all cases, the result is an integer that, when given to the `intBitsToFloat(int)` (p. 1909) method, will produce a floating-point value the same as the argument to `floatToRawIntBits`.

Parameters:

value The float to convert to a raw int.

Returns:

the raw int value of the float

6.364.2.10 virtual float decaf::lang::Float::floatValue () const [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements `decaf::lang::Number` (p. 2836).

6.364.2.11 static float decaf::lang::Float::intBitsToFloat (int bits) [static]

Returns the float value corresponding to a given bit representation. The argument is considered to be a representation of a floating-point value according to the IEEE 754 floating-point "single format" bit layout.

If the argument is 0x7f800000, the result is positive infinity. If the argument is 0xff800000, the result is negative infinity. If the argument is any value in the range 0x7f800001 through 0x7fffffff or in the range 0xff800001 through 0xffffffff, the result is a NaN. No IEEE 754 floating-point operation provided by C++ can distinguish between two NaN values of the same type with different bit patterns. Distinct values of NaN are only distinguishable by use of the `Float::floatToRawIntBits` (p. 1908) method.

Parameters:

bits - the bits of the float encoded as a float

Returns:

a new float created from the int bits.

6.364.2.12 virtual int decaf::lang::Float::intValue () const [inline, virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements `decaf::lang::Number` (p. 2836).

6.364.2.13 `static bool decaf::lang::Float::isInfinite (float value) [static]`**Parameters:**

value - The float to check.

Returns:

true if the float is equal to infinity.

6.364.2.14 `bool decaf::lang::Float::isInfinite () const`**Returns:**

true if the float is equal to positive infinity.

6.364.2.15 `static bool decaf::lang::Float::isNaN (float value) [static]`**Parameters:**

value - The float to check.

Returns:

true if the float is equal to NaN.

6.364.2.16 `bool decaf::lang::Float::isNaN () const`**Returns:**

true if the float is equal to NaN.

6.364.2.17 `virtual long long decaf::lang::Float::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.364.2.18 `virtual bool decaf::lang::Float::operator< (const float & f) const [inline, virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

f - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable**< float > (p. 1215).

6.364.2.19 **virtual bool decaf::lang::Float::operator< (const Float & *f*) const**
 [inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

f - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.364.2.20 **virtual bool decaf::lang::Float::operator== (const float & *f*) const**
 [inline, virtual]

Compares equality between this object and the one passed.

Parameters:

f - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable**< float > (p. 1215).

6.364.2.21 **virtual bool decaf::lang::Float::operator== (const Float & *f*) const**
 [inline, virtual]

Compares equality between this object and the one passed.

Parameters:

f - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.364.2.22 **static float decaf::lang::Float::parseFloat (const std::string & *value*)**
 throw (exceptions::NumberFormatException) [static]

Returns a new float initialized to the value represented by the specified string, as performed by the valueOf method of class **Float** (p. 1904).

Parameters:

value - the string to parse

Returns:

a float parsed from the string

Exceptions:

NumberFormatException

6.364.2.23 `virtual short decaf::lang::Float::shortValue () const` `[inline, virtual]`

Answers the short value which the receiver represents.

Returns:

short the value of the receiver.

Reimplemented from `decaf::lang::Number` (p. 2837).

6.364.2.24 `static std::string decaf::lang::Float::toHexString (float value)` `[static]`

Returns a hexadecimal string representation of the float argument. All characters mentioned below are ASCII characters.

* If the argument is NaN, the result is the string "NaN". * Otherwise, the result is a string that represents the sign and magnitude (absolute value) of the argument. If the sign is negative, the first character of the result is '-'; if the sign is positive, no sign character appears in the result. As for the magnitude m: o If m is infinity, it is represented by the string "Infinity"; thus, positive infinity produces the result "Infinity" and negative infinity produces the result "-Infinity". o If m is zero, it is represented by the string "0x0.0p0"; thus, negative zero produces the result "-0x0.0p0" and positive zero produces the result "0x0.0p0". o If m is a float value with a normalized representation, substrings are used to represent the significand and exponent fields. The significand is represented by the characters "0x1." followed by a lowercase hexadecimal representation of the rest of the significand as a fraction. Trailing zeros in the hexadecimal representation are removed unless all the digits are zero, in which case a single zero is used. Next, the exponent is represented by "p" followed by a decimal string of the unbiased exponent as if produced by a call to **Integer.toString** (p. 2089) on the exponent value. o If m is a float value with a subnormal representation, the significand is represented by the characters "0x0." followed by a hexadecimal representation of the rest of the significand as a fraction. Trailing zeros in the hexadecimal representation are removed. Next, the exponent is represented by "p-126". Note that there must be at least one nonzero digit in a subnormal significand.

Parameters:

value - The float to convert to a string

Returns:

the Hex formatted float string.

6.364.2.25 static std::string decaf::lang::Float::toString (float *value*) [static]

Returns a string representation of the float argument. All characters mentioned below are ASCII characters.

If the argument is NaN, the result is the string "NaN". Otherwise, the result is a string that represents the sign and magnitude (absolute value) of the argument. If the sign is negative, the first character of the result is '-'; if the sign is positive, no sign character appears in the result. As for the magnitude *m*:

- o If *m* is infinity, it is represented by the characters "Infinity"; thus, positive infinity produces the result "Infinity" and negative infinity produces the result "-Infinity".
- o If *m* is zero, it is represented by the characters "0.0"; thus, negative zero produces the result "-0.0" and positive zero produces the result "0.0".
- o If *m* is greater than or equal to 10⁻³ but less than 10⁷, then it is represented as the integer part of *m*, in decimal form with no leading zeroes, followed by '.', followed by one or more decimal digits representing the fractional part of *m*.
- o If *m* is less than 10⁻³ or greater than or equal to 10⁷, then it is represented in so-called "computerized scientific notation." Let *n* be the unique integer such that 10^{*n*} ≤ *m* < 10^{*n*+1}; then let *a* be the mathematically exact quotient of *m* and 10^{*n*} so that 1 ≤ *a* < 10. The magnitude is then represented as the integer part of *a*, as a single decimal digit, followed by '.', followed by decimal digits representing the fractional part of *a*, followed by the letter 'E', followed by a representation of *n* as a decimal integer, as produced by the method **Integer.toString(int)** (p. 2089).

Parameters:

value - The float to convert to a string

Returns:

the formatted float string.

6.364.2.26 std::string decaf::lang::Float::toString () const**Returns:**

this **Float** (p. 1904) Object as a **String** (p. 3665) Representation

6.364.2.27 static Float decaf::lang::Float::valueOf (const std::string & *value*) throw (exceptions::NumberFormatException) [static]

Returns a **Float** (p. 1904) instance that wraps a primitive float which is parsed from the string value passed.

Parameters:

value - the string to parse

Returns:

a new **Float** (p. 1904) instance wrapping the float parsed from value

Exceptions:

NumberFormatException on error.

6.364.2.28 `static Float decaf::lang::Float::valueOf (float value)` [static]

Returns a **Float** (p. 1904) instance representing the specified float value.

Parameters:

value - float to wrap

Returns:

new **Float** (p. 1904) instance wrapping the primitive value

6.364.3 **Field Documentation****6.364.3.1** `const float decaf::lang::Float::MAX_VALUE` [static]

The maximum value that the primitive type can hold.

6.364.3.2 `const float decaf::lang::Float::MIN_VALUE` [static]

The minimum value that the primitive type can hold.

6.364.3.3 `const float decaf::lang::Float::NaN` [static]

Constant for the Not a **Number** (p. 2835) Value.

6.364.3.4 `const float decaf::lang::Float::NEGATIVE_INFINITY` [static]

Constant for Negative Infinity.

6.364.3.5 `const float decaf::lang::Float::POSITIVE_INFINITY` [static]

Constant for Positive Infinity.

6.364.3.6 `const int decaf::lang::Float::SIZE = 32` [static]

The size in bits of the primitive int type.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Float.h`

6.365 decaf::internal::nio::FloatArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/FloatArrayBuffer.h> Inheritance diagram for decaf::internal::nio::FloatArrayBuffer:

Public Member Functions

- **FloatArrayBuffer** (int size, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **FloatArrayBuffer** (p. 1915) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **FloatArrayBuffer** (float *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **FloatArrayBuffer** (p. 1915) object that wraps the given array.*

- **FloatArrayBuffer** (const decaf::lang::Pointer< **ByteArrayAdapter** > &array, int offset, int capacity, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a byte buffer that wraps the passed **ByteArrayAdapter** and start at the given offset.*

- **FloatArrayBuffer** (const **FloatArrayBuffer** &other)

*Create a **FloatArrayBuffer** (p. 1915) that mirrors this one, meaning it shares a reference to this buffers **ByteArrayAdapter** and when changes are made to that data it is reflected in both.*

- virtual ~**FloatArrayBuffer** ()
- virtual float * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the float array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

*Invoke the **hasArray** method before invoking this method in order to ensure that this buffer has an accessible backing array.*

Returns:

*the array that backs this **Buffer** (p. 928).*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

*Invoke the **hasArray** method before invoking this method in order to ensure that this buffer has an accessible backing array.*

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual **FloatBuffer * asReadOnlyBuffer ()** const

Creates a new, read-only float buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only float buffer which the caller then owns.

- virtual **FloatBuffer & compact ()** throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

*a reference to this **FloatBuffer** (p. 1925).*

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual **FloatBuffer * duplicate ()**

Creates a new float buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*a new float **Buffer** (p. 928) which the caller owns.*

- virtual float **get ()** throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the float at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

- virtual float **get (int index)** const throw (lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the float is to be read

Returns:

the float that is located at the given index

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible float array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual FloatBuffer & **put** (float value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given floats into this buffer at the current position, and then increments the position.

Parameters:

value The floats value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit
ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual FloatBuffer & **put** (int index, float value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given floats into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.
value The floats to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.
ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual FloatBuffer * **slice** () const

Creates a new **FloatBuffer** (p. 1925) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*the newly create **FloatBuffer** (p. 1925) which the caller owns.*

Protected Member Functions

- virtual void **setReadOnly** (bool value)

*Sets this **FloatArrayBuffer** (p. 1915) as Read-Only.*

6.365.1 Constructor & Destructor Documentation

6.365.1.1 `decaf::internal::nio::FloatArrayBuffer::FloatArrayBuffer` (int *size*, bool *readOnly* = false) throw (`decaf::lang::exceptions::IllegalArgumentException`)

Creates a **FloatArrayBuffer** (p.1915) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

***IllegalArgumentException** if the capacity value is negative.*

6.365.1.2 `decaf::internal::nio::FloatArrayBuffer::FloatArrayBuffer` (float * *array*, int *size*, int *offset*, int *length*, bool *readOnly* = false) throw (`decaf::lang::exceptions::NullPointerException`, `decaf::lang::exceptions::IndexOutOfBoundsException`)

Creates a **FloatArrayBuffer** (p.1915) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.365.1.3 `decaf::internal::nio::FloatArrayBuffer::FloatArrayBuffer`
`(const decaf::lang::Pointer< ByteArrayAdapter > &`
`array, int offset, int capacity, bool readOnly = false)`
`throw (decaf::lang::exceptions::NullPointerException,`
`decaf::lang::exceptions::IndexOutOfBoundsException)`

Creates a byte buffer that wraps the passed `ByteArrayAdapter` and start at the given offset. The capacity and limit of the new `FloatArrayBuffer` (p. 1915) will be that of the remaining capacity of the passed buffer.

Parameters:

array The `ByteArrayAdapter` to wrap.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if array is NULL

IndexOutOfBoundsException if offset + length is greater than array size.

6.365.1.4 `decaf::internal::nio::FloatArrayBuffer::FloatArrayBuffer (const`
`FloatArrayBuffer & other)`

Create a `FloatArrayBuffer` (p. 1915) that mirrors this one, meaning it shares a reference to this buffers `ByteArrayAdapter` and when changes are made to that data it is reflected in both.

Parameters:

other The `FloatArrayBuffer` (p. 1915) this one is to mirror.

6.365.1.5 `virtual decaf::internal::nio::FloatArrayBuffer::~~FloatArrayBuffer ()`
`[virtual]`

6.365.2 Member Function Documentation

6.365.2.1 `virtual float* decaf::internal::nio::FloatArrayBuffer::array ()`
`throw (decaf::lang::exceptions::UnsupportedOperationException,`
`decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the float array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::FloatBuffer** (p. 1928).

6.365.2.2 `virtual int decaf::internal::nio::FloatArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::FloatBuffer** (p. 1928).

6.365.2.3 `virtual FloatBuffer* de-
caf::internal::nio::FloatArrayBuffer::asReadOnlyBuffer ()
const [virtual]`

Creates a new, read-only float buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only float buffer which the caller then owns.

Implements **decaf::nio::FloatBuffer** (p. 1928).

**6.365.2.4 virtual FloatBuffer& decaf::internal::nio::FloatArrayBuffer::compact ()
throw (decaf::nio::ReadOnlyBufferException) [virtual]**

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **FloatBuffer** (p. 1925).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::FloatBuffer** (p. 1929).

**6.365.2.5 virtual FloatBuffer* decaf::internal::nio::FloatArrayBuffer::duplicate ()
[virtual]**

Creates a new float buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new float **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::FloatBuffer** (p. 1929).

**6.365.2.6 virtual float decaf::internal::nio::FloatArrayBuffer::get (int *index*) const
throw (lang::exceptions::IndexOutOfBoundsException) [virtual]**

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the float is to be read

Returns:

the float that is located at the given index

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

Implements **decaf::nio::FloatBuffer** (p. 1930).

6.365.2.7 `virtual float decaf::internal::nio::FloatArrayBuffer::get () throw (decaf::nio::BufferUnderflowException) [virtual]`

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the float at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implements **decaf::nio::FloatBuffer** (p. 1931).

6.365.2.8 `virtual bool decaf::internal::nio::FloatArrayBuffer::hasArray () const [inline, virtual]`

Tells whether or not this buffer is backed by an accessible float array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implements **decaf::nio::FloatBuffer** (p. 1931).

6.365.2.9 `virtual bool decaf::internal::nio::FloatArrayBuffer::isReadOnly () const [inline, virtual]`

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.365.2.10 `virtual FloatBuffer& decaf::internal::nio::FloatArrayBuffer::put (int index, float value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes the given floats into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The floats to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::FloatBuffer** (p. 1931).

6.365.2.11 `virtual FloatBuffer& decaf::internal::nio::FloatArrayBuffer::put (float value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes the given floats into this buffer at the current position, and then increments the position.

Parameters:

value The floats value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::FloatBuffer** (p. 1932).

6.365.2.12 `virtual void decaf::internal::nio::FloatArrayBuffer::setReadOnly (bool value) [inline, protected, virtual]`

Sets this **FloatArrayBuffer** (p. 1915) as Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.365.2.13 `virtual FloatBuffer* decaf::internal::nio::FloatArrayBuffer::slice () const [virtual]`

Creates a new **FloatBuffer** (p. 1925) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **FloatBuffer** (p.1925) which the caller owns.

Implements **decaf::nio::FloatBuffer** (p.1934).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/FloatArrayBuffer.h`

6.366 decaf::nio::FloatBuffer Class Reference

This class defines four categories of operations upon float buffers:.

#include <src/main/decaf/nio/FloatBuffer.h> Inheritance diagram for decaf::nio::FloatBuffer:

Public Member Functions

- virtual **~FloatBuffer** ()
- virtual std::string **toString** () const
- virtual float * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the float array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **FloatBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only float buffer that shares this buffer's content.
- virtual **FloatBuffer** & **compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **FloatBuffer** * **duplicate** ()=0
Creates a new float buffer that shares this buffer's content.
- virtual float **get** ()=0 throw (BufferUnderflowException)
Relative get method.
- virtual float **get** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **FloatBuffer** & **get** (std::vector< float > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **FloatBuffer** & **get** (float *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible float array.
- **FloatBuffer** & **put** (**FloatBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the floats remaining in the given source buffer into this buffer.

- **FloatBuffer** & **put** (const float *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers floats into this buffer from the given source array.

- **FloatBuffer** & **put** (std::vector< float > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source floats array into this buffer.

- virtual **FloatBuffer** & **put** (float value)=0 throw (BufferOverflowException, ReadOnlyBufferException)

Writes the given floats into this buffer at the current position, and then increments the position.

- virtual **FloatBuffer** & **put** (int index, float value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)

Writes the given floats into this buffer at the given index.

- virtual **FloatBuffer** * **slice** () const =0

*Creates a new **FloatBuffer** (p. 1925) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **FloatBuffer** &value) const

- virtual bool **equals** (const **FloatBuffer** &value) const

- virtual bool **operator==** (const **FloatBuffer** &value) const

- virtual bool **operator<** (const **FloatBuffer** &value) const

Static Public Member Functions

- static **FloatBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

Allocates a new Double buffer.

- static **FloatBuffer** * **wrap** (float *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **FloatBuffer** (p. 1925).*

- static **FloatBuffer** * **wrap** (std::vector< float > &buffer)

*Wraps the passed STL float Vector in a **FloatBuffer** (p. 1925).*

Protected Member Functions

- **FloatBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **FloatBuffer** (p. 1925) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.366.1 Detailed Description

This class defines four categories of operations upon float buffers: o Absolute and relative get and put methods that read and write single floats; o Relative bulk get methods that transfer contiguous sequences of floats from this buffer into an array; and o Relative bulk put methods that transfer contiguous sequences of floats from a float array or some other float buffer into this buffer o Methods for compacting, duplicating, and slicing a float buffer.

Double buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing float array into a buffer, or by creating a view of an existing byte buffer

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained.

6.366.2 Constructor & Destructor Documentation

6.366.2.1 decaf::nio::FloatBuffer::FloatBuffer (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **FloatBuffer** (p. 1925) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size and limit of the **Buffer** (p. 928) in floats.

Exceptions:

IllegalArgumentException if capacity is negative.

6.366.2.2 virtual decaf::nio::FloatBuffer::~~FloatBuffer () [inline, virtual]

6.366.3 Member Function Documentation

6.366.3.1 static FloatBuffer* decaf::nio::FloatBuffer::allocate (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new Double buffer. The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Double buffer in floats.

Returns:

the **FloatBuffer** (p. 1925) that was allocated, caller owns.

6.366.3.2 `virtual float* decaf::nio::FloatBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the float array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::FloatArrayBuffer` (p. 1919).

6.366.3.3 `virtual int decaf::nio::FloatBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::FloatArrayBuffer` (p. 1920).

6.366.3.4 `virtual FloatBuffer* decaf::nio::FloatBuffer::asReadOnlyBuffer () const [pure virtual]`

Creates a new, read-only float buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only float buffer which the caller then owns.

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p. 1920).

6.366.3.5 virtual FloatBuffer& decaf::nio::FloatBuffer::compact () throw (ReadOnlyBufferException) [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **FloatBuffer** (p. 1925).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p. 1921).

6.366.3.6 virtual int decaf::nio::FloatBuffer::compareTo (const FloatBuffer & value) const [virtual]

6.366.3.7 virtual FloatBuffer* decaf::nio::FloatBuffer::duplicate () [pure virtual]

Creates a new float buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new float **Buffer** (p. 928) which the caller owns.

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p. 1921).

6.366.3.8 virtual bool decaf::nio::FloatBuffer::equals (const FloatBuffer & value) const [virtual]

6.366.3.9 FloatBuffer& decaf::nio::FloatBuffer::get (float * buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

Relative bulk get method. This method transfers floats from this buffer into the given destination array. If there are fewer floats remaining in the buffer than are required to satisfy the request, that is, if $\text{length} > \text{remaining}()$ (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies length floats from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by length.

Parameters:

buffer The pointer to an allocated buffer to fill.
size The size of the passed in buffer.
offset The position in the buffer to start filling.
length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length floats remaining in this buffer
NullPointerException if the passed buffer is null.
IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

**6.366.3.10 FloatBuffer& decaf::nio::FloatBuffer::get (std::vector< float > *buffer*)
 throw (BufferUnderflowException)**

Relative bulk get method. This method transfers values from this buffer into the given destination vector. An invocation of this method of the form src.get(a) behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call buffer.resize(N) before calling this get method.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length floats remaining in this buffer

6.366.3.11 virtual float decaf::nio::FloatBuffer::get (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the float is to be read

Returns:

the float that is located at the given index

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p.1921).

6.366.3.12 virtual float decaf::nio::FloatBuffer::get () throw (BufferUnderflowException) [pure virtual]

Relative get method. Reads the value at this buffer's current position, and then increments the position.

Returns:

the float at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p.1922).

6.366.3.13 virtual bool decaf::nio::FloatBuffer::hasArray () const [pure virtual]

Tells whether or not this buffer is backed by an accessible float array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only

Implemented in **decaf::internal::nio::FloatArrayBuffer** (p.1922).

6.366.3.14 virtual bool decaf::nio::FloatBuffer::operator< (const FloatBuffer & value) const [virtual]

6.366.3.15 virtual bool decaf::nio::FloatBuffer::operator== (const FloatBuffer & value) const [virtual]

6.366.3.16 virtual FloatBuffer& decaf::nio::FloatBuffer::put (int index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes the given floats into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The floats to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written, or index is negative.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::FloatArrayBuffer` (p. 1922).

6.366.3.17 `virtual FloatBuffer& decaf::nio::FloatBuffer::put (float value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes the given floats into this buffer at the current position, and then increments the position.

Parameters:

value The floats value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in `decaf::internal::nio::FloatArrayBuffer` (p. 1923).

6.366.3.18 `FloatBuffer& decaf::nio::FloatBuffer::put (std::vector< float > & buffer) throw (BufferOverflowException, ReadOnlyBufferException)`

This method transfers the entire content of the given source floats array into this buffer. This is the same as calling `put(&buffer[0], 0, buffer.size())`.

Parameters:

buffer The buffer whose contents are copied to this `FloatBuffer` (p. 1925)

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer

ReadOnlyBufferException (p. 3169) if this buffer is read-only

6.366.3.19 `FloatBuffer& decaf::nio::FloatBuffer::put (const float * buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)`

This method transfers floats into this buffer from the given source array. If there are more floats to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no floats are transferred and a `BufferOverflowException` (p. 954) is thrown.

Otherwise, this method copies length bytes from the given array into this buffer, starting at the given offset in the array and at the current position of this buffer. The position of this buffer is then incremented by length.

Parameters:

- buffer* The array from which floats are to be read.
- size* The size of the passed in buffer.
- offset* The offset within the array of the first float to be read.
- length* The number of floats to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

- BufferOverflowException** (p. 954) if there is insufficient space in this buffer
- ReadOnlyBufferException** (p. 3169) if this buffer is read-only
- NullPointerException** if the passed buffer is null.
- IndexOutOfBoundsException** if the preconditions of size, offset, or length are not met.

6.366.3.20 FloatBuffer& decaf::nio::FloatBuffer::put (FloatBuffer & src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the floats remaining in the given source buffer into this buffer. If there are more floats remaining in the source buffer than in this buffer, that is, if `src.remaining() > remaining()` (p. 933), then no floats are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` floats from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

- src* The buffer to take floats from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

- BufferOverflowException** (p. 954) if there is insufficient space in this buffer for the remaining floats in the source buffer
- IllegalArgumentException** if the source buffer is this buffer.
- ReadOnlyBufferException** (p. 3169) if this buffer is read-only.

6.366.3.21 `virtual FloatBuffer* decaf::nio::FloatBuffer::slice () const` [pure virtual]

Creates a new **FloatBuffer** (p. 1925) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **FloatBuffer** (p. 1925) which the caller owns.

Implemented in `decaf::internal::nio::FloatArrayBuffer` (p. 1923).

6.366.3.22 `virtual std::string decaf::nio::FloatBuffer::toString () const` [virtual]

Returns:

a `std::string` describing this object

6.366.3.23 `static FloatBuffer* decaf::nio::FloatBuffer::wrap (std::vector< float > & buffer)` [static]

Wraps the passed STL float Vector in a **FloatBuffer** (p. 1925). The new buffer will be backed by the given float array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer - The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new **FloatBuffer** (p. 1925) that is backed by *buffer*, caller owns.

6.366.3.24 `static FloatBuffer* decaf::nio::FloatBuffer::wrap (float * array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [static]

Wraps the passed buffer with a new **FloatBuffer** (p. 1925). The new buffer will be backed by the given float array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

- array* The array that will back the new buffer.
- size* The size of the array that was passed in.
- offset* The offset of the subarray to be used.
- length* The length of the subarray to be used.

Returns:

a new **FloatBuffer** (p. 1925) that is backed by buffer, caller owns.

Exceptions:

- NullPointerException* if the array pointer is NULL.
- IndexOutOfBoundsException* if the preconditions of size, offset, or length are not met.

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**FloatBuffer.h**

6.367 decaf::io::Flushable Class Reference

A **Flushable** (p. 1936) is a destination of data that can be flushed.

#include <src/main/decaf/io/Flushable.h> Inheritance diagram for decaf::io::Flushable:

Public Member Functions

- virtual **~Flushable** ()
- virtual void **flush** ()=0 throw (decaf::io::IOException)
Flushes this stream by writing any buffered output to the underlying stream.

6.367.1 Detailed Description

A **Flushable** (p. 1936) is a destination of data that can be flushed. The flush method is invoked to write any buffered output to the underlying stream.

Since:

1.0

6.367.2 Constructor & Destructor Documentation

6.367.2.1 virtual decaf::io::Flushable::~~Flushable () [inline, virtual]

6.367.3 Member Function Documentation

6.367.3.1 virtual void decaf::io::Flushable::flush () throw (decaf::io::IOException)
[pure virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Implemented in **decaf::internal::io::StandardErrorOutputStream** (p. 3580), **decaf::internal::io::StandardOutputStream** (p. 3585), **decaf::io::BufferedOutputStream** (p. 941), **decaf::io::FilterOutputStream** (p. 1902), **decaf::io::OutputStream** (p. 2910), and **decaf::io::OutputStreamWriter** (p. 2916).

The documentation for this class was generated from the following file:

- src/main/decaf/io/**Flushable.h**

6.368 activemq::commands::FlushCommand Class Reference

#include <src/main/activemq/commands/FlushCommand.h> Inheritance diagram for activemq::commands::FlushCommand:

Public Member Functions

- **FlushCommand** ()
- virtual **~FlushCommand** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **FlushCommand * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_FLUSHCOMMAND** = 15

6.368.1 Constructor & Destructor Documentation

6.368.1.1 `activemq::commands::FlushCommand::FlushCommand ()`

6.368.1.2 `virtual activemq::commands::FlushCommand::~~FlushCommand ()`
[virtual]

6.368.2 Member Function Documentation

6.368.2.1 `virtual FlushCommand* activemq::commands::FlushCommand::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.368.2.2 `virtual void activemq::commands::FlushCommand::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.368.2.3 `virtual bool activemq::commands::FlushCommand::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.368.2.4 `virtual unsigned char activemq::commands::FlushCommand::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.368.2.5 `virtual std::string activemq::commands::FlushCommand::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.368.2.6 `virtual Pointer<Command> activemq::commands::FlushCommand::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.368.3 Field Documentation

6.368.3.1 `const unsigned char activemq::commands::FlushCommand::ID _ - FLUSHCOMMAND = 15 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/FlushCommand.h`

6.369 activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1940).

#include <src/main/activemq/wireformat/openwire/marshal/v6/FlushCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.369.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1940).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.369.2 Constructor & Destructor Documentation

6.369.2.1 `activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.369.2.2 `virtual activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.369.3 Member Function Documentation

6.369.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.369.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.369.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.369.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.369.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.369.3.6 virtual void activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.369.3.7 virtual void activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/FlushCommandMarshaller.h

6.370 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1944).

#include <src/main/activemq/wireformat/openwire/marshal/v2/FlushCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.370.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1944).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.370.2 Constructor & Destructor Documentation

6.370.2.1 `activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.370.2.2 `virtual activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.370.3 Member Function Documentation

6.370.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.370.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.370.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.370.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.370.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.370.3.6 virtual void activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.370.3.7 virtual void activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/FlushCommandMarshaller.h

6.371 activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1948).

#include <src/main/activemq/wireformat/openwire/marshal/v3/FlushCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.371.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1948).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.371.2 Constructor & Destructor Documentation

6.371.2.1 `activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.371.2.2 `virtual activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.371.3 Member Function Documentation

6.371.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.371.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.371.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.371.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.371.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.371.3.6 virtual void activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.371.3.7 virtual void activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/FlushCommandMarshaller.h

6.372 activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1952).

#include <src/main/activemq/wireformat/openwire/marshal/v4/FlushCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.372.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1952).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.372.2 Constructor & Destructor Documentation

6.372.2.1 `activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.372.2.2 `virtual activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.372.3 Member Function Documentation

6.372.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.372.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.372.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.372.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.372.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.372.3.6 virtual void activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.372.3.7 virtual void activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**FlushCommandMarshaller.h**

6.373 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1956).

#include <src/main/activemq/wireformat/openwire/marshal/v1/FlushCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.373.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1956).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.373.2 Constructor & Destructor Documentation

6.373.2.1 `activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.373.2.2 `virtual activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.373.3 Member Function Documentation

6.373.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.373.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.373.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.373.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.373.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.373.3.6 virtual void activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.373.3.7 virtual void activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**FlushCommandMarshaller.h**

6.374 activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1960).

#include <src/main/activemq/wireformat/openwire/marshal/v5/FlushCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller:

Public Member Functions

- **FlushCommandMarshaller** ()
- virtual **~FlushCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.374.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **FlushCommandMarshaller** (p.1960).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.374.2 Constructor & Destructor Documentation

6.374.2.1 `activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::FlushCommandMarshaller()` [inline]

6.374.2.2 `virtual activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::~~FlushCommandMarshaller()` [inline, virtual]

6.374.3 Member Function Documentation

6.374.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.374.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.374.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.374.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.374.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.374.3.6 virtual void activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.374.3.7 virtual void activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/FlushCommandMarshaller.h

6.375 decaf::util::logging::Formatter Class Reference

A **Formatter** (p. 1964) provides support for formatting LogRecords.

#include <src/main/decaf/util/logging/Formatter.h> Inheritance diagram for decaf::util::logging::Formatter:

Public Member Functions

- virtual **~Formatter** ()
- virtual std::string **format** (const **LogRecord** &record) const =0
Format the given log record and return the formatted string.
- virtual std::string **formatMessage** (const **LogRecord** &record) const
Format the message string from a log record.
- virtual std::string **getHead** (const **Handler** *handler DECAF_UNUSED)
Return the header string for a set of formatted records.
- virtual std::string **getTail** (const **Handler** *handler DECAF_UNUSED)
Return the tail string for a set of formatted records.

6.375.1 Detailed Description

A **Formatter** (p. 1964) provides support for formatting LogRecords. Typically each **logging** (p. 175) **Handler** (p. 1978) will have a **Formatter** (p. 1964) associated with it. The **Formatter** (p. 1964) takes a **LogRecord** (p. 2413) and converts it to a string.

Some formatters (such as the **XMLFormatter** (p. 4060)) need to wrap head and tail strings around a set of formatted records. The **getHeader** and **getTail** methods can be used to obtain these strings.

6.375.2 Constructor & Destructor Documentation

6.375.2.1 virtual decaf::util::logging::Formatter::~~Formatter () [inline, virtual]

6.375.3 Member Function Documentation

6.375.3.1 virtual std::string decaf::util::logging::Formatter::format (const **LogRecord** & *record*) const [pure virtual]

Format the given log record and return the formatted string.

Parameters:

record The Log Record to Format

Returns:

the formatted record.

Implemented in `decaf::util::logging::SimpleFormatter` (p. 3500), and `decaf::util::logging::XMLFormatter` (p. 4060).

6.375.3.2 `virtual std::string decaf::util::logging::Formatter::formatMessage (const LogRecord & record) const` [virtual]

Format the message string from a log record.

Parameters:

record The Log Record to Format

Returns:

the formatted message

6.375.3.3 `virtual std::string decaf::util::logging::Formatter::getHead (const Handler *handler DECAF_UNUSED)` [inline, virtual]

Return the header string for a set of formatted records. In the default implementation this method should return empty string.

Parameters:

handler The target handler, can be NULL.

Returns:

the head string.

6.375.3.4 `virtual std::string decaf::util::logging::Formatter::getTail (const Handler *handler DECAF_UNUSED)` [inline, virtual]

Return the tail string for a set of formatted records. In the default implementation this method should return empty string

Parameters:

handler the target handler, can be null

Returns:

the tail string

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/Formatter.h`

6.376 decaf::util::concurrent::Future< V > Class Template Reference

A **Future** (p.1966) represents the result of an asynchronous computation.

```
#include <src/main/decaf/util/concurrent/Future.h>
```

Public Member Functions

- virtual **~Future** ()
- bool **cancel** (bool mayInterruptIfRunning)=0
Attempts to cancel execution of this task.
- bool **isCancelled** () const =0
Returns true if this task was canceled before it completed normally.
- bool **isDone** () const =0
Returns true if this task completed.
- V **get** ()=0 throw (CancellationException, InterruptedException, ExecutionException)
Waits if necessary for the computation to complete, and then retrieves its result.
- V **get** (long long timeout, **TimeUnit** unit)=0 throw (InterruptedException, ExecutionException, TimeoutException)
Waits if necessary for at most the given time for the computation to complete, and then retrieves its result, if available.

6.376.1 Detailed Description

```
template<typename V> class decaf::util::concurrent::Future< V >
```

A **Future** (p.1966) represents the result of an asynchronous computation. Methods are provided to check if the computation is complete, to wait for its completion, and to retrieve the result of the computation. The result can only be retrieved using method **get** when the computation has completed, blocking if necessary until it is ready. Cancellation is performed by the **cancel** method. Additional methods are provided to determine if the task completed normally or was canceled. Once a computation has completed, the computation cannot be canceled. If you would like to use a **Future** (p.1966) for the sake of cancellability but not provide a usable result, you can declare types of the form **Future<void*>** and return null as a result of the underlying task.

6.376.2 Constructor & Destructor Documentation

6.376.2.1 `template<typename V > virtual decaf::util::concurrent::Future< V >::~~Future () [inline, virtual]`

6.376.3 Member Function Documentation

6.376.3.1 `template<typename V > bool decaf::util::concurrent::Future< V >::cancel (bool mayInterruptIfRunning) [pure virtual]`

Attempts to cancel execution of this task. This attempt will fail if the task has already completed, has already been canceled, or could not be canceled for some other reason. If successful, and this task has not started when cancel is called, this task should never run. If the task has already started, then the *mayInterruptIfRunning* parameter determines whether the thread executing this task should be interrupted in an attempt to stop the task.

After this method returns, subsequent calls to **isDone()** (p. 1968) will always return true. Subsequent calls to **isCancelled()** (p. 1968) will always return true if this method returned true.

Parameters:

mayInterruptIfRunning - true if the thread executing this task should be interrupted; otherwise, in-progress tasks are allowed to complete.

Returns:

false if the task could not be canceled, typically because it has already completed normally;
true otherwise

6.376.3.2 `template<typename V > V decaf::util::concurrent::Future< V >::get (long long timeout, TimeUnit unit) throw (InterruptedException, ExecutionException, TimeoutException) [pure virtual]`

Waits if necessary for at most the given time for the computation to complete, and then retrieves its result, if available.

Parameters:

timeout - the maximum time to wait

unit - the time unit of the timeout argument

Returns:

the computed result

Exceptions:

CancellationException (p. 1083) - if the computation was canceled

ExecutionException (p. 1866) - if the computation threw an exception

InterruptedException - if the current thread was interrupted while waiting

TimeoutException (p. 3787) - if the wait timed out

6.376.3.3 `template<typename V > V decaf::util::concurrent::Future< V >::get () throw (CancellationException, InterruptedException, ExecutionException) [pure virtual]`

Waits if necessary for the computation to complete, and then retrieves its result.

Returns:

the computed result.

Exceptions:

CancellationException (p. 1083) - if the computation was canceled

ExecutionException (p. 1866) - if the computation threw an exception

InterruptedException - if the current thread was interrupted while waiting

6.376.3.4 `template<typename V > bool decaf::util::concurrent::Future< V >::isCancelled () const [pure virtual]`

Returns true if this task was canceled before it completed normally.

Returns:

true if this task was canceled before it completed

6.376.3.5 `template<typename V > bool decaf::util::concurrent::Future< V >::isDone () const [pure virtual]`

Returns true if this task completed. Completion may be due to normal termination, an exception, or cancellation -- in all of these cases, this method will return true.

Returns:

true if this task completed

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Future.h`

6.377 activemq::transport::correlator::FutureResponse Class Reference

A container that holds a response object.

```
#include <src/main/activemq/transport/correlator/FutureResponse.h>
```

Public Member Functions

- **FutureResponse** ()
- virtual **~FutureResponse** ()
- virtual const **Pointer**< **Response** > & **getResponse** () const
Getters for the response property.
- virtual **Pointer**< **Response** > & **getResponse** ()
- virtual const **Pointer**< **Response** > & **getResponse** (unsigned int timeout) const
Getters for the response property.
- virtual **Pointer**< **Response** > & **getResponse** (unsigned int timeout)
- virtual void **setResponse** (const **Pointer**< **Response** > &response)
Setter for the response property.

6.377.1 Detailed Description

A container that holds a response object. Callers of the `getResponse` method will block until a response has been receive unless they call the `getRepsonse` that takes a timeout.

6.377.2 Constructor & Destructor Documentation

6.377.2.1 `activemq::transport::correlator::FutureResponse::FutureResponse ()`
[inline]

6.377.2.2 `virtual`
`activemq::transport::correlator::FutureResponse::~~FutureResponse ()`
[inline, virtual]

6.377.3 Member Function Documentation

6.377.3.1 `virtual` `Pointer`<`Response`>& `activemq::transport::correlator::FutureResponse::getResponse (unsigned int timeout)` [inline, virtual]

6.377.3.2 `virtual` const `Pointer`<`Response`>& `activemq::transport::correlator::FutureResponse::getResponse (unsigned int timeout)` const [inline, virtual]

Getters for the response property. Timed Wait.

Parameters:

timeout - time to wait in milliseconds

Returns:

the response object for the request

6.377.3.3 `virtual Pointer<Response>& activemq::transport::correlator::FutureResponse::getResponse () [inline, virtual]`

6.377.3.4 `virtual const Pointer<Response>& activemq::transport::correlator::FutureResponse::getResponse () const [inline, virtual]`

Getters for the response property. Infinite Wait.

Returns:

the response object for the request

6.377.3.5 `virtual void activemq::transport::correlator::FutureResponse::setResponse (const Pointer< Response > & response) [inline, virtual]`

Setter for the response property.

Parameters:

response the response object for the request.

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/correlator/FutureResponse.h`

6.378 decaf::security::GeneralSecurityException Class Reference

#include <src/main/decaf/security/GeneralSecurityException.h> Inheritance diagram for decaf::security::GeneralSecurityException:

Public Member Functions

- **GeneralSecurityException** () throw ()
Default Constructor.
- **GeneralSecurityException** (const decaf::lang::Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **GeneralSecurityException** (const GeneralSecurityException &ex) throw ()
Copy Constructor.
- **GeneralSecurityException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **GeneralSecurityException** (const std::exception *cause) throw ()
Constructor.
- **GeneralSecurityException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **GeneralSecurityException** * clone () const
Clones this exception.
- virtual ~**GeneralSecurityException** () throw ()

6.378.1 Constructor & Destructor Documentation

6.378.1.1 decaf::security::GeneralSecurityException::GeneralSecurityException () throw () [inline]

Default Constructor.

6.378.1.2 decaf::security::GeneralSecurityException::GeneralSecurityException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.378.1.3 decaf::security::GeneralSecurityException::GeneralSecurityException (const GeneralSecurityException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.378.1.4 decaf::security::GeneralSecurityException::GeneralSecurityException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.378.1.5 decaf::security::GeneralSecurityException::GeneralSecurityException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.378.1.6 decaf::security::GeneralSecurityException::GeneralSecurityException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.378.1.7 virtual
 decaf::security::GeneralSecurityException::~~GeneralSecurityException ()
 throw () [inline, virtual]

6.378.2 Member Function Documentation

6.378.2.1 virtual GeneralSecurityException* de-
 caf::security::GeneralSecurityException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from **decaf::lang::Exception** (p. 1834).

Reimplemented in **decaf::security::cert::CertificateEncodingException**
 (p. 1091), **decaf::security::cert::CertificateException** (p. 1093), **de-
 caf::security::cert::CertificateExpiredException** (p. 1095), **de-
 caf::security::cert::CertificateNotYetValidException** (p. 1097), **de-
 caf::security::cert::CertificateParsingException** (p. 1099), **de-
 caf::security::InvalidKeyException** (p. 2134), **decaf::security::KeyException**
 (p. 2297), **decaf::security::KeyManagementException** (p. 2300),
decaf::security::NoSuchAlgorithmException (p. 2825), **de-
 caf::security::NoSuchProviderException** (p. 2831), and **de-
 caf::security::SignatureException** (p. 3499).

The documentation for this class was generated from the following file:

- src/main/decaf/security/**GeneralSecurityException.h**

6.379 decaf::internal::util::GenericResource< T > Class Template Reference

A Generic **Resource** (p. 3280) wraps some type and will delete it when the **Resource** (p. 3280) itself is deleted.

#include <src/main/decaf/internal/util/GenericResource.h> Inheritance diagram for decaf::internal::util::GenericResource< T >:

Public Member Functions

- **GenericResource** (T *value)
- virtual ~**GenericResource** ()
- T * **getManaged** () const
- void **setManaged** (T *value)

6.379.1 Detailed Description

```
template<typename T> class decaf::internal::util::GenericResource< T >
```

A Generic **Resource** (p. 3280) wraps some type and will delete it when the **Resource** (p. 3280) itself is deleted.

Since:

1.0

6.379.2 Constructor & Destructor Documentation

6.379.2.1 `template<typename T> decaf::internal::util::GenericResource< T >::GenericResource (T * value) [inline, explicit]`

6.379.2.2 `template<typename T> virtual decaf::internal::util::GenericResource< T >::~~GenericResource () [inline, virtual]`

6.379.3 Member Function Documentation

6.379.3.1 `template<typename T> T* decaf::internal::util::GenericResource< T >::getManaged () const [inline]`

6.379.3.2 `template<typename T> void decaf::internal::util::GenericResource< T >::setManaged (T * value) [inline]`

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/**GenericResource.h**

6.380 gz_header_s Struct Reference

```
#include <src/main/decaf/internal/util/zip/zlib.h>
```

Data Fields

- int text
- uLong time
- int xflags
- int os
- Bytef * extra
- uInt extra_len
- uInt extra_max
- Bytef * name
- uInt name_max
- Bytef * comment
- uInt comm_max
- int hcrc
- int done

6.380.1 Field Documentation

6.380.1.1 uInt gz_header_s::comm_max

6.380.1.2 Bytef* gz_header_s::comment

6.380.1.3 int gz_header_s::done

6.380.1.4 Bytef* gz_header_s::extra

6.380.1.5 uInt gz_header_s::extra_len

6.380.1.6 uInt gz_header_s::extra_max

6.380.1.7 int gz_header_s::hcrc

6.380.1.8 Bytef* gz_header_s::name

6.380.1.9 uInt gz_header_s::name_max

6.380.1.10 int gz_header_s::os

6.380.1.11 int gz_header_s::text

6.380.1.12 uLong gz_header_s::time

6.380.1.13 int gz_header_s::xflags

The documentation for this struct was generated from the following file:

- src/main/decaf/internal/util/zip/zlib.h

6.381 gz_state Struct Reference

```
#include <src/main/decaf/internal/util/zip/gzguts.h>
```

Data Fields

- int **mode**
- int **fd**
- char * **path**
- z_off64_t **pos**
- unsigned **size**
- unsigned **want**
- unsigned char * **in**
- unsigned char * **out**
- unsigned char * **next**
- unsigned **have**
- int **eof**
- z_off64_t **start**
- z_off64_t **raw**
- int **how**
- int **direct**
- int **level**
- int **strategy**
- z_off64_t **skip**
- int **seek**
- int **err**
- char * **msg**
- z_stream **strm**

6.381.1 Field Documentation

- 6.381.1.1 `int gz_state::direct`
- 6.381.1.2 `int gz_state::eof`
- 6.381.1.3 `int gz_state::err`
- 6.381.1.4 `int gz_state::fd`
- 6.381.1.5 `unsigned gz_state::have`
- 6.381.1.6 `int gz_state::how`
- 6.381.1.7 `unsigned char* gz_state::in`
- 6.381.1.8 `int gz_state::level`
- 6.381.1.9 `int gz_state::mode`
- 6.381.1.10 `char* gz_state::msg`
- 6.381.1.11 `unsigned char* gz_state::next`
- 6.381.1.12 `unsigned char* gz_state::out`
- 6.381.1.13 `char* gz_state::path`
- 6.381.1.14 `z_off64_t gz_state::pos`
- 6.381.1.15 `z_off64_t gz_state::raw`
- 6.381.1.16 `int gz_state::seek`
- 6.381.1.17 `unsigned gz_state::size`
- 6.381.1.18 `z_off64_t gz_state::skip`
- 6.381.1.19 `z_off64_t gz_state::start`
- 6.381.1.20 `int gz_state::strategy`
- 6.381.1.21 `z_stream gz_state::strm`
- 6.381.1.22 `unsigned gz_state::want`

The documentation for this struct was generated from the following file:

- `src/main/decaf/internal/util/zip/gzguts.h`

6.382 decaf::util::logging::Handler Class Reference

A **Handler** (p. 1978) object takes log messages from a **Logger** (p. 2386) and exports them.

#include <src/main/decaf/util/logging/Handler.h> Inheritance diagram for decaf::util::logging::Handler:

Public Member Functions

- **Handler** ()
- virtual **~Handler** ()
- virtual void **flush** ()=0
Flush the Handler's output, clears any buffers.
- virtual void **publish** (const **LogRecord** &record)=0
*Publish the Log Record to this **Handler** (p. 1978).*
- virtual bool **isLoggable** (const **LogRecord** &record) const
*Check if this **Handler** (p. 1978) would actually log a given **LogRecord** (p. 2413).*
- virtual void **setFilter** (**Filter** *filter)
*Sets the **Filter** (p. 1893) that this **Handler** (p. 1978) uses to filter Log Records.*
- virtual **Filter** * **getFilter** ()
*Gets the **Filter** (p. 1893) that this **Handler** (p. 1978) uses to filter Log Records.*
- virtual void **setLevel** (const **Level** &value)
*Set (p. 3439) the log level specifying which message levels will be logged by this **Handler** (p. 1978).*
- virtual **Level** **getLevel** ()
*Get the log level specifying which message levels will be logged by this **Handler** (p. 1978).*
- virtual void **setFormatter** (**Formatter** *formatter)
*Sets the **Formatter** (p. 1964) used by this **Handler** (p. 1978).*
- virtual **Formatter** * **getFormatter** ()
*Gets the **Formatter** (p. 1964) used by this **Handler** (p. 1978).*
- virtual void **setErrorManager** (**ErrorManager** *errorManager)
*Sets the **Formatter** (p. 1964) used by this **Handler** (p. 1978).*
- virtual **ErrorManager** * **getErrorManager** ()
*Gets the **ErrorManager** (p. 1828) used by this **Handler** (p. 1978).*

Protected Member Functions

- void **reportError** (const std::string &message, **decaf::lang::Exception** *ex, int code)
*Protected convenience method to report an error to this Handler's **ErrorManager** (p. 1828).*

6.382.1 Detailed Description

A **Handler** (p.1978) object takes log messages from a **Logger** (p.2386) and exports them. It might for example, write them to a console or write them to a file, or send them to a network **logging** (p.175) service, or forward them to an OS log, or whatever.

A **Handler** (p.1978) can be disabled by doing a **setLevel(Level.OFF** (p.2336)) and can be re-enabled by doing a **setLevel** with an appropriate level.

Handler (p.1978) classes typically use **LogManager** (p.2406) properties to set default values for the Handler's **Filter** (p.1893), **Formatter** (p.1964), and **Level** (p.2332). See the specific documentation for each concrete **Handler** (p.1978) class.

6.382.2 Constructor & Destructor Documentation

6.382.2.1 **decaf::util::logging::Handler::Handler** ()

6.382.2.2 **virtual decaf::util::logging::Handler::~~Handler** () [virtual]

6.382.3 Member Function Documentation

6.382.3.1 **virtual void decaf::util::logging::Handler::flush** () [pure virtual]

Flush the Handler's output, clears any buffers.

Implemented in **decaf::util::logging::StreamHandler** (p.3651).

6.382.3.2 **virtual ErrorManager* decaf::util::logging::Handler::getErrorManager** ()
[inline, virtual]

Gets the **ErrorManager** (p.1828) used by this **Handler** (p.1978).

Returns:

ErrorManager (p.1828) derived pointer or NULL.

6.382.3.3 **virtual Filter* decaf::util::logging::Handler::getFilter** () [inline, virtual]

Gets the **Filter** (p.1893) that this **Handler** (p.1978) uses to filter Log Records.

Returns:

Filter (p.1893) derived instance

6.382.3.4 virtual Formatter* decaf::util::logging::Handler::getFormatter () [inline, virtual]

Gets the **Formatter** (p. 1964) used by this **Handler** (p. 1978).

Returns:

Filter (p. 1893) derived instance

6.382.3.5 virtual Level decaf::util::logging::Handler::getLevel () [inline, virtual]

Get the log level specifying which message levels will be logged by this **Handler** (p. 1978).

Returns:

Level (p. 2332) enumeration value

6.382.3.6 virtual bool decaf::util::logging::Handler::isLoggable (const LogRecord & record) const [virtual]

Check if this **Handler** (p. 1978) would actually log a given **LogRecord** (p. 2413). This method checks if the **LogRecord** (p. 2413) has an appropriate **Level** (p. 2332) and whether it satisfies any **Filter** (p. 1893). It also may make other **Handler** (p. 1978) specific checks that might prevent a handler from **logging** (p. 175) the **LogRecord** (p. 2413).

Parameters:

record **LogRecord** (p. 2413) to check

Reimplemented in **decaf::util::logging::StreamHandler** (p. 3651).

6.382.3.7 virtual void decaf::util::logging::Handler::publish (const LogRecord & record) [pure virtual]

Publish the Log Record to this **Handler** (p. 1978).

Parameters:

record The Log Record to Publish

Implemented in **decaf::util::logging::ConsoleHandler** (p. 1400), and **decaf::util::logging::StreamHandler** (p. 3651).

6.382.3.8 void decaf::util::logging::Handler::reportError (const std::string & message, decaf::lang::Exception * ex, int code) [protected]

Protected convenience method to report an error to this Handler's **ErrorManager** (p. 1828).

Parameters:

message - a descriptive string (may be empty)

ex - an exception (may be NULL)

code (p. 1183) - an error **code** (p. 1183) defined in **ErrorManager** (p. 1828)

6.382.3.9 virtual void decaf::util::logging::Handler::setErrorManager (ErrorManager * *errorManager*) [virtual]

Sets the **Formatter** (p.1964) used by this **Handler** (p.1978). The **ErrorManager**'s "error" method will be invoked if any errors occur while using this **Handler** (p.1978).

Parameters:

errorManager **ErrorManager** (p.1828) derived instance

6.382.3.10 virtual void decaf::util::logging::Handler::setFilter (Filter * *filter*) [inline, virtual]

Sets the **Filter** (p.1893) that this **Handler** (p.1978) uses to filter Log Records. For each call of publish the **Handler** (p.1978) will call this **Filter** (p.1893) (if it is non-null) to check if the **LogRecord** (p.2413) should be published or discarded.

Parameters:

filter **Filter** (p.1893) derived instance

6.382.3.11 virtual void decaf::util::logging::Handler::setFormatter (Formatter * *formatter*) [virtual]

Sets the **Formatter** (p.1964) used by this **Handler** (p.1978). Some **Handlers** may not use **Formatters**, in which case the **Formatter** (p.1964) will be remembered, but not used.

Parameters:

formatter **Filter** (p.1893) derived instance

6.382.3.12 virtual void decaf::util::logging::Handler::setLevel (const Level & *value*) [inline, virtual]

Set (p.3439) the log level specifying which message levels will be logged by this **Handler** (p.1978). The intention is to allow developers to turn on voluminous **logging** (p.175), but to limit the messages that are sent to certain **Handlers**.

Parameters:

value **Level** (p.2332) enumeration value

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**Handler.h**

6.383 decaf::internal::util::HexStringParser Class Reference

```
#include <src/main/decaf/internal/util/HexStringParser.h>
```

Public Member Functions

- **HexStringParser** (int exponentWidth, int mantissaWidth)
Create a new HexParser.
- virtual **~HexStringParser** ()
- long long **parse** (const std::string &hexString)
Parses a hex string using the specs given in the constructor and returns a long long with the bits of the parsed string, the caller can then convert those to a float or double as needed.

Static Public Member Functions

- static double **parseDouble** (const std::string &hexString)
- static float **parseFloat** (const std::string &hexString)

6.383.1 Constructor & Destructor Documentation

6.383.1.1 decaf::internal::util::HexStringParser::HexStringParser (int exponentWidth, int mantissaWidth)

Create a new HexParser.

Parameters:

- exponentWidth* - Width of the exponent for the type to parse
mantissaWidth - Width of the mantissa for the type to parse

6.383.1.2 virtual decaf::internal::util::HexStringParser::~~HexStringParser () [inline, virtual]

6.383.2 Member Function Documentation

6.383.2.1 long long decaf::internal::util::HexStringParser::parse (const std::string &hexString)

Parses a hex string using the specs given in the constructor and returns a long long with the bits of the parsed string, the caller can then convert those to a float or double as needed.

Parameters:

- hexString* - string to parse

Returns:

- the bits parsed from the string

6.383.2.2 static double decaf::internal::util::HexStringParser::parseDouble (const std::string & *hexString*) [static]

6.383.2.3 static float decaf::internal::util::HexStringParser::parseFloat (const std::string & *hexString*) [static]

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/**HexStringParser.h**

6.384 activemq::wireformat::openwire::utils::HexTable Class Reference

The **HexTable** (p.1984) class maps hexadecimal strings to the value of an index into the table, i.e.

```
#include <src/main/activemq/wireformat/openwire/utils/HexTable.h>
```

Public Member Functions

- **HexTable** ()
- virtual **~HexTable** ()
- virtual const std::string & **operator[]** (std::size_t index) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Index operator for this Table, will throw an exception if the index requested is out of bounds for this table.

- virtual const std::string & **operator[]** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual std::size_t **size** () const

Returns the max size of this Table.

6.384.1 Detailed Description

The **HexTable** (p.1984) class maps hexadecimal strings to the value of an index into the table, i.e. the class will return "FF" for the index 255 in the table.

6.384.2 Constructor & Destructor Documentation

6.384.2.1 activemq::wireformat::openwire::utils::HexTable::HexTable ()

6.384.2.2 virtual activemq::wireformat::openwire::utils::HexTable::~~HexTable ()
[inline, virtual]

6.384.3 Member Function Documentation

6.384.3.1 virtual const std::string&
activemq::wireformat::openwire::utils::HexTable::operator[] (std::size_t
index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException
) [virtual]

6.384.3.2 virtual const std::string&
activemq::wireformat::openwire::utils::HexTable::operator[] (std::size_t
index) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
[virtual]

Index operator for this Table, will throw an exception if the index requested is out of bounds for this table.

Parameters:

index The index of the value in the table to fetch.

Returns:

string containing the hex value if the index

Exceptions:

IndexOutOfBoundsException

6.384.3.3 `virtual std::size_t activemq::wireformat::openwire::utils::HexTable::size
() const [inline, virtual]`

Returns the max size of this Table.

Returns:

an integer size value

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/utils/HexTable.h`

6.385 decaf::net::HttpRetryException Class Reference

#include <src/main/decaf/net/HttpRetryException.h> Inheritance diagram for decaf::net::HttpRetryException:

Public Member Functions

- **HttpRetryException** () throw ()
Default Constructor.
- **HttpRetryException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **HttpRetryException** (const **HttpRetryException** &ex) throw ()
Copy Constructor.
- **HttpRetryException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **HttpRetryException** (const std::exception *cause) throw ()
Constructor.
- **HttpRetryException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **HttpRetryException** * **clone** () const
Clones this exception.
- virtual ~**HttpRetryException** () throw ()

6.385.1 Constructor & Destructor Documentation

6.385.1.1 decaf::net::HttpRetryException::HttpRetryException () throw () [inline]

Default Constructor.

6.385.1.2 decaf::net::HttpRetryException::HttpRetryException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.385.1.3 decaf::net::HttpRetryException::HttpRetryException (const HttpRetryException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.385.1.4 decaf::net::HttpRetryException::HttpRetryException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.385.1.5 decaf::net::HttpRetryException::HttpRetryException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.385.1.6 decaf::net::HttpRetryException::HttpRetryException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.385.1.7 `virtual decaf::net::HttpRetryException::~~HttpRetryException () throw
() [inline, virtual]`

6.385.2 Member Function Documentation

6.385.2.1 `virtual HttpRetryException* decaf::net::HttpRetryException::clone ()
const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/HttpRetryException.h`

6.386 activemq::util::IdGenerator Class Reference

```
#include <src/main/activemq/util/IdGenerator.h>
```

Data Structures

- class **StaticData**

Public Member Functions

- **IdGenerator** ()
- **IdGenerator** (const std::string &prefix)
- virtual **~IdGenerator** ()
- std::string **generateId** () const

Static Public Member Functions

- static std::string **getHostname** ()
Since the initialization of this object results in the retrieval of the machine's host name we can quickly return it here.
- static std::string **getSeedFromId** (const std::string &id)
Gets the seed value from a Generated Id, the count portion is removed.
- static long long **getSequenceFromId** (const std::string &id)
Gets the count value from a Generated Id, the seed portion is removed.
- static int **compare** (const std::string &id1, const std::string &id2)
Compares two generated id values.

6.386.1 Constructor & Destructor Documentation

6.386.1.1 activemq::util::IdGenerator::IdGenerator ()

6.386.1.2 activemq::util::IdGenerator::IdGenerator (const std::string & *prefix*)

6.386.1.3 virtual activemq::util::IdGenerator::~~IdGenerator () [virtual]

6.386.2 Member Function Documentation

6.386.2.1 static int activemq::util::IdGenerator::compare (const std::string & *id1*, const std::string & *id2*) [static]

Compares two generated id values.

Parameters:

id1 The first id to compare, or left hand side.

id2 The second id to compare, or right hand side.

Returns:

zero if ids are equal or positive if $id1 > id2$...

6.386.2.2 `std::string activemq::util::IdGenerator::generateId () const`**Returns:**

a newly generated unique id.

6.386.2.3 `static std::string activemq::util::IdGenerator::getHostname () [static]`

Since the initialization of this object results in the retrieval of the machine's host name we can quickly return it here.

Returns:

the previously retrieved host name.

6.386.2.4 `static std::string activemq::util::IdGenerator::getSeedFromId (const std::string & id) [static]`

Gets the seed value from a Generated Id, the count portion is removed.

Returns:

the seed portion of the Id, minus the count value.

6.386.2.5 `static long long activemq::util::IdGenerator::getSequenceFromId (const std::string & id) [static]`

Gets the count value from a Generated Id, the seed portion is removed.

Returns:

the sequence count portion of the id, minus the seed value.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/IdGenerator.h`

6.387 decaf::lang::exceptions::IllegalArgumentException Class Reference

#include <src/main/decaf/lang/exceptions/IllegalArgumentException.h>Inheritance diagram for decaf::lang::exceptions::IllegalArgumentException:

Public Member Functions

- **IllegalArgumentException** () throw ()
Default Constructor.
- **IllegalArgumentException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **IllegalArgumentException** (const **IllegalArgumentException** &ex) throw ()
Copy Constructor.
- **IllegalArgumentException** (const std::exception *cause) throw ()
Constructor.
- **IllegalArgumentException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalArgumentException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **IllegalArgumentException** * **clone** () const
Clones this exception.
- virtual ~**IllegalArgumentException** () throw ()

6.387.1 Constructor & Destructor Documentation

6.387.1.1 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException () throw () [inline]

Default Constructor.

6.387.1.2 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException (const Exception & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

**6.387.1.3 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException
(const IllegalArgumentException & *ex*) throw () [inline]**

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

**6.387.1.4 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException
(const std::exception * *cause*) throw () [inline]**

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

**6.387.1.5 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException
(const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()
[inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

**6.387.1.6 decaf::lang::exceptions::IllegalArgumentException::IllegalArgumentException
(const char * *file*, const int *lineNumber*, const std::exception * *cause*,
const char * *msg*, ...) throw () [inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.387.1.7 virtual
decaf::lang::exceptions::IllegalArgumentException::~~IllegalArgumentException
() throw () [inline, virtual]

6.387.2 Member Function Documentation

6.387.2.1 virtual IllegalArgumentException* de-
cafe::lang::exceptions::IllegalArgumentException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**IllegalArgumentException.h**

6.388 decaf::lang::exceptions::IllegalMonitorStateException Class Reference

#include <src/main/decaf/lang/exceptions/IllegalMonitorStateException.h> Inheritance diagram for decaf::lang::exceptions::IllegalMonitorStateException:

Public Member Functions

- **IllegalMonitorStateException** () throw ()
Default Constructor.
- **IllegalMonitorStateException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **IllegalMonitorStateException** (const **IllegalMonitorStateException** &ex) throw ()
Copy Constructor.
- **IllegalMonitorStateException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalMonitorStateException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalMonitorStateException** (const std::exception *cause) throw ()
Constructor.
- virtual **IllegalMonitorStateException** * clone () const
Clones this exception.
- virtual ~**IllegalMonitorStateException** () throw ()

6.388.1 Constructor & Destructor Documentation

6.388.1.1 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException () throw () [inline]

Default Constructor.

6.388.1.2 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.388.1.3 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException (const IllegalMonitorStateException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.388.1.4 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.388.1.5 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.388.1.6 decaf::lang::exceptions::IllegalMonitorStateException::IllegalMonitorStateException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.388.1.7 **virtual**
decaf::lang::exceptions::IllegalMonitorStateException::~~IllegalMonitorStateException
() throw () [inline, virtual]

6.388.2 Member Function Documentation

6.388.2.1 **virtual IllegalMonitorStateException* de-**
caf::lang::exceptions::IllegalMonitorStateException::clone
() const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/IllegalMonitorStateException.h`

6.389 cms::IllegalStateException Class Reference

This exception is thrown when a method is invoked at an illegal or inappropriate time or if the provider is not in an appropriate state for the requested operation.

#include <src/main/cms/IllegalStateException.h> Inheritance diagram for cms::IllegalStateException:

Public Member Functions

- **IllegalStateException** () throw ()
- **IllegalStateException** (const **IllegalStateException** &ex) throw ()
- **IllegalStateException** (const std::string &message, const std::exception *cause) throw ()
- **IllegalStateException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**IllegalStateException** () throw ()

6.389.1 Detailed Description

This exception is thrown when a method is invoked at an illegal or inappropriate time or if the provider is not in an appropriate state for the requested operation. For example, this exception must be thrown if **Session.commit** (p. 3369) is called on a non-transacted session.

Since:

1.3

6.389.2 Constructor & Destructor Documentation

6.389.2.1 cms::IllegalStateException::IllegalStateException () throw ()

6.389.2.2 cms::IllegalStateException::IllegalStateException (const **IllegalStateException** & ex) throw ()

6.389.2.3 cms::IllegalStateException::IllegalStateException (const std::string & *message*, const std::exception * *cause*) throw ()

6.389.2.4 cms::IllegalStateException::IllegalStateException (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()

6.389.2.5 virtual cms::IllegalStateException::~~IllegalStateException () throw ()
[virtual]

The documentation for this class was generated from the following file:

- src/main/cms/**IllegalStateException.h**

6.390 decaf::lang::exceptions::IllegalStateException Class Reference

#include <src/main/decaf/lang/exceptions/IllegalStateException.h> Inheritance diagram for decaf::lang::exceptions::IllegalStateException:

Public Member Functions

- **IllegalStateException** () throw ()
Default Constructor.
- **IllegalStateException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **IllegalStateException** (const **IllegalStateException** &ex) throw ()
Copy Constructor.
- **IllegalStateException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalStateException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalStateException** (const std::exception *cause) throw ()
Constructor.
- virtual **IllegalStateException** * clone () const
Clones this exception.
- virtual ~**IllegalStateException** () throw ()

6.390.1 Constructor & Destructor Documentation

6.390.1.1 decaf::lang::exceptions::IllegalStateException::IllegalStateException () throw () [inline]

Default Constructor.

6.390.1.2 decaf::lang::exceptions::IllegalStateException::IllegalStateException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

**6.390.1.3 decaf::lang::exceptions::IllegalStateException::IllegalStateException
(const IllegalStateException & *ex*) throw () [inline]**

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

**6.390.1.4 decaf::lang::exceptions::IllegalStateException::IllegalStateException
(const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()
[inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

**6.390.1.5 decaf::lang::exceptions::IllegalStateException::IllegalStateException
(const char * *file*, const int *lineNumber*, const std::exception * *cause*,
const char * *msg*, ...) throw () [inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

**6.390.1.6 decaf::lang::exceptions::IllegalStateException::IllegalStateException
(const std::exception * *cause*) throw () [inline]**

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.390.1.7 **virtual**
 decaf::lang::exceptions::IllegalStateException::~~IllegalStateException ()
 throw () [inline, virtual]

6.390.2 Member Function Documentation

6.390.2.1 **virtual IllegalStateException* de-**
 caf::lang::exceptions::IllegalStateException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

Reimplemented in **decaf::nio::InvalidMarkException** (p. 2137).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/IllegalStateException.h`

6.391 decaf::lang::exceptions::IllegalThreadStateException Class Reference

#include <src/main/decaf/lang/exceptions/IllegalThreadStateException.h> Inheritance diagram for decaf::lang::exceptions::IllegalThreadStateException:

Public Member Functions

- **IllegalThreadStateException** () throw ()
Default Constructor.
- **IllegalThreadStateException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **IllegalThreadStateException** (const **IllegalThreadStateException** &ex) throw ()
Copy Constructor.
- **IllegalThreadStateException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalThreadStateException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IllegalThreadStateException** (const std::exception *cause) throw ()
Constructor.
- virtual **IllegalThreadStateException** * clone () const
Clones this exception.
- virtual ~**IllegalThreadStateException** () throw ()

6.391.1 Constructor & Destructor Documentation

6.391.1.1 decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException () throw () [inline]

Default Constructor.

6.391.1.2 decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.391.1.3 `decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException (const IllegalThreadStateException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.391.1.4 `decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.391.1.5 `decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.391.1.6 `decaf::lang::exceptions::IllegalThreadStateException::IllegalThreadStateException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.391.1.7 virtual
decaf::lang::exceptions::IllegalThreadStateException::~~IllegalThreadStateException
() throw () [inline, virtual]

6.391.2 Member Function Documentation

6.391.2.1 virtual IllegalThreadStateException* de-
caf::lang::exceptions::IllegalThreadStateException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**IllegalThreadStateException.h**

6.392 activemq::transport::inactivity::InactivityMonitor

Class Reference

#include <src/main/activemq/transport/inactivity/InactivityMonitor.h> Inheritance diagram for activemq::transport::inactivity::InactivityMonitor:

Public Member Functions

- **InactivityMonitor** (const **Pointer**< **Transport** > &next, const **Pointer**< **wireformat::WireFormat** > &wireFormat)
- **InactivityMonitor** (const **Pointer**< **Transport** > &next, const **decaf::util::Properties** &properties, const **Pointer**< **wireformat::WireFormat** > &wireFormat)
- virtual ~**InactivityMonitor** ()
- virtual void **close** () throw (decaf::io::IOException)
Stops the polling thread and closes the streams.
- virtual void **onException** (const **decaf::lang::Exception** &ex)
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **onCommand** (const **Pointer**< **Command** > &command)
Event handler for the receipt of a command.
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- bool **isKeepAliveResponseRequired** () const
- void **setKeepAliveResponseRequired** (bool value)
- long long **getReadCheckTime** () const
- void **setReadCheckTime** (long long value)
- long long **getWriteCheckTime** () const
- void **setWriteCheckTime** (long long value)
- long long **getInitialDelayTime** () const
- void **setInitialDelayTime** (long long value) const

Friends

- class **ReadChecker**
- class **AsyncSignalReadErrorTask**
- class **WriteChecker**
- class **AsyncWriteTask**

6.392.1 Constructor & Destructor Documentation

- 6.392.1.1 `activemq::transport::inactivity::InactivityMonitor::InactivityMonitor (const Pointer< Transport > & next, const Pointer< wireformat::WireFormat > & wireFormat)`
- 6.392.1.2 `activemq::transport::inactivity::InactivityMonitor::InactivityMonitor (const Pointer< Transport > & next, const decaf::util::Properties & properties, const Pointer< wireformat::WireFormat > & wireFormat)`
- 6.392.1.3 `virtual
activemq::transport::inactivity::InactivityMonitor::~~InactivityMonitor ()
[virtual]`

6.392.2 Member Function Documentation

- 6.392.2.1 `virtual void activemq::transport::inactivity::InactivityMonitor::close ()
throw (decaf::io::IOException) [virtual]`

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if an error occurs while closing the **Transport** (p. 3883).

Reimplemented from **activemq::transport::TransportFilter** (p. 3893).

- 6.392.2.2 `long long ac-
tivemq::transport::inactivity::InactivityMonitor::getInitialDelayTime ()
const`
- 6.392.2.3 `long long ac-
tivemq::transport::inactivity::InactivityMonitor::getReadCheckTime ()
const`
- 6.392.2.4 `long long ac-
tivemq::transport::inactivity::InactivityMonitor::getWriteCheckTime ()
const`
- 6.392.2.5 `bool ac-
tivemq::transport::inactivity::InactivityMonitor::isKeepAliveResponseRequired
() const`
- 6.392.2.6 `virtual void ac-
tivemq::transport::inactivity::InactivityMonitor::onCommand (const
Pointer< Command > & command) [virtual]`

Event handler for the receipt of a command.

Parameters:

command - the received command object.

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.392.2.7 `virtual void activemq::transport::inactivity::InactivityMonitor::oneway
(const Pointer< Command > & command) throw (decaf::io::IOException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.392.2.8 `virtual void ac-
tivemq::transport::inactivity::InactivityMonitor::onException (const
decaf::lang::Exception & ex) [virtual]`

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception to handle.

Reimplemented from **activemq::transport::TransportFilter** (p. 3896).

- 6.392.2.9** void activemq::transport::inactivity::InactivityMonitor::setInitialDelayTime (long long *value*) const
- 6.392.2.10** void activemq::transport::inactivity::InactivityMonitor::setKeepAliveResponseRequired (bool *value*)
- 6.392.2.11** void activemq::transport::inactivity::InactivityMonitor::setReadCheckTime (long long *value*)
- 6.392.2.12** void activemq::transport::inactivity::InactivityMonitor::setWriteCheckTime (long long *value*)

6.392.3 Friends And Related Function Documentation

- 6.392.3.1** friend class AsyncSignalReadErrorTask [friend]
- 6.392.3.2** friend class AsyncWriteTask [friend]
- 6.392.3.3** friend class ReadChecker [friend]
- 6.392.3.4** friend class WriteChecker [friend]

The documentation for this class was generated from the following file:

- src/main/activemq/transport/inactivity/**InactivityMonitor.h**

6.393 decaf::lang::exceptions::IndexOutOfBoundsException Class Reference

#include <src/main/decaf/lang/exceptions/IndexOutOfBoundsException.h>Inheritance diagram for decaf::lang::exceptions::IndexOutOfBoundsException:

Public Member Functions

- **IndexOutOfBoundsException** () throw ()
Default Constructor.
- **IndexOutOfBoundsException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **IndexOutOfBoundsException** (const **IndexOutOfBoundsException** &ex) throw ()
Copy Constructor.
- **IndexOutOfBoundsException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IndexOutOfBoundsException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IndexOutOfBoundsException** (const std::exception *cause) throw ()
Constructor.
- virtual **IndexOutOfBoundsException** * clone () const
Clones this exception.
- virtual ~**IndexOutOfBoundsException** () throw ()

6.393.1 Constructor & Destructor Documentation

6.393.1.1 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException () throw () [inline]

Default Constructor.

6.393.1.2 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.393.1.3 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException (const IndexOutOfBoundsException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.393.1.4 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.393.1.5 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.393.1.6 decaf::lang::exceptions::IndexOutOfBoundsException::IndexOutOfBoundsException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.393.1.7 **virtual**
decaf::lang::exceptions::IndexOutOfBoundsException::~~IndexOutOfBoundsException
() throw () [inline, virtual]

6.393.2 **Member Function Documentation**

6.393.2.1 **virtual IndexOutOfBoundsException* de-**
caf::lang::exceptions::IndexOutOfBoundsException::clone
() const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**IndexOutOfBoundsException.h**

6.394 decaf::net::Inet4Address Class Reference

#include <src/main/decaf/net/Inet4Address.h> Inheritance diagram for decaf::net::Inet4Address:

Public Member Functions

- virtual `~Inet4Address ()`
- virtual bool `isAnyLocalAddress ()` const
*Check if this **InetAddress** (p. 2016) is a valid wildcard address.*
- virtual bool `isLoopbackAddress ()` const
*Check if this **InetAddress** (p. 2016) is a valid loopback address.*
- virtual bool `isMulticastAddress ()` const
*Check if this **InetAddress** (p. 2016) is a valid Multicast address.*
- virtual bool `isLinkLocalAddress ()` const
*Check if this **InetAddress** (p. 2016) is a valid link local address.*
- virtual bool `isSiteLocalAddress ()` const
*Check if this **InetAddress** (p. 2016) is a valid site local address.*
- virtual bool `isMCGlobal ()` const
*Check if this **InetAddress** (p. 2016) is Multicast and has Global scope.*
- virtual bool `isMCNodeLocal ()` const
*Check if this **InetAddress** (p. 2016) is Multicast and has Node Local scope.*
- virtual bool `isMCLinkLocal ()` const
*Check if this **InetAddress** (p. 2016) is Multicast and has Link Local scope.*
- virtual bool `isMCSiteLocal ()` const
*Check if this **InetAddress** (p. 2016) is Multicast and has Site Local scope.*
- virtual bool `isMCOrgLocal ()` const
*Check if this **InetAddress** (p. 2016) is Multicast and has Organization scope.*

Protected Member Functions

- `Inet4Address ()`
- `Inet4Address (const unsigned char *ipAddress, int numBytes)`
- `Inet4Address (const std::string &hostname, const unsigned char *ipAddress, int numBytes)`

Friends

- class `InetAddress`

6.394.1 Constructor & Destructor Documentation

- 6.394.1.1** `decaf::net::Inet4Address::Inet4Address ()` [protected]
- 6.394.1.2** `decaf::net::Inet4Address::Inet4Address (const unsigned char * ipAddress, int numBytes)` [protected]
- 6.394.1.3** `decaf::net::Inet4Address::Inet4Address (const std::string & hostname, const unsigned char * ipAddress, int numBytes)` [protected]
- 6.394.1.4** `virtual decaf::net::Inet4Address::~~Inet4Address ()` [virtual]

6.394.2 Member Function Documentation

- 6.394.2.1** `virtual bool decaf::net::Inet4Address::isAnyLocalAddress () const` [virtual]

Check if this `InetAddress` (p. 2016) is a valid wildcard address.

Returns:

true if the address is a wildcard address.

Reimplemented from `decaf::net::InetAddress` (p. 2020).

- 6.394.2.2** `virtual bool decaf::net::Inet4Address::isLinkLocalAddress () const` [virtual]

Check if this `InetAddress` (p. 2016) is a valid link local address.

Returns:

true if the address is a link local address.

Reimplemented from `decaf::net::InetAddress` (p. 2020).

- 6.394.2.3** `virtual bool decaf::net::Inet4Address::isLoopbackAddress () const` [virtual]

Check if this `InetAddress` (p. 2016) is a valid loopback address.

Returns:

true if the address is a loopback address.

Reimplemented from `decaf::net::InetAddress` (p. 2020).

6.394.2.4 virtual bool decaf::net::Inet4Address::isMCGlobal () const [virtual]

Check if this **InetAddress** (p. 2016) is Multicast and has Global scope.

Returns:

true if the address is Multicast and has Global scope.

Reimplemented from **decaf::net::InetAddress** (p. 2021).

6.394.2.5 virtual bool decaf::net::Inet4Address::isMCLinkLocal () const [virtual]

Check if this **InetAddress** (p. 2016) is Multicast and has Link Local scope.

Returns:

true if the address is Multicast and has Link Local scope.

Reimplemented from **decaf::net::InetAddress** (p. 2021).

6.394.2.6 virtual bool decaf::net::Inet4Address::isMCNodeLocal () const [virtual]

Check if this **InetAddress** (p. 2016) is Multicast and has Node Local scope.

Returns:

true if the address is Multicast and has Node Local scope.

Reimplemented from **decaf::net::InetAddress** (p. 2021).

6.394.2.7 virtual bool decaf::net::Inet4Address::isMCOrgLocal () const [virtual]

Check if this **InetAddress** (p. 2016) is Multicast and has Organization scope.

Returns:

true if the address is Multicast and has Organization scope.

Reimplemented from **decaf::net::InetAddress** (p. 2021).

6.394.2.8 virtual bool decaf::net::Inet4Address::isMCSiteLocal () const [virtual]

Check if this **InetAddress** (p. 2016) is Multicast and has Site Local scope.

Returns:

true if the address is Multicast and has Site Local scope.

Reimplemented from **decaf::net::InetAddress** (p. 2021).

6.394.2.9 **virtual bool decaf::net::Inet4Address::isMulticastAddress () const**
 [virtual]

Check if this **InetAddress** (p. 2016) is a valid Multicast address.

Returns:

 true if the address is a Multicast address.

Reimplemented from **decaf::net::InetAddress** (p. 2022).

6.394.2.10 **virtual bool decaf::net::Inet4Address::isSiteLocalAddress () const**
 [virtual]

Check if this **InetAddress** (p. 2016) is a valid site local address.

Returns:

 true if the address is a site local address.

Reimplemented from **decaf::net::InetAddress** (p. 2022).

6.394.3 Friends And Related Function Documentation

6.394.3.1 **friend class InetAddress** [friend]

The documentation for this class was generated from the following file:

- `src/main/decaf/net/Inet4Address.h`

6.395 decaf::net::Inet6Address Class Reference

#include <src/main/decaf/net/Inet6Address.h> Inheritance diagram for decaf::net::Inet6Address:

Public Member Functions

- virtual ~Inet6Address ()

Protected Member Functions

- Inet6Address ()
- Inet6Address (const unsigned char *ipAddress, int numBytes)
- Inet6Address (const std::string &hostname, const unsigned char *ipAddress, int numBytes)

Friends

- class InetAddress

6.395.1 Constructor & Destructor Documentation

6.395.1.1 decaf::net::Inet6Address::Inet6Address () [protected]

6.395.1.2 decaf::net::Inet6Address::Inet6Address (const unsigned char * *ipAddress*, int *numBytes*) [protected]

6.395.1.3 decaf::net::Inet6Address::Inet6Address (const std::string & *hostname*, const unsigned char * *ipAddress*, int *numBytes*) [protected]

6.395.1.4 virtual decaf::net::Inet6Address::~~Inet6Address () [virtual]

6.395.2 Friends And Related Function Documentation

6.395.2.1 friend class InetAddress [friend]

The documentation for this class was generated from the following file:

- src/main/decaf/net/Inet6Address.h

6.396 decaf::net::InetAddress Class Reference

Represents an IP address.

#include <src/main/decaf/net/InetAddress.h> Inheritance diagram for decaf::net::InetAddress:

Public Member Functions

- virtual `~InetAddress ()`
- virtual `decaf::lang::ArrayPointer< unsigned char > getAddress () const`
Returns the Raw IP address in Network byte order.
- virtual `std::string getHostAddress () const`
Returns a textual representation of the IP Address.
- virtual `std::string getHostName () const`
*Get the host name associated with this **InetAddress** (p. 2016) instance.*
- virtual `std::string toString () const`
*Returns a string representation of the **InetAddress** (p. 2016) in the form 'hostname / ipaddress'.*
- virtual `bool isAnyLocalAddress () const`
*Check if this **InetAddress** (p. 2016) is a valid wildcard address.*
- virtual `bool isLoopbackAddress () const`
*Check if this **InetAddress** (p. 2016) is a valid loopback address.*
- virtual `bool isMulticastAddress () const`
*Check if this **InetAddress** (p. 2016) is a valid Multicast address.*
- virtual `bool isLinkLocalAddress () const`
*Check if this **InetAddress** (p. 2016) is a valid link local address.*
- virtual `bool isSiteLocalAddress () const`
*Check if this **InetAddress** (p. 2016) is a valid site local address.*
- virtual `bool isMCGlobal () const`
*Check if this **InetAddress** (p. 2016) is Multicast and has Global scope.*
- virtual `bool isMCNodeLocal () const`
*Check if this **InetAddress** (p. 2016) is Multicast and has Node Local scope.*
- virtual `bool isMCLinkLocal () const`
*Check if this **InetAddress** (p. 2016) is Multicast and has Link Local scope.*
- virtual `bool isMCSiteLocal () const`

*Check if this **InetAddress** (p. 2016) is Multicast and has Site Local scope.*

- virtual bool **isMCOrgLocal** () const

*Check if this **InetAddress** (p. 2016) is Multicast and has Organization scope.*

Static Public Member Functions

- static **InetAddress** **getByAddress** (const unsigned char *bytes, int numBytes)

*Given a raw IP Address in byte array form, create and return a new **InetAddress** (p. 2016) instance.*

- static **InetAddress** **getByAddress** (const std::string &hostname, const unsigned char *bytes, int numBytes)

*Given a host name and IPAddress return a new **InetAddress** (p. 2016).*

- static **InetAddress** **getLocalHost** ()

*Gets an **InetAddress** (p. 2016) that is the local host address.*

Protected Member Functions

- **InetAddress** ()
- **InetAddress** (const unsigned char *ipAddress, int numBytes)
- **InetAddress** (const std::string &hostname, const unsigned char *ipAddress, int numBytes)

Static Protected Member Functions

- static unsigned int **bytesToInt** (const unsigned char *bytes, int start)

Converts the bytes in an address array to an int starting from the value start treating the start value as the high order byte.

- static **InetAddress** **getAnyAddress** ()
- static **InetAddress** **getLoopbackAddress** ()

Protected Attributes

- std::string **hostname**
- bool **reached**
- decaf::lang::ArrayPointer< unsigned char > **addressBytes**

Static Protected Attributes

- static const unsigned char **loopbackBytes** [4]
- static const unsigned char **anyBytes** [4]

6.396.1 Detailed Description

Represents an IP address.

Since:

1.0

6.396.2 Constructor & Destructor Documentation

6.396.2.1 `decaf::net::InetAddress::InetAddress ()` [protected]

6.396.2.2 `decaf::net::InetAddress::InetAddress (const unsigned char * ipAddress, int numBytes)` [protected]

6.396.2.3 `decaf::net::InetAddress::InetAddress (const std::string & hostname, const unsigned char * ipAddress, int numBytes)` [protected]

6.396.2.4 `virtual decaf::net::InetAddress::~~InetAddress ()` [virtual]

6.396.3 Member Function Documentation

6.396.3.1 `static unsigned int decaf::net::InetAddress::bytesToInt (const unsigned char * bytes, int start)` [static, protected]

Converts the bytes in an address array to an int starting from the value start treating the start value as the high order byte.

Parameters:

bytes The array of bytes to convert to an int.

start The index in the array to treat as the high order byte.

Returns:

an unsigned int that represents the address value.

6.396.3.2 `virtual decaf::lang::ArrayPointer<unsigned char> decaf::net::InetAddress::getAddress () const` [virtual]

Returns the Raw IP address in Network byte order. The returned address is a copy of the bytes contained in this `InetAddress` (p.2016).

Returns:

and ArrayPointer containing the raw bytes of the network address.

6.396.3.3 static InetAddress decaf::net::InetAddress::getAnyAddress () [static, protected]

6.396.3.4 static InetAddress decaf::net::InetAddress::getByAddress (const std::string & *hostname*, const unsigned char * *bytes*, int *numBytes*) [static]

Given a host name and IPAddress return a new **InetAddress** (p. 2016). There is no name service checking or address validation done on the provided host name. The host name can either be machine name or the text based representation of the IP Address.

An IPV4 address must be only four bytes in length and an IPV6 address must be 16 bytes in length.

Returns:

a copy of an **InetAddress** (p. 2016) that represents the given byte array address.

Exceptions:

UnknownHostException (p. 3907) if the address array length is invalid.

6.396.3.5 static InetAddress decaf::net::InetAddress::getByAddress (const unsigned char * *bytes*, int *numBytes*) [static]

Given a raw IP Address in byte array form, create and return a new **InetAddress** (p. 2016) instance. An IPV4 address must be only four bytes in length and an IPV6 address must be 16 bytes in length.

Returns:

a copy of an **InetAddress** (p. 2016) that represents the given byte array address.

Exceptions:

UnknownHostException (p. 3907) if the address array length is invalid.

6.396.3.6 virtual std::string decaf::net::InetAddress::getHostAddress () const [virtual]

Returns a textual representation of the IP Address.

Returns:

the string form of the IP Address.

6.396.3.7 virtual std::string decaf::net::InetAddress::getHostName () const [virtual]

Get the host name associated with this **InetAddress** (p. 2016) instance. If a host name was set upon construction then that value is returned, otherwise a reverse name lookup will be performed to attempt to get the host name associated with the set IP Address. If the host name cannot be resolved the textual representation of the IP Address is returned instead.

Returns:

the name of the host associated with this set IP Address.

6.396.3.8 static InetAddress decaf::net::InetAddress::getLocalHost () [static]

Gets an **InetAddress** (p. 2016) that is the local host address. If the localhost value cannot be resolved than the **InetAddress** (p. 2016) for Loopback is returned.

Returns:

a new **InetAddress** (p. 2016) object that contains the local host address.

Exceptions:

UnknownHostException (p. 3907) if the address for local host is not found.

6.396.3.9 static InetAddress decaf::net::InetAddress::getLoopbackAddress () [static, protected]**6.396.3.10 virtual bool decaf::net::InetAddress::isAnyLocalAddress () const [inline, virtual]**

Check if this **InetAddress** (p. 2016) is a valid wildcard address.

Returns:

true if the address is a wildcard address.

Reimplemented in **decaf::net::Inet4Address** (p. 2012).

6.396.3.11 virtual bool decaf::net::InetAddress::isLinkLocalAddress () const [inline, virtual]

Check if this **InetAddress** (p. 2016) is a valid link local address.

Returns:

true if the address is a link local address.

Reimplemented in **decaf::net::Inet4Address** (p. 2012).

6.396.3.12 virtual bool decaf::net::InetAddress::isLoopbackAddress () const [inline, virtual]

Check if this **InetAddress** (p. 2016) is a valid loopback address.

Returns:

true if the address is a loopback address.

Reimplemented in **decaf::net::Inet4Address** (p. 2012).

6.396.3.13 `virtual bool decaf::net::InetAddress::isMCGlobal () const [inline, virtual]`

Check if this **InetAddress** (p. 2016) is Multicast and has Global scope.

Returns:

true if the address is Multicast and has Global scope.

Reimplemented in **decaf::net::Inet4Address** (p. 2013).

6.396.3.14 `virtual bool decaf::net::InetAddress::isMCLinkLocal () const [inline, virtual]`

Check if this **InetAddress** (p. 2016) is Multicast and has Link Local scope.

Returns:

true if the address is Multicast and has Link Local scope.

Reimplemented in **decaf::net::Inet4Address** (p. 2013).

6.396.3.15 `virtual bool decaf::net::InetAddress::isMCNodeLocal () const [inline, virtual]`

Check if this **InetAddress** (p. 2016) is Multicast and has Node Local scope.

Returns:

true if the address is Multicast and has Node Local scope.

Reimplemented in **decaf::net::Inet4Address** (p. 2013).

6.396.3.16 `virtual bool decaf::net::InetAddress::isMCOrgLocal () const [inline, virtual]`

Check if this **InetAddress** (p. 2016) is Multicast and has Organization scope.

Returns:

true if the address is Multicast and has Organization scope.

Reimplemented in **decaf::net::Inet4Address** (p. 2013).

6.396.3.17 `virtual bool decaf::net::InetAddress::isMCSiteLocal () const [inline, virtual]`

Check if this **InetAddress** (p. 2016) is Multicast and has Site Local scope.

Returns:

true if the address is Multicast and has Site Local scope.

Reimplemented in **decaf::net::Inet4Address** (p. 2013).

6.396.3.18 `virtual bool decaf::net::InetAddress::isMulticastAddress () const`
[inline, virtual]

Check if this **InetAddress** (p. 2016) is a valid Multicast address.

Returns:

true if the address is a Multicast address.

Reimplemented in **decaf::net::Inet4Address** (p. 2014).

6.396.3.19 `virtual bool decaf::net::InetAddress::isSiteLocalAddress () const`
[inline, virtual]

Check if this **InetAddress** (p. 2016) is a valid site local address.

Returns:

true if the address is a site local address.

Reimplemented in **decaf::net::Inet4Address** (p. 2014).

6.396.3.20 `virtual std::string decaf::net::InetAddress::toString () const` [virtual]

Returns a string representation of the **InetAddress** (p. 2016) in the form 'hostname / ipaddress'.
If the hostname is not resolved than it appears as empty.

Returns:

string value of this **InetAddress** (p. 2016).

6.396.4 Field Documentation

6.396.4.1 `decaf::lang::ArrayPointer<unsigned char> decaf::net::InetAddress::addressBytes` [mutable, protected]

6.396.4.2 `const unsigned char decaf::net::InetAddress::anyBytes[4]` [static, protected]

6.396.4.3 `std::string decaf::net::InetAddress::hostname` [mutable, protected]

6.396.4.4 `const unsigned char decaf::net::InetAddress::loopbackBytes[4]` [static, protected]

6.396.4.5 `bool decaf::net::InetAddress::reached` [mutable, protected]

The documentation for this class was generated from the following file:

- `src/main/decaf/net/InetAddress.h`

6.397 decaf::net::InetSocketAddress Class Reference

#include <src/main/decaf/net/InetSocketAddress.h> Inheritance diagram for decaf::net::InetSocketAddress:

Public Member Functions

- **InetSocketAddress** ()
- virtual **~InetSocketAddress** ()

6.397.1 Constructor & Destructor Documentation

6.397.1.1 decaf::net::InetSocketAddress::InetSocketAddress ()

6.397.1.2 virtual decaf::net::InetSocketAddress::~~InetSocketAddress () [virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/net/**InetSocketAddress.h**

6.398 inflate__state Struct Reference

```
#include <src/main/decaf/internal/util/zip/inflate.h>
```

Data Fields

- **inflate__mode** mode
- int **last**
- int **wrap**
- int **havedict**
- int **flags**
- unsigned **dmax**
- unsigned long **check**
- unsigned long **total**
- **gz_headerp** head
- unsigned **wbits**
- unsigned **wsize**
- unsigned **whave**
- unsigned **wnext**
- unsigned char FAR * **window**
- unsigned long **hold**
- unsigned **bits**
- unsigned **length**
- unsigned **offset**
- unsigned **extra**
- **code** const FAR * **lencode**
- **code** const FAR * **distcode**
- unsigned **lenbits**
- unsigned **distbits**
- unsigned **ncode**
- unsigned **nlen**
- unsigned **ndist**
- unsigned **have**
- **code** FAR * **next**
- unsigned short **lens** [320]
- unsigned short **work** [288]
- **code** **codes** [ENOUGH]
- int **sane**
- int **back**
- unsigned **was**

6.398.1 Field Documentation

- 6.398.1.1 `int inflate__state::back`
- 6.398.1.2 `unsigned inflate__state::bits`
- 6.398.1.3 `unsigned long inflate__state::check`
- 6.398.1.4 `code inflate__state::codes[ENOUGH]`
- 6.398.1.5 `unsigned inflate__state::distbits`
- 6.398.1.6 `code const FAR* inflate__state::distcode`
- 6.398.1.7 `unsigned inflate__state::dmax`
- 6.398.1.8 `unsigned inflate__state::extra`
- 6.398.1.9 `int inflate__state::flags`
- 6.398.1.10 `unsigned inflate__state::have`
- 6.398.1.11 `int inflate__state::havedict`
- 6.398.1.12 `gz_headerp inflate__state::head`
- 6.398.1.13 `unsigned long inflate__state::hold`
- 6.398.1.14 `int inflate__state::last`
- 6.398.1.15 `unsigned inflate__state::lenbits`
- 6.398.1.16 `code const FAR* inflate__state::lencode`
- 6.398.1.17 `unsigned inflate__state::length`
- 6.398.1.18 `unsigned short inflate__state::lens[320]`
- 6.398.1.19 `inflate__mode inflate__state::mode`
- 6.398.1.20 `unsigned inflate__state::ncode`
- 6.398.1.21 `unsigned inflate__state::ndist`
- 6.398.1.22 `code FAR* inflate__state::next`
- 6.398.1.23 `unsigned inflate__state::nlen`
- 6.398.1.24 `unsigned inflate__state::offset`
- 6.398.1.25 `int inflate__state::sane`
- 6.398.1.26 `unsigned long inflate__state::total`
- 6.398.1.27 `unsigned inflate__state::was`
- 6.398.1.28 `unsigned inflate__state::wbits`
- 6.398.1.29 `unsigned inflate__state::whave`
- 6.398.1.30 `unsigned char FAR* inflate__state::window`

- `src/main/decaf/internal/util/zip/inflate.h`

6.399 decaf::util::zip::Inflater Class Reference

This class uncompresses data that was compressed using the *DEFLATE* algorithm (see specification).

```
#include <src/main/decaf/util/zip/Inflater.h>
```

Public Member Functions

- **Inflater** ()
Creates a new decompressor.
- **Inflater** (bool nowrap)
Creates a new decompressor.
- virtual ~**Inflater** ()
- void **setInput** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets input data for decompression.
- void **setInput** (const std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)
Sets input data for decompression.
- void **setInput** (const std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException)
Sets input data for decompression.
- int **getRemaining** () const
Returns the total number of bytes remaining in the input buffer.
- void **setDictionary** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Sets the preset dictionary to the given array of bytes.
- void **setDictionary** (const std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Sets the preset dictionary to the given array of bytes.
- void **setDictionary** (const std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IllegalArgumentException)
Sets the preset dictionary to the given array of bytes.

- `bool needsInput () const`
- `bool needsDictionary () const`
- `void finish ()`
When called, indicates that decompression should end with the current contents of the input buffer.
- `bool finished () const`
- `int inflate (unsigned char *buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::util::zip::DataFormatException)`
Uncompresses bytes into specified buffer.
- `int inflate (std::vector< unsigned char > &buffer, int offset, int length) throw (decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::util::zip::DataFormatException)`
Uncompresses bytes into specified buffer.
- `int inflate (std::vector< unsigned char > &buffer) throw (decaf::lang::exceptions::IllegalStateException, decaf::util::zip::DataFormatException)`
Uncompresses bytes into specified buffer.
- `long long getAdler () const throw (decaf::lang::exceptions::IllegalStateException)`
- `long long getBytesRead () const throw (decaf::lang::exceptions::IllegalStateException)`
- `long long getBytesWritten () const throw (decaf::lang::exceptions::IllegalStateException)`
- `void reset () throw (decaf::lang::exceptions::IllegalStateException)`
Resets deflater so that a new set of input data can be processed.
- `void end ()`
Closes the decompressor and discards any unprocessed input.

6.399.1 Detailed Description

This class uncompresses data that was compressed using the *DEFLATE* algorithm (see [specification](#)). Basically this class is part of the API to the stream based ZLIB compression library and is used as such by [InflaterInputStream](#) (p. 2035) and its descendants.

The typical usage of a [Inflater](#) (p. 2027) outside this package consists of a specific call to one of its constructors before being passed to an instance of [InflaterInputStream](#) (p. 2035).

See also:

[InflaterInputStream](#) (p. 2035)
[Deflater](#) (p. 1706)

Since:

1.0

6.399.2 Constructor & Destructor Documentation

6.399.2.1 decaf::util::zip::Inflater::Inflater ()

Creates a new decompressor. This constructor defaults the inflater to use the ZLIB header and checksum fields.

6.399.2.2 decaf::util::zip::Inflater::Inflater (bool nowrap)

Creates a new decompressor. If the parameter 'nowrap' is true then the ZLIB header and checksum fields will not be used. This provides compatibility with the compression format used by both GZIP and PKZIP.

Note: When using the 'nowrap' option it is also necessary to provide an extra "dummy" byte as input. This is required by the ZLIB native library in order to support certain optimizations.

6.399.2.3 virtual decaf::util::zip::Inflater::~Inflater () [virtual]

6.399.3 Member Function Documentation

6.399.3.1 void decaf::util::zip::Inflater::end ()

Closes the decompressor and discards any unprocessed input. This method should be called when the decompressor is no longer being used, but will also be called automatically by the destructor. Once this method is called, the behavior of the **Inflater** (p. 2027) object is undefined.

6.399.3.2 void decaf::util::zip::Inflater::finish ()

When called, indicates that decompression should end with the current contents of the input buffer.

6.399.3.3 bool decaf::util::zip::Inflater::finished () const

Returns:

true if the end of the compressed data output stream has been reached.

6.399.3.4 long long decaf::util::zip::Inflater::getAdler () const throw (decaf::lang::exceptions::IllegalStateException)

Returns:

the ADLER-32 value of the uncompressed data.

Exceptions:

IllegalStateException if in the end state.

6.399.3.5 `long long decaf::util::zip::Inflater::getBytesRead () const throw (decaf::lang::exceptions::IllegalStateException)`

Returns:

the total number of compressed bytes input so far.

Exceptions:

IllegalStateException if in the end state.

6.399.3.6 `long long decaf::util::zip::Inflater::getBytesWritten () const throw (decaf::lang::exceptions::IllegalStateException)`

Returns:

the total number of decompressed bytes output so far.

Exceptions:

IllegalStateException if in the end state.

6.399.3.7 `int decaf::util::zip::Inflater::getRemaining () const`

Returns the total number of bytes remaining in the input buffer. This can be used to find out what bytes still remain in the input buffer after decompression has finished.

Returns:

the total number of bytes remaining in the input buffer

6.399.3.8 `int decaf::util::zip::Inflater::inflate (std::vector< unsigned char > & buffer) throw (decaf::lang::exceptions::IllegalStateException, decaf::util::zip::DataFormatException)`

Uncompresses bytes into specified buffer. Returns actual number of bytes uncompressed. A return value of 0 indicates that **needsInput()** (p. 2032) or **needsDictionary()** (p. 2032) should be called in order to determine if more input data or a preset dictionary is required. In the latter case, **getAdler()** (p. 2029) can be used to get the Adler-32 value of the dictionary required.

Parameters:

buffer The Buffer to write the compressed data to.

Exceptions:

IllegalStateException if in the end state.

DataFormatException (p. 1555) if the compressed data format is invalid.

6.399.3.9 `int decaf::util::zip::Inflater::inflate (std::vector< unsigned char > & buffer, int offset, int length) throw (decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::util::zip::DataFormatException)`

Uncompresses bytes into specified buffer. Returns actual number of bytes uncompressed. A return value of 0 indicates that **needsInput()** (p. 2032) or **needsDictionary()** (p. 2032) should be called in order to determine if more input data or a preset dictionary is required. In the latter case, **getAdler()** (p. 2029) can be used to get the Adler-32 value of the dictionary required.

Parameters:

buffer The Buffer to write the compressed data to.

offset The position in the Buffer to start writing at.

length The maximum number of byte of data to write.

Exceptions:

IllegalStateException if in the end state.

IndexOutOfBoundsException if the offset + length > size of the buffer.

DataFormatException (p. 1555) if the compressed data format is invalid.

6.399.3.10 `int decaf::util::zip::Inflater::inflate (unsigned char * buffer, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::util::zip::DataFormatException)`

Uncompresses bytes into specified buffer. Returns actual number of bytes uncompressed. A return value of 0 indicates that **needsInput()** (p. 2032) or **needsDictionary()** (p. 2032) should be called in order to determine if more input data or a preset dictionary is required. In the latter case, **getAdler()** (p. 2029) can be used to get the Adler-32 value of the dictionary required.

Parameters:

buffer The Buffer to write the compressed data to.

size The size of the buffer passed in.

offset The position in the Buffer to start writing at.

length The maximum number of byte of data to write.

Exceptions:

NullPointerException if buffer is NULL.

IllegalStateException if in the end state.

IndexOutOfBoundsException if the offset + length > size of the buffer.

DataFormatException (p. 1555) if the compressed data format is invalid.

6.399.3.11 `bool decaf::util::zip::Inflater::needsDictionary () const`**Returns:**

true if a preset dictionary is needed for decompression.

6.399.3.12 `bool decaf::util::zip::Inflater::needsInput () const`**Returns:**

true if the input data buffer is empty and `setInput()` (p. 2034) should be called in order to provide more input

6.399.3.13 `void decaf::util::zip::Inflater::reset () throw (decaf::lang::exceptions::IllegalStateException)`

Resets deflater so that a new set of input data can be processed. Keeps current decompression level and strategy settings.

Exceptions:

IllegalStateException if in the end state.

6.399.3.14 `void decaf::util::zip::Inflater::setDictionary (const std::vector< unsigned char > & buffer) throw (decaf::lang::exceptions::IllegalStateException, decaf::lang::exceptions::IllegalArgumentException)`

Sets the preset dictionary to the given array of bytes. Should be called when `inflate()` (p. 2031) returns 0 and `needsDictionary()` (p. 2032) returns true indicating that a preset dictionary is required. The method `getAdler()` (p. 2029) can be used to get the Adler-32 value of the dictionary needed.

Parameters:

buffer The Buffer to read in for decompression.

Exceptions:

IllegalStateException if in the end state.

IllegalArgumentException if the given dictionary doesn't match the required dictionaries checksum value.

6.399.3.15 `void decaf::util::zip::Inflater::setDictionary (const std::vector< unsigned char > & buffer, int offset, int length) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Sets the preset dictionary to the given array of bytes. Should be called when `inflate()` (p. 2031) returns 0 and `needsDictionary()` (p. 2032) returns true indicating that a preset dictionary is required. The method `getAdler()` (p. 2029) can be used to get the Adler-32 value of the dictionary needed.

Parameters:

buffer The Buffer to read in for decompression.
offset The position in the Buffer to start reading from.
length The number of bytes to read from the input buffer.

Exceptions:

IndexOutOfBoundsException if the offset + length > size of the buffer.
IllegalStateException if in the end state.
IllegalArgumentException if the given dictionary doesn't match the required dictionaries checksum value.

6.399.3.16 void decaf::util::zip::Inflater::setDictionary (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Sets the preset dictionary to the given array of bytes. Should be called when **inflate()** (p. 2031) returns 0 and **needsDictionary()** (p. 2032) returns true indicating that a preset dictionary is required. The method **getAdler()** (p. 2029) can be used to get the Adler-32 value of the dictionary needed.

Parameters:

buffer The Buffer to read in for decompression.
size The size of the buffer passed in.
offset The position in the Buffer to start reading from.
length The number of bytes to read from the input buffer.

Exceptions:

NullPointerException if buffer is NULL.
IndexOutOfBoundsException if the offset + length > size of the buffer.
IllegalStateException if in the end state.
IllegalArgumentException if the given dictionary doesn't match the required dictionaries checksum value.

6.399.3.17 void decaf::util::zip::Inflater::setInput (const std::vector< unsigned char > & *buffer*) throw (decaf::lang::exceptions::IllegalStateException)

Sets input data for decompression. This should be called whenever **needsInput()** (p. 2032) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for decompression.

Exceptions:

IllegalStateException if in the end state.

6.399.3.18 void decaf::util::zip::Inflater::setInput (const std::vector< unsigned char > & *buffer*, int *offset*, int *length*) throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Sets input data for decompression. This should be called whenever **needsInput()** (p. 2032) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for decompression.

offset The position in the Buffer to start reading from.

length The number of bytes to read from the input buffer.

Exceptions:

IndexOutOfBoundsException if the offset + length > size of the buffer.

IllegalStateException if in the end state.

6.399.3.19 void decaf::util::zip::Inflater::setInput (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::IllegalStateException)

Sets input data for decompression. This should be called whenever **needsInput()** (p. 2032) returns true indicating that more input data is required.

Parameters:

buffer The Buffer to read in for decompression.

size The size of the buffer passed in.

offset The position in the Buffer to start reading from.

length The number of bytes to read from the input buffer.

Exceptions:

NullPointerException if buffer is NULL.

IndexOutOfBoundsException if the offset + length > size of the buffer.

IllegalStateException if in the end state.

The documentation for this class was generated from the following file:

- src/main/decaf/util/zip/**Inflater.h**

6.400 decaf::util::zip::InflaterInputStream Class Reference

A `FilterInputStream` that decompresses data read from the wrapped `InputStream` instance.

#include <src/main/decaf/util/zip/InflaterInputStream.h> Inheritance diagram for decaf::util::zip::InflaterInputStream:

Public Member Functions

- **InflaterInputStream** (decaf::io::InputStream *inputStream, bool own=false)
Create an instance of this class with a default inflater and buffer size.
- **InflaterInputStream** (decaf::io::InputStream *inputStream, Inflater *inflater, bool own=false)
*Creates a new **InflaterInputStream** (p. 2035) with a user supplied **Inflater** (p. 2027) and a default buffer size.*
- **InflaterInputStream** (decaf::io::InputStream *inputStream, Inflater *inflater, int bufferSize, bool own=false)
*Creates a new **DeflateOutputStream** with a user supplied **Inflater** (p. 2027) and specified buffer size.*
- virtual ~**InflaterInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)
*Indicates the number of bytes available.
 The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.
 The default implementation of this method returns zero.*
Returns:
the number of bytes available on this input stream.
Exceptions:
***IOException** (p. 2142) if an I/O error occurs.*
- virtual void **close** () throw (decaf::io::IOException)
*Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream.
 The default implementation of this method does nothing.*
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
*Skips over and discards n bytes of data from this input stream.
 The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

- virtual void **mark** (int readLimit)

Marks the current position in the stream. A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

- virtual void **reset** () throw (decaf::io::IOException)

Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual bool **markSupported** () const

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Protected Member Functions

- virtual void **fill** () throw (decaf::io::IOException)

Fills the input buffer with the next chunk of data.

- virtual int **doReadByte** () throw (decaf::io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int **length**) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

Protected Attributes

- **Inflater * inflater**
*The **Inflater** (p. 2027) instance to use.*
- std::vector< unsigned char > **buff**
The buffer to hold chunks of data read from the stream before inflation.
- int **length**
The amount of data currently stored in the input buffer.
- bool **ownInflater**
- bool **atEOF**

Static Protected Attributes

- static const int **DEFAULT_BUFFER_SIZE**

6.400.1 Detailed Description

A FilterInputStream that decompresses data read from the wrapped InputStream instance.

Since:

1.0

6.400.2 Constructor & Destructor Documentation

6.400.2.1 decaf::util::zip::InflaterInputStream::InflaterInputStream (decaf::io::InputStream * *inputStream*, bool *own* = false)

Create an instance of this class with a default inflater and buffer size.

Parameters:

- inputStream* The InputStream instance to wrap.
- own* Should this Filter take ownership of the InputStream pointer (defaults to false).

6.400.2.2 decaf::util::zip::InflaterInputStream::InflaterInputStream (decaf::io::InputStream * *inputStream*, Inflater * *inflater*, bool *own* = false)

Creates a new **InflaterInputStream** (p. 2035) with a user supplied **Inflater** (p. 2027) and a default buffer size. When the user supplied a **Inflater** (p. 2027) instance the **InflaterInputStream** (p. 2035) does not take ownership of the **Inflater** (p. 2027) pointer, the caller is still responsible for deleting the **Inflater** (p. 2027).

Parameters:

- inputStream* The InputStream instance to wrap.
- inflater* The user supplied **Inflater** (p. 2027) to use for decompression. (
- own* Should this filter take ownership of the InputStream pointer (default is false).

Exceptions:

- NullPointerException* if the **Inflater** (p. 2027) given is NULL.

6.400.2.3 decaf::util::zip::InflaterInputStream::InflaterInputStream (decaf::io::InputStream * inputStream, Inflater * inflater, int bufferSize, bool own = false)

Creates a new DeflateOutputStream with a user supplied **Inflater** (p. 2027) and specified buffer size. When the user supplied a **Inflater** (p. 2027) instance the **InflaterInputStream** (p. 2035) does not take ownership of the **Inflater** (p. 2027) pointer, the caller is still responsible for deleting the **Inflater** (p. 2027).

Parameters:

- inputStream* The InputStream instance to wrap.
- inflater* The user supplied **Inflater** (p. 2027) to use for decompression.
- bufferSize* The size of the input buffer.
- own* Should this filter take ownership of the InputStream pointer (default is false).

Exceptions:

- NullPointerException* if the **Inflater** (p. 2027) given is NULL.
- IllegalArgumentException* if the bufferSize value is zero.

6.400.2.4 virtual decaf::util::zip::InflaterInputStream::~~InflaterInputStream () [virtual]

6.400.3 Member Function Documentation

6.400.3.1 virtual int decaf::util::zip::InflaterInputStream::available () const throw (decaf::io::IOException) [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

- the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Until EOF this method always returns 1, thereafter it always returns 0.

Reimplemented from **decaf::io::FilterInputStream** (p. 1896).

6.400.3.2 virtual void decaf::util::zip::InflaterInputStream::close () throw (decaf::io::IOException) [virtual]

Closes the **InputStream** (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.

The default implementation of this method does nothing. Closes any resources associated with this **InflaterInputStream** (p. 2035).

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.400.3.3 virtual int decaf::util::zip::InflaterInputStream::doReadArrayBounded (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.400.3.4 virtual int decaf::util::zip::InflaterInputStream::doReadByte () throw (decaf::io::IOException) [protected, virtual]

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.400.3.5 virtual void decaf::util::zip::InflaterInputStream::fill () throw (decaf::io::IOException) [protected, virtual]

Fills the input buffer with the next chunk of data.

Exceptions:

IOException if an I/O error occurs.

6.400.3.6 virtual void decaf::util::zip::InflaterInputStream::mark (int *readLimit*) [virtual]

Marks the current position in the stream A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Does nothing.

Reimplemented from **decaf::io::FilterInputStream** (p. 1897).

6.400.3.7 virtual bool decaf::util::zip::InflaterInputStream::markSupported () const [virtual]

Determines if this input stream supports the mark and reset methods.

Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Always returns false.

Reimplemented from **decaf::io::FilterInputStream** (p. 1898).

6.400.3.8 virtual void decaf::util::zip::InflaterInputStream::reset () throw (decaf::io::IOException) [virtual]

Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Always throws an **IOException** when called.

Reimplemented from **decaf::io::FilterInputStream** (p. 1898).

6.400.3.9 `virtual long long decaf::util::zip::InflaterInputStream::skip
(long long num) throw (decaf::io::IOException,
decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

Skips over and discards *n* bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until *num* bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Skips the specified amount of uncompressed input data.

Reimplemented from **decaf::io::FilterInputStream** (p. 1899).

6.400.4 Field Documentation

6.400.4.1 `bool decaf::util::zip::InflaterInputStream::atEOF` [protected]

6.400.4.2 `std::vector<unsigned char> decaf::util::zip::InflaterInputStream::buff`
[protected]

The buffer to hold chunks of data read from the stream before inflation.

6.400.4.3 `const int decaf::util::zip::InflaterInputStream::DEFAULT_BUFFER_ -
SIZE` [static, protected]

6.400.4.4 `Inflater* decaf::util::zip::InflaterInputStream::inflater` [protected]

The **Inflater** (p. 2027) instance to use.

6.400.4.5 `int decaf::util::zip::InflaterInputStream::length` [protected]

The amount of data currently stored in the input buffer.

6.400.4.6 `bool decaf::util::zip::InflaterInputStream::ownInflater` [protected]

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/InflaterInputStream.h`

6.401 decaf::io::InputStream Class Reference

A base class that must be implemented by all classes wishing to provide a class that reads in a stream of bytes.

#include <src/main/decaf/io/InputStream.h> Inheritance diagram for decaf::io::InputStream:

Public Member Functions

- **InputStream** ()
- virtual **~InputStream** ()
- virtual void **close** () throw (decaf::io::IOException)
*Closes the **InputStream** (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.*
- virtual void **mark** (int readLimit)
Marks the current position in the stream A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.
- virtual void **reset** () throw (decaf::io::IOException)
Repositions this stream to the position at the time the mark method was last called on this input stream.
- virtual bool **markSupported** () const
Determines if this input stream supports the mark and reset methods.
- virtual int **available** () const throw (decaf::io::IOException)
Indicates the number of bytes available.
- virtual int **read** () throw (decaf::io::IOException)
Reads a single byte from the buffer.
- virtual int **read** (unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
Reads up to size bytes of data from the input stream into an array of bytes.
- virtual int **read** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Reads up to length bytes of data from the input stream into an array of bytes.
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Skips over and discards n bytes of data from this input stream.
- virtual std::string **toString** () const
Output a String representation of this object.

- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

Protected Member Functions

- virtual int **doReadByte** ()=0 throw (decaf::io::IOException)
- virtual int **doReadArray** (unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.401.1 Detailed Description

A base class that must be implemented by all classes wishing to provide a class that reads in a stream of bytes.

Since:

1.0

6.401.2 Constructor & Destructor Documentation

6.401.2.1 `decaf::io::InputStream::InputStream ()`

6.401.2.2 `virtual decaf::io::InputStream::~~InputStream ()` [virtual]

6.401.3 Member Function Documentation

6.401.3.1 `virtual int decaf::io::InputStream::available () const throw (decaf::io::IOException)` [inline, virtual]

Indicates the number of bytes available. The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented in `decaf::internal::io::StandardInputStream` (p. 3582), `decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream` (p. 2883), `decaf::internal::net::tcp::TcpSocketInputStream` (p. 3748), `decaf::io::BlockingByteArrayInputStream` (p. 840), `decaf::io::BufferedInputStream` (p. 936), `decaf::io::ByteArrayInputStream` (p. 1023), `decaf::io::FilterInputStream` (p. 1896), `decaf::io::PushbackInputStream` (p. 3143), and `decaf::util::zip::InflaterInputStream` (p. 2038).

6.401.3.2 `virtual void decaf::io::InputStream::close () throw (decaf::io::IOException)` [virtual]

Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream. The default implementation of this method does nothing.

Implements `decaf::io::Closeable` (p. 1149).

Reimplemented in `decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream` (p. 2883), `decaf::internal::net::tcp::TcpSocketInputStream` (p. 3748), `decaf::io::BlockingByteArrayInputStream` (p. 841), `decaf::io::BufferedInputStream` (p. 937), `decaf::io::FilterInputStream` (p. 1897), and `decaf::util::zip::InflaterInputStream` (p. 2039).

6.401.3.3 `virtual int decaf::io::InputStream::doReadArray (unsigned char * buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Reimplemented in `decaf::io::FilterInputStream` (p. 1897).

6.401.3.4 `virtual int decaf::io::InputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Reimplemented in `activemq::io::LoggingInputStream` (p. 2399), `decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream` (p. 2883), `decaf::internal::net::tcp::TcpSocketInputStream` (p. 3749), `decaf::io::BlockingByteArrayInputStream` (p. 841), `decaf::io::BufferedInputStream` (p. 937), `decaf::io::ByteArrayInputStream` (p. 1024), `decaf::io::FilterInputStream` (p. 1897), `decaf::io::PushbackInputStream` (p. 3144), `decaf::util::zip::CheckedInputStream` (p. 1138), and `decaf::util::zip::InflaterInputStream` (p. 2039).

6.401.3.5 `virtual int decaf::io::InputStream::doReadByte () throw (decaf::io::IOException)` [protected, pure virtual]

Implemented in `activemq::io::LoggingInputStream` (p. 2400), `decaf::internal::io::StandardInputStream` (p. 3583), `decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream` (p. 2884), `decaf::internal::net::tcp::TcpSocketInputStream` (p. 3749), `decaf::io::BlockingByteArrayInputStream` (p. 841), `decaf::io::BufferedInputStream` (p. 937), `decaf::io::ByteArrayInputStream` (p. 1024), `decaf::io::FilterInputStream` (p. 1897), `decaf::io::PushbackInputStream` (p. 3144), `decaf::util::zip::CheckedInputStream` (p. 1138), and `decaf::util::zip::InflaterInputStream` (p. 2039).

6.401.3.6 `virtual void decaf::io::InputStream::lock () throw (decaf::lang::exceptions::RuntimeException)` [inline, virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3701).

6.401.3.7 `virtual void decaf::io::InputStream::mark (int readLimit)` [virtual]

Marks the current position in the stream. A subsequent call to the reset method repositions this stream at the last marked position so that subsequent reads re-read the same bytes. If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the reset method is called so long the readLimit is not reached.

Calling mark on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Reimplemented in `decaf::io::BufferedInputStream` (p. 937), `decaf::io::ByteArrayInputStream` (p. 1024), `decaf::io::FilterInputStream` (p. 1897),

decaf::io::PushbackInputStream (p. 3144), and **decaf::util::zip::InflaterInputStream** (p. 2039).

6.401.3.8 `virtual bool decaf::io::InputStream::markSupported () const [inline, virtual]`

Determines if this input stream supports the mark and reset methods. Whether or not mark and reset are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Reimplemented in **decaf::io::BufferedInputStream** (p. 937), **decaf::io::ByteArrayInputStream** (p. 1024), **decaf::io::FilterInputStream** (p. 1898), **decaf::io::PushbackInputStream** (p. 3144), and **decaf::util::zip::InflaterInputStream** (p. 2040).

6.401.3.9 `virtual void decaf::io::InputStream::notify ()
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [inline,
virtual]`

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3702).

6.401.3.10 `virtual void decaf::io::InputStream::notifyAll ()
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [inline,
virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.401.3.11 `virtual int decaf::io::InputStream::read (unsigned char * buffer,
int size, int offset, int length) throw (decaf::io::IOException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException) [virtual]`

Reads up to *length* bytes of data from the input stream into an array of bytes. An attempt is made to read as many as *length* bytes, but a smaller number may be read. The number of bytes actually read is returned as an integer.

This method blocks until input data is available, end of file is detected, or an exception is thrown.

If *length* is zero, then no bytes are read and 0 is returned; otherwise, there is an attempt to read at least one byte. If no byte is available because the stream is at end of file, the value -1 is returned; otherwise, at least one byte is read and stored into *b*.

The first byte read is stored into element *b*[*off*], the next one into *b*[*off*+1], and so on. The number of bytes read is, at most, equal to *length*. Let *k* be the number of bytes actually read; these bytes will be stored in elements *b*[*off*] through *b*[*off*+*k*-1], leaving elements *b*[*offset*+*k*] through *b*[*offset*+*length*-1] unaffected.

In every case, elements *b*[0] through *b*[*offset*] and elements *b*[*offset*+*length*] through *b*[*b.length*-1] are unaffected.

This method called the protected virtual method `doReadArrayBounded` which simply calls the method `doReadByte()` (p. 2046) repeatedly. If the first such call results in an **IOException** (p. 2142), that exception is returned. If any subsequent call to `doReadByte()` (p. 2046) results in a **IOException** (p. 2142), the exception is caught and treated as if it were end of file; the bytes read up to that point are stored into the buffer and the number of bytes read before the exception occurred is returned. The default implementation of this method blocks until the requested amount of input data has been read, end of file is detected, or an exception is thrown. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

buffer The target buffer to write the read in data to.

size The size in bytes of the target buffer.

offset The position in the buffer to start inserting the read in data.

length The maximum number of bytes that should be read into buffer.

Returns:

The number of bytes read or -1 if EOF is detected

Exceptions:

IOException (p. 2142) if an I/O error occurs.

NullPointerException if buffer passed is NULL.

IndexOutOfBoundsException if *length* > *size* - *offset*.

6.401.3.12 `virtual int decaf::io::InputStream::read (unsigned char
* buffer, int size) throw (decaf::io::IOException,
decaf::lang::exceptions::NullPointerException) [virtual]`

Reads up to *size* bytes of data from the input stream into an array of bytes. An attempt is made to read as many as *size* bytes, but a smaller number may be read. The number of bytes actually read is returned as an integer.

This method blocks until input data is available, end of file is detected, or an exception is thrown.

If size is zero, then no bytes are read and 0 is returned; otherwise, there is an attempt to read at least one byte. If no byte is available because the stream is at end of file, the value -1 is returned; otherwise, at least one byte is read and stored into b.

This method called the protected virtual method `doReadArray` which by default is the same as calling `read(buffer, size, 0, size)`. Subclasses can customize the behavior of this method by overriding the `doReadArray` method to provide a better performing read operation.

Parameters:

buffer The target buffer to write the read in data to.

size The size in bytes of the target buffer.

Returns:

The number of bytes read or -1 if EOF is detected

Exceptions:

IOException (p. 2142) if an I/O error occurs.

NullPointerException if buffer passed is NULL.

6.401.3.13 virtual int decaf::io::InputStream::read () throw (decaf::io::IOException) [virtual]

Reads a single byte from the buffer. The value byte is returned as an int in the range 0 to 255. If no byte is available because the end of the stream has been reached, the value -1 is returned. This method blocks until input data is available, the end of the stream is detected, or an exception is thrown.

The default implementation of this method calls the **internal** (p. 144) virtual method `doReadByte` which is a pure virtual method and must be overridden by all subclasses.

Returns:

The next byte or -1 if the end of stream is reached.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

6.401.3.14 virtual void decaf::io::InputStream::reset () throw (decaf::io::IOException) [virtual]

Repositions this stream to the position at the time the mark method was last called on this input stream. If the method `markSupported` returns true, then: * If the method `mark` has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method `markSupported` returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented in **decaf::io::BufferedInputStream** (p. 938), **decaf::io::ByteArrayInputStream** (p. 1025), **decaf::io::FilterInputStream** (p. 1898), **decaf::io::PushbackInputStream** (p. 3145), and **decaf::util::zip::InflaterInputStream** (p. 2040).

6.401.3.15 `virtual long long decaf::io::InputStream::skip (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

Skips over and discards n bytes of data from this input stream. The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream** (p. 2884), **decaf::internal::net::tcp::TcpSocketInputStream** (p. 3749), **decaf::io::BlockingByteArrayInputStream** (p. 841), **decaf::io::BufferedInputStream** (p. 938), **decaf::io::ByteArrayInputStream** (p. 1026), **decaf::io::FilterInputStream** (p. 1899), **decaf::io::PushbackInputStream** (p. 3145), **decaf::util::zip::CheckedInputStream** (p. 1139), and **decaf::util::zip::InflaterInputStream** (p. 2041).

6.401.3.16 `virtual std::string decaf::io::InputStream::toString () const` [virtual]

Output a String representation of this object. The default version of this method just prints the Class Name.

Returns:

a string representation of the object.

6.401.3.17 `virtual bool decaf::io::InputStream::tryLock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

6.401.3.18 `virtual void decaf::io::InputStream::unlock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

6.401.3.19 `virtual void decaf::io::InputStream::wait (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.401.3.20 `virtual void decaf::io::InputStream::wait (long long
 millisecs) throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException,
 decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

6.401.3.21 `virtual void decaf::io::InputStream::wait () throw
 (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException,
 decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/InputStream.h`

6.402 decaf::io::InputStreamReader Class Reference

An **InputStreamReader** (p. 2053) is a bridge from byte streams to character streams.

#include <src/main/decaf/io/InputStreamReader.h> Inheritance diagram for decaf::io::InputStreamReader:

Public Member Functions

- **InputStreamReader** (**InputStream** *stream, bool own=false)
*Create a new **InputStreamReader** (p. 2053) that wraps the given **InputStream** (p. 2043).*
- virtual ~**InputStreamReader** ()
- virtual void **close** () throw (decaf::io::IOException)
Closes this object and deallocates the appropriate resources.
- virtual bool **ready** () const throw (decaf::io::IOException)
Tells whether this stream is ready to be read.

Protected Member Functions

- virtual int **doReadArrayBounded** (char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Override this method to customize the functionality of the method read(unsigned char buffer, int size, int offset, int length).*
- virtual void **checkClosed** () const throw (decaf::io::IOException)

6.402.1 Detailed Description

An **InputStreamReader** (p. 2053) is a bridge from byte streams to character streams. For top efficiency, consider wrapping an **InputStreamReader** (p. 2053) within a **BufferedReader**. For example:

```
BufferedReader* in = new BufferedReader( new InputStreamReader (p. 2053)( System.in, false ), true );
```

See also:

OutputStreamWriter (p. 2915)

Since:

1.0

6.402.2 Constructor & Destructor Documentation

6.402.2.1 `decaf::io::InputStreamReader::InputStreamReader (InputStream * stream, bool own = false)`

Create a new **InputStreamReader** (p. 2053) that wraps the given **InputStream** (p. 2043).

Parameters:

stream The **InputStream** (p. 2043) to read from. (cannot be null).

own Does this object own the passed **InputStream** (p. 2043) (defaults to false).

Exceptions:

NullPointerException if the passed **InputStream** (p. 2043) is NULL.

6.402.2.2 `virtual decaf::io::InputStreamReader::~~InputStreamReader ()` [virtual]

6.402.3 Member Function Documentation

6.402.3.1 `virtual void decaf::io::InputStreamReader::checkClosed () const throw (decaf::io::IOException)` [protected, virtual]

6.402.3.2 `virtual void decaf::io::InputStreamReader::close () throw (decaf::io::IOException)` [virtual]

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

Implements **decaf::io::Closeable** (p. 1149).

6.402.3.3 `virtual int decaf::io::InputStreamReader::doReadArrayBounded (char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Override this method to customize the functionality of the method `read(unsigned char* buffer, int size, int offset, int length)`. All subclasses must override this method to provide the basic **Reader** (p. 3163) functionality.

Implements **decaf::io::Reader** (p. 3164).

6.402.3.4 `virtual bool decaf::io::InputStreamReader::ready () const throw (decaf::io::IOException)` [virtual]

Tells whether this stream is ready to be read.

Returns:

True if the next **read()** (p. 3166) is guaranteed not to block for input, false otherwise. Note that returning false does not guarantee that the next read will block.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::Reader** (p. 3167).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/InputStreamReader.h`

6.403 decaf::internal::nio::IntArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/IntArrayBuffer.h> Inheritance diagram for decaf::internal::nio::IntArrayBuffer:

Public Member Functions

- **IntArrayBuffer** (int size, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **IntArrayBuffer** (p. 2056) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **IntArrayBuffer** (int *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **IntArrayBuffer** (p. 2056) object that wraps the given array.*

- **IntArrayBuffer** (const decaf::lang::Pointer< ByteArrayAdapter > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset.

- **IntArrayBuffer** (const IntArrayBuffer &other)

*Create a **IntArrayBuffer** (p. 2056) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.*

- virtual ~**IntArrayBuffer** ()
- virtual int * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the int array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

*the array that backs this **Buffer** (p. 928).*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual **IntArrayBuffer** * **asReadOnlyBuffer** () const

Creates a new, read-only int buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only int buffer which the caller then owns.

- virtual **IntArrayBuffer** & **compact** () throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **IntArrayBuffer** (p. 2066)

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **IntArrayBuffer** * **duplicate** ()

Creates a new int buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new int **Buffer** (p. 928) which the caller owns.

- virtual int **get** () throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the int at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

- virtual int **get** (int index) const throw (lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the int is to be read.

Returns:

the int that is located at the given index.

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit, or *index* is negative.

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible int array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual IntBuffer & **put** (int value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given integer into this buffer at the current position, and then increments the position.

Parameters:

value The integer value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual IntBuffer & **put** (int index, int value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given ints into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The ints to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException - If *index* greater than the buffer's limit minus the size of the type being written, or the *index* is negative.

ReadOnlyBufferException (p. 3169) - If this buffer is read-only.

- virtual IntBuffer * **slice** () const

Creates a new **IntBuffer** (p. 2066) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **IntBuffer** (p. 2066) which the caller owns.

Protected Member Functions

- virtual void **setReadOnly** (bool value)

Sets this **IntArrayBuffer** (p. 2056) as Read-Only.

6.403.1 Constructor & Destructor Documentation

6.403.1.1 decaf::internal::nio::IntArrayBuffer::IntArrayBuffer (int size, bool readOnly = false) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a **IntArrayBuffer** (p. 2056) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.403.1.2 decaf::internal::nio::IntArrayBuffer::IntArrayBuffer (int * array, int size, int offset, int length, bool readOnly = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a **IntArrayBuffer** (p. 2056) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.403.1.3 `decaf::internal::nio::IntArrayBuffer::IntArrayBuffer`
 (const decaf::lang::Pointer< ByteArrayAdapter > &
array, int *offset*, int *length*, bool *readOnly* = false)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset. The capacity and limit of the new **IntArrayBuffer** (p.2056) will be that of the remaining capacity of the passed buffer.

Parameters:

array The ByteArrayAdapter to wrap.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if array is NULL

IndexOutOfBoundsException if offset + length is greater than array size.

6.403.1.4 `decaf::internal::nio::IntArrayBuffer::IntArrayBuffer` (const
 IntArrayBuffer & *other*)

Create a **IntArrayBuffer** (p.2056) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.

Parameters:

other The **IntArrayBuffer** (p.2056) this one is to mirror.

6.403.1.5 `virtual decaf::internal::nio::IntArrayBuffer::~~IntArrayBuffer` ()
 [virtual]

6.403.2 Member Function Documentation

6.403.2.1 `virtual int* decaf::internal::nio::IntArrayBuffer::array` () throw
 (decaf::lang::exceptions::UnsupportedOperationException,
 decaf::nio::ReadOnlyBufferException) [virtual]

Returns the int array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::IntBuffer** (p. 2069).

6.403.2.2 `virtual int decaf::internal::nio::IntArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::IntBuffer** (p. 2069).

6.403.2.3 `virtual IntBuffer* decaf::internal::nio::IntArrayBuffer::asReadOnlyBuffer
() const [virtual]`

Creates a new, read-only int buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only int buffer which the caller then owns.

Implements **decaf::nio::IntBuffer** (p. 2069).

6.403.2.4 `virtual IntBuffer& decaf::internal::nio::IntArrayBuffer::compact () throw (decaf::nio::ReadOnlyBufferException) [virtual]`

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index `p = position()` (p. 932) is copied to index zero, the byte at index `p + 1` is copied to index one, and so forth until the byte at index `limit()` (p. 932) - 1 is copied to index `n = limit() - 1 - p`. The buffer's position is then set to `n+1` and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **IntBuffer** (p. 2066)

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::IntBuffer** (p. 2070).

6.403.2.5 `virtual IntBuffer* decaf::internal::nio::IntArrayBuffer::duplicate () [virtual]`

Creates a new int buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new int **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::IntBuffer** (p. 2070).

6.403.2.6 `virtual int decaf::internal::nio::IntArrayBuffer::get (int index) const throw (lang::exceptions::IndexOutOfBoundsException) [virtual]`

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the int is to be read.

Returns:

the int that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implements **decaf::nio::IntBuffer** (p. 2071).

6.403.2.7 virtual int decaf::internal::nio::IntArrayBuffer::get () throw (decaf::nio::BufferUnderflowException) [virtual]

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the int at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implements **decaf::nio::IntBuffer** (p. 2072).

6.403.2.8 virtual bool decaf::internal::nio::IntArrayBuffer::hasArray () const [inline, virtual]

Tells whether or not this buffer is backed by an accessible int array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implements **decaf::nio::IntBuffer** (p. 2072).

6.403.2.9 virtual bool decaf::internal::nio::IntArrayBuffer::isReadOnly () const [inline, virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.403.2.10 virtual IntBuffer& decaf::internal::nio::IntArrayBuffer::put (int index, int value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given ints into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The ints to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException - If index greater than the buffer's limit minus the size of the type being written, or the index is negative.

ReadOnlyBufferException (p. 3169) - If this buffer is read-only.

Implements **decaf::nio::IntBuffer** (p. 2072).

6.403.2.11 `virtual IntBuffer& decaf::internal::nio::IntArrayBuffer::put (int value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes the given integer into this buffer at the current position, and then increments the position.

Parameters:

value The integer value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::IntBuffer** (p. 2073).

6.403.2.12 `virtual void decaf::internal::nio::IntArrayBuffer::setReadOnly (bool value) [inline, protected, virtual]`

Sets this **IntArrayBuffer** (p. 2056) as Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.403.2.13 `virtual IntBuffer* decaf::internal::nio::IntArrayBuffer::slice () const [virtual]`

Creates a new **IntBuffer** (p. 2066) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **IntBuffer** (p. 2066) which the caller owns.

Implements **decaf::nio::IntBuffer** (p. 2075).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/IntArrayBuffer.h`

6.404 decaf::nio::IntBuffer Class Reference

This class defines four categories of operations upon int buffers:.

#include <src/main/decaf/nio/IntBuffer.h>Inheritance diagram for decaf::nio::IntBuffer:

Public Member Functions

- virtual **~IntBuffer** ()
- virtual std::string **toString** () const
- virtual int * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the int array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **IntBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only int buffer that shares this buffer's content.
- virtual **IntBuffer** & **compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **IntBuffer** * **duplicate** ()=0
Creates a new int buffer that shares this buffer's content.
- virtual int **get** ()=0 throw (BufferUnderflowException)
Relative get method.
- virtual int **get** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **IntBuffer** & **get** (std::vector< int > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **IntBuffer** & **get** (int *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible int array.
- **IntBuffer** & **put** (**IntBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)
This method transfers the ints remaining in the given source buffer into this buffer.

- **IntBuffer** & **put** (const int *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers ints into this buffer from the given source array.

- **IntBuffer** & **put** (std::vector< int > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source ints array into this buffer.

- virtual **IntBuffer** & **put** (int value)=0 throw (BufferOverflowException, ReadOnlyBufferException)

Writes the given integer into this buffer at the current position, and then increments the position.

- virtual **IntBuffer** & **put** (int index, int value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)

Writes the given ints into this buffer at the given index.

- virtual **IntBuffer** * **slice** () const =0

*Creates a new **IntBuffer** (p. 2066) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **IntBuffer** &value) const

- virtual bool **equals** (const **IntBuffer** &value) const

- virtual bool **operator==** (const **IntBuffer** &value) const

- virtual bool **operator<** (const **IntBuffer** &value) const

Static Public Member Functions

- static **IntBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

Allocates a new Double buffer.

- static **IntBuffer** * **wrap** (int *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **IntBuffer** (p. 2066).*

- static **IntBuffer** * **wrap** (std::vector< int > &buffer)

*Wraps the passed STL int Vector in a **IntBuffer** (p. 2066).*

Protected Member Functions

- **IntBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **IntBuffer** (p. 2066) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.404.1 Detailed Description

This class defines four categories of operations upon int buffers: o Absolute and relative get and put methods that read and write single ints; o Relative bulk get methods that transfer contiguous sequences of ints from this buffer into an array; and o Relative bulk put methods that transfer contiguous sequences of ints from a int array or some other int buffer into this buffer o Methods for compacting, duplicating, and slicing a int buffer.

Double buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing int array into a buffer, or by creating a view of an existing byte buffer

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained.

6.404.2 Constructor & Destructor Documentation

- 6.404.2.1** decaf::nio::IntBuffer::IntBuffer (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **IntBuffer** (p. 2066) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size and limit of the **Buffer** (p. 928) in integers.

Exceptions:

IllegalArgumentException if capacity is negative.

- 6.404.2.2** virtual decaf::nio::IntBuffer::~~IntBuffer () [inline, virtual]

6.404.3 Member Function Documentation

- 6.404.3.1** static IntBuffer* decaf::nio::IntBuffer::allocate (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new Double buffer. The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Double buffer in integers.

Returns:

the **IntBuffer** (p. 2066) that was allocated, caller owns.

6.404.3.2 virtual int* decaf::nio::IntBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]

Returns the int array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2060).

6.404.3.3 virtual int decaf::nio::IntBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2061).

6.404.3.4 virtual IntBuffer* decaf::nio::IntBuffer::asReadOnlyBuffer () const [pure virtual]

Creates a new, read-only int buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only int buffer which the caller then owns.

Implemented in `decaf::internal::nio::IntArrayBuffer` (p. 2061).

6.404.3.5 `virtual IntBuffer& decaf::nio::IntBuffer::compact () throw (ReadOnlyBufferException)` [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this `IntBuffer` (p. 2066)

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::IntArrayBuffer` (p. 2062).

6.404.3.6 `virtual int decaf::nio::IntBuffer::compareTo (const IntBuffer & value) const` [virtual]

6.404.3.7 `virtual IntBuffer* decaf::nio::IntBuffer::duplicate ()` [pure virtual]

Creates a new int buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new int `Buffer` (p. 928) which the caller owns.

Implemented in `decaf::internal::nio::IntArrayBuffer` (p. 2062).

6.404.3.8 `virtual bool decaf::nio::IntBuffer::equals (const IntBuffer & value) const` [virtual]

6.404.3.9 `IntBuffer& decaf::nio::IntBuffer::get (int * buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)`

Relative bulk get method. This method transfers ints from this buffer into the given destination array. If there are fewer ints remaining in the buffer than are required to satisfy the request, that is, if $\text{length} > \text{remaining}()$ (p. 933), then no bytes are transferred and a `BufferUnderflowException` (p. 957) is thrown.

Otherwise, this method copies length ints from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by length.

Parameters:

buffer The pointer to an allocated buffer to fill.
size The size of the buffer that was passed in.
offset The position in the buffer to start filling.
length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length ints remaining in this buffer.
NullPointerException if the passed buffer is null.
IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.404.3.10 IntBuffer& decaf::nio::IntBuffer::get (std::vector< int > *buffer*) throw (BufferUnderflowException)

Relative bulk get method. This method transfers values from this buffer into the given destination vector. An invocation of this method of the form src.get(a) behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call buffer.resize(N) before calling this get method.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length ints remaining in this buffer.

6.404.3.11 virtual int decaf::nio::IntBuffer::get (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the int is to be read.

Returns:

the int that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2062).

6.404.3.12 **virtual int decaf::nio::IntBuffer::get () throw (BufferUnderflowException) [pure virtual]**

Relative get method. Reads the value at this buffer's current position, and then increments the position.

Returns:

the int at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2063).

6.404.3.13 **virtual bool decaf::nio::IntBuffer::hasArray () const [pure virtual]**

Tells whether or not this buffer is backed by an accessible int array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2063).

6.404.3.14 **virtual bool decaf::nio::IntBuffer::operator< (const IntBuffer & value) const [virtual]**

6.404.3.15 **virtual bool decaf::nio::IntBuffer::operator== (const IntBuffer & value) const [virtual]**

6.404.3.16 **virtual IntBuffer& decaf::nio::IntBuffer::put (int index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]**

Writes the given ints into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The ints to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException - If index greater than the buffer's limit minus the size of the type being written, or the index is negative.

ReadOnlyBufferException (p. 3169) - If this buffer is read-only.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2063).

6.404.3.17 virtual IntBuffer& decaf::nio::IntBuffer::put (int *value*) throw (BufferOverflowException, ReadOnlyBufferException) [pure virtual]

Writes the given integer into this buffer at the current position, and then increments the position.

Parameters:

value The integer value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2064).

6.404.3.18 IntBuffer& decaf::nio::IntBuffer::put (std::vector< int > & *buffer*) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source ints array into this buffer. This is the same as calling put(&buffer[0], 0, buffer.size()).

Parameters:

buffer The buffer whose contents are copied to this **IntBuffer** (p. 2066).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.404.3.19 `IntBuffer& decaf::nio::IntBuffer::put (const int *
buffer, int size, int offset, int length) throw (
BufferOverflowException, ReadOnlyBufferException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException)`

This method transfers ints into this buffer from the given source array. If there are more ints to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no ints are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `length` bytes from the given array into this buffer, starting at the given offset in the array and at the current position of this buffer. The position of this buffer is then incremented by `length`.

Parameters:

buffer The array from which integers are to be read.

size The size of the buffer passed.

offset The offset within the array of the first char to be read.

length The number of integers to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

NullPointerException if the passed buffer is null.

IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.404.3.20 `IntBuffer& decaf::nio::IntBuffer::put (IntBuffer & src) throw
(BufferOverflowException, ReadOnlyBufferException,
decaf::lang::exceptions::IllegalArgumentException)`

This method transfers the ints remaining in the given source buffer into this buffer. If there are more ints remaining in the source buffer than in this buffer, that is, if `src.remaining() > remaining()` (p. 933), then no ints are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` ints from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

src The buffer to take ints from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer for the remaining ints in the source buffer.

IllegalArgumentException if the source buffer is this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.404.3.21 virtual IntBuffer* decaf::nio::IntBuffer::slice () const [pure virtual]

Creates a new **IntBuffer** (p. 2066) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **IntBuffer** (p. 2066) which the caller owns.

Implemented in **decaf::internal::nio::IntArrayBuffer** (p. 2064).

6.404.3.22 virtual std::string decaf::nio::IntBuffer::toString () const [virtual]**Returns:**

a std::string describing this object

6.404.3.23 static IntBuffer* decaf::nio::IntBuffer::wrap (std::vector< int > & buffer) [static]

Wraps the passed STL int Vector in a **IntBuffer** (p. 2066). The new buffer will be backed by the given int array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be buffer.size(), its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling vector.resize(N).

Returns:

a new **IntBuffer** (p. 2066) that is backed by buffer, caller owns.

6.404.3.24 static IntBuffer* decaf::nio::IntBuffer::wrap (int * array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [static]

Wraps the passed buffer with a new **IntBuffer** (p. 2066). The new buffer will be backed by the given int array; that is, modifications to the buffer will cause the array to be modified and vice

versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

- array*** The array that will back the new buffer.
- size*** The size of the passed in array.
- offset*** The offset of the subarray to be used.
- length*** The length of the subarray to be used.

Returns:

- a new **IntBuffer** (p.2066) that is backed by buffer, caller owns.

Exceptions:

- NullPointerException*** if the array pointer is NULL.
- IndexOutOfBoundsException*** if the preconditions of size, offset, or length are not met.

The documentation for this class was generated from the following file:

- `src/main/decaf/nio/IntBuffer.h`

6.405 decaf::lang::Integer Class Reference

#include <src/main/decaf/lang/Integer.h> Inheritance diagram for decaf::lang::Integer:

Public Member Functions

- **Integer** (int value)
- **Integer** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Integer** ()
- virtual int **compareTo** (const **Integer** &i) const
*Compares this **Integer** (p. 2077) instance with another.*
- bool **equals** (const **Integer** &i) const
- virtual bool **operator==** (const **Integer** &i) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Integer** &i) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const int &i) const
*Compares this **Integer** (p. 2077) instance with another.*
- bool **equals** (const int &i) const
- virtual bool **operator==** (const int &i) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const int &i) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const
Answers the long value which the receiver represents.

Static Public Member Functions

- static **Integer** **decode** (const std::string &value) throw (exceptions::NumberFormatException)
*Decodes a **String** (p. 3665) into a **Integer** (p. 2077).*
- static int **reverseBytes** (int value)
Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified int value.
- static int **reverse** (int value)
Returns the value obtained by reversing the order of the bits in the two's complement binary representation of the specified int value.
- static int **parseInt** (const std::string &s, int radix) throw (exceptions::NumberFormatException)
Parses the string argument as a signed int in the radix specified by the second argument.
- static int **parseInt** (const std::string &s) throw (exceptions::NumberFormatException)
Parses the string argument as a signed decimal int.
- static **Integer** **valueOf** (int value)
*Returns a **Integer** (p. 2077) instance representing the specified int value.*
- static **Integer** **valueOf** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a **Integer** (p. 2077) object holding the value given by the specified std::string.*
- static **Integer** **valueOf** (const std::string &value, int radix) throw (exceptions::NumberFormatException)
*Returns a **Integer** (p. 2077) object holding the value extracted from the specified std::string when parsed with the radix given by the second argument.*
- static int **bitCount** (int value)
Returns the number of one-bits in the two's complement binary representation of the specified int value.
- static std::string **toString** (int value)
*Converts the int to a **String** (p. 3665) representation.*
- static std::string **toString** (int value, int radix)
Returns a string representation of the first argument in the radix specified by the second argument.
- static std::string **toHexString** (int value)
Returns a string representation of the integer argument as an unsigned integer in base 16.
- static std::string **toOctalString** (int value)
Returns a string representation of the integer argument as an unsigned integer in base 8.
- static std::string **toBinaryString** (int value)
Returns a string representation of the integer argument as an unsigned integer in base 2.

- static int **highestOneBit** (int value)
Returns an int value with at most a single one-bit, in the position of the highest-order ("leftmost") one-bit in the specified int value.
- static int **lowestOneBit** (int value)
Returns an int value with at most a single one-bit, in the position of the lowest-order ("rightmost") one-bit in the specified int value.
- static int **numberOfLeadingZeros** (int value)
Returns the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified int value.
- static int **numberOfTrailingZeros** (int value)
Returns the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified int value.
- static int **rotateLeft** (int value, int distance)
Returns the value obtained by rotating the two's complement binary representation of the specified int value left by the specified number of bits.
- static int **rotateRight** (int value, int distance)
Returns the value obtained by rotating the two's complement binary representation of the specified int value right by the specified number of bits.
- static int **signum** (int value)
Returns the signum function of the specified int value.

Static Public Attributes

- static const int **SIZE** = 32
The size in bits of the primitive int type.
- static const int **MAX_VALUE** = (int)0x7FFFFFFF
The maximum value that the primitive type can hold.
- static const int **MIN_VALUE** = (int)0x80000000
The minimum value that the primitive type can hold.

6.405.1 Constructor & Destructor Documentation

6.405.1.1 decaf::lang::Integer::Integer (int value)

Parameters:

value The primitive value to wrap in an Integer (p. 2077) instance.

6.405.1.2 `decaf::lang::Integer::Integer (const std::string & value) throw (exceptions::NumberFormatException)`

Parameters:

value The base 10 encoded string to decode to an `Integer` (p.2077) and wrap.

Exceptions:

NumberFormatException

6.405.1.3 `virtual decaf::lang::Integer::~~Integer () [inline, virtual]`

6.405.2 Member Function Documentation

6.405.2.1 `static int decaf::lang::Integer::bitCount (int value) [static]`

Returns the number of one-bits in the two's complement binary representation of the specified int value. This function is sometimes referred to as the population count.

Parameters:

value - the int to count

Returns:

the number of one-bits in the two's complement binary representation of the specified int value.

6.405.2.2 `virtual unsigned char decaf::lang::Integer::byteValue () const [inline, virtual]`

Answers the byte value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from `decaf::lang::Number` (p.2835).

6.405.2.3 `virtual int decaf::lang::Integer::compareTo (const int & i) const [virtual]`

Compares this `Integer` (p.2077) instance with another.

Parameters:

i - the `Integer` (p.2077) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements `decaf::lang::Comparable< int >` (p.1214).

6.405.2.4 virtual int decaf::lang::Integer::compareTo (const Integer & i) const [virtual]

Compares this **Integer** (p.2077) instance with another.

Parameters:

i - the **Integer** (p.2077) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.405.2.5 static Integer decaf::lang::Integer::decode (const std::string & value) throw (exceptions::NumberFormatException) [static]

Decodes a **String** (p.3665) into a **Integer** (p.2077). Accepts decimal, hexadecimal, and octal numbers given by the following grammar:

The sequence of characters following an (optional) negative sign and/or radix specifier ("0x", "0X", "#", or leading zero) is parsed as by the Integer.parseInt method with the indicated radix (10, 16, or 8). This sequence of characters must represent a positive value or a NumberFormatException will be thrown. The result is negated if first character of the specified **String** (p.3665) is the minus sign. No whitespace characters are permitted in the string.

Parameters:

value - The string to decode

Returns:

a **Integer** (p.2077) object containing the decoded value

Exceptions:

NumberFormatException if the string is not formatted correctly.

6.405.2.6 virtual double decaf::lang::Integer::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p.2836).

6.405.2.7 bool decaf::lang::Integer::equals (const int & i) const [inline, virtual]**Parameters:**

i - the **Integer** (p.2077) object to compare against.

Returns:

true if the two **Integer** (p. 2077) Objects have the same value.

Implements **decaf::lang::Comparable**< **int** > (p. 1215).

6.405.2.8 bool decaf::lang::Integer::equals (const Integer & i) const [inline]**Parameters:**

i - the **Integer** (p. 2077) object to compare against.

Returns:

true if the two **Integer** (p. 2077) Objects have the same value.

6.405.2.9 virtual float decaf::lang::Integer::floatValue () const [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.405.2.10 static int decaf::lang::Integer::highestOneBit (int value) [static]

Returns an int value with at most a single one-bit, in the position of the highest-order ("leftmost") one-bit in the specified int value. Returns zero if the specified value has no one-bits in its two's complement binary representation, that is, if it is equal to zero.

Parameters:

value - the int to be inspected

Returns:

an int value with a single one-bit, in the position of the highest-order one-bit in the specified value, or zero if the specified value is itself equal to zero.

6.405.2.11 virtual int decaf::lang::Integer::intValue () const [inline, virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.405.2.12 `virtual long long decaf::lang::Integer::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.405.2.13 `static int decaf::lang::Integer::lowestOneBit (int value) [static]`

Returns an int value with at most a single one-bit, in the position of the lowest-order ("rightmost") one-bit in the specified int value. Returns zero if the specified value has no one-bits in its two's complement binary representation, that is, if it is equal to zero.

Parameters:

value - the int to be inspected

Returns:

an int value with a single one-bit, in the position of the lowest-order one-bit in the specified value, or zero if the specified value is itself equal to zero.

6.405.2.14 `static int decaf::lang::Integer::numberOfLeadingZeros (int value) [static]`

Returns the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified int value. Returns 32 if the specified value has no one-bits in its two's complement representation, in other words if it is equal to zero.

Note that this method is closely related to the logarithm base 2. For all positive int values x:

$\ast \text{floor}(\log_2(x)) = 31 - \text{numberOfLeadingZeros}(x) \ast \text{ceil}(\log_2(x)) = 32 - \text{numberOfLeadingZeros}(x - 1)$

Parameters:

value - the int to be inspected

Returns:

the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified int value, or 32 if the value is equal to zero.

6.405.2.15 `static int decaf::lang::Integer::numberOfTrailingZeros (int value) [static]`

Returns the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified int value. Returns 32 if the specified value has no one-bits in its two's complement representation, in other words if it is equal to zero.

Parameters:

value - the int to be inspected

Returns:

the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified int value, or 32 if the value is equal to zero.

6.405.2.16 `virtual bool decaf::lang::Integer::operator< (const int & i) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

i - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< int >` (p. 1215).

6.405.2.17 `virtual bool decaf::lang::Integer::operator< (const Integer & i) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

i - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.405.2.18 `virtual bool decaf::lang::Integer::operator== (const int & i) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

i - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< int >` (p. 1215).

6.405.2.19 `virtual bool decaf::lang::Integer::operator==(const Integer & i) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

i - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.405.2.20 `static int decaf::lang::Integer::parseInt (const std::string & s) throw (`
`exceptions::NumberFormatException) [static]`

Parses the string argument as a signed decimal int. The characters in the string must all be decimal digits, except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting int value is returned, exactly as if the argument and the radix 10 were given as arguments to the parseInt(const std::string, int) method.

Parameters:

s - **String** (p. 3665) to convert to a int

Returns:

the converted int value

Exceptions:

NumberFormatException if the string is not a int.

6.405.2.21 `static int decaf::lang::Integer::parseInt (const std::string & s, int radix)`
`throw (exceptions::NumberFormatException) [static]`

Parses the string argument as a signed int in the radix specified by the second argument. The characters in the string must all be digits, of the specified radix (as determined by whether **Character.digit(char, int)** (p. 1103) returns a nonnegative value) except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting byte value is returned.

An exception of type *NumberFormatException* is thrown if any of the following situations occurs:
* The first argument is null or is a string of length zero. * The radix is either smaller than **Character.MIN_RADIX** (p. 1107) or larger than **Character.MAX_RADIX** (p. 1106). * Any character of the string is not a digit of the specified radix, except that the first character may be a minus sign '-' provided that the string is longer than length 1. * The value represented by the string is not a value of type int.

Parameters:

s - the **String** (p. 3665) containing the int representation to be parsed

radix - the radix to be used while parsing s

Returns:

the int represented by the string argument in the specified radix.

Exceptions:

NumberFormatException - If **String** (p.3665) does not contain a parsable int.

6.405.2.22 static int decaf::lang::Integer::reverse (int *value*) [static]

Returns the value obtained by reversing the order of the bits in the two's complement binary representation of the specified int value.

Parameters:

value - the value whose bits are to be reversed

Returns:

the reversed bits int.

6.405.2.23 static int decaf::lang::Integer::reverseBytes (int *value*) [static]

Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified int value.

Parameters:

value - the int whose bytes we are to reverse

Returns:

the reversed int.

6.405.2.24 static int decaf::lang::Integer::rotateLeft (int *value*, int *distance*) [static]

Returns the value obtained by rotating the two's complement binary representation of the specified int value left by the specified number of bits. (Bits shifted out of the left hand, or high-order, side reenter on the right, or low-order.)

Note that left rotation with a negative distance is equivalent to right rotation: `rotateLeft(val, -distance) == rotateRight(val, distance)`. Note also that rotation by any multiple of 32 is a no-op, so all but the last five bits of the rotation distance can be ignored, even if the distance is negative: `rotateLeft(val, distance) == rotateLeft(val, distance & 0x1F)`.

Parameters:

value - the int to be inspected

distance - the number of bits to rotate

Returns:

the value obtained by rotating the two's complement binary representation of the specified int value left by the specified number of bits.

6.405.2.25 static int decaf::lang::Integer::rotateRight (int *value*, int *distance*)
[static]

Returns the value obtained by rotating the two's complement binary representation of the specified int value right by the specified number of bits. (Bits shifted out of the right hand, or low-order, side reenter on the left, or high-order.)

Note that right rotation with a negative distance is equivalent to left rotation: rotateRight(val, -distance) == rotateLeft(val, distance). Note also that rotation by any multiple of 32 is a no-op, so all but the last five bits of the rotation distance can be ignored, even if the distance is negative: rotateRight(val, distance) == rotateRight(val, distance & 0x1F).

Parameters:

value - the int to be inspected

distance - the number of bits to rotate

Returns:

the value obtained by rotating the two's complement binary representation of the specified int value right by the specified number of bits.

6.405.2.26 virtual short decaf::lang::Integer::shortValue () const [inline, virtual]

Answers the short value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2837).

6.405.2.27 static int decaf::lang::Integer::signum (int *value*) [static]

Returns the signum function of the specified int value. (The return value is -1 if the specified value is negative; 0 if the specified value is zero; and 1 if the specified value is positive.)

Parameters:

value - the int to be inspected

Returns:

the signum function of the specified int value.

6.405.2.28 static std::string decaf::lang::Integer::toBinaryString (int *value*)
[static]

Returns a string representation of the integer argument as an unsigned integer in base 2. The unsigned integer value is the argument plus 2^{32} if the argument is negative; otherwise it is equal to the argument. This value is converted to a string of ASCII digits in binary (base 2) with no extra leading 0s. If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character.

The characters '0' and '1' are used as binary digits.

Parameters:

value - the int to be translated to a binary string

Returns:

the unsigned int value as a binary string

6.405.2.29 static std::string decaf::lang::Integer::toHexString (int *value*) [static]

Returns a string representation of the integer argument as an unsigned integer in base 16. The unsigned integer value is the argument plus 2^{32} if the argument is negative; otherwise, it is equal to the argument. This value is converted to a string of ASCII digits in hexadecimal (base 16) with no extra leading 0s. If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character. The following characters are used as hexadecimal digits:

0123456789abcdef

If uppercase letters are desired, the toUpperCase() method may be called on the result:

Parameters:

value - the int to be translated to an Octal string

Returns:

the unsigned int value as a Octal string

6.405.2.30 static std::string decaf::lang::Integer::toOctalString (int *value*) [static]

Returns a string representation of the integer argument as an unsigned integer in base 8. The unsigned integer value is the argument plus 2^{32} if the argument is negative; otherwise, it is equal to the argument. This value is converted to a string of ASCII digits in octal (base 8) with no extra leading 0s.

If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character. The following characters are used as octal digits:

01234567

Parameters:

value - the int to be translated to an Octal string

Returns:

the unsigned int value as a Octal string

6.405.2.31 static std::string decaf::lang::Integer::toString (int *value*, int *radix*) [static]

Returns a string representation of the first argument in the radix specified by the second argument. If the radix is smaller than **Character.MIN_RADIX** (p.1107) or larger than **Character.MAX_RADIX** (p.1106), then the radix 10 is used instead.

If the first argument is negative, the first element of the result is the ASCII minus character '-'. If the first argument is not negative, no sign character appears in the result.

The remaining characters of the result represent the magnitude of the first argument. If the magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the magnitude will not be the zero character. The following ASCII characters are used as digits:

0123456789abcdefghijklmnopqrstuvwxyz

Parameters:

value - the int to convert to a string

radix - the radix to format the string in

Returns:

an int formatted to the string value of the radix given.

6.405.2.32 static std::string decaf::lang::Integer::toString (int *value*) [static]

Converts the int to a **String** (p. 3665) representation.

Parameters:

value The int to convert to a std::string instance.

Returns:

string representation

6.405.2.33 std::string decaf::lang::Integer::toString () const

Returns:

this Integer (p. 2077) Object as a **String** (p. 3665) Representation

6.405.2.34 static Integer decaf::lang::Integer::valueOf (const std::string & *value*, int *radix*) throw (exceptions::NumberFormatException) [static]

Returns a **Integer** (p. 2077) object holding the value extracted from the specified std::string when parsed with the radix given by the second argument. The first argument is interpreted as representing a signed int in the radix specified by the second argument, exactly as if the argument were given to the parseInt(std::string, int) method. The result is a **Integer** (p. 2077) object that represents the int value specified by the string.

Parameters:

value - std::string to parse as base (radix)

radix - base of the string to parse.

Returns:

new **Integer** (p. 2077) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a valid int.

6.405.2.35 `static Integer decaf::lang::Integer::valueOf (const std::string & value)
 throw (exceptions::NumberFormatException) [static]`

Returns a **Integer** (p. 2077) object holding the value given by the specified `std::string`. The argument is interpreted as representing a signed decimal int, exactly as if the argument were given to the `parseInt(std::string)` method. The result is a **Integer** (p. 2077) object that represents the int value specified by the string.

Parameters:

value - `std::string` to parse as base 10

Returns:

new **Integer** (p. 2077) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a decimal int.

6.405.2.36 `static Integer decaf::lang::Integer::valueOf (int value) [inline, static]`

Returns a **Integer** (p. 2077) instance representing the specified int value.

Parameters:

value - the int to wrap

Returns:

the new **Integer** (p. 2077) object wrapping value.

6.405.3 Field Documentation

6.405.3.1 `const int decaf::lang::Integer::MAX_VALUE = (int)0x7FFFFFFF
 [static]`

The maximum value that the primitive type can hold.

6.405.3.2 `const int decaf::lang::Integer::MIN_VALUE = (int)0x80000000 [static]`

The minimum value that the primitive type can hold.

6.405.3.3 `const int decaf::lang::Integer::SIZE = 32 [static]`

The size in bits of the primitive int type.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Integer.h`

6.406 activemq::commands::IntegerResponse Class Reference

#include <src/main/activemq/commands/IntegerResponse.h> Inheritance diagram for activemq::commands::IntegerResponse:

Public Member Functions

- **IntegerResponse** ()
- virtual **~IntegerResponse** ()
- virtual unsigned char **getDataStructureType** () const

Get the unique identifier that this object and its own Marshaler share.

- virtual **IntegerResponse * cloneDataStructure** () const

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

- virtual void **copyDataStructure** (const **DataStructure** *src)

Copy the contents of the passed object into this object's members, overwriting any existing data.

- virtual std::string **toString** () const

*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*

- virtual bool **equals** (const **DataStructure** *value) const

*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

- virtual int **getResult** () const
- virtual void **setResult** (int result)

Static Public Attributes

- static const unsigned char **ID_INTEGERRESPONSE** = 34

Protected Attributes

- int **result**

6.406.1 Constructor & Destructor Documentation

6.406.1.1 `activemq::commands::IntegerResponse::IntegerResponse ()`

6.406.1.2 `virtual activemq::commands::IntegerResponse::~~IntegerResponse ()`
[virtual]

6.406.2 Member Function Documentation

6.406.2.1 `virtual IntegerResponse* activemq::commands::IntegerResponse::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.406.2.2 `virtual void activemq::commands::IntegerResponse::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::Response` (p. 3286).

6.406.2.3 `virtual bool activemq::commands::IntegerResponse::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::Response` (p. 3286).

6.406.2.4 `virtual unsigned char activemq::commands::IntegerResponse::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Reimplemented from `activemq::commands::Response` (p.3287).

6.406.2.5 `virtual int activemq::commands::IntegerResponse::getResult () const`
[virtual]

6.406.2.6 `virtual void activemq::commands::IntegerResponse::setResult (int result)`
[virtual]

6.406.2.7 `virtual std::string activemq::commands::IntegerResponse::toString ()`
`const` [virtual]

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::Response` (p.3287).

6.406.3 Field Documentation

6.406.3.1 `const unsigned char activemq::commands::IntegerResponse::ID_-`
`INTEGERRESPONSE = 34` [static]

6.406.3.2 `int activemq::commands::IntegerResponse::result` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/IntegerResponse.h`

6.407 activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2094).

#include <src/main/activemq/wireformat/openwire/marshal/v6/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.407.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2094).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.407.2 Constructor & Destructor Documentation

6.407.2.1 `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.407.2.2 `virtual activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.407.3 Member Function Documentation

6.407.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.407.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.407.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3321).

6.407.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.407.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller` (p. 3322).

6.407.3.6 virtual void activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3323).

6.407.3.7 virtual void activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller** (p. 3324).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**IntegerResponseMarshaller.h**

6.408 activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2098).

#include <src/main/activemq/wireformat/openwire/marshal/v2/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.408.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2098).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.408.2 Constructor & Destructor Documentation

6.408.2.1 `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.408.2.2 `virtual activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.408.3 Member Function Documentation

6.408.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.408.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.408.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3301).

6.408.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.408.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller` (p. 3302).

6.408.3.6 virtual void activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3303).

6.408.3.7 virtual void activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller** (p. 3304).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**IntegerResponseMarshaller.h**

6.409 activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2102).

#include <src/main/activemq/wireformat/openwire/marshal/v3/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.409.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2102).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.409.2 Constructor & Destructor Documentation

6.409.2.1 `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.409.2.2 `virtual activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.409.3 Member Function Documentation

6.409.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.409.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.409.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3311).

6.409.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.409.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller` (p. 3312).

6.409.3.6 virtual void activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p.3313).

6.409.3.7 virtual void activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller** (p.3314).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**IntegerResponseMarshaller.h**

6.410 activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2106).

#include <src/main/activemq/wireformat/openwire/marshal/v4/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.410.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2106).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.410.2 Constructor & Destructor Documentation

6.410.2.1 `activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.410.2.2 `virtual activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.410.3 Member Function Documentation

6.410.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.410.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.410.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3296).

6.410.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.410.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller` (p. 3297).

6.410.3.6 virtual void activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3298).

6.410.3.7 virtual void activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller** (p. 3299).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**IntegerResponseMarshaller.h**

6.411 activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2110).

#include <src/main/activemq/wireformat/openwire/marshal/v1/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.411.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2110).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.411.2 Constructor & Destructor Documentation

6.411.2.1 `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.411.2.2 `virtual activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.411.3 Member Function Documentation

6.411.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.411.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.411.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3316).

6.411.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.411.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller` (p. 3317).

6.411.3.6 virtual void activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3318).

6.411.3.7 virtual void activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller** (p. 3319).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**IntegerResponseMarshaller.h**

6.412 activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2114).

#include <src/main/activemq/wireformat/openwire/marshal/v5/IntegerResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller:

Public Member Functions

- **IntegerResponseMarshaller** ()
- virtual **~IntegerResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.412.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2114).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.412.2 Constructor & Destructor Documentation

6.412.2.1 `activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::IntegerResponseMarshaller()` [inline]

6.412.2.2 `virtual activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::~~IntegerResponseMarshaller()` [inline, virtual]

6.412.3 Member Function Documentation

6.412.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.412.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.412.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3306).

6.412.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.412.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller` (p. 3307).

6.412.3.6 virtual void activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3308).

6.412.3.7 virtual void activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller** (p. 3309).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/IntegerResponseMarshaller.h

6.413 internal_state Struct Reference

```
#include <src/main/decaf/internal/util/zip/deflate.h>
```

Data Fields

- **z_stream** strm
- **int** status
- **Bytef** * pending_buf
- **ulg** pending_buf_size
- **Bytef** * pending_out
- **uInt** pending
- **int** wrap
- **gz_headerp** gzhead
- **uInt** gzindex
- **Byte** method
- **int** last_flush
- **uInt** w_size
- **uInt** w_bits
- **uInt** w_mask
- **Bytef** * window
- **ulg** window_size
- **Posf** * prev
- **Posf** * head
- **uInt** ins_h
- **uInt** hash_size
- **uInt** hash_bits
- **uInt** hash_mask
- **uInt** hash_shift
- **long** block_start
- **uInt** match_length
- **IPos** prev_match
- **int** match_available
- **uInt** strstart
- **uInt** match_start
- **uInt** lookahead
- **uInt** prev_length
- **uInt** max_chain_length
- **uInt** max_lazy_match
- **int** level
- **int** strategy
- **uInt** good_match
- **int** nice_match
- **struct ct_data_s** dyn_ltree [HEAP_SIZE]
- **struct ct_data_s** dyn_dtree [2 *D_CODES+1]
- **struct ct_data_s** bl_tree [2 *BL_CODES+1]
- **struct tree_desc_s** l_desc
- **struct tree_desc_s** d_desc
- **struct tree_desc_s** bl_desc
- **ush** bl_count [MAX_BITS+1]

- `int heap [2 * L_CODES + 1]`
- `int heap_len`
- `int heap_max`
- `uch depth [2 * L_CODES + 1]`
- `uchf * l_buf`
- `uInt lit_bufsize`
- `uInt last_lit`
- `ushf * d_buf`
- `ulg opt_len`
- `ulg static_len`
- `uInt matches`
- `int last_eob_len`
- `ush bi_buf`
- `int bi_valid`
- `ulg high_water`
- `int dummy`

6.413.1 Field Documentation

- 6.413.1.1 ush internal_state::bi_buf
- 6.413.1.2 int internal_state::bi_valid
- 6.413.1.3 ush internal_state::bl_count[MAX_BITS+1]
- 6.413.1.4 struct tree_desc_s internal_state::bl_desc [read]
- 6.413.1.5 struct ct_data_s internal_state::bl_tree[2 *BL_CODES+1] [read]
- 6.413.1.6 long internal_state::block_start
- 6.413.1.7 ushf* internal_state::d_buf
- 6.413.1.8 struct tree_desc_s internal_state::d_desc [read]
- 6.413.1.9 uch internal_state::depth[2 *L_CODES+1]
- 6.413.1.10 int internal_state::dummy
- 6.413.1.11 struct ct_data_s internal_state::dyn_dtree[2 *D_CODES+1] [read]
- 6.413.1.12 struct ct_data_s internal_state::dyn_ltree[HEAP_SIZE] [read]
- 6.413.1.13 uInt internal_state::good_match
- 6.413.1.14 gz_headerp internal_state::gzhead
- 6.413.1.15 uInt internal_state::gzindex
- 6.413.1.16 uInt internal_state::hash_bits
- 6.413.1.17 uInt internal_state::hash_mask
- 6.413.1.18 uInt internal_state::hash_shift
- 6.413.1.19 uInt internal_state::hash_size
- 6.413.1.20 Posf* internal_state::head
- 6.413.1.21 int internal_state::heap[2 *L_CODES+1]
- 6.413.1.22 int internal_state::heap_len
- 6.413.1.23 int internal_state::heap_max
- 6.413.1.24 ulg internal_state::high_water
- 6.413.1.25 uInt internal_state::ins_h
- 6.413.1.26 uchf* internal_state::l_buf
- 6.413.1.27 struct tree_desc_s internal_state::l_desc [read]
- 6.413.1.28 int internal_state::last_eob_len
- 6.413.1.29 int internal_state::last_flush
- 6.413.1.30 uInt internal_state::last_lit

- src/main/decaf/internal/util/zip/**deflate.h**
- src/main/decaf/internal/util/zip/**zlib.h**

6.414 activemq::transport::mock::InternalCommandListener Class Reference

Listens for Commands sent from the **MockTransport** (p. 2768).

#include <src/main/activemq/transport/mock/InternalCommandListener.h>Inheritance diagram for activemq::transport::mock::InternalCommandListener:

Public Member Functions

- **InternalCommandListener** ()
- virtual **~InternalCommandListener** ()
- void **setTransport** (**MockTransport** *transport)
- void **setResponseBuilder** (const **Pointer**< **ResponseBuilder** > &responseBuilder)
- virtual void **onCommand** (const **Pointer**< **Command** > &command)
Event handler for the receipt of a command.
- void **run** ()
Default implementation of the run method - does nothing.

6.414.1 Detailed Description

Listens for Commands sent from the **MockTransport** (p. 2768). This class processes all outbound **commands** (p. 87) and sends responses that are constructed by calling the Protocol provided **ResponseBuilder** (p. 3289) and getting a set of Commands to send back into the **MockTransport** (p. 2768) as incoming Commands and Responses.

6.414.2 Constructor & Destructor Documentation

6.414.2.1 **activemq::transport::mock::InternalCommandListener::InternalCommandListener** ()

6.414.2.2 **virtual**
activemq::transport::mock::InternalCommandListener::~~InternalCommandListener
 () [virtual]

6.414.3 Member Function Documentation

6.414.3.1 **virtual void** **activemq::transport::mock::InternalCommandListener::onCommand** (const **Pointer**< **Command** > & *command*) [virtual]

Event handler for the receipt of a command. The **transport** (p. 97) passes off all received **commands** (p. 87) to its listeners, the listener then owns the Object. If there is no registered listener the **Transport** (p. 3883) deletes the command upon receipt.

Parameters:

command the received command object.

Implements **activemq::transport::TransportListener** (p. 3900).

6.414.3.2 void activemq::transport::mock::InternalCommandListener::run ()
[virtual]

Default implementation of the run method - does nothing.

Reimplemented from **decaf::lang::Thread** (p. 3771).

6.414.3.3 void activemq::transport::mock::InternalCommandListener::setResponseBuilder
(const Pointer< ResponseBuilder > & *responseBuilder*) [inline]**6.414.3.4 void activemq::transport::mock::InternalCommandListener::setTransport**
(MockTransport * *transport*) [inline]

The documentation for this class was generated from the following file:

- src/main/activemq/transport/mock/**InternalCommandListener.h**

6.415 decaf::lang::exceptions::InterruptedException Class Reference

#include <src/main/decaf/lang/exceptions/InterruptedException.h> Inheritance diagram for decaf::lang::exceptions::InterruptedException:

Public Member Functions

- **InterruptedException** () throw ()
Default Constructor.
- **InterruptedException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **InterruptedException** (const **InterruptedException** &ex) throw ()
Copy Constructor.
- **InterruptedException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **InterruptedException** (const std::exception *cause) throw ()
Constructor.
- **InterruptedException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **InterruptedException** * **clone** () const
Clones this exception.
- virtual ~**InterruptedException** () throw ()

6.415.1 Constructor & Destructor Documentation

6.415.1.1 decaf::lang::exceptions::InterruptedException::InterruptedException () throw () [inline]

Default Constructor.

6.415.1.2 decaf::lang::exceptions::InterruptedException::InterruptedException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.415.1.3 decaf::lang::exceptions::InterruptedException::InterruptedException
(const InterruptedException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p.1831) whose data is to be copied into this one.

6.415.1.4 decaf::lang::exceptions::InterruptedException::InterruptedException
(const char * *file*, const int *lineNumber*, const std::exception * *cause*,
const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.415.1.5 decaf::lang::exceptions::InterruptedException::InterruptedException
(const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p.2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.415.1.6 decaf::lang::exceptions::InterruptedException::InterruptedException
(const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()
[inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.415.1.7 **virtual**
decaf::lang::exceptions::InterruptedException::~~InterruptedException ()
throw () [inline, virtual]

6.415.2 Member Function Documentation

6.415.2.1 **virtual InterruptedException* de-**
caf::lang::exceptions::InterruptedException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**InterruptedException.h**

6.416 decaf::io::InterruptedIOException Class Reference

#include <src/main/decaf/io/InterruptedIOException.h> Inheritance diagram for decaf::io::InterruptedIOException:

Public Member Functions

- **InterruptedIOException** () throw ()
Default Constructor.
- **InterruptedIOException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **InterruptedIOException** (const InterruptedIOException &ex) throw ()
Copy Constructor.
- **InterruptedIOException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **InterruptedIOException** (const std::exception *cause) throw ()
Constructor.
- **InterruptedIOException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **InterruptedIOException** * clone () const
Clones this exception.
- virtual ~**InterruptedIOException** () throw ()

6.416.1 Constructor & Destructor Documentation

6.416.1.1 decaf::io::InterruptedIOException::InterruptedIOException () throw () [inline]

Default Constructor.

6.416.1.2 decaf::io::InterruptedIOException::InterruptedIOException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.416.1.3 `decaf::io::InterruptedIOException::InterruptedIOException (const InterruptedIOException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.416.1.4 `decaf::io::InterruptedIOException::InterruptedIOException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.416.1.5 `decaf::io::InterruptedIOException::InterruptedIOException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.416.1.6 `decaf::io::InterruptedIOException::InterruptedIOException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.416.1.7 virtual decaf::io::InterruptedIOException::~~InterruptedIOException ()
throw () [inline, virtual]

6.416.2 Member Function Documentation

6.416.2.1 virtual InterruptedIOException* decaf::io::InterruptedIOException::clone
() const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new exception that is a copy of this one.

Reimplemented from **decaf::io::IOException** (p. 2144).

Reimplemented in **decaf::net::SocketTimeoutException** (p. 3544).

The documentation for this class was generated from the following file:

- src/main/decaf/io/**InterruptedIOException.h**

6.417 cms::InvalidClientIdException Class Reference

This exception must be thrown when a client attempts to set a connection's client ID to a value that is rejected by a provider.

#include <src/main/cms/InvalidClientIdException.h> Inheritance diagram for cms::InvalidClientIdException:

Public Member Functions

- **InvalidClientIdException** () throw ()
- **InvalidClientIdException** (const **InvalidClientIdException** &ex) throw ()
- **InvalidClientIdException** (const std::string &message, const std::exception *cause) throw ()
- **InvalidClientIdException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**InvalidClientIdException** () throw ()

6.417.1 Detailed Description

This exception must be thrown when a client attempts to set a connection's client ID to a value that is rejected by a provider.

Since:

1.3

6.417.2 Constructor & Destructor Documentation

- 6.417.2.1** cms::InvalidClientIdException::InvalidClientIdException () throw ()
- 6.417.2.2** cms::InvalidClientIdException::InvalidClientIdException (const InvalidClientIdException & ex) throw ()
- 6.417.2.3** cms::InvalidClientIdException::InvalidClientIdException (const std::string & message, const std::exception * cause) throw ()
- 6.417.2.4** cms::InvalidClientIdException::InvalidClientIdException (const std::string & message, const std::exception * cause, const std::vector< std::pair< std::string, int > > & stackTrace) throw ()
- 6.417.2.5** virtual cms::InvalidClientIdException::~InvalidClientIdException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/InvalidClientIdException.h

6.418 cms::InvalidDestinationException Class Reference

This exception must be thrown when a destination either is not understood by a provider or is no longer valid.

#include <src/main/cms/InvalidDestinationException.h> Inheritance diagram for cms::InvalidDestinationException:

Public Member Functions

- **InvalidDestinationException** () throw ()
- **InvalidDestinationException** (const **InvalidDestinationException** &ex) throw ()
- **InvalidDestinationException** (const std::string &message, const std::exception *cause) throw ()
- **InvalidDestinationException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**InvalidDestinationException** () throw ()

6.418.1 Detailed Description

This exception must be thrown when a destination either is not understood by a provider or is no longer valid.

Since:

1.3

6.418.2 Constructor & Destructor Documentation

- 6.418.2.1 **cms::InvalidDestinationException::InvalidDestinationException** () throw ()
- 6.418.2.2 **cms::InvalidDestinationException::InvalidDestinationException** (const **InvalidDestinationException** & *ex*) throw ()
- 6.418.2.3 **cms::InvalidDestinationException::InvalidDestinationException** (const std::string & *message*, const std::exception * *cause*) throw ()
- 6.418.2.4 **cms::InvalidDestinationException::InvalidDestinationException** (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()
- 6.418.2.5 virtual **cms::InvalidDestinationException::~~InvalidDestinationException** () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/**InvalidDestinationException.h**

6.419 decaf::security::InvalidKeyException Class Reference

`#include <src/main/decaf/security/InvalidKeyException.h>` Inheritance diagram for `decaf::security::InvalidKeyException`:

Public Member Functions

- **InvalidKeyException** () throw ()
Default Constructor.
- **InvalidKeyException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **InvalidKeyException** (const **InvalidKeyException** &ex) throw ()
Copy Constructor.
- **InvalidKeyException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **InvalidKeyException** (const std::exception *cause) throw ()
Constructor.
- **InvalidKeyException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **InvalidKeyException** * clone () const
Clones this exception.
- virtual ~**InvalidKeyException** () throw ()

6.419.1 Constructor & Destructor Documentation

6.419.1.1 decaf::security::InvalidKeyException::InvalidKeyException () throw () [inline]

Default Constructor.

6.419.1.2 decaf::security::InvalidKeyException::InvalidKeyException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.419.1.3 decaf::security::InvalidKeyException::InvalidKeyException (const InvalidKeyException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.419.1.4 decaf::security::InvalidKeyException::InvalidKeyException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.419.1.5 decaf::security::InvalidKeyException::InvalidKeyException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.419.1.6 decaf::security::InvalidKeyException::InvalidKeyException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.419.1.7 `virtual decaf::security::InvalidKeyException::~~InvalidKeyException ()
throw () [inline, virtual]`

6.419.2 Member Function Documentation

6.419.2.1 `virtual InvalidKeyException* decaf::security::InvalidKeyException::clone
() const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::KeyException` (p. 2297).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/InvalidKeyException.h`

6.420 decaf::nio::InvalidMarkException Class Reference

#include <src/main/decaf/nio/InvalidMarkException.h> Inheritance diagram for decaf::nio::InvalidMarkException:

Public Member Functions

- **InvalidMarkException** () throw ()
Default Constructor.
- **InvalidMarkException** (const lang::Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **InvalidMarkException** (const InvalidMarkException &ex) throw ()
Copy Constructor.
- **InvalidMarkException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **InvalidMarkException** (const std::exception *cause) throw ()
Constructor.
- **InvalidMarkException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **InvalidMarkException** * clone () const
Clones this exception.
- virtual ~**InvalidMarkException** () throw ()

6.420.1 Constructor & Destructor Documentation

6.420.1.1 decaf::nio::InvalidMarkException::InvalidMarkException () throw () [inline]

Default Constructor.

6.420.1.2 decaf::nio::InvalidMarkException::InvalidMarkException (const lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex The Exception whose state data is to be copied into this Exception.

6.420.1.3 `decaf::nio::InvalidMarkException::InvalidMarkException (const InvalidMarkException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex The Exception whose state data is to be copied into this Exception.

6.420.1.4 `decaf::nio::InvalidMarkException::InvalidMarkException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.420.1.5 `decaf::nio::InvalidMarkException::InvalidMarkException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.420.1.6 `decaf::nio::InvalidMarkException::InvalidMarkException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.420.1.7 virtual decaf::nio::InvalidMarkException::~InvalidMarkException ()
throw () [inline, virtual]

6.420.2 Member Function Documentation

6.420.2.1 virtual InvalidMarkException* decaf::nio::InvalidMarkException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A new Exception instance that is a copy of this Exception.

Reimplemented from **decaf::lang::exceptions::IllegalStateException** (p. 2000).

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**InvalidMarkException.h**

6.421 cms::InvalidSelectorException Class Reference

This exception must be thrown when a CMS client attempts to give a provider a message selector with invalid syntax.

#include <src/main/cms/InvalidSelectorException.h> Inheritance diagram for cms::InvalidSelectorException:

Public Member Functions

- **InvalidSelectorException** () throw ()
- **InvalidSelectorException** (const **InvalidSelectorException** &ex) throw ()
- **InvalidSelectorException** (const std::string &message, const std::exception *cause) throw ()
- **InvalidSelectorException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**InvalidSelectorException** () throw ()

6.421.1 Detailed Description

This exception must be thrown when a CMS client attempts to give a provider a message selector with invalid syntax.

Since:

1.3

6.421.2 Constructor & Destructor Documentation

6.421.2.1 cms::InvalidSelectorException::InvalidSelectorException () throw ()

6.421.2.2 cms::InvalidSelectorException::InvalidSelectorException (const InvalidSelectorException & ex) throw ()

6.421.2.3 cms::InvalidSelectorException::InvalidSelectorException (const std::string & message, const std::exception * cause) throw ()

6.421.2.4 cms::InvalidSelectorException::InvalidSelectorException (const std::string & message, const std::exception * cause, const std::vector< std::pair< std::string, int > > & stackTrace) throw ()

6.421.2.5 virtual cms::InvalidSelectorException::~InvalidSelectorException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/**InvalidSelectorException.h**

6.422 decaf::lang::exceptions::InvalidStateException Class Reference

#include <src/main/decaf/lang/exceptions/InvalidStateException.h> Inheritance diagram for decaf::lang::exceptions::InvalidStateException:

Public Member Functions

- **InvalidStateException** () throw ()
Default Constructor.
- **InvalidStateException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **InvalidStateException** (const **InvalidStateException** &ex) throw ()
Copy Constructor.
- **InvalidStateException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **InvalidStateException** (const std::exception *cause) throw ()
Constructor.
- **InvalidStateException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **InvalidStateException** * clone () const
Clones this exception.
- virtual ~**InvalidStateException** () throw ()

6.422.1 Constructor & Destructor Documentation

6.422.1.1 decaf::lang::exceptions::InvalidStateException::InvalidStateException () throw () [inline]

Default Constructor.

6.422.1.2 decaf::lang::exceptions::InvalidStateException::InvalidStateException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.422.1.3 `decaf::lang::exceptions::InvalidStateException::InvalidStateException` (const InvalidStateException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p.1831) whose data is to be copied into this one.

6.422.1.4 `decaf::lang::exceptions::InvalidStateException::InvalidStateException` (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.422.1.5 `decaf::lang::exceptions::InvalidStateException::InvalidStateException` (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p.2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.422.1.6 `decaf::lang::exceptions::InvalidStateException::InvalidStateException` (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.422.1.7 virtual
decaf::lang::exceptions::InvalidStateException::~InvalidStateException ()
throw () [inline, virtual]

6.422.2 Member Function Documentation

6.422.2.1 virtual InvalidStateException* decaf::lang::exceptions::InvalidStateException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**InvalidStateException.h**

6.423 decaf::io::IOException Class Reference

#include <src/main/decaf/io/IOException.h> Inheritance diagram for decaf::io::IOException:

Public Member Functions

- **IOException** () throw ()
Default Constructor.
- **IOException** (const **lang::Exception** &ex) throw ()
Copy Constructor.
- **IOException** (const **IOException** &ex) throw ()
Copy Constructor.
- **IOException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **IOException** (const std::exception *cause) throw ()
Constructor.
- **IOException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **IOException** * **clone** () const
Clones this exception.
- virtual ~**IOException** () throw ()

6.423.1 Constructor & Destructor Documentation

6.423.1.1 decaf::io::IOException::IOException () throw () [inline]

Default Constructor.

6.423.1.2 decaf::io::IOException::IOException (const **lang::Exception** & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.423.1.3 decaf::io::IOException::IOException (const IOException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.423.1.4 decaf::io::IOException::IOException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.423.1.5 decaf::io::IOException::IOException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.423.1.6 decaf::io::IOException::IOException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.423.1.7 `virtual decaf::io::IOException::~~IOException () throw () [inline, virtual]`

6.423.2 Member Function Documentation

6.423.2.1 `virtual IOException* decaf::io::IOException::clone () const [inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an Exception that is a copy of this instance.

Reimplemented from `decaf::lang::Exception` (p. 1834).

Reimplemented in `decaf::internal::net::ssl::openssl::OpenSSLSocketException` (p. 2873), `decaf::io::EOFException` (p. 1827), `decaf::io::InterruptedIOException` (p. 2129), `decaf::io::UnsupportedEncodingException` (p. 3915), `decaf::io::UTFDataFormatException` (p. 3968), `decaf::net::BindException` (p. 838), `decaf::net::ConnectException` (p. 1261), `decaf::net::HttpRetryException` (p. 1988), `decaf::net::MalformedURLException` (p. 2458), `decaf::net::NoRouteToHostException` (p. 2822), `decaf::net::PortUnreachableException` (p. 2975), `decaf::net::ProtocolException` (p. 3139), `decaf::net::SocketException` (p. 3522), `decaf::net::SocketTimeoutException` (p. 3544), `decaf::net::UnknownHostException` (p. 3909), `decaf::net::UnknownServiceException` (p. 3912), and `decaf::util::zip::ZipException` (p. 4066).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/IOException.h`

6.424 activemq::transport::IOTransport Class Reference

Implementation of the **Transport** (p. 3883) interface that performs marshaling of **commands** (p. 87) to IO streams.

#include <src/main/activemq/transport/IOTransport.h> Inheritance diagram for activemq::transport::IOTransport:

Public Member Functions

- **IOTransport** ()
Default Constructor.
- **IOTransport** (const **Pointer**< **wireformat::WireFormat** > &wireFormat)
*Create an instance of this **Transport** (p. 3883) and assign its **WireFormat** instance at creation time.*
- virtual ~**IOTransport** ()
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Not supported by this class - throws an exception.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Not supported by this class - throws an exception.
- virtual void **setWireFormat** (const **Pointer**< **wireformat::WireFormat** > &wireFormat)
*Sets the **WireFormat** instance to use.*
- virtual void **setTransportListener** (**TransportListener** *listener)
*Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual **TransportListener** * **getTransportListener** () const
*Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual void **setInputStream** (decaf::io::DataInputStream *is)
*Sets the input stream for in-coming **commands** (p. 87).*
- virtual void **setOutputStream** (decaf::io::DataOutputStream *os)
*Sets the output stream for out-going **commands** (p. 87).*
- virtual void **start** () throw (decaf::io::IOException)

Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87).

- virtual void **stop** () throw (decaf::io::IOException)

*Stops the **Transport** (p. 3883), terminating any **threads** (p. 96) and stopping all read and write operations.*

- virtual void **close** () throw (decaf::io::IOException)

Stops the polling thread and closes the streams.

- virtual void **run** ()

Runs the polling thread.

- virtual **Transport * narrow** (const std::type_info &typeId)

*Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.*

- virtual bool **isFaultTolerant** () const

*Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.*

- virtual bool **isConnected** () const

*Is the **Transport** (p. 3883) Connected to its Broker.*

- virtual bool **isClosed** () const

*Has the **Transport** (p. 3883) been shutdown and no longer usable.*

- virtual std::string **getRemoteAddress** () const

- virtual void **reconnect** (const decaf::net::URI &uri AMQCPP_UNUSED) throw (decaf::io::IOException)

reconnect to another location

6.424.1 Detailed Description

Implementation of the **Transport** (p. 3883) interface that performs marshaling of **commands** (p. 87) to IO streams. This class does not implement the request method, it only handles oneway messages. A thread polls on the input stream for in-coming **commands** (p. 87). When a command is received, the command listener is notified. The polling thread is not started until the start method is called. The close method will close the associated streams. Close can be called explicitly by the user, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

6.424.2 Constructor & Destructor Documentation

6.424.2.1 activemq::transport::IOTransport::IOTransport ()

Default Constructor.

6.424.2.2 `activemq::transport::IOTransport::IOTransport (const Pointer< wireformat::WireFormat > & wireFormat)`

Create an instance of this **Transport** (p. 3883) and assign its **WireFormat** instance at creation time.

Parameters:

wireFormat Data encoder / decoder to use when reading and writing.

6.424.2.3 `virtual activemq::transport::IOTransport::~~IOTransport ()` [virtual]

6.424.3 Member Function Documentation

6.424.3.1 `virtual void activemq::transport::IOTransport::close () throw (decaf::io::IOException)` [virtual]

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if errors occur.

Implements **decaf::io::Closeable** (p. 1149).

6.424.3.2 `virtual std::string activemq::transport::IOTransport::getRemoteAddress () const` [inline, virtual]

Returns:

the remote address for this connection

Implements **activemq::transport::Transport** (p. 3884).

6.424.3.3 `virtual TransportListener* activemq::transport::IOTransport::getTransportListener () const` [inline, virtual]

Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).

Returns:

The listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3884).

6.424.3.4 `virtual bool activemq::transport::IOTransport::isClosed () const` [inline, virtual]

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

Implements **activemq::transport::Transport** (p. 3885).

6.424.3.5 virtual bool activemq::transport::IOTransport::isConnected () const
[inline, virtual]

Is the **Transport** (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Implements **activemq::transport::Transport** (p. 3885).

6.424.3.6 virtual bool activemq::transport::IOTransport::isFaultTolerant () const
[inline, virtual]

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Implements **activemq::transport::Transport** (p. 3885).

6.424.3.7 virtual Transport* activemq::transport::IOTransport::narrow (const std::type_info & typeId) [inline, virtual]

Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.

Parameters:

typeId - The type_info of the Object we are searching for.

Returns:

the requested Object. or NULL if its not in this chain.

Implements **activemq::transport::Transport** (p. 3885).

6.424.3.8 virtual void activemq::transport::IOTransport::oneway (const Pointer< Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3886).

6.424.3.9 `virtual void activemq::transport::IOTransport::reconnect
(const decaf::net::URI &uri AMQCPP_UNUSED) throw (
decaf::io::IOException) [inline, virtual]`

reconnect to another location

Parameters:

uri

Exceptions:

IOException on failure of if not supported

6.424.3.10 `virtual Pointer<Response> activemq::transport::IOTransport::request
(const Pointer< Command > & command, unsigned
int timeout) throw (decaf::io::IOException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Not supported by this class - throws an exception.

Parameters:

command the command to be sent.

timeout the time to wait for a response.

Returns:

the response to the command sent.

Exceptions:

UnsupportedOperationException.

Implements **activemq::transport::Transport** (p. 3886).

6.424.3.11 `virtual Pointer<Response> activemq::transport::IOTransport::request
(const Pointer< Command > & command)
throw (decaf::io::IOException, de-
caaf::lang::exceptions::UnsupportedOperationException)
[virtual]`

Not supported by this class - throws an exception.

Parameters:

command the command to be sent.

Returns:

the response to the command sent.

Exceptions:

UnsupportedOperationException.

Implements **activemq::transport::Transport** (p. 3887).

6.424.3.12 **virtual void activemq::transport::IOTransport::run ()** [virtual]

Runs the polling thread.

Implements **decaf::lang::Runnable** (p. 3325).

6.424.3.13 **virtual void activemq::transport::IOTransport::setInputStream**
(**decaf::io::DataInputStream * is**) [inline, virtual]

Sets the input stream for in-coming **commands** (p. 87).

Parameters:

is The input stream.

6.424.3.14 **virtual void activemq::transport::IOTransport::setOutputStream**
(**decaf::io::DataOutputStream * os**) [inline, virtual]

Sets the output stream for out-going **commands** (p. 87).

Parameters:

os The output stream.

6.424.3.15 **virtual void activemq::transport::IOTransport::setTransportListener**
(**TransportListener * listener**) [inline, virtual]

Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).

Parameters:

listener the listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3887).

6.424.3.16 **virtual void activemq::transport::IOTransport::setWireFormat** (**const**
Pointer< wireformat::WireFormat > & wireFormat) [inline, virtual]

Sets the WireFormat instance to use.

Parameters:

wireFormat The WireFormat the object used to encode / decode **commands** (p. 87).

Implements **activemq::transport::Transport** (p. 3888).

6.424.3.17 virtual void activemq::transport::IOTransport::start () throw (decaf::io::IOException) [virtual]

Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87). If this object has been closed, throws an exception. Before calling start, the caller must set the IO streams and the reader and writer objects.

Exceptions:

CMSEException if an error occurs or if this **transport** (p. 97) has already been closed.

Implements **activemq::transport::Transport** (p. 3888).

6.424.3.18 virtual void activemq::transport::IOTransport::stop () throw (decaf::io::IOException) [virtual]

Stops the **Transport** (p. 3883), terminating any **threads** (p. 96) and stopping all read and write operations.

Exceptions:

IOException if an error occurs while stopping the **Transport** (p. 3883).

Implements **activemq::transport::Transport** (p. 3888).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/**IOTransport.h**

6.425 decaf::lang::Iterable< E > Class Template Reference

Implementing this interface allows an object to be cast to an **Iterable** (p. 2152) type for generic collections API calls.

#include <src/main/decaf/lang/Iterable.h> Inheritance diagram for decaf::lang::Iterable< E >:

Public Member Functions

- virtual `~Iterable ()`
- virtual `decaf::util::Iterator< E > * iterator ()=0`
- virtual `decaf::util::Iterator< E > * iterator () const =0`

6.425.1 Detailed Description

`template<typename E> class decaf::lang::Iterable< E >`

Implementing this interface allows an object to be cast to an **Iterable** (p. 2152) type for generic collections API calls.

6.425.2 Constructor & Destructor Documentation

6.425.2.1 `template<typename E> virtual decaf::lang::Iterable< E >::~~Iterable ()`
[inline, virtual]

6.425.3 Member Function Documentation

6.425.3.1 `template<typename E> virtual decaf::util::Iterator<E>* decaf::lang::Iterable< E >::iterator () const` [pure virtual]

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3721), `decaf::util::PriorityQueue< E >` (p. 3032), `decaf::util::StlList< E >` (p. 3598), `decaf::util::StlSet< E >` (p. 3627), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), `decaf::util::StlList< cms::Connection * >` (p. 3598), `decaf::util::StlSet< transport::TransportListener * >` (p. 3627), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3627), `decaf::util::StlSet< Resource * >` (p. 3627), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3627).

6.425.3.2 `template<typename E> virtual decaf::util::Iterator<E>*`
`decaf::lang::Iterable< E >::iterator ()` [pure virtual]

Returns:

an iterator over a set of elements of type T.

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3721), `decaf::util::PriorityQueue< E >` (p. 3032), `decaf::util::StlList< E >` (p. 3598), `decaf::util::StlSet< E >` (p. 3628), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), `decaf::util::StlList< cms::Connection * >` (p. 3598), `decaf::util::StlSet< transport::TransportListener * >` (p. 3628), `decaf::util::StlSet< Pointer< Synchronization > >` (p. 3628), `decaf::util::StlSet< Resource * >` (p. 3628), and `decaf::util::StlSet< ActiveMQSession * >` (p. 3628).

Referenced by `decaf::util::AbstractCollection< cms::Connection * >::clear()`, `decaf::util::AbstractCollection< cms::Connection * >::contains()`, `decaf::util::AbstractCollection< cms::Connection * >::copy()`, `decaf::util::AbstractCollection< cms::Connection * >::operator=()`, `decaf::util::AbstractCollection< cms::Connection * >::remove()`, `decaf::util::AbstractSet< ActiveMQSession * >::removeAll()`, `decaf::util::AbstractCollection< cms::Connection * >::removeAll()`, `decaf::util::AbstractCollection< cms::Connection * >::retainAll()`, and `decaf::util::AbstractCollection< cms::Connection * >::toArray()`.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Iterable.h`

6.426 decaf::util::Iterator< T > Class Template Reference

Defines an object that can be used to iterate over the elements of a collection.

#include <src/main/decaf/util/Iterator.h> Inheritance diagram for decaf::util::Iterator< T >:

Public Member Functions

- virtual **~Iterator** ()
- virtual T **next** ()=0 throw (lang::exceptions::NoSuchElementException)
Returns the next element in the iteration.
- virtual bool **hasNext** () const =0
Returns true if the iteration has more elements.
- virtual void **remove** ()=0 throw (lang::exceptions::IllegalStateException, lang::exceptions::UnsupportedOperationException)
Removes from the underlying collection the last element returned by the iterator (optional operation).

6.426.1 Detailed Description

template<typename T> class decaf::util::Iterator< T >

Defines an object that can be used to iterate over the elements of a collection. The iterator provides a way to access and remove elements with well defined semantics.

6.426.2 Constructor & Destructor Documentation

6.426.2.1 template<typename T> virtual decaf::util::Iterator< T >::~~Iterator ()
[inline, virtual]

6.426.3 Member Function Documentation

6.426.3.1 template<typename T> virtual bool decaf::util::Iterator< T >::hasNext () const [pure virtual]

Returns true if the iteration has more elements. Returns false if the next call to next would result in an NoSuchElementException to be thrown.

6.426.3.2 template<typename T> virtual T decaf::util::Iterator< T >::next ()
throw (lang::exceptions::NoSuchElementException) [pure virtual]

Returns the next element in the iteration. Calling this method repeatedly until the **hasNext()** (p. 2154) method returns false will return each element in the underlying collection exactly once.

Returns:

next element in the iteration of elements

Exceptions:

NoSuchElementException - iteration has no more elements.

6.426.3.3 `template<typename T> virtual void decaf::util::Iterator< T
>::remove () throw (lang::exceptions::IllegalStateException,
lang::exceptions::UnsupportedOperationException) [pure virtual]`

Removes from the underlying collection the last element returned by the iterator (optional operation). This method can be called only once per call to next. The behavior of an iterator is unspecified if the underlying collection is modified while the iteration is in progress in any way other than by calling this method.

Exceptions:

UnsupportedOperationException - if the remove operation is not supported by this **Iterator** (p. 2154).

IllegalStateException - if the next method has not yet been called, or the remove method has already been called after the last call to the next method.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Iterator.h`

6.427 activemq::commands::JournalQueueAck Class Reference

#include <src/main/activemq/commands/JournalQueueAck.h> Inheritance diagram for activemq::commands::JournalQueueAck:

Public Member Functions

- **JournalQueueAck** ()
- virtual **~JournalQueueAck** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **JournalQueueAck * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual const **Pointer**< **MessageAck** > & **getMessageAck** () const
- virtual **Pointer**< **MessageAck** > & **getMessageAck** ()
- virtual void **setMessageAck** (const **Pointer**< **MessageAck** > &messageAck)

Static Public Attributes

- static const unsigned char **ID_JOURNALQUEUEACK** = 52

Protected Attributes

- **Pointer**< **ActiveMQDestination** > **destination**
- **Pointer**< **MessageAck** > **messageAck**

6.427.1 Constructor & Destructor Documentation

6.427.1.1 `activemq::commands::JournalQueueAck::JournalQueueAck ()`

6.427.1.2 `virtual activemq::commands::JournalQueueAck::~~JournalQueueAck ()`
[virtual]

6.427.2 Member Function Documentation

6.427.2.1 `virtual JournalQueueAck* activemq::commands::JournalQueueAck::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.427.2.2 `virtual void activemq::commands::JournalQueueAck::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.427.2.3 `virtual bool activemq::commands::JournalQueueAck::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

6.427.2.4 `virtual unsigned char activemq::commands::JournalQueueAck::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.427.2.5 `virtual Pointer<ActiveMQDestination>& activemq::commands::JournalQueueAck::getDestination ()`
[virtual]
- 6.427.2.6 `virtual const Pointer<ActiveMQDestination>& activemq::commands::JournalQueueAck::getDestination () const`
[virtual]
- 6.427.2.7 `virtual Pointer<MessageAck>& activemq::commands::JournalQueueAck::getMessageAck ()`
[virtual]
- 6.427.2.8 `virtual const Pointer<MessageAck>& activemq::commands::JournalQueueAck::getMessageAck () const` [virtual]
- 6.427.2.9 `virtual void activemq::commands::JournalQueueAck::setDestination (const Pointer< ActiveMQDestination > & destination)` [virtual]
- 6.427.2.10 `virtual void activemq::commands::JournalQueueAck::setMessageAck (const Pointer< MessageAck > & messageAck)` [virtual]
- 6.427.2.11 `virtual std::string activemq::commands::JournalQueueAck::toString () const` [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataStructure` (p.833).

6.427.3 Field Documentation

- 6.427.3.1 `Pointer<ActiveMQDestination> activemq::commands::JournalQueueAck::destination`
[protected]
- 6.427.3.2 `const unsigned char activemq::commands::JournalQueueAck::ID _ - JOURNALQUEUEACK = 52` [static]
- 6.427.3.3 `Pointer<MessageAck> activemq::commands::JournalQueueAck::messageAck`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/JournalQueueAck.h`

6.428 activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2159).

#include <src/main/activemq/wireformat/openwire/marshal/v6/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.428.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2159).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.428.2 Constructor & Destructor Documentation

6.428.2.1 `activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.428.2.2 `virtual activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.428.3 Member Function Documentation

6.428.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.428.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.428.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.428.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.428.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.428.3.6 virtual void activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.428.3.7 virtual void activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**JournalQueueAckMarshaller.h**

6.429 activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2163).

#include <src/main/activemq/wireformat/openwire/marshal/v2/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.429.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2163).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.429.2 Constructor & Destructor Documentation

6.429.2.1 `activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.429.2.2 `virtual activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.429.3 Member Function Documentation

6.429.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.429.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.429.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.429.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.429.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.429.3.6 virtual void activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.429.3.7 virtual void activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/JournalQueueAckMarshaller.h

6.430 activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2167).

#include <src/main/activemq/wireformat/openwire/marshal/v5/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.430.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2167).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.430.2 Constructor & Destructor Documentation

6.430.2.1 `activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.430.2.2 `virtual activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.430.3 Member Function Documentation

6.430.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.430.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.430.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.430.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.430.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.430.3.6 virtual void activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.430.3.7 virtual void activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/JournalQueueAckMarshaller.h

6.431 activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2171).

#include <src/main/activemq/wireformat/openwire/marshal/v3/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.431.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2171).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.431.2 Constructor & Destructor Documentation

6.431.2.1 `activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.431.2.2 `virtual activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.431.3 Member Function Documentation

6.431.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.431.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.431.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.431.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.431.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.431.3.6 virtual void activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.431.3.7 virtual void activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/JournalQueueAckMarshaller.h

6.432 activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2175).

#include <src/main/activemq/wireformat/openwire/marshal/v4/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.432.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2175).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.432.2 Constructor & Destructor Documentation

6.432.2.1 `activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.432.2.2 `virtual activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.432.3 Member Function Documentation

6.432.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.432.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.432.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.432.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.432.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.432.3.6 virtual void activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.432.3.7 virtual void activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**JournalQueueAckMarshaller.h**

6.433 activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2179).

#include <src/main/activemq/wireformat/openwire/marshal/v1/JournalQueueAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller:

Public Member Functions

- **JournalQueueAckMarshaller** ()
- virtual **~JournalQueueAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.433.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2179).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.433.2 Constructor & Destructor Documentation

6.433.2.1 `activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::JournalQueueAckMarshaller()` [inline]

6.433.2.2 `virtual activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::~~JournalQueueAckMarshaller()` [inline, virtual]

6.433.3 Member Function Documentation

6.433.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.433.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.433.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.433.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.433.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.433.3.6 virtual void activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.433.3.7 virtual void activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**JournalQueueAckMarshaller.h**

6.434 activemq::commands::JournalTopicAck Class Reference

#include <src/main/activemq/commands/JournalTopicAck.h> Inheritance diagram for activemq::commands::JournalTopicAck:

Public Member Functions

- **JournalTopicAck** ()
- virtual **~JournalTopicAck** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **JournalTopicAck * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src) const
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual const **Pointer**< **MessageId** > & **getMessageId** () const
- virtual **Pointer**< **MessageId** > & **getMessageId** ()
- virtual void **setMessageId** (const **Pointer**< **MessageId** > &messageId)
- virtual long long **getMessageSequenceId** () const
- virtual void **setMessageSequenceId** (long long messageSequenceId)
- virtual const std::string & **getSubscriptionName** () const
- virtual std::string & **getSubscriptionName** ()
- virtual void **setSubscriptionName** (const std::string &subscriptionName)
- virtual const std::string & **getClientId** () const
- virtual std::string & **getClientId** ()
- virtual void **setClientId** (const std::string &clientId)
- virtual const **Pointer**< **TransactionId** > & **getTransactionId** () const
- virtual **Pointer**< **TransactionId** > & **getTransactionId** ()
- virtual void **setTransactionId** (const **Pointer**< **TransactionId** > &transactionId)

Static Public Attributes

- static const unsigned char **ID_JOURNALTOPICACK** = 50

Protected Attributes

- **Pointer**< **ActiveMQDestination** > **destination**
- **Pointer**< **MessageId** > **messageId**
- long long **messageSequenceId**
- std::string **subscriptionName**
- std::string **clientId**
- **Pointer**< **TransactionId** > **transactionId**

6.434.1 Constructor & Destructor Documentation

6.434.1.1 **activemq::commands::JournalTopicAck::JournalTopicAck ()**

6.434.1.2 **virtual activemq::commands::JournalTopicAck::~~JournalTopicAck ()**
[virtual]

6.434.2 Member Function Documentation

6.434.2.1 **virtual JournalTopicAck* activemq::commands::JournalTopicAck::cloneDataStructure () const** [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.434.2.2 **virtual void activemq::commands::JournalTopicAck::copyDataStructure (const DataStructure * src) [virtual]**

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.434.2.3 **virtual bool activemq::commands::JournalTopicAck::equals (const DataStructure * value) const** [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.434.2.4 `virtual std::string& activemq::commands::JournalTopicAck::getClientId () [virtual]`

6.434.2.5 `virtual const std::string& activemq::commands::JournalTopicAck::getClientId () const [virtual]`

6.434.2.6 `virtual unsigned char activemq::commands::JournalTopicAck::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSetructure** (p. 1660) type copy.

Implements **activemq::commands::DataSetructure** (p. 1662).

-
- 6.434.2.7 `virtual Pointer<ActiveMQDestination>& activemq::commands::JournalTopicAck::getDestination ()`
[virtual]
 - 6.434.2.8 `virtual const Pointer<ActiveMQDestination>& activemq::commands::JournalTopicAck::getDestination () const`
[virtual]
 - 6.434.2.9 `virtual Pointer<MessageId>& activemq::commands::JournalTopicAck::getMessageId ()`
[virtual]
 - 6.434.2.10 `virtual const Pointer<MessageId>& activemq::commands::JournalTopicAck::getMessageId () const` [virtual]
 - 6.434.2.11 `virtual long long activemq::commands::JournalTopicAck::getMessageSequenceId () const`
[virtual]
 - 6.434.2.12 `virtual std::string& activemq::commands::JournalTopicAck::getSubscriptionName ()`
[virtual]
 - 6.434.2.13 `virtual const std::string& activemq::commands::JournalTopicAck::getSubscriptionName () const`
[virtual]
 - 6.434.2.14 `virtual Pointer<TransactionId>& activemq::commands::JournalTopicAck::getTransactionId ()`
[virtual]
 - 6.434.2.15 `virtual const Pointer<TransactionId>& activemq::commands::JournalTopicAck::getTransactionId () const`
[virtual]
 - 6.434.2.16 `virtual void activemq::commands::JournalTopicAck::setClientId (const std::string & clientId)` [virtual]
 - 6.434.2.17 `virtual void activemq::commands::JournalTopicAck::setDestination (const Pointer< ActiveMQDestination > & destination)` [virtual]
 - 6.434.2.18 `virtual void activemq::commands::JournalTopicAck::setMessageId (const Pointer< MessageId > & messageId)` [virtual]
 - 6.434.2.19 `virtual void activemq::commands::JournalTopicAck::setMessageSequenceId (long long messageSequenceId)` [virtual]
 - 6.434.2.20 `virtual void activemq::commands::JournalTopicAck::setSubscriptionName (const std::string & subscriptionName)` [virtual]
 - 6.434.2.21 `virtual void activemq::commands::JournalTopicAck::setTransactionId (const Pointer< TransactionId > & transactionId)` [virtual]
 - 6.434.2.22 `virtual std::string activemq::commands::JournalTopicAck::toString () const` [virtual]
-

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataStructure` (p. 833).

6.434.3 Field Documentation

- 6.434.3.1** `std::string activemq::commands::JournalTopicAck::clientId` [protected]
- 6.434.3.2** `Pointer<ActiveMQDestination> activemq::commands::JournalTopicAck::destination` [protected]
- 6.434.3.3** `const unsigned char activemq::commands::JournalTopicAck::ID_ - JOURNALTOPICACK = 50` [static]
- 6.434.3.4** `Pointer<MessageId> activemq::commands::JournalTopicAck::messageId` [protected]
- 6.434.3.5** `long long activemq::commands::JournalTopicAck::messageSequenceId` [protected]
- 6.434.3.6** `std::string activemq::commands::JournalTopicAck::subscriptionName` [protected]
- 6.434.3.7** `Pointer<TransactionId> activemq::commands::JournalTopicAck::transactionId` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/JournalTopicAck.h`

6.435 activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2188).

#include <src/main/activemq/wireformat/openwire/marshal/v5/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.435.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2188).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.435.2 Constructor & Destructor Documentation

6.435.2.1 `activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::JournalTopicAckMarshaller()` [inline]

6.435.2.2 `virtual activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller()` [inline, virtual]

6.435.3 Member Function Documentation

6.435.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.435.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.435.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.435.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.435.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.435.3.6 virtual void activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.435.3.7 virtual void activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**JournalTopicAckMarshaller.h**

6.436 activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2192).

#include <src/main/activemq/wireformat/openwire/marshal/v2/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.436.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2192).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.436.2 Constructor & Destructor Documentation

6.436.2.1 `activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::JournalTopicAckMarshaller()` [inline]

6.436.2.2 `virtual activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller()` [inline, virtual]

6.436.3 Member Function Documentation

6.436.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.436.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.436.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.436.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.436.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.436.3.6 virtual void activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.436.3.7 virtual void activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**JournalTopicAckMarshaller.h**

6.437 activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2196).

#include <src/main/activemq/wireformat/openwire/marshal/v3/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.437.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2196).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.437.2 Constructor & Destructor Documentation

6.437.2.1 `activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::JournalTopicAckMarshaller()` [inline]

6.437.2.2 `virtual activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller()` [inline, virtual]

6.437.3 Member Function Documentation

6.437.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.437.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.437.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.437.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.437.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.437.3.6 virtual void activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

6.437.3.7 virtual void activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**JournalTopicAckMarshaller.h**

6.438 activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2200).

#include <src/main/activemq/wireformat/openwire/marshal/v6/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.438.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2200).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.438.2 Constructor & Destructor Documentation

6.438.2.1 `activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::JournalTopicAckMarshaller()` `[inline]`

6.438.2.2 `virtual activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller()` `[inline, virtual]`

6.438.3 Member Function Documentation

6.438.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.438.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.438.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.438.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.438.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.438.3.6 virtual void activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.438.3.7 virtual void activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**JournalTopicAckMarshaller.h**

6.439 activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2204).

#include <src/main/activemq/wireformat/openwire/marshal/v4/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.439.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2204).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.439.2 Constructor & Destructor Documentation

6.439.2.1 `activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::JournalTopicAckMarshaller()` [inline]

6.439.2.2 `virtual activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller()` [inline, virtual]

6.439.3 Member Function Documentation

6.439.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.439.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.439.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.439.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.439.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.439.3.6 virtual void activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.439.3.7 virtual void activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**JournalTopicAckMarshaller.h**

6.440 activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2208).

#include <src/main/activemq/wireformat/openwire/marshal/v1/JournalTopicAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller:

Public Member Functions

- **JournalTopicAckMarshaller** ()
- virtual **~JournalTopicAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.440.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2208).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.440.2 Constructor & Destructor Documentation

6.440.2.1 **activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::JournalTopicAckMarshaller**
() [inline]

6.440.2.2 **virtual**
activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::~~JournalTopicAckMarshaller
() [inline, virtual]

6.440.3 Member Function Documentation

6.440.3.1 **virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::createObject**
() const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1611).

6.440.3.2 **virtual unsigned char activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::getDataStructureType**
() const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1617).

6.440.3.3 **virtual void activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::looseMarshal**
(**OpenWireFormat * wireFormat**, **commands::DataStructure * dataStructure**, **decaf::io::DataOutputStream * dataOut**) throw (**decaf::io::IOException**) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.440.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.440.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.440.3.6 virtual void activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.440.3.7 virtual void activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**JournalTopicAckMarshaller.h**

6.441 activemq::commands::JournalTrace Class Reference

#include <src/main/activemq/commands/JournalTrace.h> Inheritance diagram for activemq::commands::JournalTrace:

Public Member Functions

- **JournalTrace** ()
- virtual **~JournalTrace** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **JournalTrace * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getMessage** () const
- virtual std::string & **getMessage** ()
- virtual void **setMessage** (const std::string &message)

Static Public Attributes

- static const unsigned char **ID_JOURNALTRACE** = 53

Protected Attributes

- std::string **message**

6.441.1 Constructor & Destructor Documentation

6.441.1.1 `activemq::commands::JournalTrace::JournalTrace ()`

6.441.1.2 `virtual activemq::commands::JournalTrace::~~JournalTrace ()` [virtual]

6.441.2 Member Function Documentation

6.441.2.1 `virtual JournalTrace* activemq::commands::JournalTrace::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.441.2.2 `virtual void activemq::commands::JournalTrace::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.441.2.3 `virtual bool activemq::commands::JournalTrace::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

6.441.2.4 `virtual unsigned char activemq::commands::JournalTrace::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.441.2.5 `virtual std::string& activemq::commands::JournalTrace::getMessage ()`
[virtual]
- 6.441.2.6 `virtual const std::string& activemq::commands::JournalTrace::getMessage`
`() const` [virtual]
- 6.441.2.7 `virtual void activemq::commands::JournalTrace::setMessage (const`
`std::string & message)` [virtual]
- 6.441.2.8 `virtual std::string activemq::commands::JournalTrace::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataStructure` (p.833).

6.441.3 Field Documentation

- 6.441.3.1 `const unsigned char activemq::commands::JournalTrace::ID_ -`
`JOURNALTRACE = 53` [static]
- 6.441.3.2 `std::string activemq::commands::JournalTrace::message` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/JournalTrace.h`

6.442 activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2215).

#include <src/main/activemq/wireformat/openwire/marshal/v2/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.442.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2215).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.442.2 Constructor & Destructor Documentation

6.442.2.1 `activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.442.2.2 `virtual activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.442.3 Member Function Documentation

6.442.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.442.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.442.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.442.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.442.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.442.3.6 virtual void activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.442.3.7 virtual void activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**JournalTraceMarshaller.h**

6.443 activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2219).

#include <src/main/activemq/wireformat/openwire/marshal/v3/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.443.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2219).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.443.2 Constructor & Destructor Documentation

6.443.2.1 `activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.443.2.2 `virtual activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.443.3 Member Function Documentation

6.443.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.443.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.443.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.443.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.443.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.443.3.6 virtual void activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.443.3.7 virtual void activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**JournalTraceMarshaller.h**

6.444 activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2223).

#include <src/main/activemq/wireformat/openwire/marshal/v6/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.444.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2223).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.444.2 Constructor & Destructor Documentation

6.444.2.1 `activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.444.2.2 `virtual activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.444.3 Member Function Documentation

6.444.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.444.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.444.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.444.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.444.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.444.3.6 virtual void activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.444.3.7 virtual void activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**JournalTraceMarshaller.h**

6.445 activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2227).

#include <src/main/activemq/wireformat/openwire/marshal/v4/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.445.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2227).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.445.2 Constructor & Destructor Documentation

6.445.2.1 `activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.445.2.2 `virtual activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.445.3 Member Function Documentation

6.445.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.445.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.445.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.445.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.445.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.445.3.6 virtual void activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.445.3.7 virtual void activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**JournalTraceMarshaller.h**

6.446 activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2231).

#include <src/main/activemq/wireformat/openwire/marshal/v1/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.446.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2231).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.446.2 Constructor & Destructor Documentation

6.446.2.1 `activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.446.2.2 `virtual activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.446.3 Member Function Documentation

6.446.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.446.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.446.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.446.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.446.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.446.3.6 virtual void activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.446.3.7 virtual void activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**JournalTraceMarshaller.h**

6.447 activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2235).

#include <src/main/activemq/wireformat/openwire/marshal/v5/JournalTraceMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller:

Public Member Functions

- **JournalTraceMarshaller** ()
- virtual **~JournalTraceMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.447.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **JournalTraceMarshaller** (p.2235).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.447.2 Constructor & Destructor Documentation

6.447.2.1 `activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::JournalTraceMarshaller()` [inline]

6.447.2.2 `virtual activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::~~JournalTraceMarshaller()` [inline, virtual]

6.447.3 Member Function Documentation

6.447.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.447.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.447.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.447.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.447.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.447.3.6 virtual void activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.447.3.7 virtual void activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**JournalTraceMarshaller.h**

6.448 activemq::commands::JournalTransaction Class Reference

#include <src/main/activemq/commands/JournalTransaction.h> Inheritance diagram for activemq::commands::JournalTransaction:

Public Member Functions

- **JournalTransaction** ()
- virtual **~JournalTransaction** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **JournalTransaction * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **TransactionId** > & **getTransactionId** () const
- virtual **Pointer**< **TransactionId** > & **getTransactionId** ()
- virtual void **setTransactionId** (const **Pointer**< **TransactionId** > &transactionId)
- virtual unsigned char **getType** () const
- virtual void **setType** (unsigned char type)
- virtual bool **getWasPrepared** () const
- virtual void **setWasPrepared** (bool wasPrepared)

Static Public Attributes

- static const unsigned char **ID_JOURNALTRANSACTION** = 54

Protected Attributes

- **Pointer**< **TransactionId** > **transactionId**
- unsigned char **type**
- bool **wasPrepared**

6.448.1 Constructor & Destructor Documentation

6.448.1.1 `activemq::commands::JournalTransaction::JournalTransaction ()`

6.448.1.2 `virtual activemq::commands::JournalTransaction::~~JournalTransaction ()`
[virtual]

6.448.2 Member Function Documentation

6.448.2.1 `virtual JournalTransaction* activemq::commands::JournalTransaction::cloneDataStructure () const`
[virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.448.2.2 `virtual void activemq::commands::JournalTransaction::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.448.2.3 `virtual bool activemq::commands::JournalTransaction::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

6.448.2.4 `virtual unsigned char activemq::commands::JournalTransaction::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.448.2.5 virtual Pointer<TransactionId>& activemq::commands::JournalTransaction::getTransactionId () [virtual]
- 6.448.2.6 virtual const Pointer<TransactionId>& activemq::commands::JournalTransaction::getTransactionId () const [virtual]
- 6.448.2.7 virtual unsigned char activemq::commands::JournalTransaction::getType () const [virtual]
- 6.448.2.8 virtual bool activemq::commands::JournalTransaction::getWasPrepared () const [virtual]
- 6.448.2.9 virtual void activemq::commands::JournalTransaction::setTransactionId (const Pointer< TransactionId > & *transactionId*) [virtual]
- 6.448.2.10 virtual void activemq::commands::JournalTransaction::setType (unsigned char *type*) [virtual]
- 6.448.2.11 virtual void activemq::commands::JournalTransaction::setWasPrepared (bool *wasPrepared*) [virtual]
- 6.448.2.12 virtual std::string activemq::commands::JournalTransaction::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p.833).

6.448.3 Field Documentation

- 6.448.3.1 const unsigned char activemq::commands::JournalTransaction::ID_ - JOURNALTRANSACTION = 54 [static]
- 6.448.3.2 Pointer<TransactionId> activemq::commands::JournalTransaction::transactionId [protected]
- 6.448.3.3 unsigned char activemq::commands::JournalTransaction::type [protected]
- 6.448.3.4 bool activemq::commands::JournalTransaction::wasPrepared [protected]

The documentation for this class was generated from the following file:

- src/main/activemq/commands/**JournalTransaction.h**

6.449 activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2242).

#include <src/main/activemq/wireformat/openwire/marshal/v6/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.449.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2242).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.449.2 Constructor & Destructor Documentation

6.449.2.1 `activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::JournalTrans
() [inline]`

6.449.2.2 `virtual
activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::~~JournalTra
() [inline, virtual]`

6.449.3 Member Function Documentation

6.449.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.449.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.449.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.449.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.449.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.449.3.6 virtual void activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.449.3.7 virtual void activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**JournalTransactionMarshaller.h**

6.450 activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2246).

#include <src/main/activemq/wireformat/openwire/marshal/v2/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.450.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2246).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.450.2 Constructor & Destructor Documentation

6.450.2.1 `activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::JournalTrans
() [inline]`

6.450.2.2 `virtual
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::~~JournalTra
() [inline, virtual]`

6.450.3 Member Function Documentation

6.450.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.450.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.450.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.450.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.450.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::tightMarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.450.3.6 virtual void activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.450.3.7 virtual void activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**JournalTransactionMarshaller.h**

6.451 activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2250).

#include <src/main/activemq/wireformat/openwire/marshal/v3/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.451.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2250).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.451.2 Constructor & Destructor Documentation

6.451.2.1 `activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::JournalTrans
() [inline]`

6.451.2.2 `virtual
activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::~~JournalTra
() [inline, virtual]`

6.451.3 Member Function Documentation

6.451.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.451.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.451.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.451.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.451.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::tightMarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.451.3.6 virtual void activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.451.3.7 virtual void activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**JournalTransactionMarshaller.h**

6.452 activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2254).

#include <src/main/activemq/wireformat/openwire/marshal/v5/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.452.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2254).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.452.2 Constructor & Destructor Documentation

6.452.2.1 `activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::JournalTrans
() [inline]`

6.452.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::~~JournalTra
() [inline, virtual]`

6.452.3 Member Function Documentation

6.452.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.452.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.452.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.452.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.452.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.452.3.6 virtual void activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.452.3.7 virtual void activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**JournalTransactionMarshaller.h**

6.453 activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2258).

#include <src/main/activemq/wireformat/openwire/marshal/v4/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.453.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2258).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.453.2 Constructor & Destructor Documentation

6.453.2.1 `activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::JournalTrans
() [inline]`

6.453.2.2 `virtual
activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::~~JournalTra
() [inline, virtual]`

6.453.3 Member Function Documentation

6.453.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.453.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::getDataStructu
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.453.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.453.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.453.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.453.3.6 virtual void activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.453.3.7 virtual void activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**JournalTransactionMarshaller.h**

6.454 activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2262).

#include <src/main/activemq/wireformat/openwire/marshal/v1/JournalTransactionMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller:

Public Member Functions

- **JournalTransactionMarshaller** ()
- virtual **~JournalTransactionMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.454.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2262).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.454.2 Constructor & Destructor Documentation

6.454.2.1 `activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::JournalTrans
 () [inline]`

6.454.2.2 `virtual
 activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::~~JournalTra
 () [inline, virtual]`

6.454.3 Member Function Documentation

6.454.3.1 `virtual commands::DataStructure* ac-
 tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::createObject
 () const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.454.3.2 `virtual unsigned char ac-
 tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::getDataStructu
 () const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.454.3.3 `virtual void ac-
 tivemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::looseMarshal
 (OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
 decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.454.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.454.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.454.3.6 virtual void activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.454.3.7 virtual void activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**JournalTransactionMarshaller.h**

6.455 activemq::commands::KeepAliveInfo Class Reference

#include <src/main/activemq/commands/KeepAliveInfo.h> Inheritance diagram for activemq::commands::KeepAliveInfo:

Public Member Functions

- **KeepAliveInfo** ()
- virtual **~KeepAliveInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **KeepAliveInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual bool **isKeepAliveInfo** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_KEEPAALIVEINFO** = 10

6.455.1 Constructor & Destructor Documentation

6.455.1.1 `activemq::commands::KeepAliveInfo::KeepAliveInfo ()`

6.455.1.2 `virtual activemq::commands::KeepAliveInfo::~~KeepAliveInfo ()`
[virtual]

6.455.2 Member Function Documentation

6.455.2.1 `virtual KeepAliveInfo* activemq::commands::KeepAliveInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.455.2.2 `virtual void activemq::commands::KeepAliveInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.455.2.3 `virtual bool activemq::commands::KeepAliveInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.455.2.4 `virtual unsigned char activemq::commands::KeepAliveInfo::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.455.2.5 `virtual bool activemq::commands::KeepAliveInfo::isKeepAliveInfo () const [inline, virtual]`

Returns:

an answer of true to the **isKeepAliveInfo()** (p. 2268) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 761).

6.455.2.6 `virtual std::string activemq::commands::KeepAliveInfo::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.455.2.7 `virtual Pointer<Command> activemq::commands::KeepAliveInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.455.3 Field Documentation

6.455.3.1 `const unsigned char activemq::commands::KeepAliveInfo::ID_ - KEEPALIVEINFO = 10 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/KeepAliveInfo.h`

6.456 activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2269).

#include <src/main/activemq/wireformat/openwire/marshal/v6/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.456.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2269).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.456.2 Constructor & Destructor Documentation

6.456.2.1 `activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.456.2.2 `virtual
activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.456.3 Member Function Documentation

6.456.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.456.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.456.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.456.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.456.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.456.3.6 virtual void activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.456.3.7 virtual void activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/KeepAliveInfoMarshaller.h

6.457 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2273).

#include <src/main/activemq/wireformat/openwire/marshal/v2/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.457.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2273).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.457.2 Constructor & Destructor Documentation

6.457.2.1 `activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.457.2.2 `virtual
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.457.3 Member Function Documentation

6.457.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.457.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.457.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.457.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.457.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.457.3.6 virtual void activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.457.3.7 virtual void activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/KeepAliveInfoMarshaller.h

6.458 activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2277).

#include <src/main/activemq/wireformat/openwire/marshal/v3/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.458.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2277).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.458.2 Constructor & Destructor Documentation

6.458.2.1 `activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.458.2.2 `virtual
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.458.3 Member Function Documentation

6.458.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.458.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.458.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.458.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.458.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.458.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.458.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/KeepAliveInfoMarshaller.h`

6.459 activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2281).

#include <src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.459.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2281).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.459.2 Constructor & Destructor Documentation

6.459.2.1 `activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.459.2.2 `virtual
activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.459.3 Member Function Documentation

6.459.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.459.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.459.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.459.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.459.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.459.3.6 virtual void activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.459.3.7 virtual void activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h

6.460 activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2285).

#include <src/main/activemq/wireformat/openwire/marshal/v5/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.460.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2285).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.460.2 Constructor & Destructor Documentation

6.460.2.1 `activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.460.2.2 `virtual
activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.460.3 Member Function Documentation

6.460.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.460.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.460.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.460.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.460.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.460.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.460.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/KeepAliveInfoMarshaller.h`

6.461 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2289).

#include <src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller:

Public Member Functions

- **KeepAliveInfoMarshaller** ()
- virtual **~KeepAliveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.461.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p.2289).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.461.2 Constructor & Destructor Documentation

6.461.2.1 `activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::KeepAliveInfoMar
() [inline]`

6.461.2.2 `virtual
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::~~KeepAliveInfoM
() [inline, virtual]`

6.461.3 Member Function Documentation

6.461.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.461.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::getDataStructureTy
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.461.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.461.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.461.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.461.3.6 virtual void activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.461.3.7 virtual void activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h

6.462 decaf::security::Key Class Reference

The **Key** (p. 2293) interface is the top-level interface for all keys.

#include <src/main/decaf/security/Key.h> Inheritance diagram for decaf::security::Key:

Public Member Functions

- virtual **~Key** ()
- virtual std::string **getAlgorithm** () const =0
Returns the standard algorithm name for this key.
- virtual void **getEncoded** (std::vector< unsigned char > &output) const =0
Provides the key in its primary encoding format, or nothing if this key does not support encoding.
- virtual std::string **getFormat** () const =0
Returns the name of the primary encoding format of this key, or an empty string if this key does not support encoding.

6.462.1 Detailed Description

The **Key** (p. 2293) interface is the top-level interface for all keys. It defines the functionality shared by all key objects. All keys have three characteristics:

An Algorithm

This is the key algorithm for that key. The key algorithm is usually an encryption or asymmetric operation algorithm (such as DSA or RSA), which will work with those algorithms and with related algorithms (such as MD5 with RSA, SHA-1 with RSA, Raw DSA, etc.) The name of the algorithm of a key is obtained using the getAlgorithm method.

An Encoded Form

This is an external encoded form for the key used when a standard representation of the key is needed outside the application, as when transmitting the key to some other party. The key is encoded according to a standard format (such as X.509 SubjectPublicKeyInfo or PKCS#8), and is returned using the getEncoded method. Note: The syntax of the ASN.1 type SubjectPublicKeyInfo is defined as follows:

```
SubjectPublicKeyInfo ::= SEQUENCE {
algorithm AlgorithmIdentifier,
subjectPublicKey BIT STRING }
AlgorithmIdentifier ::= SEQUENCE {
algorithm OBJECT IDENTIFIER,
parameters ANY DEFINED BY algorithm OPTIONAL }
```

For more information, see RFC 2459: Internet X.509 Public **Key** (p. 2293) Infrastructure Certificate and CRL Profile.

A Format

This is the name of the format of the encoded key. It is returned by the `getFormat` method.

6.462.2 Constructor & Destructor Documentation

6.462.2.1 `virtual decaf::security::Key::~~Key () [inline, virtual]`

6.462.3 Member Function Documentation

6.462.3.1 `virtual std::string decaf::security::Key::getAlgorithm () const [pure virtual]`

Returns the standard algorithm name for this key. For example, "DSA" would indicate that this key is a DSA key.

Returns:

the name of the algorithm associated with this key.

6.462.3.2 `virtual void decaf::security::Key::getEncoded (std::vector< unsigned char > & output) const [pure virtual]`

Provides the key in its primary encoding format, or nothing if this key does not support encoding.

Parameters:

output Receives the encoded key, or nothing if the key does not support encoding.

6.462.3.3 `virtual std::string decaf::security::Key::getFormat () const [pure virtual]`

Returns the name of the primary encoding format of this key, or an empty string if this key does not support encoding. The primary encoding format is named in terms of the appropriate ASN.1 data format, if an ASN.1 specification for this key exists. For example, the name of the ASN.1 data format for public keys is `SubjectPublicKeyInfo`, as defined by the X.509 standard; in this case, the returned format is "X.509". Similarly, the name of the ASN.1 data format for private keys is `PrivateKeyInfo`, as defined by the PKCS #8 standard; in this case, the returned format is "PKCS#8".

Returns:

the primary encoding format of the key.

The documentation for this class was generated from the following file:

- `src/main/decaf/security/Key.h`

6.463 decaf::security::KeyException Class Reference

#include <src/main/decaf/security/KeyException.h> Inheritance diagram for decaf::security::KeyException:

Public Member Functions

- **KeyException** () throw ()
Default Constructor.
- **KeyException** (const decaf::lang::Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **KeyException** (const **KeyException** &ex) throw ()
Copy Constructor.
- **KeyException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **KeyException** (const std::exception *cause) throw ()
Constructor.
- **KeyException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **KeyException** * clone () const
Clones this exception.
- virtual ~**KeyException** () throw ()

6.463.1 Constructor & Destructor Documentation

6.463.1.1 decaf::security::KeyException::KeyException () throw () [inline]

Default Constructor.

6.463.1.2 decaf::security::KeyException::KeyException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.463.1.3 decaf::security::KeyException::KeyException (const KeyException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.463.1.4 decaf::security::KeyException::KeyException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.463.1.5 decaf::security::KeyException::KeyException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.463.1.6 decaf::security::KeyException::KeyException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.463.1.7 `virtual decaf::security::KeyException::~~KeyException () throw ()`
[inline, virtual]

6.463.2 Member Function Documentation

6.463.2.1 `virtual KeyException* decaf::security::KeyException::clone () const`
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from `decaf::security::GeneralSecurityException` (p. 1973).

Reimplemented in `decaf::security::InvalidKeyException` (p. 2134), and `decaf::security::KeyManagementException` (p. 2300).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/KeyException.h`

6.464 decaf::security::KeyManagementException Class Reference

#include <src/main/decaf/security/KeyManagementException.h> Inheritance diagram for decaf::security::KeyManagementException:

Public Member Functions

- **KeyManagementException** () throw ()
Default Constructor.
- **KeyManagementException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **KeyManagementException** (const **KeyManagementException** &ex) throw ()
Copy Constructor.
- **KeyManagementException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **KeyManagementException** (const std::exception *cause) throw ()
Constructor.
- **KeyManagementException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **KeyManagementException** * clone () const
Clones this exception.
- virtual ~**KeyManagementException** () throw ()

6.464.1 Constructor & Destructor Documentation

6.464.1.1 decaf::security::KeyManagementException::KeyManagementException () throw () [inline]

Default Constructor.

6.464.1.2 decaf::security::KeyManagementException::KeyManagementException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.464.1.3 decaf::security::KeyManagementException::KeyManagementException (const KeyManagementException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.464.1.4 decaf::security::KeyManagementException::KeyManagementException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.464.1.5 decaf::security::KeyManagementException::KeyManagementException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.464.1.6 decaf::security::KeyManagementException::KeyManagementException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.464.1.7 **virtual**
 decaf::security::KeyManagementException::~~KeyManagementException
 () throw () [inline, virtual]

6.464.2 Member Function Documentation

6.464.2.1 **virtual KeyManagementException* de-**
 caf::security::KeyManagementException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

 A deep copy of this exception.

Reimplemented from **decaf::security::KeyException** (p. 2297).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/KeyManagementException.h`

6.465 activemq::commands::LastPartialCommand Class Reference

#include <src/main/activemq/commands/LastPartialCommand.h> Inheritance diagram for activemq::commands::LastPartialCommand:

Public Member Functions

- **LastPartialCommand** ()
- virtual **~LastPartialCommand** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **LastPartialCommand * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*

Static Public Attributes

- static const unsigned char **ID_LASTPARTIALCOMMAND** = 61

6.465.1 Constructor & Destructor Documentation

6.465.1.1 **activemq::commands::LastPartialCommand::LastPartialCommand** ()

6.465.1.2 **virtual**
activemq::commands::LastPartialCommand::~~LastPartialCommand ()
[virtual]

6.465.2 Member Function Documentation

6.465.2.1 **virtual LastPartialCommand*** **activemq::commands::LastPartialCommand::cloneDataStructure** () const
[virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::PartialCommand` (p. 2919).

6.465.2.2 `virtual void activemq::commands::LastPartialCommand::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::PartialCommand` (p. 2919).

6.465.2.3 `virtual bool activemq::commands::LastPartialCommand::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::PartialCommand` (p. 2919).

6.465.2.4 `virtual unsigned char activemq::commands::LastPartialCommand::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Reimplemented from `activemq::commands::PartialCommand` (p. 2920).

6.465.2.5 `virtual std::string activemq::commands::LastPartialCommand::toString () const [virtual]`

Returns a string containing the information for this `DataStructure` (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::PartialCommand` (p. 2920).

6.465.3 Field Documentation

6.465.3.1 `const unsigned char activemq::commands::LastPartialCommand::ID_ - LASTPARTIALCOMMAND = 61` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/LastPartialCommand.h`

6.466 activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2304).

#include <src/main/activemq/wireformat/openwire/marshal/v6/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.466.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2304). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.466.2 Constructor & Destructor Documentation

6.466.2.1 `activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` [inline]

6.466.2.2 `virtual activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` [inline, virtual]

6.466.3 Member Function Documentation

6.466.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2923).

6.466.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2923).

6.466.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2923).

6.466.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2924).

6.466.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller` (p. 2924).

6.466.3.6 virtual void activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller** (p. 2925).

6.466.3.7 virtual void activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller** (p. 2925).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**LastPartialCommandMarshaller.h**

6.467 activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2308).

#include <src/main/activemq/wireformat/openwire/marshal/v3/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.467.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2308). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.467.2 Constructor & Destructor Documentation

6.467.2.1 `activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` [inline]

6.467.2.2 `virtual activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` [inline, virtual]

6.467.3 Member Function Documentation

6.467.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2935).

6.467.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2935).

6.467.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2935).

6.467.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2936).

6.467.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller` (p. 2936).

6.467.3.6 virtual void activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller** (p. 2937).

6.467.3.7 virtual void activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller** (p. 2937).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**LastPartialCommandMarshaller.h**

6.468 activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2312).

#include <src/main/activemq/wireformat/openwire/marshal/v2/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.468.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2312). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.468.2 Constructor & Destructor Documentation

6.468.2.1 `activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` `[inline]`

6.468.2.2 `virtual activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` `[inline, virtual]`

6.468.3 Member Function Documentation

6.468.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2927).

6.468.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2927).

6.468.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2927).

6.468.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2928).

6.468.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller` (p. 2928).

6.468.3.6 virtual void activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller** (p. 2929).

6.468.3.7 virtual void activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller** (p. 2929).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**LastPartialCommandMarshaller.h**

6.469 activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2316).

#include <src/main/activemq/wireformat/openwire/marshal/v5/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.469.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2316). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.469.2 Constructor & Destructor Documentation

6.469.2.1 `activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` [inline]

6.469.2.2 `virtual activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` [inline, virtual]

6.469.3 Member Function Documentation

6.469.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2931).

6.469.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2931).

6.469.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2931).

6.469.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2932).

6.469.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller` (p. 2932).

6.469.3.6 virtual void activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller** (p. 2933).

6.469.3.7 virtual void activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller** (p. 2933).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**LastPartialCommandMarshaller.h**

6.470 activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2320).

#include <src/main/activemq/wireformat/openwire/marshal/v4/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.470.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2320). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.470.2 Constructor & Destructor Documentation

6.470.2.1 `activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` [inline]

6.470.2.2 `virtual activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` [inline, virtual]

6.470.3 Member Function Documentation

6.470.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2939).

6.470.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2939).

6.470.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2939).

6.470.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2940).

6.470.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller` (p. 2940).

6.470.3.6 virtual void activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller** (p. 2941).

6.470.3.7 virtual void activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller** (p. 2941).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**LastPartialCommandMarshaller.h**

6.471 activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2324).

#include <src/main/activemq/wireformat/openwire/marshal/v1/LastPartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller:

Public Member Functions

- **LastPartialCommandMarshaller** ()
- virtual **~LastPartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.471.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **LastPartialCommandMarshaller** (p.2324). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.471.2 Constructor & Destructor Documentation

6.471.2.1 `activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::LastPartialCommandMarshaller()` [inline]

6.471.2.2 `virtual activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::~LastPartialCommandMarshaller()` [inline, virtual]

6.471.3 Member Function Documentation

6.471.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2943).

6.471.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaller.

Returns:

byte holding the data structure type value

Reimplemented from `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2943).

6.471.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2943).

6.471.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2944).

6.471.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller` (p. 2944).

6.471.3.6 virtual void activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller** (p. 2945).

6.471.3.7 virtual void activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller** (p. 2945).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**LastPartialCommandMarshaller.h**

6.472 decaf::util::comparators::Less< E > Class Template Reference

Simple **Less** (p. 2328) **Comparator** (p. 1217) that compares to elements to determine if the first is less than the second.

#include <src/main/decaf/util/comparators/Less.h> Inheritance diagram for decaf::util::comparators::Less< E >:

Public Member Functions

- **Less** ()
- virtual **~Less** ()
- virtual bool **operator**() (const E &left, const E &right) const
*Implementation of the Binary function interface as a means of allowing a **Comparator** (p. 1217) to be passed to an STL **Map** (p. 2459) for use as the sorting criteria.*
- virtual int **compare** (const E &o1, const E &o2) const
Compares its two arguments for order.

6.472.1 Detailed Description

template<typename E> class decaf::util::comparators::Less< E >

Simple **Less** (p. 2328) **Comparator** (p. 1217) that compares to elements to determine if the first is less than the second. This can be used in **Collection** (p. 1184) classes to sort elements according to their natural ordering. By design the Comparator's compare function return more information about comparison than the STL binary function's boolean compare operator. In this case the compare method will return

Since:

1.0

6.472.2 Constructor & Destructor Documentation

6.472.2.1 template<typename E > decaf::util::comparators::Less< E >::Less ()
[inline]

6.472.2.2 template<typename E > virtual decaf::util::comparators::Less< E >::~~Less () [inline, virtual]

6.472.3 Member Function Documentation

6.472.3.1 template<typename E > virtual int decaf::util::comparators::Less< E >::compare (const E & o1, const E & o2) const [inline, virtual]

Compares its two arguments for order. Returns a negative integer, zero, or a positive integer as the first argument is less than, equal to, or greater than the second.

The implementor must ensure that $\text{sgn}(\text{compare}(x, y)) == -\text{sgn}(\text{compare}(y, x))$ for all x and y . (This implies that $\text{compare}(x, y)$ must throw an exception if and only if $\text{compare}(y, x)$ throws an exception.)

The implementor must also ensure that the relation is transitive: $((\text{compare}(x, y) > 0) \ \&\& \ (\text{compare}(y, z) > 0))$ implies $\text{compare}(x, z) > 0$.

Finally, the implementer must ensure that $\text{compare}(x, y) == 0$ implies that $\text{sgn}(\text{compare}(x, z)) == \text{sgn}(\text{compare}(y, z))$ for all z .

It is generally the case, but not strictly required that $(\text{compare}(x, y) == 0) == (x == y)$. Generally speaking, any comparator that violates this condition should clearly indicate this fact. The recommended language is "Note: this comparator imposes orderings that are inconsistent with equals."

Parameters:

- o1* - the first object to be compared
- o2* - the second object to be compared

Returns:

a negative integer, zero, or a positive integer as the first argument is less than, equal to, or greater than the second.

Implements **decaf::util::Comparator< E >** (p.1217).

6.472.3.2 `template<typename E> virtual bool decaf::util::comparators::Less< E >::operator() (const E & left, const E & right) const [inline, virtual]`

Implementation of the Binary function interface as a means of allowing a **Comparator** (p.1217) to be passed to an STL **Map** (p.2459) for use as the sorting criteria.

Parameters:

- left* - the Left hand side operand.
- right* - the Right hand side operand.

Returns:

true if the vale of left is less than the value of right.

Implements **decaf::util::Comparator< E >** (p.1218).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/comparators/Less.h`

6.473 std::less< decaf::lang::ArrayPointer< T > > Struct Template Reference

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

#include <src/main/decaf/lang/ArrayPointer.h> Inheritance diagram for std::less< decaf::lang::ArrayPointer< T > >:

Public Member Functions

- **bool operator()** (const **decaf::lang::ArrayPointer< T >** &left, const **decaf::lang::ArrayPointer< T >** &right) const

6.473.1 Detailed Description

template<typename T> struct std::less< decaf::lang::ArrayPointer< T > >

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

6.473.2 Member Function Documentation

- 6.473.2.1** template<typename T > bool std::less< decaf::lang::ArrayPointer< T > >::operator() (const decaf::lang::ArrayPointer< T > & *left*, const decaf::lang::ArrayPointer< T > & *right*) const [inline]

References decaf::lang::ArrayPointer< T, REFCOUNTER >::get().

The documentation for this struct was generated from the following file:

- src/main/decaf/lang/**ArrayPointer.h**

6.474 `std::less< decaf::lang::Pointer< T > >` Struct Template Reference

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

`#include <src/main/decaf/lang/Pointer.h>` Inheritance diagram for `std::less< decaf::lang::Pointer< T > >`:

Public Member Functions

- `bool operator() (const decaf::lang::Pointer< T > &left, const decaf::lang::Pointer< T > &right) const`

6.474.1 Detailed Description

`template<typename T> struct std::less< decaf::lang::Pointer< T > >`

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

6.474.2 Member Function Documentation

- 6.474.2.1** `template<typename T > bool std::less< decaf::lang::Pointer< T > >::operator() (const decaf::lang::Pointer< T > & left, const decaf::lang::Pointer< T > & right) const` [inline]

References `decaf::lang::Pointer< T, REFCOUNTER >::get()`.

The documentation for this struct was generated from the following file:

- `src/main/decaf/lang/Pointer.h`

6.475 decaf::util::logging::Level Class Reference

The **Level** (p. 2332) class defines a set of standard **logging** (p. 175) levels that can be used to control **logging** (p. 175) output.

#include <src/main/decaf/util/logging/Level.h> Inheritance diagram for decaf::util::logging::Level:

Public Member Functions

- virtual **~Level** ()
- int **intValue** () const
- std::string **getName** () const
- std::string **toString** () const
- virtual int **compareTo** (const **Level** &value) const
- virtual bool **equals** (const **Level** &value) const
- virtual bool **operator==** (const **Level** &value) const
- virtual bool **operator<** (const **Level** &value) const

Static Public Member Functions

- static **Level** **parse** (const std::string &name) throw (decaf::lang::exceptions::IllegalArgumentException)
*Parse a level name string into a **Level** (p. 2332).*

Static Public Attributes

- static const **Level** **INHERIT**
*NULL is a special level that indicates that the **Logger** (p. 2386) should get its **Level** (p. 2332) from its parent **Logger** (p. 2386), the value is initialized as zero.*
- static const **Level** **OFF**
*OFF is a special level that can be used to turn off **logging** (p. 175).*
- static const **Level** **SEVERE**
SEVERE is a message level indicating a serious failure.
- static const **Level** **WARNING**
WARNING is a message level indicating a potential problem.
- static const **Level** **INFO**
INFO is a message level for informational messages.
- static const **Level** **DEBUG**
DEBUG is a level for more verbose informative messages.
- static const **Level** **CONFIG**

CONFIG is a message level for static configuration messages.

- static const **Level FINE**

FINE is a message level providing tracing information.

- static const **Level FINER**

FINER indicates a fairly detailed tracing message.

- static const **Level FINEST**

FINEST indicates a highly detailed tracing message.

- static const **Level ALL**

ALL indicates that all messages should be logged.

Protected Member Functions

- **Level** (const std::string &name, int value)

*Create a named **Level** (p. 2332) with a given integer value.*

6.475.1 Detailed Description

The **Level** (p. 2332) class defines a set of standard **logging** (p. 175) levels that can be used to control **logging** (p. 175) output. The **logging** (p. 175) **Level** (p. 2332) objects are ordered and are specified by ordered integers. Enabling **logging** (p. 175) at a given level also enables **logging** (p. 175) at all higher levels.

Clients should normally use the predefined **Level** (p. 2332) constants such as **Level.SEVERE** (p. 2336).

The levels in descending order are:

* SEVERE (highest value) * WARNING * INFO * DEBUG * CONFIG * FINE * FINER * FINEST (lowest value)

In addition there is a level OFF that can be used to turn off **logging** (p. 175), and a level ALL that can be used to enable **logging** (p. 175) of all messages.

It is possible for third parties to define additional **logging** (p. 175) levels by subclassing **Level** (p. 2332). In such cases subclasses should take care to chose unique integer level values.

Since:

1.0

6.475.2 Constructor & Destructor Documentation

6.475.2.1 decaf::util::logging::Level::Level (const std::string & name, int value) [protected]

Create a named **Level** (p. 2332) with a given integer value.

Parameters:

- name* Name of the level, e.g. SEVERE
value Unique integer value of this level, e.g. 100

6.475.2.2 virtual decaf::util::logging::Level::~~Level () [virtual]

6.475.3 Member Function Documentation

6.475.3.1 virtual int decaf::util::logging::Level::compareTo (const Level & *value*) const [virtual]

6.475.3.2 virtual bool decaf::util::logging::Level::equals (const Level & *value*) const [virtual]

6.475.3.3 std::string decaf::util::logging::Level::getName () const [inline]

Returns:

the name of this **Level** (p. 2332) instance.

6.475.3.4 int decaf::util::logging::Level::intValue () const [inline]

Returns:

the integer value of this level instance.

6.475.3.5 virtual bool decaf::util::logging::Level::operator< (const Level & *value*) const [virtual]

6.475.3.6 virtual bool decaf::util::logging::Level::operator== (const Level & *value*) const [virtual]

6.475.3.7 static Level decaf::util::logging::Level::parse (const std::string & *name*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Parse a level name string into a **Level** (p. 2332). The argument string may consist of either a level name or an integer value.

For example:

```
* "SEVERE" * "1000"
```

Parameters:

name - The name or int value of the desired **Level** (p. 2332)

Returns:

the parsed **Level** (p. 2332) value, passing in a level name that is an int value that is not one of the known **Level** (p. 2332) values will result in a new **Level** (p. 2332) that has been initialized with that int value and name as the string form of the int.

Exceptions:

IllegalArgumentException if the value is not valid, validity means that the string is either a valid int (between Integer::MIN_VALUE and Integer::MAX_VALUE or is one of the known level names.

6.475.3.8 std::string decaf::util::logging::Level::toString () const [inline]**Returns:**

the string value of this **Level** (p. 2332), e.g. "SEVERE".

6.475.4 Field Documentation**6.475.4.1 const Level decaf::util::logging::Level::ALL [static]**

ALL indicates that all messages should be logged. This level is initialized to Integer::MIN_VALUE.

6.475.4.2 const Level decaf::util::logging::Level::CONFIG [static]

CONFIG is a message level for static configuration messages. CONFIG messages are intended to provide a variety of static configuration information, to assist in debugging problems that may be associated with particular configurations. For example, CONFIG message might include the CPU type, the System properties, etc. This level is initialized to 600.

6.475.4.3 const Level decaf::util::logging::Level::DEBUG [static]

DEBUG is a level for more verbose informative messages. DEBUG messages are intended to provide a more detailed message intended for use by developers in tracking the behavior of a client. DEBUG messages typically contain more implementation specific information that might not be significant to end users or system admins. This level is initialized to 700.

6.475.4.4 const Level decaf::util::logging::Level::FINE [static]

FINE is a message level providing tracing information. All of FINE, FINER, and FINEST are intended for relatively detailed tracing. The exact meaning of the three levels will vary between subsystems, but in general, FINEST should be used for the most detailed output, FINER for somewhat less detailed output, and FINE for the lowest volume (and most important) messages.

In general the FINE level should be used for information that will be broadly interesting to developers who do not have a specialized interest in the specific subsystem.

FINE messages might include things like minor (recoverable) failures. Issues indicating potential performance problems are also worth **logging** (p. 175) as FINE. This level is initialized to 500.

6.475.4.5 const Level decaf::util::logging::Level::FINER [static]

FINER indicates a fairly detailed tracing message. By default **logging** (p. 175) calls for entering, returning, or throwing an exception are traced at this level. This level is initialized to 400.

6.475.4.6 const Level decaf::util::logging::Level::FINEST [static]

FINEST indicates a highly detailed tracing message. This level is initialized to 300.

6.475.4.7 const Level decaf::util::logging::Level::INFO [static]

INFO is a message level for informational messages. Typically INFO messages will be written to the console or its equivalent. So the INFO level should only be used for reasonably significant messages that will make sense to end users and system admins. This level is initialized to 800.

6.475.4.8 const Level decaf::util::logging::Level::INHERIT [static]

NULL is a special level that indicates that the **Logger** (p. 2386) should get its **Level** (p. 2332) from its parent **Logger** (p. 2386), the value is initialized as zero.

6.475.4.9 const Level decaf::util::logging::Level::OFF [static]

OFF is a special level that can be used to turn off **logging** (p. 175). This level is initialized to `Integer::MAX_VALUE`

6.475.4.10 const Level decaf::util::logging::Level::SEVERE [static]

SEVERE is a message level indicating a serious failure. In general SEVERE messages should describe events that are of considerable importance and which will prevent normal program execution. They should be reasonably intelligible to end users and to system administrators. This level is initialized to 1000.

6.475.4.11 const Level decaf::util::logging::Level::WARNING [static]

WARNING is a message level indicating a potential problem. In general WARNING messages should describe events that will be of interest to end users or system managers, or which indicate potential problems. This level is initialized to 900.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/Level.h`

6.476 decaf::util::List< E > Class Template Reference

An ordered collection (also known as a sequence).

#include <src/main/decaf/util/List.h> Inheritance diagram for decaf::util::List< E >:

Public Member Functions

- **List** ()
- virtual **~List** ()
- virtual **ListIterator**< E > * **listIterator** ()=0
- virtual **ListIterator**< E > * **listIterator** () const =0
- virtual **ListIterator**< E > * **listIterator** (std::size_t index)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual **ListIterator**< E > * **listIterator** (std::size_t index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual std::size_t **indexOf** (const E &value)=0 throw (decaf::lang::exceptions::NoSuchElementException)
Returns the index of the first occurrence of the specified element in this list, or -1 if this list does not contain the element.
- virtual std::size_t **lastIndexOf** (const E &value)=0 throw (decaf::lang::exceptions::NoSuchElementException)
Returns the index of the last occurrence of the specified element in this list, or -1 if this list does not contain the element.
- virtual E **get** (std::size_t index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Gets the element contained at position passed.
- virtual E **set** (std::size_t index, const E &element)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Replaces the element at the specified position in this list with the specified element.
- virtual void **add** (std::size_t index, const E &element)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException)
Inserts the specified element at the specified position in this list.
- virtual bool **addAll** (std::size_t index, const **Collection**< E > &source)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException)
Inserts all of the elements in the specified collection into this list at the specified position (optional operation).
- virtual E **remove** (std::size_t index)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException)
Removes the element at the specified position in this list.

6.476.1 Detailed Description

template<typename E> class decaf::util::List< E >

An ordered collection (also known as a sequence). The user of this interface has precise control over where in the list each element is inserted. The user can access elements by their integer index (position in the list), and search for elements in the list.

Unlike sets, lists typically allow duplicate elements. More formally, lists typically allow pairs of elements *e1* and *e2* such that *e1.equals(e2)*, and they typically allow multiple null elements if they allow null elements at all. It is not inconceivable that someone might wish to implement a list that prohibits duplicates, by throwing runtime exceptions when the user attempts to insert them, but we expect this usage to be rare.

6.476.2 Constructor & Destructor Documentation

6.476.2.1 **template<typename E> decaf::util::List< E >::List ()** [inline]

6.476.2.2 **template<typename E> virtual decaf::util::List< E >::~~List ()** [inline, virtual]

6.476.3 Member Function Documentation

6.476.3.1 **template<typename E> virtual void decaf::util::List< E >::add (std::size_t *index*, const E & *element*)** throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Inserts the specified element at the specified position in this list. Shifts the element currently at that position (if any) and any subsequent elements to the right (adds one to their indices).

Parameters:

index - index at which the specified element is to be inserted

element - element to be inserted

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

Implemented in **decaf::util::StlList< E >** (p. 3594), **decaf::util::StlList< cms::MessageConsumer * >** (p. 3594), **decaf::util::StlList< CompositeTask * >** (p. 3594), **decaf::util::StlList< URI >** (p. 3594), **decaf::util::StlList< Pointer< DestinationInfo > >** (p. 3594), **decaf::util::StlList< PrimitiveValueNode >** (p. 3594), **decaf::util::StlList< Pointer< Command > >** (p. 3594), **decaf::util::StlList< Pointer< BackupTransport > >** (p. 3594), **decaf::util::StlList< cms::MessageProducer * >** (p. 3594), **decaf::util::StlList< cms::Destination * >** (p. 3594), **decaf::util::StlList< cms::Session * >** (p. 3594), and **decaf::util::StlList< cms::Connection * >** (p. 3594).

6.476.3.2 `template<typename E> virtual bool decaf::util::List< E >::addAll
(std::size_t index, const Collection< E > & source) throw
(decaf::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Inserts all of the elements in the specified collection into this list at the specified position (optional operation). Shifts the element currently at that position (if any) and any subsequent elements to the right (increases their indices). The new elements will appear in this list in the order that they are returned by the specified collection's iterator. The behavior of this operation is undefined if the specified collection is modified while the operation is in progress. (Note that this will occur if the specified collection is this list, and it's nonempty.)

Parameters:

index The index at which to insert the first element from the specified collection
source The **Collection** (p. 1184) containing elements to be added to this list

Returns:

true if this list changed as a result of the call

Exceptions:

IndexOutOfBoundsException - if the index is greater than size
UnsupportedOperationException - If the collection is non-modifiable.

Implemented in `decaf::util::StlList< E >` (p. 3595), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3595), `decaf::util::StlList< CompositeTask * >` (p. 3595), `decaf::util::StlList< URI >` (p. 3595), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3595), `decaf::util::StlList< PrimitiveValueNode >` (p. 3595), `decaf::util::StlList< Pointer< Command > >` (p. 3595), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3595), `decaf::util::StlList< cms::MessageProducer * >` (p. 3595), `decaf::util::StlList< cms::Destination * >` (p. 3595), `decaf::util::StlList< cms::Session * >` (p. 3595), and `decaf::util::StlList< cms::Connection * >` (p. 3595).

6.476.3.3 `template<typename E> virtual E decaf::util::List< E >::get (std::size_t
index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException
) [pure virtual]`

Gets the element contained at position passed.

Parameters:

index - position to get

Returns:

value at index

Implemented in `decaf::util::StlList< E >` (p. 3597), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3597), `decaf::util::StlList< CompositeTask * >` (p. 3597), `decaf::util::StlList< URI >` (p. 3597), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3597), `decaf::util::StlList< PrimitiveValueNode >` (p. 3597), `decaf::util::StlList< Pointer< Command > >` (p. 3597), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3597), `decaf::util::StlList< cms::MessageProducer * >` (p. 3597), `decaf::util::StlList< cms::Destination * >` (p. 3597), `decaf::util::StlList< cms::Session * >` (p. 3597), and `decaf::util::StlList< cms::Connection * >` (p. 3597).

6.476.3.4 `template<typename E> virtual std::size_t decaf::util::List<E>::indexOf (const E & value) throw (decaf::lang::exceptions::NoSuchElementException) [pure virtual]`

Returns the index of the first occurrence of the specified element in this list, or -1 if this list does not contain the element. More formally, returns the lowest index *i* such that `get(i) == value`, or -1 if there is no such index.

Parameters:

value - element to search for

Returns:

the index of the first occurrence of the specified element in this list,

Exceptions:

NoSuchElementException if *value* is not in the list

Implemented in `decaf::util::StlList< E >` (p. 3597), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3597), `decaf::util::StlList< CompositeTask * >` (p. 3597), `decaf::util::StlList< URI >` (p. 3597), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3597), `decaf::util::StlList< PrimitiveValueNode >` (p. 3597), `decaf::util::StlList< Pointer< Command > >` (p. 3597), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3597), `decaf::util::StlList< cms::MessageProducer * >` (p. 3597), `decaf::util::StlList< cms::Destination * >` (p. 3597), `decaf::util::StlList< cms::Session * >` (p. 3597), and `decaf::util::StlList< cms::Connection * >` (p. 3597).

6.476.3.5 `template<typename E> virtual size_t decaf::util::List<E>::lastIndexOf (const E & value) throw (decaf::lang::exceptions::NoSuchElementException) [pure virtual]`

Returns the index of the last occurrence of the specified element in this list, or -1 if this list does not contain the element. More formally, returns the highest index *i* such that `get(i) == value` or -1 if there is no such index.

Parameters:

value - element to search for

Returns:

the index of the last occurrence of the specified element in this list.

Exceptions:

NoSuchElementException if *value* is not in the list

Implemented in `decaf::util::StlList< E >` (p. 3598), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), and `decaf::util::StlList< cms::Connection * >` (p. 3598).

6.476.3.6 `template<typename E> virtual ListIterator<E>* decaf::util::List< E >::listIterator (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Implemented in `decaf::util::StlList< E >` (p. 3598), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3598), `decaf::util::StlList< CompositeTask * >` (p. 3598), `decaf::util::StlList< URI >` (p. 3598), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3598), `decaf::util::StlList< PrimitiveValueNode >` (p. 3598), `decaf::util::StlList< Pointer< Command > >` (p. 3598), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3598), `decaf::util::StlList< cms::MessageProducer * >` (p. 3598), `decaf::util::StlList< cms::Destination * >` (p. 3598), `decaf::util::StlList< cms::Session * >` (p. 3598), and `decaf::util::StlList< cms::Connection * >` (p. 3598).

6.476.3.7 `template<typename E> virtual ListIterator<E>* decaf::util::List< E >::listIterator (std::size_t index) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Parameters:

index index of first element to be returned from the list iterator (by a call to the next method).

Returns:

a list iterator of the elements in this list (in proper sequence), starting at the specified position in this list. The specified index indicates the first element that would be returned by an initial call to next. An initial call to previous would return the element with the specified index minus one.

Exceptions:

IndexOutOfBoundsException if the index is out of range (`index < 0 || index > size()` (p. 1192))

Implemented in `decaf::util::StlList< E >` (p. 3599), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3599), `decaf::util::StlList< CompositeTask * >` (p. 3599), `decaf::util::StlList< URI >` (p. 3599), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3599), `decaf::util::StlList< PrimitiveValueNode >` (p. 3599), `decaf::util::StlList< Pointer< Command > >` (p. 3599), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3599), `decaf::util::StlList< cms::MessageProducer * >` (p. 3599), `decaf::util::StlList< cms::Destination * >` (p. 3599), `decaf::util::StlList< cms::Session * >` (p. 3599), and `decaf::util::StlList< cms::Connection * >` (p. 3599).

6.476.3.8 `template<typename E> virtual ListIterator<E>* decaf::util::List< E >::listIterator () const [pure virtual]`

Implemented in `decaf::util::StlList< E >` (p. 3599), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3599), `decaf::util::StlList< CompositeTask * >` (p. 3599), `decaf::util::StlList< URI >` (p. 3599), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3599), `decaf::util::StlList< PrimitiveValueNode >` (p. 3599), `decaf::util::StlList< Pointer< Command > >` (p. 3599), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3599), `decaf::util::StlList< cms::MessageProducer * >` (p. 3599), `decaf::util::StlList< cms::Destination * >` (p. 3599), `decaf::util::StlList< cms::Session * >` (p. 3599), and `decaf::util::StlList< cms::Connection * >` (p. 3599).

6.476.3.9 `template<typename E> virtual ListIterator<E>* decaf::util::List< E >::listIterator () [pure virtual]`

Returns:

a list iterator over the elements in this list (in proper sequence).

Implemented in `decaf::util::StlList< E >` (p. 3599), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3599), `decaf::util::StlList< CompositeTask * >` (p. 3599), `decaf::util::StlList< URI >` (p. 3599), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3599), `decaf::util::StlList< PrimitiveValueNode >` (p. 3599), `decaf::util::StlList< Pointer< Command > >` (p. 3599), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3599), `decaf::util::StlList< cms::MessageProducer * >` (p. 3599), `decaf::util::StlList< cms::Destination * >` (p. 3599), `decaf::util::StlList< cms::Session * >` (p. 3599), and `decaf::util::StlList< cms::Connection * >` (p. 3599).

6.476.3.10 `template<typename E> virtual E decaf::util::List< E >::remove (std::size_t index) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Removes the element at the specified position in this list. Shifts any subsequent elements to the left (subtracts one from their indices). Returns the element that was removed from the list.

Parameters:

index - the index of the element to be removed

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

Implemented in `decaf::util::StlList< E >` (p. 3599), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3599), `decaf::util::StlList< CompositeTask * >` (p. 3599), `decaf::util::StlList< URI >` (p. 3599), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3599), `decaf::util::StlList< PrimitiveValueNode >` (p. 3599), `decaf::util::StlList< Pointer< Command > >` (p. 3599), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3599), `decaf::util::StlList< cms::MessageProducer * >` (p. 3599), `decaf::util::StlList< cms::Destination * >` (p. 3599), `decaf::util::StlList< cms::Session * >` (p. 3599), and `decaf::util::StlList< cms::Connection * >` (p. 3599).

6.476.3.11 `template<typename E> virtual E decaf::util::List< E >::set (std::size_t index, const E & element) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]`

Replaces the element at the specified position in this list with the specified element.

Parameters:

index - index of the element to replace

element - element to be stored at the specified position

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

Implemented in `decaf::util::StlList< E >` (p. 3600), `decaf::util::StlList< cms::MessageConsumer * >` (p. 3600), `decaf::util::StlList< CompositeTask * >` (p. 3600), `decaf::util::StlList< URI >` (p. 3600), `decaf::util::StlList< Pointer< DestinationInfo > >` (p. 3600), `decaf::util::StlList< PrimitiveValueNode >` (p. 3600), `decaf::util::StlList< Pointer< Command > >` (p. 3600), `decaf::util::StlList< Pointer< BackupTransport > >` (p. 3600), `decaf::util::StlList< cms::MessageProducer * >` (p. 3600), `decaf::util::StlList< cms::Destination * >` (p. 3600), `decaf::util::StlList< cms::Session * >` (p. 3600), and `decaf::util::StlList< cms::Connection * >` (p. 3600).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/List.h`

6.477 decaf::util::ListIterator< E > Class Template Reference

An iterator for lists that allows the programmer to traverse the list in either direction, modify the list during iteration, and obtain the iterator's current position in the list.

```
#include <src/main/decaf/util/ListIterator.h> Inheritance diagram for
decaf::util::ListIterator< E >:
```

Public Member Functions

- virtual `~ListIterator()`
- virtual void `add` (const E &e)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into the list (optional operation).
- virtual void `set` (const E &e)=0 throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Replaces the last element returned by next or previous with the specified element (optional operation).
- virtual bool `hasPrevious()` const =0
Returns true if this list iterator has more elements when traversing the list in the reverse direction.
- virtual E `previous()`=0
Returns the previous element in the list.
- virtual int `nextIndex()` const =0
Returns the index of the element that would be returned by a subsequent call to next.
- virtual int `previousIndex()` const =0
Returns the index of the element that would be returned by a subsequent call to previous.

6.477.1 Detailed Description

```
template<typename E> class decaf::util::ListIterator< E >
```

An iterator for lists that allows the programmer to traverse the list in either direction, modify the list during iteration, and obtain the iterator's current position in the list. Note that the `remove()` (p. 2155) and `set(Object)` methods are not defined in terms of the cursor position; they are defined to operate on the last element returned by a call to `next()` (p. 2154) or `previous()` (p. 2346).

6.477.2 Constructor & Destructor Documentation

6.477.2.1 `template<typename E > virtual decaf::util::ListIterator< E >::~~ListIterator () [inline, virtual]`

6.477.3 Member Function Documentation

6.477.3.1 `template<typename E > virtual void decaf::util::ListIterator< E >::add (const E & e) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException) [pure virtual]`

Inserts the specified element into the list (optional operation). The element is inserted immediately before the next element that would be returned by next, if any, and after the next element that would be returned by previous, if any. (If the list contains no elements, the new element becomes the sole element on the list.) The new element is inserted before the implicit cursor: a subsequent call to next would be unaffected, and a subsequent call to previous would return the new element. (This call increases by one the value that would be returned by a call to nextIndex or previousIndex.)

Parameters:

e - the element to insert.

Exceptions:

UnsupportedOperationException - if the add method is not supported by this list iterator.

IllegalArgumentException - if some aspect of this element prevents it from being added to this list.

6.477.3.2 `template<typename E > virtual bool decaf::util::ListIterator< E >::hasPrevious () const [pure virtual]`

Returns true if this list iterator has more elements when traversing the list in the reverse direction. (In other words, returns true if previous would return an element rather than throwing an exception.)

Returns:

true if the list iterator has more elements when traversing the list in the reverse direction.

6.477.3.3 `template<typename E > virtual int decaf::util::ListIterator< E >::nextIndex () const [pure virtual]`

Returns the index of the element that would be returned by a subsequent call to next. (Returns list size if the list iterator is at the end of the list.)

Returns:

the index of the element that would be returned by a subsequent call to next, or list size if list iterator is at end of list.

6.477.3.4 `template<typename E > virtual E decaf::util::ListIterator< E >::previous
() [pure virtual]`

Returns the previous element in the list. This method may be called repeatedly to iterate through the list backwards, or intermixed with calls to `next` to go back and forth. (Note that alternating calls to `next` and `previous` will return the same element repeatedly.)

Returns:

the previous element in the list.

Exceptions:

NoSuchElementException - if the iteration has no previous element.

6.477.3.5 `template<typename E > virtual int decaf::util::ListIterator< E
>::previousIndex () const [pure virtual]`

Returns the index of the element that would be returned by a subsequent call to `previous`. (Returns -1 if the list iterator is at the beginning of the list.)

Returns:

the index of the element that would be returned by a subsequent call to `previous`, or -1 if list iterator is at beginning of list.

6.477.3.6 `template<typename E > virtual void
decaf::util::ListIterator< E >::set (const E & e) throw (
decaf::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException) [pure virtual]`

Replaces the last element returned by `next` or `previous` with the specified element (optional operation). This call can be made only if neither **ListIterator.remove** (p. 2155) nor **ListIterator.add** (p. 2345) have been called after the last call to `next` or `previous`.

Parameters:

e - the element with which to replace the last element returned by `next` or `previous`.

Exceptions:

UnsupportedOperationException - if the add method is not supported by this list iterator.

IllegalArgumentException - if some aspect of this element prevents it from being added to this list.

IllegalStateException - if neither `next` nor `previous` have been called, or `remove` or `add` have been called after the last call to `next` or `previous`.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/ListIterator.h`

6.478 activemq::commands::LocalTransactionId Class Reference

#include <src/main/activemq/commands/LocalTransactionId.h> Inheritance diagram for activemq::commands::LocalTransactionId:

Public Types

- typedef decaf::lang::PointerComparator< LocalTransactionId > COMPARATOR

Public Member Functions

- LocalTransactionId ()
- LocalTransactionId (const LocalTransactionId &other)
- virtual ~LocalTransactionId ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual LocalTransactionId * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const DataStructure *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
Returns a string containing the information for this DataStructure (p. 1660) such as its type and value of its elements.
- virtual bool **equals** (const DataStructure *value) const
Compares the DataStructure (p. 1660) passed in to this one, and returns if they are equivalent.
- virtual long long **getValue** () const
- virtual void **setValue** (long long value)
- virtual const Pointer< ConnectionId > & **getConnectionId** () const
- virtual Pointer< ConnectionId > & **getConnectionId** ()
- virtual void **setConnectionId** (const Pointer< ConnectionId > &connectionId)
- virtual int **compareTo** (const LocalTransactionId &value) const
- virtual bool **equals** (const LocalTransactionId &value) const
- virtual bool **operator==** (const LocalTransactionId &value) const
- virtual bool **operator<** (const LocalTransactionId &value) const
- LocalTransactionId & **operator=** (const LocalTransactionId &other)

Static Public Attributes

- static const unsigned char **ID_LOCALTRANSACTIONID** = 111

Protected Attributes

- long long **value**
- **Pointer< ConnectionId > connectionId**

6.478.1 Member Typedef Documentation

6.478.1.1 `typedef decaf::lang::PointerComparator<LocalTransactionId>
activemq::commands::LocalTransactionId::COMPARATOR`

Reimplemented from `activemq::commands::TransactionId` (p. 3819).

6.478.2 Constructor & Destructor Documentation

6.478.2.1 `activemq::commands::LocalTransactionId::LocalTransactionId ()`

6.478.2.2 `activemq::commands::LocalTransactionId::LocalTransactionId (const
LocalTransactionId & other)`

6.478.2.3 `virtual activemq::commands::LocalTransactionId::~~LocalTransactionId ()
[virtual]`

6.478.3 Member Function Documentation

6.478.3.1 `virtual LocalTransactionId* ac-
tivemq::commands::LocalTransactionId::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.478.3.2 `virtual int activemq::commands::LocalTransactionId::compareTo (const
LocalTransactionId & value) const [virtual]`

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.478.3.3 `virtual void activemq::commands::LocalTransactionId::copyDataStructure
(const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.478.3.4 `virtual bool activemq::commands::LocalTransactionId::equals (const LocalTransactionId & value) const` [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.478.3.5 `virtual bool activemq::commands::LocalTransactionId::equals (const DataStructure * value) const` [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.3.6 `virtual Pointer<ConnectionId>& activemq::commands::LocalTransactionId::getConnectionId ()` [virtual]

6.478.3.7 `virtual const Pointer<ConnectionId>& activemq::commands::LocalTransactionId::getConnectionId () const` [virtual]

6.478.3.8 `virtual unsigned char activemq::commands::LocalTransactionId::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.3.9 `virtual long long activemq::commands::LocalTransactionId::getValue () const` [virtual]

6.478.3.10 `virtual bool activemq::commands::LocalTransactionId::operator< (const LocalTransactionId & value) const` [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.3.11 `LocalTransactionId& activemq::commands::LocalTransactionId::operator= (const LocalTransactionId & other)`

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.3.12 `virtual bool activemq::commands::LocalTransactionId::operator==(const LocalTransactionId & value) const` [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.3.13 `virtual void activemq::commands::LocalTransactionId::setConnectionId(const Pointer< ConnectionId > & connectionId)` [virtual]

6.478.3.14 `virtual void activemq::commands::LocalTransactionId::setValue (long long value)` [virtual]

6.478.3.15 `virtual std::string activemq::commands::LocalTransactionId::toString () const` [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.478.4 Field Documentation

6.478.4.1 `Pointer<ConnectionId> activemq::commands::LocalTransactionId::connectionId` [protected]

6.478.4.2 `const unsigned char activemq::commands::LocalTransactionId::ID_LOCALTRANSACTIONID = 111` [static]

6.478.4.3 `long long activemq::commands::LocalTransactionId::value` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/LocalTransactionId.h`

6.479 activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2351).

#include <src/main/activemq/wireformat/openwire/marshal/v6/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.479.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2351).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.479.2 Constructor & Destructor Documentation

6.479.2.1 `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.479.2.2 `virtual activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.479.3 Member Function Documentation

6.479.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.479.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.479.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3844).

6.479.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3844).

6.479.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3845).

6.479.3.6 `virtual void activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller** (p. 3845).

6.479.3.7 `virtual void activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller** (p. 3846).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/LocalTransactionIdMarshaller.h`

6.480 activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2355).

#include <src/main/activemq/wireformat/openwire/marshal/v2/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.480.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2355).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.480.2 Constructor & Destructor Documentation

6.480.2.1 `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.480.2.2 `virtual activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.480.3 Member Function Documentation

6.480.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.480.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.480.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3832).

6.480.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3832).

6.480.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3833).

6.480.3.6 `virtual void activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller** (p. 3833).

6.480.3.7 `virtual void activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller** (p. 3834).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/LocalTransactionIdMarshaller.h`

6.481 activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2359).

#include <src/main/activemq/wireformat/openwire/marshal/v3/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.481.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2359).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.481.2 Constructor & Destructor Documentation

6.481.2.1 `activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.481.2.2 `virtual activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.481.3 Member Function Documentation

6.481.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.481.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.481.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3836).

6.481.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3836).

6.481.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3837).

6.481.3.6 `virtual void activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller** (p. 3837).

6.481.3.7 `virtual void activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller** (p. 3838).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/LocalTransactionIdMarshaller.h`

6.482 activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2363).

#include <src/main/activemq/wireformat/openwire/marshal/v5/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.482.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2363).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.482.2 Constructor & Destructor Documentation

6.482.2.1 `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.482.2.2 `virtual activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.482.3 Member Function Documentation

6.482.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.482.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.482.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3824).

6.482.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3824).

6.482.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3825).

6.482.3.6 virtual void activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3825).

6.482.3.7 virtual void activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3826).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**LocalTransactionIdMarshaller.h**

6.483 activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2367).

#include <src/main/activemq/wireformat/openwire/marshal/v4/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.483.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2367).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.483.2 Constructor & Destructor Documentation

6.483.2.1 `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.483.2.2 `virtual activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.483.3 Member Function Documentation

6.483.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.483.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.483.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3840).

6.483.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3840).

6.483.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3841).

6.483.3.6 virtual void activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller** (p. 3841).

6.483.3.7 virtual void activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller** (p. 3842).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**LocalTransactionIdMarshaller.h**

6.484 activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2371).

#include <src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller:

Public Member Functions

- **LocalTransactionIdMarshaller** ()
- virtual **~LocalTransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.484.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2371).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.484.2 Constructor & Destructor Documentation

6.484.2.1 `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::LocalTransactionIdMarshaller()` [inline]

6.484.2.2 `virtual activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::~LocalTransactionIdMarshaller()` [inline, virtual]

6.484.3 Member Function Documentation

6.484.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.484.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.484.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3828).

6.484.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3828).

6.484.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3829).

6.484.3.6 `virtual void activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller** (p. 3829).

6.484.3.7 `virtual void activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller** (p. 3830).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionIdMarshaller.h`

6.485 decaf::util::concurrent::Lock Class Reference

A wrapper class around a given synchronization mechanism that provides automatic release upon destruction.

```
#include <src/main/decaf/util/concurrent/Lock.h>
```

Public Member Functions

- **Lock** (**Synchronizable** *object, const bool initiallyLocked=true)
*Constructor - initializes the object member and **locks** (p. 174) the object if desired.*
- virtual ~**Lock** ()
Destructor - Unlocks the object if it is locked.
- void **lock** ()
Locks the object.
- void **unlock** ()
Unlocks the object if it is already locked, otherwise a call to this method has no effect.
- bool **isLocked** () const
Indicates whether or not the object is locked.

6.485.1 Detailed Description

A wrapper class around a given synchronization mechanism that provides automatic release upon destruction.

Since:

1.0

6.485.2 Constructor & Destructor Documentation

6.485.2.1 decaf::util::concurrent::Lock::Lock (**Synchronizable** * object, const bool initiallyLocked = true)

Constructor - initializes the object member and **locks** (p. 174) the object if desired.

Parameters:

object The sync object to control

initiallyLocked If true, the object will automatically be locked.

6.485.2.2 virtual decaf::util::concurrent::Lock::~~Lock () [virtual]

Destructor - Unlocks the object if it is locked.

6.485.3 Member Function Documentation

6.485.3.1 `bool decaf::util::concurrent::Lock::isLocked () const [inline]`

Indicates whether or not the object is locked.

Returns:

true if the object is locked, otherwise false.

6.485.3.2 `void decaf::util::concurrent::Lock::lock ()`

Locks the object.

6.485.3.3 `void decaf::util::concurrent::Lock::unlock ()`

Unlocks the object if it is already locked, otherwise a call to this method has no effect.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Lock.h`

6.486 decaf::util::concurrent::locks::Lock Class Reference

Lock (p. 2377) implementations provide more extensive locking operations than can be obtained using synchronized statements.

#include <src/main/decaf/util/concurrent/locks/Lock.h> Inheritance diagram for decaf::util::concurrent::locks::Lock:

Public Member Functions

- virtual **~Lock** ()
- virtual void **lock** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Acquires the lock.
- virtual void **lockInterruptibly** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException)
Acquires the lock unless the current thread is interrupted.
- virtual bool **tryLock** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Acquires the lock only if it is free at the time of invocation.
- virtual bool **tryLock** (long long time, const **TimeUnit** &unit)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException)
Acquires the lock if it is free within the given waiting time and the current thread has not been interrupted.
- virtual void **unlock** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Releases the lock.
- virtual **Condition** * **newCondition** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::UnsupportedOperationException)
*Returns a new **Condition** (p. 1249) instance that is bound to this **Lock** (p. 2377) instance.*

6.486.1 Detailed Description

Lock (p. 2377) implementations provide more extensive locking operations than can be obtained using synchronized statements. They allow more flexible structuring, may have quite different properties, and may support multiple associated **Condition** (p. 1249) objects.

A lock is a tool for controlling access to a shared resource by multiple threads. Commonly, a lock provides exclusive access to a shared resource: only one thread at a time can acquire the lock and all access to the shared resource requires that the lock be acquired first. However, some **locks** (p. 174) may allow **concurrent** (p. 171) access to a shared resource, such as the read lock of a **ReadWriteLock** (p. 3172).

While the scoping mechanism for synchronized statements makes it much easier to program with monitor **locks** (p. 174), and helps avoid many common programming errors involving **locks**

(p. 174), there are occasions where you need to work with **locks** (p. 174) in a more flexible way. For example, some algorithms for traversing concurrently accessed data structures require the use of "hand-over-hand" or "chain locking": you acquire the lock of node A, then node B, then release A and acquire C, then release B and acquire D and so on. Implementations of the **Lock** (p. 2377) interface enable the use of such techniques by allowing a lock to be acquired and released in different scopes, and allowing multiple **locks** (p. 174) to be acquired and released in any order.

With this increased flexibility comes additional responsibility. The absence of block-structured locking removes the automatic release of **locks** (p. 174) that occurs with synchronized statements. In most cases, the following idiom should be used:

```
Lock (p. 2377) l = ...; l.lock(); try { // access the resource protected by this lock } catch(...) { l.unlock(); }
```

When locking and unlocking occur in different scopes, care must be taken to ensure that all **code** (p. 1183) that is executed while the lock is held is protected by try-catch ensure that the lock is released when necessary.

Lock (p. 2377) implementations provide additional functionality over the use of synchronized methods and statements by providing a non-blocking attempt to acquire a lock (**tryLock()** (p. 2381)), an attempt to acquire the lock that can be interrupted (**lockInterruptibly()** (p. 2379), and an attempt to acquire the lock that can timeout (**tryLock(long, TimeUnit)**).

Note that **Lock** (p. 2377) instances are just normal objects and can themselves be used as the target in a synchronized statement.

The three forms of lock acquisition (interruptible, non-interruptible, and timed) may differ in their performance characteristics, ordering guarantees, or other implementation qualities. Further, the ability to interrupt the ongoing acquisition of a lock may not be available in a given **Lock** (p. 2377) class. Consequently, an implementation is not required to define exactly the same guarantees or semantics for all three forms of lock acquisition, nor is it required to support interruption of an ongoing lock acquisition. An implementation is required to clearly document the semantics and guarantees provided by each of the locking methods. It must also obey the interruption semantics as defined in this interface, to the extent that interruption of lock acquisition is supported: which is either totally, or only on method entry.

As interruption generally implies cancellation, and checks for interruption are often infrequent, an implementation can favor responding to an interrupt over normal method return. This is true even if it can be shown that the interrupt occurred after another action may have unblocked the thread. An implementation should document this behavior.

Since:

1.0

6.486.2 Constructor & Destructor Documentation

6.486.2.1 `virtual decaf::util::concurrent::locks::Lock::~~Lock () [inline, virtual]`

6.486.3 Member Function Documentation

6.486.3.1 `virtual void decaf::util::concurrent::locks::Lock::lock () throw (decaf::lang::exceptions::RuntimeException) [pure virtual]`

Acquires the lock. If the lock is not available then the current thread becomes disabled for thread scheduling purposes and lies dormant until the lock has been acquired.

Implementation Considerations

A **Lock** (p. 2377) implementation may be able to detect erroneous use of the lock, such as an invocation that would cause deadlock, and may throw an exception in such circumstances. The circumstances and the exception type must be documented by that **Lock** (p. 2377) implementation.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3185).

6.486.3.2 virtual void decaf::util::concurrent::locks::Lock::lockInterruptibly () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException) [pure virtual]

Acquires the lock unless the current thread is interrupted. Acquires the lock if it is available and returns immediately.

If the lock is not available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of two things happens:

* The lock is acquired by the current thread; or * Some other thread interrupts the current thread, and interruption of lock acquisition is supported.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while acquiring the lock, and interruption of lock acquisition is supported,

then InterruptedException is thrown and the current thread's interrupted status is cleared.

Implementation Considerations

The ability to interrupt a lock acquisition in some implementations may not be possible, and if possible may be an expensive operation. The programmer should be aware that this may be the case. An implementation should document when this is the case.

An implementation can favor responding to an interrupt over normal method return.

A **Lock** (p. 2377) implementation may be able to detect erroneous use of the lock, such as an invocation that would cause deadlock, and may throw an exception in such circumstances. The circumstances and the exception type must be documented by that **Lock** (p. 2377) implementation.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

InterruptedException if the current thread is interrupted while acquiring the lock (and interruption of lock acquisition is supported).

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3185).

6.486.3.3 virtual Condition* decaf::util::concurrent::locks::Lock::newCondition () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]

Returns a new **Condition** (p. 1249) instance that is bound to this **Lock** (p. 2377) instance. Before waiting on the condition the lock must be held by the current thread. A call to **Condition.await()**

(p. 1251) will atomically release the lock before waiting and re-acquire the lock before the wait returns.

Implementation Considerations

The exact operation of the **Condition** (p. 1249) instance depends on the **Lock** (p. 2377) implementation and must be documented by that implementation.

Returns:

A new **Condition** (p. 1249) instance for this **Lock** (p. 2377) instance the caller must delete the returned **Condition** (p. 1249) object when done with it.

Exceptions:

RuntimeException if an error occurs while creating the **Condition** (p. 1249).

UnsupportedOperationException if this **Lock** (p. 2377) implementation does not support conditions

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3186).

6.486.3.4 virtual bool decaf::util::concurrent::locks::Lock::tryLock
(long long time, const TimeUnit & unit) throw
(decaf::lang::exceptions::RuntimeException, de-
caf::lang::exceptions::InterruptedException) [pure
virtual]

Acquires the lock if it is free within the given waiting time and the current thread has not been interrupted. If the lock is available this method returns immediately with the value true. If the lock is not available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

* The lock is acquired by the current thread; or * Some other thread interrupts the current thread, and interruption of lock acquisition is supported; or * The specified waiting time elapses

If the lock is acquired then the value true is returned.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while acquiring the lock, and interruption of lock acquisition is supported,

then InterruptedException is thrown and the current thread's interrupted status is cleared.

If the specified waiting time elapses then the value false is returned. If the time is less than or equal to zero, the method will not wait at all.

Implementation Considerations

The ability to interrupt a lock acquisition in some implementations may not be possible, and if possible may be an expensive operation. The programmer should be aware that this may be the case. An implementation should document when this is the case.

An implementation can favor responding to an interrupt over normal method return, or reporting a timeout.

A **Lock** (p. 2377) implementation may be able to detect erroneous use of the lock, such as an invocation that would cause deadlock, and may throw an (unchecked) exception in such circumstances. The circumstances and the exception type must be documented by that **Lock** (p. 2377) implementation.

Parameters:

time the maximum time to wait for the lock

unit the time unit of the time argument

Returns:

true if the lock was acquired and false if the waiting time elapsed before the lock was acquired

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

InterruptedException if the current thread is interrupted while acquiring the lock (and interruption of lock acquisition is supported)

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3186).

6.486.3.5 virtual bool decaf::util::concurrent::locks::Lock::tryLock () throw (decaf::lang::exceptions::RuntimeException) [pure virtual]

Acquires the lock only if it is free at the time of invocation. Acquires the lock if it is available and returns immediately with the value true. If the lock is not available then this method will return immediately with the value false.

A typical usage idiom for this method would be:

```
Lock (p. 2377) lock = ...; if (lock.tryLock()) { try { // manipulate protected state } catch(...) { lock.unlock(); } } else { // perform alternative actions }
```

This usage ensures that the lock is unlocked if it was acquired, and doesn't try to unlock if the lock was not acquired.

Returns:

true if the lock was acquired and false otherwise

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3187).

6.486.3.6 virtual void decaf::util::concurrent::locks::Lock::unlock () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [pure virtual]

Releases the lock. Implementation Considerations

A **Lock** (p. 2377) implementation will usually impose restrictions on which thread can release a lock (typically only the holder of the lock can release it) and may throw an exception if the restriction is violated. Any restrictions and the exception type must be documented by that **Lock** (p. 2377) implementation.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

IllegalMonitorStateException if the current thread is not the owner of the lock.

Implemented in **decaf::util::concurrent::locks::ReentrantLock** (p. 3188).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/locks/`**Lock.h**

6.487 decaf::util::concurrent::locks::LockSupport Class Reference

Basic thread blocking primitives for creating **locks** (p.174) and other synchronization classes.

```
#include <src/main/decaf/util/concurrent/locks/LockSupport.h>
```

Public Member Functions

- `~LockSupport ()`

Static Public Member Functions

- static void **unpark** (decaf::lang::Thread *thread) throw ()
Makes available the permit for the given thread, if it was not already available.
- static void **park** () throw ()
Disables the current thread for thread scheduling purposes unless the permit is available.
- static void **parkNanos** (long long nanos) throw ()
Disables the current thread for thread scheduling purposes, for up to the specified waiting time, unless the permit is available.
- static void **parkUntil** (long long deadline) throw ()
Disables the current thread for thread scheduling purposes, until the specified deadline, unless the permit is available.

6.487.1 Detailed Description

Basic thread blocking primitives for creating **locks** (p.174) and other synchronization classes. This class associates, with each thread that uses it, a permit (in the sense of the **Semaphore** (p.3341) class). A call to **park** will return immediately if the permit is available, consuming it in the process; otherwise it may block. A call to **unpark** makes the permit available, if it was not already available. (Unlike with Semaphores though, permits do not accumulate. There is at most one.)

Methods **park** and **unpark** provide efficient means of blocking and unblocking threads. Races between one thread invoking **park** and another thread trying to **unpark** it will preserve liveness, due to the permit. Additionally, **park** will return if the caller's thread was interrupted, and timeout versions are supported. The **park** method may also return at any other time, for "no reason", so in general must be invoked within a loop that rechecks conditions upon return. In this sense **park** serves as an optimization of a "busy wait" that does not waste as much time spinning, but must be paired with an **unpark** to be effective.

These methods are designed to be used as tools for creating higher-level synchronization utilities, and are not in themselves useful for most concurrency control applications. The **park** method is designed for use only in constructions of the form:

```
while (!canProceed()) { ... LockSupport.park(this); }
```

where neither `canProceed` nor any other actions prior to the call to `park` entail locking or blocking. Because only one permit is associated with each thread, any intermediary uses of `park` could interfere with its intended effects.

Sample Usage. Here is a sketch of a first-in-first-out non-reentrant lock class:

```
class FIFOMutex { private:
AtomicBoolean locked; ConcurrentLinkedQueue<Thread*> waiters;
public:
void lock() {
bool wasInterrupted = false; Thread* current = Thread::currentThread(); waiters.add( current );
// Block while not first in queue or cannot acquire lock while( waiters.peek() != current ||
!locked.compareAndSet( false, true ) ) {
LockSupport.park(this); if( Thread::interrupted() ) // ignore interrupts while waiting wasInter-
rupted = true; }
waiters.remove(); if( wasInterrupted ) // reassert interrupt status on exit current.interrupt(); }
void unlock() { locked.set( false ); LockSupport.unpark (p. 2385)( waiters.peek() ); } };
```

Since:

1.0

6.487.2 Constructor & Destructor Documentation

6.487.2.1 `decaf::util::concurrent::locks::LockSupport::~~LockSupport ()`

6.487.3 Member Function Documentation

6.487.3.1 `static void decaf::util::concurrent::locks::LockSupport::park () throw ()` [static]

Disables the current thread for thread scheduling purposes unless the permit is available. If the permit is available then it is consumed and the call returns immediately; otherwise the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

- * Some other thread invokes `unpark` with the current thread as the target; or
- * Some other thread interrupts the current thread; or
- * The call spuriously (that is, for no reason) returns.

This method does not report which of these caused the method to return. Callers should re-check the conditions which caused the thread to park in the first place. Callers may also determine, for example, the interrupt status of the thread upon return.

6.487.3.2 `static void decaf::util::concurrent::locks::LockSupport::parkNanos (long long nanos) throw ()` [static]

Disables the current thread for thread scheduling purposes, for up to the specified waiting time, unless the permit is available. If the permit is available then it is consumed and the call returns immediately; otherwise the current thread becomes disabled for thread scheduling purposes and lies dormant until one of four things happens:

* Some other thread invokes `unpark` with the current thread as the target; or * Some other thread interrupts the current thread; or * The specified waiting time elapses; or * The call spuriously (that is, for no reason) returns.

This method does not report which of these caused the method to return. Callers should re-check the conditions which caused the thread to park in the first place. Callers may also determine, for example, the interrupt status of the thread, or the elapsed time upon return.

Parameters:

nanos the maximum number of nanoseconds to wait

6.487.3.3 static void decaf::util::concurrent::locks::LockSupport::parkUntil (long long *deadline*) throw () [static]

Disables the current thread for thread scheduling purposes, until the specified deadline, unless the permit is available. If the permit is available then it is consumed and the call returns immediately; otherwise the current thread becomes disabled for thread scheduling purposes and lies dormant until one of four things happens:

* Some other thread invokes `unpark` with the current thread as the target; or * Some other thread interrupts the current thread; or * The specified deadline passes; or * The call spuriously (that is, for no reason) returns.

This method does not report which of these caused the method to return. Callers should re-check the conditions which caused the thread to park in the first place. Callers may also determine, for example, the interrupt status of the thread, or the current time upon return.

Parameters:

deadline the absolute time, in milliseconds from the Epoch, to wait until

6.487.3.4 static void decaf::util::concurrent::locks::LockSupport::unpark (decaf::lang::Thread * *thread*) throw () [static]

Makes available the permit for the given thread, if it was not already available. If the thread was blocked on `park` then it will unblock. Otherwise, its next call to `park` is guaranteed not to block. This operation is not guaranteed to have any effect at all if the given thread has not been started.

Parameters:

thread the thread to unpark, or NULL in which case the method has no effect.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/locks/LockSupport.h`

6.488 decaf::util::logging::Logger Class Reference

A **Logger** (p. 2386) object is used to log messages for a specific system or application component.

```
#include <src/main/decaf/util/logging/Logger.h>
```

Public Member Functions

- virtual **~Logger** ()
- const std::string & **getName** () const
*Gets the name of this **Logger** (p. 2386).*
- **Logger** * **getParent** () const
*Gets the parent of this **Logger** (p. 2386) which will be the nearest existing **Logger** (p. 2386) in this Loggers namespace.*
- void **setParent** (**Logger** *parent)
*Set (p. 3439) the parent for this **Logger** (p. 2386).*
- void **addHandler** (**Handler** *handler) throw (lang::exceptions::NullPointerException)
*Add a log **Handler** (p. 1978) to receive **logging** (p. 175) messages.*
- void **removeHandler** (**Handler** *handler)
*Removes the specified **Handler** (p. 1978) from this logger, ownership of the **Handler** (p. 1978) pointer is returned to the caller.*
- const std::list< **Handler** * > & **getHandlers** () const
Gets a vector containing all the handlers that this class has been assigned to use.
- void **setFilter** (**Filter** *filter)
*Set (p. 3439) a filter to control output on this **Logger** (p. 2386).*
- const **Filter** * **getFilter** () const
*Gets the **Filter** (p. 1893) object that this class is using.*
- **Level** **getLevel** () const
*Get the log **Level** (p. 2332) that has been specified for this **Logger** (p. 2386).*
- void **setLevel** (const **Level** &level)
Set (p. 3439) the log level specifying which message levels will be logged by this logger.
- bool **getUseParentHandlers** () const
Discover whether or not this logger is sending its output to its parent logger.
- void **setUseParentHandlers** (bool value)
*Specify whether or not this logger should send its output to it's parent **Logger** (p. 2386).*
- virtual void **entering** (const std::string &blockName, const std::string &file, const int line)
*Logs an **Block Enter** message.*

- virtual void **exiting** (const std::string &blockName, const std::string &file, const int line)
Logs an Block Exit message.
- virtual void **severe** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a SEVERE Level (p. 2332) Log.
- virtual void **warning** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a WARN Level (p. 2332) Log.
- virtual void **info** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a INFO Level (p. 2332) Log.
- virtual void **debug** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a DEBUG Level (p. 2332) Log.
- virtual void **config** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a CONFIG Level (p. 2332) Log.
- virtual void **fine** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a FINE Level (p. 2332) Log.
- virtual void **finer** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a FINER Level (p. 2332) Log.
- virtual void **finest** (const std::string &file, const int line, const std::string functionName, const std::string &message)
Log a FINEST Level (p. 2332) Log.
- virtual void **throwing** (const std::string &file, const int line, const std::string functionName, const decaf::lang::Throwable &thrown)
Log throwing an exception.
- virtual bool **isLoggable** (const Level &level) const
Check if a message of the given level would actually be logged by this logger.
- virtual void **log** (LogRecord &record)
Log a LogRecord (p. 2413).
- virtual void **log** (const Level &level, const std::string &message)
Log a message, with no arguments.
- virtual void **log** (const Level &levels, const std::string &file, const int line, const std::string &message,...)
Log a message, with the list of params that is formatted into the message string.

- virtual void **log** (const **Level** &level, const std::string &file, const int line, const std::string &message, **lang::Exception** &ex)

Log a message, with associated Throwable information.

Static Public Member Functions

- static **Logger** * **getAnonymousLogger** ()
Creates an anonymous logger.
- static **Logger** * **getLogger** (const std::string &name)
Find or create a logger for a named subsystem.

Protected Member Functions

- **Logger** (const std::string &name)
*Creates a new instance of the **Logger** (p. 2386) with the given name.*

6.488.1 Detailed Description

A **Logger** (p. 2386) object is used to log messages for a specific system or application component. Loggers are normally named, using a hierarchical dot-separated namespace. **Logger** (p. 2386) names can be arbitrary strings, but they should normally be based on the namespace or class name of the logged component, such as **decaf.net** (p. 160) or **org.apache.decaf**. In addition it is possible to create "anonymous" Loggers that are not stored in the **Logger** (p. 2386) namespace.

Logger (p. 2386) objects may be obtained by calls on one of the **getLogger** factory methods. These will either create a new **Logger** (p. 2386) or return a suitable existing **Logger** (p. 2386).

Logging messages will be forwarded to registered **Handler** (p. 1978) objects, which can forward the messages to a variety of destinations, including consoles, files, OS logs, etc.

Each **Logger** (p. 2386) keeps track of a "parent" **Logger** (p. 2386), which is its nearest existing ancestor in the **Logger** (p. 2386) namespace.

Each **Logger** (p. 2386) has a "Level" associated with it. This reflects a minimum **Level** (p. 2332) that this logger cares about. If a Logger's level is set to **Level::INHERIT** (p. 2336), then its effective level is inherited from its parent, which may in turn obtain it recursively from its parent, and so on up the tree.

The log level can be configured based on the properties from the **logging** (p. 175) configuration file, as described in the description of the **LogManager** (p. 2406) class. However it may also be dynamically changed by calls on the **Logger.setLevel** (p. 2395) method. If a logger's level is changed the change may also affect child loggers, since any child logger that has 'inherit' as its level will inherit its effective level from its parent.

On each **logging** (p. 175) call the **Logger** (p. 2386) initially performs a cheap check of the request level (e.g. SEVERE or FINE) against the effective log level of the logger. If the request level is lower than the log level, the **logging** (p. 175) call returns immediately.

After passing this initial (cheap) test, the **Logger** (p. 2386) will allocate a **LogRecord** (p. 2413) to describe the **logging** (p. 175) message. It will then call a **Filter** (p. 1893) (if present) to do a

more detailed check on whether the record should be published. If that passes it will then publish the **LogRecord** (p. 2413) to its output **Handlers**. By default, loggers also publish to their parent's **Handlers**, recursively up the tree.

Formatting is the responsibility of the output **Handler** (p. 1978), which will typically call a **Formatter** (p. 1964).

Note that formatting need not occur synchronously. It may be delayed until a **LogRecord** (p. 2413) is actually written to an external sink.

All methods on **Logger** (p. 2386) are thread safe.

Since:

1.0

6.488.2 Constructor & Destructor Documentation

6.488.2.1 decaf::util::logging::Logger::Logger (const std::string & *name*) [protected]

Creates a new instance of the **Logger** (p. 2386) with the given name. The logger will be initially configured with a null **Level** (p. 2332) and with useParentHandlers true.

Parameters:

name A name for the logger. This should be a dot-separated name and should normally be based on the package name or class name of the subsystem, such as **decaf.net** (p. 160) or org.apache.decaf. It may be empty for anonymous Loggers.

6.488.2.2 virtual decaf::util::logging::Logger::~~Logger () [virtual]

6.488.3 Member Function Documentation

6.488.3.1 void decaf::util::logging::Logger::addHandler (Handler * *handler*) throw (lang::exceptions::NullPointerException)

Add a log **Handler** (p. 1978) to receive **logging** (p. 175) messages. By default, Loggers also send their output to their parent logger. Typically the root **Logger** (p. 2386) is configured with a set of **Handlers** that essentially act as default handlers for all loggers.

The ownership of the given **Handler** (p. 1978) is passed to the **Logger** (p. 2386) and the **Handler** (p. 1978) will be deleted when this **Logger** (p. 2386) is destroyed unless the caller first calls **removeHandler** with the same pointer value as was originally given.

Parameters:

handler A Logging **Handler** (p. 1978)

Exceptions:

NullPointerException if the **Handler** (p. 1978) given is NULL.

6.488.3.2 `virtual void decaf::util::logging::Logger::config (const std::string & file,
const int line, const std::string functionName, const std::string &
message)` [virtual]

Log a CONFIG **Level** (p. 2332) Log. If the logger is currently enabled for the CONFIG message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects.

Parameters:

file The file name where the log was generated.
line The line number where the log was generated.
functionName The name of the function that logged this.
message The message to log at this **Level** (p. 2332).

6.488.3.3 `virtual void decaf::util::logging::Logger::debug (const std::string & file,
const int line, const std::string functionName, const std::string &
message)` [virtual]

Log a DEBUG **Level** (p. 2332) Log. If the logger is currently enabled for the DEBUG message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects.

Parameters:

file The file name where the log was generated.
line The line number where the log was generated.
functionName The name of the function that logged this.
message The message to log at this **Level** (p. 2332).

6.488.3.4 `virtual void decaf::util::logging::Logger::entering (const std::string &
blockName, const std::string & file, const int line)` [virtual]

Logs an Block Enter message. This is a convenience method that is used to tag a block enter, a log record with the given information is logged at the **Level::FINER** (p. 2335) log level.

Parameters:

blockName The source block name, (usually ClassName::MethodName, or MethodName).
file The source file name where this method was called from.
line The source line number where this method was called from.

6.488.3.5 `virtual void decaf::util::logging::Logger::exiting (const std::string &
blockName, const std::string & file, const int line)` [virtual]

Logs an Block Exit message. This is a convenience method that is used to tag a block enter, a log record with the given information is logged at the **Level::FINER** (p. 2335) log level.

Parameters:

blockName The source block name, (usually ClassName::MethodName, or MethodName).
file The source file name where this method was called from.
line The source line number where this method was called from.

6.488.3.6 virtual void decaf::util::logging::Logger::fine (const std::string & *file*, const int *line*, const std::string *functionName*, const std::string & *message*) [virtual]

Log a FINE **Level** (p.2332) Log. If the logger is currently enabled for the FINE message level then the given message is forwarded to all the registered output **Handler** (p.1978) objects.

Parameters:

file The file name where the log was generated.
line The line number where the log was generated.
functionName The name of the function that logged this.
message The message to log at this **Level** (p.2332).

6.488.3.7 virtual void decaf::util::logging::Logger::finer (const std::string & *file*, const int *line*, const std::string *functionName*, const std::string & *message*) [virtual]

Log a FINER **Level** (p.2332) Log. If the logger is currently enabled for the FINER message level then the given message is forwarded to all the registered output **Handler** (p.1978) objects.

Parameters:

file The file name where the log was generated.
line The line number where the log was generated.
functionName The name of the function that logged this.
message The message to log at this **Level** (p.2332).

6.488.3.8 virtual void decaf::util::logging::Logger::finest (const std::string & *file*, const int *line*, const std::string *functionName*, const std::string & *message*) [virtual]

Log a FINEST **Level** (p.2332) Log. If the logger is currently enabled for the FINEST message level then the given message is forwarded to all the registered output **Handler** (p.1978) objects.

Parameters:

file The file name where the log was generated.
line The line number where the log was generated.
functionName The name of the function that logged this.
message The message to log at this **Level** (p.2332).

6.488.3.9 static Logger* decaf::util::logging::Logger::getAnonymousLogger () [static]

Creates an anonymous logger. The newly created **Logger** (p.2386) is not registered in the **Log-Manager** (p.2406) namespace. There will be no access checks on updates to the logger. Even although the new logger is anonymous, it is configured to have the root logger ("") as its parent. This means that by default it inherits its effective level and handlers from the root logger.

The caller is responsible for destroying the returned logger.

Returns:

Newly created anonymous logger

6.488.3.10 `const Filter* decaf::util::logging::Logger::getFilter () const [inline]`

Gets the **Filter** (p. 1893) object that this class is using.

Returns:

the **Filter** (p. 1893) in use, (can be NULL).

6.488.3.11 `const std::list<Handler*>& decaf::util::logging::Logger::getHandlers () const`

Gets a vector containing all the handlers that this class has been assigned to use.

Returns:

a list of handlers that are used by this logger

6.488.3.12 `Level decaf::util::logging::Logger::getLevel () const [inline]`

Get the log **Level** (p. 2332) that has been specified for this **Logger** (p. 2386). The result may be the INHERIT level, which means that this logger's effective level will be inherited from its parent.

Returns:

the level that is currently set

6.488.3.13 `static Logger* decaf::util::logging::Logger::getLogger (const std::string & name) [static]`

Find or create a logger for a named subsystem. If a logger has already been created with the given name it is returned. Otherwise a new logger is created.

If a new logger is created its log level will be configured based on the **LogManager** (p. 2406) and it will be configured to also send **logging** (p. 175) output to its parent loggers Handlers. It will be registered in the **LogManager** (p. 2406) global namespace.

Parameters:

name - A name for the logger. This should be a dot-separated name and should normally be based on the package name or class name of the subsystem, such as **cms** (p. 140) or **activemq.core.ActiveMQConnection** (p. 273)

Returns:

a suitable logger.

6.488.3.14 `const std::string& decaf::util::logging::Logger::getName () const [inline]`

Gets the name of this **Logger** (p. 2386).

Returns:

logger name

6.488.3.15 `Logger* decaf::util::logging::Logger::getParent () const [inline]`

Gets the parent of this **Logger** (p. 2386) which will be the nearest existing **Logger** (p. 2386) in this Loggers namespace. If this is the Root **Logger** (p. 2386) than this method returns NULL.

Returns:

Pointer to this Loggers nearest parent **Logger** (p. 2386).

6.488.3.16 `bool decaf::util::logging::Logger::getUseParentHandlers () const [inline]`

Discover whether or not this logger is sending its output to its parent logger.

Returns:

true if using Parent Handlers

6.488.3.17 `virtual void decaf::util::logging::Logger::info (const std::string & file, const int line, const std::string functionName, const std::string & message) [virtual]`

Log a INFO **Level** (p. 2332) Log. If the logger is currently enabled for the INFO message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects.

Parameters:

file The file name where the log was generated.

line The line number where the log was generated.

functionName The name of the function that logged this.

message The message to log at this **Level** (p. 2332).

6.488.3.18 `virtual bool decaf::util::logging::Logger::isLoggable (const Level & level) const [virtual]`

Check if a message of the given level would actually be logged by this logger. This check is based on the Loggers effective level, which may be inherited from its parent.

Parameters:

level - a message **logging** (p. 175) level

Returns:

true if the given message level is currently being logged.

6.488.3.19 `virtual void decaf::util::logging::Logger::log (const Level & level,
const std::string & file, const int line, const std::string & message,
lang::Exception & ex) [virtual]`

Log a message, with associated Throwable information. If the logger is currently enabled for the given message level then the given arguments are stored in a **LogRecord** (p. 2413) which is forwarded to all registered output handlers. Note that the thrown argument is stored in the **LogRecord** (p. 2413) thrown property, rather than the **LogRecord** (p. 2413) parameters property. Thus is it processed specially by output Formatters and is not treated as a formatting parameter to the **LogRecord** (p. 2413) message property.

Parameters:

level the **Level** (p. 2332) to log at.

file File that the message was logged in.

line the line number where the message was logged at.

message the message to log.

ex the Exception to log

6.488.3.20 `virtual void decaf::util::logging::Logger::log (const Level & levels, const
std::string & file, const int line, const std::string & message, ...)
[virtual]`

Log a message, with the list of params that is formatted into the message string. If the logger is currently enabled for the given message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects

Parameters:

level the **Level** (p. 2332) to log at

file the message to log

line the line in the file

... variable length argument to format the message string.

6.488.3.21 `virtual void decaf::util::logging::Logger::log (const Level & level, const
std::string & message) [virtual]`

Log a message, with no arguments. If the logger is currently enabled for the given message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects

Parameters:

level the **Level** (p. 2332) to log at

message the message to log

6.488.3.22 virtual void decaf::util::logging::Logger::log (LogRecord & *record*)
[virtual]

Log a **LogRecord** (p. 2413). All the other **logging** (p. 175) methods in this class call through this method to actually perform any **logging** (p. 175). Subclasses can override this single method to capture all log activity.

Parameters:

record - the **LogRecord** (p. 2413) to be published

6.488.3.23 void decaf::util::logging::Logger::removeHandler (Handler * *handler*)

Removes the specified **Handler** (p. 1978) from this logger, ownership of the **Handler** (p. 1978) pointer is returned to the caller. Returns silently if the given **Handler** (p. 1978) is not found.

Parameters:

handler The **Handler** (p. 1978) to remove

6.488.3.24 void decaf::util::logging::Logger::setFilter (Filter * *filter*)

Set (p. 3439) a filter to control output on this **Logger** (p. 2386). After passing the initial "level" check, the **Logger** (p. 2386) will call this **Filter** (p. 1893) to check if a log record should really be published.

The caller releases ownership of this filter to this logger

Parameters:

filter The **Filter** (p. 1893) to use, (can be NULL).

6.488.3.25 void decaf::util::logging::Logger::setLevel (const Level & *level*) [inline]

Set (p. 3439) the log level specifying which message levels will be logged by this logger. Message levels lower than this value will be discarded. The level value **Level::OFF** (p. 2336) can be used to turn off **logging** (p. 175).

If the new level is the **INHERIT Level** (p. 2332), it means that this node should inherit its level from its nearest ancestor with a specific (non-**INHERIT**) level value.

Parameters:

level The new **Level** (p. 2332) value to use when **logging** (p. 175).

6.488.3.26 void decaf::util::logging::Logger::setParent (Logger * *parent*) [inline]

Set (p. 3439) the parent for this **Logger** (p. 2386). This method is used by the **LogManager** (p. 2406) to update a **Logger** (p. 2386) when the namespace changes.

It should not be called from application **code** (p. 1183).

6.488.3.27 `void decaf::util::logging::Logger::setUseParentHandlers (bool value)`
[inline]

Specify whether or not this logger should send its output to its parent **Logger** (p. 2386). This means that any LogRecords will also be written to the parent's Handlers, and potentially to its parent, recursively up the namespace.

Parameters:

value True is output is to be written to the parent

6.488.3.28 `virtual void decaf::util::logging::Logger::severe (const std::string & file,
const int line, const std::string functionName, const std::string &
message)` [virtual]

Log a SEVERE **Level** (p. 2332) Log. If the logger is currently enabled for the SEVERE message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects.

Parameters:

file The file name where the log was generated.

line The line number where the log was generated.

functionName The name of the function that logged this.

message The message to log at this **Level** (p. 2332).

6.488.3.29 `virtual void decaf::util::logging::Logger::throwing (const std::string
& file, const int line, const std::string functionName, const
decaf::lang::Throwable & thrown)` [virtual]

Log throwing an exception. This is a convenience method to log that a method is terminating by throwing an exception. The **logging** (p. 175) is done using the FINER level.

If the logger is currently enabled for the given message level then the given arguments are stored in a **LogRecord** (p. 2413) which is forwarded to all registered output handlers. The LogRecord's message is set to "THROW".

Parameters:

file The file name where the log was generated.

line The line number where the log was generated.

functionName The name of the function that logged this.

thrown The Throwable that will be thrown, will be cloned.

6.488.3.30 `virtual void decaf::util::logging::Logger::warning (const std::string &
file, const int line, const std::string functionName, const std::string &
message)` [virtual]

Log a WARN **Level** (p. 2332) Log. If the logger is currently enabled for the WARN message level then the given message is forwarded to all the registered output **Handler** (p. 1978) objects.

Parameters:

- file* The file name where the log was generated.
- line* The line number where the log was generated.
- functionName* The name of the function that logged this.
- message* The message to log at this **Level** (p. 2332).

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**Logger.h**

6.489 decaf::util::logging::LoggerHierarchy Class Reference

```
#include <src/main/decaf/util/logging/LoggerHierarchy.h>
```

Public Member Functions

- **LoggerHierarchy** ()
- virtual **~LoggerHierarchy** ()

6.489.1 Constructor & Destructor Documentation

6.489.1.1 decaf::util::logging::LoggerHierarchy::LoggerHierarchy ()

6.489.1.2 virtual decaf::util::logging::LoggerHierarchy::~~LoggerHierarchy ()
[virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**LoggerHierarchy.h**

6.490 activemq::io::LoggingInputStream Class Reference

#include <src/main/activemq/io/LoggingInputStream.h> Inheritance diagram for activemq::io::LoggingInputStream:

Public Member Functions

- **LoggingInputStream** (decaf::io::InputStream *inputStream, bool own=false)
Creates a DataInputStream that uses the specified underlying InputStream.
- virtual ~**LoggingInputStream** ()

Protected Member Functions

- virtual int **doReadByte** () throw (decaf::io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.490.1 Constructor & Destructor Documentation

6.490.1.1 activemq::io::LoggingInputStream::LoggingInputStream (decaf::io::InputStream * inputStream, bool own = false)

Creates a DataInputStream that uses the specified underlying InputStream.

Parameters:

- inputStream* the InputStream instance to wrap.
- own* indicates if this class owns the wrapped string defaults to false.

6.490.1.2 virtual activemq::io::LoggingInputStream::~~LoggingInputStream () [virtual]

6.490.2 Member Function Documentation

6.490.2.1 virtual int activemq::io::LoggingInputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from decaf::io::FilterInputStream (p.1897).

6.490.2.2 `virtual int activemq::io::LoggingInputStream::doReadByte () throw (decaf::io::IOException)` [protected, virtual]

Reimplemented from `decaf::io::FilterInputStream` (p.1897).

The documentation for this class was generated from the following file:

- `src/main/activemq/io/LoggingInputStream.h`

6.491 activemq::io::LoggingOutputStream Class Reference

OutputStream filter that just logs the data being written.

#include <src/main/activemq/io/LoggingOutputStream.h> Inheritance diagram for activemq::io::LoggingOutputStream:

Public Member Functions

- **LoggingOutputStream** (OutputStream *next, bool **own**=false)
Constructor.
- virtual ~**LoggingOutputStream** ()

Protected Member Functions

- virtual void **doWriteByte** (unsigned char c) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.491.1 Detailed Description

OutputStream filter that just logs the data being written.

6.491.2 Constructor & Destructor Documentation

6.491.2.1 activemq::io::LoggingOutputStream::LoggingOutputStream (OutputStream * next, bool own = false)

Constructor.

Parameters:

- next* The OutputStream to wrap an write logs to.
- own* If true, this object will control the lifetime of the output stream that it encapsulates.

6.491.2.2 virtual activemq::io::LoggingOutputStream::~~LoggingOutputStream () [virtual]

6.491.3 Member Function Documentation

6.491.3.1 virtual void activemq::io::LoggingOutputStream::doWriteArrayBounded (const unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented from decaf::io::FilterOutputStream (p. 1902).

6.491.3.2 `virtual void activemq::io::LoggingOutputStream::doWriteByte (unsigned char c) throw (decaf::io::IOException)` [protected, virtual]

Reimplemented from `decaf::io::FilterOutputStream` (p. 1902).

The documentation for this class was generated from the following file:

- `src/main/activemq/io/LoggingOutputStream.h`

6.492 activemq::transport::logging::LoggingTransport Class Reference

A **transport** (p. 97) filter that logs **commands** (p. 87) as they are sent/received.

#include <src/main/activemq/transport/logging/LoggingTransport.h> Inheritance diagram for activemq::transport::logging::LoggingTransport:

Public Member Functions

- **LoggingTransport** (const **Pointer**< **Transport** > &next)

Constructor.

- virtual ~**LoggingTransport** ()
- virtual void **onCommand** (const **Pointer**< **Command** > &command)

Event handler for the receipt of a command.

- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Sends a one-way command.

- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Not supported by this class - throws an exception.

- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Not supported by this class - throws an exception.

6.492.1 Detailed Description

A **transport** (p. 97) filter that logs **commands** (p. 87) as they are sent/received.

6.492.2 Constructor & Destructor Documentation

6.492.2.1 activemq::transport::logging::LoggingTransport::LoggingTransport (const **Pointer**< **Transport** > & next)

Constructor.

Parameters:

next - the next **Transport** (p. 3883) in the chain

6.492.2.2 `virtual`
`activemq::transport::logging::LoggingTransport::~~LoggingTransport ()`
`[inline, virtual]`

6.492.3 Member Function Documentation

6.492.3.1 `virtual void activemq::transport::logging::LoggingTransport::onCommand`
`(const Pointer< Command > & command) [virtual]`

Event handler for the receipt of a command.

Parameters:

command - the received command object.

Reimplemented from `activemq::transport::TransportFilter` (p. 3895).

6.492.3.2 `virtual void activemq::transport::logging::LoggingTransport::oneway`
`(const Pointer< Command > & command) throw (decaf::io::IOException,`
`decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this `transport` (p. 97).

Reimplemented from `activemq::transport::TransportFilter` (p. 3895).

6.492.3.3 `virtual Pointer<Response> ac-`
`tivemq::transport::logging::LoggingTransport::request`
`(const Pointer< Command > & command, un-`
`signed int timeout) throw (decaf::io::IOException,`
`decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Not supported by this class - throws an exception.

Parameters:

command the command that is sent as a request

timeout the time to wait for a response.

Exceptions:

UnsupportedOperationException.

Reimplemented from `activemq::transport::TransportFilter` (p. 3896).

6.492.3.4 virtual `Pointer<Response>` `activemq::transport::logging::LoggingTransport::request` (`const Pointer< Command > & command`) throw (`decaf::io::IOException`, `decaf::lang::exceptions::UnsupportedOperationException`) [virtual]

Not supported by this class - throws an exception.

Parameters:

command the command that is sent as a request

Exceptions:

UnsupportedOperationException.

Reimplemented from `activemq::transport::TransportFilter` (p. 3897).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/logging/LoggingTransport.h`

6.493 decaf::util::logging::LogManager Class Reference

There is a single global **LogManager** (p.2406) object that is used to maintain a set of shared state about Loggers and log services.

```
#include <src/main/decaf/util/logging/LogManager.h>
```

Public Member Functions

- virtual **~LogManager** ()
- bool **addLogger** (**Logger** *logger) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Add a named logger.
- **Logger** * **getLogger** (const std::string &name)
*Retrieves or creates a new **Logger** (p.2386) using the name specified a new logger inherits the configuration of the logger's parent if there is no configuration data for the logger.*
- int **getLoggerNames** (const std::vector< std::string > &names)
*Gets a list of known **Logger** (p.2386) Names from this Manager, new loggers added while this method is in progress are not guaranteed to be in the list.*
- void **setProperties** (const **util::Properties** &properties)
*Sets the **Properties** (p.3126) this **LogManager** (p.2406) should use to configure its loggers.*
- const **util::Properties** & **getProperties** () const
*Gets a reference to the Logging **Properties** (p.3126) used by this logger.*
- std::string **getProperty** (const std::string &name)
*Gets the value of a named property of this **LogManager** (p.2406).*
- void **addPropertyChangeListener** (PropertyChangeListener *listener)
*Adds a change listener for **LogManager** (p.2406) **Properties** (p.3126), adding the same instance of a change event listener does nothing.*
- void **removePropertyChangeListener** (PropertyChangeListener *listener)
*Removes a properties change listener from the **LogManager** (p.2406), if the listener is not found of the param is NULL this method returns silently.*
- void **readConfiguration** () throw (decaf::io::IOException)
*Reinitialize the **logging** (p.175) properties and reread the **logging** (p.175) configuration.*
- void **readConfiguration** (decaf::io::InputStream *stream) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
*Reinitialize the **logging** (p.175) properties and reread the **logging** (p.175) configuration from the given stream, which should be in **decaf.util.Properties** (p.3126) format.*
- void **reset** ()
*Reset the **logging** (p.175) configuration.*

Static Public Member Functions

- static **LogManager** & **getLogManager** ()
*Get the global **LogManager** (p. 2406) instance.*

Protected Member Functions

- **LogManager** ()
Constructor, hidden to protect against direct instantiation.
- **LogManager** (const **LogManager** &manager)
Copy Constructor.
- void **operator=** (const **LogManager** &manager)
Assignment operator.

Friends

- class **decaf::lang::Runtime**

6.493.1 Detailed Description

There is a single global **LogManager** (p. 2406) object that is used to maintain a set of shared state about Loggers and log services. This **LogManager** (p. 2406) object:

* Manages a hierarchical namespace of **Logger** (p. 2386) objects. All named Loggers are stored in this namespace. * Manages a set of **logging** (p. 175) control properties. These are simple key-value pairs that can be used by Handlers and other **logging** (p. 175) objects to configure themselves.

The global **LogManager** (p. 2406) object can be retrieved using **LogManager::getLogManager()** (p. 2410). The **LogManager** (p. 2406) object is created during class initialization and cannot subsequently be changed.

TODO By default, the **LogManager** (p. 2406) reads its initial configuration from a properties file "lib/logging.properties" in the JRE directory. If you edit that property file you can change the default **logging** (p. 175) configuration for all uses of that JRE.

In addition, the **LogManager** (p. 2406) uses two optional system properties that allow more control over reading the initial configuration:

* "decaf.logger.config.class" * "decaf.logger.config.file"

These two properties may be set via the Preferences API, or as command line property definitions to the "java" command, or as system property definitions passed to JNI_CreateJavaVM.

If the "java.util.logging.config.class" property is set, then the property value is treated as a class name. The given class will be loaded, an object will be instantiated, and that object's constructor is responsible for reading in the initial configuration. (That object may use other system properties to control its configuration.) The alternate configuration class can use readConfiguration(InputStream) to define properties in the **LogManager** (p. 2406).

If "decaf.util.logging.config.class" property is not set, then the "decaf.util.logging.config.file" system property can be used to specify a properties file (in **decaf.util.Properties** (p. 3126) format). The initial **logging** (p. 175) configuration will be read from this file.

If neither of these properties is defined then, as described above, the **LogManager** (p. 2406) will read its initial configuration from a properties file "lib/logging.properties" in the working directory.

The properties for loggers and Handlers will have names starting with the dot-separated name for the handler or logger. ***TODO***

The global **logging** (p. 175) properties may include:

- * A property "handlers". This defines a whitespace separated list of class names for handler classes to load and register as handlers on the root **Logger** (p. 2386) (the **Logger** (p. 2386) named ""). Each class name must be for a **Handler** (p. 1978) class which has a default constructor. Note that these Handlers may be created lazily, when they are first used.
- * A property "<logger>.handlers". This defines a whitespace or comma separated list of class names for handlers classes to load and register as handlers to the specified logger. Each class name must be for a **Handler** (p. 1978) class which has a default constructor. Note that these Handlers may be created lazily, when they are first used.
- * A property "<logger>.useParentHandlers". This defines a boolean value. By default every logger calls its parent in addition to handling the **logging** (p. 175) message itself, this often result in messages being handled by the root logger as well. When setting this property to false a **Handler** (p. 1978) needs to be configured for this logger otherwise no **logging** (p. 175) messages are delivered.
- * A property "config". This property is intended to allow arbitrary configuration **code** (p. 1183) to be run. The property defines a whitespace separated list of class names. A new instance will be created for each named class. The default constructor of each class may execute arbitrary **code** (p. 1183) to update the **logging** (p. 175) configuration, such as setting logger levels, adding handlers, adding filters, etc.

Loggers are organized into a naming hierarchy based on their dot separated names. Thus "a.b.c" is a child of "a.b", but "a.b1" and a.b2 are peers.

All properties whose names end with ".level" are assumed to define log levels for Loggers. Thus "foo.level" defines a log level for the logger called "foo" and (recursively) for any of its children in the naming hierarchy. Log Levels are applied in the order they are defined in the properties file. Thus level settings for child nodes in the tree should come after settings for their parents. The property name ".level" can be used to set the level for the root of the tree.

All methods on the **LogManager** (p. 2406) object are multi-thread safe.

Since:

1.0

6.493.2 Constructor & Destructor Documentation

6.493.2.1 `virtual decaf::util::logging::LogManager::~~LogManager ()` [virtual]

6.493.2.2 `decaf::util::logging::LogManager::LogManager ()` [protected]

Constructor, hidden to protect against direct instantiation.

6.493.2.3 `decaf::util::logging::LogManager::LogManager (const LogManager & manager)` [protected]

Copy Constructor.

Parameters:

manager the Manager to copy

6.493.3 Member Function Documentation

6.493.3.1 `bool decaf::util::logging::LogManager::addLogger (Logger *
logger) throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException)`

Add a named logger. This does nothing and returns false if a logger with the same name is already registered.

The **Logger** (p. 2386) factory methods call this method to register each newly created **Logger** (p. 2386).

Parameters:

logger The new **Logger** (p. 2386) instance to add to this **LogManager** (p. 2406).

Exceptions:

NullPointerException if logger is NULL.

IllegalArgumentException if the logger has no name.

6.493.3.2 `void decaf::util::logging::LogManager::addPropertyChangeListener
(PropertyChangeListener * listener)`

Adds a change listener for **LogManager** (p. 2406) **Properties** (p. 3126), adding the same instance of a change event listener does nothing.

Parameters:

listener The PropertyChangeListener to add (can be NULL).

6.493.3.3 `Logger* decaf::util::logging::LogManager::getLogger (const std::string &
name)`

Retrieves or creates a new **Logger** (p. 2386) using the name specified a new logger inherits the configuration of the logger's parent if there is no configuration data for the logger.

Parameters:

name The name of the **Logger** (p. 2386).

6.493.3.4 `int decaf::util::logging::LogManager::getLoggerNames (const std::vector<
std::string > & names)`

Gets a list of known **Logger** (p. 2386) Names from this Manager, new loggers added while this method is in progress are not guaranteed to be in the list.

Parameters:

names STL Vector to hold string logger names.

Returns:

names count of how many loggers were inserted.

6.493.3.5 static LogManager& decaf::util::logging::LogManager::getLogManager ()
[static]

Get the global **LogManager** (p. 2406) instance.

Returns:

A reference to the global **LogManager** (p. 2406) instance.

6.493.3.6 const util::Properties& decaf::util::logging::LogManager::getProperties ()
const [inline]

Gets a reference to the Logging **Properties** (p. 3126) used by this logger.

Returns:

The **Logger** (p. 2386) **Properties** (p. 3126) Pointer

6.493.3.7 std::string decaf::util::logging::LogManager::getProperty (const
std::string & *name*)

Gets the value of a named property of this **LogManager** (p. 2406).

Parameters:

name The name of the Property to retrieve.

Returns:

the value of the property

6.493.3.8 void decaf::util::logging::LogManager::operator= (const LogManager &
manager) [protected]

Assignment operator.

Parameters:

manager the manager to assign from

6.493.3.9 void decaf::util::logging::LogManager::readConfiguration (decaf::io::InputStream * *stream*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)

Reinitialize the **logging** (p.175) properties and reread the **logging** (p.175) configuration from the given stream, which should be in **decaf.util.Properties** (p.3126) format. A **PropertyChangeEvent** will be fired after the properties are read.

Any log level definitions in the new configuration file will be applied using **Logger.setLevel()** (p.2395), if the target **Logger** (p.2386) exists.

Parameters:

stream The **InputStream** to read the **Properties** (p.3126) from.

Exceptions:

NullPointerException if stream is NULL.

IOException if an I/O error occurs.

6.493.3.10 void decaf::util::logging::LogManager::readConfiguration () throw (decaf::io::IOException)

Reinitialize the **logging** (p.175) properties and reread the **logging** (p.175) configuration. The same rules are used for locating the configuration properties as are used at startup. So normally the **logging** (p.175) properties will be re-read from the same file that was used at startup.

Any log level definitions in the new configuration file will be applied using **Logger.setLevel()** (p.2395), if the target **Logger** (p.2386) exists.

A **PropertyChangeEvent** will be fired after the properties are read.

Exceptions:

IOException if an I/O error occurs.

6.493.3.11 void decaf::util::logging::LogManager::removePropertyChangeListener (PropertyChangeListener * *listener*)

Removes a properties change listener from the **LogManager** (p.2406), if the listener is not found of the param is NULL this method returns silently.

Parameters:

listener The **PropertyChangeListener** to remove from the listeners set.

6.493.3.12 void decaf::util::logging::LogManager::reset ()

Reset the **logging** (p.175) configuration. For all named loggers, the reset operation removes and closes all Handlers and (except for the root logger) sets the level to **INHERIT**. The root logger's level is set to **Level::INFO** (p.2336).

6.493.3.13 void decaf::util::logging::LogManager::setProperties (const util::Properties & *properties*)

Sets the **Properties** (p. 3126) this **LogManager** (p. 2406) should use to configure its loggers. Once set a properties change event is fired.

Parameters:

properties Pointer to read the configuration from

6.493.4 Friends And Related Function Documentation

6.493.4.1 friend class decaf::lang::Runtime [friend]

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**LogManager.h**

6.494 decaf::util::logging::LogRecord Class Reference

LogRecord (p. 2413) objects are used to pass **logging** (p. 175) requests between the **logging** (p. 175) framework and individual log Handlers.

```
#include <src/main/decaf/util/logging/LogRecord.h>
```

Public Member Functions

- **LogRecord** ()
- virtual **~LogRecord** ()
- **Level** **getLevel** () const
*Get **Level** (p. 2332) of this log record.*
- void **setLevel** (**Level** value)
*Set (p. 3439) the **Level** (p. 2332) of this Log Record.*
- const std::string & **getLoggerName** () const
Gets the Source Logger's Name.
- void **setLoggerName** (const std::string &loggerName)
Sets the Source Logger's Name.
- const std::string & **getSourceFile** () const
Gets the Source Log File name.
- void **setSourceFile** (const std::string &sourceFile)
Sets the Source Log File Name.
- unsigned int **getSourceLine** () const
Gets the Source Log line number.
- void **setSourceLine** (unsigned int sourceLine)
Sets the Source Log line number.
- const std::string & **getMessage** () const
Gets the Message to be Logged.
- void **setMessage** (const std::string &message)
Sets the Message to be Logged.
- const std::string & **getSourceFunction** () const
Gets the name of the function where this log was logged.
- void **setSourceFunction** (const std::string &functionName)
Sets the name of the function where this log was logged.
- long long **getTimestamp** () const
Gets the time in mills that this message was logged.

- void **setTimestamp** (long long timeStamp)
Sets the time in mills that this message was logged.
- long long **getTreadId** () const
Gets the Thread Id where this Log was created.
- void **setTreadId** (long long threadId)
Sets the Thread Id where this Log was created.
- **decaf::lang::Throwable * getThrown** () const
*Gets any Throwable associated with this **LogRecord** (p. 2413).*
- void **setThrown** (**decaf::lang::Throwable *thrown**)
*Sets the Throwable associated with this **LogRecord** (p. 2413), the pointer becomes the property of this instance of the **LogRecord** (p. 2413) and will be deleted when the record is destroyed.*

6.494.1 Detailed Description

LogRecord (p. 2413) objects are used to pass **logging** (p. 175) requests between the **logging** (p. 175) framework and individual log Handlers. When a **LogRecord** (p. 2413) is passed into the **logging** (p. 175) framework it logically belongs to the framework and should no longer be used or updated by the client application.

Since:

1.0

6.494.2 Constructor & Destructor Documentation

6.494.2.1 decaf::util::logging::LogRecord::LogRecord ()

6.494.2.2 virtual decaf::util::logging::LogRecord::~~LogRecord () [virtual]

6.494.3 Member Function Documentation

6.494.3.1 Level decaf::util::logging::LogRecord::getLevel () const [inline]

Get **Level** (p. 2332) of this log record.

Returns:

Level (p. 2332) enumeration value.

6.494.3.2 const std::string& decaf::util::logging::LogRecord::getLoggerName () const [inline]

Gets the Source Logger's Name.

Returns:

the source loggers name

6.494.3.3 `const std::string& decaf::util::logging::LogRecord::getMessage () const`
[inline]

Gets the Message to be Logged.

Returns:

the source logger's message

6.494.3.4 `const std::string& decaf::util::logging::LogRecord::getSourceFile () const`
[inline]

Gets the Source Log File name.

Returns:

the source loggers name

6.494.3.5 `const std::string& decaf::util::logging::LogRecord::getSourceFunction ()`
`const` [inline]

Gets the name of the function where this log was logged.

Returns:

the source logger's message

6.494.3.6 `unsigned int decaf::util::logging::LogRecord::getSourceLine () const`
[inline]

Gets the Source Log line number.

Returns:

the source loggers line number

6.494.3.7 `decaf::lang::Throwable* decaf::util::logging::LogRecord::getThrown ()`
`const` [inline]

Gets any Throwable associated with this **LogRecord** (p. 2413).

Returns:

point to a Throwable instance or Null.

6.494.3.8 `long long decaf::util::logging::LogRecord::getTimestamp () const`
[inline]

Gets the time in mills that this message was logged.

Returns:

UTC time in milliseconds

6.494.3.9 `long long decaf::util::logging::LogRecord::getTreadId () const [inline]`

Gets the Thread Id where this Log was created.

Returns:

the source loggers line number

6.494.3.10 `void decaf::util::logging::LogRecord::setLevel (Level value) [inline]`

Set (p. 3439) the **Level** (p. 2332) of this Log Record.

Parameters:

value **Level** (p. 2332) Enumeration Value

6.494.3.11 `void decaf::util::logging::LogRecord::setLoggerName (const std::string & loggerName) [inline]`

Sets the Source Logger's Name.

Parameters:

loggerName the source loggers name

6.494.3.12 `void decaf::util::logging::LogRecord::setMessage (const std::string & message) [inline]`

Sets the Message to be Logged.

Parameters:

message the source loggers message

6.494.3.13 `void decaf::util::logging::LogRecord::setSourceFile (const std::string & sourceFile) [inline]`

Sets the Source Log File Name.

Parameters:

sourceFile the source loggers name

6.494.3.14 `void decaf::util::logging::LogRecord::setSourceFunction (const std::string & functionName) [inline]`

Sets the name of the function where this log was logged.

Parameters:

functionName the source of the log

6.494.3.15 `void decaf::util::logging::LogRecord::setSourceLine (unsigned int sourceLine)` [inline]

Sets the Source Log line number.

Parameters:

sourceLine the source logger's line number

6.494.3.16 `void decaf::util::logging::LogRecord::setThrown (decaf::lang::Throwable * thrown)` [inline]

Sets the Throwable associated with this **LogRecord** (p. 2413), the pointer becomes the property of this instance of the **LogRecord** (p. 2413) and will be deleted when the record is destroyed.

Parameters:

thrown A pointer to a Throwable that will be associated with this record.

6.494.3.17 `void decaf::util::logging::LogRecord::setTimestamp (long long timeStamp)` [inline]

Sets the time in mills that this message was logged.

Parameters:

timeStamp UTC Time in Milliseconds.

6.494.3.18 `void decaf::util::logging::LogRecord::setTreadId (long long threadId)` [inline]

Sets the Thread Id where this Log was created.

Parameters:

threadId the source logger's line number

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/LogRecord.h`

6.495 decaf::util::logging::LogWriter Class Reference

```
#include <src/main/decaf/util/logging/LogWriter.h>
```

Public Member Functions

- **LogWriter** ()
- virtual **~LogWriter** ()
- virtual void **log** (const std::string &file, const int line, const std::string &prefix, const std::string &message)
Writes a message to the output destination.
- virtual void **log** (const std::string &message)
Writes a message to the output destination.

Static Public Member Functions

- static **LogWriter & getInstance** ()
Get the singleton instance.
- static void **returnInstance** ()
Returns a Checked out instance of this Writer.
- static void **destroy** ()
*Forcefully Delete the Instance of this **LogWriter** (p. 2418) even if there are outstanding references.*

6.495.1 Constructor & Destructor Documentation

6.495.1.1 **decaf::util::logging::LogWriter::LogWriter** ()

6.495.1.2 **virtual decaf::util::logging::LogWriter::~~LogWriter** () [virtual]

6.495.2 Member Function Documentation

6.495.2.1 **static void decaf::util::logging::LogWriter::destroy** () [static]

Forcefully Delete the Instance of this **LogWriter** (p. 2418) even if there are outstanding references.

6.495.2.2 **static LogWriter& decaf::util::logging::LogWriter::getInstance** ()
[static]

Get the singleton instance.

6.495.2.3 virtual void decaf::util::logging::LogWriter::log (const std::string & *message*) [virtual]

Writes a message to the output destination.

Parameters:

message

6.495.2.4 virtual void decaf::util::logging::LogWriter::log (const std::string & *file*, const int *line*, const std::string & *prefix*, const std::string & *message*) [virtual]

Writes a message to the output destination.

Parameters:

file

line

prefix

message

6.495.2.5 static void decaf::util::logging::LogWriter::returnInstance () [static]

Returns a Checked out instance of this Writer.

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**LogWriter.h**

6.496 decaf::lang::Long Class Reference

#include <src/main/decaf/lang/Long.h> Inheritance diagram for decaf::lang::Long:

Public Member Functions

- **Long** (long long value)
- **Long** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Long** ()
- virtual int **compareTo** (const **Long** &l) const
*Compares this **Long** (p. 2420) instance with another.*
- bool **equals** (const **Long** &l) const
- virtual bool **operator==** (const **Long** &l) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Long** &l) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const long long &l) const
*Compares this **Long** (p. 2420) instance with another.*
- bool **equals** (const long long &l) const
- virtual bool **operator==** (const long long &l) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const long long &l) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const
Answers the long value which the receiver represents.

Static Public Member Functions

- static int **bitCount** (long long value)
Returns the number of one-bits in the two's complement binary representation of the specified int value.
- static **Long decode** (const std::string &value) throw (exceptions::NumberFormatException)
*Decodes a **String** (p. 3665) into a **Long** (p. 2420).*
- static long long **highestOneBit** (long long value)
Returns an long long value with at most a single one-bit, in the position of the highest-order ("leftmost") one-bit in the specified int value.
- static long long **lowestOneBit** (long long value)
Returns an long long value with at most a single one-bit, in the position of the lowest-order ("rightmost") one-bit in the specified int value.
- static int **numberOfLeadingZeros** (long long value)
Returns the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified long long value.
- static int **numberOfTrailingZeros** (long long value)
Returns the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified long long value.
- static long long **parseLong** (const std::string &value) throw (exceptions::NumberFormatException)
Parses the string argument as a signed decimal long.
- static long long **parseLong** (const std::string &value, int radix) throw (exceptions::NumberFormatException)
*Returns a **Long** (p. 2420) object holding the value extracted from the specified string when parsed with the radix given by the second argument.*
- static long long **reverseBytes** (long long value)
Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified long long value.
- static long long **reverse** (long long value)
Returns the value obtained by reversing the order of the bits in the two's complement binary representation of the specified long long value.
- static long long **rotateLeft** (long long value, int distance)
Returns the value obtained by rotating the two's complement binary representation of the specified value left by the specified number of bits.
- static long long **rotateRight** (long long value, int distance)
Returns the value obtained by rotating the two's complement binary representation of the specified value right by the specified number of bits.
- static int **signum** (long long value)

Returns the signum function of the specified value.

- static std::string **toString** (long long value)

*Converts the long to a **String** (p. 3665) representation.*

- static std::string **toString** (long long value, int radix)
- static std::string **toHexString** (long long value)

Returns a string representation of the integer argument as an unsigned integer in base 16.

- static std::string **toOctalString** (long long value)

Returns a string representation of the long long argument as an unsigned long long in base 8.

- static std::string **toBinaryString** (long long value)

Returns a string representation of the long long argument as an unsigned long long in base 2.

- static **Long** **valueOf** (long long value)

*Returns a **Long** (p. 2420) instance representing the specified int value.*

- static **Long** **valueOf** (const std::string &value) throw (exceptions::NumberFormatException)

*Returns a **Long** (p. 2420) object holding the value given by the specified std::string.*

- static **Long** **valueOf** (const std::string &value, int radix) throw (exceptions::NumberFormatException)

*Returns a **Long** (p. 2420) object holding the value extracted from the specified std::string when parsed with the radix given by the second argument.*

Static Public Attributes

- static const int **SIZE** = 64

The size in bits of the primitive long long type.

- static const long long **MAX_VALUE** = (long long)0x7FFFFFFFFFFFFFFFFFLL

The maximum value that the primitive type can hold.

- static const long long **MIN_VALUE** = (long long)0x8000000000000000LL

The minimum value that the primitive type can hold.

6.496.1 Constructor & Destructor Documentation

6.496.1.1 decaf::lang::Long::Long (long long value)

Parameters:

value - the primitive long long to wrap

6.496.1.2 decaf::lang::Long::Long (const std::string & *value*) throw (exceptions::NumberFormatException)

Parameters:

value - the long long formatted string to wrap

Exceptions:

NumberFormatException

6.496.1.3 virtual decaf::lang::Long::~~Long () [inline, virtual]

6.496.2 Member Function Documentation

6.496.2.1 static int decaf::lang::Long::bitCount (long long *value*) [static]

Returns the number of one-bits in the two's complement binary representation of the specified int value. This function is sometimes referred to as the population count.

Parameters:

value - the long long to count

Returns:

the number of one-bits in the two's complement binary representation of the specified long long value.

6.496.2.2 virtual unsigned char decaf::lang::Long::byteValue () const [inline, virtual]

Answers the byte value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2835).

6.496.2.3 virtual int decaf::lang::Long::compareTo (const long long & *l*) const [virtual]

Compares this **Long** (p. 2420) instance with another.

Parameters:

l - the **Integer** (p. 2077) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements **decaf::lang::Comparable**< long long > (p. 1214).

6.496.2.4 virtual int decaf::lang::Long::compareTo (const Long & *l*) const
[virtual]

Compares this **Long** (p. 2420) instance with another.

Parameters:

l - the **Long** (p. 2420) instance to be compared

Returns:

zero if this object represents the same integer value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.496.2.5 static Long decaf::lang::Long::decode (const std::string & *value*) throw (exceptions::NumberFormatException) [static]

Decodes a **String** (p. 3665) into a **Long** (p. 2420). Accepts decimal, hexadecimal, and octal numbers given by the following grammar:

The sequence of characters following an (optional) negative sign and/or radix specifier ("0x", "0X", "#", or leading zero) is parsed as by the Integer.parseInt method with the indicated radix (10, 16, or 8). This sequence of characters must represent a positive value or a NumberFormatException will be thrown. The result is negated if first character of the specified **String** (p. 3665) is the minus sign. No whitespace characters are permitted in the string.

Parameters:

value - The string to decode

Returns:

a **Long** (p. 2420) object containing the decoded value

Exceptions:

NumberFormatException if the string is not formatted correctly.

6.496.2.6 virtual double decaf::lang::Long::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.496.2.7 bool decaf::lang::Long::equals (const long long & *l*) const [inline, virtual]**Parameters:**

l - the **Long** (p. 2420) object to compare against.

Returns:

true if the two **Integer** (p. 2077) Objects have the same value.

Implements **decaf::lang::Comparable**< **long long** > (p. 1215).

6.496.2.8 bool decaf::lang::Long::equals (const Long & l) const [inline]**Parameters:**

l - the **Long** (p. 2420) object to compare against.

Returns:

true if the two **Integer** (p. 2077) Objects have the same value.

6.496.2.9 virtual float decaf::lang::Long::floatValue () const [inline, virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.496.2.10 static long long decaf::lang::Long::highestOneBit (long long value) [static]

Returns an long long value with at most a single one-bit, in the position of the highest-order ("leftmost") one-bit in the specified int value. Returns zero if the specified value has no one-bits in its two's complement binary representation, that is, if it is equal to zero.

Parameters:

value - the long long to be inspected

Returns:

an long long value with a single one-bit, in the position of the highest-order one-bit in the specified value, or zero if the specified value is itself equal to zero.

6.496.2.11 virtual int decaf::lang::Long::intValue () const [inline, virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.496.2.12 `virtual long long decaf::lang::Long::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements `decaf::lang::Number` (p. 2836).

6.496.2.13 `static long long decaf::lang::Long::lowestOneBit (long long value) [static]`

Returns an long long value with at most a single one-bit, in the position of the lowest-order ("rightmost") one-bit in the specified int value. Returns zero if the specified value has no one-bits in its two's complement binary representation, that is, if it is equal to zero.

Parameters:

value - the long long to be inspected

Returns:

an long long value with a single one-bit, in the position of the lowest-order one-bit in the specified value, or zero if the specified value is itself equal to zero.

6.496.2.14 `static int decaf::lang::Long::numberOfLeadingZeros (long long value) [static]`

Returns the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified long long value. Returns 64 if the specified value has no one-bits in its two's complement representation, in other words if it is equal to zero.

Note that this method is closely related to the logarithm base 2. For all positive int values x:

$\ast \text{floor}(\log_2(x)) = 63 - \text{numberOfLeadingZeros}(x) \ast \text{ceil}(\log_2(x)) = 64 - \text{numberOfLeadingZeros}(x) - 1)$

Parameters:

value - the long long to be inspected

Returns:

the number of zero bits preceding the highest-order ("leftmost") one-bit in the two's complement binary representation of the specified long long value, or 64 if the value is equal to zero.

6.496.2.15 `static int decaf::lang::Long::numberOfTrailingZeros (long long value) [static]`

Returns the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified long long value. Returns 64 if the specified value has no one-bits in its two's complement representation, in other words if it is equal to zero.

Parameters:

value - the int to be inspected

Returns:

the number of zero bits following the lowest-order ("rightmost") one-bit in the two's complement binary representation of the specified long long value, or 64 if the value is equal to zero.

6.496.2.16 `virtual bool decaf::lang::Long::operator< (const long long & l) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

l - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< long long >` (p. 1215).

6.496.2.17 `virtual bool decaf::lang::Long::operator< (const Long & l) const`
[inline, virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

l - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.496.2.18 `virtual bool decaf::lang::Long::operator== (const long long & l) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

l - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< long long >` (p. 1215).

6.496.2.19 `virtual bool decaf::lang::Long::operator== (const Long & l) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

l - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.496.2.20 `static long long decaf::lang::Long::parseLong (const std::string & value,`
`int radix) throw (exceptions::NumberFormatException)` [static]

Returns a **Long** (p. 2420) object holding the value extracted from the specified string when parsed with the radix given by the second argument. The first argument is interpreted as representing a signed long in the radix specified by the second argument, exactly as if the arguments were given to the `parseLong(std::string, int)` method. The result is a **Long** (p. 2420) object that represents the long long value specified by the string.

Parameters:

value - **String** (p. 3665) to parse

radix - the base encoding of the string

Returns:

long long value

Exceptions:

NumberFormatException on invalid string value

6.496.2.21 `static long long decaf::lang::Long::parseLong (const std::string & value)`
`throw (exceptions::NumberFormatException)` [static]

Parses the string argument as a signed decimal long. The characters in the string must all be decimal digits, except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting long value is returned, exactly as if the argument and the radix 10 were given as arguments to the `parseLong(java.lang.String, int)` method.

Note that the characters LL or ULL are not permitted to appear at the end of this string as would normally be permitted in a C++ program.

Parameters:

value - **String** (p. 3665) to parse

Returns:

long long value

Exceptions:

NumberFormatException on invalid string value

6.496.2.22 static long long decaf::lang::Long::reverse (long long *value*) [static]

Returns the value obtained by reversing the order of the bits in the two's complement binary representation of the specified long long value.

Parameters:

value - the value whose bits are to be reversed

Returns:

the reversed bits long long.

6.496.2.23 static long long decaf::lang::Long::reverseBytes (long long *value*) [static]

Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified long long value.

Parameters:

value - the long long whose bytes we are to reverse

Returns:

the reversed long long.

6.496.2.24 static long long decaf::lang::Long::rotateLeft (long long *value*, int *distance*) [static]

Returns the value obtained by rotating the two's complement binary representation of the specified value left by the specified number of bits. (Bits shifted out of the left hand, or high-order, side reenter on the right, or low-order.)

Note that left rotation with a negative distance is equivalent to right rotation: rotateLeft(val, -distance) == rotateRight(val, distance). Note also that rotation by any multiple of 32 is a no-op, so all but the last five bits of the rotation distance can be ignored, even if the distance is negative: rotateLeft(val, distance) == rotateLeft(val, distance & 0x1F).

Parameters:

value - the long long to be inspected

distance - the number of bits to rotate

Returns:

the value obtained by rotating the two's complement binary representation of the specified value left by the specified number of bits.

6.496.2.25 static long long decaf::lang::Long::rotateRight (long long *value*, int *distance*) [static]

Returns the value obtained by rotating the two's complement binary representation of the specified value right by the specified number of bits. (Bits shifted out of the right hand, or low-order, side reenter on the left, or high-order.)

Note that right rotation with a negative distance is equivalent to left rotation: `rotateRight(val, -distance) == rotateLeft(val, distance)`. Note also that rotation by any multiple of 32 is a no-op, so all but the last five bits of the rotation distance can be ignored, even if the distance is negative: `rotateRight(val, distance) == rotateRight(val, distance & 0x1F)`.

Parameters:

value - the long long to be inspected
distance - the number of bits to rotate

Returns:

the value obtained by rotating the two's complement binary representation of the specified value right by the specified number of bits.

6.496.2.26 `virtual short decaf::lang::Long::shortValue () const [inline, virtual]`

Answers the short value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from `decaf::lang::Number` (p. 2837).

6.496.2.27 `static int decaf::lang::Long::signum (long long value) [static]`

Returns the signum function of the specified value. (The return value is -1 if the specified value is negative; 0 if the specified value is zero; and 1 if the specified value is positive.)

Parameters:

value - the long long to be inspected

Returns:

the signum function of the specified long long value.

6.496.2.28 `static std::string decaf::lang::Long::toBinaryString (long long value) [static]`

Returns a string representation of the long long argument as an unsigned long long in base 2. The unsigned long long value is the argument plus 2^{32} if the argument is negative; otherwise it is equal to the argument. This value is converted to a string of ASCII digits in binary (base 2) with no extra leading 0s. If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character. The characters '0' and '1' are used as binary digits.

Parameters:

value - the long long to be translated to a binary string

Returns:

the unsigned long long value as a binary string

6.496.2.29 `static std::string decaf::lang::Long::toHexString (long long value)`
 [static]

Returns a string representation of the integer argument as an unsigned integer in base 16. The unsigned integer value is the argument plus 2^{32} if the argument is negative; otherwise, it is equal to the argument. This value is converted to a string of ASCII digits in hexadecimal (base 16) with no extra leading 0s. If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character. The following characters are used as hexadecimal digits:

0123456789abcdef

If uppercase letters are desired, the `toUpperCase()` method may be called on the result:

Parameters:

value - the long long to be translated to an Octal string

Returns:

the unsigned long long value as a Octal string

6.496.2.30 `static std::string decaf::lang::Long::toOctalString (long long value)`
 [static]

Returns a string representation of the long long argument as an unsigned long long in base 8. The unsigned long long value is the argument plus 2^{32} if the argument is negative; otherwise, it is equal to the argument. This value is converted to a string of ASCII digits in octal (base 8) with no extra leading 0s.

If the unsigned magnitude is zero, it is represented by a single zero character '0'; otherwise, the first character of the representation of the unsigned magnitude will not be the zero character. The following characters are used as octal digits:

01234567

Parameters:

value - the long long to be translated to an Octal string

Returns:

the unsigned long long value as a Octal string

6.496.2.31 `static std::string decaf::lang::Long::toString (long long value, int radix)`
 [static]**6.496.2.32** `static std::string decaf::lang::Long::toString (long long value)` [static]

Converts the long to a **String** (p. 3665) representation.

Parameters:

value The long to convert to a std::string.

Returns:

string representation

6.496.2.33 `std::string decaf::lang::Long::toString () const`**Returns:**

this **Long** (p. 2420) Object as a **String** (p. 3665) Representation

6.496.2.34 `static Long decaf::lang::Long::valueOf (const std::string & value, int radix) throw (exceptions::NumberFormatException) [static]`

Returns a **Long** (p. 2420) object holding the value extracted from the specified `std::string` when parsed with the radix given by the second argument. The first argument is interpreted as representing a signed long long in the radix specified by the second argument, exactly as if the argument were given to the `parseLong(std::string, int)` method. The result is a **Long** (p. 2420) object that represents the long long value specified by the string.

Parameters:

value - `std::string` to parse as base (radix)

radix - base of the string to parse.

Returns:

new **Long** (p. 2420) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a valid long long.

6.496.2.35 `static Long decaf::lang::Long::valueOf (const std::string & value) throw (exceptions::NumberFormatException) [static]`

Returns a **Long** (p. 2420) object holding the value given by the specified `std::string`. The argument is interpreted as representing a signed decimal long long, exactly as if the argument were given to the `parseLong(std::string)` method. The result is a **Integer** (p. 2077) object that represents the long long value specified by the string.

Parameters:

value - `std::string` to parse as base 10

Returns:

new **Long** (p. 2420) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a decimal long long.

6.496.2.36 `static Long decaf::lang::Long::valueOf (long long value) [inline, static]`

Returns a **Long** (p. 2420) instance representing the specified `int` value.

Parameters:

value - the long long to wrap

Returns:

the new **Integer** (p. 2077) object wrapping value.

6.496.3 Field Documentation

6.496.3.1 `const long long decaf::lang::Long::MAX_VALUE = (long long)0x7FFFFFFFFFFFFFFFFLL [static]`

The maximum value that the primitive type can hold.

6.496.3.2 `const long long decaf::lang::Long::MIN_VALUE = (long long)0x8000000000000000LL [static]`

The minimum value that the primitive type can hold.

6.496.3.3 `const int decaf::lang::Long::SIZE = 64 [static]`

The size in bits of the primitive long long type.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Long.h`

6.497 decaf::internal::nio::LongArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/LongArrayBuffer.h> Inheritance diagram for decaf::internal::nio::LongArrayBuffer:

Public Member Functions

- **LongArrayBuffer** (int size, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **IntArrayBuffer** (p. 2056) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **LongArrayBuffer** (long long *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **LongArrayBuffer** (p. 2434) object that wraps the given array.*

- **LongArrayBuffer** (const decaf::lang::Pointer< ByteArrayAdapter > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset.

- **LongArrayBuffer** (const LongArrayBuffer &other)

*Create a **LongArrayBuffer** (p. 2434) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.*

- virtual ~**LongArrayBuffer** ()
- virtual long long * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the long long array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

*the array that backs this **Buffer** (p. 928).*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset long longo the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual LongBuffer * **asReadOnlyBuffer** () const

Creates a new, read-only long long buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only long long buffer which the caller then owns.

- virtual LongBuffer & **compact** () throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

*a reference to this **LongBuffer** (p. 2444).*

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual LongBuffer * **duplicate** ()

Creates a new long long buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*a new long long **Buffer** (p. 928) which the caller owns.*

- virtual long long **get** () throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the long long at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

- virtual long long **get** (int index) const throw (lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the long long is to be read.

Returns:

the long long that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible long long array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual LongBuffer & **put** (long long value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given long longs long longo this buffer at the current position, and then increments the position.

Parameters:

value The long longs value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual LongBuffer & **put** (int index, long long value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given long longs long longo this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The long longs to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

- virtual LongBuffer * **slice** () const

Creates a new **LongBuffer** (p. 2444) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **LongBuffer** (p. 2444) which the caller owns.

Protected Member Functions

- virtual void **setReadOnly** (bool value)

Sets this **LongArrayBuffer** (p. 2434) as Read-Only.

6.497.1 Constructor & Destructor Documentation

6.497.1.1 decaf::internal::nio::LongArrayBuffer::LongArrayBuffer (int size, bool readOnly = false) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a **IntArrayBuffer** (p. 2056) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.497.1.2 decaf::internal::nio::LongArrayBuffer::LongArrayBuffer (long long * array, int size, int offset, int length, bool readOnly = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a **LongArrayBuffer** (p. 2434) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.497.1.3 `decaf::internal::nio::LongArrayBuffer::LongArrayBuffer`
 (const decaf::lang::Pointer< ByteArrayAdapter > &
array, int *offset*, int *length*, bool *readOnly* = false)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset. The capacity and limit of the new **LongArrayBuffer** (p. 2434) will be that of the remaining capacity of the passed buffer.

Parameters:

array The ByteArrayAdapter to wrap.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if array is NULL

IndexOutOfBoundsException if offset + length is greater than array size.

6.497.1.4 `decaf::internal::nio::LongArrayBuffer::LongArrayBuffer` (const
 LongArrayBuffer & *other*)

Create a **LongArrayBuffer** (p. 2434) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.

Parameters:

other The **LongArrayBuffer** (p. 2434) this one is to mirror.

6.497.1.5 `virtual decaf::internal::nio::LongArrayBuffer::~~LongArrayBuffer` ()
 [virtual]

6.497.2 Member Function Documentation

6.497.2.1 `virtual long long* decaf::internal::nio::LongArrayBuffer::array` ()
 throw (decaf::lang::exceptions::UnsupportedOperationException,
 decaf::nio::ReadOnlyBufferException) [virtual]

Returns the long long array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::LongBuffer** (p. 2447).

6.497.2.2 `virtual int decaf::internal::nio::LongArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset long into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::LongBuffer** (p. 2447).

6.497.2.3 `virtual LongBuffer* de-
caf::internal::nio::LongArrayBuffer::asReadOnlyBuffer ()
const [virtual]`

Creates a new, read-only long long buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only long long buffer which the caller then owns.

Implements **decaf::nio::LongBuffer** (p. 2447).

6.497.2.4 **virtual LongBuffer& decaf::internal::nio::LongArrayBuffer::compact ()** **throw (decaf::nio::ReadOnlyBufferException)** [virtual]

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **LongBuffer** (p. 2444).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::LongBuffer** (p. 2448).

6.497.2.5 **virtual LongBuffer* decaf::internal::nio::LongArrayBuffer::duplicate ()** [virtual]

Creates a new long long buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new long long **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::LongBuffer** (p. 2448).

6.497.2.6 **virtual long long decaf::internal::nio::LongArrayBuffer::get (int *index*)** **const throw (lang::exceptions::IndexOutOfBoundsException)** [virtual]

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the long long is to be read.

Returns:

the long long that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implements **decaf::nio::LongBuffer** (p. 2449).

6.497.2.7 virtual long long decaf::internal::nio::LongArrayBuffer::get () throw (decaf::nio::BufferUnderflowException) [virtual]

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the long long at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implements **decaf::nio::LongBuffer** (p. 2450).

6.497.2.8 virtual bool decaf::internal::nio::LongArrayBuffer::hasArray () const [inline, virtual]

Tells whether or not this buffer is backed by an accessible long long array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implements **decaf::nio::LongBuffer** (p. 2450).

6.497.2.9 virtual bool decaf::internal::nio::LongArrayBuffer::isReadOnly () const [inline, virtual]

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.497.2.10 virtual LongBuffer& decaf::internal::nio::LongArrayBuffer::put (int index, long long value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]

Writes the given long longs long longo this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data

value The long longs to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::LongBuffer** (p. 2450).

6.497.2.11 `virtual LongBuffer& decaf::internal::nio::LongArrayBuffer::put (long long value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)` [virtual]

Writes the given long longs long longo this buffer at the current position, and then increments the position.

Parameters:

value The long longs value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implements **decaf::nio::LongBuffer** (p. 2451).

6.497.2.12 `virtual void decaf::internal::nio::LongArrayBuffer::setReadOnly (bool value)` [inline, protected, virtual]

Sets this **LongArrayBuffer** (p. 2434) as Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.497.2.13 `virtual LongBuffer* decaf::internal::nio::LongArrayBuffer::slice () const` [virtual]

Creates a new **LongBuffer** (p. 2444) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **LongBuffer** (p. 2444) which the caller owns.

Implements **decaf::nio::LongBuffer** (p. 2453).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/LongArrayBuffer.h`

6.498 decaf::nio::LongBuffer Class Reference

This class defines four categories of operations upon long long buffers:.

#include <src/main/decaf/nio/LongBuffer.h> Inheritance diagram for decaf::nio::LongBuffer:

Public Member Functions

- virtual **~LongBuffer** ()
- virtual std::string **toString** () const
- virtual long long * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the long long array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **LongBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only long long buffer that shares this buffer's content.
- virtual **LongBuffer** & **compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **LongBuffer** * **duplicate** ()=0
Creates a new long long buffer that shares this buffer's content.
- virtual long long **get** ()=0 throw (BufferUnderflowException)
Relative get method.
- virtual long long **get** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **LongBuffer** & **get** (std::vector< long long > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **LongBuffer** & **get** (long long *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible long long array.
- **LongBuffer** & **put** (**LongBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, lang::exceptions::IllegalArgumentException)

This method transfers the long longs remaining in the given source buffer long longo this buffer.

- **LongBuffer** & **put** (const long long *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers long longs long longo this buffer from the given source array.

- **LongBuffer** & **put** (std::vector< long long > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source long longs array long longo this buffer.

- virtual **LongBuffer** & **put** (long long value)=0 throw (BufferOverflowException, ReadOnlyBufferException)

Writes the given long longs long longo this buffer at the current position, and then increments the position.

- virtual **LongBuffer** & **put** (int index, long long value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)

Writes the given long longs long longo this buffer at the given index.

- virtual **LongBuffer** * **slice** () const =0

*Creates a new **LongBuffer** (p. 2444) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **LongBuffer** &value) const

- virtual bool **equals** (const **LongBuffer** &value) const

- virtual bool **operator==** (const **LongBuffer** &value) const

- virtual bool **operator<** (const **LongBuffer** &value) const

Static Public Member Functions

- static **LongBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

Allocates a new Double buffer.

- static **LongBuffer** * **wrap** (long long *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **LongBuffer** (p. 2444).*

- static **LongBuffer** * **wrap** (std::vector< long long > &buffer)

*Wraps the passed STL long long Vector in a **LongBuffer** (p. 2444).*

Protected Member Functions

- **LongBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **LongBuffer** (p. 2444) object that has its backing array allocated long longernally and is then owned and deleted when this object is deleted.*

6.498.1 Detailed Description

This class defines four categories of operations upon long long buffers:. o Absolute and relative get and put methods that read and write single long longs; o Relative bulk get methods that transfer contiguous sequences of long longs from this buffer long longo an array; and o Relative bulk put methods that transfer contiguous sequences of long longs from a long long array or some other long long buffer long longo this buffer o Methods for compacting, duplicating, and slicing a long long buffer.

Double buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing long long array long longo a buffer, or by creating a view of an existing byte buffer

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained.

6.498.2 Constructor & Destructor Documentation

6.498.2.1 decaf::nio::LongBuffer::LongBuffer (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **LongBuffer** (p. 2444) object that has its backing array allocated long longernally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size and limit of the **Buffer** (p. 928) in long longs.

Exceptions:

IllegalArgumentException if capacity is negative.

6.498.2.2 virtual decaf::nio::LongBuffer::~~LongBuffer () [inline, virtual]

6.498.3 Member Function Documentation

6.498.3.1 static LongBuffer* decaf::nio::LongBuffer::allocate (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new Double buffer. The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Double buffer in long longs.

Returns:

the **LongBuffer** (p. 2444) that was allocated, caller owns.

6.498.3.2 `virtual long long* decaf::nio::LongBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the long long array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928).

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::LongArrayBuffer` (p. 2438).

6.498.3.3 `virtual int decaf::nio::LongBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset long longo the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::LongArrayBuffer` (p. 2439).

6.498.3.4 `virtual LongBuffer* decaf::nio::LongBuffer::asReadOnlyBuffer () const [pure virtual]`

Creates a new, read-only long long buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new

buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only long long buffer which the caller then owns.

Implemented in `decaf::internal::nio::LongArrayBuffer` (p. 2439).

6.498.3.5 `virtual LongBuffer& decaf::nio::LongBuffer::compact () throw (ReadOnlyBufferException)` [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this `LongBuffer` (p. 2444).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::LongArrayBuffer` (p. 2440).

6.498.3.6 `virtual int decaf::nio::LongBuffer::compareTo (const LongBuffer & value) const` [virtual]

6.498.3.7 `virtual LongBuffer* decaf::nio::LongBuffer::duplicate ()` [pure virtual]

Creates a new long long buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new long long `Buffer` (p. 928) which the caller owns.

Implemented in `decaf::internal::nio::LongArrayBuffer` (p. 2440).

6.498.3.8 virtual bool decaf::nio::LongBuffer::equals (const LongBuffer & *value*)
const [virtual]

6.498.3.9 LongBuffer& decaf::nio::LongBuffer::get (long long * *buffer*, int *size*, int *offset*, int *length*) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

Relative bulk get method. This method transfers long longs from this buffer long longo the given destination array. If there are fewer long longs remaining in the buffer than are required to satisfy the request, that is, if *length* > **remaining()** (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies *length* long longs from this buffer long longo the given array, starting at the current position of this buffer and at the given *offset* in the array. The position of this buffer is then incremented by *length*.

Parameters:

buffer The pointer to an allocated long long buffer to fill.

size The size of the passed in buffer.

offset The position in the buffer to start filling.

length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than *length* long longs remaining in this buffer

NullPolong longerException if the passed buffer is null.

IndexOutOfBoundsException if the preconditions of *size*, *offset*, or *length* are not met.

6.498.3.10 LongBuffer& decaf::nio::LongBuffer::get (std::vector< long long > *buffer*) throw (BufferUnderflowException)

Relative bulk get method. This method transfers values from this buffer long longo the given destination vector. An invocation of this method of the form *src.get(a)* behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call *buffer.resize(N)* before calling this get method.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than *length* long longs remaining in this buffer.

6.498.3.11 **virtual long long decaf::nio::LongBuffer::get (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)** [pure virtual]

Absolute get method. Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the long long is to be read.

Returns:

the long long that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or index is negative.

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2440).

6.498.3.12 **virtual long long decaf::nio::LongBuffer::get () throw (BufferUnderflowException)** [pure virtual]

Relative get method. Reads the value at this buffer's current position, and then increments the position.

Returns:

the long long at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2441).

6.498.3.13 **virtual bool decaf::nio::LongBuffer::hasArray () const** [pure virtual]

Tells whether or not this buffer is backed by an accessible long long array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2441).

- 6.498.3.14** `virtual bool decaf::nio::LongBuffer::operator< (const LongBuffer & value) const` [virtual]
- 6.498.3.15** `virtual bool decaf::nio::LongBuffer::operator== (const LongBuffer & value) const` [virtual]
- 6.498.3.16** `virtual LongBuffer& decaf::nio::LongBuffer::put (int index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)` [pure virtual]

Writes the given long longs long longo this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data
value The long longs to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2441).

- 6.498.3.17** `virtual LongBuffer& decaf::nio::LongBuffer::put (long long value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes the given long longs long longo this buffer at the current position, and then increments the position.

Parameters:

value The long longs value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit

ReadOnlyBufferException (p. 3169) if this buffer is read-only

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2442).

- 6.498.3.18** `LongBuffer& decaf::nio::LongBuffer::put (std::vector< long long > & buffer) throw (BufferOverflowException, ReadOnlyBufferException)`

This method transfers the entire content of the given source long longs array long longo this buffer. This is the same as calling `put(&buffer[0], 0, buffer.size()`.

Parameters:

buffer The buffer whose contents are copied to this **LongBuffer** (p. 2444).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.498.3.19 **LongBuffer& decaf::nio::LongBuffer::put (const long long * *buffer*, int *size*, int *offset*, int *length*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)**

This method transfers long longs long longo this buffer from the given source array. If there are more long longs to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no long longs are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies length bytes from the given array long longo this buffer, starting at the given offset in the array and at the current position of this buffer. The position of this buffer is then incremented by length.

Parameters:

buffer The array from which long longs are to be read.

size The size of the buffer passed.

offset The offset within the array of the first char to be read.

length The number of long longs to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer

ReadOnlyBufferException (p. 3169) if this buffer is read-only

NullPointerException if the passed buffer is null.

IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.498.3.20 **LongBuffer& decaf::nio::LongBuffer::put (LongBuffer & *src*) throw (BufferOverflowException, ReadOnlyBufferException, lang::exceptions::IllegalArgumentException)**

This method transfers the long longs remaining in the given source buffer long longo this buffer. If there are more long longs remaining in the source buffer than in this buffer, that is, if

`src.remaining() > remaining()` (p. 933), then no long longs are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` long longs from the given buffer long longo this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

src The buffer to take long longs from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer for the remaining long longs in the source buffer

IllegalArgumentException if the source buffer is this buffer

ReadOnlyBufferException (p. 3169) if this buffer is read-only

6.498.3.21 virtual LongBuffer* decaf::nio::LongBuffer::slice () const [pure virtual]

Creates a new **LongBuffer** (p. 2444) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **LongBuffer** (p. 2444) which the caller owns.

Implemented in **decaf::internal::nio::LongArrayBuffer** (p. 2442).

6.498.3.22 virtual std::string decaf::nio::LongBuffer::toString () const [virtual]

Returns:

a `std::string` describing this object

6.498.3.23 static LongBuffer* decaf::nio::LongBuffer::wrap (std::vector< long long > & buffer) [static]

Wraps the passed STL long long Vector in a **LongBuffer** (p. 2444). The new buffer will be backed by the given long long array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new **LongBuffer** (p. 2444) that is backed by *buffer*, caller owns.

6.498.3.24 `static LongBuffer* decaf::nio::LongBuffer::wrap (long
long * array, int size, int offset, int length)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException) [static]`

Wraps the passed buffer with a new **LongBuffer** (p. 2444). The new buffer will be backed by the given long long array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

array The array that will back the new buffer.

size The size of the passed in array.

offset The offset of the subarray to be used.

length The length of the subarray to be used.

Returns:

a new **LongBuffer** (p. 2444) that is backed by *buffer*, caller owns.

Exceptions:

NullPointerException if the array pointer is NULL.

IndexOutOfBoundsException if the preconditions of *size*, *offset*, or *length* are not met.

The documentation for this class was generated from the following file:

- `src/main/decaf/nio/LongBuffer.h`

6.499 activemq::util::LongSequenceGenerator Class Reference

This class is used to generate a sequence of long long values that are incremented each time a new value is requested.

```
#include <src/main/activemq/util/LongSequenceGenerator.h>
```

Public Member Functions

- **LongSequenceGenerator** ()
- virtual **~LongSequenceGenerator** ()
- long long **getNextSequenceId** ()
- long long **getLastSequenceId** ()

6.499.1 Detailed Description

This class is used to generate a sequence of long long values that are incremented each time a new value is requested. This class is thread safe so the ids can be requested in different **threads** (p. 96) safely.

6.499.2 Constructor & Destructor Documentation

6.499.2.1 **activemq::util::LongSequenceGenerator::LongSequenceGenerator** ()

6.499.2.2 **virtual**
activemq::util::LongSequenceGenerator::~~LongSequenceGenerator ()
[inline, virtual]

6.499.3 Member Function Documentation

6.499.3.1 **long long activemq::util::LongSequenceGenerator::getLastSequenceId** ()

Returns:

the last id that was generated.

6.499.3.2 **long long activemq::util::LongSequenceGenerator::getNextSequenceId** ()

Returns:

the next id in the sequence.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/LongSequenceGenerator.h`

6.500 decaf::net::MalformedURLException Class Reference

#include <src/main/decaf/net/MalformedURLException.h> Inheritance diagram for decaf::net::MalformedURLException:

Public Member Functions

- **MalformedURLException** () throw ()
Default Constructor.
- **MalformedURLException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **MalformedURLException** (const **MalformedURLException** &ex) throw ()
Copy Constructor.
- **MalformedURLException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **MalformedURLException** (const std::exception *cause) throw ()
Constructor.
- **MalformedURLException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **MalformedURLException** * clone () const
Clones this exception.
- virtual ~**MalformedURLException** () throw ()

6.500.1 Constructor & Destructor Documentation

6.500.1.1 decaf::net::MalformedURLException::MalformedURLException () throw () [inline]

Default Constructor.

6.500.1.2 decaf::net::MalformedURLException::MalformedURLException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.500.1.3 decaf::net::MalformedURLException::MalformedURLException (const MalformedURLException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.500.1.4 decaf::net::MalformedURLException::MalformedURLException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.500.1.5 decaf::net::MalformedURLException::MalformedURLException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.500.1.6 decaf::net::MalformedURLException::MalformedURLException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.500.1.7 `virtual decaf::net::MalformedURLException::~~MalformedURLException
() throw () [inline, virtual]`

6.500.2 Member Function Documentation

6.500.2.1 `virtual MalformedURLException* de-
caf::net::MalformedURLException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/MalformedURLException.h`

6.501 decaf::util::Map< K, V, COMPARATOR > Class Template Reference

Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map.

#include <src/main/decaf/util/Map.h> Inheritance diagram for decaf::util::Map< K, V, COMPARATOR >:

Data Structures

- class **Entry**

Public Member Functions

- **Map** ()
Default constructor - does nothing.
- virtual ~**Map** ()
- virtual bool **equals** (const **Map** &source) const =0
Comparison, equality is dependent on the method of determining if the element are equal.
- virtual void **copy** (const **Map** &source)=0
Copies the content of the source map into this map.
- virtual void **clear** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException)
Removes all keys and values from this map.
- virtual bool **containsKey** (const K &key) const =0
Indicates whether or this map contains a value for the given key.
- virtual bool **containsValue** (const V &value) const =0
Indicates whether or this map contains a value for the given value, i.e.
- virtual bool **isEmpty** () const =0
- virtual std::size_t **size** () const =0
- virtual V & **get** (const K &key)=0 throw (lang::exceptions::NoSuchElementException)
*Gets the value mapped to the specified key in the **Map** (p. 2459).*
- virtual const V & **get** (const K &key) const =0 throw (lang::exceptions::NoSuchElementException)
*Gets the value mapped to the specified key in the **Map** (p. 2459).*
- virtual void **put** (const K &key, const V &value)=0 throw (decaf::lang::exceptions::UnsupportedOperationException)
Sets the value for the specified key.

- virtual void **putAll** (const **Map**< K, V, COMPARATOR > &other)=0 throw (decaf::lang::exceptions::UnsupportedOperationException)
*Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.*
- virtual V **remove** (const K &key)=0 throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)
Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.
- virtual std::vector< K > **keySet** () const =0
*Returns a **Set** (p. 3439) view of the mappings contained in this map.*
- virtual std::vector< V > **values** () const =0

6.501.1 Detailed Description

```
template<typename K, typename V, typename COMPARATOR = std::less<K>>
class decaf::util::Map< K, V, COMPARATOR >
```

Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map.

6.501.2 Constructor & Destructor Documentation

6.501.2.1 template<typename K, typename V, typename COMPARATOR = std::less<K>> decaf::util::Map< K, V, COMPARATOR >::Map () [inline]

Default constructor - does nothing.

6.501.2.2 template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual decaf::util::Map< K, V, COMPARATOR >::~~Map () [inline, virtual]

6.501.3 Member Function Documentation

6.501.3.1 template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::Map< K, V, COMPARATOR >::clear () throw (decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]

Removes all keys and values from this map.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1237), decaf::util::StlMap< K, V, COMPARATOR > (p. 3606), decaf::util::concurrent::ConcurrentStlMap< Pointer<

MessageId >, Pointer< Message >, MessageId::COMPARATOR >
 (p. 1237), decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-
 tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR
 > (p. 1237), decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-
 sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR
 > (p. 1237), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId
 >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1237),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >,
 Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1237),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer<
 ProducerState >, ProducerId::COMPARATOR > (p. 1237), decaf::util::StlMap<
 cms::Session *, SessionResolver * > (p. 3606), decaf::util::StlMap< std::string,
 WireFormatFactory * > (p. 3606), decaf::util::StlMap< std::string, PrimitiveVal-
 ueNode > (p. 3606), decaf::util::StlMap< std::string, cms::Queue * > (p. 3606),
 decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com-
 mands::ProducerId::COMPARATOR > (p. 3606), decaf::util::StlMap< std::string,
 CachedConsumer * > (p. 3606), decaf::util::StlMap< Pointer< commands::ConsumerId
 >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3606),
 decaf::util::StlMap< std::string, TransportFactory * > (p. 3606), decaf::util::StlMap<
 Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR
 > (p. 3606), decaf::util::StlMap< int, Pointer< Command > > (p. 3606),
 decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, com-
 mands::ConsumerId::COMPARATOR > (p. 3606), decaf::util::StlMap< std::string,
 CachedProducer * > (p. 3606), and decaf::util::StlMap< std::string, cms::Topic * >
 (p. 3606).

6.501.3.2 template<typename K, typename V, typename COMPARATOR =
 std::less<K>> virtual bool decaf::util::Map< K, V, COMPARATOR
 >::containsKey (const K & *key*) const [pure virtual]

Indicates whether or this map contains a value for the given key.

Parameters:

key The key to look up.

Returns:

true if this map contains the value, otherwise false.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COM-
 PARATOR > (p. 1238), decaf::util::StlMap< K, V, COMPARA-
 TOR > (p. 3606), decaf::util::concurrent::ConcurrentStlMap< Pointer<
 MessageId >, Pointer< Message >, MessageId::COMPARATOR >
 (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-
 tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR
 > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-
 sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR
 > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId
 >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1238),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >,
 Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1238),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer<
 ProducerState >, ProducerId::COMPARATOR > (p. 1238), decaf::util::StlMap<

cms::Session *, SessionResolver * > (p. 3606), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3606), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3606), decaf::util::StlMap< std::string, cms::Queue * > (p. 3606), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3606), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3606), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3606), decaf::util::StlMap< std::string, TransportFactory * > (p. 3606), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3606), decaf::util::StlMap< int, Pointer< Command > > (p. 3606), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3606), decaf::util::StlMap< std::string, CachedProducer * > (p. 3606), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3606).

6.501.3.3 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::Map< K, V, COMPARATOR >::containsValue (const V & value) const` [pure virtual]

Indicates whether or this map contains a value for the given value, i.e. they are equal, this is done by operator== so the types must pass equivalence testing in this manner.

Parameters:

value The Value to look up.

Returns:

true if this map contains the value, otherwise false.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1238), decaf::util::StlMap< K, V, COMPARATOR > (p. 3607), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1238), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1238), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3607), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3607), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3607), decaf::util::StlMap< std::string, cms::Queue * > (p. 3607), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3607), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3607), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3607), decaf::util::StlMap< std::string, TransportFactory * > (p. 3607), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3607), decaf::util::StlMap< int, Pointer< Command > > (p. 3607),

`decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR >` (p. 3607), `decaf::util::StlMap< std::string, CachedProducer * >` (p. 3607), and `decaf::util::StlMap< std::string, cms::Topic * >` (p. 3607).

6.501.3.4 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::Map< K, V, COMPARATOR >::copy (const Map< K, V, COMPARATOR > & source) [pure virtual]`

Copies the content of the source map into this map. Erases all existing data in this map.

Parameters:

source The source object to copy from.

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1239), and `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3607).

6.501.3.5 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::Map< K, V, COMPARATOR >::equals (const Map< K, V, COMPARATOR > & source) const [pure virtual]`

Comparison, equality is dependent on the method of determining if the element are equal.

Parameters:

source - `Map` (p. 2459) to compare to this one.

Returns:

true if the `Map` (p. 2459) passed is equal in value to this one.

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1239), and `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3608).

6.501.3.6 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual const V& decaf::util::Map< K, V, COMPARATOR >::get (const K & key) const throw (lang::exceptions::NoSuchElementException) [pure virtual]`

Gets the value mapped to the specified key in the `Map` (p. 2459). If there is no element in the map whose key is equivalent to the key provided then a `NoSuchElementException` is thrown.

Parameters:

key The search key.

Returns:

A {const} reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implemented in **decaf::util::concurrent::ConcurrentStlMap**< **K**, **V**, **COMPARATOR** > (p. 1239), **decaf::util::StlMap**< **K**, **V**, **COMPARATOR** > (p. 3608), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **MessageId** >, **Pointer**< **Message** >, **MessageId::COMPARATOR** > (p. 1239), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ConnectionId** >, **Pointer**< **ConnectionState** >, **ConnectionId::COMPARATOR** > (p. 1239), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ConsumerId** >, **Pointer**< **ConsumerState** >, **ConsumerId::COMPARATOR** > (p. 1239), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **SessionId** >, **Pointer**< **SessionState** >, **SessionId::COMPARATOR** > (p. 1239), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **LocalTransactionId** >, **Pointer**< **TransactionState** >, **LocalTransactionId::COMPARATOR** > (p. 1239), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**< **ProducerId** >, **Pointer**< **ProducerState** >, **ProducerId::COMPARATOR** > (p. 1239), **decaf::util::StlMap**< **cms::Session** *, **SessionResolver** * > (p. 3608), **decaf::util::StlMap**< **std::string**, **WireFormatFactory** * > (p. 3608), **decaf::util::StlMap**< **std::string**, **PrimitiveValueNode** > (p. 3608), **decaf::util::StlMap**< **std::string**, **cms::Queue** * > (p. 3608), **decaf::util::StlMap**< **Pointer**< **commands::ProducerId** >, **ActiveMQProducer** *, **commands::ProducerId::COMPARATOR** > (p. 3608), **decaf::util::StlMap**< **std::string**, **CachedConsumer** * > (p. 3608), **decaf::util::StlMap**< **Pointer**< **commands::ConsumerId** >, **ActiveMQConsumer** *, **commands::ConsumerId::COMPARATOR** > (p. 3608), **decaf::util::StlMap**< **std::string**, **TransportFactory** * > (p. 3608), **decaf::util::StlMap**< **Pointer**< **ConsumerId** >, **Pointer**< **ConsumerInfo** >, **ConsumerId::COMPARATOR** > (p. 3608), **decaf::util::StlMap**< **int**, **Pointer**< **Command** > > (p. 3608), **decaf::util::StlMap**< **Pointer**< **commands::ConsumerId** >, **Dispatcher** *, **commands::ConsumerId::COMPARATOR** > (p. 3608), **decaf::util::StlMap**< **std::string**, **CachedProducer** * > (p. 3608), and **decaf::util::StlMap**< **std::string**, **cms::Topic** * > (p. 3608).

6.501.3.7 **template**<typename **K**, typename **V**, typename **COMPARATOR** = **std::less**<**K**>> **virtual** **V**& **decaf::util::Map**< **K**, **V**, **COMPARATOR** >::**get** (**const** **K** & *key*) **throw** (**lang::exceptions::NoSuchElementException**)
[pure virtual]

Gets the value mapped to the specified key in the **Map** (p. 2459). If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.

Parameters:

key The search key.

Returns:

A reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implemented in **decaf::util::concurrent::ConcurrentStlMap**< **K**, **V**, **COMPARATOR** > (p. 1240), **decaf::util::StlMap**< **K**, **V**, **COMPARATOR** > (p. 3608), **decaf::util::concurrent::ConcurrentStlMap**< **Pointer**<

MessageId >, Pointer< Message >, MessageId::COMPARATOR >
 (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-
 tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR
 > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-
 sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR
 > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId
 >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1240),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >,
 Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1240),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer<
 ProducerState >, ProducerId::COMPARATOR > (p. 1240), decaf::util::StlMap<
 cms::Session *, SessionResolver * > (p. 3608), decaf::util::StlMap< std::string,
 WireFormatFactory * > (p. 3608), decaf::util::StlMap< std::string, PrimitiveVal-
 ueNode > (p. 3608), decaf::util::StlMap< std::string, cms::Queue * > (p. 3608),
 decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com-
 mands::ProducerId::COMPARATOR > (p. 3608), decaf::util::StlMap< std::string,
 CachedConsumer * > (p. 3608), decaf::util::StlMap< Pointer< commands::ConsumerId
 >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3608),
 decaf::util::StlMap< std::string, TransportFactory * > (p. 3608), decaf::util::StlMap<
 Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR
 > (p. 3608), decaf::util::StlMap< int, Pointer< Command > > (p. 3608),
 decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, com-
 mands::ConsumerId::COMPARATOR > (p. 3608), decaf::util::StlMap< std::string,
 CachedProducer * > (p. 3608), and decaf::util::StlMap< std::string, cms::Topic * >
 (p. 3608).

Referenced by decaf::util::StlMap< std::string, cms::Topic * >::equals(), and
 decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >,
 ProducerId::COMPARATOR >::equals().

6.501.3.8 `template<typename K, typename V, typename COMPARATOR =
 std::less<K>> virtual bool decaf::util::Map< K, V, COMPARATOR
 >::isEmpty () const [pure virtual]`

Returns:

if the **Map** (p. 2459) contains any element or not, TRUE or FALSE

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COM-
 PARATOR > (p. 1240), decaf::util::StlMap< K, V, COMPARA-
 TOR > (p. 3609), decaf::util::concurrent::ConcurrentStlMap< Pointer<
 MessageId >, Pointer< Message >, MessageId::COMPARATOR >
 (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-
 tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR
 > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-
 sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR
 > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId
 >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1240),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >,
 Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1240),
 decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer<
 ProducerState >, ProducerId::COMPARATOR > (p. 1240), decaf::util::StlMap<
 cms::Session *, SessionResolver * > (p. 3609), decaf::util::StlMap< std::string,
 WireFormatFactory * > (p. 3609), decaf::util::StlMap< std::string, PrimitiveVal-

ueNode > (p. 3609), decaf::util::StlMap< std::string, cms::Queue * > (p. 3609), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3609), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, TransportFactory * > (p. 3609), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< int, Pointer< Command > > (p. 3609), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedProducer * > (p. 3609), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3609).

6.501.3.9 `template<typename K, typename V, typename COMPARATOR
= std::less<K>> virtual std::vector<K> decaf::util::Map< K, V,
COMPARATOR >::keySet () const [pure virtual]`

Returns a **Set** (p. 3439) view of the mappings contained in this map. The set is backed by the map, so changes to the map are reflected in the set, and vice-versa. If the map is modified while an iteration over the set is in progress (except through the iterator's own remove operation, or through the setValue operation on a map entry returned by the iterator) the results of the iteration are undefined. The set supports element removal, which removes the corresponding mapping from the map, via the **Iterator.remove** (p. 2155), **Set.remove** (p. 187), **removeAll**, **retainAll** and **clear** operations. It does not support the **add** or **addAll** operations.

Returns:

the entire set of keys in this map as a std::vector.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1240), decaf::util::StlMap< K, V, COMPARATOR > (p. 3609), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1240), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1240), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3609), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3609), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3609), decaf::util::StlMap< std::string, cms::Queue * > (p. 3609), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3609), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, TransportFactory * > (p. 3609), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< int, Pointer< Command > > (p. 3609),

decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedProducer * > (p. 3609), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3609).

Referenced by decaf::util::StlMap< std::string, cms::Topic * >::equals(), and decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::equals().

```
6.501.3.10  template<typename K, typename V, typename COMPARATOR
            = std::less<K>> virtual void decaf::util::Map< K, V,
            COMPARATOR >::put (const K & key, const V & value) throw (
            decaf::lang::exceptions::UnsupportedOperationException ) [pure
            virtual]
```

Sets the value for the specified key.

Parameters:

key The target key.

value The value to be set.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1242), decaf::util::StlMap< K, V, COMPARATOR > (p. 3610), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1242), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1242), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1242), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1242), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1242), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1242), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3610), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3610), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3610), decaf::util::StlMap< std::string, cms::Queue * > (p. 3610), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3610), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, TransportFactory * > (p. 3610), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< int, Pointer< Command > > (p. 3610), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, CachedProducer * > (p. 3610), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3610).

6.501.3.11 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::Map< K, V, COMPARATOR >::putAll (const Map< K, V, COMPARATOR > & other) throw (decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]`

Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.

Parameters:

other A **Map** (p. 2459) instance whose elements are to all be inserted in this **Map** (p. 2459).

Exceptions:

UnsupportedOperationException If the implementing class does not support the putAll operation.

Implemented in `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1242), `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3611), `decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >` (p. 1242), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p. 1242), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p. 1242), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p. 1242), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p. 1242), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p. 1242), `decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR >` (p. 3611), `decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR >` (p. 3611), `decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR >` (p. 3611), and `decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR >` (p. 3611).

6.501.3.12 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual V decaf::util::Map< K, V, COMPARATOR >::remove (const K & key) throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]`

Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.

Parameters:

key The search key.

Returns:

a copy of the element that was previously mapped to the given key

Exceptions:

NoSuchElementException if this key is not in the **Map** (p. 2459).

UnsupportedOperationException if this map is unmodifiable.

Implemented in **decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >** (p. 1244), **decaf::util::StlMap< K, V, COMPARATOR >** (p. 3611), **decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >** (p. 1244), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >** (p. 1244), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >** (p. 1244), **decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >** (p. 1244), **decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >** (p. 1244), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >** (p. 1244), **decaf::util::StlMap< cms::Session *, SessionResolver * >** (p. 3611), **decaf::util::StlMap< std::string, WireFormatFactory * >** (p. 3611), **decaf::util::StlMap< std::string, PrimitiveValueNode >** (p. 3611), **decaf::util::StlMap< std::string, cms::Queue * >** (p. 3611), **decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR >** (p. 3611), **decaf::util::StlMap< std::string, CachedConsumer * >** (p. 3611), **decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR >** (p. 3611), **decaf::util::StlMap< std::string, TransportFactory * >** (p. 3611), **decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR >** (p. 3611), **decaf::util::StlMap< int, Pointer< Command > >** (p. 3611), **decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR >** (p. 3611), **decaf::util::StlMap< std::string, CachedProducer * >** (p. 3611), and **decaf::util::StlMap< std::string, cms::Topic * >** (p. 3611).

6.501.3.13 `template<typename K, typename V, typename COMPARATOR
= std::less<K>> virtual std::size_t decaf::util::Map< K, V,
COMPARATOR >::size () const [pure virtual]`

Returns:

The number of elements (key/value pairs) in this map.

Implemented in **decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >** (p. 1246), **decaf::util::StlMap< K, V, COMPARATOR >** (p. 3612), **decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >** (p. 1246), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >** (p. 1246), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >** (p. 1246), **decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >** (p. 1246), **decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >** (p. 1246),

decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1246), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3612), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3612), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3612), decaf::util::StlMap< std::string, cms::Queue * > (p. 3612), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3612), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, TransportFactory * > (p. 3612), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< int, Pointer< Command > > (p. 3612), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, CachedProducer * > (p. 3612), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3612).

6.501.3.14 `template<typename K, typename V, typename COMPARATOR
= std::less<K>> virtual std::vector<V> decaf::util::Map< K, V,
COMPARATOR >::values () const [pure virtual]`

Returns:

the entire set of values in this map as a std::vector.

Implemented in decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1246), decaf::util::StlMap< K, V, COMPARATOR > (p. 3612), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1246), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1246), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1246), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1246), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1246), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1246), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3612), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3612), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3612), decaf::util::StlMap< std::string, cms::Queue * > (p. 3612), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3612), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, TransportFactory * > (p. 3612), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< int, Pointer< Command > > (p. 3612), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3612), decaf::util::StlMap< std::string, CachedProducer * > (p. 3612), and decaf::util::StlMap< std::string, cms::Topic * > (p. 3612).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Map.h`

6.502 cms::MapMessage Class Reference

A **MapMessage** (p. 2472) object is used to send a set of name-value pairs.

#include <src/main/cms/MapMessage.h> Inheritance diagram for cms::MapMessage:

Public Member Functions

- virtual **~MapMessage** ()
- virtual std::vector< std::string > **getMapNames** () const =0 throw (CMSEException)
*Returns an Enumeration of all the names in the **MapMessage** (p. 2472) object.*
- virtual bool **itemExists** (const std::string &name) const =0 throw (CMSEException)
*Indicates whether an item exists in this **MapMessage** (p. 2472) object.*
- virtual bool **getBoolean** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)
Returns the Boolean value of the Specified name.
- virtual void **setBoolean** (const std::string &name, bool value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a boolean value with the specified name into the Map.
- virtual unsigned char **getByte** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)
Returns the Byte value of the Specified name.
- virtual void **setByte** (const std::string &name, unsigned char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Byte value with the specified name into the Map.
- virtual std::vector< unsigned char > **getBytes** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)
Returns the Bytes value of the Specified name.
- virtual void **setBytes** (const std::string &name, const std::vector< unsigned char > &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Bytes value with the specified name into the Map.
- virtual char **getChar** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)
Returns the Char value of the Specified name.
- virtual void **setChar** (const std::string &name, char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets a Char value with the specified name into the Map.
- virtual double **getDouble** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the Double value of the Specified name.

- virtual void **setDouble** (const std::string &name, double value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a Double value with the specified name into the Map.

- virtual float **getFloat** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the Float value of the Specified name.

- virtual void **setFloat** (const std::string &name, float value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a Float value with the specified name into the Map.

- virtual int **getInt** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the Int value of the Specified name.

- virtual void **setInt** (const std::string &name, int value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a Int value with the specified name into the Map.

- virtual long long **getLong** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the Long value of the Specified name.

- virtual void **setLong** (const std::string &name, long long value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a Long value with the specified name into the Map.

- virtual short **getShort** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the Short value of the Specified name.

- virtual void **setShort** (const std::string &name, short value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a Short value with the specified name into the Map.

- virtual std::string **getString** (const std::string &name) const =0 throw (cms::MessageFormatException, cms::CMSEException)

Returns the String value of the Specified name.

- virtual void **setString** (const std::string &name, const std::string &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Sets a String value with the specified name into the Map.

6.502.1 Detailed Description

A **MapMessage** (p.2472) object is used to send a set of name-value pairs. The names are String objects, and the values are primitive data types in the Java programming language. The

names must have a value that is not null, and not an empty string. The entries can be accessed sequentially or randomly by name. The order of the entries is undefined. **MapMessage** (p. 2472) inherits from the **Message** (p. 2534) interface and adds a message body that contains a Map.

When a client receives a **MapMessage** (p. 2472), it is in read-only mode. If a client attempts to write to the message at this point, a **MessageNotWriteableException** (p. 2724) is thrown. To place the **MapMessage** (p. 2472) back into a state where it can be read from and written to, call the `clearBody` method.

MapMessage (p. 2472) objects support the following conversion table. The marked cases must be supported. The unmarked cases must throw a **CMSEException** (p. 1160). The String-to-primitive conversions may throw a **MessageFormatException** (p. 2662) if the primitive's `valueOf()` method does not accept it as a valid String representation of the primitive.

A value written as the row type can be read as the column type.

	boolean	byte	short	char	int	long	float	double	String	byte[]
boolean	X								X	
byte		X	X		X	X			X	
short			X		X	X			X	
char				X					X	
int					X	X			X	
long						X			X	
float							X	X	X	
double								X	X	
String	X	X	X		X	X	X	X	X	
byte[]										X

Since:

1.0

6.502.2 Constructor & Destructor Documentation

6.502.2.1 `virtual cms::MapMessage::~~MapMessage () [inline, virtual]`

6.502.3 Member Function Documentation

6.502.3.1 `virtual bool cms::MapMessage::getBoolean (const std::string & name)
const throw (cms::MessageFormatException, cms::CMSEException)
[pure virtual]`

Returns the Boolean value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 364).

6.502.3.2 virtual unsigned char cms::MapMessage::getBytes (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [pure virtual]

Returns the Byte value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 365).

6.502.3.3 virtual std::vector<unsigned char> cms::MapMessage::getBytes (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [pure virtual]

Returns the Bytes value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 365).

6.502.3.4 virtual char cms::MapMessage::getChar (const std::string & *name*) const throw (cms::MessageFormatException, cms::CMSException) [pure virtual]

Returns the Char value of the Specified name.

Parameters:

name name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 365).

6.502.3.5 `virtual double cms::MapMessage::getDouble (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException)` [pure virtual]

Returns the Double value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 366).

6.502.3.6 `virtual float cms::MapMessage::getFloat (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException)` [pure virtual]

Returns the Float value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 366).

6.502.3.7 `virtual int cms::MapMessage::getInt (const std::string & name) const throw (cms::MessageFormatException, cms::CMSEException)` [pure virtual]

Returns the Int value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 366).

6.502.3.8 `virtual long long cms::MapMessage::getLong (const std::string & name)
 const throw (cms::MessageFormatException, cms::CMSException)
 [pure virtual]`

Returns the Long value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 367).

6.502.3.9 `virtual std::vector< std::string > cms::MapMessage::getMapNames ()
 const throw (CMSException) [pure virtual]`

Returns an Enumeration of all the names in the `MapMessage` (p. 2472) object.

Returns:

STL Vector of String values, each of which is the name of an item in the `MapMessage` (p. 2472)

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 367).

6.502.3.10 `virtual short cms::MapMessage::getShort (const std::string & name)
 const throw (cms::MessageFormatException, cms::CMSException)
 [pure virtual]`

Returns the Short value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 368).

6.502.3.11 `virtual std::string cms::MapMessage::getString (const std::string & name) const throw (cms::MessageFormatException, cms::CMSException) [pure virtual]`

Returns the String value of the Specified name.

Parameters:

name Name of the value to fetch from the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 368).

6.502.3.12 `virtual bool cms::MapMessage::itemExists (const std::string & name) const throw (CMSException) [pure virtual]`

Indicates whether an item exists in this `MapMessage` (p. 2472) object.

Parameters:

name String name of the Object in question

Returns:

boolean value indicating if the name is in the map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 368).

6.502.3.13 `virtual void cms::MapMessage::setBoolean (const std::string & name, bool value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Sets a boolean value with the specified name into the Map.

Parameters:

name the name of the boolean

value the boolean value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageNotWritableException - if the `Message` (p. 2534) is in Read-only Mode.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 369).

6.502.3.14 `virtual void cms::MapMessage::setByte (const std::string & name, unsigned char value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Sets a Byte value with the specified name into the Map.

Parameters:

name the name of the Byte
value the Byte value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.
MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 369).

6.502.3.15 `virtual void cms::MapMessage::setBytes (const std::string & name, const std::vector< unsigned char > & value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Sets a Bytes value with the specified name into the Map.

Parameters:

name The name of the Bytes
value The Bytes value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.
MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 370).

6.502.3.16 `virtual void cms::MapMessage::setChar (const std::string & name, char value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Sets a Char value with the specified name into the Map.

Parameters:

name the name of the Char
value the Char value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 370).

6.502.3.17 `virtual void cms::MapMessage::setDouble (const std::string & name, double value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Sets a Double value with the specified name into the Map.

Parameters:

name The name of the Double

value The Double value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 370).

6.502.3.18 `virtual void cms::MapMessage::setFloat (const std::string & name, float value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Sets a Float value with the specified name into the Map.

Parameters:

name The name of the Float

value The Float value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 371).

6.502.3.19 `virtual void cms::MapMessage::setInt (const std::string & name, int value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Sets a Int value with the specified name into the Map.

Parameters:

name The name of the Int

value The Int value to set in the Map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 371).

6.502.3.20 virtual void cms::MapMessage::setLong (const std::string & *name*, long long *value*) throw (cms::MessageNotWriteableException, cms::CMSEException) [pure virtual]

Sets a Long value with the specified name into the Map.

Parameters:

name The name of the Long

value The Long value to set in the Map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 371).

6.502.3.21 virtual void cms::MapMessage::setShort (const std::string & *name*, short *value*) throw (cms::MessageNotWriteableException, cms::CMSEException) [pure virtual]

Sets a Short value with the specified name into the Map.

Parameters:

name The name of the Short

value The Short value to set in the Map

Exceptions:

CMSEException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 372).

6.502.3.22 `virtual void cms::MapMessage::setString (const std::string & name,
const std::string & value) throw (cms::MessageNotWriteableException,
cms::CMSException)` [pure virtual]

Sets a String value with the specified name into the Map.

Parameters:

name The name of the String

value The String value to set in the Map

Exceptions:

CMSException (p. 1160) - if the operation fails due to an internal error.

MessageNotWriteableException (p. 2724) - if the **Message** (p. 2534) is in Read-only Mode.

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 372).

The documentation for this class was generated from the following file:

- `src/main/cms/MapMessage.h`

6.503 decaf::util::logging::MarkBlockLogger Class Reference

Defines a class that can be used to mark the entry and exit from scoped blocks.

```
#include <src/main/decaf/util/logging/MarkBlockLogger.h>
```

Public Member Functions

- **MarkBlockLogger** (**Logger** *logger, const std::string &blockName)
Constructor - Marks Block entry.
- virtual ~**MarkBlockLogger** ()

6.503.1 Detailed Description

Defines a class that can be used to mark the entry and exit from scoped blocks. Create an instance of this class at the start of a scoped block, passing it the logger to use and the name of the block. The block entry and exit will be marked using the scope name, logger to the logger at the MARKBLOCK log level.

6.503.2 Constructor & Destructor Documentation

6.503.2.1 decaf::util::logging::MarkBlockLogger::MarkBlockLogger (**Logger** *logger, const std::string & blockName) [inline]

Constructor - Marks Block entry.

Parameters:

logger **Logger** (p.2386) to use
blockName Block name

6.503.2.2 virtual decaf::util::logging::MarkBlockLogger::~~MarkBlockLogger () [inline, virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/MarkBlockLogger.h

6.504 activemq::wireformat::MarshalAware Class Reference

#include <src/main/activemq/wireformat/MarshalAware.h> Inheritance diagram for activemq::wireformat::MarshalAware:

Public Member Functions

- virtual `~MarshalAware ()`
- virtual `bool isMarshalAware () const =0`
Determine if the class implementing this interface is really wanting to be told about marshaling.
- virtual `void beforeMarshal (WireFormat *wireFormat)=0 throw (decaf::io::IOException)`
Called before marshaling is started to prepare the object to be marshaled.
- virtual `void afterMarshal (WireFormat *wireFormat)=0 throw (decaf::io::IOException)`
Called after marshaling is started to cleanup the object being marshaled.
- virtual `void beforeUnmarshal (WireFormat *wireFormat)=0 throw (decaf::io::IOException)`
Called before unmarshaling is started to prepare the object to be unmarshaled.
- virtual `void afterUnmarshal (WireFormat *wireFormat)=0 throw (decaf::io::IOException)`
Called after unmarshaling is started to cleanup the object being unmarshaled.
- virtual `void setMarshaledForm (WireFormat *wireFormat, const std::vector< char > &data)=0`
Called to set the data to this object that will contain the objects marshaled form.
- virtual `std::vector< unsigned char > getMarshaledForm (WireFormat *wireFormat)=0`
Called to get the data to this object that will contain the objects marshaled form.

6.504.1 Constructor & Destructor Documentation

- 6.504.1.1** `virtual activemq::wireformat::MarshalAware::~~MarshalAware ()`
 [inline, virtual]

6.504.2 Member Function Documentation

- 6.504.2.1** `virtual void activemq::wireformat::MarshalAware::afterMarshal (WireFormat * wireFormat) throw (decaf::io::IOException)` [pure virtual]

Called after marshaling is started to cleanup the object being marshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control marshaling

6.504.2.2 virtual void activemq::wireformat::MarshalAware::afterUnmarshal
(WireFormat * *wireFormat*) throw (decaf::io::IOException) [pure
virtual]

Called after unmarshaling is started to cleanup the object being unmarshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control unmarshaling

6.504.2.3 virtual void activemq::wireformat::MarshalAware::beforeMarshal
(WireFormat * *wireFormat*) throw (decaf::io::IOException) [pure
virtual]

Called before marshaling is started to prepare the object to be marshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control marshaling

Implemented in **activemq::commands::ActiveMQMapMessage** (p. 363), and **activemq::commands::ActiveMQTextMessage** (p. 663).

6.504.2.4 virtual void activemq::wireformat::MarshalAware::beforeUnmarshal
(WireFormat * *wireFormat*) throw (decaf::io::IOException) [pure
virtual]

Called before unmarshaling is started to prepare the object to be unmarshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control unmarshaling

6.504.2.5 virtual std::vector<unsigned char> activemq::wireformat::MarshalAware::getMarshaledForm
(WireFormat * *wireFormat*) [pure virtual]

Called to get the data to this object that will contain the objects marshaled form.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control unmarshaling

Returns:

buffer that holds the objects data.

6.504.2.6 `virtual bool activemq::wireformat::MarshalAware::isMarshalAware ()` `const` [pure virtual]

Determine if the class implementing this interface is really wanting to be told about marshaling. Normally if you didn't want to be marshal aware you just wouldn't implement this interface but since this is C++ and we don't have true interfaces we need a flat inheritance hierarchy, so we always implement this.

Returns:

true if this class cares about marshaling.

Implemented in `activemq::commands::ActiveMQMapMessage` (p. 368), `activemq::commands::BaseDataStructure` (p. 832), `activemq::commands::Message` (p. 2526), and `activemq::commands::WireFormatInfo` (p. 3987).

6.504.2.7 `virtual void activemq::wireformat::MarshalAware::setMarshaledForm` `(WireFormat * wireFormat, const std::vector< char > & data)` [pure virtual]

Called to set the data to this object that will contain the objects marshaled form.

Parameters:

wireFormat - the `wireformat` (p. 105) object to control unmarshaling
data - vector of object binary data

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/MarshalAware.h`

6.505 activemq::wireformat::openwire::marshal::v6::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v6/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure(OpenWireFormat *format)`

6.505.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.505.2 Constructor & Destructor Documentation

- 6.505.2.1 virtual
activemq::wireformat::openwire::marshal::v6::MarshallerFactory::~MarshallerFactory()
[inline, virtual]

6.505.3 Member Function Documentation

- 6.505.3.1 virtual void ac-
tivemq::wireformat::openwire::marshal::v6::MarshallerFactory::configure
(OpenWireFormat * *format*) [virtual]

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**MarshallerFactory.h**

6.506 activemq::wireformat::openwire::marshal::v3::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v3/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure(OpenWireFormat *format)`

6.506.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.506.2 Constructor & Destructor Documentation

- 6.506.2.1** virtual
`activemq::wireformat::openwire::marshal::v3::MarshallerFactory::~MarshallerFactory()` [inline, virtual]

6.506.3 Member Function Documentation

- 6.506.3.1** virtual void `activemq::wireformat::openwire::marshal::v3::MarshallerFactory::configure(OpenWireFormat * format)` [virtual]

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/MarshallerFactory.h`

6.507 activemq::wireformat::openwire::marshal::v4::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v4/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure(OpenWireFormat *format)`

6.507.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.507.2 Constructor & Destructor Documentation

6.507.2.1 virtual
`activemq::wireformat::openwire::marshal::v4::MarshallerFactory::~MarshallerFactory()` [inline, virtual]

6.507.3 Member Function Documentation

6.507.3.1 virtual void `ac-`
`tivemq::wireformat::openwire::marshal::v4::MarshallerFactory::configure`
`(OpenWireFormat * format)` [virtual]

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/MarshallerFactory.h`

6.508 activemq::wireformat::openwire::marshal::v5::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v5/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure(OpenWireFormat *format)`

6.508.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.508.2 Constructor & Destructor Documentation

- 6.508.2.1** virtual
`activemq::wireformat::openwire::marshal::v5::MarshallerFactory::~MarshallerFactory()` [inline, virtual]

6.508.3 Member Function Documentation

- 6.508.3.1** virtual void `activemq::wireformat::openwire::marshal::v5::MarshallerFactory::configure(OpenWireFormat * format)` [virtual]

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/MarshallerFactory.h`

6.509 activemq::wireformat::openwire::marshal::v1::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v1/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure (OpenWireFormat *format)`

6.509.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.509.2 Constructor & Destructor Documentation

- 6.509.2.1 virtual
activemq::wireformat::openwire::marshal::v1::MarshallerFactory::~MarshallerFactory
() [inline, virtual]

6.509.3 Member Function Documentation

- 6.509.3.1 virtual void ac-
tivemq::wireformat::openwire::marshal::v1::MarshallerFactory::configure
(OpenWireFormat * *format*) [virtual]

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**MarshallerFactory.h**

6.510 activemq::wireformat::openwire::marshal::v2::MarshallerFactory Class Reference

Used to create marshallers for a specific version of the wire protocol.

```
#include <src/main/activemq/wireformat/openwire/marshal/v2/MarshallerFactory.h>
```

Public Member Functions

- virtual `~MarshallerFactory()`
- virtual void `configure(OpenWireFormat *format)`

6.510.1 Detailed Description

Used to create marshallers for a specific version of the wire protocol. NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Groovy scripts in the activemq-openwire-generator module

6.510.2 Constructor & Destructor Documentation

- 6.510.2.1** virtual
`activemq::wireformat::openwire::marshal::v2::MarshallerFactory::~MarshallerFactory()` [inline, virtual]

6.510.3 Member Function Documentation

- 6.510.3.1** virtual void `activemq::wireformat::openwire::marshal::v2::MarshallerFactory::configure(OpenWireFormat * format)` [virtual]

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/MarshallerFactory.h`

6.511 activemq::util::MarshallingSupport Class Reference

```
#include <src/main/activemq/util/MarshallingSupport.h>
```

Public Member Functions

- **MarshallingSupport** ()
- virtual **~MarshallingSupport** ()

Static Public Member Functions

- static void **writeString** (decaf::io::DataOutputStream &dataOut, const std::string &value) throw (decaf::io::IOException)

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string.

- static void **writeString16** (decaf::io::DataOutputStream &dataOut, const std::string &value) throw (decaf::io::IOException)

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string.

- static void **writeString32** (decaf::io::DataOutputStream &dataOut, const std::string &value) throw (decaf::io::IOException)

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string.

- static std::string **readString16** (decaf::io::DataInputStream &dataIn) throw (decaf::io::IOException)

Reads an Openwire encoded string from the provided DataInputStream.

- static std::string **readString32** (decaf::io::DataInputStream &dataIn) throw (decaf::io::IOException)

Reads an Openwire encoded string from the provided DataInputStream.

- static std::string **asciiToModifiedUtf8** (const std::string &asciiString) throw (decaf::io::UTFDataFormatException)

Given an ASCII String with byte values [0..255] convert the string to a string containing the modified UTF-8 form of that same string.

- static std::string **modifiedUtf8ToAscii** (const std::string modifiedUtf8String) throw (decaf::io::UTFDataFormatException)

Given a string that contains bytes in the Java Modified UTF-8 format convert that string back into ASCII values from [0..255].

6.511.1 Constructor & Destructor Documentation

6.511.1.1 `activemq::util::MarshallingSupport::MarshallingSupport ()`

6.511.1.2 `virtual activemq::util::MarshallingSupport::~~MarshallingSupport ()`
[virtual]

6.511.2 Member Function Documentation

6.511.2.1 `static std::string activemq::util::MarshallingSupport::asciiToModifiedUtf8 (const std::string & asciiString) throw (decaf::io::UTFDataFormatException)` [static]

Given an ASCII String with byte values [0..255] convert the string to a string containing the modified UTF-8 form of that same string. This allows an ASCII string containing values greater than 127 as well as embedded NULLs to be sent to a Java client.

Parameters:

asciiString The ASCII string to encode as Modified UTF-8

Returns:

a string containing the Modified UTF-8 encoded form of the provided string.

Exceptions:

UTFDataFormatException if the length of the encoded string would exceed the size of an signed integer.

6.511.2.2 `static std::string activemq::util::MarshallingSupport::modifiedUtf8ToAscii (const std::string modifiedUtf8String) throw (decaf::io::UTFDataFormatException)` [static]

Given a string that contains bytes in the Java Modified UTF-8 format convert that string back into ASCII values from [0..255]. This will handle any string sent from a Java client which contains values within the [0..255] range or has embedded Nulls. Strings that have encoded values greater than 255 will cause an exception to be thrown.

Parameters:

modifiedUtf8String The string to convert from Modified UTF-8 to ASCII.

Returns:

the ASCII encoded version of the provided string.

Exceptions:

UTFDataFormatException if the provided string contains invalid data or the character values encoded in the string exceed ASCII value 255.

6.511.2.3 `static std::string activemq::util::MarshallingSupport::readString16
 (decaf::io::DataInputStream & dataIn) throw (decaf::io::IOException)
 [static]`

Reads an Openwire encoded string from the provided DataInputStream. No string processing is performed by this method, clients that know the data contains UTF-8 encoded content must use one of the utility methods of this class to decode the UTF-8 data.

This version assumes a size prefix of 16bits.

Parameters:

dataIn The DataInputStream to read the String data from.

Returns:

the String value.

Exceptions:

IOException if an I/O error occurs while writing the string.

6.511.2.4 `static std::string activemq::util::MarshallingSupport::readString32
 (decaf::io::DataInputStream & dataIn) throw (decaf::io::IOException)
 [static]`

Reads an Openwire encoded string from the provided DataInputStream. No string processing is performed by this method, clients that know the data contains UTF-8 encoded content must use one of the utility methods of this class to decode the UTF-8 data.

This version assumes a size prefix of 32bits.

Parameters:

dataIn The DataInputStream to read the String data from.

Returns:

the String value.

Exceptions:

IOException if an I/O error occurs while writing the string.

6.511.2.5 `static void activemq::util::MarshallingSupport::writeString
 (decaf::io::DataOutputStream & dataOut, const std::string & value)
 throw (decaf::io::IOException) [static]`

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string. User must encode to Modified UTF-8 as needed.

Parameters:

dataOut The DataOutputStream to write the String data to.

value Thre String value to write in Openwire form.

Exceptions:

IOException if an I/O error occurs while writing the string.

6.511.2.6 `static void activemq::util::MarshallingSupport::writeString16`
(`decaf::io::DataOutputStream & dataOut, const std::string & value`)
`throw (decaf::io::IOException) [static]`

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string. User must encode to Modified UTF-8 as needed. This method write out only the size as a short and the string data no Openwire Type tag is appended.

Parameters:

dataOut The DataOutputStream to write the String data to.

value Thre String value to write in Openwire form.

Exceptions:

IOException if an I/O error occurs while writing the string.

6.511.2.7 `static void activemq::util::MarshallingSupport::writeString32`
(`decaf::io::DataOutputStream & dataOut, const std::string & value`)
`throw (decaf::io::IOException) [static]`

Write the string object to the given DataOutputStream as Raw bytes, no string encoding is done on this char values in the string. User must encode to Modified UTF-8 as needed. This method write out only the size as a int and the string data no Openwire Type tag is appended.

Parameters:

dataOut The DataOutputStream to write the String data to.

value Thre String value to write in Openwire form.

Exceptions:

IOException if an I/O error occurs while writing the string.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/MarshallingSupport.h`

6.512 decaf::lang::Math Class Reference

The class `Math` (p. 2497) contains methods for performing basic numeric operations such as the elementary exponential, logarithm, square root, and trigonometric functions.

```
#include <src/main/decaf/lang/Math.h>
```

Public Member Functions

- `Math ()`
- `virtual ~Math ()`

Static Public Member Functions

- static int **abs** (int value)
Returns the absolute value of an int value.
- static long long **abs** (long long value)
Returns the absolute value of an long long value.
- static float **abs** (float value)
Returns the absolute value of a float value.
- static double **abs** (double value)
Returns the absolute value of a double value.
- static double **sqrt** (double value)
Returns the arc cosine of an angle, in the range of 0.0 through pi.
- static double **pow** (double base, double exp)
Returns the value of the first argument raised to the power of the second argument.
- static short **min** (short a, short b)
Returns the double value that is closest in value to the argument and is equal to a mathematical integer.
- static int **min** (int a, int b)
*Returns the smaller of two *int* values.*
- static unsigned int **min** (unsigned int a, unsigned int b)
*Returns the smaller of two *unsigned int* values.*
- static long long **min** (long long a, long long b)
*Returns the smaller of two *long long* values.*
- static float **min** (float a, float b)
Returns the smaller of two float values.
- static double **min** (double a, double b)
Returns the smaller of two double values.

- static short **max** (short a, short b)
*Returns the larger of two **short** values.*
- static int **max** (int a, int b)
*Returns the larger of two **int** values.*
- static long long **max** (long long a, long long b)
*Returns the larger of two **long long** values.*
- static float **max** (float a, float b)
Returns the greater of two float values.
- static double **max** (double a, double b)
Returns the greater of two double values.
- static double **ceil** (double value)
Returns the natural logarithm (base e) of a double value.
- static double **floor** (double value)
Returns the largest (closest to positive infinity) double value that is less than or equal to the argument and is equal to a mathematical integer.
- static int **round** (float value)
Returns the closest int to the argument.
- static long long **round** (double value)
Returns the closest long long to the argument.
- static double **random** ()
Computes the remainder operation on two arguments as prescribed by the IEEE 754 standard.
- static float **signum** (float value)
Returns Euler's number e raised to the power of a double value.
- static double **signum** (double value)
Returns the signum function of the argument; zero if the argument is zero, 1.0f if the argument is greater than zero, -1.0f if the argument is less than zero.
- static double **toRadians** (double angdeg)
Returns the measure in radians of the supplied degree angle.
- static double **toDegrees** (double angrad)
Returns the measure in degrees of the supplied radian angle.

Static Public Attributes

- static const double **E**
- static const double **PI**

6.512.1 Detailed Description

The class `Math` (p. 2497) contains methods for performing basic numeric operations such as the elementary exponential, logarithm, square root, and trigonometric functions.

6.512.2 Constructor & Destructor Documentation

6.512.2.1 `decaf::lang::Math::Math ()` [inline]

6.512.2.2 `virtual decaf::lang::Math::~~Math ()` [inline, virtual]

6.512.3 Member Function Documentation

6.512.3.1 `static double decaf::lang::Math::abs (double value)` [static]

Returns the absolute value of a double value. If the argument is not negative, the argument is returned. If the argument is negative, the negation of the argument is returned. Special cases:

- o If the argument is positive zero or negative zero, the result is positive zero.
- o If the argument is infinite, the result is positive infinity.
- o If the argument is NaN, the result is NaN.

In other words, the result is the same as the value of the expression: `Double::longBitsToDouble` (p. 1794)(`0x7fffffffffffffffULL & Double::doubleToLongBits(value)`)

Parameters:

value - the value to return the abs of

Returns:

the value if positive, otherwise the negative of value

6.512.3.2 `static float decaf::lang::Math::abs (float value)` [static]

Returns the absolute value of a float value. If the argument is not negative, the argument is returned. If the argument is negative, the negation of the argument is returned. Special cases:

- o If the argument is positive zero or negative zero, the result is positive zero.
- o If the argument is infinite, the result is positive infinity.
- o If the argument is NaN, the result is NaN.

In other words, the result is the same as the value of the expression: `Float::intBitsToFloat` (p. 1909)(`0x7fffffff & Float::floatToIntBits(value)`)

Parameters:

value - the value to return the abs of

Returns:

the value if positive, otherwise the negative of value

6.512.3.3 `static long long decaf::lang::Math::abs (long long value)` [inline, static]

Returns the absolute value of an long long value. If the argument is not negative, the argument is returned. If the argument is negative, the negation of the argument is returned.

Parameters:

value - the value to return the abs of

Returns:

the value if positive, otherwise the negative of value

6.512.3.4 static int decaf::lang::Math::abs (int *value*) [inline, static]

Returns the absolute value of an int value. If the argument is not negative, the argument is returned. If the argument is negative, the negation of the argument is returned.

Parameters:

value - the value to return the abs of

Returns:

the value if positive, otherwise the negative of value

6.512.3.5 static double decaf::lang::Math::ceil (double *value*) [static]

Returns the natural logarithm (base e) of a double value. Special cases:

o If the argument is NaN or less than zero, then the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is positive zero or negative zero, then the result is negative infinity.

Parameters:

value the value to compute the natural log of.

Returns:

the natural log of value. Returns the base 10 logarithm of a double value. Special cases:

o If the argument is NaN or less than zero, then the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is positive zero or negative zero, then the result is negative infinity. o If the argument is equal to 10ⁿ for integer n, then the result is n.

Parameters:

value - the value to operate on

Returns:

the long base 10 of value Returns the natural logarithm of the sum of the argument and 1. Note that for small values x, the result of log1p(x) is much closer to the true result of ln(1 + x) than the floating-point evaluation of log(1.0+x).

Special cases:

o If the argument is NaN or less than -1, then the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is negative one, then the result is negative infinity. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the value to operate on

Returns:

the the value $\ln(x + 1)$, the natural log of $x + 1$ Returns the smallest (closest to negative infinity) double value that is greater than or equal to the argument and is equal to a mathematical integer. Special cases:

o If the argument value is already equal to a mathematical integer, then the result is the same as the argument. o If the argument is NaN or an infinity or positive zero or negative zero, then the result is the same as the argument. o If the argument value is less than zero but greater than -1.0, then the result is negative zero.

Note that the value of `Math.ceil(x)` is exactly the value of `-Math.floor(-x)`.

Parameters:

value - the value to find the ceiling of

Returns:

the smallest (closest to negative infinity) floating-point value that is greater than or equal to the argument and is equal to a mathematical integer.

6.512.3.6 static double decaf::lang::Math::floor (double *value*) [static]

Returns the largest (closest to positive infinity) double value that is less than or equal to the argument and is equal to a mathematical integer. Special cases:

o If the argument value is already equal to a mathematical integer, then the result is the same as the argument. o If the argument is NaN or an infinity or positive zero or negative zero, then the result is the same as the argument.

Parameters:

value - the value to find the floor of

Returns:

the largest (closest to positive infinity) floating-point value that less than or equal to the argument and is equal to a mathematical integer.

6.512.3.7 static double decaf::lang::Math::max (double *a*, double *b*) [static]

Returns the greater of two double values. That is, the result is the argument closer to positive infinity. If the arguments have the same value, the result is that same value. If either value is NaN, then the result is NaN. Unlike the numerical comparison operators, this method considers negative zero to be strictly smaller than positive zero. If one argument is positive zero and the other negative zero, the result is positive zero.

Parameters:

a - an argument.

b - another argument.

Returns:

the larger of a and b .

6.512.3.8 static float decaf::lang::Math::max (float *a*, float *b*) [static]

Returns the greater of two float values. That is, the result is the argument closer to positive infinity. If the arguments have the same value, the result is that same value. If either value is NaN, then the result is NaN. Unlike the numerical comparison operators, this method considers negative zero to be strictly smaller than positive zero. If one argument is positive zero and the other negative zero, the result is positive zero.

Parameters:

a - an argument.

b - another argument.

Returns:

the larger of **a** and **b**.

```
6.512.3.9 static long long decaf::lang::Math::max (long long a, long long b)
[inline, static]
```

Returns the larger of two `long long` values. That is, the result the argument closer to the value of `Long::MAX_VALUE` (p.2433). If the arguments have the same value, the result is that same value.

Parameters:

a - an argument.

b - another argument.

Returns:

the larger of a and b .

```
6.512.3.10 static int decaf::lang::Math::max (int a, int b) [inline, static]
```

Returns the larger of two `int` values. That is, the result the argument closer to the value of `Integer::MAX_VALUE` (p.2090). If the arguments have the same value, the result is that same value.

Parameters:

a - an argument.

b - another argument.

Returns:

the larger of a and b .

6.512.3.11 static short decaf::lang::Math::max (short *a*, short *b*) [inline, static]

Returns the larger of two `short` values. That is, the result the argument closer to the value of `Short::MAX_VALUE` (p.3448). If the arguments have the same value, the result is that same value.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the larger of *a* and *b*.

6.512.3.12 static double decaf::lang::Math::min (double *a*, double *b*) [static]

Returns the smaller of two double values. That is, the result is the value closer to negative infinity. If the arguments have the same value, the result is that same value. If either value is NaN, then the result is NaN. Unlike the numerical comparison operators, this method considers negative zero to be strictly smaller than positive zero. If one argument is positive zero and the other is negative zero, the result is negative zero.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.13 static float decaf::lang::Math::min (float *a*, float *b*) [static]

Returns the smaller of two float values. That is, the result is the value closer to negative infinity. If the arguments have the same value, the result is that same value. If either value is NaN, then the result is NaN. Unlike the numerical comparison operators, this method considers negative zero to be strictly smaller than positive zero. If one argument is positive zero and the other is negative zero, the result is negative zero.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.14 `static long long decaf::lang::Math::min (long long a, long long b)`
[inline, static]

Returns the smaller of two `long long` values. That is, the result the argument closer to the value of `Long::MIN_VALUE` (p.2433). If the arguments have the same value, the result is that same value.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.15 `static unsigned int decaf::lang::Math::min (unsigned int a, unsigned int b)`
[inline, static]

Returns the smaller of two `unsigned int` values. That is, the result the argument closer to the value of `Integer::MIN_VALUE` (p.2090). If the arguments have the same value, the result is that same value.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.16 `static int decaf::lang::Math::min (int a, int b)` [inline, static]

Returns the smaller of two `int` values. That is, the result the argument closer to the value of `Integer::MIN_VALUE` (p.2090). If the arguments have the same value, the result is that same value.

Parameters:

- a* - an argument.
- b* - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.17 `static short decaf::lang::Math::min (short a, short b)` [inline, static]

Returns the double value that is closest in value to the argument and is equal to a mathematical integer. If two double values that are mathematical integers are equally close, the result is the integer value that is even. Special cases:

o If the argument value is already equal to a mathematical integer, then the result is the same as the argument. o If the argument is NaN or an infinity or positive zero or negative zero, then the result is the same as the argument.

Parameters:

value - the value to round to the nearest integer

Returns:

the rounded value Returns the smaller of two short values. That is, the result is the argument closer to the value of `decaf.lang.Short::MIN_VALUE` (p. 3448). If the arguments have the same value, the result is that same value.

Parameters:

a - an argument.

b - another argument.

Returns:

the smaller of *a* and *b*.

6.512.3.18 `static double decaf::lang::Math::pow (double base, double exp)` [static]

Returns the value of the first argument raised to the power of the second argument. Special cases:

o If the second argument is positive or negative zero, then the result is 1.0. o If the second argument is 1.0, then the result is the same as the first argument. o If the second argument is NaN, then the result is NaN. o If the first argument is NaN and the second argument is nonzero, then the result is NaN.

Parameters:

base - the base

exp - the exponent

Returns:

the base raised to the power of *exp*.

6.512.3.19 `static double decaf::lang::Math::random ()` [static]

Computes the remainder operation on two arguments as prescribed by the IEEE 754 standard. The remainder value is mathematically equal to $f1 - f2 \times n$, where *n* is the mathematical integer closest to the exact mathematical value of the quotient $f1/f2$, and if two mathematical integers are equally close to $f1/f2$, then *n* is the integer that is even. If the remainder is zero, its sign is the same as the sign of the first argument. Special cases:

o If either argument is NaN, or the first argument is infinite, or the second argument is positive zero or negative zero, then the result is NaN. o If the first argument is finite and the second argument is infinite, then the result is the same as the first argument.

Parameters:

f1 - the dividend.

f2 - the divisor

Returns:

the IEEE remainder of value Returns a double value with a positive sign, greater than or equal to 0.0 and less than 1.0. Returned values are chosen pseudorandomly with (approximately) uniform distribution from that range.

When this method is first called, it creates a single new pseudorandom-number generator; This new pseudorandom-number generator is used thereafter for all calls to this method and is used nowhere else.

This method is properly synchronized to allow correct use by more than one thread. However, if many threads need to generate pseudorandom numbers at a great rate, it may reduce contention for each thread to have its own pseudorandom-number generator.

Returns:

a pseudorandom double greater than or equal to 0.0 and less than 1.0.

6.512.3.20 static long long decaf::lang::Math::round (double *value*) [static]

Returns the closest long long to the argument. The result is rounded to an integer by adding 1/2, taking the floor of the result, and casting the result to type long long. In other words, the result is equal to the value of the expression: (long long) **Math.floor** (p. 2501)(a + 0.5d)

o If the argument is NaN, the result is 0. o If the argument is negative infinity or any value less than or equal to the value of **Long::MIN_VALUE** (p. 2433), the result is equal to the value of **Long::MIN_VALUE** (p. 2433). o If the argument is positive infinity or any value greater than or equal to the value of **Long::MAX_VALUE** (p. 2433), the result is equal to the value of **Long::MAX_VALUE** (p. 2433).

Parameters:

value - the value to round

Returns:

the value of the argument rounded to the nearest integral value.

6.512.3.21 static int decaf::lang::Math::round (float *value*) [static]

Returns the closest int to the argument. The result is rounded to an integer by adding 1/2, taking the floor of the result, and casting the result to type int. In other words, the result is equal to the value of the expression: (int) **Math.floor** (p. 2501)(a + 0.5f)

o If the argument is NaN, the result is 0. o If the argument is negative infinity or any value less than or equal to the value of **Integer::MIN_VALUE** (p. 2090), the result is equal to the value of **Integer::MIN_VALUE** (p. 2090). o If the argument is positive infinity or any value greater than or equal to the value of **Integer::MAX_VALUE** (p. 2090), the result is equal to the value of **Integer::MAX_VALUE** (p. 2090).

Parameters:

value - the value to round

Returns:

the value of the argument rounded to the nearest integral value.

6.512.3.22 static double decaf::lang::Math::signum (double *value*) [static]

Returns the signum function of the argument; zero if the argument is zero, 1.0f if the argument is greater than zero, -1.0f if the argument is less than zero. Special Cases:

o If the argument is NaN, then the result is NaN. o If the argument is positive zero or negative zero, then the result is the same as the argument.

Parameters:

value - the floating-point value whose signum is to be returned

Returns:

the signum function of the argument

6.512.3.23 static float decaf::lang::Math::signum (float *value*) [static]

Returns Euler's number e raised to the power of a double value. Special cases:

o If the argument is NaN, the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is negative infinity, then the result is positive zero.

Parameters:

value - the exponent to raise e to

Returns:

the value e^x , where e is the base of the natural logarithms. Returns $e^x - 1$. Note that for values of x near 0, the exact sum of $\expm1(x) + 1$ is much closer to the true result of e^x than $\exp(x)$. Special cases:

o If the argument is NaN, the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is negative infinity, then the result is -1.0. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the value to raise $e^x - 1$

Returns:

the value $e^x - 1$. Returns $\sqrt{x^2 + y^2}$ without intermediate overflow or underflow. Special cases:

If either argument is infinite, then the result is positive infinity. If either argument is NaN and neither argument is infinite, then the result is NaN.

Parameters:

x - an argument

y - another argument

Returns:

the $\sqrt{x^2 + y^2}$ without intermediate overflow or underflow Returns the signum function of the argument; zero if the argument is zero, 1.0 if the argument is greater than zero, -1.0 if the argument is less than zero. Special Cases:

o If the argument is NaN, then the result is NaN. o If the argument is positive zero or negative zero, then the result is the same as the argument.

Parameters:

value - the floating-point value whose signum is to be returned

Returns:

the signum function of the argument

6.512.3.24 static double decaf::lang::Math::sqrt (double *value*) [static]

Returns the arc cosine of an angle, in the range of 0.0 through pi. Special case:

o If the argument is NaN or its absolute value is greater than 1, then the result is NaN.

Parameters:

value - the value to return the arc cosine of.

Returns:

arc cosine of value in radians. Returns the arc sine of an angle, in the range of -pi/2 through pi/2. Special cases:

o If the argument is NaN or its absolute value is greater than 1, then the result is NaN. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the value to return the arc cosine of.

Returns:

arc cosine of value in radians. Returns the arc tangent of an angle, in the range of -pi/2 through pi/2. Special cases:

o If the argument is NaN, then the result is NaN. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the value to return the arc cosine of.

Returns:

arc tangent of value in radians. Converts rectangular coordinates (x, y) to polar (r, theta). This method computes the phase theta by computing an arc tangent of y/x in the range of -pi to pi. Special cases:

o If either argument is NaN, then the result is NaN. o If the first argument is positive zero and the second argument is positive, or the first argument is positive and finite and the second argument is positive infinity, then the result is positive zero. o If the first argument is negative zero and the second argument is positive, or the first argument is negative and finite and the second argument is positive infinity, then the result is negative zero. o If the first argument is positive zero and the second argument is negative, or the first argument is positive and finite and the second argument is negative infinity, then the result is the double value closest to pi. o If the first argument is negative zero and the second argument is negative, or the first argument is negative and finite and the second argument is negative infinity, then the result is the double value closest to -pi. o If the first argument is positive and the second argument is positive zero or negative zero, or the first argument is positive infinity and the second argument is finite, then the result is the double value closest to pi/2. o If the first argument is negative and the second argument is positive zero or negative zero, or the first argument is negative infinity and the second argument is finite, then the result is the double value closest to -pi/2. o If both arguments are positive infinity, then the result is the double value closest to pi/4. o If the first argument is positive infinity and the second argument is negative infinity, then the result is the double value closest to 3*pi/4. o If the first argument is negative infinity and the second argument is positive infinity, then the result is the double value closest to -pi/4. o If both arguments are negative infinity, then the result is the double value closest to -3*pi/4.

Parameters:

y - the ordinate coordinate
x - the abscissa coordinate

Returns:

the theta component of the point (r, theta) in polar coordinates that corresponds to the point (x, y) in Cartesian coordinates. Returns the cube root of a double value. For positive finite x, cbrt(-x) == -cbrt(x); that is, the cube root of a negative value is the negative of the cube root of that value's magnitude. Special cases:

o If the argument is NaN, then the result is NaN. o If the argument is infinite, then the result is an infinity with the same sign as the argument. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the double to compute the cube root of

Returns:

the cube root of value Returns the trigonometric cosine of an angle. Special cases:

o If the argument is NaN or an infinity, then the result is NaN.

Parameters:

value - an value in radians

Returns:

the cosine of the argument. Returns the hyperbolic cosine of a double value. The hyperbolic cosine of x is defined to be $(e^x + e^{-x})/2$ where e is Euler's number. Special cases:

o If the argument is NaN, then the result is NaN. o If the argument is infinite, then the result is positive infinity. o If the argument is zero, then the result is 1.0.

Parameters:

value - the number whose hyperbolic cosine is to be found

Returns:

the hyperbolic cosine of value Returns the trigonometric sine of an angle. Special case:

o If the argument is NaN or an infinity, then the result is NaN. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the number whose sin is to be found

Returns:

the sine of value Returns the hyperbolic sine of a double value. The hyperbolic sine of x is defined to be $(e^x - e^{-x})/2$ where e is Euler's number. Special cases:

o If the argument is NaN, then the result is NaN. o If the argument is infinite, then the result is an infinity with the same sign as the argument. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the number whose hyperbolic sin is to be found

Returns:

the hyperbolic sine of value Returns the trigonometric tangent of an angle. Special cases:

o If the argument is NaN or an infinity, then the result is NaN. o If the argument is zero, then the result is a zero with the same sign as the argument.

Parameters:

value - the number whose tangent is to be found

Returns:

the tangent of value Returns the hyperbolic tangent of a double value. The hyperbolic tangent of x is defined to be $(e^x - e^{-x})/(e^x + e^{-x})$, in other words, $\sinh(x)/\cosh(x)$. Note that the absolute value of the exact \tanh is always less than 1. Special cases:

o If the argument is NaN, then the result is NaN. o If the argument is zero, then the result is a zero with the same sign as the argument. o If the argument is positive infinity, then the result is +1.0. o If the argument is negative infinity, then the result is -1.0.

Parameters:

value - the number whose hyperbolic tangent is to be found

Returns:

the hyperbolic cosine of value Returns the correctly rounded positive square root of a double value. Special cases:

o If the argument is NaN or less than zero, then the result is NaN. o If the argument is positive infinity, then the result is positive infinity. o If the argument is positive zero or negative zero, then the result is the same as the argument.

Otherwise, the result is the double value closest to the true mathematical square root of the argument value.

Parameters:

value - the value to find the square root of
the square root of the argument.

6.512.3.25 `static double decaf::lang::Math::toDegrees (double angrad)` [inline, static]

Returns the measure in degrees of the supplied radian angle.

Parameters:

angrad - an angle in radians

Returns:

the degree measure of the angle.

6.512.3.26 `static double decaf::lang::Math::toRadians (double angdeg)` [inline, static]

Returns the measure in radians of the supplied degree angle.

Parameters:

angdeg - an angle in degrees

Returns:

the radian measure of the angle.

6.512.4 Field Documentation

6.512.4.1 `const double decaf::lang::Math::E` [static]

6.512.4.2 `const double decaf::lang::Math::PI` [static]

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Math.h`

6.513 activemq::util::MemoryUsage Class Reference

#include <src/main/activemq/util/MemoryUsage.h> Inheritance diagram for activemq::util::MemoryUsage:

Public Member Functions

- **MemoryUsage** ()
Default Constructor.
- **MemoryUsage** (unsigned long long limit)
*Creates an instance of an **Usage** (p. 3964) monitor with a set limit.*
- virtual ~**MemoryUsage** ()
- virtual void **waitForSpace** ()
*Waits forever for more space to be returned to this **Usage** (p. 3964) Manager.*
- virtual void **waitForSpace** (unsigned int timeout)
*Waits for more space to be returned to this **Usage** (p. 3964) Manager, times out when the given time span in milliseconds elapses.*
- virtual void **enqueueUsage** (unsigned long long value)
Tries to increase the usage by value amount but blocks if this object is currently full.
- virtual void **increaseUsage** (unsigned long long value)
Increases the usage by the value amount.
- virtual void **decreaseUsage** (unsigned long long value)
Decreases the usage by the value amount.
- virtual bool **isFull** () const
*Returns true if this **Usage** (p. 3964) instance is full, i.e.*
- unsigned long long **getUsage** () const
Gets the current usage amount.
- void **setUsage** (unsigned long long usage)
Sets the current usage amount.
- unsigned long long **getLimit** () const
Gets the current limit amount.
- void **setLimit** (unsigned long long limit)
Sets the current limit amount.

6.513.1 Constructor & Destructor Documentation

6.513.1.1 activemq::util::MemoryUsage::MemoryUsage ()

Default Constructor.

6.513.1.2 activemq::util::MemoryUsage::MemoryUsage (unsigned long long *limit*)

Creates an instance of an **Usage** (p. 3964) monitor with a set limit.

Parameters:

limit - amount of memory this manager allows.

6.513.1.3 virtual activemq::util::MemoryUsage::~~MemoryUsage () [virtual]

6.513.2 Member Function Documentation

6.513.2.1 virtual void activemq::util::MemoryUsage::decreaseUsage (unsigned long long *value*) [virtual]

Decreases the usage by the value amount.

Parameters:

value Amount of space to return to the pool

Implements **activemq::util::Usage** (p. 3964).

6.513.2.2 virtual void activemq::util::MemoryUsage::enqueueUsage (unsigned long long *value*) [inline, virtual]

Tries to increase the usage by value amount but blocks if this object is currently full.

Parameters:

value Amount of usage in bytes to add.

Implements **activemq::util::Usage** (p. 3964).

6.513.2.3 unsigned long long activemq::util::MemoryUsage::getLimit () const [inline]

Gets the current limit amount.

Returns:

the amount that can be used before full.

6.513.2.4 `unsigned long long activemq::util::MemoryUsage::getUsage () const`
 `[inline]`

Gets the current usage amount.

Returns:

the amount of bytes currently used.

6.513.2.5 `virtual void activemq::util::MemoryUsage::increaseUsage (unsigned long`
 `long value) [virtual]`

Increases the usage by the value amount.

Parameters:

value Amount of usage to add.

Implements `activemq::util::Usage` (p. 3965).

6.513.2.6 `virtual bool activemq::util::MemoryUsage::isFull () const [virtual]`

Returns true if this `Usage` (p. 3964) instance is full, i.e. `Usage` (p. 3964) $\geq 100\%$

Implements `activemq::util::Usage` (p. 3965).

6.513.2.7 `void activemq::util::MemoryUsage::setLimit (unsigned long long limit)`
 `[inline]`

Sets the current limit amount.

Parameters:

limit - The amount that can be used before full.

6.513.2.8 `void activemq::util::MemoryUsage::setUsage (unsigned long long usage)`
 `[inline]`

Sets the current usage amount.

Parameters:

usage - The amount to tag as used.

6.513.2.9 `virtual void activemq::util::MemoryUsage::waitForSpace (unsigned int`
 `timeout) [virtual]`

Waits for more space to be returned to this `Usage` (p. 3964) Manager, times out when the given time span in milliseconds elapses.

Parameters:

timeout The time to wait for more space.

Implements `activemq::util::Usage` (p. 3965).

6.513.2.10 virtual void activemq::util::MemoryUsage::waitForSpace () [virtual]

Waits forever for more space to be returned to this **Usage** (p. 3964) Manager.

Implements **activemq::util::Usage** (p. 3965).

The documentation for this class was generated from the following file:

- src/main/activemq/util/**MemoryUsage.h**

6.514 activemq::commands::Message Class Reference

#include <src/main/activemq/commands/Message.h> Inheritance diagram for activemq::commands::Message:

Public Member Functions

- **Message** ()
- virtual **~Message** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **Message * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual void **beforeMarshal** (**wireformat::WireFormat** *wireFormat AMQCPP_UNUSED) throw (decaf::io::IOException)
Handles the marshaling of the objects properties into the internal byte array before the object is marshaled to the wire.
- virtual void **afterUnmarshal** (**wireformat::WireFormat** *wireFormat AMQCPP_UNUSED) throw (decaf::io::IOException)
Called after unmarshaling is started to cleanup the object being unmarshaled.
- virtual bool **isMarshalAware** () const
Indicates that this command is aware of Marshaling, and needs to have its Marshaling methods invoked.
- virtual void **setAckHandler** (const **Pointer**< **core::ActiveMQAckHandler** > &handler)
*Sets the Acknowledgment Handler that this **Message** (p. 2516) will use when the Acknowledge method is called.*
- virtual **Pointer**< **core::ActiveMQAckHandler** > **getAckHandler** () const
*Gets the Acknowledgment Handler that this **Message** (p. 2516) will use when the Acknowledge method is called.*
- void **setConnection** (**core::ActiveMQConnection** *connection)

Sets the `ActiveMQConnection` instance that this `Command` (p. 1194) was created from when the session create methods are called to create a `Message` (p. 2516).

- **core::ActiveMQConnection * getConnection () const**
Gets the `ActiveMQConnection` instance that this `Command` (p. 1194) was created from when the session create methods are called to create a `Message` (p. 2516).
- virtual unsigned int **getSize () const**
Returns the Size of this message in Bytes.
- virtual bool **isExpired () const**
Returns if this message has expired, meaning that its Expiration time has elapsed.
- virtual void **onSend ()**
Allows derived `Message` (p. 2516) classes to perform tasks before a message is sent.
- **util::PrimitiveMap & getMessageProperties ()**
Gets a reference to the Message's Properties object, allows the derived classes to get and set their own specific properties.
- const **util::PrimitiveMap & getMessageProperties () const**
- bool **isReadOnlyProperties () const**
Returns if the `Message` (p. 2516) Properties Are Read Only.
- void **setReadOnlyProperties (bool value)**
Set the Read Only State of the `Message` (p. 2516) Properties.
- bool **isReadOnlyBody () const**
Returns if the `Message` (p. 2516) Body is Read Only.
- void **setReadOnlyBody (bool value)**
Set the Read Only State of the `Message` (p. 2516) Content.
- virtual const **Pointer< ProducerId > & getProducerId () const**
- virtual **Pointer< ProducerId > & getProducerId ()**
- virtual void **setProducerId (const Pointer< ProducerId > &producerId)**
- virtual const **Pointer< ActiveMQDestination > & getDestination () const**
- virtual **Pointer< ActiveMQDestination > & getDestination ()**
- virtual void **setDestination (const Pointer< ActiveMQDestination > &destination)**
- virtual const **Pointer< TransactionId > & getTransactionId () const**
- virtual **Pointer< TransactionId > & getTransactionId ()**
- virtual void **setTransactionId (const Pointer< TransactionId > &transactionId)**
- virtual const **Pointer< ActiveMQDestination > & getOriginalDestination () const**
- virtual **Pointer< ActiveMQDestination > & getOriginalDestination ()**
- virtual void **setOriginalDestination (const Pointer< ActiveMQDestination > &originalDestination)**
- virtual const **Pointer< MessageId > & getMessageId () const**
- virtual **Pointer< MessageId > & getMessageId ()**
- virtual void **setMessageId (const Pointer< MessageId > &messageId)**
- virtual const **Pointer< TransactionId > & getOriginalTransactionId () const**
- virtual **Pointer< TransactionId > & getOriginalTransactionId ()**

- virtual void **setOriginalTransactionId** (const **Pointer**< **TransactionId** > &**originalTransactionId**)
- virtual const std::string & **getGroupID** () const
- virtual std::string & **getGroupID** ()
- virtual void **setGroupID** (const std::string &**groupID**)
- virtual int **getGroupSequence** () const
- virtual void **setGroupSequence** (int **groupSequence**)
- virtual const std::string & **getCorrelationId** () const
- virtual std::string & **getCorrelationId** ()
- virtual void **setCorrelationId** (const std::string &**correlationId**)
- virtual bool **isPersistent** () const
- virtual void **setPersistent** (bool **persistent**)
- virtual long long **getExpiration** () const
- virtual void **setExpiration** (long long **expiration**)
- virtual unsigned char **getPriority** () const
- virtual void **setPriority** (unsigned char **priority**)
- virtual const **Pointer**< **ActiveMQDestination** > & **getReplyTo** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getReplyTo** ()
- virtual void **setReplyTo** (const **Pointer**< **ActiveMQDestination** > &**replyTo**)
- virtual long long **getTimestamp** () const
- virtual void **setTimestamp** (long long **timestamp**)
- virtual const std::string & **getType** () const
- virtual std::string & **getType** ()
- virtual void **setType** (const std::string &**type**)
- virtual const std::vector< unsigned char > & **getContent** () const
- virtual std::vector< unsigned char > & **getContent** ()
- virtual void **setContent** (const std::vector< unsigned char > &**content**)
- virtual const std::vector< unsigned char > & **getMarshaledProperties** () const
- virtual std::vector< unsigned char > & **getMarshaledProperties** ()
- virtual void **setMarshaledProperties** (const std::vector< unsigned char > &**marshalledProperties**)
- virtual const **Pointer**< **DataStructure** > & **getDataStructure** () const
- virtual **Pointer**< **DataStructure** > & **getDataStructure** ()
- virtual void **setDataStructure** (const **Pointer**< **DataStructure** > &**dataStructure**)
- virtual const **Pointer**< **ConsumerId** > & **getTargetConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getTargetConsumerId** ()
- virtual void **setTargetConsumerId** (const **Pointer**< **ConsumerId** > &**targetConsumerId**)
- virtual bool **isCompressed** () const
- virtual void **setCompressed** (bool **compressed**)
- virtual int **getRedeliveryCounter** () const
- virtual void **setRedeliveryCounter** (int **redeliveryCounter**)
- virtual const std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** () const
- virtual std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getBrokerPath** ()
- virtual void **setBrokerPath** (const std::vector< **decaf::lang::Pointer**< **BrokerId** > > &**brokerPath**)
- virtual long long **getArrival** () const
- virtual void **setArrival** (long long **arrival**)
- virtual const std::string & **getUserID** () const

- virtual std::string & **getUserID** ()
- virtual void **setUserID** (const std::string &userID)
- virtual bool **isRecievedByDFBridge** () const
- virtual void **setRecievedByDFBridge** (bool recievedByDFBridge)
- virtual bool **isDroppable** () const
- virtual void **setDroppable** (bool droppable)
- virtual const std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getCluster** () const
- virtual std::vector< **decaf::lang::Pointer**< **BrokerId** > > & **getCluster** ()
- virtual void **setCluster** (const std::vector< **decaf::lang::Pointer**< **BrokerId** > > &cluster)
- virtual long long **getBrokerInTime** () const
- virtual void **setBrokerInTime** (long long brokerInTime)
- virtual long long **getBrokerOutTime** () const
- virtual void **setBrokerOutTime** (long long brokerOutTime)
- virtual bool **isMessage** () const
- virtual **Pointer**< **Command** > **visit** (**activemq::state::CommandVisitor** *visitor) throw (exceptions::ActiveMQException)

Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID _MESSAGE** = 0

Protected Attributes

- **core::ActiveMQConnection** * connection
- **Pointer**< **ProducerId** > producerId
- **Pointer**< **ActiveMQDestination** > destination
- **Pointer**< **TransactionId** > transactionId
- **Pointer**< **ActiveMQDestination** > originalDestination
- **Pointer**< **MessageId** > messageId
- **Pointer**< **TransactionId** > originalTransactionId
- std::string **groupID**
- int **groupSequence**
- std::string **correlationId**
- bool **persistent**
- long long **expiration**
- unsigned char **priority**
- **Pointer**< **ActiveMQDestination** > replyTo
- long long **timestamp**
- std::string **type**
- std::vector< unsigned char > **content**
- std::vector< unsigned char > **marshalledProperties**
- **Pointer**< **DataStructure** > **dataStructure**
- **Pointer**< **ConsumerId** > **targetConsumerId**
- bool **compressed**
- int **redeliveryCounter**
- std::vector< **decaf::lang::Pointer**< **BrokerId** > > **brokerPath**

- long long **arrival**
- std::string **userID**
- bool **recievedByDFBridge**
- bool **droppable**
- std::vector< decaf::lang::Pointer< BrokerId > > **cluster**
- long long **brokerInTime**
- long long **brokerOutTime**

Static Protected Attributes

- static const unsigned int **DEFAULT_MESSAGE_SIZE** = 1024

6.514.1 Constructor & Destructor Documentation

6.514.1.1 `activemq::commands::Message::Message ()`

6.514.1.2 `virtual activemq::commands::Message::~Message () [virtual]`

6.514.2 Member Function Documentation

6.514.2.1 `virtual void activemq::commands::Message::afterUnmarshal (wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (decaf::io::IOException) [virtual]`

Called after unmarshaling is started to cleanup the object being unmarshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control unmarshaling

Reimplemented from **activemq::commands::BaseDataStructure** (p. 831).

6.514.2.2 `virtual void activemq::commands::Message::beforeMarshal (wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (decaf::io::IOException) [virtual]`

Handles the marshaling of the objects properties into the internal byte array before the object is marshaled to the wire.

Parameters:

wireFormat - the **wireformat** (p. 105) controller

Reimplemented from **activemq::commands::BaseDataStructure** (p. 831).

6.514.2.3 `virtual Message* activemq::commands::Message::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 205), **activemq::commands::ActiveMQBytesMessage** (p. 237), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage** (p. 444), **activemq::commands::ActiveMQStreamMessage** (p. 540), and **activemq::commands::ActiveMQTextMessage** (p. 664).

6.514.2.4 virtual void activemq::commands::Message::copyDataStructure (const DataStructure * *src*) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 205), **activemq::commands::ActiveMQBytesMessage** (p. 237), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage** (p. 444), **activemq::commands::ActiveMQStreamMessage** (p. 540), and **activemq::commands::ActiveMQTextMessage** (p. 664).

6.514.2.5 virtual bool activemq::commands::Message::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 206), **activemq::commands::ActiveMQBytesMessage** (p. 237), **activemq::commands::ActiveMQMapMessage** (p. 364), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQMessageTemplate< T >** (p. 429), **activemq::commands::ActiveMQObjectMessage** (p. 444), **activemq::commands::ActiveMQStreamMessage** (p. 541), **activemq::commands::ActiveMQTextMessage** (p. 664), **activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::Message >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >** (p. 429), **activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >** (p. 429), and **activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >** (p. 429).

6.514.2.6 `virtual Pointer<core::ActiveMQAckHandler>
activemq::commands::Message::getAckHandler () const [inline,
virtual]`

Gets the Acknowledgment Handler that this **Message** (p. 2516) will use when the Acknowledge method is called.

Returns:

handler ActiveMQAckHandler to call or NULL if not set

6.514.2.7 `virtual long long activemq::commands::Message::getArrival () const
[virtual]`

6.514.2.8 `virtual long long activemq::commands::Message::getBrokerInTime ()
const [virtual]`

6.514.2.9 `virtual long long activemq::commands::Message::getBrokerOutTime ()
const [virtual]`

6.514.2.10 `virtual std::vector< decaf::lang::Pointer<BrokerId> >&
activemq::commands::Message::getBrokerPath () [virtual]`

6.514.2.11 `virtual const std::vector< decaf::lang::Pointer<BrokerId> >&
activemq::commands::Message::getBrokerPath () const [virtual]`

6.514.2.12 `virtual std::vector< decaf::lang::Pointer<BrokerId> >&
activemq::commands::Message::getCluster () [virtual]`

6.514.2.13 `virtual const std::vector< decaf::lang::Pointer<BrokerId> >&
activemq::commands::Message::getCluster () const [virtual]`

6.514.2.14 `core::ActiveMQConnection* ac-
tivemq::commands::Message::getConnection () const
[inline]`

Gets the ActiveMQConnection instance that this **Command** (p. 1194) was created from when the session create methods are called to create a **Message** (p. 2516).

Returns:

the ActiveMQConnection parent for this **Message** (p. 2516) or NULL if not set.

- 6.514.2.15 `virtual std::vector<unsigned char>& activemq::commands::Message::getContent ()` [virtual]
- 6.514.2.16 `virtual const std::vector<unsigned char>& activemq::commands::Message::getContent () const` [virtual]
- 6.514.2.17 `virtual std::string& activemq::commands::Message::getCorrelationId ()` [virtual]
- 6.514.2.18 `virtual const std::string& activemq::commands::Message::getCorrelationId () const` [virtual]
- 6.514.2.19 `virtual Pointer<DataStructure>& activemq::commands::Message::getDataStructure ()` [virtual]
- 6.514.2.20 `virtual const Pointer<DataStructure>& activemq::commands::Message::getDataStructure () const` [virtual]
- 6.514.2.21 `virtual unsigned char activemq::commands::Message::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 206), **activemq::commands::ActiveMQBytesMessage** (p. 238), **activemq::commands::ActiveMQMapMessage** (p. 366), **activemq::commands::ActiveMQMessage** (p. 399), **activemq::commands::ActiveMQObjectMessage** (p. 445), **activemq::commands::ActiveMQStreamMessage** (p. 541), and **activemq::commands::ActiveMQTextMessage** (p. 664).

- 6.514.2.22 `virtual Pointer<ActiveMQDestination>& activemq::commands::Message::getDestination ()` [virtual]
- 6.514.2.23 `virtual const Pointer<ActiveMQDestination>& activemq::commands::Message::getDestination () const` [virtual]
- 6.514.2.24 `virtual long long activemq::commands::Message::getExpiration () const` [virtual]
- 6.514.2.25 `virtual std::string& activemq::commands::Message::getGroupID ()` [virtual]
- 6.514.2.26 `virtual const std::string& activemq::commands::Message::getGroupID () const` [virtual]
- 6.514.2.27 `virtual int activemq::commands::Message::getGroupSequence () const` [virtual]
- 6.514.2.28 `virtual std::vector<unsigned char>& activemq::commands::Message::getMarshalledProperties ()` [virtual]
- 6.514.2.29 `virtual const std::vector<unsigned char>& activemq::commands::Message::getMarshalledProperties () const` [virtual]
- 6.514.2.30 `virtual Pointer<MessageId>& activemq::commands::Message::getMessageId ()` [virtual]
- 6.514.2.31 `virtual const Pointer<MessageId>& activemq::commands::Message::getMessageId () const` [virtual]
- 6.514.2.32 `const util::PrimitiveMap& activemq::commands::Message::getMessageProperties () const` [inline]
- 6.514.2.33 `util::PrimitiveMap& activemq::commands::Message::getMessageProperties ()` [inline]

Gets a reference to the Message's Properties object, allows the derived classes to get and set their own specific properties.

Returns:

a reference to the Primitive Map that holds message properties.

- 6.514.2.34 `virtual Pointer<ActiveMQDestination>& activemq::commands::Message::getOriginalDestination ()`
[virtual]
- 6.514.2.35 `virtual const Pointer<ActiveMQDestination>& activemq::commands::Message::getOriginalDestination () const`
[virtual]
- 6.514.2.36 `virtual Pointer<TransactionId>& activemq::commands::Message::getOriginalTransactionId ()`
[virtual]
- 6.514.2.37 `virtual const Pointer<TransactionId>& activemq::commands::Message::getOriginalTransactionId () const`
[virtual]
- 6.514.2.38 `virtual unsigned char activemq::commands::Message::getPriority () const` [virtual]
- 6.514.2.39 `virtual Pointer<ProducerId>& activemq::commands::Message::getProducerId ()`
[virtual]
- 6.514.2.40 `virtual const Pointer<ProducerId>& activemq::commands::Message::getProducerId () const`
[virtual]
- 6.514.2.41 `virtual int activemq::commands::Message::getRedeliveryCounter () const` [virtual]
- 6.514.2.42 `virtual Pointer<ActiveMQDestination>& activemq::commands::Message::getReplyTo ()` [virtual]
- 6.514.2.43 `virtual const Pointer<ActiveMQDestination>& activemq::commands::Message::getReplyTo () const` [virtual]
- 6.514.2.44 `virtual unsigned int activemq::commands::Message::getSize () const`
[virtual]

Returns the Size of this message in Bytes.

Returns:

number of bytes this message equates to.

Reimplemented in `activemq::commands::ActiveMQTextMessage` (p. 665).

- 6.514.2.45** `virtual Pointer<ConsumerId>& activemq::commands::Message::getTargetConsumerId ()`
[virtual]
- 6.514.2.46** `virtual const Pointer<ConsumerId>& activemq::commands::Message::getTargetConsumerId ()`
`const` [virtual]
- 6.514.2.47** `virtual long long activemq::commands::Message::getTimestamp ()` `const`
[virtual]
- 6.514.2.48** `virtual Pointer<TransactionId>& activemq::commands::Message::getTransactionId ()`
[virtual]
- 6.514.2.49** `virtual const Pointer<TransactionId>& activemq::commands::Message::getTransactionId ()` `const`
[virtual]
- 6.514.2.50** `virtual std::string& activemq::commands::Message::getType ()`
[virtual]
- 6.514.2.51** `virtual const std::string& activemq::commands::Message::getType ()` `const` [virtual]
- 6.514.2.52** `virtual std::string& activemq::commands::Message::getUserID ()`
[virtual]
- 6.514.2.53** `virtual const std::string& activemq::commands::Message::getUserID ()` `const` [virtual]
- 6.514.2.54** `virtual bool activemq::commands::Message::isCompressed ()` `const`
[virtual]
- 6.514.2.55** `virtual bool activemq::commands::Message::isDroppable ()` `const`
[virtual]
- 6.514.2.56** `virtual bool activemq::commands::Message::isExpired ()` `const`
[virtual]

Returns if this message has expired, meaning that its Expiration time has elapsed.

Returns:

true if message is expired.

- 6.514.2.57** `virtual bool activemq::commands::Message::isMarshalAware ()` `const`
[inline, virtual]

Indicates that this command is aware of Marshaling, and needs to have its Marshaling methods invoked.

Returns:

boolean indicating desire to be in marshaling stages

Reimplemented from `activemq::commands::BaseDataStructure` (p. 832).

Reimplemented in `activemq::commands::ActiveMQMapMessage` (p. 368).

6.514.2.58 `virtual bool activemq::commands::Message::isMessage () const`
[inline, virtual]

Returns:

an answer of true to the `isMessage()` (p. 2527) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 761).

6.514.2.59 `virtual bool activemq::commands::Message::isPersistent () const`
[virtual]

6.514.2.60 `bool activemq::commands::Message::isReadOnlyBody () const` [inline]

Returns if the `Message` (p. 2516) Body is Read Only.

Returns:

true if `Message` (p. 2516) Content is Read Only.

6.514.2.61 `bool activemq::commands::Message::isReadOnlyProperties () const`
[inline]

Returns if the `Message` (p. 2516) Properties Are Read Only.

Returns:

true if `Message` (p. 2516) Properties are Read Only.

6.514.2.62 `virtual bool activemq::commands::Message::isRecievedByDFBridge ()`
`const` [virtual]

6.514.2.63 `virtual void activemq::commands::Message::onSend ()` [inline,
virtual]

Allows derived `Message` (p. 2516) classes to perform tasks before a message is sent.

Reimplemented in `activemq::commands::ActiveMQBytesMessage` (p. 238),
`activemq::commands::ActiveMQMessageTemplate< T >` (p. 436),
`activemq::commands::ActiveMQStreamMessage` (p. 541),
`activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 436),
`activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 436),
`activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 436),
`activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 436),
`activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 436), and
`activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 436).

6.514.2.64 `virtual void activemq::commands::Message::setAckHandler (const Pointer< core::ActiveMQAckHandler > & handler) [inline, virtual]`

Sets the Acknowledgment Handler that this **Message** (p. 2516) will use when the Acknowledge method is called.

Parameters:

handler ActiveMQAckHandler to call

6.514.2.65 `virtual void activemq::commands::Message::setArrival (long long arrival) [virtual]`

6.514.2.66 `virtual void activemq::commands::Message::setBrokerInTime (long long brokerInTime) [virtual]`

6.514.2.67 `virtual void activemq::commands::Message::setBrokerOutTime (long long brokerOutTime) [virtual]`

6.514.2.68 `virtual void activemq::commands::Message::setBrokerPath (const std::vector< decaf::lang::Pointer< BrokerId > > & brokerPath) [virtual]`

6.514.2.69 `virtual void activemq::commands::Message::setCluster (const std::vector< decaf::lang::Pointer< BrokerId > > & cluster) [virtual]`

6.514.2.70 `virtual void activemq::commands::Message::setCompressed (bool compressed) [virtual]`

6.514.2.71 `void activemq::commands::Message::setConnection (core::ActiveMQConnection * connection) [inline]`

Sets the ActiveMQConnection instance that this **Command** (p. 1194) was created from when the session create methods are called to create a **Message** (p. 2516).

Parameters:

handler ActiveMQConnection parent for this message

- 6.514.2.72 virtual void activemq::commands::Message::setContent (const std::vector< unsigned char > & *content*) [virtual]
- 6.514.2.73 virtual void activemq::commands::Message::setCorrelationId (const std::string & *correlationId*) [virtual]
- 6.514.2.74 virtual void activemq::commands::Message::setDataStructure (const Pointer< DataStructure > & *dataStructure*) [virtual]
- 6.514.2.75 virtual void activemq::commands::Message::setDestination (const Pointer< ActiveMQDestination > & *destination*) [virtual]
- 6.514.2.76 virtual void activemq::commands::Message::setDroppable (bool *droppable*) [virtual]
- 6.514.2.77 virtual void activemq::commands::Message::setExpiration (long long *expiration*) [virtual]
- 6.514.2.78 virtual void activemq::commands::Message::setGroupID (const std::string & *groupID*) [virtual]
- 6.514.2.79 virtual void activemq::commands::Message::setGroupSequence (int *groupSequence*) [virtual]
- 6.514.2.80 virtual void activemq::commands::Message::setMarshaledProperties (const std::vector< unsigned char > & *marshalledProperties*) [virtual]
- 6.514.2.81 virtual void activemq::commands::Message::setMessageId (const Pointer< MessageId > & *messageId*) [virtual]
- 6.514.2.82 virtual void activemq::commands::Message::setOriginalDestination (const Pointer< ActiveMQDestination > & *originalDestination*) [virtual]
- 6.514.2.83 virtual void activemq::commands::Message::setOriginalTransactionId (const Pointer< TransactionId > & *originalTransactionId*) [virtual]
- 6.514.2.84 virtual void activemq::commands::Message::setPersistent (bool *persistent*) [virtual]
- 6.514.2.85 virtual void activemq::commands::Message::setPriority (unsigned char *priority*) [virtual]
- 6.514.2.86 virtual void activemq::commands::Message::setProducerId (const Pointer< ProducerId > & *producerId*) [virtual]
- 6.514.2.87 void activemq::commands::Message::setReadOnlyBody (bool *value*) [inline]

Set the Read Only State of the Message (p. 2516) Content.

Parameters:

value - true if Content should be read only.

6.514.2.88 `void activemq::commands::Message::setReadOnlyProperties (bool value) [inline]`

Set the Read Only State of the **Message** (p. 2516) Properties.

Parameters:

value - true if Properties should be read only.

6.514.2.89 `virtual void activemq::commands::Message::setRecievedByDFBridge (bool recievedByDFBridge) [virtual]`

6.514.2.90 `virtual void activemq::commands::Message::setRedeliveryCounter (int redeliveryCounter) [virtual]`

6.514.2.91 `virtual void activemq::commands::Message::setReplyTo (const Pointer< ActiveMQDestination > & replyTo) [virtual]`

6.514.2.92 `virtual void activemq::commands::Message::setTargetConsumerId (const Pointer< ConsumerId > & targetConsumerId) [virtual]`

6.514.2.93 `virtual void activemq::commands::Message::setTimestamp (long long timestamp) [virtual]`

6.514.2.94 `virtual void activemq::commands::Message::setTransactionId (const Pointer< TransactionId > & transactionId) [virtual]`

6.514.2.95 `virtual void activemq::commands::Message::setType (const std::string & type) [virtual]`

6.514.2.96 `virtual void activemq::commands::Message::setUserID (const std::string & userID) [virtual]`

6.514.2.97 `virtual std::string activemq::commands::Message::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

Reimplemented in **activemq::commands::ActiveMQBlobMessage** (p. 208), **activemq::commands::ActiveMQBytesMessage** (p. 244), **activemq::commands::ActiveMQMapMessage** (p. 372), **activemq::commands::ActiveMQMessage** (p. 400), **activemq::commands::ActiveMQObjectMessage** (p. 445), **activemq::commands::ActiveMQStreamMessage** (p. 547), and **activemq::commands::ActiveMQTextMessage** (p. 666).

6.514.2.98 `virtual Pointer<Command> activemq::commands::Message::visit
(activemq::state::CommandVisitor * visitor) throw (
exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.514.3 Field Documentation

- 6.514.3.1 `long long activemq::commands::Message::arrival` [protected]
- 6.514.3.2 `long long activemq::commands::Message::brokerInTime` [protected]
- 6.514.3.3 `long long activemq::commands::Message::brokerOutTime` [protected]
- 6.514.3.4 `std::vector< decaf::lang::Pointer<BrokerId> > activemq::commands::Message::brokerPath` [protected]
- 6.514.3.5 `std::vector< decaf::lang::Pointer<BrokerId> > activemq::commands::Message::cluster` [protected]
- 6.514.3.6 `bool activemq::commands::Message::compressed` [protected]
- 6.514.3.7 `core::ActiveMQConnection* activemq::commands::Message::connection` [protected]
- 6.514.3.8 `std::vector<unsigned char> activemq::commands::Message::content` [protected]
- 6.514.3.9 `std::string activemq::commands::Message::correlationId` [protected]
- 6.514.3.10 `Pointer<DataStructure> activemq::commands::Message::dataStructure` [protected]
- 6.514.3.11 `const unsigned int activemq::commands::Message::DEFAULT_MESSAGE_SIZE = 1024` [static, protected]
- 6.514.3.12 `Pointer<ActiveMQDestination> activemq::commands::Message::destination` [protected]
- 6.514.3.13 `bool activemq::commands::Message::droppable` [protected]
- 6.514.3.14 `long long activemq::commands::Message::expiration` [protected]
- 6.514.3.15 `std::string activemq::commands::Message::groupID` [protected]
- 6.514.3.16 `int activemq::commands::Message::groupSequence` [protected]
- 6.514.3.17 `const unsigned char activemq::commands::Message::ID_MESSAGE = 0` [static]
- 6.514.3.18 `std::vector<unsigned char> activemq::commands::Message::marshalledProperties` [protected]
- 6.514.3.19 `Pointer<MessageId> activemq::commands::Message::messageId` [protected]
- 6.514.3.20 `Pointer<ActiveMQDestination> activemq::commands::Message::originalDestination` [protected]
- 6.514.3.21 `Pointer<TransactionId> activemq::commands::Message::originalTransactionId` [protected]
- 6.514.3.22 `bool activemq::commands::Message::persistent` [protected]
- 6.514.3.23 `unsigned char activemq::commands::Message::priority` [protected]

- `src/main/activemq/commands/Message.h`

6.515 cms::Message Class Reference

Root of all messages.

#include <src/main/cms/Message.h> Inheritance diagram for cms::Message:

Public Member Functions

- virtual `~Message ()`
- virtual `Message * clone () const =0`
Clone this message exactly, returns a new instance that the caller is required to delete.
- virtual void `acknowledge () const =0 throw (IllegalStateException, CMSEException)`
Acknowledges all consumed messages of the session of this consumed message.
- virtual void `clearBody ()=0 throw (CMSEException)`
Clears out the body of the message.
- virtual void `clearProperties ()=0 throw (CMSEException)`
Clears out the message body.
- virtual `std::vector< std::string > getPropertyNames () const =0 throw (CMSEException)`
Retrieves the property names.
- virtual bool `propertyExists (const std::string &name) const =0 throw (CMSEException)`
Indicates whether or not a given property exists.
- virtual bool `getBooleanProperty (const std::string &name) const =0 throw (MessageFormatException, CMSEException)`
Gets a boolean property.
- virtual unsigned char `getByteProperty (const std::string &name) const =0 throw (MessageFormatException, CMSEException)`
Gets a byte property.
- virtual double `getDoubleProperty (const std::string &name) const =0 throw (MessageFormatException, CMSEException)`
Gets a double property.
- virtual float `getFloatProperty (const std::string &name) const =0 throw (MessageFormatException, CMSEException)`
Gets a float property.
- virtual int `getIntProperty (const std::string &name) const =0 throw (MessageFormatException, CMSEException)`
Gets a int property.

- virtual long long **getLongProperty** (const std::string &name) const =0 throw (MessageFormatException, CMSException)
Gets a long property.
- virtual short **getShortProperty** (const std::string &name) const =0 throw (MessageFormatException, CMSException)
Gets a short property.
- virtual std::string **getStringProperty** (const std::string &name) const =0 throw (MessageFormatException, CMSException)
Gets a string property.
- virtual void **setBooleanProperty** (const std::string &name, bool value)=0 throw (MessageNotWriteableException, CMSException)
Sets a boolean property.
- virtual void **setByteProperty** (const std::string &name, unsigned char value)=0 throw (MessageNotWriteableException, CMSException)
Sets a byte property.
- virtual void **setDoubleProperty** (const std::string &name, double value)=0 throw (MessageNotWriteableException, CMSException)
Sets a double property.
- virtual void **setFloatProperty** (const std::string &name, float value)=0 throw (MessageNotWriteableException, CMSException)
Sets a float property.
- virtual void **setIntProperty** (const std::string &name, int value)=0 throw (MessageNotWriteableException, CMSException)
Sets a int property.
- virtual void **setLongProperty** (const std::string &name, long long value)=0 throw (MessageNotWriteableException, CMSException)
Sets a long property.
- virtual void **setShortProperty** (const std::string &name, short value)=0 throw (MessageNotWriteableException, CMSException)
Sets a short property.
- virtual void **setStringProperty** (const std::string &name, const std::string &value)=0 throw (MessageNotWriteableException, CMSException)
Sets a string property.
- virtual std::string **getCMSCorrelationID** () const =0 throw (CMSException)
Gets the correlation ID for the message.
- virtual void **setCMSCorrelationID** (const std::string &correlationId)=0 throw (CMSException)
Sets the correlation ID for the message.

- virtual int **getCMSDeliveryMode** () const =0 throw (CMSEException)
*Gets the **DeliveryMode** (p. 1721) for this message.*
- virtual void **setCMSDeliveryMode** (int mode)=0 throw (CMSEException)
*Sets the **DeliveryMode** (p. 1721) for this message.*
- virtual const **Destination** * **getCMSDestination** () const =0 throw (CMSEException)
*Gets the **Destination** (p. 1723) object for this message.*
- virtual void **setCMSDestination** (const **Destination** *destination)=0 throw (CMSEException)
*Sets the **Destination** (p. 1723) object for this message.*
- virtual long long **getCMSExpiration** () const =0 throw (CMSEException)
Gets the message's expiration value.
- virtual void **setCMSExpiration** (long long expireTime)=0 throw (CMSEException)
Sets the message's expiration value.
- virtual std::string **getCMSMessageID** () const =0 throw (CMSEException)
The CMSMessageID header field contains a value that uniquely identifies each message sent by a provider.
- virtual void **setCMSMessageID** (const std::string &id)=0 throw (CMSEException)
Sets the message ID.
- virtual int **getCMSPriority** () const =0 throw (CMSEException)
Gets the message priority level.
- virtual void **setCMSPriority** (int priority)=0 throw (CMSEException)
Sets the Priority Value for this message.
- virtual bool **getCMSRedelivered** () const =0 throw (CMSEException)
Gets an indication of whether this message is being redelivered.
- virtual void **setCMSRedelivered** (bool redelivered)=0 throw (CMSEException)
Specifies whether this message is being redelivered.
- virtual const **cms::Destination** * **getCMSReplyTo** () const =0 throw (CMSEException)
*Gets the **Destination** (p. 1723) object to which a reply to this message should be sent.*
- virtual void **setCMSReplyTo** (const **cms::Destination** *destination)=0 throw (CMSEException)
*Sets the **Destination** (p. 1723) object to which a reply to this message should be sent.*
- virtual long long **getCMSTimestamp** () const =0 throw (CMSEException)
Gets the message timestamp.
- virtual void **setCMSTimestamp** (long long timeStamp)=0 throw (CMSEException)

Sets the message timestamp.

- virtual std::string **getCMSType** () const =0 throw (CMSEException)
Gets the message type identifier supplied by the client when the message was sent.
- virtual void **setCMSType** (const std::string &type)=0 throw (CMSEException)
Sets the message type.

6.515.1 Detailed Description

Root of all messages. As in JMS, a message is comprised of 3 parts: CMS-specific headers, user-defined properties, and the body.

Message (p. 2534) Bodies

The CMS API defines four types of message bodies, each type is contained within its own **Message** (p. 2534) Interface definition.

- Stream - A **StreamMessage** (p. 3652) object's message body contains a stream of primitive values in the C++ language. It is filled and read sequentially. Unlike the **BytesMessage** (p. 1056) type the values written to a **StreamMessage** (p. 3652) retain information on their type and rules for type conversion are enforced when reading back the values from the **Message** (p. 2534) Body.
- Map - A **MapMessage** (p. 2472) object's message body contains a set of name-value pairs, where names are std::string objects, and values are C++ primitives. The entries can be accessed sequentially or randomly by name. The **MapMessage** (p. 2472) makes no guarantee on the order of the elements within the **Message** (p. 2534) body.
- Text - A **TextMessage** (p. 3763) object's message body contains a std::string object. This message type can be used to transport plain-text messages, and XML messages.
- Bytes - A **BytesMessage** (p. 1056) object's message body contains a stream of uninterpreted bytes. This message type is for literally encoding a body to match an existing message format. In many cases, it is possible to use one of the other body types, which are easier to use.

Message (p. 2534) Properties

Message (p. 2534) properties support the following conversion table. The marked cases must be supported. The unmarked cases must throw a **CMSEException** (p. 1160). The String-to-primitive conversions may throw a runtime exception if the primitive's valueOf method does not accept the String as a valid representation of the primitive.

A value written as the row type can be read as the column type.

	boolean	byte	short	int	long	float	double	String
boolean	X							X
byte		X	X	X	X			X
short			X	X	X			X
int				X	X			X
long					X			X
float						X	X	X
double							X	X
String	X	X	X	X	X	X	X	X

|-----

When a **Message** (p. 2534) is delivered its properties are considered to be in a read-only mode and cannot be changed. Attempting to change the value of a delivered Message's properties will result in a **CMSEException** (p. 1160) being thrown.

See also:

JMS API

Since:

1.0

6.515.2 Constructor & Destructor Documentation

6.515.2.1 `virtual cms::Message::~Message () [inline, virtual]`

6.515.3 Member Function Documentation

6.515.3.1 `virtual void cms::Message::acknowledge () const throw (
 IllegalStateException, CMSEException) [pure virtual]`

Acknowledges all consumed messages of the session of this consumed message. All consumed CMS messages support the acknowledge method for use when a client has specified that its CMS session's consumed messages are to be explicitly acknowledged. By invoking acknowledge on a consumed message, a client acknowledges all messages consumed by the session that the message was delivered to.

Calls to acknowledge are ignored for both transacted sessions and sessions specified to use implicit acknowledgment modes.

A client may individually acknowledge each message as it is consumed, or it may choose to acknowledge messages as an application-defined group (which is done by calling acknowledge on the last received message of the group, thereby acknowledging all messages consumed by the session.)

Messages that have been received but not acknowledged may be redelivered.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

IllegalStateException (p. 1997) - if this method is called on a closed session.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 428), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 428), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 428), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 428), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 428), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 428).

6.515.3.2 `virtual void cms::Message::clearBody () throw (CMSEException) [pure virtual]`

Clears out the body of the message. This does not clear the headers or properties.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQBytesMessage` (p. 236), `activemq::commands::ActiveMQMapMessage` (p. 363), `activemq::commands::ActiveMQStreamMessage` (p. 540), `activemq::commands::ActiveMQTextMessage` (p. 663), `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 428), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 428), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 428), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 428), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 428), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 428).

6.515.3.3 virtual void cms::Message::clearProperties () throw (CMSEException) [pure virtual]

Clears out the message body. Clearing a message's body does not clear its header values or property entries.

If this message body was read-only, calling this method leaves the message body in the same state as an empty body in a newly created message.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 429), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 429), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 429), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 429), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 429), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 429).

6.515.3.4 virtual Message* cms::Message::clone () const [pure virtual]

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

Implemented in `activemq::commands::ActiveMQBlobMessage` (p. 205), `activemq::commands::ActiveMQBytesMessage` (p. 236), `activemq::commands::ActiveMQMapMessage` (p. 363), `activemq::commands::ActiveMQMessage` (p. 398), `activemq::commands::ActiveMQObjectMessage` (p. 444), `activemq::commands::ActiveMQStreamMessage` (p. 540), `activemq::commands::ActiveMQTextMessage` (p. 663), and `cms::BytesMessage` (p. 1059).

6.515.3.5 `virtual bool cms::Message::getBooleanProperty (const std::string & name) const throw (MessageFormatException, CMSEException) [pure virtual]`

Gets a boolean property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 429), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 429), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 429), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 429), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 429), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 429).

6.515.3.6 `virtual unsigned char cms::Message::getByteProperty (const std::string & name) const throw (MessageFormatException, CMSEException) [pure virtual]`

Gets a byte property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 430), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 430).

6.515.3.7 virtual std::string cms::Message::getCMSCorrelationID () const throw (CMSEException) [pure virtual]

Gets the correlation ID for the message. This method is used to return correlation ID values that are either provider-specific message IDs or application-specific String values.

Returns:

string representation of the correlation Id

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 430), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 430).

6.515.3.8 virtual int cms::Message::getCMSDeliveryMode () const throw (CMSEException) [pure virtual]

Gets the **DeliveryMode** (p.1721) for this message.

Returns:

DeliveryMode (p. 1721) enumerated value.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 430), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 430), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 430).

6.515.3.9 virtual const Destination* cms::Message::getCMSDestination () const throw (CMSEException) [pure virtual]

Gets the **Destination** (p. 1723) object for this message. The CMSDestination header field contains the destination to which the message is being sent.

When a message is sent, this field is ignored. After completion of the send or publish method, the field holds the destination specified by the method.

When a message is received, its CMSDestination value must be equivalent to the value assigned when it was sent.

Returns:

Destination (p. 1723) object

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 431), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 431).

6.515.3.10 `virtual long long cms::Message::getCMSExpiration () const throw (CMSEException) [pure virtual]`

Gets the message's expiration value. When a message is sent, the CMSExpiration header field is left unassigned. After completion of the send or publish method, it holds the expiration time of the message. This is the sum of the time-to-live value specified by the client and the GMT at the time of the send or publish.

If the time-to-live is specified as zero, CMSExpiration is set to zero to indicate that the message does not expire.

When a message's expiration time is reached, a provider should discard it. The CMS API does not define any form of notification of message expiration.

Clients should not receive messages that have expired; however, the CMS API does not guarantee that this will not happen.

Returns:

the time the message expires, which is the sum of the time-to-live value specified by the client and the GMT at the time of the send

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 431), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 431), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 431).

6.515.3.11 `virtual std::string cms::Message::getCMSMessageID () const throw (CMSEException) [pure virtual]`

The CMSMessageID header field contains a value that uniquely identifies each message sent by a provider. When a message is sent, CMSMessageID can be ignored. When the send or publish method returns, it contains a provider-assigned value.

A CMSMessageID is a String value that should function as a unique key for identifying messages in a historical repository. The exact scope of uniqueness is provider-defined. It should at least cover all messages for a specific installation of a provider, where an installation is some connected set of message routers.

All CMSMessageID values must start with the prefix 'ID:'. Uniqueness of message ID values across different providers is not required.

Since message IDs take some effort to create and increase a message's size, some CMS providers may be able to optimize message overhead if they are given a hint that the message ID is not used by an application. By calling the **MessageProducer.setDisableMessageID** (p. 2730) method, a CMS client enables this potential optimization for all messages sent by that message producer. If the CMS provider accepts this hint, these messages must have the message ID set to null; if the provider ignores the hint, the message ID must be set to its normal unique value.

Returns:

provider-assigned message id

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in **activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>** (p. 431), **activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>** (p. 431), **activemq::commands::ActiveMQMessageTemplate<cms::Message>** (p. 431), **activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>** (p. 431), **activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>** (p. 431), and **activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>** (p. 431).

6.515.3.12 virtual int cms::Message::getCMSPriority () const throw (CMSException) [pure virtual]

Gets the message priority level. The CMS API defines ten levels of priority value, with 0 as the lowest priority and 9 as the highest. In addition, clients should consider priorities 0-4 as gradations of normal priority and priorities 5-9 as gradations of expedited priority.

The CMS API does not require that a provider strictly implement priority ordering of messages; however, it should do its best to deliver expedited messages ahead of normal messages.

Returns:

priority value

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in **activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>** (p. 432), **activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>** (p. 432), **activemq::commands::ActiveMQMessageTemplate<cms::Message>** (p. 432), **activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>** (p. 432), **activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>** (p. 432), and **activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>** (p. 432).

6.515.3.13 `virtual bool cms::Message::getCMSRedelivered () const throw (CMSEException) [pure virtual]`

Gets an indication of whether this message is being redelivered. If a client receives a message with the CMSRedelivered field set, it is likely, but not guaranteed, that this message was delivered earlier but that its receipt was not acknowledged at that time.

Returns:

true if this message is being redelivered

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 432), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 432).

6.515.3.14 `virtual const cms::Destination* cms::Message::getCMSReplyTo () const throw (CMSEException) [pure virtual]`

Gets the **Destination** (p. 1723) object to which a reply to this message should be sent.

Returns:

Destination (p. 1723) to which to send a response to this message

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate< cms::BytesMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::MapMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::Message >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::StreamMessage >` (p. 432), `activemq::commands::ActiveMQMessageTemplate< cms::TextMessage >` (p. 432), and `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >` (p. 432).

6.515.3.15 `virtual long long cms::Message::getCMSTimestamp () const throw (CMSEException) [pure virtual]`

Gets the message timestamp. The CMSTimestamp header field contains the time a message was handed off to a provider to be sent. It is not the time the message was actually transmitted, because the actual send may occur later due to transactions or other client-side queuing of messages.

When a message is sent, CMSTimestamp is ignored. When the send or publish method returns, it contains a time value somewhere in the interval between the call and the return. The value is in the format of a normal millis time value in the Java programming language.

Since timestamps take some effort to create and increase a message's size, some CMS providers may be able to optimize message overhead if they are given a hint that the timestamp is not used by an application. By calling the `MessageProducer.setDisableMessageTimestamp` method, a CMS client enables this potential optimization for all messages sent by that message producer. If the CMS provider accepts this hint, these messages must have the timestamp set to zero; if the provider ignores the hint, the timestamp must be set to its normal value.

Returns:

the message timestamp

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 432), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 432), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 432), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 432), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 432), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 432).

6.515.3.16 `virtual std::string cms::Message::getCMSType () const throw (CMSEException) [pure virtual]`

Gets the message type identifier supplied by the client when the message was sent.

Returns:

the message type

See also:

`setCMSType` (p. 2554)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 433), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 433).

6.515.3.17 `virtual double cms::Message::getDoubleProperty (const std::string & name) const throw (MessageFormatException, CMSEException) [pure virtual]`

Gets a double property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 433), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 433).

6.515.3.18 `virtual float cms::Message::getFloatProperty (const std::string & name)
const throw (MessageFormatException, CMSEException) [pure
virtual]`

Gets a float property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 433), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 433), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 433).

6.515.3.19 `virtual int cms::Message::getIntProperty (const std::string & name)
const throw (MessageFormatException, CMSEException) [pure
virtual]`

Gets a int property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 434), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 434).

6.515.3.20 `virtual long long cms::Message::getLongProperty (const std::string & name) const throw (MessageFormatException, CMSEException)` [pure virtual]

Gets a long property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 434), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 434), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 434).

6.515.3.21 `virtual std::vector<std::string> cms::Message::getPropertyNames () const throw (CMSEException)` [pure virtual]

Retrieves the property names.

Returns:

The complete set of property names currently in this message.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 435), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 435).

6.515.3.22 `virtual short cms::Message::getShortProperty (const std::string & name) const throw (MessageFormatException, CMSEException) [pure virtual]`

Gets a short property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 435), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 435).

6.515.3.23 `virtual std::string cms::Message::getStringProperty (const std::string & name) const throw (MessageFormatException, CMSEException) [pure virtual]`

Gets a string property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

Exceptions:

CMSEException (p. 1160) if the property does not exist.

MessageFormatException (p. 2662) - if this type conversion is invalid.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 435), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 435), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 435).

6.515.3.24 `virtual bool cms::Message::propertyExists (const std::string & name) const throw (CMSException)` [pure virtual]

Indicates whether or not a given property exists.

Parameters:

name The name of the property to look up.

Returns:

True if the property exists in this message.

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 436), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 436), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 436), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 436), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 436), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 436).

6.515.3.25 `virtual void cms::Message::setBooleanProperty (const std::string & name, bool value) throw (MessageNotWriteableException, CMSException)` [pure virtual]

Sets a boolean property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 436), `activemq::commands::ActiveMQMessageTemplate<`

`cms::MapMessage` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::Message` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::StreamMessage` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::TextMessage` > (p. 436), and `activemq::commands::ActiveMQMessageTemplate<`
`cms::ObjectMessage` > (p. 436).

6.515.3.26 `virtual void cms::Message::setByteProperty (const std::string & name, unsigned char value) throw (MessageNotWriteableException, CMSException) [pure virtual]`

Sets a byte property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<`
`cms::BytesMessage` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::MapMessage` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::Message` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::StreamMessage` > (p. 436), `activemq::commands::ActiveMQMessageTemplate<`
`cms::TextMessage` > (p. 436), and `activemq::commands::ActiveMQMessageTemplate<`
`cms::ObjectMessage` > (p. 436).

6.515.3.27 `virtual void cms::Message::setCMSCorrelationID (const std::string & correlationId) throw (CMSException) [pure virtual]`

Sets the correlation ID for the message. A client can use the CMSCorrelationID header field to link one message with another. A typical use is to link a response message with its request message.

CMSCorrelationID can hold one of the following:

- A provider-specific message ID
- An application-specific String
- A provider-native byte[] value

Since each message sent by a CMS provider is assigned a message ID value, it is convenient to link messages via message ID. All message ID values must start with the 'ID:' prefix.

In some cases, an application (made up of several clients) needs to use an application-specific value for linking messages. For instance, an application may use CMSCorrelationID to hold a value referencing some external information. Application-specified values must not start with the 'ID:' prefix; this is reserved for provider-generated message ID values.

If a provider supports the native concept of correlation ID, a CMS client may need to assign specific CMSCorrelationID values to match those expected by clients that do not use the CMS API. A byte[] value is used for this purpose. CMS providers without native correlation ID values are not required to support byte[] values. The use of a byte[] value for CMSCorrelationID is non-portable.

Parameters:

correlationId The message ID of a message being referred to.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 437), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 437).

6.515.3.28 virtual void cms::Message::setCMSDeliveryMode (int *mode*) throw (CMSEException) [pure virtual]

Sets the **DeliveryMode** (p. 1721) for this message. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

mode **DeliveryMode** (p. 1721) enumerated value.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 437), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 437).

6.515.3.29 virtual void cms::Message::setCMSDestination (const Destination * *destination*) throw (CMSEException) [pure virtual]

Sets the **Destination** (p. 1723) object for this message. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

destination **Destination** (p. 1723) Object

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 437), `activemq::commands::ActiveMQMessageTemplate<`

`cms::MapMessage` > (p. 437), `activemq::commands::ActiveMQMessageTemplate<`
`cms::Message` > (p. 437), `activemq::commands::ActiveMQMessageTemplate<`
`cms::StreamMessage` > (p. 437), `activemq::commands::ActiveMQMessageTemplate<`
`cms::TextMessage` > (p. 437), and `activemq::commands::ActiveMQMessageTemplate<`
`cms::ObjectMessage` > (p. 437).

6.515.3.30 `virtual void cms::Message::setCMSExpiration (long long expireTime)
throw (CMSException) [pure virtual]`

Sets the message's expiration value. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

expireTime the message's expiration time

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<`
`cms::BytesMessage` > (p. 438), `activemq::commands::ActiveMQMessageTemplate<`
`cms::MapMessage` > (p. 438), `activemq::commands::ActiveMQMessageTemplate<`
`cms::Message` > (p. 438), `activemq::commands::ActiveMQMessageTemplate<`
`cms::StreamMessage` > (p. 438), `activemq::commands::ActiveMQMessageTemplate<`
`cms::TextMessage` > (p. 438), and `activemq::commands::ActiveMQMessageTemplate<`
`cms::ObjectMessage` > (p. 438).

6.515.3.31 `virtual void cms::Message::setCMSMessageID (const std::string & id)
throw (CMSException) [pure virtual]`

Sets the message ID. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

id the ID of the message

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

6.515.3.32 `virtual void cms::Message::setCMSPriority (int priority) throw (
CMSException) [pure virtual]`

Sets the Priority Value for this message. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

priority priority value for this message

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 438), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 438).

6.515.3.33 virtual void cms::Message::setCMSRedelivered (bool *redelivered*) throw (CMSException) [pure virtual]

Specifies whether this message is being redelivered. This field is set at the time the message is delivered. This method can be used to change the value for a message that has been received.

Parameters:

redelivered boolean redelivered value

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::Message>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage>` (p. 438), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage>` (p. 438), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage>` (p. 438).

6.515.3.34 virtual void cms::Message::setCMSReplyTo (const cms::Destination * *destination*) throw (CMSException) [pure virtual]

Sets the **Destination** (p.1723) object to which a reply to this message should be sent. The CMSReplyTo header field contains the destination where a reply to the current message should be sent. If it is null, no reply is expected. The destination may be either a **Queue** (p. 3148) object or a **Topic** (p. 3817) object.

Messages sent with a null CMSReplyTo value may be a notification of some event, or they may just be some data the sender thinks is of interest.

Messages with a CMSReplyTo value typically expect a response. A response is optional; it is up to the client to decide. These messages are called requests. A message sent in response to a request is called a reply.

In some cases a client may wish to match a request it sent earlier with a reply it has just received. The client can use the CMSCorrelationID header field for this purpose.

Parameters:

destination **Destination** (p.1723) to which to send a response to this message

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 439), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 439).

6.515.3.35 `virtual void cms::Message::setCMSTimestamp (long long timeStamp) throw (CMSEException)` [pure virtual]

Sets the message timestamp. CMS providers set this field when a message is sent. This method can be used to change the value for a message that has been received.

Parameters:

timeStamp integer time stamp value

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 439), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 439).

6.515.3.36 `virtual void cms::Message::setCMSType (const std::string & type) throw (CMSEException)` [pure virtual]

Sets the message type. Some CMS providers use a message repository that contains the definitions of messages sent by applications. The CMSType header field may reference a message's definition in the provider's repository.

The CMS API does not define a standard message definition repository, nor does it define a naming policy for the definitions it contains.

Some messaging systems require that a message type definition for each application message be created and that each message specify its type. In order to work with such CMS providers, CMS clients should assign a value to CMSType, whether the application makes use of it or not. This ensures that the field is properly set for those providers that require it.

To ensure portability, CMS clients should use symbolic values for CMSType that can be configured at installation time to the values defined in the current provider's message repository. If string literals are used, they may not be valid type names for some CMS providers.

Parameters:

type the message type

See also:

`getCMSType` (p. 2545)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 439), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 439), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 439).

6.515.3.37 `virtual void cms::Message::setDoubleProperty (const std::string & name, double value) throw (MessageNotWriteableException, CMSEException) [pure virtual]`

Sets a double property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSEException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 440), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 440).

6.515.3.38 `virtual void cms::Message::setFloatProperty (const std::string & name, float value) throw (MessageNotWriteableException, CMSEException) [pure virtual]`

Sets a float property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSEException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 440), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 440).

6.515.3.39 `virtual void cms::Message::setIntProperty (const std::string & name, int value) throw (MessageNotWriteableException, CMSException)` [pure virtual]

Sets a int property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::MapMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::Message >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::StreamMessage >` (p. 440), `activemq::commands::ActiveMQMessageTemplate<cms::TextMessage >` (p. 440), and `activemq::commands::ActiveMQMessageTemplate<cms::ObjectMessage >` (p. 440).

6.515.3.40 `virtual void cms::Message::setLongProperty (const std::string & name, long long value) throw (MessageNotWriteableException, CMSException)` [pure virtual]

Sets a long property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in `activemq::commands::ActiveMQMessageTemplate<cms::BytesMessage >` (p. 441), `activemq::commands::ActiveMQMessageTemplate<`

cms::MapMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::Message > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::StreamMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::TextMessage > (p. 441), and **activemq::commands::ActiveMQMessageTemplate**<
cms::ObjectMessage > (p. 441).

6.515.3.41 `virtual void cms::Message::setShortProperty (const std::string & name, short value) throw (MessageNotWriteableException, CMSException)` [pure virtual]

Sets a short property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in **activemq::commands::ActiveMQMessageTemplate**<
cms::BytesMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::MapMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::Message > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::StreamMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::TextMessage > (p. 441), and **activemq::commands::ActiveMQMessageTemplate**<
cms::ObjectMessage > (p. 441).

6.515.3.42 `virtual void cms::Message::setStringProperty (const std::string & name, const std::string & value) throw (MessageNotWriteableException, CMSException)` [pure virtual]

Sets a string property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

Exceptions:

CMSException (p. 1160) - if the name is an empty string.

MessageNotWriteableException (p. 2724) - if properties are read-only

Implemented in **activemq::commands::ActiveMQMessageTemplate**<
cms::BytesMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::MapMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::Message > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::StreamMessage > (p. 441), **activemq::commands::ActiveMQMessageTemplate**<
cms::TextMessage > (p. 441), and **activemq::commands::ActiveMQMessageTemplate**<
cms::ObjectMessage > (p. 441).

The documentation for this class was generated from the following file:

- `src/main/cms/Message.h`

6.516 activemq::commands::MessageAck Class Reference

#include <src/main/activemq/commands/MessageAck.h> Inheritance diagram for activemq::commands::MessageAck:

Public Member Functions

- **MessageAck** ()
- virtual **~MessageAck** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **MessageAck * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual const **Pointer**< **TransactionId** > & **getTransactionId** () const
- virtual **Pointer**< **TransactionId** > & **getTransactionId** ()
- virtual void **setTransactionId** (const **Pointer**< **TransactionId** > &transactionId)
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual unsigned char **getAckType** () const
- virtual void **setAckType** (unsigned char ackType)
- virtual const **Pointer**< **MessageId** > & **getFirstMessageId** () const
- virtual **Pointer**< **MessageId** > & **getFirstMessageId** ()
- virtual void **setFirstMessageId** (const **Pointer**< **MessageId** > &firstMessageId)
- virtual const **Pointer**< **MessageId** > & **getLastMessageId** () const
- virtual **Pointer**< **MessageId** > & **getLastMessageId** ()
- virtual void **setLastMessageId** (const **Pointer**< **MessageId** > &lastMessageId)
- virtual int **getMessageCount** () const
- virtual void **setMessageCount** (int messageCount)
- virtual bool **isMessageAck** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_MESSAGEACK** = 22

Protected Attributes

- **Pointer**< **ActiveMQDestination** > **destination**
- **Pointer**< **TransactionId** > **transactionId**
- **Pointer**< **ConsumerId** > **consumerId**
- unsigned char **ackType**
- **Pointer**< **MessageId** > **firstMessageId**
- **Pointer**< **MessageId** > **lastMessageId**
- int **messageCount**

6.516.1 Constructor & Destructor Documentation

6.516.1.1 **activemq::commands::MessageAck::MessageAck ()**

6.516.1.2 **virtual activemq::commands::MessageAck::~~MessageAck ()** [virtual]

6.516.2 Member Function Documentation

6.516.2.1 **virtual MessageAck* activemq::commands::MessageAck::cloneDataStructure ()**
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.516.2.2 **virtual void activemq::commands::MessageAck::copyDataStructure (const DataStructure * *src*)** [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.516.2.3 **virtual bool activemq::commands::MessageAck::equals (const DataStructure * *value*)** const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.516.2.4 virtual unsigned char activemq::commands::MessageAck::getAckType ()
const [virtual]

6.516.2.5 virtual Pointer<ConsumerId>& activemq::commands::MessageAck::getConsumerId ()
[virtual]

6.516.2.6 virtual const Pointer<ConsumerId>& activemq::commands::MessageAck::getConsumerId () const
[virtual]

6.516.2.7 virtual unsigned char activemq::commands::MessageAck::getDataStructureType ()
const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.516.2.8** `virtual Pointer<ActiveMQDestination>& activemq::commands::MessageAck::getDestination ()`
[virtual]
- 6.516.2.9** `virtual const Pointer<ActiveMQDestination>& activemq::commands::MessageAck::getDestination () const` [virtual]
- 6.516.2.10** `virtual Pointer<MessageId>& activemq::commands::MessageAck::getFirstMessageId ()`
[virtual]
- 6.516.2.11** `virtual const Pointer<MessageId>& activemq::commands::MessageAck::getFirstMessageId ()`
`const` [virtual]
- 6.516.2.12** `virtual Pointer<MessageId>& activemq::commands::MessageAck::getLastMessageId ()`
[virtual]
- 6.516.2.13** `virtual const Pointer<MessageId>& activemq::commands::MessageAck::getLastMessageId ()`
`const` [virtual]
- 6.516.2.14** `virtual int activemq::commands::MessageAck::getMessageCount () const`
[virtual]
- 6.516.2.15** `virtual Pointer<TransactionId>& activemq::commands::MessageAck::getTransactionId ()`
[virtual]
- 6.516.2.16** `virtual const Pointer<TransactionId>& activemq::commands::MessageAck::getTransactionId () const`
[virtual]
- 6.516.2.17** `virtual bool activemq::commands::MessageAck::isMessageAck () const`
[inline, virtual]

Returns:

an answer of true to the `isMessageAck()` (p. 2562) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 761).

- 6.516.2.18 `virtual void activemq::commands::MessageAck::setAckType (unsigned char ackType) [virtual]`
- 6.516.2.19 `virtual void activemq::commands::MessageAck::setConsumerId (const Pointer< ConsumerId > & consumerId) [virtual]`
- 6.516.2.20 `virtual void activemq::commands::MessageAck::setDestination (const Pointer< ActiveMQDestination > & destination) [virtual]`
- 6.516.2.21 `virtual void activemq::commands::MessageAck::setFirstMessageId (const Pointer< MessageId > & firstMessageId) [virtual]`
- 6.516.2.22 `virtual void activemq::commands::MessageAck::setLastMessageId (const Pointer< MessageId > & lastMessageId) [virtual]`
- 6.516.2.23 `virtual void activemq::commands::MessageAck::setMessageCount (int messageCount) [virtual]`
- 6.516.2.24 `virtual void activemq::commands::MessageAck::setTransactionId (const Pointer< TransactionId > & transactionId) [virtual]`
- 6.516.2.25 `virtual std::string activemq::commands::MessageAck::toString () const [virtual]`

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.516.2.26 `virtual Pointer<Command> activemq::commands::MessageAck::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.516.3 Field Documentation

- 6.516.3.1 `unsigned char activemq::commands::MessageAck::ackType` [protected]
- 6.516.3.2 `Pointer<ConsumerId> activemq::commands::MessageAck::consumerId` [protected]
- 6.516.3.3 `Pointer<ActiveMQDestination> activemq::commands::MessageAck::destination` [protected]
- 6.516.3.4 `Pointer<MessageId> activemq::commands::MessageAck::firstMessageId` [protected]
- 6.516.3.5 `const unsigned char activemq::commands::MessageAck::ID_ - MESSAGEACK = 22` [static]
- 6.516.3.6 `Pointer<MessageId> activemq::commands::MessageAck::lastMessageId` [protected]
- 6.516.3.7 `int activemq::commands::MessageAck::messageCount` [protected]
- 6.516.3.8 `Pointer<TransactionId> activemq::commands::MessageAck::transactionId` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/MessageAck.h`

6.517 activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2565).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessageAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller:

Public Member Functions

- `MessageAckMarshaller ()`
- `virtual ~MessageAckMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.517.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2565).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.517.2 Constructor & Destructor Documentation

6.517.2.1 `activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.517.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.517.3 Member Function Documentation

6.517.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.517.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.517.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.517.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.517.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.517.3.6 virtual void activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.517.3.7 virtual void activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/MessageAckMarshaller.h

6.518 activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2569).

#include <src/main/activemq/wireformat/openwire/marshal/v2/MessageAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller:

Public Member Functions

- `MessageAckMarshaller ()`
- `virtual ~MessageAckMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.518.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2569).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.518.2 Constructor & Destructor Documentation

6.518.2.1 `activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.518.2.2 `virtual activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.518.3 Member Function Documentation

6.518.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.518.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.518.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.518.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.518.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.518.3.6 virtual void activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.518.3.7 virtual void activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/MessageAckMarshaller.h

6.519 activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2573).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessageAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller:

Public Member Functions

- `MessageAckMarshaller ()`
- `virtual ~MessageAckMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.519.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for `MessageAckMarshaller` (p.2573).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.519.2 Constructor & Destructor Documentation

6.519.2.1 `activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.519.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.519.3 Member Function Documentation

6.519.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.519.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.519.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.519.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.519.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.519.3.6 virtual void activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.519.3.7 virtual void activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/MessageAckMarshaller.h

6.520 activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2577).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessageAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller:

Public Member Functions

- **MessageAckMarshaller** ()
- virtual **~MessageAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.520.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2577).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.520.2 Constructor & Destructor Documentation

6.520.2.1 `activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.520.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.520.3 Member Function Documentation

6.520.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.520.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.520.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.520.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.520.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.520.3.6 virtual void activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.520.3.7 virtual void activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/MessageAckMarshaller.h

6.521 activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2581).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessageAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller:

Public Member Functions

- **MessageAckMarshaller** ()
- virtual **~MessageAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.521.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2581).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.521.2 Constructor & Destructor Documentation

6.521.2.1 `activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.521.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.521.3 Member Function Documentation

6.521.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.521.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.521.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.521.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.521.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.521.3.6 virtual void activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.521.3.7 virtual void activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/MessageAckMarshaller.h

6.522 activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2585).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessageAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller:

Public Member Functions

- **MessageAckMarshaller** ()
- virtual **~MessageAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.522.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessageAckMarshaller** (p.2585).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.522.2 Constructor & Destructor Documentation

6.522.2.1 `activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::MessageAckMarshaller()` [inline]

6.522.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::~~MessageAckMarshaller()` [inline, virtual]

6.522.3 Member Function Documentation

6.522.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.522.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.522.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.522.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.522.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.522.3.6 virtual void activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.522.3.7 virtual void activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/MessageAckMarshaller.h

6.523 cms::MessageConsumer Class Reference

A client uses a `MessageConsumer` (p. 2589) to received messages from a destination.

```
#include <src/main/cms/MessageConsumer.h> Inheritance diagram for
cms::MessageConsumer:
```

Public Member Functions

- virtual `~MessageConsumer ()`
- virtual `Message * receive ()=0 throw (CMSEException)`
*Synchronously Receive a **Message** (p. 2534).*
- virtual `Message * receive (int millisecs)=0 throw (CMSEException)`
*Synchronously Receive a **Message** (p. 2534), time out after defined interval.*
- virtual `Message * receiveNoWait ()=0 throw (CMSEException)`
*Receive a **Message** (p. 2534), does not wait if there isn't a new message to read, returns **NULL** if nothing read.*
- virtual void `setMessageListener (MessageListener *listener)=0 throw (CMSEException)`
*Sets the **MessageListener** (p. 2692) that this class will send notifs on.*
- virtual `MessageListener * getMessageListener () const =0 throw (CMSEException)`
*Gets the **MessageListener** (p. 2692) that this class will send new **Message** (p. 2534) notification events to.*
- virtual std::string `getMessageSelector () const =0 throw (cms::CMSEException)`
Gets this message consumer's message selector expression.

6.523.1 Detailed Description

A client uses a `MessageConsumer` (p. 2589) to received messages from a destination. A client may either synchronously receive a message consumer's messages or have the consumer asynchronously deliver them as they arrive.

For synchronous receipt, a client can request the next message from a message consumer using one of its `receive` methods. There are several variations of `receive` that allow a client to poll or wait for the next message.

For asynchronous delivery, a client can register a `MessageListener` (p. 2692) object with a message consumer. As messages arrive at the message consumer, it delivers them by calling the `MessageListener` (p. 2692)'s `onMessage` method.

When the `MessageConsumer`'s `close` method is called the method can block while an asynchronous message delivery is in progress or until a `receive` operation completes. A blocked consumer in a `receive` call will return a Null when the `close` method is called.

See also:

`MessageListener` (p. 2692)

Since:

1.0

6.523.2 Constructor & Destructor Documentation

6.523.2.1 `virtual cms::MessageConsumer::~~MessageConsumer () [inline, virtual]`

6.523.3 Member Function Documentation

6.523.3.1 `virtual MessageListener* cms::MessageConsumer::getMessageListener () const throw (CMSEException) [pure virtual]`

Gets the `MessageListener` (p. 2692) that this class will send new `Message` (p. 2534) notification events to.

Returns:

The listener of messages received by this consumer

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1072), and `activemq::core::ActiveMQConsumer` (p. 315).

6.523.3.2 `virtual std::string cms::MessageConsumer::getMessageSelector () const throw (cms::CMSEException) [pure virtual]`

Gets this message consumer's message selector expression.

Returns:

This Consumer's selector expression or "".

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1072), and `activemq::core::ActiveMQConsumer` (p. 316).

6.523.3.3 `virtual Message* cms::MessageConsumer::receive (int millisecs) throw (CMSEException) [pure virtual]`

Synchronously Receive a `Message` (p. 2534), time out after defined interval. Returns null if nothing read.

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1073), and `activemq::core::ActiveMQConsumer` (p. 317).

6.523.3.4 virtual Message* cms::MessageConsumer::receive () throw (CMSEException) [pure virtual]

Synchronously Receive a **Message** (p. 2534).

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1073), and `activemq::core::ActiveMQConsumer` (p. 317).

6.523.3.5 virtual Message* cms::MessageConsumer::receiveNoWait () throw (CMSEException) [pure virtual]

Receive a **Message** (p. 2534), does not wait if there isn't a new message to read, returns NULL if nothing read.

Returns:

new message which the caller owns and must delete.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1073), and `activemq::core::ActiveMQConsumer` (p. 317).

6.523.3.6 virtual void cms::MessageConsumer::setMessageListener (MessageListener * listener) throw (CMSEException) [pure virtual]

Sets the **MessageListener** (p. 2692) that this class will send notifs on.

Parameters:

listener The listener of messages received by this consumer.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::CachedConsumer` (p. 1073), and `activemq::core::ActiveMQConsumer` (p. 318).

The documentation for this class was generated from the following file:

- `src/main/cms/MessageConsumer.h`

6.524 activemq::cmsutil::MessageCreator Class Reference

Creates the user-defined message to be sent by the CmsTemplate (p. 1170).

```
#include <src/main/activemq/cmsutil/MessageCreator.h>
```

Public Member Functions

- virtual `~MessageCreator()`
- virtual `cms::Message * createMessage (cms::Session *session)=0` throw (`cms::CMSEException`)

Creates a message from the given session.

6.524.1 Detailed Description

Creates the user-defined message to be sent by the CmsTemplate (p. 1170).

6.524.2 Constructor & Destructor Documentation

6.524.2.1 virtual `activemq::cmsutil::MessageCreator::~MessageCreator()`
[inline, virtual]

6.524.3 Member Function Documentation

6.524.3.1 virtual `cms::Message* activemq::cmsutil::MessageCreator::createMessage (cms::Session * session)` throw (`cms::CMSEException`) [pure virtual]

Creates a message from the given session.

Parameters:

session the CMS Session

Exceptions:

cms::CMSEException (p. 1160) if thrown by CMS API methods

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/MessageCreator.h`

6.525 activemq::commands::MessageDispatch Class Reference

#include <src/main/activemq/commands/MessageDispatch.h> Inheritance diagram for activemq::commands::MessageDispatch:

Public Member Functions

- **MessageDispatch** ()
- virtual **~MessageDispatch** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **MessageDispatch** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual const **Pointer**< **Message** > & **getMessage** () const
- virtual **Pointer**< **Message** > & **getMessage** ()
- virtual void **setMessage** (const **Pointer**< **Message** > &message)
- virtual int **getRedeliveryCounter** () const
- virtual void **setRedeliveryCounter** (int redeliveryCounter)
- virtual bool **isMessageDispatch** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_MESSAGE_DISPATCH** = 21

Protected Attributes

- `Pointer< ConsumerId > consumerId`
- `Pointer< ActiveMQDestination > destination`
- `Pointer< Message > message`
- `int redeliveryCounter`

6.525.1 Constructor & Destructor Documentation

6.525.1.1 `activemq::commands::MessageDispatch::MessageDispatch ()`

6.525.1.2 `virtual activemq::commands::MessageDispatch::~~MessageDispatch ()`
[virtual]

6.525.2 Member Function Documentation

6.525.2.1 `virtual MessageDispatch* activemq::commands::MessageDispatch::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.525.2.2 `virtual void activemq::commands::MessageDispatch::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.525.2.3 `virtual bool activemq::commands::MessageDispatch::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.525.2.4 `virtual Pointer<ConsumerId>& activemq::commands::MessageDispatch::getConsumerId ()`
[virtual]
- 6.525.2.5 `virtual const Pointer<ConsumerId>& activemq::commands::MessageDispatch::getConsumerId ()`
const [virtual]
- 6.525.2.6 `virtual unsigned char activemq::commands::MessageDispatch::getDataStructureType ()` const
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSet** (p. 1660) type copy.

Implements **activemq::commands::DataSet** (p. 1662).

- 6.525.2.7 `virtual Pointer<ActiveMQDestination>& activemq::commands::MessageDispatch::getDestination ()`
[virtual]
- 6.525.2.8 `virtual const Pointer<ActiveMQDestination>& activemq::commands::MessageDispatch::getDestination ()` const
[virtual]
- 6.525.2.9 `virtual Pointer<Message>& activemq::commands::MessageDispatch::getMessage ()`
[virtual]
- 6.525.2.10 `virtual const Pointer<Message>& activemq::commands::MessageDispatch::getMessage ()`
const [virtual]
- 6.525.2.11 `virtual int activemq::commands::MessageDispatch::getRedeliveryCounter ()` const
[virtual]
- 6.525.2.12 `virtual bool activemq::commands::MessageDispatch::isMessageDispatch ()` const [inline, virtual]

Returns:

an answer of true to the **isMessageDispatch()** (p. 2596) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 761).

- 6.525.2.13** `virtual void activemq::commands::MessageDispatch::setConsumerId (const Pointer< ConsumerId > & consumerId) [virtual]`
- 6.525.2.14** `virtual void activemq::commands::MessageDispatch::setDestination (const Pointer< ActiveMQDestination > & destination) [virtual]`
- 6.525.2.15** `virtual void activemq::commands::MessageDispatch::setMessage (const Pointer< Message > & message) [virtual]`
- 6.525.2.16** `virtual void activemq::commands::MessageDispatch::setRedeliveryCounter (int redeliveryCounter) [virtual]`
- 6.525.2.17** `virtual std::string activemq::commands::MessageDispatch::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.525.2.18** `virtual Pointer<Command> activemq::commands::MessageDispatch::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.525.3 Field Documentation

- 6.525.3.1 `Pointer<ConsumerId> activemq::commands::MessageDispatch::consumerId`
[protected]
- 6.525.3.2 `Pointer<ActiveMQDestination> activemq::commands::MessageDispatch::destination`
[protected]
- 6.525.3.3 `const unsigned char activemq::commands::MessageDispatch::ID_ -
MESSAGEDISPATCH = 21` [static]
- 6.525.3.4 `Pointer<Message> activemq::commands::MessageDispatch::message`
[protected]
- 6.525.3.5 `int activemq::commands::MessageDispatch::redeliveryCounter`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/MessageDispatch.h`

6.526 activemq::core::MessageDispatchChannel Class Reference

#include <src/main/activemq/core/MessageDispatchChannel.h> Inheritance diagram for activemq::core::MessageDispatchChannel:

Public Member Functions

- **MessageDispatchChannel** ()
- virtual **~MessageDispatchChannel** ()
- void **enqueue** (const **Pointer**< **MessageDispatch** > &message)
Add a Message to the Channel behind all pending message.
- void **enqueueFirst** (const **Pointer**< **MessageDispatch** > &message)
Add a message to the front of the Channel.
- bool **isEmpty** () const
- bool **isClosed** () const
- bool **isRunning** () const
- **Pointer**< **MessageDispatch** > **dequeue** (long long timeout) throw (exceptions::ActiveMQException)
Used to get an enqueued message.
- **Pointer**< **MessageDispatch** > **dequeueNowait** ()
Used to get an enqueued message if there is one queued right now.
- **Pointer**< **MessageDispatch** > **peek** () const
Peek in the Queue and return the first message in the Channel without removing it from the channel.
- void **start** ()
Starts dispatch of messages from the Channel.
- void **stop** ()
Stops dispatch of message from the Channel.
- void **close** ()
Close this channel no messages will be dispatched after this method is called.
- void **clear** ()
Clear the Channel, all pending messages are removed.
- int **size** () const
- std::vector< **Pointer**< **MessageDispatch** > > **removeAll** ()
Remove all messages that are currently in the Channel and return them as a list of Messages.
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)

Locks the object.

- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentOutOfRangeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

6.526.1 Constructor & Destructor Documentation

6.526.1.1 activemq::core::MessageDispatchChannel::MessageDispatchChannel ()

6.526.1.2 virtual activemq::core::MessageDispatchChannel::~~MessageDispatchChannel () [virtual]

6.526.2 Member Function Documentation

6.526.2.1 void activemq::core::MessageDispatchChannel::clear ()

Clear the Channel, all pending messages are removed.

6.526.2.2 void activemq::core::MessageDispatchChannel::close ()

Close this channel no messages will be dispatched after this method is called.

6.526.2.3 `Pointer<MessageDispatch> activemq::core::MessageDispatchChannel::dequeue (long long timeout) throw (exceptions::ActiveMQException)`

Used to get an enqueued message. The amount of time this method blocks is based on the timeout value. - if timeout==1 then it blocks until a message is received. - if timeout==0 then it tries to not block at all, it returns a message if it is available - if timeout>0 then it blocks up to timeout amount of time. Expired messages will be consumed by this method.

Returns:

null if we timeout or if the consumer is closed.

Exceptions:

ActiveMQException

6.526.2.4 `Pointer<MessageDispatch> activemq::core::MessageDispatchChannel::dequeueNoWait ()`

Used to get an enqueued message if there is one queued right now. If there is no waiting message then this method returns Null.

Returns:

a message if there is one in the queue.

6.526.2.5 `void activemq::core::MessageDispatchChannel::enqueue (const Pointer< MessageDispatch > & message)`

Add a Message to the Channel behind all pending message.

Parameters:

message - The message to add to the Channel.

6.526.2.6 `void activemq::core::MessageDispatchChannel::enqueueFirst (const Pointer< MessageDispatch > & message)`

Add a message to the front of the Channel.

Parameters:

message - The Message to add to the front of the Channel.

6.526.2.7 `bool activemq::core::MessageDispatchChannel::isClosed () const [inline]`

Returns:

has the Queue been closed.

6.526.2.8 `bool activemq::core::MessageDispatchChannel::isEmpty () const`**Returns:**

true if there are no messages in the Channel.

6.526.2.9 `bool activemq::core::MessageDispatchChannel::isRunning () const`
[inline]**Returns:**

true if the Channel currently running and will dequeue message.

6.526.2.10 `virtual void activemq::core::MessageDispatchChannel::lock () throw (`
`decaf::lang::exceptions::RuntimeException)` [inline, virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3701).

6.526.2.11 `virtual void activemq::core::MessageDispatchChannel::notify`
`() throw (decaf::lang::exceptions::RuntimeException,`
`decaf::lang::exceptions::IllegalMonitorStateException)` [inline,
virtual]

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads (p. 96).

Implements `decaf::util::concurrent::Synchronizable` (p. 3702).

6.526.2.12 `virtual void activemq::core::MessageDispatchChannel::notifyAll`
`() throw (decaf::lang::exceptions::RuntimeException,`
`decaf::lang::exceptions::IllegalMonitorStateException)` [inline,
virtual]

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting **threads** (p. 96).

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.526.2.13 `Pointer<MessageDispatch> activemq::core::MessageDispatchChannel::peek () const`

Peek in the Queue and return the first message in the Channel without removing it from the channel.

Returns:

a message if there is one in the queue.

6.526.2.14 `std::vector< Pointer<MessageDispatch> > activemq::core::MessageDispatchChannel::removeAll ()`

Remove all messages that are currently in the Channel and return them as a list of Messages.

Returns:

a list of Messages that was previously in the Channel.

6.526.2.15 `int activemq::core::MessageDispatchChannel::size () const`

Returns:

the number of Messages currently in the Channel.

6.526.2.16 `void activemq::core::MessageDispatchChannel::start ()`

Starts dispatch of messages from the Channel.

6.526.2.17 `void activemq::core::MessageDispatchChannel::stop ()`

Stops dispatch of message from the Channel.

6.526.2.18 `virtual bool activemq::core::MessageDispatchChannel::tryLock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3704).

6.526.2.19 `virtual void activemq::core::MessageDispatchChannel::unlock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3705).

6.526.2.20 `virtual void activemq::core::MessageDispatchChannel::wait (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3707).

6.526.2.21 `virtual void activemq::core::MessageDispatchChannel::wait (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

```
6.526.2.22 virtual void activemq::core::MessageDispatchChannel::wait  
() throw ( decaf::lang::exceptions::RuntimeException,  
decaf::lang::exceptions::IllegalMonitorStateException,  
decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- src/main/activemq/core/MessageDispatchChannel.h

6.527 activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2606).

`#include <src/main/activemq/wireformat/openwire/marshal/v2/MessageDispatchMarshaller.h>` Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.527.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2606).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.527.2 Constructor & Destructor Documentation

6.527.2.1 `activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::MessageDispatch
() [inline]`

6.527.2.2 `virtual
activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::~~MessageDispatch
() [inline, virtual]`

6.527.3 Member Function Documentation

6.527.3.1 `virtual commands::DataStructure* ac-
tivemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::createObject
() const [virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.527.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::getDataStructure
() const [virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.527.3.3 `virtual void ac-
tivemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::looseMarshal
(OpenWireFormat * wireFormat, commands::DataStructure *
dataStructure, decaf::io::DataOutputStream * dataOut) throw (
decaf::io::IOException) [virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.527.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.527.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.527.3.6 virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.527.3.7 virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/MessageDispatchMarshaller.h

6.528 activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2610).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.528.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2610).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.528.2 Constructor & Destructor Documentation

6.528.2.1 `activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::MessageDispatchMarshaller()` [inline]

6.528.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::~~MessageDispatchMarshaller()` [inline, virtual]

6.528.3 Member Function Documentation

6.528.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.528.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.528.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.528.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.528.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.528.3.6 virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.528.3.7 virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchMarshaller.h

6.529 activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2614).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.529.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2614).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.529.2 Constructor & Destructor Documentation

6.529.2.1 `activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::MessageDispatchMarshaller()` [inline]

6.529.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::~~MessageDispatchMarshaller()` [inline, virtual]

6.529.3 Member Function Documentation

6.529.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.529.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.529.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.529.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.529.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.529.3.6 virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.529.3.7 virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchMarshaller.h

6.530 activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2618).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessageDispatchMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.530.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2618).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.530.2 Constructor & Destructor Documentation

6.530.2.1 `activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::MessageDispatchMarshaller()` [inline]

6.530.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::~~MessageDispatchMarshaller()` [inline, virtual]

6.530.3 Member Function Documentation

6.530.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.530.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.530.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.530.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.530.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.530.3.6 virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.530.3.7 virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/MessageDispatchMarshaller.h

6.531 activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2622).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.531.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2622).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.531.2 Constructor & Destructor Documentation

6.531.2.1 `activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::MessageDispatchMarshaller()` [inline]

6.531.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::~~MessageDispatchMarshaller()` [inline, virtual]

6.531.3 Member Function Documentation

6.531.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.531.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.531.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.531.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.531.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.531.3.6 virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.531.3.7 virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchMarshaller.h

6.532 activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2626).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessageDispatchMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller`:

Public Member Functions

- `MessageDispatchMarshaller ()`
- `virtual ~MessageDispatchMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.532.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageDispatchMarshaller` (p. 2626).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.532.2 Constructor & Destructor Documentation

6.532.2.1 `activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::MessageDispatchMarshaller()` [inline]

6.532.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::~~MessageDispatchMarshaller()` [inline, virtual]

6.532.3 Member Function Documentation

6.532.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.532.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.532.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.532.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.532.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.532.3.6 virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.532.3.7 virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/MessageDispatchMarshaller.h

6.533 activemq::commands::MessageDispatchNotification Class Reference

#include <src/main/activemq/commands/MessageDispatchNotification.h> Inheritance diagram for activemq::commands::MessageDispatchNotification:

Public Member Functions

- **MessageDispatchNotification** ()
- virtual **~MessageDispatchNotification** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **MessageDispatchNotification * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual long long **getDeliverySequenceId** () const
- virtual void **setDeliverySequenceId** (long long deliverySequenceId)
- virtual const **Pointer**< **MessageId** > & **getMessageId** () const
- virtual **Pointer**< **MessageId** > & **getMessageId** ()
- virtual void **setMessageId** (const **Pointer**< **MessageId** > &messageId)
- virtual bool **isMessageDispatchNotification** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_MESSAGE_DISPATCH_NOTIFICATION** = 90

Protected Attributes

- **Pointer**< **ConsumerId** > **consumerId**
- **Pointer**< **ActiveMQDestination** > **destination**
- long long **deliverySequenceId**
- **Pointer**< **MessageId** > **messageId**

6.533.1 Constructor & Destructor Documentation

6.533.1.1 **activemq::commands::MessageDispatchNotification::MessageDispatchNotification**
()

6.533.1.2 **virtual**
activemq::commands::MessageDispatchNotification::~~MessageDispatchNotification
() [virtual]

6.533.2 Member Function Documentation

6.533.2.1 **virtual MessageDispatchNotification* ac-**
tivemq::commands::MessageDispatchNotification::cloneDataStructure ()
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.533.2.2 **virtual void ac-**
tivemq::commands::MessageDispatchNotification::copyDataStructure
(**const DataStructure * src**) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.533.2.3 **virtual bool activemq::commands::MessageDispatchNotification::equals**
(**const DataStructure * value**) **const** [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

- 6.533.2.4 `virtual Pointer<ConsumerId>& activemq::commands::MessageDispatchNotification::getConsumerId ()`
[virtual]
- 6.533.2.5 `virtual const Pointer<ConsumerId>& activemq::commands::MessageDispatchNotification::getConsumerId ()`
const [virtual]
- 6.533.2.6 `virtual unsigned char activemq::commands::MessageDispatchNotification::getDataStructureType ()` const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.533.2.7 `virtual long long activemq::commands::MessageDispatchNotification::getDeliverySequenceId ()` const [virtual]
- 6.533.2.8 `virtual Pointer<ActiveMQDestination>& activemq::commands::MessageDispatchNotification::getDestination ()`
[virtual]
- 6.533.2.9 `virtual const Pointer<ActiveMQDestination>& activemq::commands::MessageDispatchNotification::getDestination ()`
const [virtual]
- 6.533.2.10 `virtual Pointer<MessageId>& activemq::commands::MessageDispatchNotification::getMessageId ()`
[virtual]
- 6.533.2.11 `virtual const Pointer<MessageId>& activemq::commands::MessageDispatchNotification::getMessageId ()` const
[virtual]
- 6.533.2.12 `virtual bool activemq::commands::MessageDispatchNotification::isMessageDispatchNotification ()` const [inline, virtual]

Returns:

an answer of true to the **isMessageDispatchNotification()** (p. 2632) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 761).

- 6.533.2.13** virtual void activemq::commands::MessageDispatchNotification::setConsumerId (const Pointer< ConsumerId > & *consumerId*) [virtual]
- 6.533.2.14** virtual void activemq::commands::MessageDispatchNotification::setDeliverySequenceId (long long *deliverySequenceId*) [virtual]
- 6.533.2.15** virtual void activemq::commands::MessageDispatchNotification::setDestination (const Pointer< ActiveMQDestination > & *destination*) [virtual]
- 6.533.2.16** virtual void activemq::commands::MessageDispatchNotification::setMessageId (const Pointer< MessageId > & *messageId*) [virtual]
- 6.533.2.17** virtual std::string activemq::commands::MessageDispatchNotification::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.533.2.18** virtual Pointer<Command> activemq::commands::MessageDispatchNotification::visit (activemq::state::CommandVisitor * *visitor*) throw (exceptions::ActiveMQException) [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.533.3 Field Documentation

- 6.533.3.1 `Pointer<ConsumerId> activemq::commands::MessageDispatchNotification::consumerId`
[protected]
- 6.533.3.2 `long long activemq::commands::MessageDispatchNotification::deliverySequenceId`
[protected]
- 6.533.3.3 `Pointer<ActiveMQDestination> activemq::commands::MessageDispatchNotification::destination`
[protected]
- 6.533.3.4 `const unsigned char activemq::commands::MessageDispatchNotification::ID - MESSAGEDISPATCHNOTIFICATION = 90` [static]
- 6.533.3.5 `Pointer<MessageId> activemq::commands::MessageDispatchNotification::messageId`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/MessageDispatchNotification.h`

6.534 ac-

tivemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller

Class Reference

6.534 ~~activemq::wireformat::openwire::marshal::v6::MessageDispatchNo~~²⁶³⁷

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2635).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual ~**MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.534.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2635). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.534.2 Constructor & Destructor Documentation

6.534.2.1 `activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.534.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.534.3 Member Function Documentation

6.534.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.534.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.534.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.534 ac-
ativemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller
Class Reference **2639**
 Reimplemented from **ativemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller**
 (p. 794).

6.534.3.4 virtual void ac-
ativemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **ativemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller**
 (p. 795).

6.534.3.5 virtual int ac-
ativemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **ativemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller**
 (p. 796).

6.534.3.6 virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.534.3.7 virtual void activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/MessageDispatchNotificationMarshaller.h

6.535 ac-

tivemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller

Class Reference

6.535 — activemq::wireformat::openwire::marshal::v2::MessageDispatchNo 2641

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2639).

#include <src/main/activemq/wireformat/openwire/marshal/v2/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual ~**MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.535.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2639). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.535.2 Constructor & Destructor Documentation

6.535.2.1 `activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.535.2.2 `virtual activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.535.3 Member Function Documentation

6.535.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.535.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.535.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.535 **ac-**
tivemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller
Class Reference **2643**
 Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller**
 (p. 801).

6.535.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller**
 (p. 802).

6.535.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure *
***dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException**
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller**
 (p. 803).

6.535.3.6 virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.535.3.7 virtual void activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/MessageDispatchNotificationMarshaller.h

6.536 ac-

tivemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller

Class Reference

6.536 — activemq::wireformat::openwire::marshal::v3::MessageDispatchNo²⁶⁴⁵

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2643).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual ~**MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.536.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2643). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.536.2 Constructor & Destructor Documentation

6.536.2.1 `activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.536.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.536.3 Member Function Documentation

6.536.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.536.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.536.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.536 **ac-**
tivemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller
Class Reference **2647**
 Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller**
 (p. 766).

6.536.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller**
 (p. 767).

6.536.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller**
 (p. 768).

6.536.3.6 virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.536.3.7 virtual void activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchNotificationMarshaller.h

6.537 ac-

tivemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller

Class Reference

6.537 ~~activemq::wireformat::openwire::marshal::v4::MessageDispatchNo~~ ²⁶⁴⁹

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2647).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual ~**MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.537.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2647). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.537.2 Constructor & Destructor Documentation

6.537.2.1 `activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.537.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.537.3 Member Function Documentation

6.537.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.537.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.537.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.537 ac-
tivemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller
Class Reference **2651**
 Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller**
 (p. 773).

6.537.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller**
 (p. 774).

6.537.3.5 virtual int ac-
tivemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller**
 (p. 775).

6.537.3.6 virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.537.3.7 virtual void activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/MessageDispatchNotificationMarshaller.h

6.538 ac-

tivemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller

Class Reference

6.538 — activemq::wireformat::openwire::marshal::v1::MessageDispatchNo 2653

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2651).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual ~**MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.538.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2651). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.538.2 Constructor & Destructor Documentation

6.538.2.1 `activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.538.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.538.3 Member Function Documentation

6.538.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.538.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.538.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.538 ac-
tivemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller
Class Reference 2655
 Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller**
 (p. 780).

6.538.3.4 virtual void ac-
tivemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller**
 (p. 781).

6.538.3.5 virtual int ac-
tivemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller**
 (p. 782).

6.538.3.6 virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.538.3.7 virtual void activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchNotificationMarshaller.h

6.539 ac-

tivemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller

Class Reference

6.539 — activemq::wireformat::openwire::marshal::v5::MessageDispatchNo²⁶⁵⁷

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2655).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchNotificationMarshaller
diagram for activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller:

Public Member Functions

- **MessageDispatchNotificationMarshaller** ()
- virtual **~MessageDispatchNotificationMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.539.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **MessageDispatchNotificationMarshaller** (p.2655). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.539.2 Constructor & Destructor Documentation

6.539.2.1 `activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::MessageDispatchNotificationMarshaller()` [inline]

6.539.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::~MessageDispatchNotificationMarshaller()` [inline, virtual]

6.539.3 Member Function Documentation

6.539.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::createDataStructure()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.539.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.539.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.539 **ac-**
tivemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller
Class Reference **2659**
 Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller**
 (p. 787).

6.539.3.4 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::looseU
(OpenWireFormat * *wireFormat*, commands::DataStructure
*** *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (**
decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller**
 (p. 788).

6.539.3.5 **virtual int ac-**
tivemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::tightM
(OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*,
utils::BooleanStream * *bs*) throw (decaf::io::IOException
) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller**
 (p. 789).

6.539.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.539.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller::tightUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchNotificationMarshaller.h`

6.540 cms::MessageEnumeration Class Reference

Defines an object that enumerates a collection of Messages.

#include <src/main/cms/MessageEnumeration.h> Inheritance diagram for cms::MessageEnumeration:

Public Member Functions

- virtual `~MessageEnumeration()`
- virtual bool `hasMoreMessages()` = 0

*Returns true if there are more **Message** (p. 2534) in the Browser that can be retrieved via the **nextMessage** method.*
- virtual `cms::Message * nextMessage()` = 0 throw (cms::CMSEException)

*Returns the Next **Message** (p. 2534) in the **Queue** (p. 3148) if one is present, if no more Message's are available then an Exception is thrown.*

6.540.1 Detailed Description

Defines an object that enumerates a collection of Messages. The client calls the `hasMoreMessages` method to determine if a **Message** (p. 2534) is available. If a **Message** (p. 2534) is available the client calls the `nextMessage` method to retrieve that **Message** (p. 2534), calling `nextMessage` when a **Message** (p. 2534) is not available results in an exception.

Since:

2.1

6.540.2 Constructor & Destructor Documentation

6.540.2.1 `virtual cms::MessageEnumeration::~~MessageEnumeration()` [inline, virtual]

6.540.3 Member Function Documentation

6.540.3.1 `virtual bool cms::MessageEnumeration::hasMoreMessages()` [pure virtual]

Returns true if there are more **Message** (p. 2534) in the Browser that can be retrieved via the `nextMessage` method. If this method returns false and the `nextMessage` method is called then an Exception will be thrown.

Returns:

true if more Message's are available in the Browser.

Implemented in `activemq::core::ActiveMQQueueBrowser` (p. 489).

6.540.3.2 `virtual cms::Message* cms::MessageEnumeration::nextMessage () throw (cms::CMSException) [pure virtual]`

Returns the Next **Message** (p. 2534) in the **Queue** (p. 3148) if one is present, if no more Message's are available then an Exception is thrown. If a **Message** (p. 2534) object pointer is returned then that object becomes the property of the caller and must be deleted by the caller when finished.

Returns:

The next **Message** (p. 2534) in the **Queue** (p. 3148).

Exceptions:

CMSException (p. 1160) if no more Message's currently in the **Queue** (p. 3148).

Implemented in `activemq::core::ActiveMQQueueBrowser` (p. 489).

The documentation for this class was generated from the following file:

- `src/main/cms/MessageEnumeration.h`

6.541 cms::MessageEOFException Class Reference

This exception must be thrown when an unexpected end of stream has been reached when a **StreamMessage** (p. 3652) or **BytesMessage** (p. 1056) is being read.

#include <src/main/cms/MessageEOFException.h> Inheritance diagram for cms::MessageEOFException:

Public Member Functions

- **MessageEOFException** () throw ()
- **MessageEOFException** (const **MessageEOFException** &ex) throw ()
- **MessageEOFException** (const std::string &message, const std::exception *cause) throw ()
- **MessageEOFException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**MessageEOFException** () throw ()

6.541.1 Detailed Description

This exception must be thrown when an unexpected end of stream has been reached when a **StreamMessage** (p. 3652) or **BytesMessage** (p. 1056) is being read.

Since:

1.3

6.541.2 Constructor & Destructor Documentation

- 6.541.2.1 **cms::MessageEOFException::MessageEOFException** () throw ()
- 6.541.2.2 **cms::MessageEOFException::MessageEOFException** (const **MessageEOFException** & *ex*) throw ()
- 6.541.2.3 **cms::MessageEOFException::MessageEOFException** (const std::string & *message*, const std::exception * *cause*) throw ()
- 6.541.2.4 **cms::MessageEOFException::MessageEOFException** (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()
- 6.541.2.5 virtual **cms::MessageEOFException::~~MessageEOFException** () throw ()
[virtual]

The documentation for this class was generated from the following file:

- src/main/cms/MessageEOFException.h

6.542 cms::MessageFormatException Class Reference

This exception must be thrown when a CMS client attempts to use a data type not supported by a message or attempts to read data in a message as the wrong type.

#include <src/main/cms/MessageFormatException.h> Inheritance diagram for cms::MessageFormatException:

Public Member Functions

- **MessageFormatException** () throw ()
- **MessageFormatException** (const **MessageFormatException** &ex) throw ()
- **MessageFormatException** (const std::string &message, const std::exception *cause) throw ()
- **MessageFormatException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**MessageFormatException** () throw ()

6.542.1 Detailed Description

This exception must be thrown when a CMS client attempts to use a data type not supported by a message or attempts to read data in a message as the wrong type. It must also be thrown when equivalent type errors are made with message property values. For example, this exception must be thrown if **StreamMessage.readShort** (p. 3659) is used to read a boolean value.

Since:

1.3

6.542.2 Constructor & Destructor Documentation

- 6.542.2.1** cms::MessageFormatException::MessageFormatException () throw ()
- 6.542.2.2** cms::MessageFormatException::MessageFormatException (const MessageFormatException & ex) throw ()
- 6.542.2.3** cms::MessageFormatException::MessageFormatException (const std::string & message, const std::exception * cause) throw ()
- 6.542.2.4** cms::MessageFormatException::MessageFormatException (const std::string & message, const std::exception * cause, const std::vector< std::pair< std::string, int > > & stackTrace) throw ()
- 6.542.2.5** virtual cms::MessageFormatException::~MessageFormatException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/MessageFormatException.h

6.543 activemq::commands::MessageId Class Reference

#include <src/main/activemq/commands/MessageId.h> Inheritance diagram for activemq::commands::MessageId:

Public Types

- typedef **decaf::lang::PointerComparator**< MessageId > **COMPARATOR**

Public Member Functions

- **MessageId** ()
- **MessageId** (const **MessageId** &other)
- **MessageId** (const std::string &messageKey)
- **MessageId** (const **Pointer**< **ProducerInfo** > &producerInfo, long long **producerSequenceId**)
- **MessageId** (const **Pointer**< **ProducerId** > &producerId, long long **producerSequenceId**)
- **MessageId** (const std::string &producerId, long long **producerSequenceId**)
- virtual ~**MessageId** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **MessageId** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- void **setValue** (const std::string &key)
- void **setTextView** (const std::string &key)
- virtual const **Pointer**< **ProducerId** > & **getProducerId** () const
- virtual **Pointer**< **ProducerId** > & **getProducerId** ()
- virtual void **setProducerId** (const **Pointer**< **ProducerId** > &producerId)
- virtual long long **getProducerSequenceId** () const
- virtual void **setProducerSequenceId** (long long **producerSequenceId**)
- virtual long long **getBrokerSequenceId** () const
- virtual void **setBrokerSequenceId** (long long **brokerSequenceId**)
- virtual int **compareTo** (const **MessageId** &value) const
- virtual bool **equals** (const **MessageId** &value) const

- virtual bool **operator**== (const **MessageId** &value) const
- virtual bool **operator**< (const **MessageId** &value) const
- **MessageId** & **operator**= (const **MessageId** &other)

Static Public Attributes

- static const unsigned char **ID_MESSAGEID** = 110

Protected Attributes

- **Pointer**< **ProducerId** > **producerId**
- long long **producerSequenceId**
- long long **brokerSequenceId**

6.543.1 Member Typedef Documentation

6.543.1.1 typedef decaf::lang::PointerComparator<MessageId>
 activemq::commands::MessageId::COMPARATOR

6.543.2 Constructor & Destructor Documentation

6.543.2.1 activemq::commands::MessageId::MessageId ()

6.543.2.2 activemq::commands::MessageId::MessageId (const **MessageId** & *other*)

6.543.2.3 activemq::commands::MessageId::MessageId (const std::string &
 messageKey)

6.543.2.4 activemq::commands::MessageId::MessageId (const **Pointer**<
 ProducerInfo > & *producerInfo*, long long *producerSequenceId*)

6.543.2.5 activemq::commands::MessageId::MessageId (const **Pointer**< **ProducerId**
 > & *producerId*, long long *producerSequenceId*)

6.543.2.6 activemq::commands::MessageId::MessageId (const std::string &
 producerId, long long *producerSequenceId*)

6.543.2.7 virtual activemq::commands::MessageId::~~MessageId () [virtual]

6.543.3 Member Function Documentation

6.543.3.1 virtual **MessageId*** activemq::commands::MessageId::cloneDataStructure
 () const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.543.3.2 `virtual int activemq::commands::MessageId::compareTo (const MessageId & value) const` [virtual]

6.543.3.3 `virtual void activemq::commands::MessageId::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.543.3.4 `virtual bool activemq::commands::MessageId::equals (const MessageId & value) const` [virtual]

6.543.3.5 `virtual bool activemq::commands::MessageId::equals (const DataStructure * value) const` [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.543.3.6 `virtual long long activemq::commands::MessageId::getBrokerSequenceId () const` [virtual]

6.543.3.7 `virtual unsigned char activemq::commands::MessageId::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.543.3.8 `virtual Pointer<ProducerId>& activemq::commands::MessageId::getProducerId ()`
[virtual]
- 6.543.3.9 `virtual const Pointer<ProducerId>& activemq::commands::MessageId::getProducerId () const`
[virtual]
- 6.543.3.10 `virtual long long activemq::commands::MessageId::getProducerSequenceId ()`
`const` [virtual]
- 6.543.3.11 `virtual bool activemq::commands::MessageId::operator< (const`
`MessageId & value) const` [virtual]
- 6.543.3.12 `MessageId& activemq::commands::MessageId::operator= (const`
`MessageId & other)`
- 6.543.3.13 `virtual bool activemq::commands::MessageId::operator== (const`
`MessageId & value) const` [virtual]
- 6.543.3.14 `virtual void activemq::commands::MessageId::setBrokerSequenceId`
`(long long brokerSequenceId)` [virtual]
- 6.543.3.15 `virtual void activemq::commands::MessageId::setProducerId (const`
`Pointer< ProducerId > & producerId)` [virtual]
- 6.543.3.16 `virtual void activemq::commands::MessageId::setProducerSequenceId`
`(long long producerSequenceId)` [virtual]
- 6.543.3.17 `void activemq::commands::MessageId::setTextView (const std::string &`
`key)`
- 6.543.3.18 `void activemq::commands::MessageId::setValue (const std::string & key)`
- 6.543.3.19 `virtual std::string activemq::commands::MessageId::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p.833).

6.543.4 Field Documentation

- 6.543.4.1 `long long activemq::commands::MessageId::brokerSequenceId`
[protected]
- 6.543.4.2 `const unsigned char activemq::commands::MessageId::ID_MESSAGEID`
`= 110` [static]
- 6.543.4.3 `Pointer<ProducerId> activemq::commands::MessageId::producerId`
[protected]
- 6.543.4.4 `long long activemq::commands::MessageId::producerSequenceId`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/MessageId.h`

6.544 activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2668).

#include <src/main/activemq/wireformat/openwire/marshal/v2/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.544.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2668). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.544.2 Constructor & Destructor Documentation

6.544.2.1 `activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::MessageIdMarshaller()` [inline]

6.544.2.2 `virtual activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::~~MessageIdMarshaller()` [inline, virtual]

6.544.3 Member Function Documentation

6.544.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.544.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.544.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.544.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.544.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.544.3.6 virtual void activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.544.3.7 virtual void activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/MessageIdMarshaller.h

6.545 activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2672).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.545.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2672). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.545.2 Constructor & Destructor Documentation

6.545.2.1 `activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::MessageIdMarshaller()` [inline]

6.545.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::~~MessageIdMarshaller()` [inline, virtual]

6.545.3 Member Function Documentation

6.545.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.545.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.545.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.545.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.545.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.545.3.6 virtual void activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.545.3.7 virtual void activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/MessageIdMarshaller.h

6.546 activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2676).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.546.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2676). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.546.2 Constructor & Destructor Documentation

6.546.2.1 `activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::MessageIdMarshaller()` [inline]

6.546.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::~~MessageIdMarshaller()` [inline, virtual]

6.546.3 Member Function Documentation

6.546.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.546.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.546.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.546.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.546.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.546.3.6 virtual void activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.546.3.7 virtual void activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/MessageIdMarshaller.h

6.547 activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2680).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.547.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2680). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.547.2 Constructor & Destructor Documentation

6.547.2.1 `activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::MessageIdMarshaller()` [inline]

6.547.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::~~MessageIdMarshaller()` [inline, virtual]

6.547.3 Member Function Documentation

6.547.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.547.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.547.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.547.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.547.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.547.3.6 virtual void activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.547.3.7 virtual void activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/MessageIdMarshaller.h

6.548 activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2684).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.548.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2684). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.548.2 Constructor & Destructor Documentation

6.548.2.1 `activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::MessageIdMarshaller()` `[inline]`

6.548.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::~~MessageIdMarshaller()` `[inline, virtual]`

6.548.3 Member Function Documentation

6.548.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.548.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.548.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.548.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.548.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.548.3.6 virtual void activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.548.3.7 virtual void activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/MessageIdMarshaller.h

6.549 activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2688).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessageIdMarshaller.h> Inheritance diagram for `activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller`:

Public Member Functions

- `MessageIdMarshaller ()`
- `virtual ~MessageIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.549.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `MessageIdMarshaller` (p. 2688). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the `activemq-openwire-generator` module

6.549.2 Constructor & Destructor Documentation

6.549.2.1 `activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::MessageIdMarshaller()` [inline]

6.549.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::~~MessageIdMarshaller()` [inline, virtual]

6.549.3 Member Function Documentation

6.549.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.549.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.549.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.549.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.549.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.549.3.6 virtual void activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.549.3.7 virtual void activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/MessageIdMarshaller.h

6.550 cms::MessageListener Class Reference

A `MessageListener` (p. 2692) object is used to receive asynchronously delivered messages.

```
#include <src/main/cms/MessageListener.h>
```

Public Member Functions

- virtual `~MessageListener ()`
- virtual void `onMessage (const Message *message)=0`

*Called asynchronously when a new message is received, the message reference can be to any of the **Message** (p. 2534) types.*

6.550.1 Detailed Description

A `MessageListener` (p. 2692) object is used to receive asynchronously delivered messages.

Since:

1.0

6.550.2 Constructor & Destructor Documentation

6.550.2.1 virtual `cms::MessageListener::~~MessageListener ()` [inline, virtual]

6.550.3 Member Function Documentation

6.550.3.1 virtual void `cms::MessageListener::onMessage (const Message * message)`
[pure virtual]

Called asynchronously when a new message is received, the message reference can be to any of the **Message** (p. 2534) types. a dynamic cast is used to find out what type of message this is. The lifetime of this object is only guaranteed to be for life of the `onMessage` function after this call-back returns the message may no longer exists. Users should copy the data or clone the message if they wish to retain information that was contained in this **Message** (p. 2534).

It is considered a programming error for this method to throw an exception.

Parameters:

message **Message** (p. 2534) object {const} pointer recipient does not own.

The documentation for this class was generated from the following file:

- `src/main/cms/MessageListener.h`

6.551 activemq::wireformat::openwire::marshal::v5::MessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2693).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.551.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2693). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.551.2 Constructor & Destructor Documentation

6.551.2.1 `activemq::wireformat::openwire::marshal::v5::MessageMarshaller::MessageMarshaller()` [inline]

6.551.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.551.3 Member Function Documentation

6.551.3.1 `virtual void activemq::wireformat::openwire::marshal::v5::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller` (p. 226), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller` (p. 262), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller` (p. 387), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller` (p. 414), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller` (p. 459), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller` (p. 565), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller` (p. 680).

6.551.3.2 `virtual void activemq::wireformat::openwire::marshal::v5::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller` (p. 227), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller` (p. 263), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller` (p. 388), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller` (p. 415), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller` (p. 460), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller` (p. 566), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller` (p. 681).

```
6.551.3.3 virtual int ac-
          tivemq::wireformat::openwire::marshal::v5::MessageMarshaller::tightMarshal1
          (OpenWireFormat * wireFormat, commands::DataStructure *
          dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException
          ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller` (p. 227), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller` (p. 263), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller` (p. 388), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller` (p. 415), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller` (p. 460), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller` (p. 566), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller` (p. 681).

6.551.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::MessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller** (p. 227), **activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller** (p. 263), **activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller** (p. 388), **activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller** (p. 415), **activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller** (p. 460), **activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller** (p. 566), and **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller** (p. 681).

6.551.3.5 `virtual void activemq::wireformat::openwire::marshal::v5::MessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller` (p. 228), `activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller` (p. 264), `activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller` (p. 389), `activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller` (p. 416), `activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller` (p. 461), `activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller` (p. 567), and `activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller` (p. 682).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h`

6.552 activemq::wireformat::openwire::marshal::v3::MessageMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2698).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.552.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2698). **NOTE!**: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.552.2 Constructor & Destructor Documentation

6.552.2.1 `activemq::wireformat::openwire::marshal::v3::MessageMarshaller::MessageMarshaller()` [inline]

6.552.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.552.3 Member Function Documentation

6.552.3.1 `virtual void activemq::wireformat::openwire::marshal::v3::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 210), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 250), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 375), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 402), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 447), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 553), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 668).

6.552.3.2 `virtual void activemq::wireformat::openwire::marshal::v3::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 211), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 251), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 376), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 403), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 448), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 554), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 669).

```
6.552.3.3  virtual int ac-
            tivemq::wireformat::openwire::marshal::v3::MessageMarshaller::tightMarshal1
            (OpenWireFormat * wireFormat,  commands::DataStructure *
            dataStructure,  utils::BooleanStream * bs) throw ( decaf::io::IOException
            ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 211), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 251), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 376), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 403), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 448), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 554), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 669).

6.552.3.4 virtual void activemq::wireformat::openwire::marshal::v3::MessageMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller** (p. 211), **activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller** (p. 251), **activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller** (p. 376), **activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller** (p. 403), **activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller** (p. 448), **activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller** (p. 554), and **activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller** (p. 669).

6.552.3.5 virtual void activemq::wireformat::openwire::marshal::v3::MessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller` (p. 212), `activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller` (p. 252), `activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller` (p. 377), `activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller` (p. 404), `activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller` (p. 449), `activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller` (p. 555), and `activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller` (p. 670).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h`

6.553 activemq::wireformat::openwire::marshal::v2::MessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2703).

#include <src/main/activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.553.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2703). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.553.2 Constructor & Destructor Documentation

6.553.2.1 `activemq::wireformat::openwire::marshal::v2::MessageMarshaller::MessageMarshaller()` [inline]

6.553.2.2 `virtual activemq::wireformat::openwire::marshal::v2::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.553.3 Member Function Documentation

6.553.3.1 `virtual void activemq::wireformat::openwire::marshal::v2::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 222), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 270), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 391), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 418), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 463), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 569), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 688).

6.553.3.2 `virtual void activemq::wireformat::openwire::marshal::v2::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 223), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 271), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 392), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 419), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 464), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 570), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 689).

```
6.553.3.3 virtual int ac-
          tivemq::wireformat::openwire::marshal::v2::MessageMarshaller::tightMarshal1
          (OpenWireFormat * wireFormat, commands::DataStructure *
          dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException
          ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 223), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 271), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 392), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 419), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 464), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 570), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 689).

6.553.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::MessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller** (p. 223), **activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller** (p. 271), **activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller** (p. 392), **activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller** (p. 419), **activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller** (p. 464), **activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller** (p. 570), and **activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller** (p. 689).

6.553.3.5 `virtual void activemq::wireformat::openwire::marshal::v2::MessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller` (p. 224), `activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller` (p. 272), `activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller` (p. 393), `activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller` (p. 420), `activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller` (p. 465), `activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller` (p. 571), and `activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller` (p. 690).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h`

6.554 activemq::wireformat::openwire::marshal::v4::MessageMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2708).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.554.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2708). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.554.2 Constructor & Destructor Documentation

- 6.554.2.1 `activemq::wireformat::openwire::marshal::v4::MessageMarshaller::MessageMarshaller()` [inline]
- 6.554.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.554.3 Member Function Documentation

- 6.554.3.1 `virtual void activemq::wireformat::openwire::marshal::v4::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller` (p. 218), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller` (p. 258), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller` (p. 383), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller` (p. 410), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller` (p. 455), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller` (p. 561), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller` (p. 672).

- 6.554.3.2 `virtual void activemq::wireformat::openwire::marshal::v4::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller` (p. 219), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller` (p. 259), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller` (p. 384), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller` (p. 411), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller` (p. 456), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller` (p. 562), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller` (p. 673).

```
6.554.3.3  virtual int ac-
            tivemq::wireformat::openwire::marshal::v4::MessageMarshaller::tightMarshal1
            (OpenWireFormat * wireFormat,  commands::DataStructure *
            dataStructure,  utils::BooleanStream * bs) throw ( decaf::io::IOException
            ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller` (p. 219), `activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller` (p. 259), `activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller` (p. 384), `activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller` (p. 411), `activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller` (p. 456), `activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller` (p. 562), and `activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller` (p. 673).

6.554.3.4 virtual void activemq::wireformat::openwire::marshal::v4::MessageMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller** (p. 219), **activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller** (p. 259), **activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller** (p. 384), **activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller** (p. 411), **activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller** (p. 456), **activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller** (p. 562), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller** (p. 673).

6.554.3.5 virtual void activemq::wireformat::openwire::marshal::v4::MessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller** (p. 220), **activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller** (p. 260), **activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller** (p. 385), **activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller** (p. 412), **activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller** (p. 457), **activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller** (p. 563), and **activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller** (p. 674).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h`

6.555 activemq::wireformat::openwire::marshal::v1::MessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2713).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.555.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2713). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.555.2 Constructor & Destructor Documentation

6.555.2.1 `activemq::wireformat::openwire::marshal::v1::MessageMarshaller::MessageMarshaller()` [inline]

6.555.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.555.3 Member Function Documentation

6.555.3.1 `virtual void activemq::wireformat::openwire::marshal::v1::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 214), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 254), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 379), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 406), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 451), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 557), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 676).

6.555.3.2 `virtual void activemq::wireformat::openwire::marshal::v1::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 215), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 255), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 380), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 407), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 452), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 558), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 677).

```
6.555.3.3 virtual int ac-
          tivemq::wireformat::openwire::marshal::v1::MessageMarshaller::tightMarshal1
          (OpenWireFormat * wireFormat, commands::DataStructure *
          dataStructure, utils::BooleanStream * bs) throw ( decaf::io::IOException
          ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 215), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 255), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 380), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 407), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 452), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 558), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 677).

6.555.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::MessageMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller** (p. 215), **activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller** (p. 255), **activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller** (p. 380), **activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller** (p. 407), **activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller** (p. 452), **activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller** (p. 558), and **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller** (p. 677).

6.555.3.5 `virtual void activemq::wireformat::openwire::marshal::v1::MessageMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller` (p. 216), `activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller` (p. 256), `activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller` (p. 381), `activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller` (p. 408), `activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller` (p. 453), `activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller` (p. 559), and `activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller` (p. 678).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h`

6.556 activemq::wireformat::openwire::marshal::v6::MessageMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2718).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::MessageMarshaller:

Public Member Functions

- **MessageMarshaller** ()
- virtual **~MessageMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.556.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2718). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.556.2 Constructor & Destructor Documentation

6.556.2.1 `activemq::wireformat::openwire::marshal::v6::MessageMarshaller::MessageMarshaller()` [inline]

6.556.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessageMarshaller::~~MessageMarshaller()` [inline, virtual]

6.556.3 Member Function Documentation

6.556.3.1 `virtual void activemq::wireformat::openwire::marshal::v6::MessageMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller` (p. 230), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller` (p. 266), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller` (p. 395), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller` (p. 422), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller` (p. 467), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller` (p. 573), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller` (p. 684).

6.556.3.2 `virtual void activemq::wireformat::openwire::marshal::v6::MessageMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller` (p. 231), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller` (p. 267), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller` (p. 396), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller` (p. 423), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller` (p. 468), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller` (p. 574), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller` (p. 685).

```
6.556.3.3  virtual int ac-
            tivemq::wireformat::openwire::marshal::v6::MessageMarshaller::tightMarshal1
            (OpenWireFormat * wireFormat,  commands::DataStructure *
            dataStructure,  utils::BooleanStream * bs) throw ( decaf::io::IOException
            ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller` (p. 231), `activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller` (p. 267), `activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller` (p. 396), `activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller` (p. 423), `activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller` (p. 468), `activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller` (p. 574), and `activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller` (p. 685).

6.556.3.4 virtual void activemq::wireformat::openwire::marshal::v6::MessageMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller** (p. 231), **activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller** (p. 267), **activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller** (p. 396), **activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller** (p. 423), **activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller** (p. 468), **activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller** (p. 574), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller** (p. 685).

6.556.3.5 virtual void activemq::wireformat::openwire::marshal::v6::MessageMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller** (p. 232), **activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller** (p. 268), **activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller** (p. 397), **activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller** (p. 424), **activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller** (p. 469), **activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller** (p. 575), and **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller** (p. 686).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h`

6.557 cms::MessageNotReadableException Class Reference

This exception must be thrown when a CMS client attempts to read a write-only message.

#include <src/main/cms/MessageNotReadableException.h> Inheritance diagram for cms::MessageNotReadableException:

Public Member Functions

- **MessageNotReadableException** () throw ()
- **MessageNotReadableException** (const **MessageNotReadableException** &ex) throw ()
- **MessageNotReadableException** (const std::string &message, const std::exception *cause) throw ()
- **MessageNotReadableException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**MessageNotReadableException** () throw ()

6.557.1 Detailed Description

This exception must be thrown when a CMS client attempts to read a write-only message.

Since:

1.3

6.557.2 Constructor & Destructor Documentation

- 6.557.2.1** cms::MessageNotReadableException::MessageNotReadableException () throw ()
- 6.557.2.2** cms::MessageNotReadableException::MessageNotReadableException (const **MessageNotReadableException** & *ex*) throw ()
- 6.557.2.3** cms::MessageNotReadableException::MessageNotReadableException (const std::string & *message*, const std::exception * *cause*) throw ()
- 6.557.2.4** cms::MessageNotReadableException::MessageNotReadableException (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()
- 6.557.2.5** virtual
cms::MessageNotReadableException::~~MessageNotReadableException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/MessageNotReadableException.h

6.558 cms::MessageNotWriteableException Class Reference

This exception must be thrown when a CMS client attempts to write to a read-only message.

#include <src/main/cms/MessageNotWriteableException.h> Inheritance diagram for cms::MessageNotWriteableException:

Public Member Functions

- **MessageNotWriteableException** () throw ()
- **MessageNotWriteableException** (const **MessageNotWriteableException** &ex) throw ()
- **MessageNotWriteableException** (const std::string &message, const std::exception *cause) throw ()
- **MessageNotWriteableException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**MessageNotWriteableException** () throw ()

6.558.1 Detailed Description

This exception must be thrown when a CMS client attempts to write to a read-only message.

Since:

1.3

6.558.2 Constructor & Destructor Documentation

- 6.558.2.1** cms::MessageNotWriteableException::MessageNotWriteableException () throw ()
- 6.558.2.2** cms::MessageNotWriteableException::MessageNotWriteableException (const **MessageNotWriteableException** & *ex*) throw ()
- 6.558.2.3** cms::MessageNotWriteableException::MessageNotWriteableException (const std::string & *message*, const std::exception * *cause*) throw ()
- 6.558.2.4** cms::MessageNotWriteableException::MessageNotWriteableException (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()
- 6.558.2.5** virtual
cms::MessageNotWriteableException::~~MessageNotWriteableException () throw () [virtual]

The documentation for this class was generated from the following file:

- src/main/cms/MessageNotWriteableException.h

6.559 cms::MessageProducer Class Reference

A client uses a `MessageProducer` (p. 2725) object to send messages to a **Destination** (p. 1723).

#include <src/main/cms/MessageProducer.h> Inheritance diagram for cms::MessageProducer:

Public Member Functions

- virtual `~MessageProducer ()`
- virtual void **send** (**Message** *message)=0 throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)
Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (**Message** *message, int deliveryMode, int priority, long long timeToLive)=0 throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)
Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (const **Destination** *destination, **Message** *message)=0 throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)
Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **send** (const **Destination** *destination, **Message** *message, int deliveryMode, int priority, long long timeToLive)=0 throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)
Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.
- virtual void **setDeliveryMode** (int mode)=0 throw (CMSEException)
Sets the delivery mode for this Producer.
- virtual int **getDeliveryMode** () const =0 throw (CMSEException)
Gets the delivery mode for this Producer.
- virtual void **setDisableMessageID** (bool value)=0 throw (CMSEException)
*Sets if **Message** (p. 2534) Ids are disabled for this Producer.*
- virtual bool **getDisableMessageID** () const =0 throw (CMSEException)
*Gets if **Message** (p. 2534) Ids are disabled for this Producer.*
- virtual void **setDisableMessageTimeStamp** (bool value)=0 throw (CMSEException)
*Sets if **Message** (p. 2534) Time Stamps are disabled for this Producer.*

- virtual bool **getDisableMessageTimeStamp** () const =0 throw (CMSEException)
*Gets if **Message** (p. 2534) Time Stamps are disabled for this Producer.*
- virtual void **setPriority** (int priority)=0 throw (CMSEException)
Sets the Priority that this Producers sends messages at.
- virtual int **getPriority** () const =0 throw (CMSEException)
Gets the Priority level that this producer sends messages at.
- virtual void **setTimeToLive** (long long time)=0 throw (CMSEException)
Sets the Time to Live that this Producers sends messages with.
- virtual long long **getTimeToLive** () const =0 throw (CMSEException)
Gets the Time to Live that this producer sends messages with.

6.559.1 Detailed Description

A client uses a **MessageProducer** (p. 2725) object to send messages to a **Destination** (p. 1723). A **MessageProducer** (p. 2725) object is created by passing a **Destination** (p. 1723) object to a message-producer creation method supplied by a session.

A client also has the option of creating a message producer without supplying a destination. In this case, a **Destination** (p. 1723) must be provided with every send operation. A typical use for this kind of message producer is to send replies to requests using the request's CMSReplyTo destination.

A client can specify a default delivery mode, priority, and time to live for messages sent by a message producer. It can also specify the delivery mode, priority, and time to live for an individual message.

A client can specify a time-to-live value in milliseconds for each message it sends. This value defines a message expiration time that is the sum of the message's time-to-live and the GMT when it is sent (for transacted sends, this is the time the client sends the message, not the time the transaction is committed).

Since:

1.0

6.559.2 Constructor & Destructor Documentation

6.559.2.1 virtual cms::MessageProducer::~MessageProducer () [inline, virtual]

6.559.3 Member Function Documentation

6.559.3.1 virtual int cms::MessageProducer::getDeliveryMode () const throw (CMSEException) [pure virtual]

Gets the delivery mode for this Producer.

Returns:

The **DeliveryMode** (p. 1721)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1076), and `activemq::core::ActiveMQProducer` (p. 472).

6.559.3.2 `virtual bool cms::MessageProducer::getDisableMessageID () const throw (CMSEException) [pure virtual]`

Gets if `Message` (p. 2534) Ids are disabled for this Producer.

Returns:

boolean indicating enable / disable (true / false)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1077), and `activemq::core::ActiveMQProducer` (p. 472).

6.559.3.3 `virtual bool cms::MessageProducer::getDisableMessageTimeStamp () const throw (CMSEException) [pure virtual]`

Gets if `Message` (p. 2534) Time Stamps are disabled for this Producer.

Returns:

boolean indicating enable / disable (true / false)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1077), and `activemq::core::ActiveMQProducer` (p. 472).

6.559.3.4 `virtual int cms::MessageProducer::getPriority () const throw (CMSEException) [pure virtual]`

Gets the Priority level that this producer sends messages at.

Returns:

int based priority level

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1077), and `activemq::core::ActiveMQProducer` (p. 473).

6.559.3.5 `virtual long long cms::MessageProducer::getTimeToLive () const throw (CMSEException)` [pure virtual]

Gets the Time to Live that this producer sends messages with.

Returns:

Time to live value in milliseconds

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1078), and `activemq::core::ActiveMQProducer` (p. 473).

6.559.3.6 `virtual void cms::MessageProducer::send (const Destination * destination, Message * message, int deliveryMode, int priority, long long timeToLive) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)` [pure virtual]

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

destination The destination on which to send the message

message The message to be sent.

deliveryMode The delivery mode to be used.

priority The priority for this message.

timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs while sending the message.

MessageFormatException (p. 2662) - if an Invalid **Message** (p. 2534) is given.

InvalidDestinationException (p. 2131) - if a client uses this method with a **MessageProducer** (p. 2725) with an invalid destination.

UnsupportedOperationException (p. 3919) - if a client uses this method with a **MessageProducer** (p. 2725) that did not specify a destination at creation time.

Implemented in `activemq::cmsutil::CachedProducer` (p. 1078), and `activemq::core::ActiveMQProducer` (p. 474).

6.559.3.7 `virtual void cms::MessageProducer::send (const Destination * destination, Message * message) throw (cms::CMSEException, cms::MessageFormatException, cms::InvalidDestinationException, cms::UnsupportedOperationException)` [pure virtual]

Sends the message to the designated destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

destination The destination on which to send the message
message the message to be sent.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs while sending the message.
MessageFormatException (p. 2662) - if an Invalid **Message** (p. 2534) is given.
InvalidDestinationException (p. 2131) - if a client uses this method with a **MessageProducer** (p. 2725) with an invalid destination.
UnsupportedOperationException (p. 3919) - if a client uses this method with a **MessageProducer** (p. 2725) that did not specify a destination at creation time.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1078), and **activemq::core::ActiveMQProducer** (p. 475).

6.559.3.8 virtual void cms::MessageProducer::send (Message * *message*,
int *deliveryMode*, int *priority*, long long *timeToLive*)
throw (cms::CMSEException, cms::MessageFormatException,
cms::InvalidDestinationException, cms::UnsupportedOperationException
) [pure virtual]

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it.

Parameters:

message The message to be sent.
deliveryMode The delivery mode to be used.
priority The priority for this message.
timeToLive The time to live value for this message in milliseconds.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs while sending the message.
MessageFormatException (p. 2662) - if an Invalid **Message** (p. 2534) is given.
InvalidDestinationException (p. 2131) - if a client uses this method with a **MessageProducer** (p. 2725) with an invalid destination.
UnsupportedOperationException (p. 3919) - if a client uses this method with a **MessageProducer** (p. 2725) that did not specify a destination at creation time.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1079), and **activemq::core::ActiveMQProducer** (p. 475).

6.559.3.9 virtual void cms::MessageProducer::send (Message * *message*)
throw (cms::CMSEException, cms::MessageFormatException,
cms::InvalidDestinationException, cms::UnsupportedOperationException
) [pure virtual]

Sends the message to the default producer destination, but does not take ownership of the message, caller must still destroy it. Uses default values for deliveryMode, priority, and time to live.

Parameters:

message The message to be sent.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs while sending the message.

MessageFormatException (p. 2662) - if an Invalid **Message** (p. 2534) is given.

InvalidDestinationException (p. 2131) - if a client uses this method with a **Message-Producer** (p. 2725) with an invalid destination.

UnsupportedOperationException (p. 3919) - if a client uses this method with a **MessageProducer** (p. 2725) that did not specify a destination at creation time.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1079), and **activemq::core::ActiveMQProducer** (p. 476).

6.559.3.10 `virtual void cms::MessageProducer::setDeliveryMode (int mode) throw (CMSEException)` [pure virtual]

Sets the delivery mode for this Producer.

Parameters:

mode The **DeliveryMode** (p. 1721)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1080), and **activemq::core::ActiveMQProducer** (p. 476).

6.559.3.11 `virtual void cms::MessageProducer::setDisableMessageID (bool value) throw (CMSEException)` [pure virtual]

Sets if **Message** (p. 2534) Ids are disabled for this Producer.

Parameters:

value boolean indicating enable / disable (true / false)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1080), and **activemq::core::ActiveMQProducer** (p. 476).

6.559.3.12 `virtual void cms::MessageProducer::setDisableMessageTimeStamp (bool value) throw (CMSEException)` [pure virtual]

Sets if **Message** (p. 2534) Time Stamps are disabled for this Producer.

Parameters:

value - boolean indicating enable / disable (true / false)

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1080), and **activemq::core::ActiveMQProducer** (p. 476).

6.559.3.13 virtual void cms::MessageProducer::setPriority (int *priority*) throw (CMSEException) [pure virtual]

Sets the Priority that this Producers sends messages at.

Parameters:

priority int value for Priority level

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1081), and **activemq::core::ActiveMQProducer** (p. 477).

6.559.3.14 virtual void cms::MessageProducer::setTimeToLive (long long *time*) throw (CMSEException) [pure virtual]

Sets the Time to Live that this Producers sends messages with. This value will be used if the time to live is not specified via the send method.

Parameters:

time default time to live value in milliseconds

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::cmsutil::CachedProducer** (p. 1081), and **activemq::core::ActiveMQProducer** (p. 477).

The documentation for this class was generated from the following file:

- src/main/cms/MessageProducer.h

6.560 activemq::wireformat::openwire::utils::MessagePropertyInterceptor Class Reference

Used the base ActiveMQMessage class to intercept calls to get and set properties in order to capture the calls that use the reserved JMS properties and get and set them in the OpenWire Message properties.

```
#include <src/main/activemq/wireformat/openwire/utils/MessagePropertyInterceptor.h>
```

Public Member Functions

- **MessagePropertyInterceptor** (**commands::Message** *message, **util::PrimitiveMap** *properties) throw (**decaf::lang::exceptions::NullPointerException**)
Constructor, accepts the Message that will be used to store JMS reserved property values, and the PrimitiveMap to get and set the rest to.
- virtual **~MessagePropertyInterceptor** ()
- virtual bool **getBooleanProperty** (const std::string &name) const
Gets a boolean property.
- virtual unsigned char **getByteProperty** (const std::string &name) const
Gets a byte property.
- virtual double **getDoubleProperty** (const std::string &name) const
Gets a double property.
- virtual float **getFloatProperty** (const std::string &name) const
Gets a float property.
- virtual int **getIntProperty** (const std::string &name) const
Gets a int property.
- virtual long long **getLongProperty** (const std::string &name) const
Gets a long property.
- virtual short **getShortProperty** (const std::string &name) const
Gets a short property.
- virtual std::string **getStringProperty** (const std::string &name) const
Gets a string property.
- virtual void **setBooleanProperty** (const std::string &name, bool value)
Sets a boolean property.
- virtual void **setByteProperty** (const std::string &name, unsigned char value)
Sets a byte property.
- virtual void **setDoubleProperty** (const std::string &name, double value)
Sets a double property.

- virtual void **setFloatProperty** (const std::string &name, float value)
Sets a float property.
- virtual void **setIntProperty** (const std::string &name, int value)
Sets a int property.
- virtual void **setLongProperty** (const std::string &name, long long value)
Sets a long property.
- virtual void **setShortProperty** (const std::string &name, short value)
Sets a short property.
- virtual void **setStringProperty** (const std::string &name, const std::string &value)
Sets a string property.

6.560.1 Detailed Description

Used the base ActiveMQMessage class to intercept calls to get and set properties in order to capture the calls that use the reserved JMS properties and get and set them in the OpenWire Message properties. Currently the only properties that are intercepted and handled are:

Name		Conversion Supported	-----	JMSXDeliveryCount	
Int, Long, String		JMSXGroupID		String	
		JMSXGroupSeq		Int, Long, String	

6.560.2 Constructor & Destructor Documentation

6.560.2.1 activemq::wireformat::openwire::utils::MessagePropertyInterceptor::MessagePropertyInterceptor (commands::Message * *message*, util::PrimitiveMap * *properties*) throw (decaf::lang::exceptions::NullPointerException)

Constructor, accepts the Message that will be used to store JMS reserved property values, and the PrimitiveMap to get and set the rest to.

Parameters:

- message* - The Message to store reserved property data in
- properties* - The PrimitiveMap to store the rest of the properties in.

Exceptions:

- NullPointerException* if either param is NULL

6.560.2.2 `virtual
activemq::wireformat::openwire::utils::MessagePropertyInterceptor::~~MessagePropertyInt
() [virtual]`

6.560.3 Member Function Documentation

6.560.3.1 `virtual bool ac-
tivemq::wireformat::openwire::utils::MessagePropertyInterceptor::getBooleanProperty
(const std::string & name) const [virtual]`

Gets a boolean property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.2 `virtual unsigned char ac-
tivemq::wireformat::openwire::utils::MessagePropertyInterceptor::getBytesProperty
(const std::string & name) const [virtual]`

Gets a byte property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.3 `virtual double ac-
tivemq::wireformat::openwire::utils::MessagePropertyInterceptor::getDoubleProperty
(const std::string & name) const [virtual]`

Gets a double property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.4 `virtual float ac-
tivemq::wireformat::openwire::utils::MessagePropertyInterceptor::getFloatProperty
(const std::string & name) const [virtual]`

Gets a float property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.5 `virtual int activemq::wireformat::openwire::utils::MessagePropertyInterceptor::getIntProperty(const std::string & name) const [virtual]`

Gets a int property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.6 `virtual long long activemq::wireformat::openwire::utils::MessagePropertyInterceptor::getLongProperty(const std::string & name) const [virtual]`

Gets a long property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.7 `virtual short activemq::wireformat::openwire::utils::MessagePropertyInterceptor::getShortProperty(const std::string & name) const [virtual]`

Gets a short property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.8 `virtual std::string activemq::wireformat::openwire::utils::MessagePropertyInterceptor::getStringProperty(const std::string & name) const [virtual]`

Gets a string property.

Parameters:

name The name of the property to retrieve.

Returns:

The value for the named property.

6.560.3.9 `virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setBooleanProperty(const std::string & name, bool value) [virtual]`

Sets a boolean property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.10 `virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setByteProperty(const std::string & name, unsigned char value) [virtual]`

Sets a byte property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.11 `virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setDoubleProperty(const std::string & name, double value) [virtual]`

Sets a double property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.12 virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setFloatProperty(const std::string & *name*, float *value*) [virtual]

Sets a float property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.13 virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setIntProperty(const std::string & *name*, int *value*) [virtual]

Sets a int property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.14 virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setLongProperty(const std::string & *name*, long long *value*) [virtual]

Sets a long property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.15 virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setShortProperty(const std::string & *name*, short *value*) [virtual]

Sets a short property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

6.560.3.16 virtual void activemq::wireformat::openwire::utils::MessagePropertyInterceptor::setStringProperty(const std::string & *name*, const std::string & *value*) [virtual]

Sets a string property.

Parameters:

name The name of the property to retrieve.

value The value for the named property.

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/utils/MessagePropertyInterceptor.h`

6.561 activemq::commands::MessagePull Class Reference

#include <src/main/activemq/commands/MessagePull.h> Inheritance diagram for activemq::commands::MessagePull:

Public Member Functions

- **MessagePull** ()
- virtual **~MessagePull** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **MessagePull * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConsumerId** > & **getConsumerId** () const
- virtual **Pointer**< **ConsumerId** > & **getConsumerId** ()
- virtual void **setConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual long long **getTimeout** () const
- virtual void **setTimeout** (long long timeout)
- virtual const std::string & **getCorrelationId** () const
- virtual std::string & **getCorrelationId** ()
- virtual void **setCorrelationId** (const std::string &correlationId)
- virtual const **Pointer**< **MessageId** > & **getMessageId** () const
- virtual **Pointer**< **MessageId** > & **getMessageId** ()
- virtual void **setMessageId** (const **Pointer**< **MessageId** > &messageId)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_MESSAGEPULL** = 20

Protected Attributes

- **Pointer**< **ConsumerId** > **consumerId**
- **Pointer**< **ActiveMQDestination** > **destination**
- long long **timeout**
- std::string **correlationId**
- **Pointer**< **MessageId** > **messageId**

6.561.1 Constructor & Destructor Documentation

6.561.1.1 **activemq::commands::MessagePull::MessagePull ()**

6.561.1.2 **virtual activemq::commands::MessagePull::~~MessagePull ()** [virtual]

6.561.2 Member Function Documentation

6.561.2.1 **virtual MessagePull* activemq::commands::MessagePull::cloneDataStructure ()**
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.561.2.2 **virtual void activemq::commands::MessagePull::copyDataStructure**
(const DataStructure * src) [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.561.2.3 **virtual bool activemq::commands::MessagePull::equals (const**
DataStructure * value) **const** [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

- 6.561.2.4 virtual Pointer<ConsumerId>& activemq::commands::MessagePull::getConsumerId () [virtual]
- 6.561.2.5 virtual const Pointer<ConsumerId>& activemq::commands::MessagePull::getConsumerId () const [virtual]
- 6.561.2.6 virtual std::string& activemq::commands::MessagePull::getCorrelationId () [virtual]
- 6.561.2.7 virtual const std::string& activemq::commands::MessagePull::getCorrelationId () const [virtual]
- 6.561.2.8 virtual unsigned char activemq::commands::MessagePull::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSetructure** (p. 1660) type copy.

Implements **activemq::commands::DataSetructure** (p. 1662).

- 6.561.2.9 virtual Pointer<ActiveMQDestination>& activemq::commands::MessagePull::getDestination ()
[virtual]
- 6.561.2.10 virtual const Pointer<ActiveMQDestination>& activemq::commands::MessagePull::getDestination () const [virtual]
- 6.561.2.11 virtual Pointer<MessageId>& activemq::commands::MessagePull::getMessageId ()
[virtual]
- 6.561.2.12 virtual const Pointer<MessageId>& activemq::commands::MessagePull::getMessageId () const
[virtual]
- 6.561.2.13 virtual long long activemq::commands::MessagePull::getTimeout ()
const [virtual]
- 6.561.2.14 virtual void activemq::commands::MessagePull::setConsumerId (const
Pointer< ConsumerId > & *consumerId*) [virtual]
- 6.561.2.15 virtual void activemq::commands::MessagePull::setCorrelationId (const
std::string & *correlationId*) [virtual]
- 6.561.2.16 virtual void activemq::commands::MessagePull::setDestination (const
Pointer< ActiveMQDestination > & *destination*) [virtual]
- 6.561.2.17 virtual void activemq::commands::MessagePull::setMessageId (const
Pointer< MessageId > & *messageId*) [virtual]
- 6.561.2.18 virtual void activemq::commands::MessagePull::setTimeout (long long
timeout) [virtual]
- 6.561.2.19 virtual std::string activemq::commands::MessagePull::toString () const
[virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.561.2.20 virtual Pointer<Command> activemq::commands::MessagePull::visit
(activemq::state::CommandVisitor * *visitor*) throw (
exceptions::ActiveMQException) [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.561.3 Field Documentation

6.561.3.1 **Pointer<ConsumerId> activemq::commands::MessagePull::consumerId**
[protected]

6.561.3.2 **std::string activemq::commands::MessagePull::correlationId** [protected]

6.561.3.3 **Pointer<ActiveMQDestination> activemq::commands::MessagePull::destination** [protected]

6.561.3.4 **const unsigned char activemq::commands::MessagePull::ID _ - MESSAGEPULL = 20** [static]

6.561.3.5 **Pointer<MessageId> activemq::commands::MessagePull::messageId**
[protected]

6.561.3.6 **long long activemq::commands::MessagePull::timeout** [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/MessagePull.h`

6.562 activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2744).

#include <src/main/activemq/wireformat/openwire/marshal/v2/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.562.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2744).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.562.2 Constructor & Destructor Documentation

6.562.2.1 `activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.562.2.2 `virtual activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.562.3 Member Function Documentation

6.562.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.562.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.562.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.562.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.562.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.562.3.6 virtual void activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.562.3.7 virtual void activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/MessagePullMarshaller.h

6.563 activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2748).

#include <src/main/activemq/wireformat/openwire/marshal/v5/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.563.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2748).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.563.2 Constructor & Destructor Documentation

6.563.2.1 `activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.563.2.2 `virtual activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.563.3 Member Function Documentation

6.563.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.563.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.563.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.563.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.563.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.563.3.6 virtual void activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.563.3.7 virtual void activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/MessagePullMarshaller.h

6.564 activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2752).

#include <src/main/activemq/wireformat/openwire/marshal/v3/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.564.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2752).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.564.2 Constructor & Destructor Documentation

6.564.2.1 `activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.564.2.2 `virtual activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.564.3 Member Function Documentation

6.564.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.564.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.564.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.564.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.564.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.564.3.6 virtual void activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.564.3.7 virtual void activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/MessagePullMarshaller.h

6.565 activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2756).

#include <src/main/activemq/wireformat/openwire/marshal/v4/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.565.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2756).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.565.2 Constructor & Destructor Documentation

6.565.2.1 `activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.565.2.2 `virtual activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.565.3 Member Function Documentation

6.565.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.565.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.565.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.565.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.565.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.565.3.6 virtual void activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.565.3.7 virtual void activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/MessagePullMarshaller.h

6.566 activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2760).

#include <src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.566.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2760).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.566.2 Constructor & Destructor Documentation

6.566.2.1 `activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.566.2.2 `virtual activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.566.3 Member Function Documentation

6.566.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.566.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.566.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.566.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.566.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.566.3.6 virtual void activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.566.3.7 virtual void activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h

6.567 activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2764).

#include <src/main/activemq/wireformat/openwire/marshal/v6/MessagePullMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller:

Public Member Functions

- **MessagePullMarshaller** ()
- virtual **~MessagePullMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.567.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **MessagePullMarshaller** (p.2764).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.567.2 Constructor & Destructor Documentation

6.567.2.1 `activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::MessagePullMarshaller()` [inline]

6.567.2.2 `virtual activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::~~MessagePullMarshaller()` [inline, virtual]

6.567.3 Member Function Documentation

6.567.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.567.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.567.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.567.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.567.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.567.3.6 virtual void activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.567.3.7 virtual void activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/MessagePullMarshaller.h

6.568 activemq::transport::mock::MockTransport Class Reference

The **MockTransport** (p. 2768) defines a base level **Transport** (p. 3883) class that is intended to be used in place of an a regular protocol **Transport** (p. 3883) such as TCP.

#include <src/main/activemq/transport/mock/MockTransport.h> Inheritance diagram for activemq::transport::mock::MockTransport:

Public Member Functions

- **MockTransport** (const **Pointer**< **wireformat::WireFormat** > &wireFormat, const **Pointer**< **ResponseBuilder** > &responseBuilder)
- virtual ~**MockTransport** ()
- void **setResponseBuilder** (const **Pointer**< **ResponseBuilder** > &responseBuilder)
*Sets the **ResponseBuilder** (p. 3289) that this class uses to create Responses to Commands sent.*
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.
- virtual void **setOutgoingListener** (**TransportListener** *listener)
*Sets a Listener that gets notified for every command that would have been sent by this **transport** (p. 97) to the Broker, this allows a client to verify that its messages are making it to the wire.*
- virtual void **setWireFormat** (const **Pointer**< **wireformat::WireFormat** > &wireFormat AMQCPP_UNUSED)
Sets the WireFormat instance to use.
- **Pointer**< **wireformat::WireFormat** > **getWireFormat** () const
Gets the currently set WireFormat.
- virtual void **setTransportListener** (**TransportListener** *listener)
*Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual **TransportListener** * **getTransportListener** () const
*Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual void **fireCommand** (const **Pointer**< **Command** > &command)

*Fires a Command back through this **transport** (p. 97) to its registered CommandListener if there is one.*

- virtual void **fireException** (const exceptions::ActiveMQException &ex)
*Fires a Exception back through this **transport** (p. 97) to its registered ExceptionListener if there is one.*
- virtual void **start** () throw (decaf::io::IOException)
*Starts the **Transport** (p. 3883), the send methods of a **Transport** (p. 3883) will throw an exception if used before the **Transport** (p. 3883) is started.*
- virtual void **stop** () throw (decaf::io::IOException)
*Stops the **Transport** (p. 3883).*
- virtual void **close** () throw (decaf::io::IOException)
Closes this object and deallocates the appropriate resources.
- virtual **Transport** * **narrow** (const std::type_info &typeId)
*Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.*
- virtual bool **isFaultTolerant** () const
*Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.*
- virtual bool **isConnected** () const
*Is the **Transport** (p. 3883) Connected to its Broker.*
- virtual bool **isClosed** () const
*Has the **Transport** (p. 3883) been shutdown and no longer usable.*
- virtual std::string **getRemoteAddress** () const
- virtual void **reconnect** (const decaf::net::URI &uri AMQCPP_UNUSED) throw (decaf::io::IOException)
reconnect to another location
- bool **isFailOnSendMessage** () const
- void **setFailOnSendMessage** (bool value)
- int **getNumSentMessageBeforeFail** () const
- void **setNumSentMessageBeforeFail** (int value)
- int **getNumSentMessages** () const
- void **setNumSentMessages** (int value)
- bool **isFailOnReceiveMessage** () const
- void **setFailOnReceiveMessage** (bool value)
- int **getNumReceivedMessageBeforeFail** () const
- void **setNumReceivedMessageBeforeFail** (int value)
- int **getNumReceivedMessages** () const
- void **setNumReceivedMessages** (int value)
- bool **isFailOnKeepAliveSends** () const
- void **setFailOnKeepAliveSends** (bool value)
- int **getNumSentKeepAlivesBeforeFail** () const

- void **setNumSentKeepAlivesBeforeFail** (int value)
- int **getNumSentKeepAlives** () const
- void **setNumSentKeepAlives** (int value)
- bool **isFailOnStart** () const
- void **setFailOnStart** (bool value)
- bool **isFailOnStop** () const
- void **setFailOnStop** (bool value)
- bool **isFailOnClose** () const
- void **setFailOnClose** (bool value)

Static Public Member Functions

- static **MockTransport** * **getInstance** ()

6.568.1 Detailed Description

The **MockTransport** (p. 2768) defines a base level **Transport** (p. 3883) class that is intended to be used in place of an a regular protocol **Transport** (p. 3883) such as TCP. This **Transport** (p. 3883) assumes that it is the base **Transport** (p. 3883) in the Transports stack, and destroys any **Transports** that are passed to it in its constructor.

This **Transport** (p. 3883) defines an Interface **ResponseBuilder** (p. 3289) which must be implemented by any protocol for which the **Transport** (p. 3883) is used to Emulate. The **Transport** (p. 3883) hands off all outbound **commands** (p. 87) to the **ResponseBuilder** (p. 3289) for processing, it is up to the builder to create appropriate responses and schedule any asynchronous messages that might result from a message sent to the Broker.

6.568.2 Constructor & Destructor Documentation

- 6.568.2.1** **activemq::transport::mock::MockTransport::MockTransport** (const **Pointer**< **wireformat::WireFormat** > & *wireFormat*, const **Pointer**< **ResponseBuilder** > & *responseBuilder*)
- 6.568.2.2** **virtual activemq::transport::mock::MockTransport::~MockTransport** ()
[inline, virtual]

6.568.3 Member Function Documentation

- 6.568.3.1** **virtual void activemq::transport::mock::MockTransport::close** () **throw** (**decaf::io::IOException**) [virtual]

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

IOException if an error occurs while closing.

Implements **decaf::io::Closeable** (p. 1149).

**6.568.3.2 virtual void activemq::transport::mock::MockTransport::fireCommand
(const Pointer< Command > & *command*) [inline, virtual]**

Fires a Command back through this **transport** (p. 97) to its registered CommandListener if there is one.

Parameters:

command - Command to send to the Listener.

**6.568.3.3 virtual void activemq::transport::mock::MockTransport::fireException
(const exceptions::ActiveMQException & *ex*) [inline, virtual]**

Fires a Exception back through this **transport** (p. 97) to its registered ExceptionListener if there is one.

Parameters:

ex The Exception that will be passed on the the **Transport** (p. 3883) listener.

**6.568.3.4 static MockTransport* ac-
tivemq::transport::mock::MockTransport::getInstance ()
[inline, static]****6.568.3.5 int ac-
tivemq::transport::mock::MockTransport::getNumReceivedMessageBeforeFail
() const [inline]****6.568.3.6 int ac-
tivemq::transport::mock::MockTransport::getNumReceivedMessages ()
const [inline]****6.568.3.7 int activemq::transport::mock::MockTransport::getNumSentKeepAlives
() const [inline]****6.568.3.8 int ac-
tivemq::transport::mock::MockTransport::getNumSentKeepAlivesBeforeFail
() const [inline]****6.568.3.9 int ac-
tivemq::transport::mock::MockTransport::getNumSentMessageBeforeFail
() const [inline]****6.568.3.10 int activemq::transport::mock::MockTransport::getNumSentMessages ()
const [inline]****6.568.3.11 virtual std::string ac-
tivemq::transport::mock::MockTransport::getRemoteAddress () const
[inline, virtual]****Returns:**

the remote address for this connection

Implements **activemq::transport::Transport** (p. 3884).

6.568.3.12 `virtual TransportListener* activemq::transport::mock::MockTransport::getTransportListener () const [inline, virtual]`

Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).

Returns:

The listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3884).

6.568.3.13 `Pointer<wireformat::WireFormat> activemq::transport::mock::MockTransport::getWireFormat () const [inline]`

Gets the currently set WireFormat.

Returns:

the current WireFormat object.

6.568.3.14 `virtual bool activemq::transport::mock::MockTransport::isClosed () const [inline, virtual]`

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

Implements **activemq::transport::Transport** (p. 3885).

6.568.3.15 `virtual bool activemq::transport::mock::MockTransport::isConnected () const [inline, virtual]`

Is the **Transport** (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Implements **activemq::transport::Transport** (p. 3885).

- 6.568.3.16 `bool activemq::transport::mock::MockTransport::isFailOnClose () const [inline]`
- 6.568.3.17 `bool activemq::transport::mock::MockTransport::isFailOnKeepAliveSends () const [inline]`
- 6.568.3.18 `bool activemq::transport::mock::MockTransport::isFailOnReceiveMessage () const [inline]`
- 6.568.3.19 `bool activemq::transport::mock::MockTransport::isFailOnSendMessage () const [inline]`
- 6.568.3.20 `bool activemq::transport::mock::MockTransport::isFailOnStart () const [inline]`
- 6.568.3.21 `bool activemq::transport::mock::MockTransport::isFailOnStop () const [inline]`
- 6.568.3.22 `virtual bool activemq::transport::mock::MockTransport::isFaultTolerant () const [inline, virtual]`

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Implements **activemq::transport::Transport** (p. 3885).

- 6.568.3.23 `virtual Transport* activemq::transport::mock::MockTransport::narrow (const std::type_info & typeId) [inline, virtual]`

Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.

Parameters:

typeId - The `type_info` of the Object we are searching for.

Returns:

the requested Object. or NULL if its not in this chain.

Implements **activemq::transport::Transport** (p. 3885).

- 6.568.3.24 `virtual void activemq::transport::mock::MockTransport::oneway (const Pointer< Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3886).

6.568.3.25 virtual void activemq::transport::mock::MockTransport::reconnect
(const decaf::net::URI &uri *AMQCPP_UNUSED*) throw (
decaf::io::IOException) [inline, virtual]

reconnect to another location

Parameters:

uri

Exceptions:

IOException on failure of if not supported

6.568.3.26 virtual Pointer<Response> ac-
tivemq::transport::mock::MockTransport::request
(const Pointer< Command > & *command*, un-
signed int *timeout*) throw (decaf::io::IOException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Sends the given command to the broker and then waits for the response.

Parameters:

command - The command to be sent.

timeout - The time to wait for this response.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3886).

6.568.3.27 virtual Pointer<Response> activemq::transport::mock::MockTransport::request (const Pointer< Command > & *command*) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Sends the given command to the broker and then waits for the response.

Parameters:

command the command to be sent.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3887).

- 6.568.3.28 `void activemq::transport::mock::MockTransport::setFailOnClose (bool value) [inline]`
- 6.568.3.29 `void activemq::transport::mock::MockTransport::setFailOnKeepAliveSends (bool value) [inline]`
- 6.568.3.30 `void activemq::transport::mock::MockTransport::setFailOnReceiveMessage (bool value) [inline]`
- 6.568.3.31 `void activemq::transport::mock::MockTransport::setFailOnSendMessage (bool value) [inline]`
- 6.568.3.32 `void activemq::transport::mock::MockTransport::setFailOnStart (bool value) [inline]`
- 6.568.3.33 `void activemq::transport::mock::MockTransport::setFailOnStop (bool value) [inline]`
- 6.568.3.34 `void activemq::transport::mock::MockTransport::setNumReceivedMessageBeforeFail (int value) [inline]`
- 6.568.3.35 `void activemq::transport::mock::MockTransport::setNumReceivedMessages (int value) [inline]`
- 6.568.3.36 `void activemq::transport::mock::MockTransport::setNumSentKeepAlives (int value) [inline]`
- 6.568.3.37 `void activemq::transport::mock::MockTransport::setNumSentKeepAlivesBeforeFail (int value) [inline]`
- 6.568.3.38 `void activemq::transport::mock::MockTransport::setNumSentMessageBeforeFail (int value) [inline]`
- 6.568.3.39 `void activemq::transport::mock::MockTransport::setNumSentMessages (int value) [inline]`
- 6.568.3.40 `virtual void activemq::transport::mock::MockTransport::setOutgoingListener (TransportListener * listener) [inline, virtual]`

Sets a Listener that gets notified for every command that would have been sent by this **transport** (p. 97) to the Broker, this allows a client to verify that its messages are making it to the wire.

Parameters:

listener - The CommandListener to notify for each message

6.568.3.41 void activemq::transport::mock::MockTransport::setResponseBuilder (const Pointer< ResponseBuilder > & *responseBuilder*) [inline]

Sets the **ResponseBuilder** (p. 3289) that this class uses to create Responses to Commands sent. These are either real Response Objects, or Commands that would have been sent Asynchronously be the Broker.

Parameters:

responseBuilder - The **ResponseBuilder** (p. 3289) to use from now on.

6.568.3.42 virtual void activemq::transport::mock::MockTransport::setTransportListener (TransportListener * *listener*) [inline, virtual]

Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).

Parameters:

listener the listener of **transport** (p. 97) events.

Implements **activemq::transport::Transport** (p. 3887).

6.568.3.43 virtual void activemq::transport::mock::MockTransport::setWireFormat (const Pointer< wireformat::WireFormat > &wireFormat *AMQCPP_UNUSED*) [inline, virtual]

Sets the WireFormat instance to use.

Parameters:

wireFormat WireFormat the object used to encode / decode **commands** (p. 87).

6.568.3.44 virtual void activemq::transport::mock::MockTransport::start () throw (decaf::io::IOException) [virtual]

Starts the **Transport** (p. 3883), the send methods of a **Transport** (p. 3883) will throw an exception if used before the **Transport** (p. 3883) is started.

Exceptions:

IOException if and error occurs while starting the **Transport** (p. 3883).

Implements **activemq::transport::Transport** (p. 3888).

6.568.3.45 virtual void activemq::transport::mock::MockTransport::stop () throw (decaf::io::IOException) [virtual]

Stops the **Transport** (p. 3883).

Exceptions:

IOException if an error occurs while stopping the **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3888).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/mock/MockTransport.h`

6.569 activemq::transport::mock::MockTransportFactory Class Reference

Manufactures MockTransports, which are objects that read from input streams and write to output streams.

#include <src/main/activemq/transport/mock/MockTransportFactory.h> Inheritance diagram for activemq::transport::mock::MockTransportFactory:

Public Member Functions

- virtual `~MockTransportFactory ()`
- virtual `Pointer< Transport > create (const decaf::net::URI &location) throw (exceptions::ActiveMQException)`

*Creates a fully configured **Transport** (p. 3883) instance which could be a chain of filters and transports.*

- virtual `Pointer< Transport > createComposite (const decaf::net::URI &location) throw (exceptions::ActiveMQException)`

*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

Protected Member Functions

- virtual `Pointer< Transport > doCreateComposite (const decaf::net::URI &location, const Pointer< wireformat::WireFormat > &wireFormat, const decaf::util::Properties &properties) throw (exceptions::ActiveMQException)`

*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

6.569.1 Detailed Description

Manufactures MockTransports, which are objects that read from input streams and write to output streams.

6.569.2 Constructor & Destructor Documentation

6.569.2.1 `virtual
activemq::transport::mock::MockTransportFactory::~MockTransportFactory
() [inline, virtual]`

6.569.3 Member Function Documentation

6.569.3.1 `virtual Pointer<Transport> ac-
tivismq::transport::mock::MockTransportFactory::create (const
decaf::net::URI & location) throw (exceptions::ActiveMQException)
[virtual]`

Creates a fully configured **Transport** (p.3883) instance which could be a chain of filters and transports.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3889).

6.569.3.2 `virtual Pointer<Transport> ac-
tivismq::transport::mock::MockTransportFactory::createComposite (const
decaf::net::URI & location) throw (exceptions::ActiveMQException)
[virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3890).

6.569.3.3 `virtual Pointer<Transport> ac-
tivismq::transport::mock::MockTransportFactory::doCreateComposite
(const decaf::net::URI & location, const Pointer<
wireformat::WireFormat > & wireFormat, const decaf::util::Properties
& properties) throw (exceptions::ActiveMQException) [protected,
virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to.

wireFormat - the assigned WireFormat for the new **Transport** (p. 3883).

properties - Properties to apply to the **transport** (p. 97).

Returns:

Pointer to a new **Transport** (p. 3883) instance.

Exceptions:

ActiveMQException if an error occurs

The documentation for this class was generated from the following file:

- src/main/activemq/transport/mock/**MockTransportFactory.h**

6.570 decaf::util::concurrent::Mutex Class Reference

Mutex (p.2782) object that offers recursive support on all platforms as well as providing the ability to use the standard wait / notify pattern used in languages like Java.

#include <src/main/decaf/util/concurrent/Mutex.h> Inheritance diagram for decaf::util::concurrent::Mutex:

Public Member Functions

- **Mutex** ()
- virtual ~**Mutex** ()
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
*Attempts to **Lock** (p.2375) the object, if the lock is already held by another thread than this method returns false.*
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

6.570.1 Detailed Description

Mutex (p.2782) object that offers recursive support on all platforms as well as providing the ability to use the standard wait / notify pattern used in languages like Java.

Since:

1.0

6.570.2 Constructor & Destructor Documentation

6.570.2.1 decaf::util::concurrent::Mutex::Mutex ()

6.570.2.2 virtual decaf::util::concurrent::Mutex::~~Mutex () [virtual]

6.570.3 Member Function Documentation

6.570.3.1 virtual void decaf::util::concurrent::Mutex::lock () throw (decaf::lang::exceptions::RuntimeException) [virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements decaf::util::concurrent::Synchronizable (p.3701).

Referenced by decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::lock(), decaf::util::StlMap< std::string, cms::Topic * >::lock(), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::lock(), and decaf::util::AbstractCollection< cms::Connection * >::lock().

6.570.3.2 virtual void decaf::util::concurrent::Mutex::notify () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [virtual]

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p.3700) Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements decaf::util::concurrent::Synchronizable (p.3702).

Referenced by decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::notify(), decaf::util::StlMap< std::string, cms::Topic * >::notify(), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::notify(), and decaf::util::AbstractCollection< cms::Connection * >::notify().

6.570.3.3 `virtual void decaf::util::concurrent::Mutex::notifyAll
() throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

Referenced by `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::notifyAll()`, `decaf::util::StlMap< std::string, cms::Topic * >::notifyAll()`, `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::notifyAll()`, and `decaf::util::AbstractCollection< cms::Connection * >::notifyAll()`.

6.570.3.4 `virtual bool decaf::util::concurrent::Mutex::tryLock () throw (
decaf::lang::exceptions::RuntimeException) [virtual]`

Attempts to **Lock** (p. 2375) the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

Referenced by `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::tryLock()`, `decaf::util::StlMap< std::string, cms::Topic * >::tryLock()`, `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::tryLock()`, and `decaf::util::AbstractCollection< cms::Connection * >::tryLock()`.

6.570.3.5 `virtual void decaf::util::concurrent::Mutex::unlock () throw (
decaf::lang::exceptions::RuntimeException) [virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

Referenced by `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::unlock()`, `decaf::util::StlMap< std::string, cms::Topic * >::unlock()`, `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::unlock()`, and `decaf::util::AbstractCollection< cms::Connection * >::unlock()`.

6.570.3.6 `virtual void decaf::util::concurrent::Mutex::wait (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [virtual]`

Waits on a signal from this object, which is generated by a call to `Notify`. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or `WAIT_INFINITE`

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.570.3.7 `virtual void decaf::util::concurrent::Mutex::wait (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [virtual]`

Waits on a signal from this object, which is generated by a call to `Notify`. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or `WAIT_INFINITE`

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

6.570.3.8 **virtual void decaf::util::concurrent::Mutex::wait ()**
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

Referenced by `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::wait()`, `decaf::util::StlMap< std::string, cms::Topic * >::wait()`, `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >::wait()`, and `decaf::util::AbstractCollection< cms::Connection * >::wait()`.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Mutex.h`

6.571 decaf::util::concurrent::MutexHandle Class Reference

```
#include <src/main/decaf/internal/util/concurrent/unix/MutexHandle.h>
```

Public Member Functions

- **MutexHandle** ()
- **~MutexHandle** ()
- **MutexHandle** ()
- **~MutexHandle** ()

Data Fields

- pthread_mutex_t **mutex**
- volatile long long **lock_owner**
- volatile long long **lock_count**
- CRITICAL_SECTION **mutex**

6.571.1 Constructor & Destructor Documentation

6.571.1.1 decaf::util::concurrent::MutexHandle::MutexHandle () [inline]

6.571.1.2 decaf::util::concurrent::MutexHandle::~~MutexHandle () [inline]

6.571.1.3 decaf::util::concurrent::MutexHandle::MutexHandle () [inline]

6.571.1.4 decaf::util::concurrent::MutexHandle::~~MutexHandle () [inline]

6.571.2 Field Documentation

6.571.2.1 volatile long long decaf::util::concurrent::MutexHandle::lock_count

6.571.2.2 volatile long long decaf::util::concurrent::MutexHandle::lock_owner

6.571.2.3 CRITICAL_SECTION decaf::util::concurrent::MutexHandle::mutex

6.571.2.4 pthread_mutex_t decaf::util::concurrent::MutexHandle::mutex

The documentation for this class was generated from the following files:

- src/main/decaf/internal/util/concurrent/unix/**MutexHandle.h**
- src/main/decaf/internal/util/concurrent/windows/**MutexHandle.h**

6.572 decaf::internal::util::concurrent::MutexImpl Class Reference

```
#include <src/main/decaf/internal/util/concurrent/MutexImpl.h>
```

Static Public Member Functions

- static **decaf::util::concurrent::MutexHandle * create** ()
Creates a Reentrant Mutex and returns the handle, throws a Runtime Exception if the Mutex cannot be created for some reason.
- static void **destroy** (decaf::util::concurrent::MutexHandle *handle)
Destroy a previously create Mutex instance.
- static void **lock** (decaf::util::concurrent::MutexHandle *handle)
Locks the Mutex.
- static bool **trylock** (decaf::util::concurrent::MutexHandle *handle)
Tries to lock the Mutex.
- static void **unlock** (decaf::util::concurrent::MutexHandle *handle)
Unlocks the Mutex allowing other Thread to then acquire the Lock on it.

6.572.1 Member Function Documentation

6.572.1.1 static decaf::util::concurrent::MutexHandle* decaf::internal::util::concurrent::MutexImpl::create () [static]

Creates a Reentrant Mutex and returns the handle, throws a Runtime Exception if the Mutex cannot be created for some reason.

Returns:

handle to a newly created Mutex.

6.572.1.2 static void decaf::internal::util::concurrent::MutexImpl::destroy (decaf::util::concurrent::MutexHandle * handle) [static]

Destroy a previously create Mutex instance.

Parameters:

mutex The Mutex instance to be destroyed.

6.572.1.3 static void decaf::internal::util::concurrent::MutexImpl::lock
(decaf::util::concurrent::MutexHandle * *handle*) [static]

Locks the Mutex. If the Mutex is already locked by another thread this method blocks until the Mutex becomes unlocked and this thread acquires the lock.

Parameters:

handle the handle to the Mutex to Lock.

6.572.1.4 static bool decaf::internal::util::concurrent::MutexImpl::trylock
(decaf::util::concurrent::MutexHandle * *handle*) [static]

Tries to lock the Mutex. If the Mutex is unlocked this Thread acquires the lock on the Mutex and this method returns true, if the Mutex is already locked then the lock is not acquired and this method returns false.

Parameters:

handle the handle to the Mutex to attempt to Lock.

Returns:

true if the lock was acquired false otherwise.

6.572.1.5 static void decaf::internal::util::concurrent::MutexImpl::unlock
(decaf::util::concurrent::MutexHandle * *handle*) [static]

Unlocks the Mutex allowing other Thread to then acquire the Lock on it.

Parameters:

handle the handle to the Mutex to attempt to Lock.

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/concurrent/MutexImpl.h

6.573 decaf::internal::net::Network Class Reference

Internal class used to manage Networking related resources and hide platform dependent calls from the higher level API.

```
#include <src/main/decaf/internal/net/Network.h>
```

Public Member Functions

- virtual `~Network ()`
- `decaf::util::concurrent::Mutex * getRuntimeLock ()`
*Gets a pointer to the **Network** (p. 2790) Runtime's Lock object, this can be used by **Network** (p. 2790) layer APIs to synchronize around certain actions such as adding a resource to the **Network** (p. 2790) layer, etc.*
- void `addNetworkResource (decaf::internal::util::Resource *value)`
*Adds a Resource to the **Network** (p. 2790) Runtime, this resource will be held by the runtime until the Library shutdown method is called at which time all the Resources held by the **Network** (p. 2790) Runtime are destroyed.*
- template<typename T >
void `addAsResource (T *value)`

Static Public Member Functions

- static `Network * getNetworkRuntime ()`
*Gets the one and only instance of the **Network** (p. 2790) class, if this is called before the **Network** (p. 2790) layer has been initialized or after it has been shutdown then an *IllegalStateException* is thrown.*
- static void `initializeNetworking ()`
Initialize the Networking layer.
- static void `shutdownNetworking ()`
*Shutdown the **Network** (p. 2790) layer and free any associated resources, classes in the Decaf library that use the networking layer will now fail if used after calling the shutdown method.*

Protected Member Functions

- `Network ()`

6.573.1 Detailed Description

Internal class used to manage Networking related resources and hide platform dependent calls from the higher level API.

Since:

1.0

6.573.2 Constructor & Destructor Documentation

6.573.2.1 `decaf::internal::net::Network::Network ()` [protected]

6.573.2.2 `virtual decaf::internal::net::Network::~~Network ()` [virtual]

6.573.3 Member Function Documentation

6.573.3.1 `template<typename T > void decaf::internal::net::Network::addAsResource (T * value)`
[inline]

6.573.3.2 `void decaf::internal::net::Network::addNetworkResource (decaf::internal::util::Resource * value)`

Adds a Resource to the **Network** (p. 2790) Runtime, this resource will be held by the runtime until the Library shutdown method is called at which time all the Resources held by the **Network** (p. 2790) Runtime are destroyed.

Parameters:

value The Resource to add to the **Network** (p. 2790) Runtime.

Exceptions:

NullPointerException if the Resource value passed is null.

6.573.3.3 `static Network* decaf::internal::net::Network::getNetworkRuntime ()`
[static]

Gets the one and only instance of the **Network** (p. 2790) class, if this is called before the **Network** (p. 2790) layer has been initialized or after it has been shutdown then an *IllegalStateException* is thrown.

Returns:

pointer to the **Network** (p. 2790) runtime for the Decaf library.

6.573.3.4 `decaf::util::concurrent::Mutex* decaf::internal::net::Network::getRuntimeLock ()`

Gets a pointer to the **Network** (p. 2790) Runtime's Lock object, this can be used by **Network** (p. 2790) layer APIs to synchronize around certain actions such as adding a resource to the **Network** (p. 2790) layer, etc. The pointer returned is owned by the **Network** (p. 2790) runtime and should not be deleted or copied by the caller.

Returns:

a pointer to the **Network** (p. 2790) Runtime's single Lock instance.

6.573.3.5 `static void decaf::internal::net::Network::initializeNetworking ()` [static]

Initialize the Networking layer.

6.573.3.6 `static void decaf::internal::net::Network::shutdownNetworking ()` [static]

Shutdown the **Network** (p. 2790) layer and free any associated resources, classes in the Decaf library that use the networking layer will now fail if used after calling the shutdown method.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/Network.h`

6.574 activemq::commands::NetworkBridgeFilter Class Reference

#include <src/main/activemq/commands/NetworkBridgeFilter.h> Inheritance diagram for activemq::commands::NetworkBridgeFilter:

Public Member Functions

- **NetworkBridgeFilter** ()
- virtual **~NetworkBridgeFilter** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **NetworkBridgeFilter * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual int **getNetworkTTL** () const
- virtual void **setNetworkTTL** (int networkTTL)
- virtual const **Pointer**< **BrokerId** > & **getNetworkBrokerId** () const
- virtual **Pointer**< **BrokerId** > & **getNetworkBrokerId** ()
- virtual void **setNetworkBrokerId** (const **Pointer**< **BrokerId** > &networkBrokerId)

Static Public Attributes

- static const unsigned char **ID_NETWORKBRIDGEFILTER** = 91

Protected Attributes

- int **networkTTL**
- **Pointer**< **BrokerId** > **networkBrokerId**

6.574.1 Constructor & Destructor Documentation

6.574.1.1 `activemq::commands::NetworkBridgeFilter::NetworkBridgeFilter ()`

6.574.1.2 `virtual
activemq::commands::NetworkBridgeFilter::~~NetworkBridgeFilter ()
[virtual]`

6.574.2 Member Function Documentation

6.574.2.1 `virtual NetworkBridgeFilter* ac-
tivemq::commands::NetworkBridgeFilter::cloneDataStructure () const
[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.574.2.2 `virtual void ac-
tivemq::commands::NetworkBridgeFilter::copyDataStructure (const
DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.574.2.3 `virtual bool activemq::commands::NetworkBridgeFilter::equals (const
DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

6.574.2.4 `virtual unsigned char ac-
tivemq::commands::NetworkBridgeFilter::getDataStructureType () const
[virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.574.2.5 `virtual Pointer<BrokerId>& activemq::commands::NetworkBridgeFilter::getNetworkBrokerId ()` [virtual]
- 6.574.2.6 `virtual const Pointer<BrokerId>& activemq::commands::NetworkBridgeFilter::getNetworkBrokerId () const` [virtual]
- 6.574.2.7 `virtual int activemq::commands::NetworkBridgeFilter::getNetworkTTL () const` [virtual]
- 6.574.2.8 `virtual void activemq::commands::NetworkBridgeFilter::setNetworkBrokerId (const Pointer< BrokerId > & networkBrokerId)` [virtual]
- 6.574.2.9 `virtual void activemq::commands::NetworkBridgeFilter::setNetworkTTL (int networkTTL)` [virtual]
- 6.574.2.10 `virtual std::string activemq::commands::NetworkBridgeFilter::toString () const` [virtual]

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataSet` (p.833).

6.574.3 Field Documentation

- 6.574.3.1 `const unsigned char activemq::commands::NetworkBridgeFilter::ID _ - NETWORKBRIDGEFILTER = 91` [static]
- 6.574.3.2 `Pointer<BrokerId> activemq::commands::NetworkBridgeFilter::networkBrokerId` [protected]
- 6.574.3.3 `int activemq::commands::NetworkBridgeFilter::networkTTL` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/NetworkBridgeFilter.h`

6.575 activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2796).

#include <src/main/activemq/wireformat/openwire/marshal/v2/NetworkBridgeFilterMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.575.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2796). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.575.2 Constructor & Destructor Documentation

6.575.2.1 `activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.575.2.2 `virtual activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.575.3 Member Function Documentation

6.575.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.575.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.575.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.575.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.575.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::tightMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.575.3.6 virtual void activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.575.3.7 virtual void activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/NetworkBridgeFilterMarshaller.h

6.576 activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilter Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2800).

#include <src/main/activemq/wireformat/openwire/marshal/v6/NetworkBridgeFilterMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.576.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2800). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.576.2 Constructor & Destructor Documentation

6.576.2.1 `activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.576.2.2 `virtual activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.576.3 Member Function Documentation

6.576.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.576.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.576.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.576.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.576.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.576.3.6 virtual void activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.576.3.7 virtual void activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/NetworkBridgeFilterMarshaller.h

6.577 activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2804).

#include <src/main/activemq/wireformat/openwire/marshal/v5/NetworkBridgeFilterMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaller.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.577.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2804). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.577.2 Constructor & Destructor Documentation

6.577.2.1 `activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.577.2.2 `virtual activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.577.3 Member Function Documentation

6.577.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.577.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.577.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.577.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.577.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::tightMarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.577.3.6 virtual void activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.577.3.7 virtual void activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/NetworkBridgeFilterMarshaller.h

6.578 activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2808).

#include <src/main/activemq/wireformat/openwire/marshal/v3/NetworkBridgeFilterMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.578.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2808). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.578.2 Constructor & Destructor Documentation

6.578.2.1 `activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.578.2.2 `virtual activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.578.3 Member Function Documentation

6.578.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.578.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.578.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.578.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.578.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.578.3.6 virtual void activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.578.3.7 virtual void activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/NetworkBridgeFilterMarshaller.h

6.579 activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2812).

#include <src/main/activemq/wireformat/openwire/marshal/v4/NetworkBridgeFilterMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.579.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2812). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.579.2 Constructor & Destructor Documentation

6.579.2.1 `activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.579.2.2 `virtual activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.579.3 Member Function Documentation

6.579.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.579.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.579.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.579.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.579.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.579.3.6 virtual void activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.579.3.7 virtual void activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/NetworkBridgeFilterMarshaller.h

6.580 activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2816).

#include <src/main/activemq/wireformat/openwire/marshal/v1/NetworkBridgeFilterMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller:

Public Member Functions

- **NetworkBridgeFilterMarshaller** ()
- virtual **~NetworkBridgeFilterMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.580.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p.2816). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.580.2 Constructor & Destructor Documentation

6.580.2.1 `activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::NetworkBridgeFilterMarshaller()` [inline]

6.580.2.2 `virtual activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::~~NetworkBridgeFilterMarshaller()` [inline, virtual]

6.580.3 Member Function Documentation

6.580.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.580.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.580.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

6.580.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

6.580.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

6.580.3.6 virtual void activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.580.3.7 virtual void activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/NetworkBridgeFilterMarshaller.h

6.581 decaf::net::NoRouteToHostException Class Reference

#include <src/main/decaf/net/NoRouteToHostException.h> Inheritance diagram for decaf::net::NoRouteToHostException:

Public Member Functions

- **NoRouteToHostException** () throw ()
Default Constructor.
- **NoRouteToHostException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **NoRouteToHostException** (const **NoRouteToHostException** &ex) throw ()
Copy Constructor.
- **NoRouteToHostException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NoRouteToHostException** (const std::exception *cause) throw ()
Constructor.
- **NoRouteToHostException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NoRouteToHostException** * clone () const
Clones this exception.
- virtual ~**NoRouteToHostException** () throw ()

6.581.1 Constructor & Destructor Documentation

6.581.1.1 decaf::net::NoRouteToHostException::NoRouteToHostException () throw () [inline]

Default Constructor.

6.581.1.2 decaf::net::NoRouteToHostException::NoRouteToHostException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.581.1.3 decaf::net::NoRouteToHostException::NoRouteToHostException (const NoRouteToHostException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.581.1.4 decaf::net::NoRouteToHostException::NoRouteToHostException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.581.1.5 decaf::net::NoRouteToHostException::NoRouteToHostException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.581.1.6 decaf::net::NoRouteToHostException::NoRouteToHostException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.581.1.7 **virtual**
decaf::net::NoRouteToHostException::~~NoRouteToHostException ()
throw () [inline, virtual]

6.581.2 Member Function Documentation

6.581.2.1 **virtual NoRouteToHostException* de-**
caf::net::NoRouteToHostException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::net::SocketException** (p. 3522).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/NoRouteToHostException.h`

6.582 decaf::security::NoSuchAlgorithmException Class Reference

#include <src/main/decaf/security/NoSuchAlgorithmException.h> Inheritance diagram for decaf::security::NoSuchAlgorithmException:

Public Member Functions

- **NoSuchAlgorithmException** () throw ()
Default Constructor.
- **NoSuchAlgorithmException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **NoSuchAlgorithmException** (const **NoSuchAlgorithmException** &ex) throw ()
Copy Constructor.
- **NoSuchAlgorithmException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NoSuchAlgorithmException** (const std::exception *cause) throw ()
Constructor.
- **NoSuchAlgorithmException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NoSuchAlgorithmException** * clone () const
Clones this exception.
- virtual ~**NoSuchAlgorithmException** () throw ()

6.582.1 Constructor & Destructor Documentation

6.582.1.1 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException () throw () [inline]

Default Constructor.

6.582.1.2 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.582.1.3 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException (const NoSuchAlgorithmException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.582.1.4 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.582.1.5 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.582.1.6 decaf::security::NoSuchAlgorithmException::NoSuchAlgorithmException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.582.1.7 **virtual**
decaf::security::NoSuchAlgorithmException::~~NoSuchAlgorithmException
() throw () [inline, virtual]

6.582.2 Member Function Documentation

6.582.2.1 **virtual** **NoSuchAlgorithmException*** **de-**
caf::security::NoSuchAlgorithmException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from **decaf::security::GeneralSecurityException** (p. 1973).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/NoSuchAlgorithmException.h`

6.583 decaf::lang::exceptions::NoSuchElementException Class Reference

#include <src/main/decaf/lang/exceptions/NoSuchElementException.h> Inheritance diagram for decaf::lang::exceptions::NoSuchElementException:

Public Member Functions

- **NoSuchElementException** () throw ()
Default Constructor.
- **NoSuchElementException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **NoSuchElementException** (const **NoSuchElementException** &ex) throw ()
Copy Constructor.
- **NoSuchElementException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NoSuchElementException** (const std::exception *cause) throw ()
Constructor.
- **NoSuchElementException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NoSuchElementException** * clone () const
Clones this exception.
- virtual ~**NoSuchElementException** () throw ()

6.583.1 Constructor & Destructor Documentation

6.583.1.1 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException () throw () [inline]

Default Constructor.

6.583.1.2 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.583.1.3 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException
(const NoSuchElementException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.583.1.4 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException
(const char * *file*, const int *lineNumber*, const std::exception * *cause*,
const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.583.1.5 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException
(const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.583.1.6 decaf::lang::exceptions::NoSuchElementException::NoSuchElementException
(const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()
[inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.583.1.7 **virtual**
decaf::lang::exceptions::NoSuchElementException::~~NoSuchElementException
() throw () [inline, virtual]

6.583.2 Member Function Documentation

6.583.2.1 **virtual** **NoSuchElementException*** **de-**
caf::lang::exceptions::NoSuchElementException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/NoSuchElementException.h`

6.584 decaf::security::NoSuchProviderException Class Reference

#include <src/main/decaf/security/NoSuchProviderException.h> Inheritance diagram for decaf::security::NoSuchProviderException:

Public Member Functions

- **NoSuchProviderException** () throw ()
Default Constructor.
- **NoSuchProviderException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **NoSuchProviderException** (const **NoSuchProviderException** &ex) throw ()
Copy Constructor.
- **NoSuchProviderException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NoSuchProviderException** (const std::exception *cause) throw ()
Constructor.
- **NoSuchProviderException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NoSuchProviderException** * clone () const
Clones this exception.
- virtual ~**NoSuchProviderException** () throw ()

6.584.1 Constructor & Destructor Documentation

6.584.1.1 decaf::security::NoSuchProviderException::NoSuchProviderException () throw () [inline]

Default Constructor.

6.584.1.2 decaf::security::NoSuchProviderException::NoSuchProviderException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.584.1.3 decaf::security::NoSuchProviderException::NoSuchProviderException (const NoSuchProviderException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.584.1.4 decaf::security::NoSuchProviderException::NoSuchProviderException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.584.1.5 decaf::security::NoSuchProviderException::NoSuchProviderException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.584.1.6 decaf::security::NoSuchProviderException::NoSuchProviderException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.584.1.7 **virtual**
decaf::security::NoSuchProviderException::~~NoSuchProviderException
() throw () [inline, virtual]

6.584.2 Member Function Documentation

6.584.2.1 **virtual NoSuchProviderException* de-**
caf::security::NoSuchProviderException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from **decaf::security::GeneralSecurityException** (p. 1973).

The documentation for this class was generated from the following file:

- src/main/decaf/security/**NoSuchProviderException.h**

6.585 decaf::lang::exceptions::NullPointerException Class Reference

#include <src/main/decaf/lang/exceptions/NullPointerException.h> Inheritance diagram for decaf::lang::exceptions::NullPointerException:

Public Member Functions

- **NullPointerException** () throw ()
Default Constructor.
- **NullPointerException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **NullPointerException** (const **NullPointerException** &ex) throw ()
Copy Constructor.
- **NullPointerException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NullPointerException** (const std::exception *cause) throw ()
Constructor.
- **NullPointerException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NullPointerException** * clone () const
Clones this exception.
- virtual ~**NullPointerException** () throw ()

6.585.1 Constructor & Destructor Documentation

6.585.1.1 decaf::lang::exceptions::NullPointerException::NullPointerException () throw () [inline]

Default Constructor.

6.585.1.2 decaf::lang::exceptions::NullPointerException::NullPointerException (const Exception & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

**6.585.1.3 decaf::lang::exceptions::NullPointerException::NullPointerException
(const NullPointerException & *ex*) throw () [inline]**

Copy Constructor.

Parameters:

ex The **Exception** (p.1831) whose data is to be copied into this one.

**6.585.1.4 decaf::lang::exceptions::NullPointerException::NullPointerException
(const char * *file*, const int *lineNumber*, const std::exception * *cause*,
const char * *msg*, ...) throw () [inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

**6.585.1.5 decaf::lang::exceptions::NullPointerException::NullPointerException
(const std::exception * *cause*) throw () [inline]**

Constructor.

Parameters:

cause **Pointer** (p.2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

**6.585.1.6 decaf::lang::exceptions::NullPointerException::NullPointerException
(const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()
[inline]**

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.585.1.7 **virtual**
 decaf::lang::exceptions::NullPointerException::~~NullPointerException ()
 throw () [inline, virtual]

6.585.2 Member Function Documentation

6.585.2.1 **virtual NullPointerException* de-**
 caf::lang::exceptions::NullPointerException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**NullPointerException.h**

6.586 decaf::lang::Number Class Reference

The abstract class **Number** (p. 2835) is the superclass of classes **Byte** (p. 960), **Double** (p. 1788), **Float** (p. 1904), **Integer** (p. 2077), **Long** (p. 2420), and **Short** (p. 3440).

#include <src/main/decaf/lang/Number.h> Inheritance diagram for decaf::lang::Number:

Public Member Functions

- virtual `~Number ()`
- virtual unsigned char `byteValue () const`
Answers the byte value which the receiver represents.
- virtual double `doubleValue () const =0`
Answers the double value which the receiver represents.
- virtual float `floatValue () const =0`
Answers the float value which the receiver represents.
- virtual int `intValue () const =0`
Answers the int value which the receiver represents.
- virtual long long `longValue () const =0`
Answers the long value which the receiver represents.
- virtual short `shortValue () const`
Answers the short value which the receiver represents.

6.586.1 Detailed Description

The abstract class **Number** (p. 2835) is the superclass of classes **Byte** (p. 960), **Double** (p. 1788), **Float** (p. 1904), **Integer** (p. 2077), **Long** (p. 2420), and **Short** (p. 3440). Subclasses of **Number** (p. 2835) must provide methods to convert the represented numeric value to byte, double, float, int, long, and short.

6.586.2 Constructor & Destructor Documentation

6.586.2.1 virtual decaf::lang::Number::~~Number () [inline, virtual]

6.586.3 Member Function Documentation

6.586.3.1 virtual unsigned char decaf::lang::Number::byteValue () const [inline, virtual]

Answers the byte value which the receiver represents.

Returns:

byte the value of the receiver.

Reimplemented in `decaf::lang::Byte` (p. 962), `decaf::lang::Character` (p. 1102), `decaf::lang::Double` (p. 1790), `decaf::lang::Float` (p. 1906), `decaf::lang::Integer` (p. 2080), `decaf::lang::Long` (p. 2423), and `decaf::lang::Short` (p. 3442).

6.586.3.2 virtual double decaf::lang::Number::doubleValue () const [pure virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implemented in `decaf::lang::Byte` (p. 963), `decaf::lang::Character` (p. 1103), `decaf::lang::Double` (p. 1792), `decaf::lang::Float` (p. 1907), `decaf::lang::Integer` (p. 2081), `decaf::lang::Long` (p. 2424), `decaf::lang::Short` (p. 3443), and `decaf::util::concurrent::atomic::AtomicInteger` (p. 743).

6.586.3.3 virtual float decaf::lang::Number::floatValue () const [pure virtual]

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implemented in `decaf::lang::Byte` (p. 964), `decaf::lang::Character` (p. 1103), `decaf::lang::Double` (p. 1793), `decaf::lang::Float` (p. 1909), `decaf::lang::Integer` (p. 2082), `decaf::lang::Long` (p. 2425), `decaf::lang::Short` (p. 3444), and `decaf::util::concurrent::atomic::AtomicInteger` (p. 743).

6.586.3.4 virtual int decaf::lang::Number::intValue () const [pure virtual]

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implemented in `decaf::lang::Byte` (p. 964), `decaf::lang::Character` (p. 1104), `decaf::lang::Double` (p. 1793), `decaf::lang::Float` (p. 1909), `decaf::lang::Integer` (p. 2082), `decaf::lang::Long` (p. 2425), `decaf::lang::Short` (p. 3444), and `decaf::util::concurrent::atomic::AtomicInteger` (p. 745).

6.586.3.5 virtual long long decaf::lang::Number::longValue () const [pure virtual]

Answers the long value which the receiver represents.

Returns:

long long the value of the receiver.

Implemented in `decaf::lang::Byte` (p. 964), `decaf::lang::Character` (p. 1105), `decaf::lang::Double` (p. 1794), `decaf::lang::Float` (p. 1910), `decaf::lang::Integer` (p. 2083), `decaf::lang::Long` (p. 2426), `decaf::lang::Short` (p. 3444), and `decaf::util::concurrent::atomic::AtomicInteger` (p. 745).

6.586.3.6 virtual short decaf::lang::Number::shortValue () const [inline, virtual]

Answers the short value which the receiver represents.

Returns:

short the value of the receiver.

Reimplemented in `decaf::lang::Byte` (p. 966), `decaf::lang::Character` (p. 1106), `decaf::lang::Double` (p. 1796), `decaf::lang::Float` (p. 1912), `decaf::lang::Integer` (p. 2087), `decaf::lang::Long` (p. 2430), and `decaf::lang::Short` (p. 3446).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Number.h`

6.587 decaf::lang::exceptions::NumberFormatException

Class Reference

#include <src/main/decaf/lang/exceptions/NumberFormatException.h> Inheritance diagram for decaf::lang::exceptions::NumberFormatException:

Public Member Functions

- **NumberFormatException** ()
Default Constructor.
- **NumberFormatException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **NumberFormatException** (const **NumberFormatException** &ex) throw ()
Copy Constructor.
- **NumberFormatException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **NumberFormatException** (const std::exception *cause) throw ()
Constructor.
- **NumberFormatException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **NumberFormatException** * **clone** () const
Clones this exception.
- virtual ~**NumberFormatException** () throw ()

6.587.1 Constructor & Destructor Documentation

6.587.1.1 decaf::lang::exceptions::NumberFormatException::NumberFormatException () [inline]

Default Constructor.

Referenced by clone().

6.587.1.2 decaf::lang::exceptions::NumberFormatException::NumberFormatException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.587.1.3 decaf::lang::exceptions::NumberFormatException::NumberFormatException (const NumberFormatException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p. 1831) whose data is to be copied into this one.

6.587.1.4 decaf::lang::exceptions::NumberFormatException::NumberFormatException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

References decaf::lang::Exception::buildMessage(), and decaf::lang::Exception::setMark().

6.587.1.5 decaf::lang::exceptions::NumberFormatException::NumberFormatException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.587.1.6 decaf::lang::exceptions::NumberFormatException::NumberFormatException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

References `decaf::lang::Exception::buildMessage()`, and `decaf::lang::Exception::setMark()`.

6.587.1.7 **virtual**
`decaf::lang::exceptions::NumberFormatException::~~NumberFormatException`
`() throw ()` [inline, virtual]

6.587.2 Member Function Documentation

6.587.2.1 **virtual** `NumberFormatException*` `decaf::lang::exceptions::NumberFormatException::clone ()`
`const` [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from `decaf::lang::Exception` (p. 1834).

References `NumberFormatException()`.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/NumberFormatException.h`

6.588 cms::ObjectMessage Class Reference

Place holder for interaction with JMS systems that support Java, the C++ client is not responsible for deserializing the contained Object.

`#include <src/main/cms/ObjectMessage.h>`Inheritance diagram for cms::ObjectMessage:

Public Member Functions

- virtual `~ObjectMessage ()`

6.588.1 Detailed Description

Place holder for interaction with JMS systems that support Java, the C++ client is not responsible for deserializing the contained Object. serialized `ObjectMessage` (p. 2841)s.

Since:

1.0

6.588.2 Constructor & Destructor Documentation

6.588.2.1 virtual cms::ObjectMessage::~ObjectMessage () [inline, virtual]

The documentation for this class was generated from the following file:

- `src/main/cms/ObjectMessage.h`

6.589 decaf::internal::net::ssl::openssl::OpenSSLContextSpi Class Reference

Provides an SSLContext that wraps the OpenSSL API.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLContextSpi.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLContextSpi:

Public Member Functions

- **OpenSSLContextSpi ()**
- virtual **~OpenSSLContextSpi ()**
- virtual void **providerInit (security::SecureRandom *random)**
Perform the initialization of this Context.
Parameters:
random Pointer to an instance of a secure random number generator.
Exceptions:
NullPointerException if the SecureRandom instance is NULL.
KeyManagementException if an error occurs while initializing the context.
- virtual **decaf::net::SocketFactory * providerGetSocketFactory ()**
*Returns a **SocketFactory** (p. 3524) instance that can be used to create new **SSLSocket** (p. 3563) objects.*
*The **SocketFactory** (p. 3524) is owned by the Service Provider and should not be destroyed by the caller.*
Returns:
SocketFactory (p. 3524) instance that can be used to create new SSLSockets.
Exceptions:
IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.
- virtual **decaf::net::ServerSocketFactory * providerGetServerSocketFactory ()**
*Returns a **ServerSocketFactory** (p. 3361) instance that can be used to create new **SSLServerSocket** (p. 3554) objects.*
*The **ServerSocketFactory** (p. 3361) is owned by the Service Provider and should not be destroyed by the caller.*
Returns:
SocketFactory (p. 3524) instance that can be used to create new SSLServerSockets.
Exceptions:
IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.

Friends

- class **OpenSSLSocket**
- class **OpenSSLSocketFactory**

6.589.1 Detailed Description

Provides an SSLContext that wraps the OpenSSL API.

Since:

1.0

6.589.2 Constructor & Destructor Documentation

6.589.2.1 decaf::internal::net::ssl::openssl::OpenSSLContextSpi::OpenSSLContextSpi()
()

6.589.2.2 virtual decaf::internal::net::ssl::openssl::OpenSSLContextSpi::~~OpenSSLContextSpi()
() [virtual]

6.589.3 Member Function Documentation

6.589.3.1 virtual decaf::net::ServerSocketFactory* decaf::internal::net::ssl::openssl::OpenSSLContextSpi::providerGetServerSocketFactory()
() [virtual]

Returns a **ServerSocketFactory** (p. 3361) instance that can be used to create new **SSLServerSocket** (p. 3554) objects.

The **ServerSocketFactory** (p. 3361) is owned by the Service Provider and should not be destroyed by the caller.

Returns:

SocketFactory (p. 3524) instance that can be used to create new SSLServerSockets.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.

Implements **decaf::net::ssl::SSLContextSpi** (p. 3549).

6.589.3.2 virtual decaf::net::SocketFactory* decaf::internal::net::ssl::openssl::OpenSSLContextSpi::providerGetSocketFactory()
() [virtual]

Returns a **SocketFactory** (p. 3524) instance that can be used to create new **SSLSocket** (p. 3563) objects.

The **SocketFactory** (p. 3524) is owned by the Service Provider and should not be destroyed by the caller.

Returns:

SocketFactory (p. 3524) instance that can be used to create new SSLSockets.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.

Implements **decaf::net::ssl::SSLContextSpi** (p. 3549).

6.589.3.3 virtual void decaf::internal::net::ssl::openssl::OpenSSLContextSpi::providerInit (security::SecureRandom * *random*) [virtual]

Perform the initialization of this Context.

Parameters:

random Pointer to an instance of a secure random number generator.

Exceptions:

NullPointerException if the SecureRandom instance is NULL.

KeyManagementException if an error occurs while initializing the context.

Implements **decaf::net::ssl::SSLContextSpi** (p. 3550).

6.589.4 Friends And Related Function Documentation

6.589.4.1 friend class OpenSSLSocket [friend]

6.589.4.2 friend class OpenSSLSocketFactory [friend]

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLContextSpi.h`

6.590 decaf::internal::net::ssl::openssl::OpenSSLParameters Class Reference

Container class for parameters that are Common to OpenSSL socket classes.

```
#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLParameters.h>
```

Public Member Functions

- virtual **~OpenSSLParameters** ()
- bool **getNeedClientAuth** () const
- void **setNeedClientAuth** (bool value)
- bool **getWantClientAuth** () const
- void **setWantClientAuth** (bool value)
- bool **getUseClientMode** () const
- void **setUseClientMode** (bool value)
- std::vector< std::string > **getSupportedCipherSuites** () const
- std::vector< std::string > **getSupportedProtocols** () const
- std::vector< std::string > **getEnabledCipherSuites** () const
- void **setEnabledCipherSuites** (const std::vector< std::string > &suites)
- std::vector< std::string > **getEnabledProtocols** () const
- void **setEnabledProtocols** (const std::vector< std::string > &protocols)
- **OpenSSLParameters * clone** () const

Creates a clone of this object such that all settings are transferred to a new instance of an SSL object whose parent is the same SSL_CTX as this object's.

6.590.1 Detailed Description

Container class for parameters that are Common to OpenSSL socket classes.

Since:

1.0

6.590.2 Constructor & Destructor Documentation

- 6.590.2.1** virtual
decaf::internal::net::ssl::openssl::OpenSSLParameters::~~OpenSSLParameters
() [virtual]

6.590.3 Member Function Documentation

- 6.590.3.1** OpenSSLParameters* de-
caf::internal::net::ssl::openssl::OpenSSLParameters::clone
() const

Creates a clone of this object such that all settings are transferred to a new instance of an SSL object whose parent is the same SSL_CTX as this object's.

- 6.590.3.2 `std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLParameters::getEnabledCipherSuites () const`
- 6.590.3.3 `std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLParameters::getEnabledProtocols () const`
- 6.590.3.4 `bool decaf::internal::net::ssl::openssl::OpenSSLParameters::getNeedClientAuth () const [inline]`
- 6.590.3.5 `std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLParameters::getSupportedCipherSuites () const`
- 6.590.3.6 `std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLParameters::getSupportedProtocols () const`
- 6.590.3.7 `bool decaf::internal::net::ssl::openssl::OpenSSLParameters::getUseClientMode () const [inline]`
- 6.590.3.8 `bool decaf::internal::net::ssl::openssl::OpenSSLParameters::getWantClientAuth () const [inline]`
- 6.590.3.9 `void decaf::internal::net::ssl::openssl::OpenSSLParameters::setEnabledCipherSuites (const std::vector< std::string > & suites)`
- 6.590.3.10 `void decaf::internal::net::ssl::openssl::OpenSSLParameters::setEnabledProtocols (const std::vector< std::string > & protocols)`
- 6.590.3.11 `void decaf::internal::net::ssl::openssl::OpenSSLParameters::setNeedClientAuth (bool value) [inline]`
- 6.590.3.12 `void decaf::internal::net::ssl::openssl::OpenSSLParameters::setUseClientMode (bool value) [inline]`
- 6.590.3.13 `void decaf::internal::net::ssl::openssl::OpenSSLParameters::setWantClientAuth (bool value) [inline]`

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLParameters.h`

6.591 decaf::internal::net::ssl::openssl::OpenSSLServerSocket Class Reference

SSLServerSocket based on OpenSSL library [code](#) (p. 1183).

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocket.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLServerSocket:

Public Member Functions

- **OpenSSLServerSocket** (OpenSSLParameters *parameters)
- virtual ~**OpenSSLServerSocket** ()
- virtual std::vector< std::string > **getSupportedCipherSuites** () const
*Gets a vector containing the names of all the cipher suites that are supported by this **SSLServerSocket** (p. 3554).
Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).*
Returns:
a vector containing the names of all the supported cipher suites.
- virtual std::vector< std::string > **getSupportedProtocols** () const
*Gets a vector containing the names of all the protocols that could be enabled for this **SSLServerSocket** (p. 3554) instance.*
Returns:
a vector containing the names of all the supported protocols.
- virtual std::vector< std::string > **getEnabledCipherSuites** () const
*Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSLServerSocket** (p. 3554).*
Returns:
vector of the names of all enabled Cipher Suites.
- virtual void **setEnabledCipherSuites** (const std::vector< std::string > &suites)
*Sets the Cipher Suites that are to be enabled on the **SSLServerSocket** (p. 3554) connection.
Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.*
Parameters:
suites An Vector of names for all the Cipher Suites that are to be enabled.
Exceptions:
IllegalArgumentException if the vector is empty or one of the names is invalid.
- virtual std::vector< std::string > **getEnabledProtocols** () const
*Returns a vector containing the names of all the currently enabled Protocols for this **SSLServerSocket** (p. 3554).*
Returns:
vector of the names of all enabled Protocols.

- virtual void **setEnabledProtocols** (const std::vector< std::string > &protocols)
*Sets the Protocols that are to be enabled on the **SSLServerSocket** (p. 3554) connection. Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.*
Parameters:
protocols An Vector of names for all the Protocols that are to be enabled.
Exceptions:
IllegalArgumentException if the vector is empty or one of the names is invalid.
- virtual bool **getWantClientAuth** () const
Returns:
*true if the **Socket** (p. 3503) request client Authentication.*
- virtual void **setWantClientAuth** (bool value)
*Sets whether or not this **Socket** (p. 3503) will request Client Authentication. If set to true the **Socket** (p. 3503) (when used in server mode) will request that the client authenticate itself, if the client doesn't send authentication the socket will still allow negotiation to continue.*
Parameters:
value Whether the server socket should request client authentication.
- virtual bool **getNeedClientAuth** () const
Returns:
*true if the **Socket** (p. 3503) requires client Authentication.*
- virtual void **setNeedClientAuth** (bool value)
*Sets whether or not this **Socket** (p. 3503) will require Client Authentication. If set to true the **Socket** (p. 3503) (when used in server mode) will require that the client authenticate itself, if the client doesn't send authentication the socket will not allow negotiation to continue.*
Parameters:
value Whether the server socket should require client authentication.
- virtual **decaf::net::Socket * accept** () throw (decaf::io::IOException)
*Listens for a connection request on the bound IPAddress and Port for this **ServerSocket** (p. 3352), the caller blocks until a connection is made. If the **SO_TIMEOUT** option is set this method could throw a **SocketTimeoutException** (p. 3542) if the operation times out.*
Returns:
*a new **Socket** (p. 3503) object pointer. Never returns NULL, the returned pointer is owned by the caller and must be explicitly freed by them.*
Exceptions:
IOException if an I/O error occurs while binding the socket.
SocketException (p. 3521) if an error occurs while blocking on the accept call.
SocketTimeoutException (p. 3542) if the **SO_TIMEOUT** option was used and the accept timed out.

6.591.1 Detailed Description

SSLServerSocket based on OpenSSL library **code** (p. 1183).

Since:

1.0

6.591.2 Constructor & Destructor Documentation

6.591.2.1 decaf::internal::net::ssl::openssl::OpenSSLServerSocket::OpenSSLServerSocket (OpenSSLParameters * *parameters*)

6.591.2.2 virtual
decaf::internal::net::ssl::openssl::OpenSSLServerSocket::~~OpenSSLServerSocket
() [virtual]

6.591.3 Member Function Documentation

6.591.3.1 virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLServerSocket::accept () throw (decaf::io::IOException) [virtual]

Listens for a connection request on the bound IPAddress and Port for this **ServerSocket** (p. 3352), the caller blocks until a connection is made.

If the SO_TIMEOUT option is set this method could throw a **SocketTimeoutException** (p. 3542) if the operation times out.

Returns:

a new **Socket** (p. 3503) object pointer. Never returns NULL, the returned pointer is owned by the caller and must be explicitly freed by them.

Exceptions:

IOException if an I/O error occurs while binding the socket.

SocketException (p. 3521) if an error occurs while blocking on the accept call.

SocketTimeoutException (p. 3542) if the SO_TIMEOUT option was used and the accept timed out.

Reimplemented from **decaf::net::ServerSocket** (p. 3356).

6.591.3.2 virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getEnabledCipherSuites () const [virtual]

Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSLServerSocket** (p. 3554).

Returns:

vector of the names of all enabled Cipher Suites.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3556).

6.591.3.3 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getEnabledProtocols() const [virtual]`

Returns a vector containing the names of all the currently enabled Protocols for this **SSLServerSocket** (p. 3554).

Returns:

vector of the names of all enabled Protocols.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3557).

6.591.3.4 `virtual bool decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getNeedClientAuth() const [virtual]`

Returns:

true if the **Socket** (p. 3503) requires client Authentication.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3557).

6.591.3.5 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getSupportedCipherSuites() const [virtual]`

Gets a vector containing the names of all the cipher suites that are supported by this **SSLServerSocket** (p. 3554).

Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).

Returns:

a vector containing the names of all the supported cipher suites.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3557).

6.591.3.6 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getSupportedProtocols() const [virtual]`

Gets a vector containing the names of all the protocols that could be enabled for this **SSLServerSocket** (p. 3554) instance.

Returns:

a vector containing the names of all the supported protocols.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3557).

6.591.3.7 virtual bool decaf::internal::net::ssl::openssl::OpenSSLServerSocket::getWantClientAuth() const [virtual]

Returns:

true if the **Socket** (p. 3503) request client Authentication.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3558).

6.591.3.8 virtual void decaf::internal::net::ssl::openssl::OpenSSLServerSocket::setEnabledCipherSuites(const std::vector< std::string > & suites) [virtual]

Sets the Cipher Suites that are to be enabled on the **SSLServerSocket** (p. 3554) connection.

Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.

Parameters:

suites An Vector of names for all the Cipher Suites that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3558).

6.591.3.9 virtual void decaf::internal::net::ssl::openssl::OpenSSLServerSocket::setEnabledProtocols(const std::vector< std::string > & protocols) [virtual]

Sets the Protocols that are to be enabled on the **SSLServerSocket** (p. 3554) connection.

Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.

Parameters:

protocols An Vector of names for all the Protocols that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3558).

6.591.3.10 virtual void decaf::internal::net::ssl::openssl::OpenSSLServerSocket::setNeedClientAuth(bool value) [virtual]

Sets whether or not this **Socket** (p. 3503) will require Client Authentication.

If set to true the **Socket** (p. 3503) (when used in server mode) will require that the client authenticate itself, if the client doesn't send authentication the socket will not allow negotiation to continue.

Parameters:

value Whether the server socket should require client authentication.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3558).

6.591.3.11 **virtual void decaf::internal::net::ssl::openssl::OpenSSLServerSocket::setWantClientAuth (bool *value*)** [virtual]

Sets whether or not this **Socket** (p. 3503) will request Client Authentication.

If set to true the **Socket** (p. 3503) (when used in server mode) will request that the client authenticate itself, if the client doesn't send authentication the socket will still allow negotiation to continue.

Parameters:

value Whether the server socket should request client authentication.

Implements **decaf::net::ssl::SSLServerSocket** (p. 3559).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocket.h`

6.592 decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory Class Reference

SSLServerSocketFactory that creates Server Sockets that use OpenSSL.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory:

Public Member Functions

- **OpenSSLServerSocketFactory (OpenSSLContextSpi *parent)**
- **virtual ~OpenSSLServerSocketFactory ()**
- **virtual decaf::net::ServerSocket * createServerSocket ()**

Create a new **ServerSocket** (p. 3352) that is unbound.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

- **virtual decaf::net::ServerSocket * createServerSocket (int port)**

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

- **virtual decaf::net::ServerSocket * createServerSocket (int port, int backlog)**

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

- **virtual decaf::net::ServerSocket * createServerSocket (int port, int backlog, const decaf::net::InetAddress *address)**

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is *NULL* than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.
backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.
address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

- virtual std::vector< std::string > **getDefaultCipherSuites** ()

Returns the list of cipher suites which are enabled by default. Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

getSupportedCipherSuites() (p. 3561)

- virtual std::vector< std::string > **getSupportedCipherSuites** ()

Returns the names of the cipher suites which could be enabled for use on an SSL connection. Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

getDefaultCipherSuites() (p. 3561)

6.592.1 Detailed Description

SSLServerSocketFactory that creates Server Sockets that use OpenSSL.

Since:

1.0

6.592.2 Constructor & Destructor Documentation

6.592.2.1 decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::OpenSSLServerSocketFactory (OpenSSLContextSpi * *parent*)

6.592.2.2 virtual
decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::~~OpenSSLServerSocketFactory () [virtual]

6.592.3 Member Function Documentation

6.592.3.1 virtual decaf::net::ServerSocket* decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::createServerSocket (int *port*, int *backlog*, const decaf::net::InetAddress * *address*) [virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is NULL than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.592.3.2 virtual decaf::net::ServerSocket* decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::createServerSocket (int *port*, int *backlog*) [virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3362).

6.592.3.3 **virtual decaf::net::ServerSocket* decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::createServerSocket(int port) [virtual]**

Create a new **ServerSocket** (p. 3352) that is bound to the given port.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implements **decaf::net::ServerSocketFactory** (p. 3363).

6.592.3.4 **virtual decaf::net::ServerSocket* decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::createServerSocket() [virtual]**

Create a new **ServerSocket** (p. 3352) that is unbound.

The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Reimplemented from **decaf::net::ServerSocketFactory** (p. 3363).

6.592.3.5 **virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::getDefaultCipherSuites() [virtual]**

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

`getSupportedCipherSuites()` (p. 3561)

Implements `decaf::net::ssl::SSLServerSocketFactory` (p. 3561).

6.592.3.6 virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory::getSupportedCipherSuites() [virtual]

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

`getDefaultCipherSuites()` (p. 3561)

Implements `decaf::net::ssl::SSLServerSocketFactory` (p. 3561).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h`

6.593 decaf::internal::net::ssl::openssl::OpenSSLSocket Class Reference

Wraps a Normal Socket object and extends or overrides functions in that class to make use of the OpenSSL Socket API.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLSocket.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLSocket:

Public Member Functions

- **OpenSSLSocket** (**OpenSSLParameters** *parameters)
- **OpenSSLSocket** (**OpenSSLParameters** *parameters, const **decaf::net::InetAddress** *address, int port)
- **OpenSSLSocket** (**OpenSSLParameters** *parameters, const **decaf::net::InetAddress** *address, int port, const **decaf::net::InetAddress** *localAddress, int localPort)
- **OpenSSLSocket** (**OpenSSLParameters** *parameters, const std::string &host, int port)
- **OpenSSLSocket** (**OpenSSLParameters** *parameters, const std::string &host, int port, const **decaf::net::InetAddress** *localAddress, int localPort)
- virtual ~**OpenSSLSocket** ()
- virtual void **connect** (const std::string &host, int port, int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)

Connects to the specified destination, with a specified timeout value.

*If a connection to the remote host is not established within the specified timeout interval than an **SocketTimeoutException** (p. 3542) is thrown. A timeout value of zero is treated as an infinite timeout.*

Parameters:

host The host name or IP address of the remote host to connect to.

port The port on the remote host to connect to.

timeout The number of Milliseconds to wait before treating the connection as failed.

Exceptions:

IOException Thrown if a failure occurred in the connect.

SocketTimeoutException (p. 3542) if the timeout for connection is exceeded.

IllegalArgumentException if the timeout value is negative or the endpoint is invalid.

- virtual void **close** () throw (decaf::io::IOException)

*Closes the **Socket** (p. 3503).*

*Once closed a **Socket** (p. 3503) cannot be connected or otherwise operated upon, a new **Socket** (p. 3503) instance must be created.*

Exceptions:

IOException if an I/O error occurs while closing the **Socket** (p. 3503).

- virtual **decaf::io::InputStream** * **getInputStream** () throw (decaf::io::IOException)

*Gets the **InputStream** for this socket if its connected.*

*The pointer returned is the property of the associated **Socket** (p. 3503) and should not be deleted by the caller.*

*When the returned **InputStream** is performing a blocking operation and the underlying connection is closed or otherwise broker the read calls will normally throw an exception to indicate the failure. Closing the **InputStream** will also close the underlying **Socket** (p. 3503).*

Returns:

The InputStream for this socket.

Exceptions:

IOException if an error occurs during creation of the *InputStream*, also if the **Socket** (p. 3503) is not connected or the input has been shutdown previously.

- virtual **decaf::io::OutputStream * getOutputStream ()** throw (decaf::io::IOException)

Gets the OutputStream for this socket if it is connected.

*The pointer returned is the property of the **Socket** (p. 3503) instance and should not be deleted by the caller.*

*Closing the returned **Socket** (p. 3503) will also close the underlying **Socket** (p. 3503).*

Returns:

the OutputStream for this socket.

Exceptions:

IOException if an error occurs during the creation of this *OutputStream*, or if the **Socket** (p. 3503) is closed or the output has been shutdown previously.

- virtual void **shutdownInput ()** throw (decaf::io::IOException)

Shuts down the InputStream for this socket essentially marking it as EOF.

The stream returns EOF for any calls to read after this method has been called.

Exceptions:

IOException if an I/O error occurs while performing this operation.

- virtual void **shutdownOutput ()** throw (decaf::io::IOException)

*Shuts down the OutputStream for this socket, any data already written to the socket will be sent, any further calls to *OutputStream::write* will throw an *IOException*.*

Exceptions:

IOException if an I/O error occurs while performing this operation.

- virtual void **setOOBInline** (bool value) throw (decaf::net::SocketException)

*Sets the value of the *OOBINLINE* for this socket, by default this option is disabled.*

*If enabled the urgent data is read inline on the *Socket*'s *InputStream*, no notification is give.*

Returns:

*true if *OOBINLINE* is enabled, false otherwise.*

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

- virtual void **sendUrgentData** (int data) throw (decaf::io::IOException)

*Sends on byte of urgent data to the **Socket** (p. 3503).*

Parameters:

data *The value to write as urgent data, only the lower eight bits are sent.*

Exceptions:

IOException if an I/O error occurs while performing this operation.

- virtual std::vector< std::string > **getSupportedCipherSuites ()** const

*Gets a vector containing the names of all the cipher suites that are supported by this **SSLSocket** (p. 3563).*

*Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).*

Returns:

a vector containing the names of all the supported cipher suites.

- virtual std::vector< std::string > **getSupportedProtocols** () const

*Gets a vector containing the names of all the protocols that could be enabled for this **SSL**Socket (p. 3563) instance.*

Returns:

a vector containing the names of all the supported protocols.

- virtual std::vector< std::string > **getEnabledCipherSuites** () const

*Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSL**Socket (p. 3503).*

Returns:

vector of the names of all enabled Cipher Suites.

- virtual void **setEnabledCipherSuites** (const std::vector< std::string > &suites)

*Sets the Cipher Suites that are to be enabled on the **SSL**Socket (p. 3503) connection. Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.*

Parameters:

***suites** An Vector of names for all the Cipher Suites that are to be enabled.*

Exceptions:

***IllegalArgumentException** if the vector is empty or one of the names is invalid.*

- virtual std::vector< std::string > **getEnabledProtocols** () const

*Returns a vector containing the names of all the currently enabled Protocols for this **SSL**Socket (p. 3503).*

Returns:

vector of the names of all enabled Protocols.

- virtual void **setEnabledProtocols** (const std::vector< std::string > &protocols)

*Sets the Protocols that are to be enabled on the **SSL**Socket (p. 3503) connection. Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.*

Parameters:

***protocols** An Vector of names for all the Protocols that are to be enabled.*

Exceptions:

***IllegalArgumentException** if the vector is empty or one of the names is invalid.*

- virtual void **startHandshake** ()

*Initiates a handshake for this **SSL** Connection, this can be necessary for several reasons such as using new encryption keys, or starting a new session.*

*When called for the first time after the socket connects this method blocks until the handshake is completed. The provider is not require to support multiple handshakes and can throw an **IOException** to indicate an error.*

Exceptions:

***IOException** if an I/O error occurs while performing the Handshake*

- virtual void **setUseClientMode** (bool value)

Determines the mode that the socket uses when a handshake is initiated, client or server.

*This method must be called prior to any handshake attempts on this **Socket** (p. 3503), once a handshake has been initiated this socket remains in the set mode; client or server, for the life of this object.*

Parameters:

value The mode setting, true for client or false for server.

Exceptions:

***IllegalArgumentException** if the handshake process has begun and mode is locked.*

- virtual bool **getUseClientMode** () const

*Gets whether this **Socket** (p. 3503) is in Client or Server mode, true indicates that the mode is set to Client.*

Returns:

*true if the **Socket** (p. 3503) is in Client mode, false otherwise.*

- virtual void **setNeedClientAuth** (bool value)

*Sets the **Socket** (p. 3503) to require that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.*

This option only applies to sockets in the Server mode.

*If the option is enabled and the client does not provide a certificate then the handshake is considered failed and the connection is refused. Calling this method resets any previous value for this option as well as clears any value set in the **setWantClientAuth** method.*

Parameters:

value The value indicating if a client is required to authenticate itself or not.

- virtual bool **getNeedClientAuth** () const

Returns if this socket is configured to require client authentication, true means that it has and that clients that failed to authenticate will be rejected.

This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

- virtual void **setWantClientAuth** (bool value)

*Sets the **Socket** (p. 3503) to request that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.*

This option only applies to sockets in the Server mode.

*If the option is enabled and the client does not provide a certificate then the handshake is considered to have succeeded, if it does send a certificate and that certificate is invalid the handshake will fail. Calling this method resets any previous value for this option as well as clears any value set in the **setNeedClientAuth** method.*

Parameters:

value The value indicating if a client is requested to authenticate itself or not.

- virtual bool **getWantClientAuth** () const

Returns if this socket is configured to request client authentication, true means that it has and that clients that failed to authenticate will be rejected but that clients that do not send a certificate are not considered to have failed authentication.

This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

- int **read** (unsigned char *buffer, int size, int offset, int length)
Reads the requested data from the Socket and write it into the passed in buffer.
- void **write** (const unsigned char *buffer, int size, int offset, int length)
Writes the specified data in the passed in buffer to the Socket.
- int **available** ()
Gets the number of bytes in the Socket buffer that can be read without blocking.

6.593.1 Detailed Description

Wraps a Normal Socket object and extends or overrides functions in that class to make use of the OpenSSL Socket API.

Since:

1.0

6.593.2 Constructor & Destructor Documentation

- 6.593.2.1** `decaf::internal::net::ssl::openssl::OpenSSLSocket::OpenSSLSocket (OpenSSLParameters * parameters)`
- 6.593.2.2** `decaf::internal::net::ssl::openssl::OpenSSLSocket::OpenSSLSocket (OpenSSLParameters * parameters, const decaf::net::InetAddress * address, int port)`
- 6.593.2.3** `decaf::internal::net::ssl::openssl::OpenSSLSocket::OpenSSLSocket (OpenSSLParameters * parameters, const decaf::net::InetAddress * address, int port, const decaf::net::InetAddress * localAddress, int localPort)`
- 6.593.2.4** `decaf::internal::net::ssl::openssl::OpenSSLSocket::OpenSSLSocket (OpenSSLParameters * parameters, const std::string & host, int port)`
- 6.593.2.5** `decaf::internal::net::ssl::openssl::OpenSSLSocket::OpenSSLSocket (OpenSSLParameters * parameters, const std::string & host, int port, const decaf::net::InetAddress * localAddress, int localPort)`
- 6.593.2.6** `virtual decaf::internal::net::ssl::openssl::OpenSSLSocket::~~OpenSSLSocket () [virtual]`

6.593.3 Member Function Documentation

- 6.593.3.1** `int decaf::internal::net::ssl::openssl::OpenSSLSocket::available ()`

Gets the number of bytes in the Socket buffer that can be read without blocking.

Returns:

the number of bytes that can be read from the Socket without blocking.

Exceptions:

IOException if an I/O error occurs while performing this operation.

6.593.3.2 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::close ()
throw (decaf::io::IOException) [virtual]`

Closes the **Socket** (p. 3503).

Once closed a **Socket** (p. 3503) cannot be connected or otherwise operated upon, a new **Socket** (p. 3503) instance must be created.

Exceptions:

IOException if an I/O error occurs while closing the **Socket** (p. 3503).

Reimplemented from **decaf::net::Socket** (p. 3509).

6.593.3.3 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::connect
(const std::string & host, int port, int timeout) throw (
decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException
) [virtual]`

Connects to the specified destination, with a specified timeout value.

If a connection to the remote host is not established within the specified timeout interval than an **SocketTimeoutException** (p. 3542) is thrown. A timeout value of zero is treated as an infinite timeout.

Parameters:

host The host name or IP address of the remote host to connect to.

port The port on the remote host to connect to.

timeout The number of Milliseconds to wait before treating the connection as failed.

Exceptions:

IOException Thrown if a failure occurred in the connect.

SocketTimeoutException (p. 3542) if the timeout for connection is exceeded.

IllegalArgumentException if the timeout value is negative or the endpoint is invalid.

Reimplemented from **decaf::net::Socket** (p. 3509).

6.593.3.4 `virtual std::vector<std::string> de-
caf::internal::net::ssl::openssl::OpenSSLSocket::getEnabledCipherSuites ()
const [virtual]`

Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSL Socket** (p. 3503).

Returns:

vector of the names of all enabled Cipher Suites.

Implements **decaf::net::ssl::SSLSocket** (p. 3566).

6.593.3.5 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLSocket::getEnabledProtocols () const [virtual]`

Returns a vector containing the names of all the currently enabled Protocols for this SSL **Socket** (p. 3503).

Returns:

vector of the names of all enabled Protocols.

Implements **decaf::net::ssl::SSLSocket** (p. 3566).

6.593.3.6 `virtual decaf::io::InputStream* decaf::internal::net::ssl::openssl::OpenSSLSocket::getInputStream () throw (decaf::io::IOException) [virtual]`

Gets the InputStream for this socket if its connected.

The pointer returned is the property of the associated **Socket** (p. 3503) and should not be deleted by the caller.

When the returned InputStream is performing a blocking operation and the underlying connection is closed or otherwise broker the read calls will normally throw an exception to indicate the failure.

Closing the InputStream will also close the underlying **Socket** (p. 3503).

Returns:

The InputStream for this socket.

Exceptions:

IOException if an error occurs during creation of the InputStream, also if the **Socket** (p. 3503) is not connected or the input has been shutdown previously.

Reimplemented from **decaf::net::Socket** (p. 3510).

6.593.3.7 `virtual bool decaf::internal::net::ssl::openssl::OpenSSLSocket::getNeedClientAuth () const [virtual]`

Returns if this socket is configured to require client authentication, true means that it has and that clients that failed to authenticate will be rejected.

This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

Implements **decaf::net::ssl::SSLSocket** (p. 3567).

6.593.3.8 `virtual decaf::io::OutputStream* decaf::internal::net::ssl::openssl::OpenSSLSocket::getOutputStream () throw (decaf::io::IOException) [virtual]`

Gets the OutputStream for this socket if it is connected.

The pointer returned is the property of the **Socket** (p. 3503) instance and should not be deleted by the caller.

Closing the returned **Socket** (p. 3503) will also close the underlying **Socket** (p. 3503).

Returns:

the OutputStream for this socket.

Exceptions:

IOException if an error occurs during the creation of this OutputStream, or if the **Socket** (p. 3503) is closed or the output has been shutdown previously.

Reimplemented from **decaf::net::Socket** (p. 3511).

6.593.3.9 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLSocket::getSupportedCipherSuites () const [virtual]`

Gets a vector containing the names of all the cipher suites that are supported by this **SSLSocket** (p. 3563).

Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).

Returns:

a vector containing the names of all the supported cipher suites.

Implements **decaf::net::ssl::SSLSocket** (p. 3567).

6.593.3.10 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLSocket::getSupportedProtocols () const [virtual]`

Gets a vector containing the names of all the protocols that could be enabled for this **SSLSocket** (p. 3563) instance.

Returns:

a vector containing the names of all the supported protocols.

Implements **decaf::net::ssl::SSLSocket** (p. 3567).

6.593.3.11 `virtual bool decaf::internal::net::ssl::openssl::OpenSSLSocket::getUseClientMode () const [virtual]`

Gets whether this **Socket** (p. 3503) is in Client or Server mode, true indicates that the mode is set to Client.

Returns:

true if the **Socket** (p. 3503) is in Client mode, false otherwise.

Implements **decaf::net::ssl::SSLSocket** (p. 3568).

6.593.3.12 **virtual bool decaf::internal::net::ssl::openssl::OpenSSLSocket::getWantClientAuth ()**
const [virtual]

Returns if this socket is configured to request client authentication, true means that it has and that clients that failed to authenticate will be rejected but that clients that do not send a certificate are not considered to have failed authentication.

This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

Implements **decaf::net::ssl::SSLSocket** (p. 3568).

6.593.3.13 **int decaf::internal::net::ssl::openssl::OpenSSLSocket::read (unsigned char * *buffer*, int *size*, int *offset*, int *length*)**

Reads the requested data from the Socket and write it into the passed in buffer.

Parameters:

buffer The buffer to read into
size The size of the specified buffer
offset The offset into the buffer where reading should start filling.
length The number of bytes past offset to fill with data.

Returns:

the actual number of bytes read or -1 if at EOF.

Exceptions:

IOException if an I/O error occurs during the read.
NullPointerException if buffer is Null.
IndexOutOfBoundsException if offset + length is greater than buffer size.

6.593.3.14 **virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::sendUrgentData (int *data*)** throw (**decaf::io::IOException**) [virtual]

Sends one byte of urgent data to the **Socket** (p. 3503).

Parameters:

data The value to write as urgent data, only the lower eight bits are sent.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented from **decaf::net::Socket** (p. 3514).

6.593.3.15 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setEnabledCipherSuites (const std::vector< std::string > & suites) [virtual]`

Sets the Cipher Suites that are to be enabled on the SSL **Socket** (p. 3503) connection.

Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.

Parameters:

suites An Vector of names for all the Cipher Suites that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implements **decaf::net::ssl::SSLSocket** (p. 3568).

6.593.3.16 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setEnabledProtocols (const std::vector< std::string > & protocols) [virtual]`

Sets the Protocols that are to be enabled on the SSL **Socket** (p. 3503) connection.

Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.

Parameters:

protocols An Vector of names for all the Protocols that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implements **decaf::net::ssl::SSLSocket** (p. 3568).

6.593.3.17 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setNeedClientAuth (bool value) [virtual]`

Sets the **Socket** (p. 3503) to require that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.

This option only applies to sockets in the Server mode.

If the option is enabled an the client does not provide a certificate then the handshake is considered failed and the connection is refused. Calling this method resets any previous value for this option as well as clears any value set in the `setWantClientAuth` method.

Parameters:

value The value indicating if a client is required to authenticate itself or not.

Implements **decaf::net::ssl::SSLSocket** (p. 3569).

6.593.3.18 **virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setOOBInline (bool *value*) throw (decaf::net::SocketException)** [virtual]

Sets the value of the OOBINLINE for this socket, by default this option is disabled.

If enabled the urgent data is read inline on the Socket's InputStream, no notification is give.

Returns:

true if OOBINLINE is enabled, false otherwise.

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

Reimplemented from **decaf::net::Socket** (p. 3515).

6.593.3.19 **virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setUseClientMode (bool *value*)** [virtual]

Determines the mode that the socket uses when a handshake is initiated, client or server.

This method must be called prior to any handshake attempts on this **Socket** (p. 3503), once a handshake has be initiated this socket remains the the set mode; client or server, for the life of this object.

Parameters:

value The mode setting, true for client or false for server.

Exceptions:

IllegalArgumentException if the handshake process has begun and mode is locked.

Implements **decaf::net::ssl::SSLSocket** (p. 3569).

6.593.3.20 **virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::setWantClientAuth (bool *value*)** [virtual]

Sets the **Socket** (p. 3503) to request that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.

This option only applies to sockets in the Server mode.

If the option is enabled an the client does not provide a certificate then the handshake is considered to have succeeded, if it does send a certificate and that certificate is invalid the the handshake will fail. Calling this method resets any previous value for this option as well as clears any value set in the setNeedClientAuth method.

Parameters:

value The value indicating if a client is requested to authenticate itself or not.

Implements **decaf::net::ssl::SSLSocket** (p. 3570).

6.593.3.21 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::shutdownInput () throw (decaf::io::IOException) [virtual]`

Shuts down the InputStream for this socket essentially marking it as EOF.

The stream returns EOF for any calls to read after this method has been called.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented from **decaf::net::Socket** (p. 3517).

6.593.3.22 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::shutdownOutput () throw (decaf::io::IOException) [virtual]`

Shuts down the OutputStream for this socket, any data already written to the socket will be sent, any further calls to OutputStream::write will throw an IOException.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented from **decaf::net::Socket** (p. 3518).

6.593.3.23 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocket::startHandshake () [virtual]`

Initiates a handshake for this SSL Connection, this can be necessary for several reasons such as using new encryption keys, or starting a new session.

When called for the first time after the socket connects this method blocks until the handshake is completed. The provider is not required to support multiple handshakes and can throw an IOException to indicate an error.

Exceptions:

IOException if an I/O error occurs while performing the Handshake

Implements **decaf::net::ssl::SSLSocket** (p. 3570).

6.593.3.24 `void decaf::internal::net::ssl::openssl::OpenSSLSocket::write (const unsigned char * buffer, int size, int offset, int length)`

Writes the specified data in the passed in buffer to the Socket.

Parameters:

- buffer* The buffer to write to the socket.
- size* The size of the specified buffer.
- offset* The offset into the buffer where the data to write starts at.
- length* The number of bytes past offset to write.

Exceptions:

- IOException*** if an I/O error occurs during the write.
- NullPointerException*** if buffer is Null.
- IndexOutOfBoundsException*** if offset + length is greater than buffer size.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLSocket.h`

6.594 decaf::internal::net::ssl::openssl::OpenSSLSocketException Class Reference

Subclass of the standard SocketException that knows how to produce an error message from the OpenSSL error stack.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketException.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLSocketException:

Public Member Functions

- **OpenSSLSocketException** () throw ()
*Creates an new **OpenSSLSocketException** (p. 2871) with default values.*
- **OpenSSLSocketException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **OpenSSLSocketException** (const **OpenSSLSocketException** &ex) throw ()
Copy Constructor.
- **OpenSSLSocketException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
*Create a new **OpenSSLSocketException** (p. 2871) and initializes the file name and line number where this message occurred.*
- **OpenSSLSocketException** (const std::exception *cause) throw ()
*Creates a new **OpenSSLSocketException** (p. 2871) with the passed exception set as the cause of this exception.*
- **OpenSSLSocketException** (const char *file, const int lineNumber, const char *msg,...) throw ()
*Create a new **OpenSSLSocketException** (p. 2871) and initializes the file name and line number where this message occurred.*
- **OpenSSLSocketException** (const char *file, const int lineNumber) throw ()
*Create a new **OpenSSLSocketException** (p. 2871) and initializes the file name and line number where this message occurred.*
- virtual **OpenSSLSocketException** * clone () const
Clones this exception.
- virtual ~**OpenSSLSocketException** () throw ()

Protected Member Functions

- std::string **getErrorString** () const
Gets and formats an error message string from the OpenSSL error stack.

6.594.1 Detailed Description

Subclass of the standard `SocketException` that knows how to produce an error message from the OpenSSL error stack.

Since:

1.0

6.594.2 Constructor & Destructor Documentation

6.594.2.1 `decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException() throw ()`

Creates an new **OpenSSLSocketException** (p.2871) with default values.

6.594.2.2 `decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException(const Exception & ex) throw ()`

Conversion Constructor from some other Exception.

Parameters:

ex An Exception object that should become this type of Exception.

6.594.2.3 `decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException(const OpenSSLSocketException & ex) throw ()`

Copy Constructor.

Parameters:

ex The **OpenSSLSocketException** (p.2871) whose values should be copied to this instance.

6.594.2.4 `decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException(const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw ()`

Create a new **OpenSSLSocketException** (p.2871) and initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown (can be null).

msg The error message to report.

... The list of primitives that are formatted into the message.

6.594.2.5 decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException (const std::exception * *cause*) throw ()

Creates a new **OpenSSLSocketException** (p. 2871) with the passed exception set as the cause of this exception.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.594.2.6 decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw ()

Create a new **OpenSSLSocketException** (p. 2871) and initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message.

Parameters:

file The file name where exception occurs.
lineNumber The line number where the exception occurred.
msg The error message to report.
... The list of primitives that are formatted into the message

6.594.2.7 decaf::internal::net::ssl::openssl::OpenSSLSocketException::OpenSSLSocketException (const char * *file*, const int *lineNumber*) throw ()

Create a new **OpenSSLSocketException** (p. 2871) and initializes the file name and line number where this message occurred. Sets the message to report by getting the complete set of error messages from the OpenSSL error stack and concatenating them into one string.

Parameters:

file The file name where exception occurs.
lineNumber The line number where the exception occurred.

6.594.2.8 virtual decaf::internal::net::ssl::openssl::OpenSSLSocketException::~~OpenSSLSocketException () throw () [virtual]**6.594.3 Member Function Documentation****6.594.3.1 virtual OpenSSLSocketException* decaf::internal::net::ssl::openssl::OpenSSLSocketException::clone () const [inline, virtual]**

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override this method.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::net::SocketException** (p. 3522).

6.594.3.2 `std::string decaf::internal::net::ssl::openssl::OpenSSLSocketException::getErrorString()` **const** [protected]

Gets and formats an error message string from the OpenSSL error stack.

Returns:

a string containing the complete OpenSSL error string.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketException.h`

6.595 decaf::internal::net::ssl::openssl::OpenSSLSocketFactory Class Reference

Client Socket Factory that creates SSL based client sockets using the OpenSSL library.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLSocketFactory:

Public Member Functions

- **OpenSSLSocketFactory** (**OpenSSLContextSpi** *parent)
- virtual **~OpenSSLSocketFactory** ()
- virtual **decaf::net::Socket** * **createSocket** () throw (decaf::io::IOException)
*Creates an unconnected **Socket** (p. 3503) object.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if the **Socket** (p. 3503) cannot be created.*
- virtual **decaf::net::Socket** * **createSocket** (const **decaf::net::InetAddress** *host, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.*
***UnknownHostException** (p. 3907) if the host name is not known.*
- virtual **decaf::net::Socket** * **createSocket** (const **decaf::net::InetAddress** *host, int port, const **decaf::net::InetAddress** *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
*The **Socket** (p. 3503) will be bound to the specified local address and port.*
Parameters:
host The host to connect the socket to.
port The port on the remote host to connect to.
*ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.*
*localPort The local port to bind the **Socket** (p. 3503) to.*
Returns:
*a new **Socket** (p. 3503) object, caller must free this object when done.*
Exceptions:
***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.*
***UnknownHostException** (p. 3907) if the host name is not known.*

- virtual **decaf::net::Socket * createSocket** (const std::string &hostname, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)

*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*

Parameters:

***host** The host name or IP address to connect the socket to.
port The port on the remote host to connect to.*

Returns:

*a new **Socket** (p. 3503) object, caller must free this object when done.*

Exceptions:

***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.*

- virtual **decaf::net::Socket * createSocket** (const std::string &name, int port, const **decaf::net::InetAddress** *ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)

*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*

Parameters:

***host** The host name or IP address to connect the socket to.
port The port on the remote host to connect to.
ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.
localPort The local port to bind the **Socket** (p. 3503) to.*

Returns:

*a new **Socket** (p. 3503) object, caller must free this object when done.*

Exceptions:

***IOException** if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.*

- virtual std::vector< std::string > **getDefaultCipherSuites** ()

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

***getSupportedCipherSuites()** (p. 3573)*

- virtual std::vector< std::string > **getSupportedCipherSuites** ()

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

***getDefaultCipherSuites()** (p. 3573)*

- virtual **decaf::net::Socket * createSocket** (**decaf::net::Socket** *socket, std::string host, int port, bool autoClose)

Returns a socket layered over an existing socket connected to the named host, at the given port. This constructor can be used when tunneling SSL through a proxy or when negotiating the use of SSL over an existing socket. The host and port refer to the logical peer destination. This socket is configured using the socket options established for this factory.

Parameters:

socket The existing socket to layer over.
host The server host the original **Socket** (p. 3503) is connected to.
port The server port the original **Socket** (p. 3503) is connected to.
autoClose Should the layered over **Socket** (p. 3503) be closed when the topmost socket is closed.

Returns:

a new **Socket** (p. 3503) instance that wraps the given **Socket** (p. 3503).

Exceptions:

IOException if an I/O exception occurs while performing this operation.
UnknownHostException (p. 3907) if the host is unknown.

6.595.1 Detailed Description

Client Socket Factory that creates SSL based client sockets using the OpenSSL library.

Since:

1.0

6.595.2 Constructor & Destructor Documentation

6.595.2.1 decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::OpenSSLSocketFactory (OpenSSLContextSpi * *parent*)

6.595.2.2 virtual
decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::~~OpenSSLSocketFactory
() [virtual]

6.595.3 Member Function Documentation

6.595.3.1 virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket (decaf::net::Socket * *socket*, std::string *host*, int *port*, bool *autoClose*) [virtual]

Returns a socket layered over an existing socket connected to the named host, at the given port.

This constructor can be used when tunneling SSL through a proxy or when negotiating the use of SSL over an existing socket. The host and port refer to the logical peer destination. This socket is configured using the socket options established for this factory.

Parameters:

socket The existing socket to layer over.
host The server host the original **Socket** (p. 3503) is connected to.
port The server port the original **Socket** (p. 3503) is connected to.
autoClose Should the layered over **Socket** (p. 3503) be closed when the topmost socket is closed.

Returns:

a new **Socket** (p. 3503) instance that wraps the given **Socket** (p. 3503).

Exceptions:

IOException if an I/O exception occurs while performing this operation.

UnknownHostException (p. 3907) if the host is unknown.

Implements **decaf::net::ssl::SSLSocketFactory** (p. 3572).

6.595.3.2 `virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket (const std::string & name, int port, const decaf::net::InetAddress * ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]`

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.595.3.3 `virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket (const std::string & hostname, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]`

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3525).

6.595.3.4 virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*, const decaf::net::InetAddress * *ifAddress*, int *localPort*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

The **Socket** (p. 3503) will be bound to the specified local address and port.

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.595.3.5 virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket (const decaf::net::InetAddress * *host*, int *port*) throw (decaf::io::IOException, decaf::net::UnknownHostException) [virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implements **decaf::net::SocketFactory** (p. 3526).

6.595.3.6 `virtual decaf::net::Socket* decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::createSocket () throw (decaf::io::IOException) [virtual]`

Creates an unconnected **Socket** (p. 3503) object.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if the **Socket** (p. 3503) cannot be created.

Reimplemented from **decaf::net::SocketFactory** (p. 3527).

6.595.3.7 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::getDefaultCipherSuites () [virtual]`

Returns the list of cipher suites which are enabled by default.

Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

getSupportedCipherSuites() (p. 3573)

Implements **decaf::net::ssl::SSLSocketFactory** (p. 3573).

6.595.3.8 `virtual std::vector<std::string> decaf::internal::net::ssl::openssl::OpenSSLSocketFactory::getSupportedCipherSuites () [virtual]`

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

getDefaultCipherSuites() (p. 3573)

Implements **decaf::net::ssl::SSLSocketFactory** (p. 3573).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h`

6.596 decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream Class Reference

An output stream for reading data from an OpenSSL Socket instance.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketInputStream.h> Inheritance diagram for decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream:

Public Member Functions

- **OpenSSLSocketInputStream** (OpenSSLSocket *socket)
- virtual ~**OpenSSLSocketInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data avaiable. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

- virtual void **close** () throw (decaf::io::IOException)
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Not supported.

Protected Member Functions

- virtual int **doReadByte** () throw (io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.596.1 Detailed Description

An output stream for reading data from an OpenSSL Socket instance.

Since:

1.0

6.596.2 Constructor & Destructor Documentation

6.596.2.1 decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::OpenSSLSocketInputStream (OpenSSLSocket * *socket*)

6.596.2.2 virtual
decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::~~OpenSSLSocketInputStream () [virtual]

6.596.3 Member Function Documentation

6.596.3.1 virtual int decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::available () const throw (decaf::io::IOException) [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.596.3.2 virtual void decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::close () throw (decaf::io::IOException) [virtual]

Close - does nothing. It is the responsibility of the owner of the socket object to close it.

Closes the **InputStream** (p. 2043) freeing any resources that might have been acquired during the lifetime of this stream.

The default implementation of this method does nothing.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.596.3.3 virtual int decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::doReadArrayBounded (unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Reimplemented from **decaf::io::InputStream** (p. 2046).

6.596.3.4 virtual int decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::doReadByte
 () throw (io::IOException) [protected, virtual]

Implements decaf::io::InputStream (p. 2046).

6.596.3.5 virtual long long decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream::skip
 (long long *num*) throw (decaf::io::IOException,
 decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Not supported. Skips over and discards *n* bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before *n* bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until *num* bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from decaf::io::InputStream (p. 2050).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketInputStream.h

6.597 decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream Class Reference

OutputStream implementation used to write data to an **OpenSSLSocket** (p. 2858) instance.

#include <src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketOutputStream.h> Inheritance
diagram for decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream:

Public Member Functions

- **OpenSSLSocketOutputStream** (**OpenSSLSocket** *socket)
- virtual ~**OpenSSLSocketOutputStream** ()
- virtual void **close** () throw (decaf::io::IOException)

*Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.*

Exceptions:

***IOException** (p. 2142) if an error occurs while closing.*

The default implementation of this method does nothing.

Protected Member Functions

- virtual void **doWriteByte** (unsigned char c) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.597.1 Detailed Description

OutputStream implementation used to write data to an **OpenSSLSocket** (p. 2858) instance.

Since:

1.0

6.597.2 Constructor & Destructor Documentation

6.597.2.1 `decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream::OpenSSLSocketOutputStream (OpenSSLSocket * socket)`

6.597.2.2 `virtual decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream::~~OpenSSLSocketOutputStream ()` [virtual]

6.597.3 Member Function Documentation

6.597.3.1 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream::close ()`
`throw (decaf::io::IOException)` [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from `decaf::io::OutputStream` (p. 2909).

6.597.3.2 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream::doWriteArrayBounded (const unsigned char * buffer, int size, int offset, int length)` throw (`decaf::io::IOException`, `decaf::lang::exceptions::NullPointerException`, `decaf::lang::exceptions::IndexOutOfBoundsException`) [protected, virtual]

Reimplemented from `decaf::io::OutputStream` (p. 2909).

6.597.3.3 `virtual void decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream::doWriteByte (unsigned char c)` throw (`decaf::io::IOException`) [protected, virtual]

Implements `decaf::io::OutputStream` (p. 2910).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketOutputStream.h`

6.598 activemq::wireformat::openwire::OpenWireFormat Class Reference

#include <src/main/activemq/wireformat/openwire/OpenWireFormat.h> Inheritance diagram for activemq::wireformat::openwire::OpenWireFormat:

Public Member Functions

- **OpenWireFormat** (const **decaf::util::Properties** &properties)
*Constructs a new **OpenWireFormat** (p. 2887) object.*
- virtual **~OpenWireFormat** ()
- virtual bool **hasNegotiator** () const
*Returns true if this **WireFormat** (p. 3976) has a Negotiator that needs to wrap the Transport that uses it.*
- virtual **Pointer< transport::Transport > createNegotiator** (const **Pointer< transport::Transport >** &transport) throw (**decaf::lang::exceptions::UnsupportedOperationException**)
If the Transport Provides a Negotiator this method will create and return a news instance of the Negotiator.
- void **addMarshaller** (**marshal::DataStreamMarshaller** *marshaller)
Allows an external source to add marshalers to this object for types that may be marshaled or unmarshaled.
- virtual void **marshal** (const **Pointer< commands::Command >** &command, const **activemq::transport::Transport** *transport, **decaf::io::DataOutputStream** *out) throw (**decaf::io::IOException**)
Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.
- virtual **Pointer< commands::Command > unmarshal** (const **activemq::transport::Transport** *transport, **decaf::io::DataInputStream** *in) throw (**decaf::io::IOException**)
Stream based un-marshaling, blocks on reads on the input stream until a complete command has been read and un-marshaled into the correct form.
- virtual int **tightMarshalNestedObject1** (**commands::DataStructure** *object, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Utility method for Tight Marshaling the given object to the boolean stream passed.
- void **tightMarshalNestedObject2** (**commands::DataStructure** *o, **decaf::io::DataOutputStream** *ds, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
*Utility method that will Tight **marshal** (p. 107) some internally nested object that implements the **DataStructure** interface.*

- **commands::DataStructure** * **tightUnmarshalNestedObject** (decaf::io::DataInputStream *dis, utils::BooleanStream *bs) throw (decaf::io::IOException)
Utility method used to Unmarshal a Nested DataStructure type object from the given DataInputStream.
- **commands::DataStructure** * **looseUnmarshalNestedObject** (decaf::io::DataInputStream *dis) throw (decaf::io::IOException)
Utility method to unmarshal an DataStructure object from an DataInputStream using the Loose Unmarshaling format.
- void **looseMarshalNestedObject** (commands::DataStructure *o, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)
Utility method to loosely Marshal an object that is derived from the DataStrcutre interface.
- void **renegotiateWireFormat** (const commands::WireFormatInfo &info) throw (decaf::lang::exceptions::IllegalStateException)
Called to re-negotiate the settings for the WireFormatInfo, these determine how the client and broker communicate.
- virtual void **setPreferedWireFormatInfo** (const Pointer< commands::WireFormatInfo > &info) throw (decaf::lang::exceptions::IllegalStateException)
Configures this object using the provided WireformatInfo object.
- virtual const Pointer< commands::WireFormatInfo > & **getPreferedWireFormatInfo** () const
Gets the Preferred WireFormatInfo object that this class holds.
- bool **isStackTraceEnabled** () const
Checks if the stackTraceEnabled flag is on.
- void **setStackTraceEnabled** (bool stackTraceEnabled)
Sets if the stackTraceEnabled flag is on.
- bool **isTcpNoDelayEnabled** () const
Checks if the tcpNoDelayEnabled flag is on.
- void **setTcpNoDelayEnabled** (bool tcpNoDelayEnabled)
Sets if the tcpNoDelayEnabled flag is on.
- int **getVersion** () const
Get the current Wireformat Version.
- void **setVersion** (int version) throw (decaf::lang::exceptions::IllegalArgumentExpection)
Set the current Wireformat Version.
- virtual bool **inReceive** () const
Is there a Message being unmarshaled?
- bool **isCacheEnabled** () const

Checks if the cacheEnabled flag is on.

- void **setCacheEnabled** (bool cacheEnabled)
Sets if the cacheEnabled flag is on.
- int **getCacheSize** () const
Returns the currently set Cache size.
- void **setCacheSize** (int value)
Sets the current Cache size.
- bool **isTightEncodingEnabled** () const
Checks if the tightEncodingEnabled flag is on.
- void **setTightEncodingEnabled** (bool tightEncodingEnabled)
Sets if the tightEncodingEnabled flag is on.
- bool **isSizePrefixDisabled** () const
Checks if the sizePrefixDisabled flag is on.
- void **setSizePrefixDisabled** (bool sizePrefixDisabled)
Sets if the sizePrefixDisabled flag is on.
- long long **getMaxInactivityDuration** () const
Gets the MaxInactivityDuration setting.
- void **setMaxInactivityDuration** (long long value)
Sets the MaxInactivityDuration setting.
- long long **getMaxInactivityDurationInitialDelay** () const
Gets the MaxInactivityDurationInitialDelay setting.
- void **setMaxInactivityDurationInitialDelay** (long long value)
Sets the MaxInactivityDurationInitialDelay setting.

Protected Member Functions

- **commands::DataStructure * doUnmarshal** (decaf::io::DataInputStream *dis)
throw (decaf::io::IOException)
Perform the actual unmarshal of data from the given DataInputStream return the unmarshalled DataStrucutre object once done, caller takes ownership of this object.
- void **destroyMarshallers** ()
Cleans up all registered Marshallers and empties the dataMarshallers vector.

Static Protected Attributes

- static const unsigned char **NULL_TYPE**
- static const int **DEFAULT_VERSION** = 1

6.598.1 Constructor & Destructor Documentation

6.598.1.1 `activemq::wireformat::openwire::OpenWireFormat::OpenWireFormat (const decaf::util::Properties & properties)`

Constructs a new **OpenWireFormat** (p. 2887) object.

Parameters:

properties - can contain optional config params.

6.598.1.2 `virtual activemq::wireformat::openwire::OpenWireFormat::~~OpenWireFormat ()` [virtual]

6.598.2 Member Function Documentation

6.598.2.1 `void activemq::wireformat::openwire::OpenWireFormat::addMarshaller (marshal::DataStreamMarshaller * marshaller)`

Allows an external source to add marshalers to this object for types that may be marshaled or unmarshaled.

Parameters:

marshaller - the Marshaler to add to the collection.

6.598.2.2 `virtual Pointer<transport::Transport> activemq::wireformat::openwire::OpenWireFormat::createNegotiator (const Pointer< transport::Transport > & transport) throw (decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

If the Transport Provides a Negotiator this method will create and return a news instance of the Negotiator.

Returns:

new instance of a **WireFormatNegotiator** (p. 4016).

Implements `activemq::wireformat::WireFormat` (p. 3977).

6.598.2.3 `void activemq::wireformat::openwire::OpenWireFormat::destroyMarshallers ()` [protected]

Cleans up all registered Marshallers and empties the dataMarshallers vector. This should be called before a reconfiguration of the version marshallers, or on destruction of this object

6.598.2.4 `commands::DataStructure* activemq::wireformat::openwire::OpenWireFormat::doUnmarshal (decaf::io::DataInputStream * dis) throw (decaf::io::IOException)`
[protected]

Perform the actual unmarshal of data from the given DataInputStream return the unmarshalled DataStrucutre object once done, caller takes ownership of this object. This method can return null if the type of the object to unmarshal is NULL, empty data.

Parameters:

dis - DataInputStream to read from

Returns:

new DataStructure* that the caller owns

Exceptions:

IOException if an error occurs during the unmarshal

6.598.2.5 `int activemq::wireformat::openwire::OpenWireFormat::getCacheSize ()`
`const [inline]`

Returns the currently set Cache size.

Returns:

the current value of the broker's cache size.

6.598.2.6 `long long activemq::wireformat::openwire::OpenWireFormat::getMaxInactivityDuration () const [inline]`

Gets the MaxInactivityDuration setting.

Returns:

maximum inactivity duration value in milliseconds.

6.598.2.7 `long long activemq::wireformat::openwire::OpenWireFormat::getMaxInactivityDurationInitialDelay () const [inline]`

Gets the MaxInactivityDurationInitialDelay setting.

Returns:

maximum inactivity duration initial delay value in milliseconds.

6.598.2.8 `virtual const Pointer<commands::WireFormatInfo>& activemq::wireformat::openwire::OpenWireFormat::getPreferredWireFormatInfo () const [inline, virtual]`

Gets the Preferred WireFormatInfo object that this class holds.

Returns:

pointer to a preferred WireFormatInfo object

6.598.2.9 `int activemq::wireformat::openwire::OpenWireFormat::getVersion () const [inline, virtual]`

Get the current Wireformat Version.

Returns:

int that identifies the version

Implements `activemq::wireformat::WireFormat` (p. 3977).

6.598.2.10 `virtual bool activemq::wireformat::openwire::OpenWireFormat::hasNegotiator () const [inline, virtual]`

Returns true if this `WireFormat` (p. 3976) has a Negotiator that needs to wrap the Transport that uses it.

Returns:

true if the `WireFormat` (p. 3976) provides a Negotiator.

Implements `activemq::wireformat::WireFormat` (p. 3977).

6.598.2.11 `virtual bool activemq::wireformat::openwire::OpenWireFormat::inReceive () const [inline, virtual]`

Is there a Message being unmarshaled?

Returns:

true while in the doUnmarshal method.

Implements `activemq::wireformat::WireFormat` (p. 3978).

6.598.2.12 `bool activemq::wireformat::openwire::OpenWireFormat::isCacheEnabled () const [inline]`

Checks if the cacheEnabled flag is on.

Returns:

true if the flag is on.

6.598.2.13 `bool activemq::wireformat::openwire::OpenWireFormat::isSizePrefixDisabled () const [inline]`

Checks if the sizePrefixDisabled flag is on.

Returns:

true if the flag is on.

6.598.2.14 `bool activemq::wireformat::openwire::OpenWireFormat::isStackTraceEnabled () const [inline]`

Checks if the stackTraceEnabled flag is on.

Returns:

true if the flag is on.

6.598.2.15 `bool activemq::wireformat::openwire::OpenWireFormat::isTcpNoDelayEnabled () const [inline]`

Checks if the tcpNoDelayEnabled flag is on.

Returns:

true if the flag is on.

6.598.2.16 `bool activemq::wireformat::openwire::OpenWireFormat::isTightEncodingEnabled () const [inline]`

Checks if the tightEncodingEnabled flag is on.

Returns:

true if the flag is on.

6.598.2.17 `void activemq::wireformat::openwire::OpenWireFormat::looseMarshalNestedObject (commands::DataStructure * o, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)`

Utility method to loosely Marshal an object that is derived from the DataStrucutre interface. The marshaled data is written to the passed in DataOutputStream.

Parameters:

o - DataStructure derived Object to Marshal

dataOut - DataOutputStream to write the data to

Exceptions:

IOException if an error occurs.

6.598.2.18 `commands::DataStructure* activemq::wireformat::openwire::OpenWireFormat::looseUnmarshalNestedObject (decaf::io::DataInputStream * dis) throw (decaf::io::IOException)`

Utility method to unmarshal an DataStructure object from an DataInputStream using the Loose Unmarshaling format. Will read the Data and construct a new DataStructure based Object, the pointer to the Object returned is now owned by the caller.

Parameters:

dis - the DataInputStream to read the data from

Returns:

a new DataStructure derived Object pointer

Exceptions:

IOException if an error occurs.

6.598.2.19 `virtual void activemq::wireformat::openwire::OpenWireFormat::marshal (const Pointer< commands::Command > & command, const activemq::transport::Transport * transport, decaf::io::DataOutputStream * out) throw (decaf::io::IOException)`
[virtual]

Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.

Parameters:

command The Command to Marshal.

transport (p. 97) The Transport instance that called this method.

out The output stream to write the command to.

Exceptions:

IOException

Implements `activemq::wireformat::WireFormat` (p. 3978).

6.598.2.20 `void activemq::wireformat::openwire::OpenWireFormat::renegotiateWireFormat (const commands::WireFormatInfo & info) throw (decaf::lang::exceptions::IllegalStateException)`

Called to re-negotiate the settings for the WireFormatInfo, these determine how the client and broker communicate.

Parameters:

info - The new Wireformat Info settings

Exceptions:

IllegalStateException is wire format can't be negotiated.

6.598.2.21 void activemq::wireformat::openwire::OpenWireFormat::setCacheEnabled (bool *cacheEnabled*) [inline]

Sets if the cacheEnabled flag is on.

Parameters:

cacheEnabled - true to turn flag is on

6.598.2.22 void activemq::wireformat::openwire::OpenWireFormat::setCacheSize (int *value*) [inline]

Sets the current Cache size.

Parameters:

value - the value to send as the broker's cache size.

6.598.2.23 void activemq::wireformat::openwire::OpenWireFormat::setMaxInactivityDuration (long long *value*) [inline]

Sets the MaxInactivityDuration setting.

Parameters:

value - the Max inactivity duration value in milliseconds.

6.598.2.24 void activemq::wireformat::openwire::OpenWireFormat::setMaxInactivityDurationInitialDelay (long long *value*) [inline]

Sets the MaxInactivityDurationInitialDelay setting.

Parameters:

value - the Max inactivity Initial Delay duration value in milliseconds.

6.598.2.25 virtual void activemq::wireformat::openwire::OpenWireFormat::setPreferredWireFormatInfo (const Pointer< commands::WireFormatInfo > & *info*) throw (decaf::lang::exceptions::IllegalStateException) [virtual]

Configures this object using the provided WireformatInfo object.

Parameters:

info - a WireFormatInfo object, takes ownership.

6.598.2.26 void activemq::wireformat::openwire::OpenWireFormat::setSizePrefixDisabled (bool *sizePrefixDisabled*) [inline]

Sets if the sizePrefixDisabled flag is on.

Parameters:

sizePrefixDisabled - true to turn flag is on

6.598.2.27 void activemq::wireformat::openwire::OpenWireFormat::setStackTraceEnabled (bool *stackTraceEnabled*) [inline]

Sets if the stackTraceEnabled flag is on.

Parameters:

stackTraceEnabled - true to turn flag is on

6.598.2.28 void activemq::wireformat::openwire::OpenWireFormat::setTcpNoDelayEnabled (bool *tcpNoDelayEnabled*) [inline]

Sets if the tcpNoDelayEnabled flag is on.

Parameters:

tcpNoDelayEnabled - true to turn flag is on

6.598.2.29 void activemq::wireformat::openwire::OpenWireFormat::setTightEncodingEnabled (bool *tightEncodingEnabled*) [inline]

Sets if the tightEncodingEnabled flag is on.

Parameters:

tightEncodingEnabled - true to turn flag is on

6.598.2.30 void activemq::wireformat::openwire::OpenWireFormat::setVersion (int *version*) throw (decaf::lang::exceptions::IllegalArgumentException) [virtual]

Set the current Wireformat Version.

Parameters:

version - int that identifies the version

Implements **activemq::wireformat::WireFormat** (p. 3978).

6.598.2.31 `virtual int activemq::wireformat::openwire::OpenWireFormat::tightMarshalNestedObject1(commands::DataStructure * object, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Utility method for Tight Marshaling the given object to the boolean stream passed.

Parameters:

object - The DataStructure to **marshal** (p. 107)

bs - the BooleanStream to write to

Returns:

size of the data returned.

6.598.2.32 `void activemq::wireformat::openwire::OpenWireFormat::tightMarshalNestedObject2(commands::DataStructure * o, decaf::io::DataOutputStream * ds, utils::BooleanStream * bs) throw (decaf::io::IOException)`

Utility method that will Tight **marshal** (p. 107) some internally nested object that implements the DataStructure interface. Writes the data to the Data Output Stream provided.

Parameters:

o - DataStructure object

ds - DataOutputStream for writing

bs - BooleanStream

Exceptions:

IOException if an error occurs.

6.598.2.33 `commands::DataStructure* activemq::wireformat::openwire::OpenWireFormat::tightUnmarshalNestedObject(decaf::io::DataInputStream * dis, utils::BooleanStream * bs) throw (decaf::io::IOException)`

Utility method used to Unmarshal a Nested DataStructure type object from the given DataInputStream. The DataStructure instance that is returned is now the property of the caller.

Parameters:

dis - DataInputStream to read from

bs - BooleanStream to read from

Returns:

Newly allocated DataStructure Object

Exceptions:

IOException if an error occurs.

6.598.2.34 `virtual Pointer<commands::Command> activemq::wireformat::openwire::OpenWireFormat::unmarshal (const activemq::transport::Transport * transport, decaf::io::DataInputStream * in) throw (decaf::io::IOException) [virtual]`

Stream based un-marshaling, blocks on reads on the input stream until a complete command has been read and un-marshaled into the correct form. Returns a Pointer to the newly un-marshaled Command.

Parameters:

transport (p. 97) - Pointer to the **transport** (p. 97) that is making this request.

in - the input stream to read the command from.

Returns:

the newly marshaled Command, caller owns the pointer

Exceptions:

IOException

Implements **activemq::wireformat::WireFormat** (p. 3979).

6.598.3 Field Documentation

6.598.3.1 `const int activemq::wireformat::openwire::OpenWireFormat::DEFAULT_VERSION = 1 [static, protected]`

6.598.3.2 `const unsigned char activemq::wireformat::openwire::OpenWireFormat::NULL_TYPE [static, protected]`

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/OpenWireFormat.h`

6.599 activemq::wireformat::openwire::OpenWireFormatFactory Class Reference

#include <src/main/activemq/wireformat/openwire/OpenWireFormatFactory.h> Inheritance diagram for activemq::wireformat::openwire::OpenWireFormatFactory:

Public Member Functions

- **OpenWireFormatFactory** ()

Constructor - Sets Defaults for all properties, these are all subject to change once the `createWireFormat` method is called.

- virtual **~OpenWireFormatFactory** ()

- virtual **Pointer< wireformat::WireFormat > createWireFormat** (const **decaf::util::Properties** &properties) throw (**decaf::lang::exceptions::IllegalStateException**)

*Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.*

6.599.1 Constructor & Destructor Documentation

6.599.1.1 activemq::wireformat::openwire::OpenWireFormatFactory::OpenWireFormatFactory () [inline]

Constructor - Sets Defaults for all properties, these are all subject to change once the `createWireFormat` method is called. URL options ----- wireFormat.stackTraceEnabled wireFormat.cacheEnabled wireFormat.tcpNoDelayEnabled wireFormat.tightEncodingEnabled wireFormat.sizePrefixDisabled wireFormat.maxInactivityDuration wireFormat.maxInactivityDurationInitialDelay

6.599.1.2 virtual activemq::wireformat::openwire::OpenWireFormatFactory::~~OpenWireFormatFactory () [inline, virtual]

6.599.2 Member Function Documentation

6.599.2.1 virtual Pointer<wireformat::WireFormat> activemq::wireformat::openwire::OpenWireFormatFactory::createWireFormat (const **decaf::util::Properties** & *properties*) throw (**decaf::lang::exceptions::IllegalStateException**) [virtual]

Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.

Parameters:

properties - the Properties for this **WireFormat** (p. 3976)

Implements **activemq::wireformat::WireFormatFactory** (p. 3980).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/OpenWireFormatFactory.h`

6.600 activemq::wireformat::openwire::OpenWireFormatNegotiator Class Reference

#include <src/main/activemq/wireformat/openwire/OpenWireFormatNegotiator.h> Inheritance diagram for activemq::wireformat::openwire::OpenWireFormatNegotiator:

Public Member Functions

- **OpenWireFormatNegotiator** (**OpenWireFormat** *wireFormat, const **Pointer**< **transport::Transport** > &next)
Constructor - Initializes this object around another Transport.
- virtual **~OpenWireFormatNegotiator** ()
- virtual void **oneway** (const **Pointer**< **commands::Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **commands::Response** > **request** (const **Pointer**< **commands::Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given request to the server and waits for the response.
- virtual **Pointer**< **commands::Response** > **request** (const **Pointer**< **commands::Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given request to the server and waits for the response.
- virtual void **onCommand** (const **Pointer**< **commands::Command** > &command)
This is called in the context of the nested transport's reading thread.
- virtual void **onTransportException** (**transport::Transport** *source, const **decaf::lang::Exception** &ex)
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **start** () throw (decaf::io::IOException)
*Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87).*
- virtual void **close** () throw (decaf::io::IOException)
Stops the polling thread and closes the streams.

6.600.1 Constructor & Destructor Documentation

6.600.1.1 activemq::wireformat::openwire::OpenWireFormatNegotiator::OpenWireFormatNegotiator (**OpenWireFormat** * wireFormat, const **Pointer**< **transport::Transport** > & next)

Constructor - Initializes this object around another Transport.

Parameters:

wireFormat - The **WireFormat** (p. 3976) object we use to negotiate

next - The next **transport** (p. 97) in the chain

6.600.1.2 **virtual**
 activemq::wireformat::openwire::OpenWireFormatNegotiator::~~OpenWireFormatNegotiator
 () [virtual]

6.600.2 Member Function Documentation

6.600.2.1 **virtual void ac-**
 tivemq::wireformat::openwire::OpenWireFormatNegotiator::close ()
 throw (decaf::io::IOException) [virtual]

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if errors occur.

Reimplemented from **activemq::transport::TransportFilter** (p. 3893).

6.600.2.2 **virtual void ac-**
 tivemq::wireformat::openwire::OpenWireFormatNegotiator::onCommand
 (const Pointer< commands::Command > & command) [virtual]

This is called in the context of the nested transport's reading thread. In the case of a response object, updates the request map and notifies those waiting on the response. Non-response messages are just delegated to the command listener.

Parameters:

command the received from the nested **transport** (p. 97).

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.600.2.3 **virtual void ac-**
 tivemq::wireformat::openwire::OpenWireFormatNegotiator::oneway
 (const Pointer< commands::Command > &
 command) throw (decaf::io::IOException, de-
 caf::lang::exceptions::UnsupportedOperationException)
 [virtual]

Sends a one-way command. Does not wait for any response from the broker. First waits for the WireFormatInfo exchange to happen so that we know how to encode out-bound data.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.600.2.4 `virtual void activemq::wireformat::openwire::OpenWireFormatNegotiator::onTransportException (transport::Transport * source, const decaf::lang::Exception & ex) [virtual]`

Event handler for an exception from a command **transport** (p. 97).

Parameters:

source The source of the exception
ex The exception.

6.600.2.5 `virtual Pointer<commands::Response> activemq::wireformat::openwire::OpenWireFormatNegotiator::request (const Pointer< commands::Command > & command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Sends the given request to the server and waits for the response. First waits for the WireFormatInfo exchange to happen so that we know how to encode out-bound data.

Parameters:

command The request to send.
timeout The time to wait for the response.

Returns:

the response from the server.

Exceptions:

IOException if an error occurs with the request.

Reimplemented from **activemq::transport::TransportFilter** (p. 3896).

6.600.2.6 `virtual Pointer<commands::Response> activemq::wireformat::openwire::OpenWireFormatNegotiator::request (const Pointer< commands::Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Sends the given request to the server and waits for the response. First waits for the WireFormatInfo exchange to happen so that we know how to encode out-bound data.

Parameters:

command The request to send.

Returns:

the response from the server.

Exceptions:

IOException if an error occurs with the request.

Reimplemented from **activemq::transport::TransportFilter** (p. 3897).

6.600.2.7 **virtual void activemq::wireformat::openwire::OpenWireFormatNegotiator::start ()**
throw (decaf::io::IOException) [virtual]

Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87). If this object has been closed, throws an exception. Before calling start, the caller must set the IO streams and the reader and writer objects.

Exceptions:

IOException if an error occurs or if this **transport** (p. 97) has already been closed.

Reimplemented from **activemq::transport::TransportFilter** (p. 3898).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/OpenWireFormatNegotiator.h`

6.601 activemq::wireformat::openwire::OpenWireResponseBuilder Class Reference

#include <src/main/activemq/wireformat/openwire/OpenWireResponseBuilder.h> Inheritance diagram for activemq::wireformat::openwire::OpenWireResponseBuilder:

Public Member Functions

- **OpenWireResponseBuilder** ()
- virtual **~OpenWireResponseBuilder** ()
- virtual **Pointer< commands::Response > buildResponse** (const **Pointer< commands::Command > &command**)

Given a Command, check if it requires a response and return the appropriate Response that the Broker would send for this Command.

- virtual void **buildIncomingCommands** (const **Pointer< commands::Command > &command**, **decaf::util::StlQueue< Pointer< commands::Command > > &queue**)

*When called the ResponseBuilder must construct all the Responses or Asynchronous **commands** (p. 87) that would be sent to this client by the Broker upon receipt of the passed command.*

6.601.1 Constructor & Destructor Documentation

6.601.1.1 **activemq::wireformat::openwire::OpenWireResponseBuilder::OpenWireResponseBuilder** () [inline]

6.601.1.2 **virtual**
activemq::wireformat::openwire::OpenWireResponseBuilder::~~OpenWireResponseBuilder () [inline, virtual]

6.601.2 Member Function Documentation

6.601.2.1 **virtual void** **activemq::wireformat::openwire::OpenWireResponseBuilder::buildIncomingCommands** (const **Pointer< commands::Command > & command**, **decaf::util::StlQueue< Pointer< commands::Command > > & queue**) [virtual]

When called the ResponseBuilder must construct all the Responses or Asynchronous **commands** (p. 87) that would be sent to this client by the Broker upon receipt of the passed command.

Parameters:

command - The Command being sent to the Broker.

queue - Queue of Command sent back from the broker.

Implements **activemq::transport::mock::ResponseBuilder** (p. 3289).

6.601.2.2 `virtual Pointer<commands::Response> activemq::wireformat::openwire::OpenWireResponseBuilder::buildResponse(const Pointer< commands::Command > & command) [virtual]`

Given a Command, check if it requires a response and return the appropriate Response that the Broker would send for this Command.

Parameters:

command - The command to build a response for

Returns:

A Response object pointer, or NULL if no response.

Implements `activemq::transport::mock::ResponseBuilder` (p. 3290).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/OpenWireResponseBuilder.h`

6.602 decaf::io::OutputStream Class Reference

Base interface for any class that wants to represent an output stream of bytes.

#include <src/main/decaf/io/OutputStream.h> Inheritance diagram for decaf::io::OutputStream:

Public Member Functions

- **OutputStream** ()
- virtual **~OutputStream** ()
- virtual void **close** () throw (decaf::io::IOException)
*Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.*
Exceptions:
IOException (p. 2142) if an error occurs while closing.
- virtual void **flush** () throw (decaf::io::IOException)
Flushes this stream by writing any buffered output to the underlying stream.
Exceptions:
IOException (p. 2142) if an I/O error occurs.
- virtual void **write** (unsigned char c) throw (decaf::io::IOException)
Writes a single byte to the output stream.
- virtual void **write** (const unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Writes an array of bytes to the output stream.
- virtual void **write** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Writes an array of bytes to the output stream in order starting at buffer[offset] and proceeding until the number of bytes specified by the length argument are written or an error occurs.
- virtual std::string **toString** () const
Output a String representation of this object.
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.

- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)

Waits on a signal from this object, which is generated by a call to Notify.

- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals a waiter on this object that it can now wake up and continue.

- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)

Signals the waiters on this object that it can now wake up and continue.

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value)=0 throw (decaf::io::IOException)
- virtual void **doWriteArray** (const unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.602.1 Detailed Description

Base interface for any class that wants to represent an output stream of bytes.

Since:

1.0

6.602.2 Constructor & Destructor Documentation

6.602.2.1 decaf::io::OutputStream::OutputStream ()

6.602.2.2 virtual decaf::io::OutputStream::~~OutputStream () [virtual]

6.602.3 Member Function Documentation

6.602.3.1 virtual void decaf::io::OutputStream::close () throw (decaf::io::IOException) [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing.

Implements decaf::io::Closeable (p. 1149).

Reimplemented in decaf::internal::io::StandardErrorOutputStream (p. 3580), decaf::internal::io::StandardOutputStream (p. 3584), decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream (p. 2886), decaf::internal::net::tcp::TcpSocketOutputStream (p. 3751), decaf::io::FilterOutputStream (p. 1901), and decaf::util::zip::DeflaterOutputStream (p. 1718).

6.602.3.2 virtual void decaf::io::OutputStream::doWriteArray (const unsigned char * *buffer*, int *size*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented in decaf::io::BufferedOutputStream (p. 941), and decaf::io::FilterOutputStream (p. 1902).

6.602.3.3 virtual void decaf::io::OutputStream::doWriteArrayBounded (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented in activemq::io::LoggingOutputStream (p. 2401), decaf::internal::io::StandardErrorOutputStream (p. 3580), decaf::internal::io::StandardOutputStream (p. 3585), decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream (p. 2886), decaf::internal::net::tcp::TcpSocketOutputStream (p. 3751), decaf::io::BufferedOutputStream (p. 941), decaf::io::ByteArrayOutputStream (p. 1029), decaf::io::DataOutputStream (p. 1580), decaf::io::FilterOutputStream (p. 1902), decaf::util::zip::CheckedOutputStream (p. 1141), and decaf::util::zip::DeflaterOutputStream (p. 1719).

6.602.3.4 virtual void decaf::io::OutputStream::doWriteByte (unsigned char *value*)
throw (decaf::io::IOException) [protected, pure virtual]

Implemented in **activemq::io::LoggingOutputStream** (p. 2402),
decaf::internal::io::StandardErrorOutputStream (p. 3580),
decaf::internal::io::StandardOutputStream (p. 3585), **de-**
caf::internal::net::ssl::openssl::OpenSSLSocketOutputStream (p. 2886),
decaf::internal::net::tcp::TcpSocketOutputStream (p. 3751), **de-**
caf::io::BufferedOutputStream (p. 941), **decaf::io::ByteArrayOutputStream**
(p. 1029), **decaf::io::DataOutputStream** (p. 1581), **decaf::io::FilterOutputStream**
(p. 1902), **decaf::util::zip::CheckedOutputStream** (p. 1141), and **de-**
caf::util::zip::DeflaterOutputStream (p. 1719).

6.602.3.5 virtual void decaf::io::OutputStream::flush () throw (
decaf::io::IOException) [virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The default implementation of this method does nothing.

Implements **decaf::io::Flushable** (p. 1936).

Reimplemented in **decaf::internal::io::StandardErrorOutputStream** (p. 3580), **de-**
caf::internal::io::StandardOutputStream (p. 3585), **decaf::io::BufferedOutputStream**
(p. 941), and **decaf::io::FilterOutputStream** (p. 1902).

6.602.3.6 virtual void decaf::io::OutputStream::lock () throw (
decaf::lang::exceptions::RuntimeException) [inline, virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3701).

6.602.3.7 virtual void decaf::io::OutputStream::notify ()
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [inline,
virtual]

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3702).

6.602.3.8 `virtual void decaf::io::OutputStream::notifyAll ()
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [inline,
virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.602.3.9 `virtual std::string decaf::io::OutputStream::toString () const [virtual]`

Output a String representation of this object. The default version of this method just prints the Class Name.

Returns:

a string representation of the object.

Reimplemented in **decaf::io::ByteArrayOutputStream** (p. 1030), and **decaf::io::FilterOutputStream** (p. 1903).

6.602.3.10 `virtual bool decaf::io::OutputStream::tryLock () throw (
decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

6.602.3.11 `virtual void decaf::io::OutputStream::unlock () throw (
decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

6.602.3.12 `virtual void decaf::io::OutputStream::wait (long long millisecs,
int nanos) throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.602.3.13 `virtual void decaf::io::OutputStream::wait (long long
millisecs) throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

6.602.3.14 `virtual void decaf::io::OutputStream::wait ()
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

6.602.3.15 `virtual void decaf::io::OutputStream::write (const unsigned
char * buffer, int size, int offset, int length) throw (
decaf::io::IOException, decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Writes an array of bytes to the output stream in order starting at `buffer[offset]` and proceeding until the number of bytes specified by the `length` argument are written or an error occurs. The default implementation of this method simply calls the `doWriteArrayBounded` method which writes the contents of the array using the `doWriteByte` method repeatedly. It is recommended that a subclass override `doWriteArrayBounded` to provide more performant means of writing the array.

Parameters:

buffer The array of bytes to write.

size The size of the buffer array passed.

offset The position to start writing in buffer.

length The number of bytes from the buffer to be written.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

NullPointerException thrown if buffer is Null.

IndexOutOfBoundsException if the `offset + length > size`. or one of the parameters is negative.

6.602.3.16 `virtual void decaf::io::OutputStream::write (const unsigned char * buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Writes an array of bytes to the output stream. The entire contents of the given vector are written to the output stream.

The default implementation of this method simply calls the `doWriteArray` which writes the contents of the array using the `doWriteByte` method repeatedly. It is recommended that a subclass override `doWriteArray` to provide more performant means of writing the array.

Parameters:

buffer The vector of bytes to write.
size The size of the buffer passed.

Exceptions:

IOException (p. 2142) if an I/O error occurs.
NullPointerException thrown if buffer is Null.
IndexOutOfBoundsException if size value is negative.

6.602.3.17 `virtual void decaf::io::OutputStream::write (unsigned char c) throw (decaf::io::IOException) [virtual]`

Writes a single byte to the output stream. The default implementation of this method calls the pure virtual method `doWriteByte` which must be implemented by any subclass of the **OutputStream** (p. 2907).

Parameters:

c The byte to write to the sink.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The documentation for this class was generated from the following file:

- `src/main/decaf/io/OutputStream.h`

6.603 decaf::io::OutputStreamWriter Class Reference

A class for turning a character stream into a byte stream.

#include <src/main/decaf/io/OutputStreamWriter.h> Inheritance diagram for decaf::io::OutputStreamWriter:

Public Member Functions

- **OutputStreamWriter** (**OutputStream** *stream, bool own=false)
*Creates a new **OutputStreamWriter** (p. 2915).*
- virtual ~**OutputStreamWriter** ()
- virtual void **close** () throw (decaf::io::IOException)
Closes this object and deallocates the appropriate resources.
- virtual void **flush** () throw (decaf::io::IOException)
Flushes this stream by writing any buffered output to the underlying stream.

Protected Member Functions

- virtual void **doWriteArrayBounded** (const char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Override this method to customize the functionality of the method write(char buffer, int size, int offset, int length).*
- virtual void **checkClosed** () const throw (decaf::io::IOException)

6.603.1 Detailed Description

A class for turning a character stream into a byte stream.

See also:

InputStreamReader (p. 2053)

Since:

1.0

6.603.2 Constructor & Destructor Documentation

6.603.2.1 decaf::io::OutputStreamWriter::OutputStreamWriter (**OutputStream** *stream, bool own = false)

Creates a new **OutputStreamWriter** (p. 2915).

Parameters:

- stream* The **OutputStream** (p. 2907) to wrap. (cannot be NULL).
- own* Indicates whether this instance own the given **OutputStream** (p. 2907). If true then the **OutputStream** (p. 2907) is destroyed when this class is.

Exceptions:

- NullPointerException* if the stream is NULL.

6.603.2.2 virtual decaf::io::OutputStreamWriter::~~OutputStreamWriter ()
[virtual]

6.603.3 Member Function Documentation

6.603.3.1 virtual void decaf::io::OutputStreamWriter::checkClosed () const throw (
decaf::io::IOException) [protected, virtual]

6.603.3.2 virtual void decaf::io::OutputStreamWriter::close () throw (
decaf::io::IOException) [virtual]

Closes this object and deallocates the appropriate resources. The object is generally no longer usable after calling close.

Exceptions:

- IOException* (p. 2142) if an error occurs while closing.

Implements **decaf::io::Closeable** (p. 1149).

6.603.3.3 virtual void decaf::io::OutputStreamWriter::doWriteArrayBounded
(const char * *buffer*, int *size*, int *offset*, int *length*) throw (
decaf::io::IOException, decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException) [protected,
virtual]

Override this method to customize the functionality of the method write(char* buffer, int size, int offset, int length). All subclasses must override this method to provide the basic **Writer** (p. 4021) functionality.

Implements **decaf::io::Writer** (p. 4024).

6.603.3.4 virtual void decaf::io::OutputStreamWriter::flush () throw (
decaf::io::IOException) [virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

- IOException* (p. 2142) if an I/O error occurs.

Implements **decaf::io::Flushable** (p. 1936).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/OutputStreamWriter.h`

6.604 activemq::commands::PartialCommand Class Reference

#include <src/main/activemq/commands/PartialCommand.h> Inheritance diagram for activemq::commands::PartialCommand:

Public Member Functions

- **PartialCommand** ()
- virtual **~PartialCommand** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **PartialCommand * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual int **getCommandId** () const
- virtual void **setCommandId** (int commandId)
- virtual const std::vector< unsigned char > & **getData** () const
- virtual std::vector< unsigned char > & **getData** ()
- virtual void **setData** (const std::vector< unsigned char > &data)

Static Public Attributes

- static const unsigned char **ID_PARTIALCOMMAND** = 60

Protected Attributes

- int **commandId**
- std::vector< unsigned char > **data**

6.604.1 Constructor & Destructor Documentation

6.604.1.1 `activemq::commands::PartialCommand::PartialCommand ()`

6.604.1.2 `virtual activemq::commands::PartialCommand::~~PartialCommand ()`
[virtual]

6.604.2 Member Function Documentation

6.604.2.1 `virtual PartialCommand* activemq::commands::PartialCommand::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

Reimplemented in `activemq::commands::LastPartialCommand` (p. 2301).

6.604.2.2 `virtual void activemq::commands::PartialCommand::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented in `activemq::commands::LastPartialCommand` (p. 2302).

6.604.2.3 `virtual bool activemq::commands::PartialCommand::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented in `activemq::commands::LastPartialCommand` (p. 2302).

6.604.2.4 `virtual int activemq::commands::PartialCommand::getCommandId ()`
`const [virtual]`

6.604.2.5 `virtual std::vector<unsigned char>& ac-`
`tivemq::commands::PartialCommand::getData ()`
`[virtual]`

6.604.2.6 `virtual const std::vector<unsigned char>& ac-`
`tivemq::commands::PartialCommand::getData () const`
`[virtual]`

6.604.2.7 `virtual unsigned char ac-`
`tivemq::commands::PartialCommand::getDataStructureType () const`
`[virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

Reimplemented in **activemq::commands::LastPartialCommand** (p. 2302).

6.604.2.8 `virtual void activemq::commands::PartialCommand::setCommandId (int`
`commandId) [virtual]`

6.604.2.9 `virtual void activemq::commands::PartialCommand::setData (const`
`std::vector< unsigned char > & data) [virtual]`

6.604.2.10 `virtual std::string activemq::commands::PartialCommand::toString ()`
`const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p. 833).

Reimplemented in **activemq::commands::LastPartialCommand** (p. 2302).

6.604.3 Field Documentation

6.604.3.1 `int activemq::commands::PartialCommand::commandId` [protected]

6.604.3.2 `std::vector<unsigned char> activemq::commands::PartialCommand::data`
[protected]

6.604.3.3 `const unsigned char activemq::commands::PartialCommand::ID_ -`
`PARTIALCOMMAND = 60` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/PartialCommand.h`

6.605 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2922).

#include <src/main/activemq/wireformat/openwire/marshal/v6/PartialCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.605.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2922).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.605.2 Constructor & Destructor Documentation

6.605.2.1 `activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.605.2.2 `virtual activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.605.3 Member Function Documentation

6.605.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller` (p. 2305).

6.605.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller` (p. 2305).

6.605.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller** (p. 2305).

6.605.3.4 virtual void activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller** (p. 2306).

6.605.3.5 virtual int activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller** (p. 2306).

6.605.3.6 virtual void activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller** (p. 2307).

6.605.3.7 virtual void activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller** (p. 2307).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/PartialCommandMarshaller.h

6.606 activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2926).

#include <src/main/activemq/wireformat/openwire/marshal/v2/PartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.606.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2926).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.606.2 Constructor & Destructor Documentation

6.606.2.1 `activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.606.2.2 `virtual activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.606.3 Member Function Documentation

6.606.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller` (p. 2313).

6.606.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller` (p. 2313).

6.606.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller** (p. 2313).

6.606.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller** (p. 2314).

6.606.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller** (p. 2314).

6.606.3.6 virtual void activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller** (p. 2315).

6.606.3.7 virtual void activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller** (p. 2315).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/PartialCommandMarshaller.h

6.607 activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2930).

#include <src/main/activemq/wireformat/openwire/marshal/v5/PartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.607.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2930).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.607.2 Constructor & Destructor Documentation

6.607.2.1 `activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.607.2.2 `virtual activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.607.3 Member Function Documentation

6.607.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller` (p. 2317).

6.607.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller` (p. 2317).

6.607.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller** (p. 2317).

6.607.3.4 virtual void activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller** (p. 2318).

6.607.3.5 virtual int activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller** (p. 2318).

6.607.3.6 virtual void activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller** (p. 2319).

6.607.3.7 virtual void activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller** (p. 2319).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/PartialCommandMarshaller.h

6.608 activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2934).

#include <src/main/activemq/wireformat/openwire/marshal/v3/PartialCommandMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.608.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2934).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.608.2 Constructor & Destructor Documentation

6.608.2.1 `activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.608.2.2 `virtual activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.608.3 Member Function Documentation

6.608.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller` (p. 2309).

6.608.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller` (p. 2309).

6.608.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller** (p. 2309).

6.608.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller** (p. 2310).

6.608.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller** (p. 2310).

6.608.3.6 virtual void activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller** (p. 2311).

6.608.3.7 virtual void activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller** (p. 2311).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**PartialCommandMarshaller.h**

6.609 activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2938).

#include <src/main/activemq/wireformat/openwire/marshal/v4/PartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.609.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2938).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.609.2 Constructor & Destructor Documentation

6.609.2.1 `activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.609.2.2 `virtual activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.609.3 Member Function Documentation

6.609.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller` (p. 2321).

6.609.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller` (p. 2321).

6.609.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller** (p. 2321).

6.609.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller** (p. 2322).

6.609.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller** (p. 2322).

6.609.3.6 virtual void activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller** (p. 2323).

6.609.3.7 virtual void activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller** (p. 2323).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**PartialCommandMarshaller.h**

6.610 activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2942).

#include <src/main/activemq/wireformat/openwire/marshal/v1/PartialCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller:

Public Member Functions

- **PartialCommandMarshaller** ()
- virtual **~PartialCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.610.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2942).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.610.2 Constructor & Destructor Documentation

6.610.2.1 `activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::PartialCommandMarshaller()` [inline]

6.610.2.2 `virtual activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::~~PartialCommandMarshaller()` [inline, virtual]

6.610.3 Member Function Documentation

6.610.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller` (p. 2325).

6.610.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller` (p. 2325).

6.610.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller** (p. 2325).

6.610.3.4 virtual void activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller** (p. 2326).

6.610.3.5 virtual int activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::tightMarshal1 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller** (p. 2326).

6.610.3.6 virtual void activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller** (p. 2327).

6.610.3.7 virtual void activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller** (p. 2327).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**PartialCommandMarshaller.h**

6.611 decaf::lang::Pointer< T, REFCOUNTER > Class Template Reference

Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used.

```
#include <src/main/decaf/lang/Pointer.h>
```

Public Types

- typedef T * **PointerType**
- typedef T & **ReferenceType**
- typedef REFCOUNTER **CounterType**

Public Member Functions

- **Pointer** ()
Default Constructor.
- **Pointer** (const **PointerType** value)
*Explicit Constructor, creates a **Pointer** (p. 2946) that contains value with a single reference.*
- **Pointer** (const **Pointer** &value) throw ()
Copy constructor.
- template<typename T1 , typename R1 >
Pointer (const **Pointer**< T1, R1 > &value) throw ()
Copy constructor.
- template<typename T1 , typename R1 >
Pointer (const **Pointer**< T1, R1 > &value, const **STATIC_CAST_TOKEN** &) throw ()
Static Cast constructor.
- template<typename T1 , typename R1 >
Pointer (const **Pointer**< T1, R1 > &value, const **DYNAMIC_CAST_TOKEN** &) throw (decaf::lang::exceptions::ClassCastException)
Dynamic Cast constructor.
- virtual ~**Pointer** () throw ()
- void **reset** (T *value)
*Resets the **Pointer** (p. 2946) to hold the new value.*
- T * **release** ()
*Releases the **Pointer** (p. 2946) held and resets the **internal** (p. 144) pointer value to Null.*
- **PointerType** **get** () const
*Gets the real pointer that is contained within this **Pointer** (p. 2946).*
- void **swap** (**Pointer** &value) throw ()

Exception (p. 1831) Safe Swap Function.

- **Pointer** & **operator**== (const **Pointer** &right) throw ()
*Assigns the value of right to this **Pointer** (p. 2946) and increments the reference Count.*
- template<typename T1 , typename R1 >
Pointer & **operator**== (const **Pointer**< T1, R1 > &right) throw ()
- **ReferenceType operator*** ()
Dereference Operator, returns a reference to the Contained value.
- **ReferenceType operator*** () const
- **PointerType operator->** ()
Indirection Operator, returns a pointer to the Contained value.
- **PointerType operator->** () const
- bool **operator!** () const
- template<typename T1 , typename R1 >
 bool **operator**== (const **Pointer**< T1, R1 > &right) const
- template<typename T1 , typename R1 >
 bool **operator!**== (const **Pointer**< T1, R1 > &right) const
- template<typename T1 >
Pointer< T1, **CounterType** > **dynamicCast** () const
- template<typename T1 >
Pointer< T1, **CounterType** > **staticCast** () const

Friends

- bool **operator**== (const **Pointer** &left, const T *right)
- bool **operator**== (const T *left, const **Pointer** &right)
- bool **operator!**== (const **Pointer** &left, const T *right)
- bool **operator!**== (const T *left, const **Pointer** &right)

6.611.1 Detailed Description

```
template<typename          T,          typename          REFCOUNTER          =
decaf::util::concurrent::atomic::AtomicRefCounter>      class      decaf::lang::Pointer<
T, REFCOUNTER >
```

Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used. This **Pointer** (p. 2946) type allows for the substitution of different Reference Counter implementations which provide a means of using invasive reference counting if desired using a custom implementation of **ReferenceCounter**.

The Decaf smart pointer provide comparison operators for comparing **Pointer** (p. 2946) instances in the same manner as normal pointer, except that it does not provide an overload of operators (<, <=, >, >=). To allow use of a **Pointer** (p. 2946) in a STL container that requires it, **Pointer** (p. 2946) provides an implementation of std::less.

Since:

1.0

6.611.2 Member Typedef Documentation

- 6.611.2.1** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef REFCOUNTER decaf::lang::Pointer< T, REFCOUNTER >::CounterType`
- 6.611.2.2** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef T* decaf::lang::Pointer< T, REFCOUNTER >::PointerType`
- 6.611.2.3** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> typedef T& decaf::lang::Pointer< T, REFCOUNTER >::ReferenceType`

6.611.3 Constructor & Destructor Documentation

- 6.611.3.1** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::Pointer< T, REFCOUNTER >::Pointer () [inline]`

Default Constructor. Initialized the contained pointer to NULL, using the -> operator results in an exception unless reset to contain a real value.

Referenced by `decaf::lang::Pointer< TransactionId >::reset()`.

- 6.611.3.2** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::Pointer< T, REFCOUNTER >::Pointer (const PointerType value) [inline, explicit]`

Explicit Constructor, creates a **Pointer** (p. 2946) that contains value with a single reference. This object now has ownership until a call to release.

Parameters:

value - instance of the type we are containing here.

- 6.611.3.3** `template<typename T, typename REFCOUNTER = decaf::util::concurrent::atomic::AtomicRefCount> decaf::lang::Pointer< T, REFCOUNTER >::Pointer (const Pointer< T, REFCOUNTER > & value) throw () [inline]`

Copy constructor. Copies the value contained in the pointer to the new instance and increments the reference counter.

6.611.3.4 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
T1 , typename R1 > decaf::lang::Pointer< T, REFCOUNTER >::Pointer
(const Pointer< T1, R1 > & value) throw () [inline]`

Copy constructor. Copies the value contained in the pointer to the new instance and increments the reference counter.

6.611.3.5 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
T1 , typename R1 > decaf::lang::Pointer< T, REFCOUNTER >::Pointer
(const Pointer< T1, R1 > & value, const STATIC_CAST_TOKEN &)
throw () [inline]`

Static Cast constructor. Copies the value contained in the pointer to the new instance and increments the reference counter performing a static cast on the value contained in the source **Pointer** (p. 2946) object.

Parameters:

value - **Pointer** (p. 2946) instance to cast to this type.

6.611.3.6 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
T1 , typename R1 > decaf::lang::Pointer< T, REFCOUNTER >::Pointer
(const Pointer< T1, R1 > & value, const DYNAMIC_CAST_TOKEN
&) throw (decaf::lang::exceptions::ClassCastException) [inline]`

Dynamic Cast constructor. Copies the value contained in the pointer to the new instance and increments the reference counter performing a dynamic cast on the value contained in the source **Pointer** (p. 2946) object. If the cast fails and return NULL then this method throws a **ClassCastException**.

Parameters:

value - **Pointer** (p. 2946) instance to cast to this type.

Exceptions:

ClassCastException if the dynamic cast returns NULL

6.611.3.7 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> virtual
decaf::lang::Pointer< T, REFCOUNTER >::~~Pointer () throw ()
[inline, virtual]`

6.611.4 Member Function Documentation

6.611.4.1 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> template<typename
T1 > Pointer<T1, CounterType> decaf::lang::Pointer< T,
REFCOUNTER >::dynamicCast () const [inline]`

6.611.4.2 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> PointerType
decaf::lang::Pointer< T, REFCOUNTER >::get () const [inline]`

Gets the real pointer that is contained within this **Pointer** (p. 2946). This is not really safe since the caller could delete or alter the pointer but it mimics the STL `auto_ptr` and gives access in cases where the caller absolutely needs the real **Pointer** (p. 2946). Use at your own risk.

Returns:

the contained pointer.

Referenced by `activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage >::equals()`, `activemq::state::ConnectionState::getTransactionState()`, `decaf::lang::operator!=()`, `decaf::lang::Pointer< TransactionId >::operator!=()`, `std::less< decaf::lang::Pointer< T > >::operator()()`, `decaf::lang::operator==()`, `decaf::lang::Pointer< TransactionId >::operator==()`, and `activemq::state::ConnectionState::removeTempDestination()`.

6.611.4.3 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> bool
decaf::lang::Pointer< T, REFCOUNTER >::operator! () const [inline]`

6.611.4.4 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> template<typename
T1 , typename R1 > bool decaf::lang::Pointer< T, REFCOUNTER
>::operator!= (const Pointer< T1, R1 > & right) const [inline]`

6.611.4.5 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> ReferenceType
decaf::lang::Pointer< T, REFCOUNTER >::operator* () const [inline]`

6.611.4.6 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> ReferenceType
decaf::lang::Pointer< T, REFCOUNTER >::operator* () [inline]`

Dereference Operator, returns a reference to the Contained value. This method throws an `NullPointerException` if the contained value is `NULL`.

Returns:

reference to the contained pointer.

Exceptions:

NullPointerException if the contained value is Null

6.611.4.7 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> PointerType
decaf::lang::Pointer< T, REFCOUNTER >::operator-> () const [inline]`

6.611.4.8 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> PointerType
decaf::lang::Pointer< T, REFCOUNTER >::operator-> () [inline]`

Indirection Operator, returns a pointer to the Contained value. This method throws an *NullPointerException* if the contained value is NULL.

Returns:

reference to the contained pointer.

Exceptions:

NullPointerException if the contained value is Null

6.611.4.9 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
T1 , typename R1 > Pointer& decaf::lang::Pointer< T, REFCOUNTER
>::operator= (const Pointer< T1, R1 > & right) throw () [inline]`

6.611.4.10 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> Pointer&
decaf::lang::Pointer< T, REFCOUNTER >::operator= (const Pointer<
T, REFCOUNTER > & right) throw () [inline]`

Assigns the value of *right* to this **Pointer** (p. 2946) and increments the reference Count.

Parameters:

right - **Pointer** (p. 2946) on the right hand side of an operator= call to this.

6.611.4.11 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
T1 , typename R1 > bool decaf::lang::Pointer< T, REFCOUNTER
>::operator== (const Pointer< T1, R1 > & right) const [inline]`

6.611.4.12 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCounter> T*
decaf::lang::Pointer< T, REFCOUNTER >::release () [inline]`

Releases the **Pointer** (p. 2946) held and resets the **internal** (p. 144) pointer value to Null. This method is not guaranteed to be safe if the **Pointer** (p. 2946) is held by more than one object or this method is called from more than one thread.

Parameters:

value - The new value to contain.

Returns:

The pointer instance that was held by this **Pointer** (p. 2946) object, the pointer is no longer owned by this **Pointer** (p. 2946) and won't be freed when this **Pointer** (p. 2946) goes out of scope.

Referenced by `decaf::lang::Pointer< TransactionId >::Pointer()`.

```
6.611.4.13  template<typename T, typename REFCOUNTER =
              decaf::util::concurrent::atomic::AtomicRefCounter> void
              decaf::lang::Pointer< T, REFCOUNTER >::reset (T * value)  [inline]
```

Resets the **Pointer** (p. 2946) to hold the new value. Before the new value is stored reset checks if the old value should be destroyed and if so calls delete. Call reset with a value of NULL is supported and acts to set this **Pointer** (p. 2946) to a NULL pointer.

Parameters:

value - The new value to contain.

```
6.611.4.14  template<typename T, typename REFCOUNTER =
              decaf::util::concurrent::atomic::AtomicRefCounter> template<typename
              T1 > Pointer<T1, CounterType> decaf::lang::Pointer< T,
              REFCOUNTER >::staticCast () const  [inline]
```

```
6.611.4.15  template<typename T, typename REFCOUNTER =
              decaf::util::concurrent::atomic::AtomicRefCounter> void
              decaf::lang::Pointer< T, REFCOUNTER >::swap (Pointer< T,
              REFCOUNTER > & value) throw ()  [inline]
```

Exception (p. 1831) Safe Swap Function.

Parameters:

value - the value to swap with this.

Referenced by `decaf::lang::Pointer< TransactionId >::operator=()`, and `decaf::lang::Pointer< TransactionId >::swap()`.

6.611.5 Friends And Related Function Documentation

6.611.5.1 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> bool operator!=
(const T * left, const Pointer< T, REFCOUNTER > & right) [friend]`

6.611.5.2 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> bool operator!=
(const Pointer< T, REFCOUNTER > & left, const T * right) [friend]`

6.611.5.3 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> bool operator==
(const T * left, const Pointer< T, REFCOUNTER > & right) [friend]`

6.611.5.4 `template<typename T, typename REFCOUNTER =
decaf::util::concurrent::atomic::AtomicRefCount> bool operator==
(const Pointer< T, REFCOUNTER > & left, const T * right) [friend]`

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Pointer.h`

6.612 decaf::lang::PointerComparator< T, R > Class Template Reference

This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the Object being Pointed to and not the value of the contained pointer in the **Pointer** (p. 2946) instance.

#include <src/main/decaf/lang/Pointer.h> Inheritance diagram for decaf::lang::PointerComparator< T, R >:

Public Member Functions

- virtual bool **operator()** (const **Pointer**< T, R > &left, const **Pointer**< T, R > &right) const
- virtual int **compare** (const **Pointer**< T, R > &left, const **Pointer**< T, R > &right) const

6.612.1 Detailed Description

template<typename T, typename R = decaf::util::concurrent::atomic::AtomicRefCounter>
class decaf::lang::PointerComparator< T, R >

This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the Object being Pointed to and not the value of the contained pointer in the **Pointer** (p. 2946) instance. This can be useful in the case where a series of values in a Collection is more efficiently accessed in the Objects Natural Order and not the underlying pointers location in memory.

Also this allows **Pointer** (p. 2946) objects that Point to different instances of the same type to be compared based on the comparison of the object itself and not just the value of the pointer.

6.612.2 Member Function Documentation

6.612.2.1 template<typename T , typename R = decaf::util::concurrent::atomic::AtomicRefCounter> virtual
int decaf::lang::PointerComparator< T, R >::compare (const **Pointer**< T, R > & *left*, const **Pointer**< T, R > & *right*) const [inline, virtual]

6.612.2.2 template<typename T , typename R = decaf::util::concurrent::atomic::AtomicRefCounter> virtual
bool decaf::lang::PointerComparator< T, R >::operator() (const **Pointer**< T, R > & *left*, const **Pointer**< T, R > & *right*) const [inline, virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Pointer.h**

6.613 activemq::cmsutil::PooledSession Class Reference

A pooled session object that wraps around a delegate session.

#include <src/main/activemq/cmsutil/PooledSession.h> Inheritance diagram for activemq::cmsutil::PooledSession:

Public Member Functions

- **PooledSession** (SessionPool *pool, cms::Session *session)
- virtual ~**PooledSession** ()
Does nothing.
- virtual cms::Session * **getSession** ()
Returns a non-constant reference to the internal session object.
- virtual const cms::Session * **getSession** () const
Returns a constant reference to the internal session object.
- virtual void **close** () throw (cms::CMSEException)
Returns this session back to the pool, but does not close or destroy the internal session object.
- virtual void **commit** () throw (cms::CMSEException)
Commits all messages done in this transaction and releases any locks currently held.
- virtual void **rollback** () throw (cms::CMSEException)
Rolls back all messages done in this transaction and releases any locks currently held.
- virtual void **recover** () throw (cms::CMSEException)
Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message.
- virtual cms::MessageConsumer * **createConsumer** (const cms::Destination *destination) throw (cms::CMSEException)
Creates a MessageConsumer for the specified destination.
- virtual cms::MessageConsumer * **createConsumer** (const cms::Destination *destination, const std::string &selector) throw (cms::CMSEException)
Creates a MessageConsumer for the specified destination, using a message selector.
- virtual cms::MessageConsumer * **createConsumer** (const cms::Destination *destination, const std::string &selector, bool noLocal) throw (cms::CMSEException)
Creates a MessageConsumer for the specified destination, using a message selector.
- virtual cms::MessageConsumer * **createDurableConsumer** (const cms::Topic *destination, const std::string &name, const std::string &selector, bool noLocal=false) throw (cms::CMSEException)
Creates a durable subscriber to the specified topic, using a Message selector.

- virtual **cms::MessageConsumer** * **createCachedConsumer** (const **cms::Destination** *destination, const std::string &selector, bool noLocal) throw (cms::CMSEException)
First checks the internal consumer cache and creates one if none exist for the given destination, selector, noLocal.
- virtual **cms::MessageProducer** * **createProducer** (const **cms::Destination** *destination) throw (cms::CMSEException)
Creates a MessageProducer to send messages to the specified destination.
- virtual **cms::MessageProducer** * **createCachedProducer** (const **cms::Destination** *destination) throw (cms::CMSEException)
First checks the internal producer cache and creates one if none exist for the given destination.
- virtual **cms::QueueBrowser** * **createBrowser** (const **cms::Queue** *queue) throw (cms::CMSEException)
Creates a new QueueBrowser to peek at Messages on the given Queue.
- virtual **cms::QueueBrowser** * **createBrowser** (const **cms::Queue** *queue, const std::string &selector) throw (cms::CMSEException)
Creates a new QueueBrowser to peek at Messages on the given Queue.
- virtual **cms::Queue** * **createQueue** (const std::string &queueName) throw (cms::CMSEException)
Creates a queue identity given a Queue name.
- virtual **cms::Topic** * **createTopic** (const std::string &topicName) throw (cms::CMSEException)
Creates a topic identity given a Queue name.
- virtual **cms::TemporaryQueue** * **createTemporaryQueue** () throw (cms::CMSEException)
Creates a TemporaryQueue object.
- virtual **cms::TemporaryTopic** * **createTemporaryTopic** () throw (cms::CMSEException)
Creates a TemporaryTopic object.
- virtual **cms::Message** * **createMessage** () throw (cms::CMSEException)
Creates a new Message.
- virtual **cms::BytesMessage** * **createBytesMessage** () throw (cms::CMSEException)
Creates a BytesMessage.
- virtual **cms::BytesMessage** * **createBytesMessage** (const unsigned char *bytes, int bytesSize) throw (cms::CMSEException)
Creates a BytesMessage and sets the payload to the passed value.
- virtual **cms::StreamMessage** * **createStreamMessage** () throw (cms::CMSEException)
Creates a new StreamMessage.

- virtual **cms::TextMessage** * **createTextMessage** () throw (cms::CMSEException)
Creates a new TextMessage.
- virtual **cms::TextMessage** * **createTextMessage** (const std::string &text) throw (cms::CMSEException)
Creates a new TextMessage and set the text to the value given.
- virtual **cms::MapMessage** * **createMapMessage** () throw (cms::CMSEException)
Creates a new MapMessage.
- virtual **cms::Session::AcknowledgeMode** **getAcknowledgeMode** () const throw (cms::CMSEException)
Returns the acknowledgment mode of the session.
- virtual bool **isTransacted** () const throw (cms::CMSEException)
Gets if the Sessions is a Transacted Session.
- virtual void **unsubscribe** (const std::string &name) throw (cms::CMSEException)
Unsubscribes a durable subscription that has been created by a client.

Protected Member Functions

- **PooledSession** (const **PooledSession** &)
- **PooledSession** & **operator=** (const **PooledSession** &)

6.613.1 Detailed Description

A pooled session object that wraps around a delegate session. Calls to close this session only result in giving the session back to the pool.

6.613.2 Constructor & Destructor Documentation

- 6.613.2.1** **activemq::cmsutil::PooledSession::PooledSession** (const **PooledSession** &)
[inline, protected]
- 6.613.2.2** **activemq::cmsutil::PooledSession::PooledSession** (SessionPool * *pool*, cms::Session * *session*)
- 6.613.2.3** **virtual activemq::cmsutil::PooledSession::~~PooledSession** () [virtual]

Does nothing.

6.613.3 Member Function Documentation

- 6.613.3.1** **virtual void activemq::cmsutil::PooledSession::close** () throw (cms::CMSEException) [virtual]

Returns this session back to the pool, but does not close or destroy the internal session object.

Implements **cms::Session** (p. 3368).

6.613.3.2 `virtual void activemq::cmsutil::PooledSession::commit () throw (cms::CMSException) [inline, virtual]`

Commits all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSException - If an internal error occurs.

IllegalStateException - if the method is not called by a transacted session.

Implements **cms::Session** (p. 3369).

References `cms::Session::commit()`.

6.613.3.3 `virtual cms::QueueBrowser* activemq::cmsutil::PooledSession::createBrowser (const cms::Queue * queue, const std::string & selector) throw (cms::CMSException) [virtual]`

Creates a new QueueBrowser to peek at Messages on the given Queue.

Parameters:

queue the Queue to browse

selector the Message selector to filter which messages are browsed.

Returns:

New QueueBrowser that is owned by the caller.

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if the destination given is invalid.

Implements **cms::Session** (p. 3369).

6.613.3.4 `virtual cms::QueueBrowser* activemq::cmsutil::PooledSession::createBrowser (const cms::Queue * queue) throw (cms::CMSException) [virtual]`

Creates a new QueueBrowser to peek at Messages on the given Queue.

Parameters:

queue the Queue to browse

Returns:

New QueueBrowser that is owned by the caller.

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if the destination given is invalid.

Implements **cms::Session** (p. 3369).

6.613.3.5 `virtual cms::BytesMessage* activemq::cmsutil::PooledSession::createBytesMessage (const unsigned char * bytes, int bytesSize) throw (cms::CMSException) [inline, virtual]`

Creates a BytesMessage and sets the payload to the passed value.

Parameters:

bytes an array of bytes to set in the message

bytesSize the size of the bytes array, or number of bytes to use

Exceptions:

CMSException - If an internal error occurs.

Implements **cms::Session** (p. 3370).

6.613.3.6 `virtual cms::BytesMessage* activemq::cmsutil::PooledSession::createBytesMessage () throw (cms::CMSException) [inline, virtual]`

Creates a BytesMessage.

Exceptions:

CMSException - If an internal error occurs.

Implements **cms::Session** (p. 3370).

6.613.3.7 `virtual cms::MessageConsumer* activemq::cmsutil::PooledSession::createCachedConsumer (const cms::Destination * destination, const std::string & selector, bool noLocal) throw (cms::CMSException) [virtual]`

First checks the internal consumer cache and creates one if none exist for the given destination, selector, noLocal. If created, the consumer is added to the pool's lifecycle manager.

Parameters:

destination the destination to receive on

selector the selector to use

noLocal whether or not to receive messages from the same connection

Returns:

the consumer resource

Exceptions:

cms::CMSEException (p. 1160) if something goes wrong.

6.613.3.8 `virtual cms::MessageProducer* activemq::cmsutil::PooledSession::createCachedProducer (const cms::Destination * destination) throw (cms::CMSEException) [virtual]`

First checks the internal producer cache and creates one if none exist for the given destination. If created, the producer is added to the pool's lifecycle manager.

Parameters:

destination the destination to send on

Returns:

the producer resource

Exceptions:

cms::CMSEException (p. 1160) if something goes wrong.

6.613.3.9 `virtual cms::MessageConsumer* activemq::cmsutil::PooledSession::createConsumer (const cms::Destination * destination, const std::string & selector, bool noLocal) throw (cms::CMSEException) [inline, virtual]`

Creates a MessageConsumer for the specified destination, using a message selector.

Parameters:

destination the Destination that this consumer receiving messages for.

selector the Message Selector to use

noLocal if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Returns:

pointer to a new MessageConsumer that is owned by the caller (caller deletes)

Exceptions:

CMSEException - If an internal error occurs.

InvalidDestinationException - if an invalid destination is specified.

InvalidSelectorException - if the message selector is invalid.

Implements **cms::Session** (p. 3370).

6.613.3.10 `virtual cms::MessageConsumer* activemq::cmsutil::PooledSession::createConsumer (const cms::Destination * destination, const std::string & selector) throw (cms::CMSException) [inline, virtual]`

Creates a MessageConsumer for the specified destination, using a message selector.

Parameters:

destination the Destination that this consumer receiving messages for.

selector the Message Selector to use

Returns:

pointer to a new MessageConsumer that is owned by the caller (caller deletes)

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if an invalid destination is specified.

InvalidSelectorException - if the message selector is invalid.

Implements **cms::Session** (p. 3371).

6.613.3.11 `virtual cms::MessageConsumer* activemq::cmsutil::PooledSession::createConsumer (const cms::Destination * destination) throw (cms::CMSException) [inline, virtual]`

Creates a MessageConsumer for the specified destination.

Parameters:

destination the Destination that this consumer receiving messages for.

Returns:

pointer to a new MessageConsumer that is owned by the caller (caller deletes)

Exceptions:

CMSException - If an internal error occurs.

InvalidDestinationException - if an invalid destination is specified.

Implements **cms::Session** (p. 3371).

6.613.3.12 `virtual cms::MessageConsumer* activemq::cmsutil::PooledSession::createDurableConsumer (const cms::Topic * destination, const std::string & name, const std::string & selector, bool noLocal = false) throw (cms::CMSException) [inline, virtual]`

Creates a durable subscriber to the specified topic, using a Message selector. Sessions that create durable consumers must use the same client Id as was used the last time the subscription was created in order to receive all messages that were delivered while the client was offline.

Parameters:

destination the topic to subscribe to
name The name used to identify the subscription
selector the Message Selector to use
noLocal if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Returns:

pointer to a new durable MessageConsumer that is owned by the caller (caller deletes)

Exceptions:

CMSEException - If an internal error occurs.
InvalidDestinationException - if an invalid destination is specified.
InvalidSelectorException - if the message selector is invalid.

Implements **cms::Session** (p. 3372).

6.613.3.13 `virtual cms::MapMessage* activemq::cmsutil::PooledSession::createMapMessage ()
throw (cms::CMSEException) [inline, virtual]`

Creates a new MapMessage.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3372).

6.613.3.14 `virtual cms::Message* activemq::cmsutil::PooledSession::createMessage
() throw (cms::CMSEException) [inline, virtual]`

Creates a new Message.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3372).

6.613.3.15 `virtual cms::MessageProducer* activemq::cmsutil::PooledSession::createProducer (const
cms::Destination * destination) throw (cms::CMSEException) [inline,
virtual]`

Creates a MessageProducer to send messages to the specified destination.

Parameters:

destination the Destination to send on

Returns:

New MessageProducer that is owned by the caller.

Exceptions:

CMSEException - If an internal error occurs.

InvalidDestinationException - if an invalid destination is specified.

Implements **cms::Session** (p. 3373).

6.613.3.16 `virtual cms::Queue* activemq::cmsutil::PooledSession::createQueue
(const std::string & queueName) throw (cms::CMSEException)
[inline, virtual]`

Creates a queue identity given a Queue name.

Parameters:

queueName the name of the new Queue

Returns:

new Queue pointer that is owned by the caller.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3373).

6.613.3.17 `virtual cms::StreamMessage* ac-
tivemq::cmsutil::PooledSession::createStreamMessage ()
throw (cms::CMSEException) [inline, virtual]`

Creates a new StreamMessage.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3373).

6.613.3.18 `virtual cms::TemporaryQueue* ac-
tivemq::cmsutil::PooledSession::createTemporaryQueue ()
throw (cms::CMSEException) [inline, virtual]`

Creates a TemporaryQueue object.

Returns:

new TemporaryQueue pointer that is owned by the caller.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3374).

6.613.3.19 `virtual cms::TemporaryTopic* activemq::cmsutil::PooledSession::createTemporaryTopic () throw (cms::CMSException) [inline, virtual]`

Creates a TemporaryTopic object.

Exceptions:

CMSException - If an internal error occurs.

Implements `cms::Session` (p. 3374).

6.613.3.20 `virtual cms::TextMessage* activemq::cmsutil::PooledSession::createTextMessage (const std::string & text) throw (cms::CMSException) [inline, virtual]`

Creates a new TextMessage and set the text to the value given.

Parameters:

text the initial text for the message

Exceptions:

CMSException - If an internal error occurs.

Implements `cms::Session` (p. 3374).

6.613.3.21 `virtual cms::TextMessage* activemq::cmsutil::PooledSession::createTextMessage () throw (cms::CMSException) [inline, virtual]`

Creates a new TextMessage.

Exceptions:

CMSException - If an internal error occurs.

Implements `cms::Session` (p. 3374).

6.613.3.22 `virtual cms::Topic* activemq::cmsutil::PooledSession::createTopic (const std::string & topicName) throw (cms::CMSException) [inline, virtual]`

Creates a topic identity given a Queue name.

Parameters:

topicName the name of the new Topic

Returns:

new Topic pointer that is owned by the caller.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3375).

6.613.3.23 `virtual cms::Session::AcknowledgeMode activemq::cmsutil::PooledSession::getAcknowledgeMode () const throw (cms::CMSEException) [inline, virtual]`

Returns the acknowledgment mode of the session.

Returns:

the Sessions Acknowledge Mode

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3375).

6.613.3.24 `virtual const cms::Session* activemq::cmsutil::PooledSession::getSession () const [inline, virtual]`

Returns a constant reference to the internal session object.

Returns:

the session object.

6.613.3.25 `virtual cms::Session* activemq::cmsutil::PooledSession::getSession () [inline, virtual]`

Returns a non-constant reference to the internal session object.

Returns:

the session object.

6.613.3.26 `virtual bool activemq::cmsutil::PooledSession::isTransacted () const throw (cms::CMSEException) [inline, virtual]`

Gets if the Sessions is a Transacted Session.

Returns:

transacted true - false.

Exceptions:

CMSEException - If an internal error occurs.

Implements **cms::Session** (p. 3375).

6.613.3.27 `PooledSession& activemq::cmsutil::PooledSession::operator= (const PooledSession &) [inline, protected]`

6.613.3.28 `virtual void activemq::cmsutil::PooledSession::recover () throw (cms::CMSEException) [inline, virtual]`

Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message. All consumers deliver messages in a serial order. Acknowledging a received message automatically acknowledges all messages that have been delivered to the client.

Restarting a session causes it to take the following actions:

- Stop message delivery
- Mark all messages that might have been delivered but not acknowledged as "redelivered"
- Restart the delivery sequence including all unacknowledged messages that had been previously delivered. Redelivered messages do not have to be delivered in exactly their original delivery order.

Exceptions:

CMSEException - if the CMS provider fails to stop and restart message delivery due to some internal error.

IllegalStateException - if the method is called by a transacted session.

Implements `cms::Session` (p. 3376).

6.613.3.29 `virtual void activemq::cmsutil::PooledSession::rollback () throw (cms::CMSEException) [inline, virtual]`

Rolls back all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSEException - If an internal error occurs.

IllegalStateException - if the method is not called by a transacted session.

Implements `cms::Session` (p. 3376).

6.613.3.30 `virtual void activemq::cmsutil::PooledSession::unsubscribe (const std::string & name) throw (cms::CMSEException) [inline, virtual]`

Unsubscribes a durable subscription that has been created by a client. This method deletes the **state** (p. 95) being maintained on behalf of the subscriber by its provider. It is erroneous for a client to delete a durable subscription while there is an active MessageConsumer or Subscriber for the subscription, or while a consumed message is part of a pending transaction or has not been acknowledged in the session.

Parameters:

name The name used to identify this subscription

Exceptions:

CMSException - If an internal error occurs.

Implements **cms::Session** (p. 3376).

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/PooledSession.h`

6.614 decaf::util::concurrent::PooledThread Class Reference

#include <src/main/decaf/util/concurrent/PooledThread.h> Inheritance diagram for decaf::util::concurrent::PooledThread:

Public Member Functions

- **PooledThread** (**ThreadPool** *pool)

Constructor.

- virtual ~**PooledThread** ()
- virtual void **run** ()

*Run Method for this object waits for something to be enqueued on the **ThreadPool** (p. 3777) and then grabs it and calls its run method.*

- virtual void **stop** () throw (lang::Exception)

Stops the Thread, thread will complete its task if currently running one, and then die.

- virtual bool **isBusy** ()

Checks to see if the thread is busy, if busy it means that this thread has taken a task from the ThreadPool's queue and is processing it.

- virtual void **setPooledThreadListener** (**PooledThreadListener** *listener)

*Adds a listener to this **PooledThread** (p. 2968) to be notified when this thread starts and completes a task.*

- virtual **PooledThreadListener** * **getPooledThreadListener** ()

*Removes a listener for this **PooledThread** (p. 2968) to be notified when this thread starts and completes a task.*

6.614.1 Constructor & Destructor Documentation

6.614.1.1 decaf::util::concurrent::PooledThread::PooledThread (**ThreadPool** * pool)

Constructor.

Parameters:

pool the parent **ThreadPool** (p. 3777) object

6.614.1.2 virtual decaf::util::concurrent::PooledThread::~~PooledThread ()
[virtual]

6.614.2 Member Function Documentation

6.614.2.1 virtual PooledThreadListener* decaf::util::concurrent::PooledThread::getPooledThreadListener ()
[inline, virtual]

Removes a listener for this PooledThread (p.2968) to be notified when this thread starts and completes a task.

Returns:

a pointer to this thread's listener or NULL

6.614.2.2 virtual bool decaf::util::concurrent::PooledThread::isBusy () [inline, virtual]

Checks to see if the thread is busy, if busy it means that this thread has taken a task from the ThreadPool's queue and is processing it.

Returns:

true if the Thread is busy

6.614.2.3 virtual void decaf::util::concurrent::PooledThread::run () [virtual]

Run Method for this object waits for something to be enqueued on the **ThreadPool** (p.3777) and then grabs it and calls its run method.

Reimplemented from **decaf::lang::Thread** (p.3771).

6.614.2.4 virtual void decaf::util::concurrent::PooledThread::setPooledThreadListener (PooledThreadListener * *listener*) [inline, virtual]

Adds a listener to this PooledThread (p.2968) to be notified when this thread starts and completes a task.

Parameters:

listener the listener to send notifications to.

6.614.2.5 virtual void decaf::util::concurrent::PooledThread::stop () throw (lang::Exception) [virtual]

Stops the Thread, thread will complete its task if currently running one, and then die. Does not block.

Exceptions:

Exception

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/PooledThread.h`

6.615 decaf::util::concurrent::PooledThreadListener Class Reference

Abstract Listener Interface for users of `ThreadPool` (p. 3777).

#include <src/main/decaf/util/concurrent/PooledThreadListener.h> Inheritance diagram for decaf::util::concurrent::PooledThreadListener:

Public Member Functions

- virtual `~PooledThreadListener ()`
- virtual void `onTaskStarted (PooledThread *thread)=0`
Called by a pooled thread when it is about to begin executing a new task.
- virtual void `onTaskCompleted (PooledThread *thread)=0`
Called by a pooled thread when it has completed a task and is going back to waiting for another task to run.
- virtual void `onTaskException (PooledThread *thread, lang::Exception &ex)=0`
*Called by a pooled thread when it has encountered an exception while running a user task, after receiving this notification the callee should assume that the **PooledThread** (p. 2968) is now no longer running.*

6.615.1 Detailed Description

Abstract Listener Interface for users of `ThreadPool` (p. 3777). The implementor of this class receives events related to the execution and termination of threads running in the **ThreadPool** (p. 3777).

Since:

1.0

6.615.2 Constructor & Destructor Documentation

- 6.615.2.1 virtual
`decaf::util::concurrent::PooledThreadListener::~~PooledThreadListener ()`
[inline, virtual]

6.615.3 Member Function Documentation

- 6.615.3.1 virtual void `decaf::util::concurrent::PooledThreadListener::onTaskCompleted (PooledThread * thread)` [pure virtual]

Called by a pooled thread when it has completed a task and is going back to waiting for another task to run.

Parameters:

thread - Pointer the the Pooled Thread that is making this call.

Implemented in **decaf::util::concurrent::ThreadPool** (p. 3780).

6.615.3.2 virtual void decaf::util::concurrent::PooledThreadListener::onTaskException
(PooledThread * *thread*, lang::Exception & *ex*) [pure virtual]

Called by a pooled thread when it has encountered an exception while running a user task, after receiving this notification the callee should assume that the **PooledThread** (p. 2968) is now no longer running.

Parameters:

thread - Pointer to the Pooled Thread that is making this call

ex - The Exception that occurred.

Implemented in **decaf::util::concurrent::ThreadPool** (p. 3780).

6.615.3.3 virtual void decaf::util::concurrent::PooledThreadListener::onTaskStarted
(PooledThread * *thread*) [pure virtual]

Called by a pooled thread when it is about to begin executing a new task.

Parameters:

thread - Pointer to the Pooled Thread that is making this call

Implemented in **decaf::util::concurrent::ThreadPool** (p. 3781).

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/**PooledThreadListener.h**

6.616 decaf::net::PortUnreachableException Class Reference

#include <src/main/decaf/net/PortUnreachableException.h> Inheritance diagram for decaf::net::PortUnreachableException:

Public Member Functions

- **PortUnreachableException** () throw ()
Default Constructor.
- **PortUnreachableException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **PortUnreachableException** (const **PortUnreachableException** &ex) throw ()
Copy Constructor.
- **PortUnreachableException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **PortUnreachableException** (const std::exception *cause) throw ()
Constructor.
- **PortUnreachableException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **PortUnreachableException** * clone () const
Clones this exception.
- virtual ~**PortUnreachableException** () throw ()

6.616.1 Constructor & Destructor Documentation

6.616.1.1 decaf::net::PortUnreachableException::PortUnreachableException () throw () [inline]

Default Constructor.

6.616.1.2 decaf::net::PortUnreachableException::PortUnreachableException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.616.1.3 decaf::net::PortUnreachableException::PortUnreachableException (const PortUnreachableException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.616.1.4 decaf::net::PortUnreachableException::PortUnreachableException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.616.1.5 decaf::net::PortUnreachableException::PortUnreachableException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.616.1.6 decaf::net::PortUnreachableException::PortUnreachableException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.616.1.7 **virtual**
 decaf::net::PortUnreachableException::~~PortUnreachableException ()
 throw () [inline, virtual]

6.616.2 Member Function Documentation

6.616.2.1 **virtual PortUnreachableException* de-**
 caf::net::PortUnreachableException::clone () const
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::net::SocketException** (p. 3522).

The documentation for this class was generated from the following file:

- src/main/decaf/net/**PortUnreachableException.h**

6.617 activemq::core::PrefetchPolicy Class Reference

Interface for a Policy object that controls message Prefetching on various destination types in ActiveMQ-CPP.

#include <src/main/activemq/core/PrefetchPolicy.h> Inheritance diagram for activemq::core::PrefetchPolicy:

Public Member Functions

- virtual **~PrefetchPolicy** ()
- virtual void **setDurableTopicPrefetch** (int value)=0
Sets the amount of prefetched messages for a Durable Topic.
- virtual int **getDurableTopicPrefetch** () const =0
Gets the amount of messages to prefetch for a Durable Topic.
- virtual void **setQueuePrefetch** (int value)=0
Sets the amount of prefetched messages for a Queue.
- virtual int **getQueuePrefetch** () const =0
Gets the amount of messages to prefetch for a Queue.
- virtual void **setQueueBrowserPrefetch** (int value)=0
Sets the amount of prefetched messages for a Queue Browser.
- virtual int **getQueueBrowserPrefetch** () const =0
Gets the amount of messages to prefetch for a Queue Browser.
- virtual void **setTopicPrefetch** (int value)=0
Sets the amount of prefetched messages for a Topic.
- virtual int **getTopicPrefetch** () const =0
Gets the amount of messages to prefetch for a Topic.
- virtual int **getMaxPrefetchLimit** (int value) const =0
Given a requested value for a new prefetch limit, compare it against some max prefetch value and return either the requested value or the maximum allowable value for prefetch.
- virtual **PrefetchPolicy * clone** () const =0
Clone the Policy and return a new pointer to that clone.
- virtual void **configure** (const **decaf::util::Properties** &properties)
Checks the supplied properties object for properties matching the configurable settings of this class.

Protected Member Functions

- `PrefetchPolicy ()`

6.617.1 Detailed Description

Interface for a Policy object that controls message Prefetching on various destination types in ActiveMQ-CPP.

Since:

3.2.0

6.617.2 Constructor & Destructor Documentation

6.617.2.1 `activemq::core::PrefetchPolicy::PrefetchPolicy ()` [protected]

6.617.2.2 `virtual activemq::core::PrefetchPolicy::~~PrefetchPolicy ()` [virtual]

6.617.3 Member Function Documentation

6.617.3.1 `virtual PrefetchPolicy* activemq::core::PrefetchPolicy::clone () const`
[pure virtual]

Clone the Policy and return a new pointer to that clone.

Returns:

pointer to a new **PrefetchPolicy** (p. 2976) instance that is a clone of this one.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1674).

6.617.3.2 `virtual void activemq::core::PrefetchPolicy::configure (const decaf::util::Properties & properties)` [virtual]

Checks the supplied properties object for properties matching the configurable settings of this class. The default implementation looks for properties named with the prefix `cms.PrefetchPolicy.XXX` where XXX is the name of a property with a public setter method. For instance `cms.PrefetchPolicy.topicPrefetch` will be used to set the value of the topic prefetch limit.

Subclasses can override this method to add more configuration options or to exclude certain parameters from being set via the properties object.

Parameters:

properties The Properties object used to configure this object.

Exceptions:

NumberFormatException if a property that is numeric cannot be converted

IllegalArgumentException if a property can't be converted to the correct type.

6.617.3.3 `virtual int activemq::core::PrefetchPolicy::getDurableTopicPrefetch () const [pure virtual]`

Gets the amount of messages to prefetch for a Durable Topic.

Returns:

value of the number of messages to prefetch.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1674).

6.617.3.4 `virtual int activemq::core::PrefetchPolicy::getMaxPrefetchLimit (int value) const [pure virtual]`

Given a requested value for a new prefetch limit, compare it against some max prefetch value and return either the requested value or the maximum allowable value for prefetch.

Returns:

the allowable value for a prefetch limit, either requested or the max.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1674).

6.617.3.5 `virtual int activemq::core::PrefetchPolicy::getQueueBrowserPrefetch () const [pure virtual]`

Gets the amount of messages to prefetch for a Queue Browser.

Returns:

value of the number of messages to prefetch.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1674).

6.617.3.6 `virtual int activemq::core::PrefetchPolicy::getQueuePrefetch () const [pure virtual]`

Gets the amount of messages to prefetch for a Queue.

Returns:

value of the number of messages to prefetch.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1675).

6.617.3.7 `virtual int activemq::core::PrefetchPolicy::getTopicPrefetch () const [pure virtual]`

Gets the amount of messages to prefetch for a Topic.

Returns:

value of the number of messages to prefetch.

Implemented in `activemq::core::policies::DefaultPrefetchPolicy` (p. 1675).

6.617.3.8 virtual void activemq::core::PrefetchPolicy::setDurableTopicPrefetch (int *value*) [pure virtual]

Sets the amount of prefetched messages for a Durable Topic.

Parameters:

value The number of messages to prefetch.

Implemented in **activemq::core::policies::DefaultPrefetchPolicy** (p. 1675).

6.617.3.9 virtual void activemq::core::PrefetchPolicy::setQueueBrowserPrefetch (int *value*) [pure virtual]

Sets the amount of prefetched messages for a Queue Browser.

Parameters:

value The number of messages to prefetch.

Implemented in **activemq::core::policies::DefaultPrefetchPolicy** (p. 1675).

6.617.3.10 virtual void activemq::core::PrefetchPolicy::setQueuePrefetch (int *value*) [pure virtual]

Sets the amount of prefetched messages for a Queue.

Parameters:

value The number of messages to prefetch.

Implemented in **activemq::core::policies::DefaultPrefetchPolicy** (p. 1676).

6.617.3.11 virtual void activemq::core::PrefetchPolicy::setTopicPrefetch (int *value*) [pure virtual]

Sets the amount of prefetched messages for a Topic.

Parameters:

value The number of messages to prefetch.

Implemented in **activemq::core::policies::DefaultPrefetchPolicy** (p. 1676).

The documentation for this class was generated from the following file:

- src/main/activemq/core/**PrefetchPolicy.h**

6.618 activemq::util::PrimitiveList Class Reference

List of primitives.

#include <src/main/activemq/util/PrimitiveList.h> Inheritance diagram for activemq::util::PrimitiveList:

Public Member Functions

- **PrimitiveList** ()
Default Constructor, creates an Empty list.
- virtual ~**PrimitiveList** ()
- **PrimitiveList** (const **decaf::util::List**< **PrimitiveValueNode** > &src)
Copy Constructor.
- **PrimitiveList** (const **PrimitiveList** &src)
Copy Constructor.
- std::string **toString** () const
Converts the contents into a formatted string that can be output in a Log File or other debugging tool.
- virtual bool **getBool** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Boolean value at the specified index.
- virtual void **setBool** (std::size_t index, bool value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual unsigned char **getByte** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Byte value at the specified index.
- virtual void **setByte** (std::size_t index, unsigned char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual char **getChar** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Character value at the specified index.

- virtual void **setChar** (std::size_t index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual short **getShort** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Short value at the specified index.
- virtual void **setShort** (std::size_t index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual int **getInt** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Integer value at the specified index.
- virtual void **setInt** (std::size_t index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual long long **getLong** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Long value at the specified index.
- virtual void **setLong** (std::size_t index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual float **getFloat** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Float value at the specified index.
- virtual void **setFloat** (std::size_t index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.
- virtual double **getDouble** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)

Gets the Double value at the specified index.

- virtual void **setDouble** (std::size_t index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

- virtual std::string **getString** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)

Gets the String value at the specified index.

- virtual void **setString** (std::size_t index, const std::string &value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

- virtual std::vector< unsigned char > **getByteArray** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException)

Gets the Byte Array value at the specified index.

- virtual void **setByteArray** (std::size_t index, const std::vector< unsigned char > &value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

6.618.1 Detailed Description

List of primitives.

6.618.2 Constructor & Destructor Documentation

6.618.2.1 activemq::util::PrimitiveList::PrimitiveList ()

Default Constructor, creates an Empty list.

6.618.2.2 virtual activemq::util::PrimitiveList::~~PrimitiveList () [virtual]

6.618.2.3 activemq::util::PrimitiveList::PrimitiveList (const decaf::util::List< PrimitiveValueNode > & src)

Copy Constructor.

Parameters:

src - the Decaf List of PrimitiveNodeValues to copy

6.618.2.4 activemq::util::PrimitiveList::PrimitiveList (const PrimitiveList & *src*)

Copy Constructor.

Parameters:

src - the **PrimitiveList** (p. 2980) to copy

6.618.3 Member Function Documentation

6.618.3.1 virtual bool activemq::util::PrimitiveList::getBool (std::size_t *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Boolean value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > **size()** (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.2 virtual unsigned char activemq::util::PrimitiveList::getBytes (std::size_t *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Byte value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > **size()** (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.3 `virtual std::vector<unsigned char> activemq::util::PrimitiveList::getByteArray (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Byte Array value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > `size()` (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.4 `virtual char activemq::util::PrimitiveList::getChar (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Character value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > `size()` (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.5 `virtual double activemq::util::PrimitiveList::getDouble (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Double value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > **size()** (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.6 virtual float activemq::util::PrimitiveList::getFloat (std::size_t *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Float value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > **size()** (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.7 virtual int activemq::util::PrimitiveList::getInt (std::size_t *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Integer value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is > **size()** (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.8 virtual long long activemq::util::PrimitiveList::getLong (std::size_t *index*)
const throw (decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Long value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is $> \text{size}()$ (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.9 virtual short activemq::util::PrimitiveList::getShort (std::size_t *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Short value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is $> \text{size}()$ (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.10 virtual std::string activemq::util::PrimitiveList::getString (std::size_t *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the String value at the specified index.

Parameters:

index - index to get value from

Returns:

value contained at the given index

Exceptions:

IndexOutOfBoundsException if index is $> \text{size}()$ (p. 3601)

UnsupportedOperationException if the type at index is not of the type that this method is to return or can convert to.

6.618.3.11 `virtual void activemq::util::PrimitiveList::setBool (std::size_t index,
bool value) throw (decaf::lang::exceptions::IndexOutOfBoundsException
)` [virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.12 `virtual void activemq::util::PrimitiveList::setByte
(std::size_t index, unsigned char value) throw (
decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.13 `virtual void activemq::util::PrimitiveList::setByteArray (std::size_t
index, const std::vector< unsigned char > & value) throw (
decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.14 `virtual void activemq::util::PrimitiveList::setChar (std::size_t index, char value) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.15 `virtual void activemq::util::PrimitiveList::setDouble (std::size_t index, double value) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.16 `virtual void activemq::util::PrimitiveList::setFloat (std::size_t index, float value) throw (decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]`

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.17 `virtual void activemq::util::PrimitiveList::setInt (std::size_t index, int value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.18 `virtual void activemq::util::PrimitiveList::setLong (std::size_t index, long long value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.19 `virtual void activemq::util::PrimitiveList::setShort (std::size_t index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException)`
[virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if index > size() (p. 3601).

6.618.3.20 `virtual void activemq::util::PrimitiveList::setString
(std::size_t index, const std::string & value) throw (
decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Sets the value at the given index to the new value specified, this method overwrites any data that was previously at the index given, but does not insert a new element if the index is greater than the size of the list.

Parameters:

index - location to set in the list

value - the new value to assign to the element at index

Exceptions:

IndexOutOfBoundsException if `index > size()` (p. 3601).

6.618.3.21 `std::string activemq::util::PrimitiveList::toString () const`

Converts the contents into a formatted string that can be output in a Log File or other debugging tool.

Returns:

formatted String of all elements in the list.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/PrimitiveList.h`

6.619 activemq::util::PrimitiveMap Class Reference

Map of named primitives.

#include <src/main/activemq/util/PrimitiveMap.h> Inheritance diagram for activemq::util::PrimitiveMap:

Public Member Functions

- **PrimitiveMap** ()
Default Constructor, creates an empty map.
- virtual ~**PrimitiveMap** ()
- **PrimitiveMap** (const **decaf::util::Map**< std::string, **PrimitiveValueNode** > &source)
Copy Constructor.
- **PrimitiveMap** (const **PrimitiveMap** &source)
Copy Constructor.
- std::string **toString** () const
Converts the contents into a formatted string that can be output in a Log File or other debugging tool.
- virtual bool **getBool** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Boolean value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.
- virtual void **setBool** (const std::string &key, bool value)
Sets the value at key to the specified type.
- virtual unsigned char **getByte** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Byte value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.
- virtual void **setByte** (const std::string &key, unsigned char value)
Sets the value at key to the specified type.
- virtual char **getChar** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)
Gets the Character value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.
- virtual void **setChar** (const std::string &key, char value)

Sets the value at key to the specified type.

- virtual short **getShort** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, de-
caf::lang::exceptions::UnsupportedOperationException)

Gets the Short value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setShort** (const std::string &key, short value)

Sets the value at key to the specified type.

- virtual int **getInt** (const std::string &key) const throw (de-
caf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)

Gets the Integer value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setInt** (const std::string &key, int value)

Sets the value at key to the specified type.

- virtual long long **getLong** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, de-
caf::lang::exceptions::UnsupportedOperationException)

Gets the Long value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setLong** (const std::string &key, long long value)

Sets the value at key to the specified type.

- virtual float **getFloat** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, de-
caf::lang::exceptions::UnsupportedOperationException)

Gets the Float value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setFloat** (const std::string &key, float value)

Sets the value at key to the specified type.

- virtual double **getDouble** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, de-
caf::lang::exceptions::UnsupportedOperationException)

Gets the Double value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setDouble** (const std::string &key, double value)

Sets the value at key to the specified type.

- virtual std::string **getString** (const std::string &key) const
throw (decaf::lang::exceptions::NoSuchElementException, de-
caf::lang::exceptions::UnsupportedOperationException)

Gets the String value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setString** (const std::string &key, const std::string &value)

Sets the value at key to the specified type.

- virtual std::vector< unsigned char > **getByteArray** (const std::string &key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)

Gets the Byte Array value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

- virtual void **setByteArray** (const std::string &key, const std::vector< unsigned char > &value)

Sets the value at key to the specified type.

6.619.1 Detailed Description

Map of named primitives.

6.619.2 Constructor & Destructor Documentation

6.619.2.1 activemq::util::PrimitiveMap::PrimitiveMap ()

Default Constructor, creates an empty map.

6.619.2.2 virtual activemq::util::PrimitiveMap::~~PrimitiveMap () [virtual]

6.619.2.3 activemq::util::PrimitiveMap::PrimitiveMap (const decaf::util::Map< std::string, PrimitiveValueNode > & source)

Copy Constructor.

Parameters:

source The Decaf Library Map instance whose elements will be copied into this Map.

6.619.2.4 activemq::util::PrimitiveMap::PrimitiveMap (const PrimitiveMap & source)

Copy Constructor.

Parameters:

source The **PrimitiveMap** (p. 2991) whose elements will be copied into this Map.

6.619.3 Member Function Documentation

6.619.3.1 `virtual bool activemq::util::PrimitiveMap::getBool (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Boolean value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.2 `virtual unsigned char activemq::util::PrimitiveMap::getBytes (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Byte value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.3 `virtual std::vector<unsigned char> activemq::util::PrimitiveMap::getBytesArray (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Byte Array value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type `NoSuchElementException` is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at *key* in the type requested.

Exceptions:

NoSuchElementException if *key* is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.4 `virtual char activemq::util::PrimitiveMap::getChar (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Character value at the given *key*, if the *key* is not in the map or cannot be returned as the requested value then an exception of type *NoSuchElementException* is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at *key* in the type requested.

Exceptions:

NoSuchElementException if *key* is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.5 `virtual double activemq::util::PrimitiveMap::getDouble (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Double value at the given *key*, if the *key* is not in the map or cannot be returned as the requested value then an exception of type *NoSuchElementException* is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at *key* in the type requested.

Exceptions:

NoSuchElementException if *key* is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.6 `virtual float activemq::util::PrimitiveMap::getFloat (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Float value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.7 `virtual int activemq::util::PrimitiveMap::getInt (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Integer value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.8 `virtual long long activemq::util::PrimitiveMap::getLong (const std::string & key) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

Gets the Long value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.9 virtual short activemq::util::PrimitiveMap::getShort (const std::string & *key*) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the Short value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.10 virtual std::string activemq::util::PrimitiveMap::getString (const std::string & *key*) const throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Gets the String value at the given key, if the key is not in the map or cannot be returned as the requested value then an exception of type NoSuchElementException is thrown.

Parameters:

key - the location to return the value from.

Returns:

the value at key in the type requested.

Exceptions:

NoSuchElementException if key is not in the map.

UnsupportedOperationException if the value cannot be converted to the type this method returns

6.619.3.11 virtual void activemq::util::PrimitiveMap::setBool (const std::string & *key*, bool *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.12 virtual void activemq::util::PrimitiveMap::setByte (const std::string & *key*, unsigned char *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.13 virtual void activemq::util::PrimitiveMap::setByteArray (const std::string & *key*, const std::vector< unsigned char > & *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.14 virtual void activemq::util::PrimitiveMap::setChar (const std::string & *key*, char *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.15 virtual void activemq::util::PrimitiveMap::setDouble (const std::string & *key*, double *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.16 virtual void activemq::util::PrimitiveMap::setFloat (const std::string & *key*, float *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.17 virtual void activemq::util::PrimitiveMap::setInt (const std::string & *key*, int *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.18 virtual void activemq::util::PrimitiveMap::setLong (const std::string & *key*, long long *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.19 virtual void activemq::util::PrimitiveMap::setShort (const std::string & *key*, short *value*) [virtual]

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.20 `virtual void activemq::util::PrimitiveMap::setString (const std::string & key, const std::string & value) [virtual]`

Sets the value at key to the specified type. Overwrites any data that was previously at this key or inserts a new element at key.

Parameters:

key - the map key to set or insert.

value - the new value to set at the key location.

6.619.3.21 `std::string activemq::util::PrimitiveMap::toString () const`

Converts the contents into a formatted string that can be output in a Log File or other debugging tool.

Returns:

formatted String of all elements in the map.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/PrimitiveMap.h`

6.620 activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller Class Reference

This class wraps the functionality needed to **marshal** (p.107) a primitive map to the Openwire Format's expectation of what the map looks like on the wire.

```
#include <src/main/activemq/wireformat/openwire/marshal/PrimitiveTypesMarshaller.h>
```

Public Member Functions

- **PrimitiveTypesMarshaller** ()
- virtual **~PrimitiveTypesMarshaller** ()

Static Public Member Functions

- static void **marshal** (const **util::PrimitiveMap** *map, std::vector< unsigned char > &buffer) throw (decaf::lang::Exception)
Marshal a primitive map object to the given byte buffer.
- static void **unmarshal** (**util::PrimitiveMap** *map, const std::vector< unsigned char > &buffer) throw (decaf::lang::Exception)
Unmarshal a PrimitiveMap from the provided Byte buffer.
- static void **marshal** (const **util::PrimitiveList** *list, std::vector< unsigned char > &buffer) throw (decaf::lang::Exception)
Marshal a primitive list object to the given byte buffer.
- static void **unmarshal** (**util::PrimitiveList** *list, const std::vector< unsigned char > &buffer) throw (decaf::lang::Exception)
Unmarshal a PrimitiveList from the provided byte buffer.
- static void **marshalMap** (const **util::PrimitiveMap** *map, **decaf::io::DataOutputStream** &dataOut) throw (decaf::lang::Exception)
Marshal a primitive map object to the given DataOutputStream.
- static **util::PrimitiveMap** * **unmarshalMap** (**decaf::io::DataInputStream** &dataIn) throw (decaf::lang::Exception)
Unmarshal a PrimitiveMap from the provided DataInputStream.
- static void **marshalList** (const **util::PrimitiveList** *list, **decaf::io::DataOutputStream** &dataOut) throw (decaf::lang::Exception)
Marshal a PrimitiveList to the given DataOutputStream.
- static **util::PrimitiveList** * **unmarshalList** (**decaf::io::DataInputStream** &dataIn) throw (decaf::lang::Exception)
Unmarshal a PrimitiveList from the given DataInputStream.

Static Protected Member Functions

- static void **marshalPrimitiveMap** (decaf::io::DataOutputStream &dataOut, const decaf::util::Map< std::string, util::PrimitiveValueNode > &map) throw (decaf::io::IOException)

Marshal a Map of Primitives to the given OutputStream, can result in recursive calls to this method if the map contains maps of maps.

- static void **marshalPrimitiveList** (decaf::io::DataOutputStream &dataOut, const decaf::util::List< util::PrimitiveValueNode > &list) throw (decaf::io::IOException)

Marshal a List of Primitives to the given OutputStream, can result in recursive calls to this method if the list contains lists of lists.

- static void **marshalPrimitive** (decaf::io::DataOutputStream &dataOut, const util::PrimitiveValueNode &value) throw (decaf::io::IOException)

Used to Marshal the Primitive types out on the Wire.

- static void **unmarshalPrimitiveMap** (decaf::io::DataInputStream &dataIn, util::PrimitiveMap &map) throw (decaf::io::IOException)

Unmarshals a Map of Primitives from the given InputStream, can result in recursive calls to this method if the map contains maps of maps.

- static void **unmarshalPrimitiveList** (decaf::io::DataInputStream &dataIn, decaf::util::StlList< util::PrimitiveValueNode > &list) throw (decaf::io::IOException)

Unmarshals a List of Primitives from the given InputStream, can result in recursive calls to this method if the list contains lists of lists.

- static util::PrimitiveValueNode **unmarshalPrimitive** (decaf::io::DataInputStream &dataIn) throw (decaf::io::IOException)

Unmarshals a Primitive Type from the stream, and returns it as a value Node.

6.620.1 Detailed Description

This class wraps the functionality needed to **marshal** (p.107) a primitive map to the Openwire Format's expectation of what the map looks like on the wire.

6.620.2 Constructor & Destructor Documentation

6.620.2.1 `activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::PrimitiveTypesMarshaller()` [inline]

6.620.2.2 `virtual activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::~~PrimitiveTypesMarshaller()` [inline, virtual]

6.620.3 Member Function Documentation

6.620.3.1 `static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshal(const util::PrimitiveList * list, std::vector< unsigned char > & buffer) throw (decaf::lang::Exception)` [static]

Marshal a primitive list object to the given byte buffer.

Parameters:

map The PrimitiveList to Marshal.

buffer The byte buffer to write the marshaled data to.

Exceptions:

Exception if an error occurs during the marshaling process.

6.620.3.2 `static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshal(const util::PrimitiveMap * map, std::vector< unsigned char > & buffer) throw (decaf::lang::Exception)` [static]

Marshal a primitive map object to the given byte buffer.

Parameters:

map Map to Marshal.

buffer The byte buffer to write the marshaled data to.

Exceptions:

Exception if an error occurs during the marshaling process.

6.620.3.3 `static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshalList(const util::PrimitiveList * list, decaf::io::DataOutputStream & dataOut) throw (decaf::lang::Exception)` [static]

Marshal a PrimitiveList to the given DataOutputStream.

Parameters:

list The list object to Marshal

dataOut Reference to a DataOutputStream to write the marshaled data to.

Exceptions:

Exception if an error occurs during the marshaling process.

6.620.3.4 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshalMap (const util::PrimitiveMap * *map*, decaf::io::DataOutputStream & *dataOut*) throw (decaf::lang::Exception) [static]

Marshal a primitive map object to the given DataOutputStream.

Parameters:

map Map to Marshal.

dataOut Reference to a DataOutputStream to write the marshaled data to.

Exceptions:

Exception if an error occurs during the marshaling process.

6.620.3.5 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshalPrimitive (decaf::io::DataOutputStream & *dataOut*, const util::PrimitiveValueNode & *value*) throw (decaf::io::IOException) [static, protected]

Used to Marshal the Primitive types out on the Wire.

Parameters:

dataOut - the DataOutputStream to write to

value - the ValueNode to write.

Exceptions:

IOException

6.620.3.6 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshalPrimitiveList (decaf::io::DataOutputStream & *dataOut*, const decaf::util::List< util::PrimitiveValueNode > & *list*) throw (decaf::io::IOException) [static, protected]

Marshal a List of Primitives to the given OutputStream, can result in recursive calls to this method if the list contains lists of lists.

Parameters:

dataOut - the DataOutputStream to write to

list - the ValueNode to write.

Exceptions:

IOException

6.620.3.7 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::marshalPrimitiveMap (decaf::io::DataOutputStream & *dataOut*, const decaf::util::Map< std::string, util::PrimitiveValueNode > & *map*) throw (decaf::io::IOException) [static, protected]

Marshal a Map of Primitives to the given OutputStream, can result in recursive calls to this method if the map contains maps of maps.

Parameters:

dataOut - the DataOutputStream to write to

map - the ValueNode to write.

Exceptions:

IOException

6.620.3.8 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshal (util::PrimitiveList * *list*, const std::vector< unsigned char > & *buffer*) throw (decaf::lang::Exception) [static]

Unmarshal a PrimitiveList from the provided byte buffer.

Parameters:

map The List to populate with values from the marshaled data.

buffer The byte buffer containing the marshaled Map.

Exceptions:

Exception if an error occurs during the unmarshal process.

6.620.3.9 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshal (util::PrimitiveMap * *map*, const std::vector< unsigned char > & *buffer*) throw (decaf::lang::Exception) [static]

Unmarshal a PrimitiveMap from the provided Byte buffer.

Parameters:

map The Map to populate with values from the marshaled data.

buffer The byte buffer containing the marshaled Map.

Exceptions:

Exception if an error occurs during the unmarshal process.

6.620.3.10 `static util::PrimitiveList* activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshalList (decaf::io::DataInputStream & dataIn) throw (decaf::lang::Exception)`
[static]

Unmarshal a PrimitiveList from the given DataInputStream.

Parameters:

dataIn The DataInputStream instance to read the marshaled PrimitiveList from.

Returns:

a pointer to a newly allocated PrimitiveList instnace.

Exceptions:

Exception if an error occurs during the unmarshal process.

6.620.3.11 `static util::PrimitiveMap* activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshalMap (decaf::io::DataInputStream & dataIn) throw (decaf::lang::Exception)`
[static]

Unmarshal a PrimitiveMap from the provided DataInputStream.

Parameters:

dataIn The DataInputStream instance to read the marshaled PrimitiveMap from.

Returns:

a pointer to a newly allocated PrimitiveMap instnace.

Exceptions:

Exception if an error occurs during the unmarshal process.

6.620.3.12 `static util::PrimitiveValueNode activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshalPrimitive (decaf::io::DataInputStream & dataIn) throw (decaf::io::IOException)`
[static, protected]

Unmarshals a Primitive Type from the stream, and returns it as a value Node.

Parameters:

dataIn - DataInputStream to read from.

Returns:

a PrimitiveValueNode containing the data.

Exceptions:

IOException

6.620.3.13 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshalPrimitiveList (decaf::io::DataInputStream & *dataIn*, decaf::util::StlList< util::PrimitiveValueNode > & *list*) throw (decaf::io::IOException) [static, protected]

Unmarshals a List of Primitives from the given InputStream, can result in recursive calls to this method if the list contains lists of lists.

Parameters:

dataIn - DataInputStream to read from.

list - the ValueNode to write.

Exceptions:

IOException

6.620.3.14 static void activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller::unmarshalPrimitiveMap (decaf::io::DataInputStream & *dataIn*, util::PrimitiveMap & *map*) throw (decaf::io::IOException) [static, protected]

Unmarshals a Map of Primitives from the given InputStream, can result in recursive calls to this method if the map contains maps of maps.

Parameters:

dataIn - DataInputStream to read from.

map - the map to fill with data.

Exceptions:

IOException

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/**PrimitiveTypesMarshaller.h**

6.621 activemq::util::PrimitiveValueNode::PrimitiveValue Union Reference

Define a union type comprised of the various types.

```
#include <src/main/activemq/util/PrimitiveValueNode.h>
```

Data Fields

- bool **boolValue**
- unsigned char **byteValue**
- char **charValue**
- short **shortValue**
- int **intValue**
- long long **longValue**
- double **doubleValue**
- float **floatValue**
- std::string * **stringValue**
- std::vector< unsigned char > * **byteArrayValue**
- decaf::util::List< PrimitiveValueNode > * **listValue**
- decaf::util::Map< std::string, PrimitiveValueNode > * **mapValue**

6.621.1 Detailed Description

Define a union type comprised of the various types.

6.621.2 Field Documentation

- 6.621.2.1 `bool` `activemq::util::PrimitiveValueNode::PrimitiveValue::boolValue`
- 6.621.2.2 `std::vector<unsigned char>*` `activemq::util::PrimitiveValueNode::PrimitiveValue::byteArrayValue`
- 6.621.2.3 `unsigned char` `activemq::util::PrimitiveValueNode::PrimitiveValue::byteValue`
- 6.621.2.4 `char` `activemq::util::PrimitiveValueNode::PrimitiveValue::charValue`
- 6.621.2.5 `double` `activemq::util::PrimitiveValueNode::PrimitiveValue::doubleValue`
- 6.621.2.6 `float` `activemq::util::PrimitiveValueNode::PrimitiveValue::floatValue`
- 6.621.2.7 `int` `activemq::util::PrimitiveValueNode::PrimitiveValue::intValue`
- 6.621.2.8 `decaf::util::List<PrimitiveValueNode>*` `activemq::util::PrimitiveValueNode::PrimitiveValue::listValue`
- 6.621.2.9 `long long` `activemq::util::PrimitiveValueNode::PrimitiveValue::longValue`
- 6.621.2.10 `decaf::util::Map<std::string, PrimitiveValueNode>*`
`activemq::util::PrimitiveValueNode::PrimitiveValue::mapValue`
- 6.621.2.11 `short` `activemq::util::PrimitiveValueNode::PrimitiveValue::shortValue`
- 6.621.2.12 `std::string*` `activemq::util::PrimitiveValueNode::PrimitiveValue::stringValue`

The documentation for this union was generated from the following file:

- `src/main/activemq/util/PrimitiveValueNode.h`

6.622 activemq::util::PrimitiveValueConverter Class Reference

Class controls the conversion of data contained in a **PrimitiveValueNode** (p.3012) from one type to another.

```
#include <src/main/activemq/util/PrimitiveValueConverter.h>
```

Public Member Functions

- **PrimitiveValueConverter** ()
- virtual **~PrimitiveValueConverter** ()
- template<typename TO >
TO **convert** (const **PrimitiveValueNode** &value) const throw (decaf::lang::exceptions::UnsupportedOperationException)

6.622.1 Detailed Description

Class controls the conversion of data contained in a **PrimitiveValueNode** (p.3012) from one type to another. If the conversion is supported then calling the convert method will throw an UnsupportedOperationException to indicate that its not possible to perform the conversion.

This class is used to implement the rules of conversion on CMS Message properties, the following conversion table must be implemented. A value written as the row type can be read in the column type.

	boolean	byte	short	int	long	float	double	String
boolean	X X							
byte		X X X X X						
short			X X X X					
int				X X X X				
long					X X			
float						X X X		
double							X X X	
String								X X X X X X X

Since:

3.0

6.622.2 Constructor & Destructor Documentation

6.622.2.1 **activemq::util::PrimitiveValueConverter::PrimitiveValueConverter** ()
[inline]

6.622.2.2 **virtual**
activemq::util::PrimitiveValueConverter::~~PrimitiveValueConverter ()
[inline, virtual]

6.622.3 Member Function Documentation

6.622.3.1 **std::vector< unsigned char > activemq::util::PrimitiveValueConverter::convert** (const **PrimitiveValueNode** & *value*) const throw (decaf::lang::exceptions::UnsupportedOperationException)
[inline]

The documentation for this class was generated from the following file:

- `src/main/activemq/util/PrimitiveValueConverter.h`

6.623 activemq::util::PrimitiveValueNode Class Reference

Class that wraps around a single value of one of the many types.

```
#include <src/main/activemq/util/PrimitiveValueNode.h>
```

Data Structures

- union **PrimitiveValue**

Define a union type comprised of the various types.

Public Types

- enum **PrimitiveType** {
 NULL_TYPE = 0, **BOOLEAN_TYPE** = 1, **BYTE_TYPE** = 2, **CHAR_TYPE** = 3,
 SHORT_TYPE = 4, **INTEGER_TYPE** = 5, **LONG_TYPE** = 6, **DOUBLE_TYPE** = 7,
 FLOAT_TYPE = 8, **STRING_TYPE** = 9, **BYTE_ARRAY_TYPE** = 10, **MAP_TYPE** = 11,
 LIST_TYPE = 12, **BIG_STRING_TYPE** = 13 }

Enumeration for the various primitive types.

Public Member Functions

- **PrimitiveValueNode** ()
Default Constructor, creates a value of the NULL_TYPE.
- **PrimitiveValueNode** (bool value)
Boolean Value Constructor.
- **PrimitiveValueNode** (unsigned char value)
Byte Value Constructor.
- **PrimitiveValueNode** (char value)
Char Value Constructor.
- **PrimitiveValueNode** (short value)
Short Value Constructor.
- **PrimitiveValueNode** (int value)
Int Value Constructor.
- **PrimitiveValueNode** (long long value)
Long Value Constructor.
- **PrimitiveValueNode** (float value)

Float Value Constructor.

- **PrimitiveValueNode** (double value)
Double Value Constructor.
- **PrimitiveValueNode** (const char *value)
String Value Constructor.
- **PrimitiveValueNode** (const std::string &value)
String Value Constructor.
- **PrimitiveValueNode** (const std::vector< unsigned char > &value)
Byte Array Value Constructor.
- **PrimitiveValueNode** (const decaf::util::List< PrimitiveValueNode > &value)
Primitive List Constructor.
- **PrimitiveValueNode** (const decaf::util::Map< std::string, PrimitiveValueNode > &value)
Primitive Map Value Constructor.
- **PrimitiveValueNode** (const PrimitiveValueNode &node)
Copy constructor.
- **~PrimitiveValueNode** ()
- **PrimitiveValueNode & operator=** (const PrimitiveValueNode &node)
Assignment operator, copies the data from the other node.
- **bool operator==** (const PrimitiveValueNode &node) const
Comparison Operator, compares this node to the other node.
- **PrimitiveType getType** () const
Gets the Value Type of this type wrapper.
- **PrimitiveValue getValue** () const
Gets the internal Primitive Value object from this wrapper.
- **void setValue** (const PrimitiveValue &value, PrimitiveType valueType)
Sets the internal PrimitiveVale object to the new value along with the tag for the type that it consists of.
- **void clear** ()
Clears the value from this wrapper converting it back to a blank NULL_ TYPE value.
- **void setBool** (bool value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- **bool getBool** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Boolean value of this Node.

- void **setByte** (unsigned char value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- unsigned char **getByte** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Byte value of this Node.
- void **setChar** (char value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- char **getChar** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Character value of this Node.
- void **setShort** (short value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- short **getShort** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Short value of this Node.
- void **setInt** (int value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- int **getInt** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Integer value of this Node.
- void **setLong** (long long value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- long long **getLong** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Long value of this Node.
- void **setFloat** (float value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- float **getFloat** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Float value of this Node.
- void **setDouble** (double value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- double **getDouble** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Double value of this Node.

- void **setString** (const std::string &value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- std::string **getString** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the String value of this Node.
- void **setByteArray** (const std::vector< unsigned char > &value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- std::vector< unsigned char > **getByteArray** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Byte Array value of this Node.
- void **setList** (const decaf::util::List< PrimitiveValueNode > &value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- const decaf::util::List< PrimitiveValueNode > & **getList** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Primitive List value of this Node.
- void **setMap** (const decaf::util::Map< std::string, PrimitiveValueNode > &value)
Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.
- const decaf::util::Map< std::string, PrimitiveValueNode > & **getMap** () const throw (decaf::lang::exceptions::NoSuchElementException)
Gets the Primitive Map value of this Node.
- std::string **toString** () const
Creates a string representation of this value.

6.623.1 Detailed Description

Class that wraps around a single value of one of the many types. Manages memory for complex types, such as strings. Note: the destructor was left non-virtual so no virtual table will be created. This probably isn't necessary, but will avoid needless memory allocation. Since we'll never extend this class, not having a virtual destructor isn't a concern.

6.623.2 Member Enumeration Documentation

6.623.2.1 enum activemq::util::PrimitiveValueNode::PrimitiveType

Enumeration for the various primitive types.

Enumerator:

NULL_ **TYPE**

BOOLEAN_TYPE
BYTE_TYPE
CHAR_TYPE
SHORT_TYPE
INTEGER_TYPE
LONG_TYPE
DOUBLE_TYPE
FLOAT_TYPE
STRING_TYPE
BYTE_ARRAY_TYPE
MAP_TYPE
LIST_TYPE
BIG_STRING_TYPE

6.623.3 Constructor & Destructor Documentation

6.623.3.1 `activemq::util::PrimitiveValueNode::PrimitiveValueNode ()`

Default Constructor, creates a value of the `NULL_TYPE`.

6.623.3.2 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (bool value)`

Boolean Value Constructor.

Parameters:

value - the new value to store.

6.623.3.3 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (unsigned char value)`

Byte Value Constructor.

Parameters:

value - the new value to store.

6.623.3.4 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (char value)`

Char Value Constructor.

Parameters:

value - the new value to store.

6.623.3.5 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (short value)`

Short Value Constructor.

Parameters:

value - the new value to store.

6.623.3.6 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (int value)`

Int Value Constructor.

Parameters:

value - the new value to store.

6.623.3.7 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (long long value)`

Long Value Constructor.

Parameters:

value - the new value to store.

6.623.3.8 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (float value)`

Float Value Constructor.

Parameters:

value - the new value to store.

6.623.3.9 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (double value)`

Double Value Constructor.

Parameters:

value - the new value to store.

6.623.3.10 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const char * value)`

String Value Constructor.

Parameters:

value - the new value to store.

6.623.3.11 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const std::string & value)`

String Value Constructor.

Parameters:

value - the new value to store.

6.623.3.12 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const std::vector< unsigned char > & value)`

Byte Array Value Constructor.

Parameters:

value - the new value to store.

6.623.3.13 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const decaf::util::List< PrimitiveValueNode > & value)`

Primitive List Constructor.

Parameters:

value - the new value to store.

6.623.3.14 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const decaf::util::Map< std::string, PrimitiveValueNode > & value)`

Primitive Map Value Constructor.

Parameters:

value - the new value to store.

6.623.3.15 `activemq::util::PrimitiveValueNode::PrimitiveValueNode (const PrimitiveValueNode & node)`

Copy constructor.

Parameters:

node The instance of another node to copy to this one.

6.623.3.16 `activemq::util::PrimitiveValueNode::~~PrimitiveValueNode () [inline]`

6.623.4 Member Function Documentation

6.623.4.1 `void activemq::util::PrimitiveValueNode::clear ()`

Clears the value from this wrapper converting it back to a blank NULL_TYPE value.

6.623.4.2 `bool activemq::util::PrimitiveValueNode::getBool () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Boolean value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.3 `unsigned char activemq::util::PrimitiveValueNode::getBytes () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Byte value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.4 `std::vector<unsigned char> activemq::util::PrimitiveValueNode::getBytesArray () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Byte Array value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.5 `char activemq::util::PrimitiveValueNode::getChar () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Character value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.6 double activemq::util::PrimitiveValueNode::getDouble () const throw (decaf::lang::exceptions::NoSuchElementException)

Gets the Double value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.7 float activemq::util::PrimitiveValueNode::getFloat () const throw (decaf::lang::exceptions::NoSuchElementException)

Gets the Float value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.8 int activemq::util::PrimitiveValueNode::getInt () const throw (decaf::lang::exceptions::NoSuchElementException)

Gets the Integer value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.9 const decaf::util::List<PrimitiveValueNode>& activemq::util::PrimitiveValueNode::getList () const throw (decaf::lang::exceptions::NoSuchElementException)

Gets the Primitive List value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.10 `long long activemq::util::PrimitiveValueNode::getLong () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Long value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.11 `const decaf::util::Map<std::string, PrimitiveValueNode>& activemq::util::PrimitiveValueNode::getMap () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Primitive Map value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.12 `short activemq::util::PrimitiveValueNode::getShort () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the Short value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.13 `std::string activemq::util::PrimitiveValueNode::getString () const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets the String value of this Node.

Returns:

value contained at the given index

Exceptions:

NoSuchElementException this node cannot be returned as the requested type.

6.623.4.14 PrimitiveType activemq::util::PrimitiveValueNode::getType () const
[inline]

Gets the Value Type of this type wrapper.

Returns:

the PrimitiveType value for this wrapper.

6.623.4.15 PrimitiveValue activemq::util::PrimitiveValueNode::getValue () const
[inline]

Gets the internal Primitive Value object from this wrapper.

Returns:

a copy of the contained **PrimitiveValue** (p. 3008)

6.623.4.16 PrimitiveValueNode& activemq::util::PrimitiveValueNode::operator=
(const PrimitiveValueNode & node)

Assignment operator, copies the data from the other node.

Parameters:

node The instance of another node to copy to this one.

6.623.4.17 bool activemq::util::PrimitiveValueNode::operator== (const
PrimitiveValueNode & node) const

Comparison Operator, compares this node to the other node.

Returns:

true if the values are the same false otherwise.

6.623.4.18 void activemq::util::PrimitiveValueNode::setBool (bool value)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.19 void activemq::util::PrimitiveValueNode::setByte (unsigned char value)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.20 void activemq::util::PrimitiveValueNode::setByteArray (const std::vector< unsigned char > & *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.21 void activemq::util::PrimitiveValueNode::setChar (char *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.22 void activemq::util::PrimitiveValueNode::setDouble (double *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.23 void activemq::util::PrimitiveValueNode::setFloat (float *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.24 void activemq::util::PrimitiveValueNode::setInt (int *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.25 void activemq::util::PrimitiveValueNode::setList (const decaf::util::List< PrimitiveValueNode > & *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.26 void activemq::util::PrimitiveValueNode::setLong (long long *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.27 void activemq::util::PrimitiveValueNode::setMap (const decaf::util::Map< std::string, PrimitiveValueNode > & *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.28 void activemq::util::PrimitiveValueNode::setShort (short *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.29 void activemq::util::PrimitiveValueNode::setString (const std::string & *value*)

Sets the value of this value node to the new value specified, this method overwrites any data that was previously at the index given.

Parameters:

value - the new value to assign to the element at index

6.623.4.30 void activemq::util::PrimitiveValueNode::setValue (const PrimitiveValue & *value*, PrimitiveType *valueType*)

Sets the internal PrimitiveVale object to the new value along with the tag for the type that it consists of.

Parameters:

value The value to set as the value contained in this Node.

valueType The type of the value being set into this one.

6.623.4.31 `std::string activemq::util::PrimitiveValueNode::toString () const`

Creates a string representation of this value.

Returns:

string value of this type wrapper.

The documentation for this class was generated from the following file:

- `src/main/activemq/util/PrimitiveValueNode.h`

6.624 decaf::security::Principal Class Reference

Base interface for a principal, which can represent an individual or organization.

```
#include <src/main/decaf/security/Principal.h>Inheritance    diagram    for    de-  
caf::security::Principal:
```

Public Member Functions

- virtual **~Principal** ()
- virtual bool **equals** (const **Principal** &another) const =0
Compares two principals to see if they are the same.
- virtual std::string **getName** () const =0
Provides the name of this principal.

6.624.1 Detailed Description

Base interface for a principal, which can represent an individual or organization.

6.624.2 Constructor & Destructor Documentation

6.624.2.1 virtual decaf::security::Principal::~~Principal () [inline, virtual]

6.624.3 Member Function Documentation

6.624.3.1 virtual bool decaf::security::Principal::equals (const **Principal** & *another*) const [pure virtual]

Compares two principals to see if they are the same.

Parameters:

another A principal to be tested for equality to this one.

Returns:

true if the given principal is equivalent to this one.

6.624.3.2 virtual std::string decaf::security::Principal::getName () const [pure virtual]

Provides the name of this principal.

Returns:

the name of this principal.

Implemented in **decaf::security::auth::x500::X500Principal** (p. 4027).

The documentation for this class was generated from the following file:

- src/main/decaf/security/**Principal.h**

6.625 decaf::util::PriorityQueue< E > Class Template Reference

An unbounded priority queue based on a binary heap algorithm.

#include <src/main/decaf/util/PriorityQueue.h> Inheritance diagram for decaf::util::PriorityQueue< E >:

Data Structures

- class **ConstPriorityQueueIterator**
- class **PriorityQueueIterator**

Public Member Functions

- **PriorityQueue** ()
*Creates a **Priority Queue** (p. 3149) with the default initial capacity.*
- **PriorityQueue** (std::size_t initialCapacity)
*Creates a **Priority Queue** (p. 3149) with the capacity value supplied.*
- **PriorityQueue** (std::size_t initialCapacity, **Comparator**< E > *comparator)
*Creates a **Priority Queue** (p. 3149) with the default initial capacity.*
- **PriorityQueue** (const **Collection**< E > &source)
*Creates a **PriorityQueue** (p. 3028) containing the elements in the specified **Collection** (p. 1184).*
- **PriorityQueue** (const **PriorityQueue**< E > &source)
*Creates a **PriorityQueue** (p. 3028) containing the elements in the specified priority queue.*
- virtual ~**PriorityQueue** ()
- **PriorityQueue**< E > & **operator=** (const **Collection**< E > &source)
*Assignment operator, assign another **Collection** (p. 1184) to this one.*
- **PriorityQueue**< E > & **operator=** (const **PriorityQueue**< E > &source)
*Assignment operator, assign another **PriorityQueue** (p. 3028) to this one.*
- virtual **decaf::util::Iterator**< E > * **iterator** ()
- virtual **decaf::util::Iterator**< E > * **iterator** () const
- virtual std::size_t **size** () const
Returns the number of elements in this collection.
- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)
Removes all elements of the queue.
- virtual bool **offer** (const E &value) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)

Inserts the specified element into the queue provided that the condition allows such an operation.

- virtual bool **poll** (E &result)
Gets and removes the element in the head of the queue.
- virtual bool **peek** (E &result) const
Gets but not removes the element in the head of the queue.
- virtual E **remove** () throw (decaf::lang::exceptions::NoSuchElementException)
Retrieves and removes the head of this queue.
- virtual bool **remove** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
Removes a single instance of the specified element from this collection, if it is present (optional operation).
- virtual bool **add** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)
Inserts the specified element into this queue if it is possible to do so immediately without violating capacity restrictions, returning true upon success and throwing an IllegalStateException if no space is currently available.
- decaf::lang::Pointer< Comparator< E > > **comparator** () const
*obtains a Copy of the Pointer instance that this **PriorityQueue** (p. 3028) is using to compare the elements in the queue with.*

Friends

- class **PriorityQueueIterator**

6.625.1 Detailed Description

template<typename E> class decaf::util::PriorityQueue< E >

An unbounded priority queue based on a binary heap algorithm. The elements of the priority queue are ordered according to their natural ordering, or by a **Comparator** (p. 1217) provided to one of the constructors that accepts Comparators. A priority queue relying on natural ordering also does not permit insertion of non-comparable objects (doing so may result in a compiler error).

The head of this queue is the least element with respect to the specified ordering. If multiple elements are tied for least value, the head is one of those elements -- ties are broken arbitrarily. The queue retrieval operations poll, remove, peek, and element access the element at the head of the queue.

A priority queue is unbounded, but has an **internal** (p. 144) capacity governing the size of an array used to store the elements on the queue. It is always at least as large as the queue size. As elements are added to a priority queue, its capacity grows automatically. The details of the growth policy are not specified.

This class and its iterator implement all of the optional methods of the **Collection** (p. 1184) and **Iterator** (p. 2154) interfaces. The **Iterator** (p. 2154) provided in method **iterator()** (p. 3032) is

not guaranteed to traverse the elements of the priority queue in any particular order. If you need ordered traversal, consider using `Arrays::sort(pq.toArray())`.

Note that this implementation is not synchronized. Multiple threads should not access a **PriorityQueue** (p. 3028) instance concurrently if any of the threads modifies the queue. Instead, use the thread-safe `PriorityBlockingQueue` class.

Implementation note: this implementation provides $O(\log(n))$ time for the enqueueing and dequeuing methods (`offer`, `poll`, **`remove()`** (p. 3034) and `add`); linear time for the `remove(Object)` and `contains(Object)` methods; and constant time for the retrieval methods (`peek`, `element`, and `size`).

Since:

1.0

6.625.2 Constructor & Destructor Documentation

6.625.2.1 `template<typename E> decaf::util::PriorityQueue< E >::PriorityQueue
() [inline]`

Creates a **Priority Queue** (p. 3149) with the default initial capacity.

6.625.2.2 `template<typename E> decaf::util::PriorityQueue< E >::PriorityQueue
(std::size_t initialCapacity) [inline]`

Creates a **Priority Queue** (p. 3149) with the capacity value supplied.

Parameters:

initialCapacity The initial number of elements allocated to this **PriorityQueue** (p. 3028).

6.625.2.3 `template<typename E> decaf::util::PriorityQueue< E >::PriorityQueue
(std::size_t initialCapacity, Comparator< E > * comparator) [inline]`

Creates a **Priority Queue** (p. 3149) with the default initial capacity. This new **PriorityQueue** (p. 3028) takes ownership of the passed **Comparator** (p. 1217) instance and uses that to determine the ordering of the elements in the **Queue** (p. 3149).

Parameters:

initialCapacity The initial number of elements allocated to this **PriorityQueue** (p. 3028).

comparator The **Comparator** (p. 1217) instance to use in sorting the elements in the **Queue** (p. 3149).

Exceptions:

NullPointerException if the passed **Comparator** (p. 1217) is NULL.

6.625.2.4 `template<typename E> decaf::util::PriorityQueue< E >::PriorityQueue
(const Collection< E > & source) [inline]`

Creates a **PriorityQueue** (p. 3028) containing the elements in the specified **Collection** (p. 1184).

Parameters:

source the **Collection** (p. 1184) whose elements are to be placed into this priority queue

6.625.2.5 `template<typename E> decaf::util::PriorityQueue< E >::PriorityQueue (const PriorityQueue< E > & source) [inline]`

Creates a **PriorityQueue** (p. 3028) containing the elements in the specified priority queue. This priority queue will be ordered according to the same ordering as the given priority queue.

Parameters:

source the priority queue whose elements are to be placed into this priority queue

6.625.2.6 `template<typename E> virtual decaf::util::PriorityQueue< E >::~~PriorityQueue () [inline, virtual]`

6.625.3 Member Function Documentation

6.625.3.1 `template<typename E> virtual bool decaf::util::PriorityQueue< E >::add (const E & value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException) [inline, virtual]`

Inserts the specified element into this queue if it is possible to do so immediately without violating capacity restrictions, returning true upon success and throwing an `IllegalStateException` if no space is currently available. This implementation returns true if offer succeeds, else throws an `IllegalStateException`.

Parameters:

value - the element to offer to the **Queue** (p. 3149).

Returns:

true if the add succeeds.

Exceptions:

IllegalArgumentException if the element cannot be added.

Reimplemented from `decaf::util::AbstractQueue< E >` (p. 195).

References `DECAF_CATCH_EXCEPTION_CONVERT`, `DECAF_CATCH_RETHROW`, `DECAF_CATCHALL_THROW`, and `decaf::util::PriorityQueue< E >::offer()`.

6.625.3.2 `template<typename E> virtual void decaf::util::PriorityQueue< E >::clear () throw (lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Removes all elements of the queue. This implementation repeatedly invokes `poll` until it returns the empty marker.

Reimplemented from `decaf::util::AbstractQueue< E >` (p. 196).

6.625.3.3 `template<typename E> decaf::lang::Pointer< Comparator<E> >
decaf::util::PriorityQueue< E >::comparator () const [inline]`

obtains a Copy of the Pointer instance that this **PriorityQueue** (p.3028) is using to compare the elements in the queue with. The returned value is a copy, the caller cannot change the value if the **internal** (p.144) Pointer value.

Returns:

a copy of the **Comparator** (p.1217) Pointer being used by this **Queue** (p.3149).

6.625.3.4 `template<typename E> virtual decaf::util::Iterator<E>*
decaf::util::PriorityQueue< E >::iterator () const [inline, virtual]`

Implements **decaf::lang::Iterable< E >** (p.2152).

6.625.3.5 `template<typename E> virtual decaf::util::Iterator<E>*
decaf::util::PriorityQueue< E >::iterator () [inline, virtual]`

Returns:

an iterator over a set of elements of type T.

Implements **decaf::lang::Iterable< E >** (p.2152).

References **decaf::util::PriorityQueue< E >::PriorityQueueIterator**.

6.625.3.6 `template<typename E> virtual bool decaf::util::PriorityQueue< E >::offer
(const E & value) throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException) [inline, virtual]`

Inserts the specified element into the queue provided that the condition allows such an operation. The method is generally preferable to the `collection.add(E)`, since the latter might throw an exception if the operation fails.

Parameters:

value the specified element to insert into the queue.

Returns:

true if the operation succeeds and false if it fails.

Exceptions:

NullPointerException if the **Queue** (p.3149) implementation does not allow Null values to be inserted into the **Queue** (p.3149).

IllegalArgumentException if some property of the specified element prevents it from being added to this queue

Implements **decaf::util::Queue< E >** (p.3150).

Referenced by **decaf::util::PriorityQueue< E >::add()**.

6.625.3.7 `template<typename E> PriorityQueue<E>& decaf::util::PriorityQueue<E>::operator= (const PriorityQueue< E > & source) [inline]`

Assignment operator, assign another **PriorityQueue** (p. 3028) to this one.

Parameters:

source The **PriorityQueue** (p. 3028) to copy to this one.

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 187).

6.625.3.8 `template<typename E> PriorityQueue<E>& decaf::util::PriorityQueue<E>::operator= (const Collection< E > & source) [inline]`

Assignment operator, assign another **Collection** (p. 1184) to this one.

Parameters:

source The **Collection** (p. 1184) to copy to this one.

6.625.3.9 `template<typename E> virtual bool decaf::util::PriorityQueue< E>::peek (E & result) const [inline, virtual]`

Gets but not removes the element in the head of the queue. The result if successful is assigned to the result parameter.

Parameters:

result Reference to an instance of the contained type to assigned the removed value to.

Returns:

true if the element at the head of the queue was removed and assigned to the result parameter.

Implements **decaf::util::Queue< E >** (p. 3151).

6.625.3.10 `template<typename E> virtual bool decaf::util::PriorityQueue< E>::poll (E & result) [inline, virtual]`

Gets and removes the element in the head of the queue. If the operation succeeds the value of the element at the head of the **Queue** (p. 3149) is assigned to the result parameter and the method returns true. If the operation fails the method returns false and the value of the result parameter is undefined.

Parameters:

result Reference to an instance of the contained type to assigned the removed value to.

Returns:

true if the element at the head of the queue was removed and assigned to the result parameter.

Implements **decaf::util::Queue< E >** (p. 3151).

6.625.3.11 `template<typename E> virtual bool decaf::util::PriorityQueue<E >::remove (const E & value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException) [inline, virtual]`

Removes a single instance of the specified element from this collection, if it is present (optional operation). More formally, removes the first element *e* such that *e* == *o*, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection.

IllegalArgumentException If the value is not a valid entry for this **Collection** (p.1184).

Reimplemented from `decaf::util::AbstractCollection< E >` (p.187).

6.625.3.12 `template<typename E> virtual E decaf::util::PriorityQueue< E >::remove () throw (decaf::lang::exceptions::NoSuchElementException) [inline, virtual]`

Retrieves and removes the head of this queue. This method differs from poll only in that it throws an exception if this queue is empty.

This implementation returns the result of poll unless the queue is empty.

Returns:

a copy of the element in the head of the queue.

Exceptions:

NoSuchElementException if the queue is empty.

Reimplemented from `decaf::util::AbstractQueue< E >` (p.196).

6.625.3.13 `template<typename E> virtual std::size_t decaf::util::PriorityQueue< E >::size () const [inline, virtual]`

Returns the number of elements in this collection. If this collection contains more than `Integer.MAX_VALUE` elements, returns `Integer.MAX_VALUE`.

Returns:

the number of elements in this collection

Implements **decaf::util::Collection< E >** (p. 1192).

6.625.4 Friends And Related Function Documentation**6.625.4.1 template<typename E> friend class PriorityQueueIterator [friend]**

Referenced by decaf::util::PriorityQueue< E >::iterator().

The documentation for this class was generated from the following file:

- src/main/decaf/util/**PriorityQueue.h**

6.626 activemq::commands::ProducerAck Class Reference

#include <src/main/activemq/commands/ProducerAck.h> Inheritance diagram for activemq::commands::ProducerAck:

Public Member Functions

- **ProducerAck** ()
- virtual **~ProducerAck** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ProducerAck * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ProducerId** > & **getProducerId** () const
- virtual **Pointer**< **ProducerId** > & **getProducerId** ()
- virtual void **setProducerId** (const **Pointer**< **ProducerId** > &producerId)
- virtual int **getSize** () const
- virtual void **setSize** (int size)
- virtual bool **isProducerAck** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_PRODUCERACK** = 19

Protected Attributes

- **Pointer**< **ProducerId** > producerId
- int size

6.626.1 Constructor & Destructor Documentation

6.626.1.1 `activemq::commands::ProducerAck::ProducerAck ()`

6.626.1.2 `virtual activemq::commands::ProducerAck::~~ProducerAck ()` [virtual]

6.626.2 Member Function Documentation

6.626.2.1 `virtual ProducerAck* activemq::commands::ProducerAck::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.626.2.2 `virtual void activemq::commands::ProducerAck::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.626.2.3 `virtual bool activemq::commands::ProducerAck::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.626.2.4 `virtual unsigned char activemq::commands::ProducerAck::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

- 6.626.2.5** `virtual Pointer<ProducerId>& activemq::commands::ProducerAck::getProducerId ()`
[virtual]
- 6.626.2.6** `virtual const Pointer<ProducerId>& activemq::commands::ProducerAck::getProducerId () const`
[virtual]
- 6.626.2.7** `virtual int activemq::commands::ProducerAck::getSize () const`
[virtual]
- 6.626.2.8** `virtual bool activemq::commands::ProducerAck::isProducerAck () const`
[inline, virtual]

Returns:

an answer of true to the **isProducerAck()** (p. 3038) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 762).

- 6.626.2.9** `virtual void activemq::commands::ProducerAck::setProducerId (const Pointer< ProducerId > & producerId)` [virtual]
- 6.626.2.10** `virtual void activemq::commands::ProducerAck::setSize (int size)`
[virtual]
- 6.626.2.11** `virtual std::string activemq::commands::ProducerAck::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.626.2.12** `virtual Pointer<Command> activemq::commands::ProducerAck::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.626.3 Field Documentation

6.626.3.1 `const unsigned char activemq::commands::ProducerAck::ID_-
PRODUCERACK = 19` [static]

6.626.3.2 `Pointer<ProducerId> activemq::commands::ProducerAck::producerId`
[protected]

6.626.3.3 `int activemq::commands::ProducerAck::size` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ProducerAck.h`

6.627 activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3040).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ProducerAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.627.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3040).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.627.2 Constructor & Destructor Documentation

6.627.2.1 `activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.627.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.627.3 Member Function Documentation

6.627.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.627.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.627.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.627.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.627.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.627.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.627.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ProducerAckMarshaller.h**

6.628 activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3044).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ProducerAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.628.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3044).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.628.2 Constructor & Destructor Documentation

6.628.2.1 `activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.628.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.628.3 Member Function Documentation

6.628.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.628.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.628.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.628.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.628.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.628.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.628.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ProducerAckMarshaller.h**

6.629 activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3048).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ProducerAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.629.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3048).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.629.2 Constructor & Destructor Documentation

6.629.2.1 `activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.629.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.629.3 Member Function Documentation

6.629.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.629.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.629.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.629.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.629.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.629.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.629.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ProducerAckMarshaller.h**

6.630 activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3052).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ProducerAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.630.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3052).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.630.2 Constructor & Destructor Documentation

6.630.2.1 `activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.630.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.630.3 Member Function Documentation

6.630.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.630.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.630.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.630.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.630.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.630.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.630.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ProducerAckMarshaller.h**

6.631 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3056).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ProducerAckMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.631.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3056).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.631.2 Constructor & Destructor Documentation

6.631.2.1 `activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.631.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.631.3 Member Function Documentation

6.631.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.631.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.631.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.631.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.631.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.631.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.631.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ProducerAckMarshaller.h**

6.632 activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3060).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ProducerAckMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller:

Public Member Functions

- **ProducerAckMarshaller** ()
- virtual **~ProducerAckMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.632.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerAckMarshaller** (p.3060).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.632.2 Constructor & Destructor Documentation

6.632.2.1 `activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::ProducerAckMarshaller()` [inline]

6.632.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::~~ProducerAckMarshaller()` [inline, virtual]

6.632.3 Member Function Documentation

6.632.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.632.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.632.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.632.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.632.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.632.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.632.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ProducerAckMarshaller.h**

6.633 activemq::cmsutil::ProducerCallback Class Reference

Callback for sending a message to a CMS destination.

#include <src/main/activemq/cmsutil/ProducerCallback.h> Inheritance diagram for activemq::cmsutil::ProducerCallback:

Public Member Functions

- virtual `~ProducerCallback()`
- virtual void `doInCms(cms::Session *session, cms::MessageProducer *producer)=0`
throw (cms::CMSException)

Execute an action given a session and producer.

6.633.1 Detailed Description

Callback for sending a message to a CMS destination.

6.633.2 Constructor & Destructor Documentation

- 6.633.2.1** virtual `activemq::cmsutil::ProducerCallback::~~ProducerCallback()`
[inline, virtual]

6.633.3 Member Function Documentation

- 6.633.3.1** virtual void `activemq::cmsutil::ProducerCallback::doInCms(cms::Session * session, cms::MessageProducer * producer) throw (cms::CMSException)` [pure virtual]

Execute an action given a session and producer.

Parameters:

session the CMS Session

producer the CMS Producer

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

Implemented in `activemq::cmsutil::CmsTemplate::SendExecutor` (p. 3350).

The documentation for this class was generated from the following file:

- src/main/activemq/cmsutil/ProducerCallback.h

6.634 activemq::cmsutil::CmsTemplate::ProducerExecutor Class Reference

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate::ProducerExecutor:

Public Member Functions

- **ProducerExecutor** (**ProducerCallback** **action*, **CmsTemplate** **parent*, **cms::Destination** **destination*)
- virtual **~ProducerExecutor** ()
- virtual void **doInCms** (**cms::Session** **session*) throw (**cms::CMSException**)
Execute any number of operations against the supplied CMS session.
- virtual **cms::Destination** * **getDestination** (**cms::Session** **session* **AMQCPP_UNUSED**) throw (**cms::CMSException**)

Protected Member Functions

- **ProducerExecutor** (const **ProducerExecutor** &)
- **ProducerExecutor** & **operator=** (const **ProducerExecutor** &)

Protected Attributes

- **ProducerCallback** * *action*
- **CmsTemplate** * *parent*
- **cms::Destination** * *destination*

6.634.1 Constructor & Destructor Documentation

- 6.634.1.1 **activemq::cmsutil::CmsTemplate::ProducerExecutor::ProducerExecutor** (const **ProducerExecutor** &) [inline, protected]
- 6.634.1.2 **activemq::cmsutil::CmsTemplate::ProducerExecutor::ProducerExecutor** (**ProducerCallback** * *action*, **CmsTemplate** * *parent*, **cms::Destination** * *destination*) [inline]
- 6.634.1.3 virtual **activemq::cmsutil::CmsTemplate::ProducerExecutor::~~ProducerExecutor** () [inline, virtual]

6.634.2 Member Function Documentation

- 6.634.2.1 virtual void **activemq::cmsutil::CmsTemplate::ProducerExecutor::doInCms** (**cms::Session** * *session*) throw (**cms::CMSException**) [virtual]

Execute any number of operations against the supplied CMS session.

Parameters:

session the CMS Session

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

Implements **activemq::cmsutil::SessionCallback** (p. 3378).

6.634.2.2 `virtual cms::Destination* activemq::cmsutil::CmsTemplate::ProducerExecutor::getDestination (cms::Session *session AMQCPP_UNUSED) throw (cms::CMSException)` [inline, virtual]

6.634.2.3 `ProducerExecutor& activemq::cmsutil::CmsTemplate::ProducerExecutor::operator= (const ProducerExecutor &)` [inline, protected]

Reimplemented in **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor** (p. 3278).

6.634.3 Field Documentation

6.634.3.1 `ProducerCallback* activemq::cmsutil::CmsTemplate::ProducerExecutor::action` [protected]

6.634.3.2 `cms::Destination* activemq::cmsutil::CmsTemplate::ProducerExecutor::destination` [protected]

6.634.3.3 `CmsTemplate* activemq::cmsutil::CmsTemplate::ProducerExecutor::parent` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsTemplate.h`

6.635 activemq::commands::ProducerId Class Reference

#include <src/main/activemq/commands/ProducerId.h> Inheritance diagram for activemq::commands::ProducerId:

Public Types

- typedef decaf::lang::PointerComparator< ProducerId > COMPARATOR

Public Member Functions

- **ProducerId** ()
- **ProducerId** (const **ProducerId** &other)
- **ProducerId** (const **SessionId** &sessionId, long long consumerId)
- **ProducerId** (std::string producerId)
- virtual ~**ProducerId** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ProducerId** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- const **Pointer**< **SessionId** > & **getParentId** () const
- void **setProducerSessionKey** (std::string sessionKey)
- virtual const std::string & **getConnectionId** () const
- virtual std::string & **getConnectionId** ()
- virtual void **setConnectionId** (const std::string &connectionId)
- virtual long long **getValue** () const
- virtual void **setValue** (long long value)
- virtual long long **getSessionId** () const
- virtual void **setSessionId** (long long sessionId)
- virtual int **compareTo** (const **ProducerId** &value) const
- virtual bool **equals** (const **ProducerId** &value) const
- virtual bool **operator==** (const **ProducerId** &value) const
- virtual bool **operator<** (const **ProducerId** &value) const
- **ProducerId** & **operator=** (const **ProducerId** &other)

Static Public Attributes

- static const unsigned char `ID_PRODUCERID` = 123

Protected Attributes

- std::string `connectionId`
- long long `value`
- long long `sessionId`

6.635.1 Member Typedef Documentation

- 6.635.1.1** `typedef decaf::lang::PointerComparator<ProducerId>`
`activemq::commands::ProducerId::COMPARATOR`

6.635.2 Constructor & Destructor Documentation

- 6.635.2.1** `activemq::commands::ProducerId::ProducerId ()`
- 6.635.2.2** `activemq::commands::ProducerId::ProducerId (const ProducerId & other)`
- 6.635.2.3** `activemq::commands::ProducerId::ProducerId (const SessionId & sessionId, long long consumerId)`
- 6.635.2.4** `activemq::commands::ProducerId::ProducerId (std::string producerId)`
- 6.635.2.5** `virtual activemq::commands::ProducerId::~~ProducerId ()` [virtual]

6.635.3 Member Function Documentation

- 6.635.3.1** `virtual ProducerId* activemq::commands::ProducerId::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p.1660).

- 6.635.3.2** `virtual int activemq::commands::ProducerId::compareTo (const ProducerId & value) const` [virtual]
- 6.635.3.3** `virtual void activemq::commands::ProducerId::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.635.3.4 virtual bool activemq::commands::ProducerId::equals (const ProducerId & *value*) const [virtual]

6.635.3.5 virtual bool activemq::commands::ProducerId::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.635.3.6 virtual std::string& activemq::commands::ProducerId::getConnectionId () [virtual]

6.635.3.7 virtual const std::string& activemq::commands::ProducerId::getConnectionId () const [virtual]

6.635.3.8 virtual unsigned char activemq::commands::ProducerId::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.635.3.9 `const Pointer<SessionId>& activemq::commands::ProducerId::getParentId () const`
- 6.635.3.10 `virtual long long activemq::commands::ProducerId::getSessionId () const [virtual]`
- 6.635.3.11 `virtual long long activemq::commands::ProducerId::getValue () const [virtual]`
- 6.635.3.12 `virtual bool activemq::commands::ProducerId::operator< (const ProducerId & value) const [virtual]`
- 6.635.3.13 `ProducerId& activemq::commands::ProducerId::operator= (const ProducerId & other)`
- 6.635.3.14 `virtual bool activemq::commands::ProducerId::operator== (const ProducerId & value) const [virtual]`
- 6.635.3.15 `virtual void activemq::commands::ProducerId::setConnectionId (const std::string & connectionId) [virtual]`
- 6.635.3.16 `void activemq::commands::ProducerId::setProducerSessionKey (std::string sessionKey)`
- 6.635.3.17 `virtual void activemq::commands::ProducerId::setSessionId (long long sessionId) [virtual]`
- 6.635.3.18 `virtual void activemq::commands::ProducerId::setValue (long long value) [virtual]`
- 6.635.3.19 `virtual std::string activemq::commands::ProducerId::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataStructure` (p.833).

6.635.4 Field Documentation

- 6.635.4.1 `std::string activemq::commands::ProducerId::connectionId [protected]`
- 6.635.4.2 `const unsigned char activemq::commands::ProducerId::ID__ - PRODUCERID = 123 [static]`

Referenced by `activemq::state::CommandVisitorAdapter::processRemoveInfo()`.

6.635.4.3 `long long activemq::commands::ProducerId::sessionId` [protected]

6.635.4.4 `long long activemq::commands::ProducerId::value` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ProducerId.h`

6.636 activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3072).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.636.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3072). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.636.2 Constructor & Destructor Documentation

6.636.2.1 `activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.636.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.636.3 Member Function Documentation

6.636.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.636.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.636.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.636.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.636.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.636.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.636.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ProducerIdMarshaller.h**

6.637 activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3076).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.637.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3076). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.637.2 Constructor & Destructor Documentation

6.637.2.1 `activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.637.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.637.3 Member Function Documentation

6.637.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.637.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.637.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.637.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.637.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::tightMarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.637.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.637.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ProducerIdMarshaller.h**

6.638 activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3080).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.638.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3080). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.638.2 Constructor & Destructor Documentation

6.638.2.1 `activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.638.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.638.3 Member Function Documentation

6.638.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.638.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.638.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.638.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.638.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.638.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.638.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ProducerIdMarshaller.h**

6.639 activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3084).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.639.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3084). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.639.2 Constructor & Destructor Documentation

6.639.2.1 `activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.639.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.639.3 Member Function Documentation

6.639.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.639.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.639.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.639.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.639.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.639.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.639.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ProducerIdMarshaller.h**

6.640 activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3088).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.640.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3088). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.640.2 Constructor & Destructor Documentation

6.640.2.1 `activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.640.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.640.3 Member Function Documentation

6.640.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.640.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.640.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.640.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.640.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.640.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.640.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ProducerIdMarshaller.h**

6.641 activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3092).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ProducerIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller:

Public Member Functions

- **ProducerIdMarshaller** ()
- virtual **~ProducerIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.641.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3092). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.641.2 Constructor & Destructor Documentation

6.641.2.1 `activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::ProducerIdMarshaller()` [inline]

6.641.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::~~ProducerIdMarshaller()` [inline, virtual]

6.641.3 Member Function Documentation

6.641.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.641.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.641.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.641.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.641.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.641.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.641.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ProducerIdMarshaller.h**

6.642 activemq::commands::ProducerInfo Class Reference

#include <src/main/activemq/commands/ProducerInfo.h> Inheritance diagram for activemq::commands::ProducerInfo:

Public Member Functions

- **ProducerInfo** ()
- virtual **~ProducerInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ProducerInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- **Pointer< RemoveInfo > createRemoveCommand** () const
- virtual const **Pointer< ProducerId > & getProducerId** () const
- virtual **Pointer< ProducerId > & getProducerId** ()
- virtual void **setProducerId** (const **Pointer< ProducerId > &producerId**)
- virtual const **Pointer< ActiveMQDestination > & getDestination** () const
- virtual **Pointer< ActiveMQDestination > & getDestination** ()
- virtual void **setDestination** (const **Pointer< ActiveMQDestination > &destination**)
- virtual const std::vector< **decaf::lang::Pointer< BrokerId > > & getBrokerPath** () const
- virtual std::vector< **decaf::lang::Pointer< BrokerId > > & getBrokerPath** ()
- virtual void **setBrokerPath** (const std::vector< **decaf::lang::Pointer< BrokerId > > &brokerPath**)
- virtual bool **isDispatchAsync** () const
- virtual void **setDispatchAsync** (bool dispatchAsync)
- virtual int **getWindowSize** () const
- virtual void **setWindowSize** (int windowSize)
- virtual bool **isProducerInfo** () const
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_PRODUCERINFO** = 6

Protected Attributes

- **Pointer< ProducerId > producerId**
- **Pointer< ActiveMQDestination > destination**
- **std::vector< decaf::lang::Pointer< BrokerId > > brokerPath**
- **bool dispatchAsync**
- **int windowSize**

6.642.1 Constructor & Destructor Documentation

6.642.1.1 **activemq::commands::ProducerInfo::ProducerInfo ()**

6.642.1.2 **virtual activemq::commands::ProducerInfo::~~ProducerInfo ()** [virtual]

6.642.2 Member Function Documentation

6.642.2.1 **virtual ProducerInfo* activemq::commands::ProducerInfo::cloneDataStructure ()**
const [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements **activemq::commands::DataStructure** (p. 1660).

6.642.2.2 **virtual void activemq::commands::ProducerInfo::copyDataStructure (const DataStructure * src)** [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from **activemq::commands::BaseCommand** (p. 759).

6.642.2.3 **Pointer<RemoveInfo> activemq::commands::ProducerInfo::createRemoveCommand ()** **const**

6.642.2.4 **virtual bool activemq::commands::ProducerInfo::equals (const DataStructure * value)** **const** [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are

the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.642.2.5 `virtual std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ProducerInfo::getBrokerPath () [virtual]`

6.642.2.6 `virtual const std::vector< decaf::lang::Pointer<BrokerId> >& activemq::commands::ProducerInfo::getBrokerPath () const [virtual]`

6.642.2.7 `virtual unsigned char activemq::commands::ProducerInfo::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

6.642.2.8 `virtual Pointer<ActiveMQDestination>& activemq::commands::ProducerInfo::getDestination () [virtual]`

6.642.2.9 `virtual const Pointer<ActiveMQDestination>& activemq::commands::ProducerInfo::getDestination () const [virtual]`

6.642.2.10 `virtual Pointer<ProducerId>& activemq::commands::ProducerInfo::getProducerId () [virtual]`

6.642.2.11 `virtual const Pointer<ProducerId>& activemq::commands::ProducerInfo::getProducerId () const [virtual]`

6.642.2.12 `virtual int activemq::commands::ProducerInfo::getWindowSize () const [virtual]`

6.642.2.13 `virtual bool activemq::commands::ProducerInfo::isDispatchAsync () const [virtual]`

6.642.2.14 `virtual bool activemq::commands::ProducerInfo::isProducerInfo () const [inline, virtual]`

Returns:

an answer of true to the `isProducerInfo()` (p. 3098) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 762).

- 6.642.2.15 `virtual void activemq::commands::ProducerInfo::setBrokerPath (const std::vector< decaf::lang::Pointer< BrokerId > > & brokerPath) [virtual]`
- 6.642.2.16 `virtual void activemq::commands::ProducerInfo::setDestination (const Pointer< ActiveMQDestination > & destination) [virtual]`
- 6.642.2.17 `virtual void activemq::commands::ProducerInfo::setDispatchAsync (bool dispatchAsync) [virtual]`
- 6.642.2.18 `virtual void activemq::commands::ProducerInfo::setProducerId (const Pointer< ProducerId > & producerId) [virtual]`
- 6.642.2.19 `virtual void activemq::commands::ProducerInfo::setWindowSize (int windowSize) [virtual]`
- 6.642.2.20 `virtual std::string activemq::commands::ProducerInfo::toString () const [virtual]`

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.642.2.21 `virtual Pointer<Command> activemq::commands::ProducerInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.642.3 Field Documentation

- 6.642.3.1 `std::vector< decaf::lang::Pointer<BrokerId> >`
`activemq::commands::ProducerInfo::brokerPath` [protected]
- 6.642.3.2 `Pointer<ActiveMQDestination>` `activemq::commands::ProducerInfo::destination`
[protected]
- 6.642.3.3 `bool` `activemq::commands::ProducerInfo::dispatchAsync` [protected]
- 6.642.3.4 `const unsigned char` `activemq::commands::ProducerInfo::ID_PRODUCERINFO = 6` [static]
- 6.642.3.5 `Pointer<ProducerId>` `activemq::commands::ProducerInfo::producerId`
[protected]
- 6.642.3.6 `int` `activemq::commands::ProducerInfo::windowSize` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ProducerInfo.h`

6.643 activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3101).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ProducerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.643.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3101).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.643.2 Constructor & Destructor Documentation

6.643.2.1 `activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.643.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.643.3 Member Function Documentation

6.643.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.643.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.643.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.643.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.643.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.643.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.643.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ProducerInfoMarshaller.h**

6.644 activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3105).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ProducerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.644.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3105).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.644.2 Constructor & Destructor Documentation

6.644.2.1 `activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.644.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.644.3 Member Function Documentation

6.644.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.644.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.644.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 801).

6.644.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 802).

6.644.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 803).

6.644.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.644.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ProducerInfoMarshaller.h**

6.645 activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3109).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ProducerInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.645.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3109).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.645.2 Constructor & Destructor Documentation

6.645.2.1 `activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.645.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.645.3 Member Function Documentation

6.645.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.645.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.645.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

6.645.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

6.645.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

6.645.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.645.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ProducerInfoMarshaller.h**

6.646 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3113).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ProducerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.646.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3113).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.646.2 Constructor & Destructor Documentation

6.646.2.1 `activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.646.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.646.3 Member Function Documentation

6.646.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.646.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.646.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 787).

6.646.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 788).

6.646.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 789).

6.646.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.646.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ProducerInfoMarshaller.h**

6.647 activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3117).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ProducerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.647.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3117).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.647.2 Constructor & Destructor Documentation

6.647.2.1 `activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.647.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.647.3 Member Function Documentation

6.647.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.647.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.647.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 766).

6.647.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 767).

6.647.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 768).

6.647.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.647.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ProducerInfoMarshaller.h**

6.648 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3121).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ProducerInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller:

Public Member Functions

- **ProducerInfoMarshaller** ()
- virtual **~ProducerInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.648.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **ProducerInfoMarshaller** (p.3121).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.648.2 Constructor & Destructor Documentation

6.648.2.1 `activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::ProducerInfoMarshaller()` [inline]

6.648.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::~~ProducerInfoMarshaller()` [inline, virtual]

6.648.3 Member Function Documentation

6.648.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.648.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.648.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.648.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.648.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.648.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.648.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ProducerInfoMarshaller.h**

6.649 activemq::state::ProducerState Class Reference

```
#include <src/main/activemq/state/ProducerState.h>
```

Public Member Functions

- **ProducerState** (const **Pointer**< **ProducerInfo** > &info)
- virtual **~ProducerState** ()
- std::string **toString** () const
- const **Pointer**< **ProducerInfo** > & **getInfo** () const
- void **setTransactionState** (const **Pointer**< **TransactionState** > &transactionState)
- **Pointer**< **TransactionState** > **getTransactionState** () const

6.649.1 Constructor & Destructor Documentation

6.649.1.1 **activemq::state::ProducerState::ProducerState** (const **Pointer**< **ProducerInfo** > & *info*)

6.649.1.2 virtual **activemq::state::ProducerState::~~ProducerState** () [virtual]

6.649.2 Member Function Documentation

6.649.2.1 const **Pointer**<**ProducerInfo**>& **activemq::state::ProducerState::getInfo** () const [inline]

6.649.2.2 **Pointer**<**TransactionState**> **activemq::state::ProducerState::getTransactionState** () const

6.649.2.3 void **activemq::state::ProducerState::setTransactionState** (const **Pointer**< **TransactionState** > & *transactionState*)

6.649.2.4 std::string **activemq::state::ProducerState::toString** () const

The documentation for this class was generated from the following file:

- src/main/activemq/state/**ProducerState.h**

6.650 decaf::util::Properties Class Reference

Java-like properties class for mapping string names to string values.

```
#include <src/main/decaf/util/Properties.h>
```

Public Member Functions

- **Properties** ()
- **Properties** (const **Properties** &src)
- virtual ~**Properties** ()
- **Properties** & **operator=** (const **Properties** &src)
Assignment Operator.
- bool **isEmpty** () const
Returns true if the properties object is empty.
- std::size_t **size** () const
- const char * **getProperty** (const std::string &name) const
Looks up the value for the given property.
- std::string **getProperty** (const std::string &name, const std::string &defaultValue) const
Looks up the value for the given property.
- std::string **setProperty** (const std::string &name, const std::string &value)
Sets the value for a given property.
- bool **hasProperty** (const std::string &name) const
Check to see if the Property exists in the set.
- std::string **remove** (const std::string &name)
Removes the property with the given name.
- std::vector< std::string > **propertyNames** () const
Returns an enumeration of all the keys in this property list, including distinct keys in the default property list if a key of the same name has not already been found from the main properties list.
- std::vector< std::pair< std::string, std::string > > **toArray** () const
Method that serializes the contents of the property map to an array.
- void **copy** (const **Properties** &source)
*Copies the contents of the given properties object to this one, if the given **Properties** (p. 3126) instance in NULL then this **List** (p. 2337) is not modified.*
- **Properties** * **clone** () const
Clones this object.
- void **clear** ()
Clears all properties from the map.

- **bool equals** (const **Properties** &source) const
*Test whether two **Properties** (p. 3126) objects are equivalent.*
- **std::string toString** () const
*Formats the contents of the **Properties** (p. 3126) Object into a string that can be logged, etc.*
- **void load** (decaf::io::InputStream *stream) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)
Reads a property list (key and element pairs) from the input byte stream.
- **void load** (decaf::io::Reader *reader) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)
Reads a property list (key and element pairs) from the input character stream in a simple line-oriented format.
- **void store** (decaf::io::OutputStream *out, const std::string &comment) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
*Writes this property list (key and element pairs) in this **Properties** (p. 3126) table to the output stream in a format suitable for loading into a **Properties** (p. 3126) table using the load(InputStream) method.*
- **void store** (decaf::io::Writer *writer, const std::string &comments) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
*Writes this property list (key and element pairs) in this **Properties** (p. 3126) table to the output character stream in a format that can be read by the load(Reader) method.*

Protected Attributes

- **decaf::lang::Pointer< Properties > defaults**
Default list used to answer for any keys not found in the properties list, can be filled in by another implementation of this class.

6.650.1 Detailed Description

Java-like properties class for mapping string names to string values. The **Properties** (p. 3126) list contains a key value pair of properties that can be loaded and stored to a stream. Each **Properties** (p. 3126) instance can contain an **internal** (p. 144) **Properties** (p. 3126) list that contains default values for keys not found in the **Properties** (p. 3126) **List** (p. 2337).

The **Properties** (p. 3126) list if a Thread Safe class, it can be shared amongst objects in multiple threads without the need for additional synchronization.

Since:

1.0

6.650.2 Constructor & Destructor Documentation

6.650.2.1 `decaf::util::Properties::Properties ()`

6.650.2.2 `decaf::util::Properties::Properties (const Properties & src)`

6.650.2.3 `virtual decaf::util::Properties::~~Properties ()` [virtual]

6.650.3 Member Function Documentation

6.650.3.1 `void decaf::util::Properties::clear ()`

Clears all properties from the map.

6.650.3.2 `Properties* decaf::util::Properties::clone () const`

Clones this object.

Returns:

a replica of this object.

6.650.3.3 `void decaf::util::Properties::copy (const Properties & source)`

Copies the contents of the given properties object to this one, if the given **Properties** (p. 3126) instance is NULL then this **List** (p. 2337) is not modified.

Parameters:

source The source properties object.

6.650.3.4 `bool decaf::util::Properties::equals (const Properties & source) const`

Test whether two **Properties** (p. 3126) objects are equivalent. Two **Properties** (p. 3126) Objects are considered equivalent when they each contain the same number of elements and each key / value pair contained within the two are equal.

This comparison does not check the contents of the Defaults instance.

Parameters:

source The **Properties** (p. 3126) object to compare this instance to.

Returns:

true if the contents of the two **Properties** (p. 3126) objects are the same.

6.650.3.5 `std::string decaf::util::Properties::getProperty (const std::string & name, const std::string & default Value) const`

Looks up the value for the given property.

Parameters:

name The name of the property to be looked up.

defaultValue The value to be returned if the given property does not exist.

Returns:

The value of the property specified by *name*, if it exists, otherwise the *defaultValue*.

6.650.3.6 const char* decaf::util::Properties::getProperty (const std::string & *name*) const

Looks up the value for the given property.

Parameters:

name The name of the property to be looked up.

Returns:

the value of the property with the given name, if it exists. If it does not exist, returns NULL.

6.650.3.7 bool decaf::util::Properties::hasProperty (const std::string & *name*) const

Check to see if the Property exists in the set.

Parameters:

name The property name to check for in this properties set.

Returns:

true if property exists, false otherwise.

6.650.3.8 bool decaf::util::Properties::isEmpty () const

Returns true if the properties object is empty.

Returns:

true if empty

6.650.3.9 void decaf::util::Properties::load (decaf::io::Reader * *reader*) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)

Reads a property list (key and element pairs) from the input character stream in a simple line-oriented format. **Properties** (p. 3126) are processed in terms of lines. There are two kinds of line, natural lines and logical lines. A natural line is defined as a line of characters that is terminated either by a set of line terminator characters (

or or

) or by the end of the stream. A natural line may be either a blank line, a comment line, or hold all or some of a key-element pair. A logical line holds all the data of a key-element pair, which may be spread out across several adjacent natural lines by escaping the line terminator sequence with a backslash character `\`. Note that a comment line cannot be extended in this manner; every natural line that is a comment must have its own comment indicator, as described below. Lines are read from input until the end of the stream is reached.

A natural line that contains only white space characters is considered blank and is ignored. A comment line has an ASCII `'#'` or `'!'` as its first non-white space character; comment lines are also ignored and do not encode key-element information. In addition to line terminators, this format considers the characters space (`' '`), tab (`'\t'`), and form feed (`'\f'`) to be white space.

If a logical line is spread across several natural lines, the backslash escaping the line terminator sequence, the line terminator sequence, and any white space at the start of the following line have no affect on the key or element values. The remainder of the discussion of key and element parsing (when loading) will assume all the characters constituting the key and element appear on a single natural line after line continuation characters have been removed. Note that it is not sufficient to only examine the character preceding a line terminator sequence to decide if the line terminator is escaped; there must be an odd number of contiguous backslashes for the line terminator to be escaped. Since the input is processed from left to right, a non-zero even number of $2n$ contiguous backslashes before a line terminator (or elsewhere) encodes n backslashes after escape processing.

The key contains all of the characters in the line starting with the first non-white space character and up to, but not including, the first unescaped `'='`, `':'`, or white space character other than a line terminator. All of these key termination characters may be included in the key by escaping them with a preceding backslash character; for example,

```
\:\=
```

would be the two-character key `":="`. Line terminator characters can be included using and

escape sequences. Any white space after the key is skipped; if the first non-white space character after the key is `'='` or `':'`, then it is ignored and any white space characters after it are also skipped. All remaining characters on the line become part of the associated element string; if there are no remaining characters, the element is the empty string `""`. Once the raw character sequences constituting the key and element are identified, escape processing is performed as described above.

As an example, each of the following three lines specifies the key `"Truth"` and the associated element value `"Beauty"`:

```
Truth = Beauty Truth:Beauty Truth :Beauty
```

As another example, the following three lines specify a single property:

```
fruits apple, banana, pear, \ cantaloupe, watermelon, \ kiwi, mango
```

The key is `"fruits"` and the associated element is: `"apple, banana, pear, cantaloupe, watermelon, kiwi, mango"`

Note that a space appears before each `\` so that a space will appear after each comma in the final result; the `\`, line terminator, and leading white space on the continuation line are merely discarded and are not replaced by one or more other characters.

As a third example, the line:

```
cheeses
```

specifies that the key is `"cheeses"` and the associated element is the empty string `""`.

Characters in keys and elements can be represented in escape sequences similar to those used for character and string literals (see §3.3 and §3.10.6 of the Java Language Specification). The differences from the character escape sequences and Unicode escapes used for characters and strings

are:

- Octal escapes are not recognized.
- The character sequence **does** not represent a backspace character.
- The method does not treat a backslash character, `\`, before a non-valid escape character as an error; the backslash is silently dropped. For example, in a C++ string the sequence `"\z"` would cause a compile time error. In contrast, this method silently drops the backslash. Therefore, this method treats the two character sequence `"\b"` as equivalent to the single character `'b'`.
- Escapes are not necessary for single and double quotes; however, by the rule above, single and double quote characters preceded by a backslash still yield single and double quote characters, respectively.

This method does not close the Reader upon its return.

Parameters:

reader The Reader that provides an character stream as input.

Exceptions:

IOException if there is an error while reading from the stream.

IllegalArgumentException if malformed data is found while reading the properties.

NullPointerException if the passed stream is Null.

6.650.3.10 `void decaf::util::Properties::load (decaf::io::InputStream
* stream) throw (decaf::io::IOException, de-
cafe::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::NullPointerException)`

Reads a property list (key and element pairs) from the input byte stream. The input stream is in a simple line-oriented format as specified in `load(Reader)` and is assumed to use the ISO 8859-1 character encoding.

This method does not close the stream upon its return.

Parameters:

stream The stream to read the properties data from.

Exceptions:

IOException if there is an error while reading from the stream.

IllegalArgumentException if malformed data is found while reading the properties.

NullPointerException if the passed stream is Null.

6.650.3.11 Properties& decaf::util::Properties::operator= (const Properties & *src*)

Assignment Operator.

Parameters:

src The **Properties** (p. 3126) list to copy to this **List** (p. 2337).

Returns:

a reference to this **List** (p. 2337) for use in chaining.

6.650.3.12 std::vector<std::string> decaf::util::Properties::propertyNames () const

Returns an enumeration of all the keys in this property list, including distinct keys in the default property list if a key of the same name has not already been found from the main properties list.

Returns:

a set of keys in this property list where the key and its corresponding value are strings, including the keys in the default property list.

6.650.3.13 std::string decaf::util::Properties::remove (const std::string & *name*)

Removes the property with the given name.

Parameters:

name The name of the property to remove.

Returns:

the previous value of the property if set, or empty string.

6.650.3.14 std::string decaf::util::Properties::setProperty (const std::string & *name*, const std::string & *value*)

Sets the value for a given property. If the property already exists, overwrites the value.

Parameters:

name The name of the value to be written.

value The value to be written.

Returns:

the old value of the property or empty string if not set.

6.650.3.15 std::size_t decaf::util::Properties::size () const**Returns:**

The number of **Properties** (p. 3126) in this **Properties** (p. 3126) Object.

6.650.3.16 `void decaf::util::Properties::store (decaf::io::Writer * writer,
const std::string & comments) throw (decaf::io::IOException,
decaf::lang::exceptions::NullPointerException)`

Writes this property list (key and element pairs) in this **Properties** (p. 3126) table to the output character stream in a format that can be read by the load(Reader) method. **Properties** (p. 3126) from the defaults table of this **Properties** (p. 3126) table (if any) are not written out by this method.

If the comments argument is not empty, then an ASCII # character, the comments string, and a line separator are first written to the output stream. Thus, the comments can serve as an identifying comment. Any one of a line feed (

'), a carriage return ("), or a carriage return followed immediately by a line feed in comments is replaced by a line separator generated by the Writer and if the next character in comments is not character # or character ! then an ASCII # is written out after that line separator.

Next, a comment line is always written, consisting of an ASCII # character, the current date and time (as if produced by the toString method of **Date** (p. 1665) for the current time), and a line separator as generated by the Writer.

Then every entry in this **Properties** (p. 3126) table is written out, one per line. For each entry the key string is written, then an ASCII =, then the associated element string. For the key, all space characters are written with a preceding \ character. For the element, leading space characters, but not embedded or trailing space characters, are written with a preceding \ character. The key and element characters #, !, =, and : are written with a preceding backslash to ensure that they are properly loaded.

After the entries have been written, the output stream is flushed. The output stream remains open after this method returns.

Parameters:

writer The Writer instance to use to output the properties.

comments A description of these properties that is written before writing the properties.

Exceptions:

IOException if there is an error while writing from the stream.

NullPointerException if the passed stream is Null.

6.650.3.17 `void decaf::util::Properties::store (decaf::io::OutputStream * out,
const std::string & comment) throw (decaf::io::IOException,
decaf::lang::exceptions::NullPointerException)`

Writes this property list (key and element pairs) in this **Properties** (p. 3126) table to the output stream in a format suitable for loading into a **Properties** (p. 3126) table using the load(InputStream) method. **Properties** (p. 3126) from the defaults table of this **Properties** (p. 3126) table (if any) are not written out by this method.

This method outputs the comments, properties keys and values in the same format as specified in store(Writer), with the following differences:

- The stream is written using the ISO 8859-1 character encoding.
- Characters not in Latin-1 in the comments are written as for their appropriate unicode hexadecimal value xxxx.

- Characters less than and characters greater than in property keys or values are written as for the appropriate hexadecimal value xxxx.

After the entries have been written, the output stream is flushed. The output stream remains open after this method returns.

Parameters:

out The OutputStream instance to write the properties to.

comment A description of these properties that is written to the output stream.

Exceptions:

IOException if there is an error while writing from the stream.

NullPointerException if the passed stream is Null.

6.650.3.18 `std::vector< std::pair< std::string, std::string > >
decaf::util::Properties::toArray () const`

Method that serializes the contents of the property map to an array.

Returns:

list of pairs where the first is the name and the second is the value.

6.650.3.19 `std::string decaf::util::Properties::toString () const`

Formats the contents of the **Properties** (p. 3126) Object into a string that can be logged, etc.

Returns:

string value of this object.

6.650.4 Field Documentation

6.650.4.1 `decaf::lang::Pointer<Properties> decaf::util::Properties::defaults
[protected]`

Default list used to answer for any keys not found in the properties list, can be filled in by another implementation of this class.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Properties.h`

6.651 decaf::util::logging::PropertiesChangeListener Class Reference

Defines the interface that classes can use to listen for change events on **Properties** (p. 3126).

```
#include <src/main/decaf/util/logging/PropertiesChangeListener.h>
```

Public Member Functions

- virtual **~PropertiesChangeListener** ()
- virtual void **onPropertiesReset** ()=0
*Indicates that the **Properties** (p. 3126) have all been reset and should be considered to be back to their default values.*
- virtual void **onPropertyChanged** (const std::string &name, const std::string &oldValue, const std::string &newValue)=0
Change Event, called when a property is changed, includes the name of the property that was changed along with it old and new values.

6.651.1 Detailed Description

Defines the interface that classes can use to listen for change events on **Properties** (p. 3126).

Since:

1.0

6.651.2 Constructor & Destructor Documentation

- 6.651.2.1** virtual
decaf::util::logging::PropertiesChangeListener::~~PropertiesChangeListener
() [inline, virtual]

6.651.3 Member Function Documentation

- 6.651.3.1** virtual void **decaf::util::logging::PropertiesChangeListener::onPropertiesReset** () [pure virtual]

Indicates that the **Properties** (p. 3126) have all been reset and should be considered to be back to their default values.

- 6.651.3.2** virtual void **decaf::util::logging::PropertiesChangeListener::onPropertyChanged** (const std::string & *name*, const std::string & *oldValue*, const std::string & *newValue*) [pure virtual]

Change Event, called when a property is changed, includes the name of the property that was changed along with it old and new values.

Parameters:

name The name of the Property that changed.

oldValue The old Value of the Property.

newValue The new Value of the Property.

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**PropertiesChangeListener.h**

6.652 decaf::net::ProtocolException Class Reference

#include <src/main/decaf/net/ProtocolException.h> Inheritance diagram for decaf::net::ProtocolException:

Public Member Functions

- **ProtocolException** () throw ()
Default Constructor.
- **ProtocolException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **ProtocolException** (const **ProtocolException** &ex) throw ()
Copy Constructor.
- **ProtocolException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ProtocolException** (const std::exception *cause) throw ()
Constructor.
- **ProtocolException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **ProtocolException** * clone () const
Clones this exception.
- virtual ~**ProtocolException** () throw ()

6.652.1 Constructor & Destructor Documentation

6.652.1.1 decaf::net::ProtocolException::ProtocolException () throw () [inline]

Default Constructor.

6.652.1.2 decaf::net::ProtocolException::ProtocolException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.652.1.3 decaf::net::ProtocolException::ProtocolException (const ProtocolException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.652.1.4 decaf::net::ProtocolException::ProtocolException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.652.1.5 decaf::net::ProtocolException::ProtocolException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.652.1.6 decaf::net::ProtocolException::ProtocolException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.652.1.7 `virtual decaf::net::ProtocolException::~~ProtocolException () throw ()`
 [inline, virtual]

6.652.2 Member Function Documentation

6.652.2.1 `virtual ProtocolException* decaf::net::ProtocolException::clone () const`
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ProtocolException.h`

6.653 decaf::security::PublicKey Class Reference

A public key.

`#include <src/main/decaf/security/PublicKey.h>`
Inheritance diagram for decaf::security::PublicKey:

Public Member Functions

- virtual `~PublicKey()`

6.653.1 Detailed Description

A public key. This interface contains no methods or constants. It merely serves to group (and provide type safety for) all public key interfaces.

6.653.2 Constructor & Destructor Documentation

6.653.2.1 virtual `decaf::security::PublicKey::~~PublicKey()` [inline, virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/security/PublicKey.h`

6.654 decaf::io::PushbackInputStream Class Reference

A **PushbackInputStream** (p. 3141) adds functionality to another input stream, namely the ability to "push back" or "unread" one byte.

#include <src/main/decaf/io/PushbackInputStream.h> Inheritance diagram for decaf::io::PushbackInputStream:

Public Member Functions

- **PushbackInputStream** (**InputStream** *stream, bool **own**=false)
*Creates a **PushbackInputStream** (p. 3141) and saves its argument, the input stream in, for later use.*
- **PushbackInputStream** (**InputStream** *stream, int bufSize, bool **own**=false) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **PushbackInputStream** (p. 3141) and saves its argument, the input stream in, for later use.*
- virtual ~**PushbackInputStream** ()
- void **unread** (unsigned char value) throw (decaf::io::IOException)
Pushes back the given byte, the byte is copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back byte.
- void **unread** (const unsigned char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Pushes back the given array of bytes, the bytes are copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back bytes.
- void **unread** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Pushes back the given array of bytes, the bytes are copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back bytes.
- virtual int **available** () const throw (decaf::io::IOException)
*Indicates the number of bytes available.
The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data avaiable. The caller should view the result of this method as an absolute.
The default implementation of this method returns zero.*
Returns:
the number of bytes available on this input stream.
Exceptions:
IOException (p. 2142) if an I/O error occurs.
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)

Skips over and discards n bytes of data from this input stream.

*The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned. The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.*

Parameters:

***num** The number of bytes to skip.*

Returns:

total bytes skipped

Exceptions:

***IOException** (p. 2142) if an I/O error occurs.*

***UnsupportedOperationException** if the concrete stream class does not support skipping bytes.*

- virtual void **mark** (int readLimit)

*Does nothing except throw an **IOException** (p. 2142).*

- virtual void **reset** () throw (decaf::io::IOException)

*Does nothing except throw an **IOException** (p. 2142).*

- virtual bool **markSupported** () const

*Does nothing except throw an **IOException** (p. 2142).*

Protected Member Functions

- virtual int **doReadByte** () throw (decaf::io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsExpection, decaf::lang::exceptions::NullPointerException)

6.654.1 Detailed Description

A **PushbackInputStream** (p. 3141) adds functionality to another input stream, namely the ability to "push back" or "unread" one byte. This is useful in situations where it is convenient for a fragment of **code** (p. 1183) to read an indefinite number of data bytes that are delimited by a particular byte value; after reading the terminating byte, the **code** (p. 1183) fragment can "unread" it, so that the next read operation on the input stream will reread the byte that was pushed back. For example, bytes representing the characters constituting an identifier might be terminated by a byte representing an operator character; a method whose job is to read just an identifier can read until it sees the operator and then push the operator back to be re-read.

Since:

1.0

6.654.2 Constructor & Destructor Documentation

6.654.2.1 decaf::io::PushbackInputStream::PushbackInputStream (InputStream * *stream*, bool *own* = false)

Creates a **PushbackInputStream** (p. 3141) and saves its argument, the input stream in, for later use. Initially, there is no pushed-back byte.

Parameters:

stream The **InputStream** (p. 2043) instance to wrap.

Boolean value indicating if this **FilterInputStream** (p. 1894) owns the wrapped stream.

6.654.2.2 decaf::io::PushbackInputStream::PushbackInputStream (InputStream * *stream*, int *bufSize*, bool *own* = false) throw (decaf::lang::exceptions::IllegalArgumentException)

Creates a **PushbackInputStream** (p. 3141) and saves its argument, the input stream in, for later use. Initially, there is no pushed-back byte.

Parameters:

stream The **InputStream** (p. 2043) instance to wrap.

bufSize The number of byte to allocate for pushback into this stream.

Boolean value indicating if this **FilterInputStream** (p. 1894) owns the wrapped stream.

Exceptions:

IllegalArgumentException if the *bufSize* argument is < zero.

6.654.2.3 virtual decaf::io::PushbackInputStream::~~PushbackInputStream () [virtual]

6.654.3 Member Function Documentation

6.654.3.1 virtual int decaf::io::PushbackInputStream::available () const throw (decaf::io::IOException) [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Returns the sum of the number of pushed back bytes if any and the amount of bytes available in the underlying stream via a call to `available`.

Reimplemented from `decaf::io::FilterInputStream` (p.1896).

6.654.3.2 `virtual int decaf::io::PushbackInputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Reimplemented from `decaf::io::FilterInputStream` (p.1897).

6.654.3.3 `virtual int decaf::io::PushbackInputStream::doReadByte () throw (decaf::io::IOException)` [protected, virtual]

Reimplemented from `decaf::io::FilterInputStream` (p.1897).

6.654.3.4 `virtual void decaf::io::PushbackInputStream::mark (int readLimit)` [virtual]

Does nothing except throw an **IOException** (p.2142). Marks the current position in the stream. A subsequent call to the `reset` method repositions this stream at the last marked position so that subsequent reads re-read the same bytes.

If a stream instance reports that marks are supported then the stream will ensure that the same bytes can be read again after the `reset` method is called so long the `readLimit` is not reached.

Calling `mark` on a closed stream instance should have no effect.

The default implementation of this method does nothing.

Parameters:

readLimit The max bytes read before marked position is invalid.

Reimplemented from `decaf::io::FilterInputStream` (p.1897).

6.654.3.5 `virtual bool decaf::io::PushbackInputStream::markSupported () const` [inline, virtual]

Does nothing except throw an **IOException** (p.2142). Determines if this input stream supports the `mark` and `reset` methods.

Whether or not `mark` and `reset` are supported is an invariant property of a particular input stream instance.

The default implementation of this method returns false.

Returns:

true if this stream instance supports marks

Reimplemented from `decaf::io::FilterInputStream` (p.1898).

6.654.3.6 virtual void decaf::io::PushbackInputStream::reset () throw (decaf::io::IOException) [virtual]

Does nothing except throw an **IOException** (p. 2142). Repositions this stream to the position at the time the mark method was last called on this input stream.

If the method markSupported returns true, then: * If the method mark has not been called since the stream was created, or the number of bytes read from the stream since mark was last called is larger than the argument to mark at that last call, then an **IOException** (p. 2142) might be thrown. * If such an **IOException** (p. 2142) is not thrown, then the stream is reset to a state such that all the bytes read since the most recent call to mark (or since the start of the file, if mark has not been called) will be resupplied to subsequent callers of the read method, followed by any bytes that otherwise would have been the next input data as of the time of the call to reset.

If the method markSupported returns false, then: * The call to reset may throw an **IOException** (p. 2142). * If an **IOException** (p. 2142) is not thrown, then the stream is reset to a fixed state that depends on the particular type of the input stream and how it was created. The bytes that will be supplied to subsequent callers of the read method depend on the particular type of the input stream.

The default implementation of this method throws an **IOException** (p. 2142).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from **decaf::io::FilterInputStream** (p. 1898).

6.654.3.7 virtual long long decaf::io::PushbackInputStream::skip (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [virtual]

Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of **InputStream** (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

This method first skips bytes in the local pushed back buffer before attempting to complete the request by calling the underlying stream skip method with the remainder of bytes that needs to be skipped.

Reimplemented from **decaf::io::FilterInputStream** (p.1899).

6.654.3.8 `void decaf::io::PushbackInputStream::unread (const unsigned char *
buffer, int size, int offset, int length) throw (decaf::io::IOException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException)`

Pushes back the given array of bytes, the bytes are copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back bytes.

Parameters:

buffer The bytes to copy to the front of push back buffer.

size The size of the array to be copied.

offset The position in the buffer to start copying from.

length The number of bytes to push back from the passed buffer.

Exceptions:

NullPointerException if the buffer passed is NULL.

IndexOutOfBoundsException if the offset + length is greater than the buffer size.

IOException (p. 2142) if there is not enough space in the pushback buffer or this stream has already been closed.

6.654.3.9 `void decaf::io::PushbackInputStream::unread (const unsigned
char * buffer, int size) throw (decaf::io::IOException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException)`

Pushes back the given array of bytes, the bytes are copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back bytes.

Parameters:

buffer The bytes to copy to the front of push back buffer.

size The size of the array to be copied.

Exceptions:

NullPointerException if the buffer passed is NULL.

IndexOutOfBoundsException if the size value given is negative.

IOException (p. 2142) if there is not enough space in the pushback buffer or this stream has already been closed.

6.654.3.10 void decaf::io::PushbackInputStream::unread (unsigned char *value*)
throw (decaf::io::IOException)

Pushes back the given byte, the byte is copied to the front of the pushback buffer, future calls to read start reading from the beginning of these pushed back byte.

Parameters:

value The byte that is to be placed at the front of the push back buffer.

Exceptions:

IOException (p. 2142) if there is not enough space in the pushback buffer or this stream has already been closed.

The documentation for this class was generated from the following file:

- src/main/decaf/io/**PushbackInputStream.h**

6.655 cms::Queue Class Reference

An interface encapsulating a provider-specific queue name.

#include <src/main/cms/Queue.h> Inheritance diagram for cms::Queue:

Public Member Functions

- virtual `~Queue ()`
- virtual `std::string getQueueName () const =0 throw (CMSEException)`
Gets the name of this queue.

6.655.1 Detailed Description

An interface encapsulating a provider-specific queue name. Messages sent to a **Queue** (p. 3148) are sent to a Single Subscriber on that **Queue** (p. 3148) **Destination** (p. 1723). This allows for Queues to be used as load balances implementing a SEDA based architecture. The length of time that a Provider will store a **Message** (p. 2534) in a **Queue** (p. 3148) is not defined by the CMS API, consult your Provider documentation for this information.

Since:

1.0

6.655.2 Constructor & Destructor Documentation

6.655.2.1 virtual `cms::Queue::~Queue ()` [inline, virtual]

6.655.3 Member Function Documentation

6.655.3.1 virtual `std::string cms::Queue::getQueueName () const throw (CMSEException)` [pure virtual]

Gets the name of this queue.

Returns:

The queue name.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::commands::ActiveMQQueue` (p. 486).

The documentation for this class was generated from the following file:

- `src/main/cms/Queue.h`

6.656 decaf::util::Queue< E > Class Template Reference

A kind of collection provides advanced operations than other basic collections, such as insertion, extraction, and inspection.

#include <src/main/decaf/util/Queue.h> Inheritance diagram for decaf::util::Queue< E >:

Public Member Functions

- virtual **~Queue** ()
- virtual bool **offer** (const E &value)=0 throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into the queue provided that the condition allows such an operation.
- virtual bool **poll** (E &result)=0
Gets and removes the element in the head of the queue.
- virtual E **remove** ()=0 throw (decaf::lang::exceptions::NoSuchElementException)
Gets and removes the element in the head of the queue.
- virtual bool **peek** (E &result) const =0
Gets but not removes the element in the head of the queue.
- virtual E **element** () const =0 throw (decaf::lang::exceptions::NoSuchElementException)
Gets but not removes the element in the head of the queue.

6.656.1 Detailed Description

template<typename E> class decaf::util::Queue< E >

A kind of collection provides advanced operations than other basic collections, such as insertion, extraction, and inspection. Generally, a queue orders its elements by means of first-in-first-out. While priority queue orders its elements according to a comparator specified or the elements' natural order. Furthermore, a stack orders its elements last-in-first out.

Queue (p.3149) does not provide blocking queue methods, which will block until the operation of the method is allowed. BlockingQueue interface defines such methods.

Unlike the Java **Queue** (p. 3149) interface the methods of this class cannot return null to indicate that a **Queue** (p. 3149) is empty since null has no meaning for elements such as classes, structs and primitive types and cannot be used in a meaningful way to check for an empty queue. Methods that would have returned null in the Java **Queue** (p. 3149) interface have been altered to return a boolean value indicating if the operation succeeded and take single argument that is a reference to the location where the returned value is to be assigned. This implies that elements in the **Queue** (p. 3149) must be *assignable* in order to utilize these methods.

Since:

1.0

6.656.2 Constructor & Destructor Documentation

6.656.2.1 `template<typename E > virtual decaf::util::Queue< E >::~~Queue ()`
`[inline, virtual]`

6.656.3 Member Function Documentation

6.656.3.1 `template<typename E > virtual E decaf::util::Queue< E >::element ()`
`const throw (decaf::lang::exceptions::NoSuchElementException) [pure`
`virtual]`

Gets but not removes the element in the head of the queue. Throws a `NoSuchElementException` if there is no element in the queue.

Returns:

the element in the head of the queue.

Exceptions:

NoSuchElementException if there is no element in the queue.

Implemented in `decaf::util::AbstractQueue< E >` (p. 196).

6.656.3.2 `template<typename E > virtual bool decaf::util::Queue< E >::offer`
`(const E & value) throw (decaf::lang::exceptions::NullPointerException,`
`decaf::lang::exceptions::IllegalArgumentException) [pure virtual]`

Inserts the specified element into the queue provided that the condition allows such an operation. The method is generally preferable to the `collection.add(E)`, since the latter might throw an exception if the operation fails.

Parameters:

value the specified element to insert into the queue.

Returns:

true if the operation succeeds and false if it fails.

Exceptions:

NullPointerException if the **Queue** (p. 3149) implementation does not allow Null values to be inserted into the **Queue** (p. 3149).

IllegalArgumentException if some property of the specified element prevents it from being added to this queue

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3721), and `decaf::util::PriorityQueue< E >` (p. 3032).

Referenced by `decaf::util::AbstractQueue< E >::add()`.

6.656.3.3 `template<typename E> virtual bool decaf::util::Queue< E >::peek (E & result) const` [pure virtual]

Gets but not removes the element in the head of the queue. The result if successful is assigned to the result parameter.

Parameters:

result Reference to an instance of the contained type to assigned the removed value to.

Returns:

true if the element at the head of the queue was removed and assigned to the result parameter.

Implemented in `decaf::util::PriorityQueue< E >` (p. 3033).

Referenced by `decaf::util::AbstractQueue< E >::element()`.

6.656.3.4 `template<typename E> virtual bool decaf::util::Queue< E >::poll (E & result)` [pure virtual]

Gets and removes the element in the head of the queue. If the operation succeeds the value of the element at the head of the **Queue** (p. 3149) is assigned to the result parameter and the method returns true. If the operation fails the method returns false and the value of the result parameter is undefined.

Parameters:

result Reference to an instance of the contained type to assigned the removed value to.

Returns:

true if the element at the head of the queue was removed and assigned to the result parameter.

Implemented in `decaf::util::concurrent::SynchronousQueue< E >` (p. 3722), and `decaf::util::PriorityQueue< E >` (p. 3033).

Referenced by `decaf::util::AbstractQueue< E >::clear()`, and `decaf::util::AbstractQueue< E >::remove()`.

6.656.3.5 `template<typename E> virtual E decaf::util::Queue< E >::remove () throw (decaf::lang::exceptions::NoSuchElementException)` [pure virtual]

Gets and removes the element in the head of the queue. Throws a `NoSuchElementException` if there is no element in the queue.

Returns:

the element in the head of the queue.

Exceptions:

NoSuchElementException if there is no element in the queue.

Implemented in `decaf::util::AbstractQueue< E >` (p. 196), and `decaf::util::PriorityQueue< E >` (p. 3034).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Queue.h`

6.657 cms::QueueBrowser Class Reference

This class implements in interface for browsing the messages in a **Queue** (p.3148) without removing them.

#include <src/main/cms/QueueBrowser.h> Inheritance diagram for cms::QueueBrowser:

Public Member Functions

- virtual ~**QueueBrowser** ()
- virtual const **Queue** * **getQueue** () const =0 throw (cms::CMSEException)
- virtual std::string **getMessageSelector** () const =0 throw (cms::CMSEException)
- virtual **cms::MessageEnumeration** * **getEnumeration** ()=0 throw (cms::CMSEException)

*Gets a pointer to an Enumeration object for browsing the Messages currently in the **Queue** (p.3148) in the order that a client would receive them.*

6.657.1 Detailed Description

This class implements in interface for browsing the messages in a **Queue** (p.3148) without removing them. To browse the contents of the **Queue** (p.3148) the client calls the **getEnumeration** method to retrieve a new instance of a **Queue** (p.3148) Enumerator. The client then calls the **hasMoreMessages** method of the Enumeration, if it returns true the client can safely call the **nextMessage** method of the Enumeration instance.

```
Enumeration* enumeration = queueBrowser->getEnumeration() (p.3153);
```

```
while( enumeration->hasMoreMessages() ) { cms::Message (p.2534)* message = enumeration->nextMessage();
```

```
// ... Do something with the Message (p.2534).
```

```
delete message; }
```

Since:

1.1

6.657.2 Constructor & Destructor Documentation

6.657.2.1 virtual cms::QueueBrowser::~~QueueBrowser () [inline, virtual]

6.657.3 Member Function Documentation

6.657.3.1 virtual cms::MessageEnumeration* cms::QueueBrowser::getEnumeration () throw (cms::CMSEException) [pure virtual]

Gets a pointer to an Enumeration object for browsing the Messages currently in the **Queue** (p.3148) in the order that a client would receive them. The pointer returned is owned by the browser and should not be deleted by the client application.

Returns:

a pointer to a **Queue** (p. 3148) Enumeration, this Pointer is owned by the **QueueBrowser** (p. 3153) and should not be deleted by the client.

Exceptions:

CMSEException (p. 1160) if an internal error occurs.

Implemented in **activemq::core::ActiveMQQueueBrowser** (p. 488).

6.657.3.2 `virtual std::string cms::QueueBrowser::getMessageSelector () const
throw (cms::CMSEException) [pure virtual]`

Returns:

the MessageSelector that is used on when this browser was created or empty string if no selector was present.

Exceptions:

CMSEException (p. 1160) if an internal error occurs.

Implemented in **activemq::core::ActiveMQQueueBrowser** (p. 488).

6.657.3.3 `virtual const Queue* cms::QueueBrowser::getQueue () const throw (
cms::CMSEException) [pure virtual]`

Returns:

the **Queue** (p. 3148) that this browser is listening on.

Exceptions:

CMSEException (p. 1160) if an internal error occurs.

Implemented in **activemq::core::ActiveMQQueueBrowser** (p. 489).

The documentation for this class was generated from the following file:

- `src/main/cms/QueueBrowser.h`

6.658 decaf::util::Random Class Reference

Random (p. 3155) Value Generator which is used to generate a stream of pseudorandom numbers.

#include <src/main/decaf/util/Random.h> Inheritance diagram for decaf::util::Random:

Public Member Functions

- **Random** ()
Construct a random generator with the current time of day in milliseconds as the initial state.
- **Random** (unsigned long long seed)
*Construct a random generator with the given **seed** as the initial state.*
- bool **nextBoolean** ()
Answers the next pseudo-random, uniformly distributed boolean value generated by this generator.
- double **nextDouble** ()
Generates a normally distributed random double number between 0.0 inclusively and 1.0 exclusively.
- float **nextFloat** ()
Generates a normally distributed random float number between 0.0 inclusively and 1.0 exclusively.
- double **nextGaussian** ()
*Pseudo-randomly generates (approximately) a normally distributed **double** value with mean 0.0 and a standard deviation value of 1.0 using the polar method of G.*
- int **nextInt** ()
*Generates a uniformly distributed 32-bit **int** value from the this random number sequence.*
- int **nextInt** (int n)
*Returns to the caller a new pseudo-random integer value which is uniformly distributed between 0 (inclusively) and the value of **n** (exclusively).*
- long long **nextLong** ()
*Generates a uniformly distributed 64-bit **int** value from the this random number sequence.*
- virtual void **nextBytes** (std::vector< unsigned char > &buf)
Modifies the byte array by a random sequence of bytes generated by this random number generator.
- virtual void **nextBytes** (unsigned char *buf, int size)
Modifies the byte array by a random sequence of bytes generated by this random number generator.
- virtual void **setSeed** (unsigned long long seed)
Modifies the seed using linear congruential formula presented in The Art of Computer Programming, Volume 2, Section 3.2.1.

Protected Member Functions

- virtual int **next** (int bits)

*Answers a pseudo-random uniformly distributed **int** value of the number of bits specified by the argument **bits** as described by Donald E.*

6.658.1 Detailed Description

Random (p. 3155) Value Generator which is used to generate a stream of pseudorandom numbers. The algorithms implemented by class **Random** (p. 3155) use a protected utility method that on each invocation can supply up to 32 pseudorandomly generated bits.

Since:

1.0

6.658.2 Constructor & Destructor Documentation

6.658.2.1 decaf::util::Random::Random ()

Construct a random generator with the current time of day in milliseconds as the initial state.

See also:

setSeed (p. 3159)

6.658.2.2 decaf::util::Random::Random (unsigned long long *seed*)

Construct a random generator with the given **seed** as the initial state.

Parameters:

seed the seed that will determine the initial state of this random number generator

See also:

setSeed (p. 3159)

6.658.3 Member Function Documentation

6.658.3.1 virtual int decaf::util::Random::next (int *bits*) [protected, virtual]

Answers a pseudo-random uniformly distributed **int** value of the number of bits specified by the argument **bits** as described by Donald E. Knuth in *The Art of Computer Programming, Volume 2: Seminumerical Algorithms*, section 3.2.1.

Returns:

int a pseudo-random generated int number

Parameters:

bits number of bits of the returned value

See also:

nextBytes (p. 3157)
nextDouble (p. 3158)
nextFloat (p. 3158)
nextInt() (p. 3159)
nextInt(int) (p. 3158)
nextGaussian (p. 3158)
nextLong (p. 3159)

Reimplemented in **decaf::security::SecureRandom** (p. 3333).

6.658.3.2 bool decaf::util::Random::nextBoolean ()

Answers the next pseudo-random, uniformly distributed boolean value generated by this generator.

Returns:

boolean a pseudo-random, uniformly distributed boolean value

6.658.3.3 virtual void decaf::util::Random::nextBytes (unsigned char * *buf*, int *size*) [virtual]

Modifies the byte array by a random sequence of bytes generated by this random number generator.

Parameters:

buf non-null array to contain the new random bytes

See also:

next (p. 3156)

Exceptions:

NullPointerException if *buff* is NULL

IllegalArgumentException if *size* is negative

Reimplemented in **decaf::security::SecureRandom** (p. 3334).

6.658.3.4 virtual void decaf::util::Random::nextBytes (std::vector< unsigned char > & *buf*) [virtual]

Modifies the byte array by a random sequence of bytes generated by this random number generator.

Parameters:

buf non-null array to contain the new random bytes

See also:

next (p. 3156)

Reimplemented in **decaf::security::SecureRandom** (p. 3334).

6.658.3.5 double decaf::util::Random::nextDouble ()

Generates a normally distributed random double number between 0.0 inclusively and 1.0 exclusively.

Returns:

double

See also:

nextFloat (p. 3158)

6.658.3.6 float decaf::util::Random::nextFloat ()

Generates a normally distributed random float number between 0.0 inclusively and 1.0 exclusively.

Returns:

float a random float number between 0.0 and 1.0

See also:

nextDouble (p. 3158)

6.658.3.7 double decaf::util::Random::nextGaussian ()

Pseudo-randomly generates (approximately) a normally distributed **double** value with mean 0.0 and a standard deviation value of 1.0 using the *polar method* of G. E. P. Box, M. E. Muller, and G. Marsaglia, as described by Donald E. Knuth in *The Art of Computer Programming, Volume 2: Seminumerical Algorithms*, section 3.4.1, subsection C, algorithm P

Returns:

double

See also:

nextDouble (p. 3158)

6.658.3.8 int decaf::util::Random::nextInt (int n)

Returns to the caller a new pseudo-random integer value which is uniformly distributed between 0 (inclusively) and the value of **n** (exclusively).

Parameters:

n The int value that defines the max value of the return.

Returns:

the next pseudo random int value.

Exceptions:

IllegalArgumentException if **n** is less than or equal to zero.

6.658.3.9 int decaf::util::Random::nextInt ()

Generates a uniformly distributed 32-bit `int` value from the this random number sequence.

Returns:

`int` uniformly distributed `int` value

See also:

`next` (p. 3156)
`nextLong` (p. 3159)

6.658.3.10 long long decaf::util::Random::nextLong ()

Generates a uniformly distributed 64-bit `int` value from the this random number sequence.

Returns:

64-bit `int` random number

See also:

`next` (p. 3156)
`nextInt()` (p. 3159)
`nextInt(int)` (p. 3158)

6.658.3.11 virtual void decaf::util::Random::setSeed (unsigned long long seed)
[virtual]

Modifies the seed using linear congruential formula presented in *The Art of Computer Programming, Volume 2*, Section 3.2.1.

Parameters:

seed the seed that alters the state of the random number generator

See also:

`next` (p. 3156)
`Random()` (p. 3156)
`Random(long)`

Reimplemented in `decaf::security::SecureRandom` (p. 3335).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Random.h`

6.659 decaf::lang::Readable Class Reference

A **Readable** (p. 3160) is a source of characters.

#include <src/main/decaf/lang/Readable.h> Inheritance diagram for decaf::lang::Readable:

Public Member Functions

- virtual **~Readable** ()
- virtual int **read** (**decaf::nio::CharBuffer** *charBuffer)=0 throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException)

Attempts to read characters into the specified character buffer.

6.659.1 Detailed Description

A **Readable** (p. 3160) is a source of characters. Characters from a **Readable** (p. 3160) are made available to callers of the read method via a CharBuffer.

Since:

1.0

6.659.2 Constructor & Destructor Documentation

6.659.2.1 virtual decaf::lang::Readable::~~Readable () [inline, virtual]

6.659.3 Member Function Documentation

6.659.3.1 virtual int decaf::lang::Readable::read (decaf::nio::CharBuffer * *charBuffer*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException) [pure virtual]

Attempts to read characters into the specified character buffer. The buffer is used as a repository of characters as-is: the only changes made are the results of a put operation. No flipping or rewinding of the buffer is performed.

Parameters:

charBuffer The Buffer to read Characters into.

Returns:

The number of char values added to the buffer, or -1 if this source of characters is at its end

Exceptions:

IOException - if an I/O error occurs

NullPointerException - if buffer is NULL.

ReadOnlyBufferException - if charBuffer is a read only buffer

Implemented in **decaf::io::Reader** (p. 3165).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Readable.h**

6.660 activemq::transport::inactivity::ReadChecker Class Reference

Runnable class that is used by the {}.

#include <src/main/activemq/transport/inactivity/ReadChecker.h>Inheritance diagram for activemq::transport::inactivity::ReadChecker:

Public Member Functions

- **ReadChecker** (**InactivityMonitor** *parent)
- virtual ~**ReadChecker** ()
- virtual void **run** ()

Run method - called by the Thread class in the context of the thread.

6.660.1 Detailed Description

Runnable class that is used by the {}.

See also:

InactivityMonitor (p. 2004)} class the check for timeouts related to **transport** (p. 97) reads.

Since:

3.1

6.660.2 Constructor & Destructor Documentation

6.660.2.1 **activemq::transport::inactivity::ReadChecker::ReadChecker** (**InactivityMonitor** * *parent*)

6.660.2.2 **virtual activemq::transport::inactivity::ReadChecker::~~ReadChecker** ()
[virtual]

6.660.3 Member Function Documentation

6.660.3.1 **virtual void activemq::transport::inactivity::ReadChecker::run** ()
[virtual]

Run method - called by the Thread class in the context of the thread.

Implements **decaf::lang::Runnable** (p. 3325).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/inactivity/**ReadChecker.h**

6.661 decaf::io::Reader Class Reference

#include <src/main/decaf/io/Reader.h> Inheritance diagram for decaf::io::Reader:

Public Member Functions

- virtual **~Reader** ()
- virtual void **mark** (int readAheadLimit) throw (decaf::io::IOException)
Marks the present position in the stream.
- virtual bool **markSupported** () const
*Tells whether this stream supports the **mark()** (p. 3165) operation.*
- virtual bool **ready** () const throw (decaf::io::IOException)
Tells whether this stream is ready to be read.
- virtual void **reset** () throw (decaf::io::IOException)
Resets the stream.
- virtual long long **skip** (long long count) throw (decaf::io::IOException)
Skips characters.
- virtual int **read** (std::vector< char > &buffer) throw (decaf::io::IOException)
Reads characters into an array.
- virtual int **read** (char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
Reads characters into an array, the method will attempt to read as much data as the size of the array.
- virtual int **read** (char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Reads characters into a portion of an array.
- virtual int **read** () throw (decaf::io::IOException)
Reads a single character.
- virtual int **read** (decaf::nio::CharBuffer *charBuffer) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException)
Attempts to read characters into the specified character buffer.

Protected Member Functions

- **Reader** ()

- virtual int **doReadArrayBounded** (char *buffer, int size, int offset, int length)=0 throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Override this method to customize the functionality of the method read(unsigned char buffer, int size, int offset, int length).*
- virtual int **doReadVector** (std::vector< char > &buffer) throw (decaf::io::IOException)
Override this method to customize the functionality of the method read(std::vector<char>& buffer) (p. 3167).
- virtual int **doReadArray** (char *buffer, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
Override this method to customize the functionality of the method read(char buffer, std::size_t length).*
- virtual int **doReadChar** () throw (decaf::io::IOException)
Override this method to customize the functionality of the method read() (p. 3166).
- virtual int **doReadCharBuffer** (decaf::nio::CharBuffer *charBuffer) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException)
Override this method to customize the functionality of the method read(CharBuffer charBuffer).*

6.661.1 Constructor & Destructor Documentation

6.661.1.1 decaf::io::Reader::Reader () [protected]

6.661.1.2 virtual decaf::io::Reader::~~Reader () [virtual]

6.661.2 Member Function Documentation

6.661.2.1 virtual int decaf::io::Reader::doReadArray (char * buffer, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException) [protected, virtual]

Override this method to customize the functionality of the method read(char* buffer, std::size_t length).

6.661.2.2 virtual int decaf::io::Reader::doReadArrayBounded (char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, pure virtual]

Override this method to customize the functionality of the method read(unsigned char* buffer, int size, int offset, int length). All subclasses must override this method to provide the basic **Reader** (p. 3163) functionality.

Implemented in **decaf::io::InputStreamReader** (p. 2054).

6.661.2.3 `virtual int decaf::io::Reader::doReadChar () throw (decaf::io::IOException)` [protected, virtual]

Override this method to customize the functionality of the method `read()` (p. 3166).

6.661.2.4 `virtual int decaf::io::Reader::doReadCharBuffer (decaf::nio::CharBuffer * charBuffer) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException)` [protected, virtual]

Override this method to customize the functionality of the method `read(CharBuffer* charBuffer)`.

6.661.2.5 `virtual int decaf::io::Reader::doReadVector (std::vector< char > & buffer) throw (decaf::io::IOException)` [protected, virtual]

Override this method to customize the functionality of the method `read(std::vector<char>& buffer)` (p. 3167).

6.661.2.6 `virtual void decaf::io::Reader::mark (int readAheadLimit) throw (decaf::io::IOException)` [virtual]

Marks the present position in the stream. Subsequent calls to `reset()` (p. 3168) will attempt to reposition the stream to this point. Not all character-input streams support the `mark()` (p. 3165) operation.

Parameters:

readAheadLimit Limit on the number of characters that may be read while still preserving the mark. After reading this many characters, attempting to reset the stream may fail.

Exceptions:

IOException (p. 2142) if an I/O error occurs, or the stream does not support mark.

6.661.2.7 `virtual bool decaf::io::Reader::markSupported () const` [inline, virtual]

Tells whether this stream supports the `mark()` (p. 3165) operation. The default implementation always returns false. Subclasses should override this method.

Returns:

true if and only if this stream supports the mark operation.

6.661.2.8 `virtual int decaf::io::Reader::read (decaf::nio::CharBuffer * charBuffer) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::nio::ReadOnlyBufferException)` [virtual]

Attempts to read characters into the specified character buffer. The buffer is used as a repository of characters as-is: the only changes made are the results of a put operation. No flipping or

rewinding of the buffer is performed.

Parameters:

charBuffer The Buffer to read Characters into.

Returns:

The number of char values added to the buffer, or -1 if this source of characters is at its end

Exceptions:

IOException (p. 2142) - if an I/O error occurs

NullPointerException - if buffer is NULL.

ReadOnlyBufferException - if charBuffer is a read only buffer

Implements **decaf::lang::Readable** (p. 3160).

6.661.2.9 virtual int decaf::io::Reader::read () throw (decaf::io::IOException)
[virtual]

Reads a single character. This method will block until a character is available, an I/O error occurs, or the end of the stream is reached.

Subclasses that intend to support efficient single-character input should override this method.

Returns:

The character read, as an integer in the range 0 to 65535 (0x00-0xffff), or -1 if the end of the stream has been reached.

Exceptions:

IOException (p. 2142) thrown if an I/O error occurs.

6.661.2.10 virtual int decaf::io::Reader::read (char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException) [virtual]

Reads characters into a portion of an array. This method will block until some input is available, an I/O error occurs, or the end of the stream is reached.

Parameters:

buffer The target char buffer.

size The size in bytes of the target buffer.

offset The position in the buffer to start filling.

length The maximum number of bytes to read.

Returns:

The number of bytes read or -1 if the end of stream is reached.

Exceptions:

IOException (p. 2142) thrown if an I/O error occurs.

NullPointerException if buffer is NULL.

IndexOutOfBoundsException if the offset + length is greater than the array size.

6.661.2.11 `virtual int decaf::io::Reader::read (char * buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)`
[virtual]

Reads characters into an array, the method will attempt to read as much data as the size of the array. This method will block until some input is available, an I/O error occurs, or the end of the stream is reached.

Parameters:

buffer The target char buffer.

size The size in bytes of the target buffer.

Returns:

The number of bytes read or -1 if the end of stream is reached.

Exceptions:

IOException (p. 2142) thrown if an I/O error occurs.

NullPointerException if buffer is NULL.

6.661.2.12 `virtual int decaf::io::Reader::read (std::vector< char > & buffer) throw (decaf::io::IOException)` [virtual]

Reads characters into an array. This method will block until some input is available, an I/O error occurs, or the end of the stream is reached.

Parameters:

buffer The buffer to read characters into.

Returns:

The number of characters read, or -1 if the end of the stream has been reached

Exceptions:

IOException (p. 2142) thrown if an I/O error occurs.

6.661.2.13 `virtual bool decaf::io::Reader::ready () const throw (decaf::io::IOException)` [virtual]

Tells whether this stream is ready to be read.

Returns:

True if the next `read()` (p. 3166) is guaranteed not to block for input, false otherwise. Note that returning false does not guarantee that the next read will block.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented in `decaf::io::InputStreamReader` (p. 2054).

**6.661.2.14 virtual void decaf::io::Reader::reset () throw (decaf::io::IOException)
[virtual]**

Resets the stream. If the stream has been marked, then attempt to reposition it at the mark. If the stream has not been marked, then attempt to reset it in some way appropriate to the particular stream, for example by repositioning it to its starting point. Not all character-input streams support the `reset()` (p. 3168) operation, and some support `reset()` (p. 3168) without supporting `mark()` (p. 3165).

Exceptions:

IOException (p. 2142) if an I/O error occurs.

6.661.2.15 virtual long long decaf::io::Reader::skip (long long count) throw (decaf::io::IOException) [virtual]

Skips characters. This method will block until some characters are available, an I/O error occurs, or the end of the stream is reached.

Parameters:

count The number of character to skip.

Returns:

the number of Character actually skipped.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The documentation for this class was generated from the following file:

- `src/main/decaf/io/Reader.h`

6.662 decaf::nio::ReadOnlyBufferException Class Reference

#include <src/main/decaf/nio/ReadOnlyBufferException.h> Inheritance diagram for decaf::nio::ReadOnlyBufferException:

Public Member Functions

- **ReadOnlyBufferException** () throw ()
Default Constructor.
- **ReadOnlyBufferException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **ReadOnlyBufferException** (const ReadOnlyBufferException &ex) throw ()
Copy Constructor.
- **ReadOnlyBufferException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ReadOnlyBufferException** (const std::exception *cause) throw ()
Constructor.
- **ReadOnlyBufferException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **ReadOnlyBufferException * clone** () const
Clones this exception.
- virtual ~**ReadOnlyBufferException** () throw ()

6.662.1 Constructor & Destructor Documentation

6.662.1.1 decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException () throw () [inline]

Default Constructor.

6.662.1.2 decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.662.1.3 `decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException (const ReadOnlyBufferException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.662.1.4 `decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.662.1.5 `decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.662.1.6 `decaf::nio::ReadOnlyBufferException::ReadOnlyBufferException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.662.1.7 virtual decaf::nio::ReadOnlyBufferException::~~ReadOnlyBufferException
() throw () [inline, virtual]

6.662.2 Member Function Documentation

6.662.2.1 virtual ReadOnlyBufferException* de-
caf::nio::ReadOnlyBufferException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Reimplemented from **decaf::lang::exceptions::UnsupportedOperationException** (p. 3918).

The documentation for this class was generated from the following file:

- src/main/decaf/nio/ReadOnlyBufferException.h

6.663 decaf::util::concurrent::locks::ReadWriteLock Class Reference

A **ReadWriteLock** (p. 3172) maintains a pair of associated **locks** (p. 174), one for read-only operations and one for writing.

```
#include <src/main/decaf/util/concurrent/locks/ReadWriteLock.h>
```

Public Member Functions

- virtual **~ReadWriteLock** ()
- virtual **Lock & readLock** ()=0
Returns the lock used for reading.
- virtual **Lock & writeLock** ()=0
Returns the lock used for writing.

6.663.1 Detailed Description

A **ReadWriteLock** (p. 3172) maintains a pair of associated **locks** (p. 174), one for read-only operations and one for writing. The read lock may be held simultaneously by multiple reader threads, so long as there are no writers. The write lock is exclusive.

All **ReadWriteLock** (p. 3172) implementations must guarantee that the memory synchronization effects of writeLock operations (as specified in the **Lock** (p. 2377) interface) also hold with respect to the associated readLock. That is, a thread successfully acquiring the read lock will see all updates made upon previous release of the write lock.

A read-write lock allows for a greater level of concurrency in accessing shared data than that permitted by a mutual exclusion lock. It exploits the fact that while only a single thread at a time (a writer thread) can modify the shared data, in many cases any number of threads can concurrently read the data (hence reader threads). In theory, the increase in concurrency permitted by the use of a read-write lock will lead to performance improvements over the use of a mutual exclusion lock. In practice this increase in concurrency will only be fully realized on a multi-processor, and then only if the access patterns for the shared data are suitable.

Whether or not a read-write lock will improve performance over the use of a mutual exclusion lock depends on the frequency that the data is read compared to being modified, the duration of the read and write operations, and the contention for the data - that is, the number of threads that will try to read or write the data at the same time. For example, a collection that is initially populated with data and thereafter infrequently modified, while being frequently searched (such as a directory of some kind) is an ideal candidate for the use of a read-write lock. However, if updates become frequent then the data spends most of its time being exclusively locked and there is little, if any increase in concurrency. Further, if the read operations are too short the overhead of the read-write lock implementation (which is inherently more complex than a mutual exclusion lock) can dominate the execution cost, particularly as many read-write lock implementations still serialize all threads through a small section of **code** (p. 1183). Ultimately, only profiling and measurement will establish whether the use of a read-write lock is suitable for your application.

Although the basic operation of a read-write lock is straight-forward, there are many policy decisions that an implementation must make, which may affect the effectiveness of the read-write lock in a given application. Examples of these policies include:

* Determining whether to grant the read lock or the write lock, when both readers and writers are waiting, at the time that a writer releases the write lock. Writer preference is common, as writes are expected to be short and infrequent. Reader preference is less common as it can lead to lengthy delays for a write if the readers are frequent and long-lived as expected. Fair, or "in-order" implementations are also possible. * Determining whether readers that request the read lock while a reader is active and a writer is waiting, are granted the read lock. Preference to the reader can delay the writer indefinitely, while preference to the writer can reduce the potential for concurrency. * Determining whether the **locks** (p. 174) are reentrant: can a thread with the write lock reacquire it? Can it acquire a read lock while holding the write lock? Is the read lock itself reentrant? * Can the write lock be downgraded to a read lock without allowing an intervening writer? Can a read lock be upgraded to a write lock, in preference to other waiting readers or writers?

You should consider all of these things when evaluating the suitability of a given implementation for your application.

Since:

1.0

6.663.2 Constructor & Destructor Documentation

6.663.2.1 `virtual decaf::util::concurrent::locks::ReadWriteLock::~~ReadWriteLock ()`
[inline, virtual]

6.663.3 Member Function Documentation

6.663.3.1 `virtual Lock& decaf::util::concurrent::locks::ReadWriteLock::readLock ()`
[pure virtual]

Returns the lock used for reading.

Returns:

the lock used for reading.

6.663.3.2 `virtual Lock& decaf::util::concurrent::locks::ReadWriteLock::writeLock ()`
[pure virtual]

Returns the lock used for writing.

Returns:

the lock used for writing.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/locks/ReadWriteLock.h`

6.664 activemq::cmsutil::CmsTemplate::ReceiveExecutor Class Reference

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate::ReceiveExecutor:

Public Member Functions

- **ReceiveExecutor** (**CmsTemplate** *parent, **cms::Destination** *destination, const std::string &selector, bool noLocal)
- virtual ~**ReceiveExecutor** ()
- virtual void **doInCms** (**cms::Session** *session) throw (cms::CMSException)

Execute any number of operations against the supplied CMS session.

- virtual **cms::Destination** * **getDestination** (**cms::Session** *session AMQCPP_UNUSED) throw (cms::CMSException)
- **cms::Message** * **getMessage** ()

Protected Member Functions

- **ReceiveExecutor** (const **ReceiveExecutor** &)
- **ReceiveExecutor** & **operator=** (const **ReceiveExecutor** &)

Protected Attributes

- **cms::Destination** * destination
- std::string selector
- bool noLocal
- **cms::Message** * message
- **CmsTemplate** * parent

6.664.1 Constructor & Destructor Documentation

- 6.664.1.1** `activemq::cmsutil::CmsTemplate::ReceiveExecutor::ReceiveExecutor (const ReceiveExecutor &) [inline, protected]`
- 6.664.1.2** `activemq::cmsutil::CmsTemplate::ReceiveExecutor::ReceiveExecutor (CmsTemplate * parent, cms::Destination * destination, const std::string & selector, bool noLocal) [inline]`
- 6.664.1.3** `virtual
activemq::cmsutil::CmsTemplate::ReceiveExecutor::~~ReceiveExecutor ()
[inline, virtual]`

6.664.2 Member Function Documentation

- 6.664.2.1** `virtual void activemq::cmsutil::CmsTemplate::ReceiveExecutor::doInCms (cms::Session * session) throw (cms::CMSException) [virtual]`

Execute any number of operations against the supplied CMS session.

Parameters:

session the CMS Session

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

Implements `activemq::cmsutil::SessionCallback` (p. 3378).

- 6.664.2.2** `virtual cms::Destination* activemq::cmsutil::CmsTemplate::ReceiveExecutor::getDestination (cms::Session *session AMQCPP_UNUSED) throw (cms::CMSException) [inline, virtual]`
- 6.664.2.3** `cms::Message* activemq::cmsutil::CmsTemplate::ReceiveExecutor::getMessage () [inline]`
- 6.664.2.4** `ReceiveExecutor& activemq::cmsutil::CmsTemplate::ReceiveExecutor::operator= (const ReceiveExecutor &) [inline, protected]`

Reimplemented in `activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor` (p. 3279).

6.664.3 Field Documentation

- 6.664.3.1 `cms::Destination*` `activemq::cmsutil::CmsTemplate::ReceiveExecutor::destination`
[protected]
- 6.664.3.2 `cms::Message*` `activemq::cmsutil::CmsTemplate::ReceiveExecutor::message`
[protected]
- 6.664.3.3 `bool` `activemq::cmsutil::CmsTemplate::ReceiveExecutor::noLocal`
[protected]
- 6.664.3.4 `CmsTemplate*` `activemq::cmsutil::CmsTemplate::ReceiveExecutor::parent`
[protected]
- 6.664.3.5 `std::string` `activemq::cmsutil::CmsTemplate::ReceiveExecutor::selector`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsTemplate.h`

6.665 activemq::core::RedeliveryPolicy Class Reference

Interface for a **RedeliveryPolicy** (p. 3177) object that controls how message Redelivery is handled in ActiveMQ-CPP when a transaction is rolled back.

#include <src/main/activemq/core/RedeliveryPolicy.h> Inheritance diagram for activemq::core::RedeliveryPolicy:

Public Member Functions

- virtual **~RedeliveryPolicy** ()
- virtual double **getBackOffMultiplier** () const =0
- virtual void **setBackOffMultiplier** (double value)=0
Sets the Back-Off Multiplier for Message Redelivery.
- virtual short **getCollisionAvoidancePercent** () const =0
- virtual void **setCollisionAvoidancePercent** (short value)=0
- virtual long long **getInitialRedeliveryDelay** () const =0
Gets the initial time that redelivery of messages is delayed.
- virtual void **setInitialRedeliveryDelay** (long long value)=0
Sets the initial time that redelivery will be delayed.
- virtual int **getMaximumRedeliveries** () const =0
Gets the Maximum number of allowed redeliveries for a message before it will be discarded by the consumer.
- virtual void **setMaximumRedeliveries** (int maximumRedeliveries)=0
Sets the Maximum allowable redeliveries for a Message.
- virtual long long **getRedeliveryDelay** (long long previousDelay)=0
Given the last used redelivery delay calculate the next value of the delay based on the settings in this Policy instance.
- virtual bool **isUseCollisionAvoidance** () const =0
- virtual void **setUseCollisionAvoidance** (bool value)=0
- virtual bool **isUseExponentialBackOff** () const =0
- virtual void **setUseExponentialBackOff** (bool value)=0
- virtual **RedeliveryPolicy** * **clone** () const =0
Create a copy of this Policy and return it.
- virtual void **configure** (const **decaf::util::Properties** &properties)
Checks the supplied properties object for properties matching the configurable settings of this class.

Static Public Attributes

- static const long long **NO_MAXIMUM_REDELIVERIES**

Protected Member Functions

- **RedeliveryPolicy** ()

6.665.1 Detailed Description

Interface for a **RedeliveryPolicy** (p. 3177) object that controls how message Redelivery is handled in ActiveMQ-CPP when a transaction is rolled back.

Since:

3.2.0

6.665.2 Constructor & Destructor Documentation

6.665.2.1 `activemq::core::RedeliveryPolicy::RedeliveryPolicy ()` [protected]

6.665.2.2 `virtual activemq::core::RedeliveryPolicy::~~RedeliveryPolicy ()` [virtual]

6.665.3 Member Function Documentation

6.665.3.1 `virtual RedeliveryPolicy* activemq::core::RedeliveryPolicy::clone () const`
[pure virtual]

Create a copy of this Policy and return it.

Returns:

pointer to a new **RedeliveryPolicy** (p. 3177) that is a copy of this one.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1678).

6.665.3.2 `virtual void activemq::core::RedeliveryPolicy::configure (const decaf::util::Properties & properties)` [virtual]

Checks the supplied properties object for properties matching the configurable settings of this class. The default implementation looks for properties named with the prefix `cms.RedeliveryPolicy.XXX` where XXX is the name of a property with a public setter method. For instance `cms.RedeliveryPolicy.useExponentialBackOff` will be used to set the value of the use exponential back off toggle.

Subclasses can override this method to add more configuration options or to exclude certain parameters from being set via the properties object.

Parameters:

properties The Properties object used to configure this object.

Exceptions:

NumberFormatException if a property that is numeric cannot be converted

IllegalArgumentException if a property can't be converted to the correct type.

6.665.3.3 `virtual double activemq::core::RedeliveryPolicy::getBackOffMultiplier () const` [pure virtual]

Returns:

The value of the Back-Off Multiplier for Message Redelivery.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1678).

6.665.3.4 `virtual short activemq::core::RedeliveryPolicy::getCollisionAvoidancePercent () const` [pure virtual]

Returns:

the currently set Collision Avoidance percentage.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1678).

6.665.3.5 `virtual long long activemq::core::RedeliveryPolicy::getInitialRedeliveryDelay () const` [pure virtual]

Gets the initial time that redelivery of messages is delayed.

Returns:

the time in milliseconds that redelivery is delayed initially.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1678).

6.665.3.6 `virtual int activemq::core::RedeliveryPolicy::getMaximumRedeliveries () const` [pure virtual]

Gets the Maximum number of allowed redeliveries for a message before it will be discarded by the consumer.

Returns:

maximum allowed redeliveries for a message.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1679).

6.665.3.7 `virtual long long activemq::core::RedeliveryPolicy::getRedeliveryDelay (long long previousDelay)` [pure virtual]

Given the last used redelivery delay calculate the next value of the delay based on the settings in this Policy instance.

Parameters:

previousDelay The last delay that was used between message redeliveries.

Returns:

the new delay to use before attempting another redelivery.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1679).

6.665.3.8 `virtual bool activemq::core::RedeliveryPolicy::isUseCollisionAvoidance () const` [pure virtual]

Returns:

whether or not collision avoidance is enabled for this Policy.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1679).

6.665.3.9 `virtual bool activemq::core::RedeliveryPolicy::isUseExponentialBackOff () const` [pure virtual]

Returns:

whether or not the exponential back off option is enabled.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1679).

6.665.3.10 `virtual void activemq::core::RedeliveryPolicy::setBackOffMultiplier (double value)` [pure virtual]

Sets the Back-Off Multiplier for Message Redelivery.

Parameters:

value The new value for the back-off multiplier.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1679).

6.665.3.11 `virtual void activemq::core::RedeliveryPolicy::setCollisionAvoidancePercent (short value)` [pure virtual]

Parameters:

value The collision avoidance percentage setting.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1680).

6.665.3.12 `virtual void activemq::core::RedeliveryPolicy::setInitialRedeliveryDelay (long long value)` [pure virtual]

Sets the initial time that redelivery will be delayed.

Parameters:

value Time in Milliseconds to wait before starting redelivery.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1680).

6.665.3.13 `virtual void activemq::core::RedeliveryPolicy::setMaximumRedeliveries(int maximumRedeliveries)` [pure virtual]

Sets the Maximum allowable redeliveries for a Message.

Parameters:

maximumRedeliveries The maximum number of times that a message will be redelivered.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1680).

6.665.3.14 `virtual void activemq::core::RedeliveryPolicy::setUseCollisionAvoidance(bool value)` [pure virtual]

Parameters:

value Enable or Disable collision avoidance for this Policy.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1680).

6.665.3.15 `virtual void activemq::core::RedeliveryPolicy::setUseExponentialBackOff(bool value)` [pure virtual]

Parameters:

value Enable or Disable the exponential back off multiplier option.

Implemented in `activemq::core::policies::DefaultRedeliveryPolicy` (p. 1681).

6.665.4 Field Documentation

6.665.4.1 `const long long activemq::core::RedeliveryPolicy::NO_MAXIMUM_REDELIVERIES` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/core/RedeliveryPolicy.h`

6.666 decaf::util::concurrent::locks::ReentrantLock Class Reference

A reentrant mutual exclusion **Lock** (p. 2377) with extended capabilities.

#include <src/main/decaf/util/concurrent/locks/ReentrantLock.h> Inheritance diagram for decaf::util::concurrent::locks::ReentrantLock:

Public Member Functions

- **ReentrantLock** ()
- virtual **~ReentrantLock** ()
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Acquires the lock.
- virtual void **lockInterruptibly** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException)
Acquires the lock unless the current thread is interrupted.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Acquires the lock only if it is not held by another thread at the time of invocation.
- virtual bool **tryLock** (long long time, const **TimeUnit** &unit) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException)
Acquires the lock if it is not held by another thread within the given waiting time and the current thread has not been interrupted.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Attempts to release this lock.
- virtual **Condition** * **newCondition** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::UnsupportedOperationException)
*Returns a **Condition** (p. 1249) instance for use with this **Lock** (p. 2377) instance.*
- int **getHoldCount** () const
Queries the number of holds on this lock by the current thread.
- bool **isHeldByCurrentThread** () const
Queries if this lock is held by the current thread.
- bool **isLocked** () const
Queries if this lock is held by any thread.
- bool **isFair** () const
Returns true if this lock has fairness set true.
- std::string **toString** () const
Returns a string identifying this lock, as well as its lock state.

6.666.1 Detailed Description

A reentrant mutual exclusion **Lock** (p.2377) with extended capabilities. A **ReentrantLock** (p.3182) is owned by the thread last successfully locking, but not yet unlocking it. A thread invoking lock will return, successfully acquiring the lock, when the lock is not owned by another thread. The method will return immediately if the current thread already owns the lock. This can be checked using methods **isHeldByCurrentThread()** (p.3184), and **getHoldCount()** (p.3183).

The constructor for this class accepts an optional fairness parameter. When set true, under contention, **locks** (p.174) favor granting access to the longest-waiting thread. Otherwise this lock does not guarantee any particular access order. Programs using fair **locks** (p.174) accessed by many threads may display lower overall throughput (i.e., are slower; often much slower) than those using the default setting, but have smaller variances in times to obtain **locks** (p.174) and guarantee lack of starvation. Note however, that fairness of **locks** (p.174) does not guarantee fairness of thread scheduling. Thus, one of many threads using a fair lock may obtain it multiple times in succession while other active threads are not progressing and not currently holding the lock. Also note that the untimed tryLock method does not honor the fairness setting. It will succeed if the lock is available even if other threads are waiting.

It is recommended practice to always immediately follow a call to lock with a try block, most typically in a before/after construction such as:

```
class X { private:
ReentrantLock (p.3182) lock; // ...

public:

void m() { lock.lock(); // block until condition holds

try { // ... method body } finally { lock.unlock() } } }
```

In addition to implementing the **Lock** (p.2377) interface, this class defines methods **isLocked** and **getLockQueueLength**, as well as some associated protected access methods that may be useful for instrumentation and monitoring.

Since:

1.0

6.666.2 Constructor & Destructor Documentation

6.666.2.1 decaf::util::concurrent::locks::ReentrantLock::ReentrantLock ()

6.666.2.2 virtual decaf::util::concurrent::locks::ReentrantLock::~ReentrantLock ()
[virtual]

6.666.3 Member Function Documentation

6.666.3.1 int decaf::util::concurrent::locks::ReentrantLock::getHoldCount () const

Queries the number of holds on this lock by the current thread. A thread has a hold on a lock for each lock action that is not matched by an unlock action.

The hold count information is typically only used for testing and debugging purposes. For example, if a certain section of **code** (p.1183) should not be entered with the lock already held then we can assert that fact:

```
class X { private:
ReentrantLock (p. 3182) lock; // ...
public:
void m() { assert( lock.getHoldCount() == 0 ); lock.lock(); try { // ... method body } catch(...)
{ lock.unlock(); } } }
```

Returns:

the number of holds on this lock by the current thread, or zero if this lock is not held by the current thread

6.666.3.2 bool decaf::util::concurrent::locks::ReentrantLock::isFair () const

Returns true if this lock has fairness set true.

Returns:

true if this lock has fairness set true

6.666.3.3 bool decaf::util::concurrent::locks::ReentrantLock::isHeldByCurrentThread () const

Queries if this lock is held by the current thread. This method is typically used for debugging and testing. For example, a method that should only be called while a lock is held can assert that this is the case:

```
class X { private: ReentrantLock (p. 3182) lock = new ReentrantLock() (p. 3183); // ...
public: void m() { assert( lock.isHeldByCurrentThread() ); // ... method body } }
```

It can also be used to ensure that a reentrant lock is used in a non-reentrant manner, for example:

```
class X { private: ReentrantLock (p. 3182) lock = new ReentrantLock() (p. 3183); // ...
public: void m() { assert !lock.isHeldByCurrentThread() (p. 3184); lock.lock(); try { // ...
method body } finally { lock.unlock(); } } }
```

Returns:

true if current thread holds this lock and false otherwise

6.666.3.4 bool decaf::util::concurrent::locks::ReentrantLock::isLocked () const

Queries if this lock is held by any thread. This method is designed for use in monitoring of the system state, not for synchronization control.

Returns:

true if any thread holds this lock and false otherwise

6.666.3.5 virtual void decaf::util::concurrent::locks::ReentrantLock::lock () throw (decaf::lang::exceptions::RuntimeException) [virtual]

Acquires the lock. Acquires the lock if it is not held by another thread and returns immediately, setting the lock hold count to one.

If the current thread already holds the lock then the hold count is incremented by one and the method returns immediately.

If the lock is held by another thread then the current thread becomes disabled for thread scheduling purposes and lies dormant until the lock has been acquired, at which time the lock hold count is set to one.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

Implements **decaf::util::concurrent::locks::Lock** (p. 2378).

6.666.3.6 virtual void decaf::util::concurrent::locks::ReentrantLock::lockInterruptibly () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException) [virtual]

Acquires the lock unless the current thread is interrupted. Acquires the lock if it is not held by another thread and returns immediately, setting the lock hold count to one.

If the current thread already holds this lock then the hold count is incremented by one and the method returns immediately.

If the lock is held by another thread then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of two things happens:

* The lock is acquired by the current thread; or * Some other thread interrupts the current thread.

If the lock is acquired by the current thread then the lock hold count is set to one.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while acquiring the lock,

then *InterruptedException* is thrown and the current thread's interrupted status is cleared.

In this implementation, as this method is an explicit interruption point, preference is given to responding to the interrupt over normal or reentrant acquisition of the lock.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

InterruptedException if the current thread is interrupted while acquiring the lock (and interruption of lock acquisition is supported).

Implements **decaf::util::concurrent::locks::Lock** (p. 2379).

6.666.3.7 `virtual Condition* decaf::util::concurrent::locks::ReentrantLock::newCondition()` `throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

Returns a **Condition** (p. 1249) instance for use with this **Lock** (p. 2377) instance. The returned **Condition** (p. 1249) instance supports the same usages as do the **Mutex** (p. 2782) Class' methods (wait, notify, and notifyAll).

* If this lock is not held when any of the **Condition** (p. 1249) waiting or signalling methods are called, then an `IllegalMonitorStateException` is thrown. * When the condition waiting methods are called the lock is released and, before they return, the lock is reacquired and the lock hold count restored to what it was when the method was called. * If a thread is interrupted while waiting then the wait will terminate, an `InterruptedException` will be thrown, and the thread's interrupted status will be cleared. * Waiting threads are signaled in FIFO order. * The ordering of lock reacquisition for threads returning from waiting methods is the same as for threads initially acquiring the lock, which is in the default case not specified, but for fair **locks** (p. 174) favors those threads that have been waiting the longest.

Exceptions:

RuntimeException if an error occurs while creating the **Condition** (p. 1249).

UnsupportedOperationException if this **Lock** (p. 2377) implementation does not support conditions

Implements `decaf::util::concurrent::locks::Lock` (p. 2379).

6.666.3.8 `std::string decaf::util::concurrent::locks::ReentrantLock::toString() const`

Returns a string identifying this lock, as well as its lock state. The state, in brackets, includes either the String "Unlocked" or the String "Locked by" followed by the name of the owning thread.

Returns:

a string identifying this lock, as well as its lock state

6.666.3.9 `virtual bool decaf::util::concurrent::locks::ReentrantLock::tryLock(long long time, const TimeUnit & unit) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::InterruptedException)` [virtual]

Acquires the lock if it is not held by another thread within the given waiting time and the current thread has not been interrupted. Acquires the lock if it is not held by another thread and returns immediately with the value true, setting the lock hold count to one. If this lock has been set to use a fair ordering policy then an available lock will not be acquired if any other threads are waiting for the lock. This is in contrast to the **tryLock()** (p. 3187) method. If you want a timed tryLock that does permit barging on a fair lock then combine the timed and un-timed forms together:

```
if (lock.tryLock() || lock.tryLock(timeout, unit) ) { ... }
```

If the current thread already holds this lock then the hold count is incremented by one and the method returns true.

If the lock is held by another thread then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

* The lock is acquired by the current thread; or * Some other thread interrupts the current thread;
or * The specified waiting time elapses

If the lock is acquired then the value true is returned and the lock hold count is set to one.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while acquiring the lock,

then InterruptedException is thrown and the current thread's interrupted status is cleared.

If the specified waiting time elapses then the value false is returned. If the time is less than or equal to zero, the method will not wait at all.

In this implementation, as this method is an explicit interruption point, preference is given to responding to the interrupt over normal or reentrant acquisition of the lock, and over reporting the elapse of the waiting time.

Parameters:

time the maximum time to wait for the lock

unit the time unit of the time argument

Returns:

true if the lock was acquired and false if the waiting time elapsed before the lock was acquired

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

InterruptedException if the current thread is interrupted while acquiring the lock (and interruption of lock acquisition is supported)

Implements **decaf::util::concurrent::locks::Lock** (p. 2380).

6.666.3.10 virtual bool decaf::util::concurrent::locks::ReentrantLock::tryLock () throw (decaf::lang::exceptions::RuntimeException) [virtual]

Acquires the lock only if it is not held by another thread at the time of invocation. Acquires the lock if it is not held by another thread and returns immediately with the value true, setting the lock hold count to one. Even when this lock has been set to use a fair ordering policy, a call to **tryLock()** (p. 3187) will immediately acquire the lock if it is available, whether or not other threads are currently waiting for the lock. This "barging" behavior can be useful in certain circumstances, even though it breaks fairness. If you want to honor the fairness setting for this lock, then use **tryLock(0, TimeUnit.SECONDS)** (p. 3816) which is almost equivalent (it also detects interruption).

If the current thread already holds this lock then the hold count is incremented by one and the method returns true.

If the lock is held by another thread then this method will return immediately with the value false.

Returns:

true if the lock was acquired and false otherwise

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

Implements **decaf::util::concurrent::locks::Lock** (p. 2381).

6.666.3.11 **virtual void decaf::util::concurrent::locks::ReentrantLock::unlock**
 () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [virtual]

Attempts to release this lock. If the current thread is the holder of this lock then the hold count is decremented. If the hold count is now zero then the lock is released. If the current thread is not the holder of this lock then `IllegalMonitorStateException` is thrown.

Exceptions:

RuntimeException if an error occurs while acquiring the lock.

Implements **decaf::util::concurrent::locks::Lock** (p. 2381).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/locks/ReentrantLock.h`

6.667 decaf::util::concurrent::RejectedExecutionException Class Reference

#include <src/main/decaf/util/concurrent/RejectedExecutionException.h> Inheritance diagram for decaf::util::concurrent::RejectedExecutionException:

Public Member Functions

- **RejectedExecutionException** () throw ()
Default Constructor.
- **RejectedExecutionException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **RejectedExecutionException** (const **RejectedExecutionException** &ex) throw ()
Copy Constructor.
- **RejectedExecutionException** (const std::exception *cause) throw ()
Constructor.
- **RejectedExecutionException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **RejectedExecutionException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **RejectedExecutionException** * clone () const
Clones this exception.
- virtual ~**RejectedExecutionException** () throw ()

6.667.1 Constructor & Destructor Documentation

6.667.1.1 decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException () throw () [inline]

Default Constructor.

6.667.1.2 decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References `decaf::lang::Exception::Exception()`.

6.667.1.3 `decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException (const RejectedExecutionException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex - The Exception to copy in this new instance.

References `decaf::lang::Exception::Exception()`.

6.667.1.4 `decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.667.1.5 `decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

msg - The message to report

... - list of primitives that are formatted into the message

6.667.1.6 `decaf::util::concurrent::RejectedExecutionException::RejectedExecutionException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file - The file name where exception occurs

lineNumber - The line number where the exception occurred.

cause - The exception that was the cause for this one to be thrown.

msg - The message to report

... - list of primitives that are formatted into the message

6.667.1.7 virtual
decaf::util::concurrent::RejectedExecutionException::~RejectedExecutionException
() throw () [inline, virtual]

6.667.2 Member Function Documentation

6.667.2.1 virtual RejectedExecutionException* de-
caf::util::concurrent::RejectedExecutionException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A new instance this exception type with a copy the current state.

Reimplemented from **decaf::lang::Exception** (p. 1834).

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/**RejectedExecutionException.h**

6.668 decaf::util::concurrent::RejectedExecutionHandler Class Reference

A handler for tasks that cannot be executed by a **ThreadPoolExecutor** (p. ??).

#include <src/main/decaf/util/concurrent/RejectedExecutionHandler.h>

Public Member Functions

- virtual **~RejectedExecutionHandler** ()
- virtual void **rejectedExecution** (Runnable *r, ThreadPoolExecutor *executer)=0 throw (RejectedExecutionException)

*Method that may be invoked by a **ThreadPoolExecutor** (p. ??) when **execute** (p. ??) cannot accept a task.*

6.668.1 Detailed Description

A handler for tasks that cannot be executed by a **ThreadPoolExecutor** (p. ??).

Since:

1.0

6.668.2 Constructor & Destructor Documentation

- 6.668.2.1** virtual
decaf::util::concurrent::RejectedExecutionHandler::~~RejectedExecutionHandler
() [inline, virtual]

6.668.3 Member Function Documentation

- 6.668.3.1** virtual void de-
caf::util::concurrent::RejectedExecutionHandler::rejectedExecution
(Runnable * r, ThreadPoolExecutor * *executer*) throw (RejectedExecutionException) [pure virtual]

Method that may be invoked by a **ThreadPoolExecutor** (p. ??) when **execute** (p. ??) cannot accept a task. This may occur when no more threads or queue slots are available because their bounds would be exceeded, or upon shutdown of the **Executor** (p. 1869).

In the absence of other alternatives, the method may throw an **RejectedExecutionException** (p. 3189), which will be propagated to the caller of **execute** (p. ??).

Parameters:

r The pointer to the runnable task requested to be executed.

executer The pointer to the executor attempting to execute this task.

Exceptions:

RejectedExecutionException (p. 3189) if there is no remedy.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/RejectedExecutionHandler.h`

6.669 activemq::commands::RemoveInfo Class Reference

#include <src/main/activemq/commands/RemoveInfo.h> Inheritance diagram for activemq::commands::RemoveInfo:

Public Member Functions

- **RemoveInfo** ()
- virtual **~RemoveInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **RemoveInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **DataStructure** > & **getObjectId** () const
- virtual **Pointer**< **DataStructure** > & **getObjectId** ()
- virtual void **setObjectId** (const **Pointer**< **DataStructure** > &objectId)
- virtual long long **getLastDeliveredSequenceId** () const
- virtual void **setLastDeliveredSequenceId** (long long lastDeliveredSequenceId)
- virtual bool **isRemoveInfo** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_REMOVEINFO** = 12

Protected Attributes

- **Pointer**< **DataStructure** > **objectId**
- long long **lastDeliveredSequenceId**

6.669.1 Constructor & Destructor Documentation

6.669.1.1 `activemq::commands::RemoveInfo::RemoveInfo ()`

6.669.1.2 `virtual activemq::commands::RemoveInfo::~~RemoveInfo ()` [virtual]

6.669.2 Member Function Documentation

6.669.2.1 `virtual RemoveInfo* activemq::commands::RemoveInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.669.2.2 `virtual void activemq::commands::RemoveInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.669.2.3 `virtual bool activemq::commands::RemoveInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.669.2.4 `virtual unsigned char activemq::commands::RemoveInfo::getDataStructureType ()`
`const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements `activemq::commands::DataStructure` (p. 1662).

6.669.2.5 `virtual long long activemq::commands::RemoveInfo::getLastDeliveredSequenceId () const`
[virtual]

6.669.2.6 `virtual Pointer<DataStructure>& activemq::commands::RemoveInfo::getObjectId ()`
[virtual]

6.669.2.7 `virtual const Pointer<DataStructure>& activemq::commands::RemoveInfo::getObjectId () const`
[virtual]

6.669.2.8 `virtual bool activemq::commands::RemoveInfo::isRemoveInfo () const`
[inline, virtual]

Returns:

an answer of true to the `isRemoveInfo()` (p. 3196) query.

Reimplemented from `activemq::commands::BaseCommand` (p. 762).

6.669.2.9 `virtual void activemq::commands::RemoveInfo::setLastDeliveredSequenceId (long long lastDeliveredSequenceId)` [virtual]

6.669.2.10 `virtual void activemq::commands::RemoveInfo::setObjectId (const Pointer< DataStructure > & objectId)` [virtual]

6.669.2.11 `virtual std::string activemq::commands::RemoveInfo::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

6.669.2.12 `virtual Pointer<Command> activemq::commands::RemoveInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements `activemq::commands::Command` (p.1198).

6.669.3 Field Documentation

- 6.669.3.1 `const unsigned char activemq::commands::RemoveInfo::ID_REMOVEINFO = 12` [static]
- 6.669.3.2 `long long activemq::commands::RemoveInfo::lastDeliveredSequenceId` [protected]
- 6.669.3.3 `Pointer<DataStructure> activemq::commands::RemoveInfo::objectId` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/RemoveInfo.h`

6.670 activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3198).

#include <src/main/activemq/wireformat/openwire/marshal/v2/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.670.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3198). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.670.2 Constructor & Destructor Documentation

6.670.2.1 `activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::RemoveInfoMarshaller()` `[inline]`

6.670.2.2 `virtual activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` `[inline, virtual]`

6.670.3 Member Function Documentation

6.670.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.670.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.670.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.670.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.670.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.670.3.6 virtual void activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p.804).

6.670.3.7 virtual void activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p.805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**RemoveInfoMarshaller.h**

6.671 activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3202).

#include <src/main/activemq/wireformat/openwire/marshal/v6/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.671.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3202). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.671.2 Constructor & Destructor Documentation

6.671.2.1 `activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::RemoveInfoMarshaller()` [inline]

6.671.2.2 `virtual activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` [inline, virtual]

6.671.3 Member Function Documentation

6.671.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.671.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.671.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.671.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.671.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.671.3.6 virtual void activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.671.3.7 virtual void activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**RemoveInfoMarshaller.h**

6.672 activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3206).

#include <src/main/activemq/wireformat/openwire/marshal/v3/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.672.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3206). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.672.2 Constructor & Destructor Documentation

6.672.2.1 `activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::RemoveInfoMarshaller()` `[inline]`

6.672.2.2 `virtual activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` `[inline, virtual]`

6.672.3 Member Function Documentation

6.672.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.672.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.672.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.672.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.672.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.672.3.6 virtual void activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.672.3.7 virtual void activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**RemoveInfoMarshaller.h**

6.673 activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3210).

#include <src/main/activemq/wireformat/openwire/marshal/v1/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.673.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3210). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.673.2 Constructor & Destructor Documentation

6.673.2.1 `activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::RemoveInfoMarshaller()` [inline]

6.673.2.2 `virtual activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` [inline, virtual]

6.673.3 Member Function Documentation

6.673.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.673.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.673.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.673.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.673.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.673.3.6 virtual void activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.673.3.7 virtual void activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**RemoveInfoMarshaller.h**

6.674 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3214).

#include <src/main/activemq/wireformat/openwire/marshal/v5/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.674.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3214). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.674.2 Constructor & Destructor Documentation

6.674.2.1 `activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::RemoveInfoMarshaller()` `[inline]`

6.674.2.2 `virtual activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` `[inline, virtual]`

6.674.3 Member Function Documentation

6.674.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.674.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.674.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.674.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.674.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.674.3.6 virtual void activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.674.3.7 virtual void activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**RemoveInfoMarshaller.h**

6.675 activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3218).

#include <src/main/activemq/wireformat/openwire/marshal/v4/RemoveInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller:

Public Member Functions

- **RemoveInfoMarshaller** ()
- virtual **~RemoveInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.675.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3218). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.675.2 Constructor & Destructor Documentation

6.675.2.1 `activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::RemoveInfoMarshaller()` [inline]

6.675.2.2 `virtual activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::~~RemoveInfoMarshaller()` [inline, virtual]

6.675.3 Member Function Documentation

6.675.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.675.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.675.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.675.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.675.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.675.3.6 virtual void activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p.776).

6.675.3.7 virtual void activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p.777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**RemoveInfoMarshaller.h**

6.676 activemq::commands::RemoveSubscriptionInfo Class Reference

#include <src/main/activemq/commands/RemoveSubscriptionInfo.h> Inheritance diagram for activemq::commands::RemoveSubscriptionInfo:

Public Member Functions

- **RemoveSubscriptionInfo** ()
- virtual **~RemoveSubscriptionInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **RemoveSubscriptionInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConnectionId** > & **getConnectionId** () const
- virtual **Pointer**< **ConnectionId** > & **getConnectionId** ()
- virtual void **setConnectionId** (const **Pointer**< **ConnectionId** > &connectionId)
- virtual const std::string & **getSubscriptionName** () const
- virtual std::string & **getSubscriptionName** ()
- virtual void **setSubscriptionName** (const std::string &subscriptionName)
- virtual const std::string & **getClientId** () const
- virtual std::string & **getClientId** ()
- virtual void **setClientId** (const std::string &clientId)
- virtual bool **isRemoveSubscriptionInfo** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_REMOVESUBSCRIPTIONINFO** = 9

Protected Attributes

- `Pointer< ConnectionId > connectionId`
- `std::string subscriptionName`
- `std::string clientId`

6.676.1 Constructor & Destructor Documentation

6.676.1.1 `activemq::commands::RemoveSubscriptionInfo::RemoveSubscriptionInfo()`

6.676.1.2 `virtual`
`activemq::commands::RemoveSubscriptionInfo::~~RemoveSubscriptionInfo()` `[virtual]`

6.676.2 Member Function Documentation

6.676.2.1 `virtual RemoveSubscriptionInfo* activemq::commands::RemoveSubscriptionInfo::cloneDataStructure()` `const` `[virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.676.2.2 `virtual void activemq::commands::RemoveSubscriptionInfo::copyDataStructure(const DataStructure * src)` `[virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.676.2.3 `virtual bool activemq::commands::RemoveSubscriptionInfo::equals(const DataStructure * value)` `const` `[virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.676.2.4** `virtual std::string& activemq::commands::RemoveSubscriptionInfo::getClientId () [virtual]`
- 6.676.2.5** `virtual const std::string& activemq::commands::RemoveSubscriptionInfo::getClientId () const [virtual]`
- 6.676.2.6** `virtual Pointer<ConnectionId>& activemq::commands::RemoveSubscriptionInfo::getConnectionId () [virtual]`
- 6.676.2.7** `virtual const Pointer<ConnectionId>& activemq::commands::RemoveSubscriptionInfo::getConnectionId () const [virtual]`
- 6.676.2.8** `virtual unsigned char activemq::commands::RemoveSubscriptionInfo::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.676.2.9** `virtual std::string& activemq::commands::RemoveSubscriptionInfo::getSubscriptionName () [virtual]`
- 6.676.2.10** `virtual const std::string& activemq::commands::RemoveSubscriptionInfo::getSubscriptionName () const [virtual]`
- 6.676.2.11** `virtual bool activemq::commands::RemoveSubscriptionInfo::isRemoveSubscriptionInfo () const [inline, virtual]`

Returns:

an answer of true to the **isRemoveSubscriptionInfo()** (p. 3224) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 762).

6.676.2.12 virtual void activemq::commands::RemoveSubscriptionInfo::setClientId (const std::string & *clientId*) [virtual]

6.676.2.13 virtual void activemq::commands::RemoveSubscriptionInfo::setConnectionId (const Pointer< ConnectionId > & *connectionId*) [virtual]

6.676.2.14 virtual void activemq::commands::RemoveSubscriptionInfo::setSubscriptionName (const std::string & *subscriptionName*) [virtual]

6.676.2.15 virtual std::string activemq::commands::RemoveSubscriptionInfo::toString () const [virtual]

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.676.2.16 virtual Pointer<Command> activemq::commands::RemoveSubscriptionInfo::visit (activemq::state::CommandVisitor * *visitor*) throw (exceptions::ActiveMQException) [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.676.3 Field Documentation

- 6.676.3.1** `std::string activemq::commands::RemoveSubscriptionInfo::clientId`
[protected]
- 6.676.3.2** `Pointer<ConnectionId> activemq::commands::RemoveSubscriptionInfo::connectionId`
[protected]
- 6.676.3.3** `const unsigned char activemq::commands::RemoveSubscriptionInfo::ID_REMOVE_SUBSCRIPTION_INFO = 9` [static]
- 6.676.3.4** `std::string activemq::commands::RemoveSubscriptionInfo::subscriptionName`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/RemoveSubscriptionInfo.h`

6.677

activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller

Class Reference

3229

6.677 ~~activemq::wireformat::openwire::marshal::v1::RemoveSubscription~~

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3227).

#include <src/main/activemq/wireformat/openwire/marshal/v1/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
 - virtual **~RemoveSubscriptionInfoMarshaller** ()
 - virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.677.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3227). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.677.2 Constructor & Destructor Documentation

6.677.2.1 `activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfoMarshaller()` [inline]

6.677.2.2 `virtual activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfoMarshaller()` [inline, virtual]

6.677.3 Member Function Documentation

6.677.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.677.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.677.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.677

activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller

Class Reference

3231

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

6.677.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

6.677.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

6.677.3.6 virtual void activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.677.3.7 virtual void activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**RemoveSubscriptionInfoMarshaller.h**

6.678

activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller

Class Reference

3233

6.678 — activemq::wireformat::openwire::marshal::v3::RemoveSubscription

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3231).

#include <src/main/activemq/wireformat/openwire/marshal/v3/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
- virtual ~**RemoveSubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure** * **createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshall an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshall an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.678.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3231). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.678.2 Constructor & Destructor Documentation

6.678.2.1 `activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfoMarshaller()` [inline]

6.678.2.2 `virtual activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfoMarshaller()` [inline, virtual]

6.678.3 Member Function Documentation

6.678.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.678.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.678.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::marshal(const OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.678

activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller

Class Reference

3235

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.678.3.4 virtual void ac-

```
tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure * dataStructure,
    decaf::io::DataInputStream * dataIn) throw ( decaf::io::IOException ) [virtual]
```

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.678.3.5 virtual int ac-

```
tivemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure * dataStructure,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.678.3.6 virtual void activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.678.3.7 virtual void activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**RemoveSubscriptionInfoMarshaller.h**

6.679

activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller

Class Reference

3237

6.679 — activemq::wireformat::openwire::marshal::v2::RemoveSubscription

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3235).

#include <src/main/activemq/wireformat/openwire/marshal/v2/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
 - virtual ~**RemoveSubscriptionInfoMarshaller** ()
 - virtual **commands::DataStructure** * **createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.679.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3235). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.679.2 Constructor & Destructor Documentation

6.679.2.1 `activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfoMarshaller()` [inline]

6.679.2.2 `virtual activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfoMarshaller()` [inline, virtual]

6.679.3 Member Function Documentation

6.679.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.679.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.679.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::marshal(const commands::DataStructure& dataStructure, decaf::io::DataOutputStream& dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.679

activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller

Class Reference

3239

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 801).

6.679.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 802).

6.679.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::tightMarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 803).

6.679.3.6 virtual void activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.679.3.7 virtual void activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**RemoveSubscriptionInfoMarshaller.h**

6.680

activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller

Class Reference

6.680 — activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3239).

#include <src/main/activemq/wireformat/openwire/marshal/v6/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
- virtual ~**RemoveSubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure** * **createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.680.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3239). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.680.2 Constructor & Destructor Documentation

6.680.2.1 `activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfoMarshaller()` [inline]

6.680.2.2 `virtual activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfoMarshaller()` [inline, virtual]

6.680.3 Member Function Documentation

6.680.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::createObject(const commands::DataStructure& dataStructure) const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.680.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.680.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::marshal(const OpenWireFormat* wireFormat, commands::DataStructure* dataStructure, decaf::io::DataOutputStream* dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.680

activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller

Class Reference

3243

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.680.3.4 virtual void ac-

```
tivemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::looseUnmarshal(
    OpenWireFormat * wireFormat, commands::DataStructure * dataStructure,
    decaf::io::DataInputStream * dataIn) throw ( decaf::io::IOException ) [virtual]
```

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.680.3.5 virtual int ac-

```
tivemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::tightMarshal(
    OpenWireFormat * wireFormat, commands::DataStructure * dataStructure,
    utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.680.3.6 virtual void activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.680.3.7 virtual void activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**RemoveSubscriptionInfoMarshaller.h**

6.681

activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller

Class Reference

6.681 — activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller

3245

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3243).

#include <src/main/activemq/wireformat/openwire/marshal/v5/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
- virtual **~RemoveSubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.681.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3243). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.681.2 Constructor & Destructor Documentation

6.681.2.1 `activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfoMarshaller()` [inline]

6.681.2.2 `virtual activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfoMarshaller()` [inline, virtual]

6.681.3 Member Function Documentation

6.681.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.681.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.681.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.681

activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller

Class Reference

3247

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 787).

6.681.3.4 virtual void ac-

tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 788).

6.681.3.5 virtual int ac-

tivemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 789).

6.681.3.6 `virtual void activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.681.3.7 `virtual void activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/RemoveSubscriptionInfoMarshaller.h`

6.682

activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller

Class Reference

3249

6.682 — activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller

Class Reference

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3247).

#include <src/main/activemq/wireformat/openwire/marshal/v4/RemoveSubscriptionInfoMarshaller.h>In diagram for activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller:

Public Member Functions

- **RemoveSubscriptionInfoMarshaller** ()
- virtual ~**RemoveSubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure** * **createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.682.1 Detailed Description

Marshaling **code** (p.1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3247). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.682.2 Constructor & Destructor Documentation

6.682.2.1 `activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::RemoveSubscriptionInfo()` [inline]

6.682.2.2 `virtual activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::~RemoveSubscriptionInfo()` [inline, virtual]

6.682.3 Member Function Documentation

6.682.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.682.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.682.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::marshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.682

activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller

Class Reference

3251

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 773).

6.682.3.4 virtual void ac-

tivemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::looseUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 774).

6.682.3.5 virtual int ac-

tivemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 775).

6.682.3.6 virtual void activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.682.3.7 virtual void activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**RemoveSubscriptionInfoMarshaller.h**

6.683 activemq::commands::ReplayCommand Class Reference

#include <src/main/activemq/commands/ReplayCommand.h> Inheritance diagram for activemq::commands::ReplayCommand:

Public Member Functions

- **ReplayCommand** ()
- virtual **~ReplayCommand** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ReplayCommand * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual int **getFirstNakNumber** () const
- virtual void **setFirstNakNumber** (int firstNakNumber)
- virtual int **getLastNakNumber** () const
- virtual void **setLastNakNumber** (int lastNakNumber)
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID _REPLAYCOMMAND** = 65

Protected Attributes

- int **firstNakNumber**
- int **lastNakNumber**

6.683.1 Constructor & Destructor Documentation

6.683.1.1 `activemq::commands::ReplayCommand::ReplayCommand ()`

6.683.1.2 `virtual activemq::commands::ReplayCommand::~~ReplayCommand ()`
[virtual]

6.683.2 Member Function Documentation

6.683.2.1 `virtual ReplayCommand* activemq::commands::ReplayCommand::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.683.2.2 `virtual void activemq::commands::ReplayCommand::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.683.2.3 `virtual bool activemq::commands::ReplayCommand::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.683.2.4 `virtual unsigned char activemq::commands::ReplayCommand::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p.1662).

- 6.683.2.5** `virtual int activemq::commands::ReplayCommand::getFirstNakNumber
() const [virtual]`
- 6.683.2.6** `virtual int activemq::commands::ReplayCommand::getLastNakNumber
() const [virtual]`
- 6.683.2.7** `virtual void activemq::commands::ReplayCommand::setFirstNakNumber
(int firstNakNumber) [virtual]`
- 6.683.2.8** `virtual void activemq::commands::ReplayCommand::setLastNakNumber
(int lastNakNumber) [virtual]`
- 6.683.2.9** `virtual std::string activemq::commands::ReplayCommand::toString ()
const [virtual]`

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.683.2.10** `virtual Pointer<Command> ac-
tivemq::commands::ReplayCommand::visit
(activemq::state::CommandVisitor * visitor) throw (
exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.683.3 Field Documentation

- 6.683.3.1** `int activemq::commands::ReplayCommand::firstNakNumber [protected]`
- 6.683.3.2** `const unsigned char activemq::commands::ReplayCommand::ID _ -
REPLAYCOMMAND = 65 [static]`
- 6.683.3.3** `int activemq::commands::ReplayCommand::lastNakNumber [protected]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ReplayCommand.h`

6.684 activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3254).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.684.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3254).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.684.2 Constructor & Destructor Documentation

6.684.2.1 `activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::ReplayCommandMarshaller()` [inline]

6.684.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` [inline, virtual]

6.684.3 Member Function Documentation

6.684.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.684.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.684.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.684.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.684.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.684.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.684.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/ReplayCommandMarshaller.h

6.685 activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3258).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.685.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3258).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.685.2 Constructor & Destructor Documentation

6.685.2.1 `activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::ReplayCommandMarshaller()` [inline]

6.685.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` [inline, virtual]

6.685.3 Member Function Documentation

6.685.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.685.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.685.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.685.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.685.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.685.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.685.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ReplayCommandMarshaller.h**

6.686 activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3262).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.686.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3262).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.686.2 Constructor & Destructor Documentation

6.686.2.1 `activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::ReplayCommandMarshaller()` `[inline]`

6.686.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` `[inline, virtual]`

6.686.3 Member Function Documentation

6.686.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.686.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.686.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.686.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.686.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.686.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.686.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/ReplayCommandMarshaller.h

6.687 activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3266).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.687.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3266).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.687.2 Constructor & Destructor Documentation

6.687.2.1 `activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::ReplayCommandMarshaller()` [inline]

6.687.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` [inline, virtual]

6.687.3 Member Function Documentation

6.687.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.687.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.687.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.687.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.687.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.687.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.687.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/ReplayCommandMarshaller.h

6.688 activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3270).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.688.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3270).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.688.2 Constructor & Destructor Documentation

6.688.2.1 `activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::ReplayCommandMarshaller()` [inline]

6.688.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` [inline, virtual]

6.688.3 Member Function Documentation

6.688.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.688.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.688.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.688.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.688.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.688.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.688.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/ReplayCommandMarshaller.h

6.689 activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3274).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ReplayCommandMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller:

Public Member Functions

- **ReplayCommandMarshaller** ()
- virtual **~ReplayCommandMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.689.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3274).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.689.2 Constructor & Destructor Documentation

6.689.2.1 `activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::ReplayCommandMarshaller()` [inline]

6.689.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::~~ReplayCommandMarshaller()` [inline, virtual]

6.689.3 Member Function Documentation

6.689.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.689.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.689.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.689.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.689.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.689.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.689.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/ReplayCommandMarshaller.h

6.690 activemq::cmsutil::CmsTemplate::ResolveProducerExecutor Class Reference

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate::ResolveProducerExecutor:

Public Member Functions

- **ResolveProducerExecutor** (**ProducerCallback** **action*, **CmsTemplate** **parent*, const std::string &*destinationName*)
- virtual **~ResolveProducerExecutor** ()
- virtual **cms::Destination** * **getDestination** (**cms::Session** **session*) throw (cms::CMSException)

Protected Member Functions

- **ResolveProducerExecutor** & **operator=** (const **ResolveProducerExecutor** &)

6.690.1 Constructor & Destructor Documentation

- 6.690.1.1** **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor::ResolveProducerExecutor** (**ProducerCallback** * *action*, **CmsTemplate** * *parent*, const std::string & *destinationName*) [inline]
- 6.690.1.2** virtual **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor::~~ResolveProducerExecutor** () [inline, virtual]

6.690.2 Member Function Documentation

- 6.690.2.1** virtual **cms::Destination*** **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor::getDestination** (**cms::Session** * *session*) throw (cms::CMSException) [virtual]
- 6.690.2.2** **ResolveProducerExecutor&** **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor::operator=** (const **ResolveProducerExecutor** &) [inline, protected]

Reimplemented from **activemq::cmsutil::CmsTemplate::ProducerExecutor** (p. 3066).

The documentation for this class was generated from the following file:

- src/main/activemq/cmsutil/**CmsTemplate.h**

6.691 activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor Class Reference

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor:

Public Member Functions

- **ResolveReceiveExecutor** (**CmsTemplate** *parent, const std::string &selector, bool noLocal, const std::string &destinationName)
- virtual ~**ResolveReceiveExecutor** ()
- virtual **cms::Destination** * **getDestination** (**cms::Session** *session) throw (cms::CMSException)

Protected Member Functions

- **ResolveReceiveExecutor** & **operator=** (const **ResolveReceiveExecutor** &)

6.691.1 Constructor & Destructor Documentation

- 6.691.1.1** **activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor::ResolveReceiveExecutor** (**CmsTemplate** * *parent*, const std::string & *selector*, bool *noLocal*, const std::string & *destinationName*) [inline]
- 6.691.1.2** virtual **activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor::~~ResolveReceiveExecutor** () [inline, virtual]

6.691.2 Member Function Documentation

- 6.691.2.1** virtual **cms::Destination*** **activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor::getDestination** (**cms::Session** * *session*) throw (cms::CMSException) [virtual]
- 6.691.2.2** **ResolveReceiveExecutor&** **activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor::operator=** (const **ResolveReceiveExecutor** &) [inline, protected]

Reimplemented from **activemq::cmsutil::CmsTemplate::ReceiveExecutor** (p. 3175).

The documentation for this class was generated from the following file:

- src/main/activemq/cmsutil/**CmsTemplate.h**

6.692 decaf::internal::util::Resource Class Reference

Interface for all Managed Resources in Decaf, these objects are added to the Runtime System and are destroyed at shutdown.

`#include <src/main/decaf/internal/util/Resource.h>`Inheritance diagram for decaf::internal::util::Resource:

Public Member Functions

- virtual `~Resource()`

6.692.1 Detailed Description

Interface for all Managed Resources in Decaf, these objects are added to the Runtime System and are destroyed at shutdown.

Since:

1.0

6.692.2 Constructor & Destructor Documentation

6.692.2.1 virtual `decaf::internal::util::Resource::~~Resource()` [virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/Resource.h`

6.693 decaf::internal::util::ResourceLifecycleManager Class Reference

```
#include <src/main/decaf/internal/util/ResourceLifecycleManager.h>
```

Public Member Functions

- **ResourceLifecycleManager** ()
- virtual **~ResourceLifecycleManager** ()
- virtual void **addResource** (**Resource** *value)

Protected Member Functions

- virtual void **destroyResources** ()

6.693.1 Detailed Description

Since:

1.0

6.693.2 Constructor & Destructor Documentation

6.693.2.1 decaf::internal::util::ResourceLifecycleManager::ResourceLifecycleManager ()

6.693.2.2 virtual decaf::internal::util::ResourceLifecycleManager::~~ResourceLifecycleManager () [virtual]

6.693.3 Member Function Documentation

6.693.3.1 virtual void decaf::internal::util::ResourceLifecycleManager::addResource (**Resource** * *value*) [virtual]

6.693.3.2 virtual void decaf::internal::util::ResourceLifecycleManager::destroyResources () [protected, virtual]

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/**ResourceLifecycleManager.h**

6.694 activemq::cmsutil::ResourceLifecycleManager Class Reference

Manages the lifecycle of a set of CMS resources.

```
#include <src/main/activemq/cmsutil/ResourceLifecycleManager.h>
```

Public Member Functions

- **ResourceLifecycleManager** ()
- virtual **~ResourceLifecycleManager** ()
*Destructor - calls **destroy**.*
- void **addConnection** (**cms::Connection** *connection) throw (cms::CMSEException)
Adds a connection so that its life will be managed by this object.
- void **addSession** (**cms::Session** *session) throw (cms::CMSEException)
Adds a session so that its life will be managed by this object.
- void **addDestination** (**cms::Destination** *dest) throw (cms::CMSEException)
Adds a destination so that its life will be managed by this object.
- void **addMessageProducer** (**cms::MessageProducer** *producer) throw (cms::CMSEException)
Adds a message producer so that its life will be managed by this object.
- void **addMessageConsumer** (**cms::MessageConsumer** *consumer) throw (cms::CMSEException)
Adds a message consumer so that its life will be managed by this object.
- void **destroy** () throw (cms::CMSEException)
Closes and destroys the contained CMS resources.
- void **releaseAll** ()
Releases all of the contained resources so that this object will no longer control their lifetimes.

Protected Member Functions

- **ResourceLifecycleManager** (const **ResourceLifecycleManager** &)
- **ResourceLifecycleManager** & **operator=** (const **ResourceLifecycleManager** &)

6.694.1 Detailed Description

Manages the lifecycle of a set of CMS resources. A call to **destroy** will close and destroy all of the contained resources in the appropriate manner.

6.694.2 Constructor & Destructor Documentation

6.694.2.1 `activemq::cmsutil::ResourceLifecycleManager::ResourceLifecycleManager (const ResourceLifecycleManager &) [inline, protected]`

6.694.2.2 `activemq::cmsutil::ResourceLifecycleManager::ResourceLifecycleManager ()`

6.694.2.3 `virtual
activemq::cmsutil::ResourceLifecycleManager::~~ResourceLifecycleManager
() [virtual]`

Destructor - calls destroy.

6.694.3 Member Function Documentation

6.694.3.1 `void activemq::cmsutil::ResourceLifecycleManager::addConnection (cms::Connection * connection) throw (cms::CMSException)`

Adds a connection so that its life will be managed by this object.

Parameters:

connection the object to be managed

6.694.3.2 `void activemq::cmsutil::ResourceLifecycleManager::addDestination (cms::Destination * dest) throw (cms::CMSException)`

Adds a destination so that its life will be managed by this object.

Parameters:

dest the object to be managed

6.694.3.3 `void ac-
tivemq::cmsutil::ResourceLifecycleManager::addMessageConsumer
(cms::MessageConsumer * consumer) throw (cms::CMSException)`

Adds a message consumer so that its life will be managed by this object.

Parameters:

consumer the object to be managed

6.694.3.4 `void activemq::cmsutil::ResourceLifecycleManager::addMessageProducer (cms::MessageProducer * producer) throw (cms::CMSException)`

Adds a message producer so that its life will be managed by this object.

Parameters:

producer the object to be managed

6.694.3.5 `void activemq::cmsutil::ResourceLifecycleManager::addSession
 (cms::Session * session) throw (cms::CMSException)`

Adds a session so that its life will be managed by this object.

Parameters:

session the object to be managed

6.694.3.6 `void activemq::cmsutil::ResourceLifecycleManager::destroy () throw (cms::CMSException)`

Closes and destroys the contained CMS resources.

Exceptions:

cms::CMSException (p. 1160) thrown if an error occurs.

6.694.3.7 `ResourceLifecycleManager& ac-
 tivemq::cmsutil::ResourceLifecycleManager::operator=
 (const ResourceLifecycleManager &) [inline, protected]`

6.694.3.8 `void activemq::cmsutil::ResourceLifecycleManager::releaseAll ()`

Releases all of the contained resources so that this object will no longer control their lifetimes.

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/ResourceLifecycleManager.h`

6.695 activemq::commands::Response Class Reference

#include <src/main/activemq/commands/Response.h> Inheritance diagram for activemq::commands::Response:

Public Member Functions

- **Response** ()
- virtual **~Response** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **Response * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual int **getCorrelationId** () const
- virtual void **setCorrelationId** (int correlationId)
- virtual bool **isResponse** () const
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_RESPONSE** = 30

Protected Attributes

- int **correlationId**

6.695.1 Constructor & Destructor Documentation

6.695.1.1 `activemq::commands::Response::Response ()`

6.695.1.2 `virtual activemq::commands::Response::~~Response () [virtual]`

6.695.2 Member Function Documentation

6.695.2.1 `virtual Response* activemq::commands::Response::cloneDataStructure () const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

Reimplemented in `activemq::commands::DataArrayResponse` (p. 1529), `activemq::commands::DataResponse` (p. 1584), `activemq::commands::ExceptionResponse` (p. 1840), and `activemq::commands::IntegerResponse` (p. 2092).

6.695.2.2 `virtual void activemq::commands::Response::copyDataStructure (const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

Reimplemented in `activemq::commands::DataArrayResponse` (p. 1529), `activemq::commands::DataResponse` (p. 1584), `activemq::commands::ExceptionResponse` (p. 1840), and `activemq::commands::IntegerResponse` (p. 2092).

6.695.2.3 `virtual bool activemq::commands::Response::equals (const DataStructure * value) const [virtual]`

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

Reimplemented in **activemq::commands::DataArrayResponse** (p. 1529), **activemq::commands::DataResponse** (p. 1584), **activemq::commands::ExceptionResponse** (p. 1840), and **activemq::commands::IntegerResponse** (p. 2092).

6.695.2.4 `virtual int activemq::commands::Response::getCorrelationId () const`
[virtual]

6.695.2.5 `virtual unsigned char activemq::commands::Response::getDataStructureType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

Reimplemented in **activemq::commands::DataArrayResponse** (p. 1530), **activemq::commands::DataResponse** (p. 1585), **activemq::commands::ExceptionResponse** (p. 1840), and **activemq::commands::IntegerResponse** (p. 2092).

6.695.2.6 `virtual bool activemq::commands::Response::isResponse () const`
[inline, virtual]

Returns:

an answer of true to the **isResponse()** (p. 3287) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 762).

6.695.2.7 `virtual void activemq::commands::Response::setCorrelationId (int correlationId)` [virtual]

6.695.2.8 `virtual std::string activemq::commands::Response::toString () const`
[virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

Reimplemented in **activemq::commands::DataArrayResponse** (p. 1530), **activemq::commands::DataResponse** (p. 1585), **activemq::commands::ExceptionResponse** (p. 1841), and **activemq::commands::IntegerResponse** (p. 2093).

6.695.2.9 `virtual Pointer<Command> activemq::commands::Response::visit
 (activemq::state::CommandVisitor * visitor) throw (
 exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements `activemq::commands::Command` (p. 1198).

6.695.3 Field Documentation

6.695.3.1 `int activemq::commands::Response::correlationId` [protected]

6.695.3.2 `const unsigned char activemq::commands::Response::ID_RESPONSE =
 30` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/Response.h`

6.696 activemq::transport::mock::ResponseBuilder Class Reference

Interface for all Protocols to implement that defines the behavior of the Broker in response to messages of that protocol.

#include <src/main/activemq/transport/mock/ResponseBuilder.h> Inheritance diagram for activemq::transport::mock::ResponseBuilder:

Public Member Functions

- virtual **~ResponseBuilder** ()
- virtual **Pointer< Response > buildResponse** (const **Pointer< Command > &command**)=0
Given a Command, check if it requires a response and return the appropriate Response that the Broker would send for this Command.
- virtual void **buildIncomingCommands** (const **Pointer< Command > &command**, **decaf::util::StlQueue< Pointer< Command > > &queue**)=0
*When called the **ResponseBuilder** (p. 3289) must construct all the Responses or Asynchronous **commands** (p. 87) that would be sent to this client by the Broker upon receipt of the passed command.*

6.696.1 Detailed Description

Interface for all Protocols to implement that defines the behavior of the Broker in response to messages of that protocol.

6.696.2 Constructor & Destructor Documentation

6.696.2.1 virtual **activemq::transport::mock::ResponseBuilder::~~ResponseBuilder** () [inline, virtual]

6.696.3 Member Function Documentation

6.696.3.1 virtual void **activemq::transport::mock::ResponseBuilder::buildIncomingCommands** (const **Pointer< Command > &command**, **decaf::util::StlQueue< Pointer< Command > > &queue**) [pure virtual]

When called the **ResponseBuilder** (p. 3289) must construct all the Responses or Asynchronous **commands** (p. 87) that would be sent to this client by the Broker upon receipt of the passed command.

Parameters:

- command* - The Command being sent to the Broker.
- queue* - Queue of Command sent back from the broker.

Implemented in **activemq::wireformat::openwire::OpenWireResponseBuilder** (p. 2905).

6.696.3.2 `virtual Pointer<Response> activemq::transport::mock::ResponseBuilder::buildResponse
(const Pointer< Command > & command) [pure virtual]`

Given a Command, check if it requires a response and return the appropriate Response that the Broker would send for this Command.

Parameters:

command - The command to build a response for

Returns:

A Response object pointer, or NULL if no response.

Implemented in **activemq::wireformat::openwire::OpenWireResponseBuilder** (p. 2906).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/mock/ResponseBuilder.h`

6.697 activemq::transport::correlator::ResponseCorrelator Class Reference

This type of **transport** (p.97) filter is responsible for correlating asynchronous responses with requests.

#include <src/main/activemq/transport/correlator/ResponseCorrelator.h> Inheritance diagram for activemq::transport::correlator::ResponseCorrelator:

Public Member Functions

- **ResponseCorrelator** (const **Pointer**< **Transport** > &next)
Constructor.
- virtual ~**ResponseCorrelator** ()
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given request to the server and waits for the response.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given request to the server and waits for the response.
- virtual void **onCommand** (const **Pointer**< **Command** > &command)
This is called in the context of the nested transport's reading thread.
- virtual void **start** () throw (decaf::io::IOException)
*Starts this **transport** (p.97) object and creates the thread for polling on the input stream for **commands** (p.87).*
- virtual void **close** () throw (decaf::io::IOException)
Stops the polling thread and closes the streams.
- virtual void **onTransportException** (**Transport** *source, const decaf::lang::Exception &ex)
*Event handler for an exception from a command **transport** (p.97).*

6.697.1 Detailed Description

This type of **transport** (p.97) filter is responsible for correlating asynchronous responses with requests. Non-response messages are simply sent directly to the CommandListener. It owns the **transport** (p.97) that it

6.697.2 Constructor & Destructor Documentation

6.697.2.1 `activemq::transport::correlator::ResponseCorrelator::ResponseCorrelator (const Pointer< Transport > & next)`

Constructor.

Parameters:

next the next **transport** (p. 97) in the chain

6.697.2.2 `virtual activemq::transport::correlator::ResponseCorrelator::~ResponseCorrelator ()` [virtual]

6.697.3 Member Function Documentation

6.697.3.1 `virtual void activemq::transport::correlator::ResponseCorrelator::close () throw (decaf::io::IOException)` [virtual]

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if errors occur.

Reimplemented from **activemq::transport::TransportFilter** (p. 3893).

6.697.3.2 `virtual void activemq::transport::correlator::ResponseCorrelator::onCommand (const Pointer< Command > & command)` [virtual]

This is called in the context of the nested transport's reading thread. In the case of a response object, updates the request map and notifies those waiting on the response. Non-response messages are just delegated to the command listener.

Parameters:

command the received from the nested **transport** (p. 97).

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.697.3.3 `virtual void activemq::transport::correlator::ResponseCorrelator::oneway (const Pointer< Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

6.697.3.4 virtual void **activemq::transport::correlator::ResponseCorrelator::onTransportException** (**Transport** * *source*, const **decaf::lang::Exception** & *ex*) [virtual]

Event handler for an exception from a command **transport** (p. 97).

Parameters:

source The source of the exception

ex The exception.

6.697.3.5 virtual **Pointer<Response>** **activemq::transport::correlator::ResponseCorrelator::request** (const **Pointer< Command >** & *command*, unsigned int *timeout*) throw (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**) [virtual]

Sends the given request to the server and waits for the response.

Parameters:

command The request to send.

timeout The time to wait for a response.

Returns:

the response from the server.

Exceptions:

IOException if an error occurs with the request.

Reimplemented from **activemq::transport::TransportFilter** (p. 3896).

6.697.3.6 virtual **Pointer<Response>** **activemq::transport::correlator::ResponseCorrelator::request** (const **Pointer< Command >** & *command*) throw (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**) [virtual]

Sends the given request to the server and waits for the response.

Parameters:

command The request to send.

Returns:

the response from the server.

Exceptions:

IOException if an error occurs with the request.

Reimplemented from **activemq::transport::TransportFilter** (p. 3897).

6.697.3.7 **virtual void activemq::transport::correlator::ResponseCorrelator::start ()**
throw (decaf::io::IOException) [virtual]

Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87). If this object has been closed, throws an exception. Before calling start, the caller must set the IO streams and the reader and writer objects.

Exceptions:

IOException if an error occurs or if this **transport** (p. 97) has already been closed.

Reimplemented from **activemq::transport::TransportFilter** (p. 3898).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/correlator/**ResponseCorrelator.h**

6.698 activemq::wireformat::openwire::marshal::v4::ResponseMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3295).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.698.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3295). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.698.2 Constructor & Destructor Documentation

6.698.2.1 `activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::ResponseMarshaller()` [inline]

6.698.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::~~ResponseMarshaller()` [inline, virtual]

6.698.3 Member Function Documentation

6.698.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1540), `activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller` (p. 1603), `activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller` (p. 1859), and `activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller` (p. 2107).

6.698.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller` (p. 1540), `activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller` (p. 1603), `activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller` (p. 1859), and `activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller` (p. 2107).

6.698.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 773).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller** (p. 1540), **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller** (p. 1603), **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller** (p. 1859), and **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller** (p. 2107).

6.698.3.4 virtual void activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 774).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller** (p. 1541), **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller** (p. 1604), **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller** (p. 1860), and **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller** (p. 2108).

6.698.3.5 virtual int activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 775).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller** (p. 1541), **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller** (p. 1604), **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller** (p. 1860), and **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller** (p. 2108).

6.698.3.6 virtual void **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::tightMarshal2** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataOutputStream** * *dataOut*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller** (p. 1542), **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller** (p. 1605), **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller** (p. 1861), and **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller** (p. 2109).

6.698.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller** (p. 1542), **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller** (p. 1605), **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller** (p. 1861), and **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller** (p. 2109).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ResponseMarshaller.h**

6.699 activemq::wireformat::openwire::marshal::v2::ResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3300).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.699.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3300). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.699.2 Constructor & Destructor Documentation

6.699.2.1 `activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::ResponseMarshaller()` `[inline]`

6.699.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::~~ResponseMarshaller()` `[inline, virtual]`

6.699.3 Member Function Documentation

6.699.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1532), `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1595), `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1847), and `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2099).

6.699.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1532), `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1595), `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1847), and `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2099).

6.699.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 801).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller** (p. 1532), **activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller** (p. 1595), **activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller** (p. 1847), and **activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller** (p. 2099).

6.699.3.4 virtual void activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 802).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller** (p. 1533), **activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller** (p. 1596), **activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller** (p. 1848), and **activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller** (p. 2100).

6.699.3.5 virtual int activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 803).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller** (p. 1533), **activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller** (p. 1596), **activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller** (p. 1848), and **activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller** (p. 2100).

6.699.3.6 virtual void ac-
tivemq::wireformat::openwire::marshal::v2::ResponseMarshaller::tightMarshal2
(OpenWireFormat * wireFormat, commands::DataStructure
*** dataStructure, decaf::io::DataOutputStream * dataOut,**
utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller** (p. 1534), **activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller** (p. 1597), **activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller** (p. 1849), and **activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller** (p. 2101).

```
6.699.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ResponseMarshaller::tightUnmarshal
(OpenWireFormat * wireFormat, commands::DataStructure
 * dataStructure, decaf::io::DataInputStream * dataIn,
 utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 805).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller` (p. 1534), `activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller` (p. 1597), `activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller` (p. 1849), and `activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller` (p. 2101).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h`

6.700 activemq::wireformat::openwire::marshal::v5::ResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3305).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.700.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3305). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.700.2 Constructor & Destructor Documentation

- 6.700.2.1** `activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::ResponseMarshaller()` [inline]
- 6.700.2.2** `virtual activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::~~ResponseMarshaller()` [inline, virtual]

6.700.3 Member Function Documentation

- 6.700.3.1** `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1548), `activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1587), `activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1855), and `activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2115).

- 6.700.3.2** `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller` (p. 1548), `activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller` (p. 1587), `activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller` (p. 1855), and `activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller` (p. 2115).

- 6.700.3.3** `virtual void activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 787).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1548), **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller** (p. 1587), **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller** (p. 1855), and **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller** (p. 2115).

6.700.3.4 virtual void activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 788).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1549), **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller** (p. 1588), **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller** (p. 1856), and **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller** (p. 2116).

6.700.3.5 virtual int activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 789).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1549), **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller** (p. 1588), **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller** (p. 1856), and **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller** (p. 2116).

6.700.3.6 virtual void **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::tightMarshal2** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataOutputStream** * *dataOut*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1550), **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller** (p. 1589), **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller** (p. 1857), and **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller** (p. 2117).

6.700.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller** (p. 1550), **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller** (p. 1589), **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller** (p. 1857), and **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller** (p. 2117).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ResponseMarshaller.h**

6.701 activemq::wireformat::openwire::marshal::v3::ResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3310).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.701.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3310). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.701.2 Constructor & Destructor Documentation

6.701.2.1 `activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::ResponseMarshaller()` [inline]

6.701.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::~~ResponseMarshaller()` [inline, virtual]

6.701.3 Member Function Documentation

6.701.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1536), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1599), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1851), and `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2103).

6.701.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1536), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1599), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1851), and `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2103).

6.701.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 766).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller** (p. 1536), **activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller** (p. 1599), **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller** (p. 1851), and **activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller** (p. 2103).

6.701.3.4 virtual void activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 767).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller** (p. 1537), **activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller** (p. 1600), **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller** (p. 1852), and **activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller** (p. 2104).

6.701.3.5 virtual int activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 768).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller** (p. 1537), **activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller** (p. 1600), **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller** (p. 1852), and **activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller** (p. 2104).

6.701.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller** (p. 1538), **activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller** (p. 1601), **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller** (p. 1853), and **activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller** (p. 2105).

```
6.701.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ResponseMarshaller::tightUnmarshal
(OpenWireFormat * wireFormat, commands::DataStructure
 * dataStructure, decaf::io::DataInputStream * dataIn,
 utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 770).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller` (p. 1538), `activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller` (p. 1601), `activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller` (p. 1853), and `activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller` (p. 2105).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h`

6.702 activemq::wireformat::openwire::marshal::v1::ResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3315).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.702.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3315). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.702.2 Constructor & Destructor Documentation

6.702.2.1 `activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::ResponseMarshaller()` [inline]

6.702.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::~~ResponseMarshaller()` [inline, virtual]

6.702.3 Member Function Documentation

6.702.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1544), `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1607), `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1863), and `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2111).

6.702.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller` (p. 1544), `activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller` (p. 1607), `activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller` (p. 1863), and `activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller` (p. 2111).

6.702.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1544), **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller** (p. 1607), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1863), and **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller** (p. 2111).

6.702.3.4 virtual void activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1545), **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller** (p. 1608), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1864), and **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller** (p. 2112).

6.702.3.5 virtual int activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1545), **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller** (p. 1608), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1864), and **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller** (p. 2112).

6.702.3.6 virtual void ac-
tivemq::wireformat::openwire::marshal::v1::ResponseMarshaller::tightMarshal2
(OpenWireFormat * wireFormat, commands::DataStructure
*** dataStructure, decaf::io::DataOutputStream * dataOut,**
utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1546), **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller** (p. 1609), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1865), and **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller** (p. 2113).

6.702.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ResponseMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller** (p. 1546), **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller** (p. 1609), **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller** (p. 1865), and **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller** (p. 2113).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ResponseMarshaller.h**

6.703 activemq::wireformat::openwire::marshal::v6::ResponseMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3320).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ResponseMarshaller:

Public Member Functions

- **ResponseMarshaller** ()
- virtual **~ResponseMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.703.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3320). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.703.2 Constructor & Destructor Documentation

6.703.2.1 `activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::ResponseMarshaller()` [inline]

6.703.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::~~ResponseMarshaller()` [inline, virtual]

6.703.3 Member Function Documentation

6.703.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1552), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1591), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1843), and `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2095).

6.703.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1552), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1591), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1843), and `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2095).

6.703.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 794).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller** (p. 1552), **activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller** (p. 1591), **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller** (p. 1843), and **activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller** (p. 2095).

6.703.3.4 virtual void activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 795).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller** (p. 1553), **activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller** (p. 1592), **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller** (p. 1844), and **activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller** (p. 2096).

6.703.3.5 virtual int activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 796).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller** (p. 1553), **activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller** (p. 1592), **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller** (p. 1844), and **activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller** (p. 2096).

6.703.3.6 virtual void ac-
tivemq::wireformat::openwire::marshal::v6::ResponseMarshaller::tightMarshal2
(OpenWireFormat * wireFormat, commands::DataStructure
*** dataStructure, decaf::io::DataOutputStream * dataOut,**
utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller** (p. 1554), **activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller** (p. 1593), **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller** (p. 1845), and **activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller** (p. 2097).

```
6.703.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ResponseMarshaller::tightUnmarshal
(OpenWireFormat * wireFormat, commands::DataStructure
 * dataStructure, decaf::io::DataInputStream * dataIn,
 utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 798).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller` (p. 1554), `activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller` (p. 1593), `activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller` (p. 1845), and `activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller` (p. 2097).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h`

6.704 decaf::lang::Runnable Class Reference

Interface for a runnable object - defines a task that can be run by a thread.

#include <src/main/decaf/lang/Runnable.h>Inheritance diagram for decaf::lang::Runnable:

Public Member Functions

- virtual `~Runnable()`
- virtual void `run()`=0

*Run method - called by the **Thread** (p. 3765) class in the context of the thread.*

6.704.1 Detailed Description

Interface for a runnable object - defines a task that can be run by a thread.

6.704.2 Constructor & Destructor Documentation

6.704.2.1 virtual decaf::lang::Runnable::~~Runnable() [inline, virtual]

6.704.3 Member Function Documentation

6.704.3.1 virtual void decaf::lang::Runnable::run() [pure virtual]

Run method - called by the **Thread** (p. 3765) class in the context of the thread.

Implemented in **activemq::threads::CompositeTaskRunner** (p. 1224), **activemq::threads::DedicatedTaskRunner** (p. 1671), **activemq::transport::inactivity::ReadChecker** (p. 3162), **activemq::transport::inactivity::WriteChecker** (p. 4020), **activemq::transport::IOTransport** (p. 2150), **activemq::transport::mock::InternalCommandListener** (p. 2123), **decaf::lang::Thread** (p. 3771), and **decaf::util::concurrent::PooledThread** (p. 2969).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Runnable.h**

6.705 decaf::lang::Runtime Class Reference

#include <src/main/decaf/lang/Runtime.h> Inheritance diagram for decaf::lang::Runtime:

Public Member Functions

- virtual `~Runtime ()`

Static Public Member Functions

- static `Runtime * getRuntime ()`
*Gets the single instance of the Decaf **Runtime** (p. 3326) for this Process.*
- static void `initializeRuntime (int argc, char **argv)`
Initialize the Decaf Library passing it the args that were passed to the application at startup.
- static void `initializeRuntime ()`
Initialize the Decaf Library.
- static void `shutdownRuntime ()`
Shutdown the Decaf Library, this call should take places after all objects that were created from the Decaf library have been deallocated.

6.705.1 Constructor & Destructor Documentation

6.705.1.1 virtual `decaf::lang::Runtime::~~Runtime ()` [inline, virtual]

6.705.2 Member Function Documentation

6.705.2.1 static `Runtime* decaf::lang::Runtime::getRuntime ()` [static]

Gets the single instance of the Decaf **Runtime** (p. 3326) for this Process.

Returns:

pointer to the single Decaf **Runtime** (p. 3326) instance that exists for this process

6.705.2.2 static void `decaf::lang::Runtime::initializeRuntime ()` [static]

Initialize the Decaf Library.

Exceptions:

runtime_error if the library is already initialized or an error occurs during initialization.

6.705.2.3 static void decaf::lang::Runtime::initializeRuntime (int *argc*, char ***argv*) [static]

Initialize the Decaf Library passing it the args that were passed to the application at startup.

Parameters:

argc - The number of args passed

argv - Array of char* values passed to the Process on start.

Exceptions:

runtime_error if the library is already initialized or an error occurs during initialization.

6.705.2.4 static void decaf::lang::Runtime::shutdownRuntime () [static]

Shutdown the Decaf Library, this call should take places after all objects that were created from the Decaf library have been deallocated.

Exceptions:

runtime_error if the library has not already been initialized or an error occurs during shutdown.

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Runtime.h**

6.706 decaf::lang::exceptions::RuntimeException Class Reference

#include <src/main/decaf/lang/exceptions/RuntimeException.h> Inheritance diagram for decaf::lang::exceptions::RuntimeException:

Public Member Functions

- **RuntimeException** () throw ()
Default Constructor.
- **RuntimeException** (const **Exception** &ex) throw ()
Conversion Constructor from some other ActiveMQException.
- **RuntimeException** (const **RuntimeException** &ex) throw ()
Copy Constructor.
- **RuntimeException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **RuntimeException** (const std::exception *cause) throw ()
Constructor.
- **RuntimeException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **RuntimeException** * clone () const
Clones this exception.
- virtual ~**RuntimeException** () throw ()

6.706.1 Constructor & Destructor Documentation

6.706.1.1 decaf::lang::exceptions::RuntimeException::RuntimeException () throw () [inline]

Default Constructor.

6.706.1.2 decaf::lang::exceptions::RuntimeException::RuntimeException (const Exception & ex) throw () [inline]

Conversion Constructor from some other ActiveMQException.

Parameters:

ex The **Exception** (p.1831) whose data is to be copied into this one.

6.706.1.3 decaf::lang::exceptions::RuntimeException::RuntimeException (const RuntimeException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The **Exception** (p.1831) whose data is to be copied into this one.

6.706.1.4 decaf::lang::exceptions::RuntimeException::RuntimeException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.706.1.5 decaf::lang::exceptions::RuntimeException::RuntimeException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause **Pointer** (p.2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.706.1.6 decaf::lang::exceptions::RuntimeException::RuntimeException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.706.1.7 `virtual decaf::lang::exceptions::RuntimeException::~~RuntimeException
() throw () [inline, virtual]`

6.706.2 Member Function Documentation

6.706.2.1 `virtual RuntimeException* de-
caf::lang::exceptions::RuntimeException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p.1831) that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/exceptions/RuntimeException.h`

6.707 decaf::security::SecureRandom Class Reference

#include <src/main/decaf/security/SecureRandom.h> Inheritance diagram for decaf::security::SecureRandom:

Public Member Functions

- **SecureRandom** ()
Creates a new instance of a secure random number generator that implements the default random number algorithm.
- **SecureRandom** (const std::vector< unsigned char > &seed)
Creates a new instance of a secure random number generator that implements the default random number algorithm.
- **SecureRandom** (const unsigned char *seed, int size)
Creates a new instance of a secure random number generator that implements the default random number algorithm.
- virtual ~**SecureRandom** ()
- virtual void **nextBytes** (std::vector< unsigned char > &buf)
Modifies the byte array by a random sequence of bytes generated by this random number generator.
Parameters:
buf non-null array to contain the new random bytes
See also:
next (p. 3156)
- virtual void **nextBytes** (unsigned char *buf, int size)
Modifies the byte array by a random sequence of bytes generated by this random number generator.
Parameters:
buf non-null array to contain the new random bytes
See also:
next (p. 3156)
Exceptions:
***NullPointerException** if buff is NULL*
***IllegalArgumentException** if size is negative*
- virtual void **setSeed** (unsigned long long seed)
Modifies the seed using linear congruential formula presented in The Art of Computer Programming, Volume 2, Section 3.2.1.
Parameters:
seed the seed that alters the state of the random number generator
See also:
next (p. 3156)
Random() (p. 3156)
Random(long)

- virtual void **setSeed** (const std::vector< unsigned char > &seed)
Supplements or sets the seed of this secure random number generator, calls to this method never reduces randomness.
- virtual void **setSeed** (const unsigned char *seed, int size)
Supplements or sets the seed of this secure random number generator, calls to this method never reduces randomness.

Protected Member Functions

- virtual int **next** (int bits)
*Answers a pseudo-random uniformly distributed **int** value of the number of bits specified by the argument **bits** as described by Donald E. Knuth in The Art of Computer Programming, Volume 2: Seminumerical Algorithms, section 3.2.1.*
Returns:
int a pseudo-random generated int number
Parameters:
bits number of bits of the returned value
See also:
nextBytes (p. 3157)
nextDouble (p. 3158)
nextFloat (p. 3158)
nextInt() (p. 3159)
nextInt(int) (p. 3158)
nextGaussian (p. 3158)
nextLong (p. 3159)

6.707.1 Detailed Description

Since:

1.0

6.707.2 Constructor & Destructor Documentation

6.707.2.1 decaf::security::SecureRandom::SecureRandom ()

Creates a new instance of a secure random number generator that implements the default random number algorithm. The **SecureRandom** (p. 3331) instance that is created with this constructor is unseeded and can be seeded by calling the setSeed method. Calls to nextBytes on an unseeded **SecureRandom** (p. 3331) result in the object seeding itself.

6.707.2.2 decaf::security::SecureRandom::SecureRandom (const std::vector< unsigned char > & seed)

Creates a new instance of a secure random number generator that implements the default random number algorithm. The **SecureRandom** (p. 3331) instance created by this constructor is seeded using the passed byte array.

Parameters:

seed The seed bytes to use to seed this secure random number generator.

**6.707.2.3 decaf::security::SecureRandom::SecureRandom (const unsigned char *
seed, int size)**

Creates a new instance of a secure random number generator that implements the default random number algorithm. The **SecureRandom** (p. 3331) instance created by this constructor is seeded using the passed byte array.

Parameters:

seed The seed bytes to use to seed this secure random number generator.

size The number of bytes in the seed buffer.

Exceptions:

NullPointerException if the seed buffer is NULL.

IllegalArgumentException if the size value is negative.

6.707.2.4 virtual decaf::security::SecureRandom::~~SecureRandom () [virtual]**6.707.3 Member Function Documentation****6.707.3.1 virtual int decaf::security::SecureRandom::next (int bits) [protected,
virtual]**

Answers a pseudo-random uniformly distributed **int** value of the number of bits specified by the argument *bits* as described by Donald E.

Knuth in *The Art of Computer Programming, Volume 2: Seminumerical Algorithms*, section 3.2.1.

Returns:

int a pseudo-random generated int number

Parameters:

bits number of bits of the returned value

See also:

nextBytes (p. 3157)
nextDouble (p. 3158)
nextFloat (p. 3158)
nextInt() (p. 3159)
nextInt(int) (p. 3158)
nextGaussian (p. 3158)
nextLong (p. 3159)

Reimplemented from **decaf::util::Random** (p. 3156).

6.707.3.2 `virtual void decaf::security::SecureRandom::nextBytes (unsigned char * buf, int size)` [virtual]

Modifies the byte array by a random sequence of bytes generated by this random number generator.

Parameters:

buf non-null array to contain the new random bytes

See also:

`next` (p. 3156)

Exceptions:

NullPointerException if *buf* is NULL

IllegalArgumentException if *size* is negative

Reimplemented from `decaf::util::Random` (p. 3157).

6.707.3.3 `virtual void decaf::security::SecureRandom::nextBytes (std::vector< unsigned char > & buf)` [virtual]

Modifies the byte array by a random sequence of bytes generated by this random number generator.

Parameters:

buf non-null array to contain the new random bytes

See also:

`next` (p. 3156)

Reimplemented from `decaf::util::Random` (p. 3157).

6.707.3.4 `virtual void decaf::security::SecureRandom::setSeed (const unsigned char * seed, int size)` [virtual]

Supplements or sets the seed of this secure random number generator, calls to this method never reduces randomness.

Parameters:

seed The seed bytes to use to seed this secure random number generator.

size The number of bytes in the seed buffer.

Exceptions:

NullPointerException if the seed buffer is NULL.

IllegalArgumentException if the size value is negative.

6.707.3.5 virtual void decaf::security::SecureRandom::setSeed (const std::vector< unsigned char > & seed) [virtual]

Supplements or sets the seed of this secure random number generator, calls to this method never reduces randomness.

Parameters:

seed A vector of bytes that is used update the seed of the RNG.

6.707.3.6 virtual void decaf::security::SecureRandom::setSeed (unsigned long long seed) [virtual]

Modifies the seed using linear congruential formula presented in *The Art of Computer Programming, Volume 2*, Section 3.2.1.

Parameters:

seed the seed that alters the state of the random number generator

See also:

next (p. 3156)
Random() (p. 3156)
Random(long)

Reimplemented from **decaf::util::Random** (p. 3159).

The documentation for this class was generated from the following file:

- src/main/decaf/security/**SecureRandom.h**

6.708 decaf::internal::security::SecureRandomImpl Class Reference

Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources.

#include <src/main/decaf/internal/security/unix/SecureRandomImpl.h> Inheritance diagram for decaf::internal::security::SecureRandomImpl:

Public Member Functions

- **SecureRandomImpl** ()
- virtual **~SecureRandomImpl** ()
- virtual void **providerSetSeed** (const unsigned char *seed, int size)
Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.
- virtual void **providerNextBytes** (unsigned char *bytes, int numBytes)
Generates the number of random bytes specified by the size parameter and write them to the passed bytes array.
- virtual unsigned char * **providerGenerateSeed** (int numBytes)
Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator.
- **SecureRandomImpl** ()
- virtual **~SecureRandomImpl** ()
- virtual void **providerSetSeed** (const unsigned char *seed, int size)
Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.
- virtual void **providerNextBytes** (unsigned char *bytes, int numBytes)
Generates the number of random bytes specified by the size parameter and write them to the passed bytes array.
- virtual unsigned char * **providerGenerateSeed** (int numBytes)
Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator.

6.708.1 Detailed Description

Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources. Secure Random Number Generator for Windows based platforms that attempts to obtain secure bytes with high entropy from known sources.

If the platform does not have a source of secure bytes then the platform random number generator is used if one exists otherwise the Decaf RNG is used as a last resort.

Since:

1.0

6.708.2 Constructor & Destructor Documentation

6.708.2.1 decaf::internal::security::SecureRandomImpl::SecureRandomImpl ()

6.708.2.2 virtual
decaf::internal::security::SecureRandomImpl::~~SecureRandomImpl ()
[virtual]

6.708.2.3 decaf::internal::security::SecureRandomImpl::SecureRandomImpl ()

6.708.2.4 virtual
decaf::internal::security::SecureRandomImpl::~~SecureRandomImpl ()
[virtual]

6.708.3 Member Function Documentation

6.708.3.1 virtual unsigned char* decaf::internal::security::SecureRandomImpl::providerGenerateSeed (int *numBytes*) [virtual]

Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator. The caller owns the returned array and must delete it.

Parameters:

numBytes The number of bytes that should be generated for the new seed array.

Implements decaf::security::SecureRandomSpi (p. 3339).

6.708.3.2 virtual unsigned char* decaf::internal::security::SecureRandomImpl::providerGenerateSeed (int *numBytes*) [virtual]

Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator. The caller owns the returned array and must delete it.

Parameters:

numBytes The number of bytes that should be generated for the new seed array.

Implements decaf::security::SecureRandomSpi (p. 3339).

6.708.3.3 virtual void decaf::internal::security::SecureRandomImpl::providerNextBytes (unsigned char * *bytes*, int *numBytes*) [virtual]

Generates the number of random bytes specified by the size parameter and write them to the passed bytes array. The array must have already been allocated and be of the correct size to prevent segmentation faults.

Parameters:

bytes The array that will be filled with random bytes equal to size.

numBytes The number of bytes to generate and write into the bytes array.

Implements **decaf::security::SecureRandomSpi** (p. 3340).

6.708.3.4 virtual void decaf::internal::security::SecureRandomImpl::providerNextBytes (unsigned char * *bytes*, int *numBytes*) [virtual]

Generates the number of random bytes specified by the size parameter and write them to the passed bytes array. The array must have already been allocated and be of the correct size to prevent segmentation faults.

Parameters:

bytes The array that will be filled with random bytes equal to size.

numBytes The number of bytes to generate and write into the bytes array.

Implements **decaf::security::SecureRandomSpi** (p. 3340).

6.708.3.5 virtual void decaf::internal::security::SecureRandomImpl::providerSetSeed (const unsigned char * *seed*, int *size*) [virtual]

Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.

Parameters:

seed The array of bytes used to update the generators seed.

size The size of the passed byte array.

Implements **decaf::security::SecureRandomSpi** (p. 3340).

6.708.3.6 virtual void decaf::internal::security::SecureRandomImpl::providerSetSeed (const unsigned char * *seed*, int *size*) [virtual]

Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.

Parameters:

seed The array of bytes used to update the generators seed.

size The size of the passed byte array.

Implements **decaf::security::SecureRandomSpi** (p. 3340).

The documentation for this class was generated from the following files:

- src/main/decaf/internal/security/unix/**SecureRandomImpl.h**
- src/main/decaf/internal/security/windows/**SecureRandomImpl.h**

6.709 decaf::security::SecureRandomSpi Class Reference

Interface class used by Security Service Providers to implement a source of secure random bytes.

#include <src/main/decaf/security/SecureRandomSpi.h> Inheritance diagram for decaf::security::SecureRandomSpi:

Public Member Functions

- **SecureRandomSpi** ()
- virtual **~SecureRandomSpi** ()
- virtual void **providerSetSeed** (const unsigned char *seed, int size)=0
Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.
- virtual void **providerNextBytes** (unsigned char *bytes, int numBytes)=0
Generates the number of random bytes specified by the size parameter and write them to the passed bytes array.
- virtual unsigned char * **providerGenerateSeed** (int numBytes)=0
Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator.

6.709.1 Detailed Description

Interface class used by Security Service Providers to implement a source of secure random bytes.

Since:

1.0

6.709.2 Constructor & Destructor Documentation

6.709.2.1 decaf::security::SecureRandomSpi::SecureRandomSpi ()

6.709.2.2 virtual decaf::security::SecureRandomSpi::~~SecureRandomSpi ()
 [virtual]

6.709.3 Member Function Documentation

6.709.3.1 virtual unsigned char* decaf::security::SecureRandomSpi::providerGenerateSeed (int *numBytes*) [pure virtual]

Generates a new set of seed bytes, the returned value may be used to seed another Random Number Generator. The caller owns the returned array and must delete it.

Parameters:

numBytes The number of bytes that should be generated for the new seed array.

Implemented in `decaf::internal::security::SecureRandomImpl` (p. 3337), and `decaf::internal::security::SecureRandomImpl` (p. 3337).

6.709.3.2 `virtual void decaf::security::SecureRandomSpi::providerNextBytes` (`unsigned char * bytes`, `int numBytes`) [pure virtual]

Generates the number of random bytes specified by the size parameter and write them to the passed bytes array. The array must have already been allocated and be of the correct size to prevent segmentation faults.

Parameters:

bytes The array that will be filled with random bytes equal to size.

numBytes The number of bytes to generate and write into the bytes array.

Implemented in `decaf::internal::security::SecureRandomImpl` (p. 3338), and `decaf::internal::security::SecureRandomImpl` (p. 3338).

6.709.3.3 `virtual void decaf::security::SecureRandomSpi::providerSetSeed` (`const unsigned char * seed`, `int size`) [pure virtual]

Reseed the Random Number Generator, the value given supplements the previous seed value if any instead of replacing it.

Parameters:

seed The array of bytes used to update the generators seed.

size The size of the passed byte array.

Implemented in `decaf::internal::security::SecureRandomImpl` (p. 3338), and `decaf::internal::security::SecureRandomImpl` (p. 3338).

The documentation for this class was generated from the following file:

- `src/main/decaf/security/SecureRandomSpi.h`

6.710 decaf::util::concurrent::Semaphore Class Reference

A counting semaphore.

```
#include <src/main/decaf/util/concurrent/Semaphore.h>
```

Public Member Functions

- **Semaphore** (int permits)
*Creates a **Semaphore** (p. 3341) with the given number of permits and nonfair fairness setting.*
- **Semaphore** (int permits, bool fair)
*Creates a **Semaphore** (p. 3341) with the given number of permits and the given fairness setting.*
- virtual **~Semaphore** ()
- void **acquire** () throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::RuntimeException)
Acquires a permit from this semaphore, blocking until one is available, or the thread is interrupted.
- void **acquireUninterruptibly** () throw (decaf::lang::exceptions::RuntimeException)
Acquires a permit from this semaphore, blocking until one is available.
- bool **tryAcquire** () throw (decaf::lang::exceptions::RuntimeException)
Acquires a permit from this semaphore, only if one is available at the time of invocation.
- bool **tryAcquire** (long long timeout, const **TimeUnit** &unit) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::RuntimeException)
Acquires a permit from this semaphore, if one becomes available within the given waiting time and the current thread has not been interrupted.
- void **release** () throw (decaf::lang::exceptions::RuntimeException)
Releases a permit, returning it to the semaphore.
- void **acquire** (int permits) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)
Acquires the given number of permits from this semaphore, blocking until all are available, or the thread is interrupted.
- void **acquireUninterruptibly** (int permits) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)
Acquires the given number of permits from this semaphore, blocking until all are available.
- bool **tryAcquire** (int permits) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)
Acquires the given number of permits from this semaphore, only if all are available at the time of invocation.
- bool **tryAcquire** (int permits, long long timeout, const **TimeUnit** &unit) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)

Acquires the given number of permits from this semaphore, if all become available within the given waiting time and the current thread has not been interrupted.

- void **release** (int permits) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)

Releases the given number of permits, returning them to the semaphore.

- int **availablePermits** () const

Returns the current number of permits available in this semaphore.

- int **drainPermits** () throw (decaf::lang::exceptions::RuntimeException)

Acquires and returns all permits that are immediately available.

- bool **isFair** () const

- std::string **toString** () const

Returns a string identifying this semaphore, as well as its state.

6.710.1 Detailed Description

A counting semaphore. Conceptually, a semaphore maintains a set of permits. Each **acquire()** (p. 3344) blocks if necessary until a permit is available, and then takes it. Each **release()** (p. 3347) adds a permit, potentially releasing a blocking acquirer. However, no actual permit objects are used; the **Semaphore** (p. 3341) just keeps a count of the number available and acts accordingly.

Semaphores are often used to restrict the number of threads than can access some (physical or logical) resource.

```
class Pool { private:
```

```
static const int MAX_AVAILABLE = 100; Semaphore (p. 3341) available;
```

```
std::vector<std::string> items; std::vector<bool> used;
```

```
Mutex (p. 2782) lock;
```

```
public:
```

```
Pool() : available( MAX_AVAILABLE, true ) { used.resize( MAX_AVAILABLE ); items.resize( MAX_AVAILABLE ); }
```

```
std::string getItem() throws InterruptedException { available.acquire(); return getNextAvailableItem(); }
```

```
void putItem( std::string x ) { if( markAsUnused(x) ) { available.release(); } }
```

```
std::string getNextAvailableItem() {
```

```
synchronized( &lock ) (p. 4893) { for( int i = 0; i < MAX_AVAILABLE; ++i ) { if( !used[i] ) { used[i] = true; return items[i]; } }
```

```
return std::string(); // not reached }
```

```
bool markAsUnused( const std::string& item ) { synchronized( &lock ) (p. 4893) { for( int i = 0; i < MAX_AVAILABLE; ++i ) { if( item == items[i] ) { if( used[i] ) { used[i] = false; return true; } else return false; } } } return false; } };
```

Before obtaining an item each thread must acquire a permit from the semaphore, guaranteeing that an item is available for use. When the thread has finished with the item it is returned back

to the pool and a permit is returned to the semaphore, allowing another thread to acquire that item. Note that no synchronization lock is held when **acquire()** (p. 3344) is called as that would prevent an item from being returned to the pool. The semaphore encapsulates the synchronization needed to restrict access to the pool, separately from any synchronization needed to maintain the consistency of the pool itself.

A semaphore initialized to one, and which is used such that it only has at most one permit available, can serve as a mutual exclusion lock. This is more commonly known as a binary semaphore, because it only has two states: one permit available, or zero permits available. When used in this way, the binary semaphore has the property (unlike many **Lock** (p. 2375) implementations), that the "lock" can be released by a thread other than the owner (as semaphores have no notion of ownership). This can be useful in some specialized contexts, such as deadlock recovery.

The constructor for this class optionally accepts a fairness parameter. When set false, this class makes no guarantees about the order in which threads acquire permits. In particular, barging is permitted, that is, a thread invoking **acquire()** (p. 3344) can be allocated a permit ahead of a thread that has been waiting - logically the new thread places itself at the head of the queue of waiting threads. When fairness is set true, the semaphore guarantees that threads invoking any of the acquire methods are selected to obtain permits in the order in which their invocation of those methods was processed (first-in-first-out; FIFO). Note that FIFO ordering necessarily applies to specific **internal** (p. 144) points of execution within these methods. So, it is possible for one thread to invoke acquire before another, but reach the ordering point after the other, and similarly upon return from the method. Also note that the untimed tryAcquire methods do not honor the fairness setting, but will take any permits that are available.

Generally, semaphores used to control resource access should be initialized as fair, to ensure that no thread is starved out from accessing a resource. When using semaphores for other kinds of synchronization control, the throughput advantages of non-fair ordering often outweigh fairness considerations.

This class also provides convenience methods to acquire and release multiple permits at a time. Beware of the increased risk of indefinite postponement when these methods are used without fairness set true.

Since:

1.0

6.710.2 Constructor & Destructor Documentation

6.710.2.1 decaf::util::concurrent::Semaphore::Semaphore (int *permits*)

Creates a **Semaphore** (p. 3341) with the given number of permits and nonfair fairness setting.

Parameters:

permits the initial number of permits available. This value may be negative, in which case releases must occur before any acquires will be granted.

6.710.2.2 decaf::util::concurrent::Semaphore::Semaphore (int *permits*, bool *fair*)

Creates a **Semaphore** (p. 3341) with the given number of permits and the given fairness setting.

Parameters:

permits the initial number of permits available. This value may be negative, in which case releases must occur before any acquires will be granted.

fair true if this semaphore will guarantee first-in first-out granting of permits under contention, else false

6.710.2.3 `virtual decaf::util::concurrent::Semaphore::~~Semaphore ()` [virtual]

6.710.3 Member Function Documentation

6.710.3.1 `void decaf::util::concurrent::Semaphore::acquire (int permits)`
`throw (decaf::lang::exceptions::InterruptedException,`
`decaf::lang::exceptions::IllegalArgumentException,`
`decaf::lang::exceptions::RuntimeException)`

Acquires the given number of permits from this semaphore, blocking until all are available, or the thread is interrupted. Acquires the given number of permits, if they are available, and returns immediately, reducing the number of available permits by the given amount.

If insufficient permits are available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of two things happens:

* Some other thread invokes one of the release methods for this semaphore, the current thread is next to be assigned permits and the number of available permits satisfies this request; or * Some other thread interrupts the current thread.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting for a permit,

then `InterruptedException` is thrown and the current thread's interrupted status is cleared. Any permits that were to be assigned to this thread are instead assigned to other threads trying to acquire permits, as if permits had been made available by a call to `release()` (p. 3347).

Parameters:

permits the number of permits to acquire.

Exceptions:

InterruptedException if the current thread is interrupted.

IllegalArgumentException if the permits argument is negative.

RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.2 `void decaf::util::concurrent::Semaphore::acquire ()`
`throw (decaf::lang::exceptions::InterruptedException,`
`decaf::lang::exceptions::RuntimeException)`

Acquires a permit from this semaphore, blocking until one is available, or the thread is interrupted. Acquires a permit, if one is available and returns immediately, reducing the number of available permits by one.

If no permit is available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of two things happens:

* Some other thread invokes the `release()` (p. 3347) method for this semaphore and the current thread is next to be assigned a permit; or * Some other thread interrupts the current thread.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting for a permit,

then InterruptedException is thrown and the current thread's interrupted status is cleared.

Exceptions:

InterruptedException - if the current thread is interrupted.

RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.3 void decaf::util::concurrent::Semaphore::acquireUninterruptibly (int permits) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)

Acquires the given number of permits from this semaphore, blocking until all are available. Acquires the given number of permits, if they are available, and returns immediately, reducing the number of available permits by the given amount.

If insufficient permits are available then the current thread becomes disabled for thread scheduling purposes and lies dormant until some other thread invokes one of the release methods for this semaphore, the current thread is next to be assigned permits and the number of available permits satisfies this request.

If the current thread is interrupted while waiting for permits then it will continue to wait and its position in the queue is not affected. When the thread does return from this method its interrupt status will be set.

Parameters:

permits the number of permits to acquire.

Exceptions:

IllegalArgumentException if the permits argument is negative.

RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.4 void decaf::util::concurrent::Semaphore::acquireUninterruptibly () throw (decaf::lang::exceptions::RuntimeException)

Acquires a permit from this semaphore, blocking until one is available. Acquires a permit, if one is available and returns immediately, reducing the number of available permits by one.

If no permit is available then the current thread becomes disabled for thread scheduling purposes and lies dormant until some other thread invokes the **release()** (p. 3347) method for this semaphore and the current thread is next to be assigned a permit.

If the current thread is interrupted while waiting for a permit then it will continue to wait, but the time at which the thread is assigned a permit may change compared to the time it would have received the permit had no interruption occurred. When the thread does return from this method its interrupt status will be set.

Exceptions:

RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.5 int decaf::util::concurrent::Semaphore::availablePermits () const

Returns the current number of permits available in this semaphore. This method is typically used for debugging and testing purposes.

Returns:

the number of permits available in this semaphore

6.710.3.6 int decaf::util::concurrent::Semaphore::drainPermits () throw (decaf::lang::exceptions::RuntimeException)

Acquires and returns all permits that are immediately available.

Returns:

the number of permits acquired

Exceptions:

RuntimeException if an unexpected error occurs while draining the **Semaphore** (p. 3341).

6.710.3.7 bool decaf::util::concurrent::Semaphore::isFair () const**Returns:**

true if this semaphore has fairness set true

6.710.3.8 void decaf::util::concurrent::Semaphore::release (int *permits*) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)

Releases the given number of permits, returning them to the semaphore. Releases the given number of permits, increasing the number of available permits by that amount. If any threads are trying to acquire permits, then one is selected and given the permits that were just released. If the number of available permits satisfies that thread's request then that thread is (re)enabled for thread scheduling purposes; otherwise the thread will wait until sufficient permits are available. If there are still permits available after this thread's request has been satisfied, then those permits are assigned in turn to other threads trying to acquire permits.

Parameters:

permits the number of permits to release

Exceptions:

IllegalArgumentException if the permits argument is negative.

RuntimeException if an unexpected error occurs while releasing the **Semaphore** (p. 3341).

6.710.3.9 void decaf::util::concurrent::Semaphore::release () throw (decaf::lang::exceptions::RuntimeException)

Releases a permit, returning it to the semaphore. Releases a permit, increasing the number of available permits by one. If any threads are trying to acquire a permit, then one is selected and given the permit that was just released. That thread is (re)enabled for thread scheduling purposes.

There is no requirement that a thread that releases a permit must have acquired that permit by calling **acquire()** (p. 3344). Correct usage of a semaphore is established by programming convention in the application.

Exceptions:

RuntimeException if an unexpected error occurs while releasing the **Semaphore** (p. 3341).

6.710.3.10 std::string decaf::util::concurrent::Semaphore::toString () const

Returns a string identifying this semaphore, as well as its state. The state, in brackets, includes the String "Permits =" followed by the number of permits.

Returns:

a string identifying this semaphore, as well as its state

6.710.3.11 bool decaf::util::concurrent::Semaphore::tryAcquire (int *permits*, long long *timeout*, const TimeUnit & *unit*) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::RuntimeException)

Acquires the given number of permits from this semaphore, if all become available within the given waiting time and the current thread has not been interrupted. Acquires the given number of permits, if they are available and returns immediately, with the value true, reducing the number of available permits by the given amount.

If insufficient permits are available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

* Some other thread invokes one of the release methods for this semaphore, the current thread is next to be assigned permits and the number of available permits satisfies this request; or * Some other thread interrupts the current thread; or * The specified waiting time elapses.

If the permits are acquired then the value true is returned.

If the current thread:

* has its interrupted status set on entry to this method; or * is interrupted while waiting to acquire the permits,

then InterruptedException is thrown and the current thread's interrupted status is cleared. Any permits that were to be assigned to this thread, are instead assigned to other threads trying to acquire permits, as if the permits had been made available by a call to **release()** (p. 3347).

If the specified waiting time elapses then the value false is returned. If the time is less than or equal to zero, the method will not wait at all. Any permits that were to be assigned to this thread, are instead assigned to other threads trying to acquire permits, as if the permits had been made available by a call to **release()** (p. 3347).

Parameters:

permits the number of permits to acquire
timeout the maximum amount of time to wait to acquire the permits.
unit the units that the timeout param represents.

Returns:

true if all permits were acquired and false if the waiting time elapsed before all permits were acquired

Exceptions:

IllegalArgumentException if the permits argument is negative.
RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.12 `bool decaf::util::concurrent::Semaphore::tryAcquire (int permits)
 throw (decaf::lang::exceptions::IllegalArgumentException,
 decaf::lang::exceptions::RuntimeException)`

Acquires the given number of permits from this semaphore, only if all are available at the time of invocation. Acquires the given number of permits, if they are available, and returns immediately, with the value true, reducing the number of available permits by the given amount.

If insufficient permits are available then this method will return immediately with the value false and the number of available permits is unchanged.

Even when this semaphore has been set to use a fair ordering policy, a call to tryAcquire will immediately acquire a permit if one is available, whether or not other threads are currently waiting. This "barging" behavior can be useful in certain circumstances, even though it breaks fairness. If you want to honor the fairness setting, then use tryAcquire(permits, 0, **TimeUnit.SECONDS** (p. 3816)) which is almost equivalent (it also detects interruption).

Parameters:

permits the number of permits to acquire

Returns:

true if the permits were acquired and false otherwise.

Exceptions:

IllegalArgumentException if the permits argument is negative.
RuntimeException if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.13 `bool decaf::util::concurrent::Semaphore::tryAcquire
 (long long timeout, const TimeUnit & unit) throw
 (decaf::lang::exceptions::InterruptedException,
 decaf::lang::exceptions::RuntimeException)`

Acquires a permit from this semaphore, if one becomes available within the given waiting time and the current thread has not been interrupted. Acquires a permit, if one is available and returns immediately, with the value true, reducing the number of available permits by one.

If no permit is available then the current thread becomes disabled for thread scheduling purposes and lies dormant until one of three things happens:

- * Some other thread invokes the **release()** (p. 3347) method for this semaphore and the current thread is next to be assigned a permit; or
- * Some other thread interrupts the current thread; or
- * The specified waiting time elapses.

If a permit is acquired then the value `true` is returned.

If the current thread:

- * has its interrupted status set on entry to this method; or
- * is interrupted while waiting to acquire a permit,

then `InterruptedException` is thrown and the current thread's interrupted status is cleared.

If the specified waiting time elapses then the value `false` is returned. If the time is less than or equal to zero, the method will not wait at all.

Parameters:

- timeout* the maximum time to wait for a permit
- unit* the time unit of the timeout argument

Returns:

`true` if a permit was acquired and `false` if the waiting time elapsed before a permit was acquired

Exceptions:

- InterruptedException* if the current thread is interrupted.
- RuntimeException* if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

6.710.3.14 `bool decaf::util::concurrent::Semaphore::tryAcquire () throw (decaf::lang::exceptions::RuntimeException)`

Acquires a permit from this semaphore, only if one is available at the time of invocation. Acquires a permit, if one is available and returns immediately, with the value `true`, reducing the number of available permits by one.

If no permit is available then this method will return immediately with the value `false`.

Even when this semaphore has been set to use a fair ordering policy, a call to **tryAcquire()** (p. 3349) will immediately acquire a permit if one is available, whether or not other threads are currently waiting. This "barging" behavior can be useful in certain circumstances, even though it breaks fairness. If you want to honor the fairness setting, then use `tryAcquire(0, TimeUnit.SECONDS)` (p. 3816)) which is almost equivalent (it also detects interruption).

Returns:

`true` if a permit was acquired and `false` otherwise

Exceptions:

- RuntimeException* if an unexpected error occurs while acquiring the **Semaphore** (p. 3341).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/Semaphore.h`

6.711 activemq::cmsutil::CmsTemplate::SendExecutor Class Reference

#include <src/main/activemq/cmsutil/CmsTemplate.h> Inheritance diagram for activemq::cmsutil::CmsTemplate::SendExecutor:

Public Member Functions

- **SendExecutor** (**MessageCreator** *messageCreator, **CmsTemplate** *parent)
- virtual **~SendExecutor** ()
- virtual void **doInCms** (**cms::Session** *session, **cms::MessageProducer** *producer) throw (**cms::CMSException**)

Execute an action given a session and producer.

Protected Member Functions

- **SendExecutor** (const **SendExecutor** &)
- **SendExecutor** & operator= (const **SendExecutor** &)

6.711.1 Constructor & Destructor Documentation

- 6.711.1.1** **activemq::cmsutil::CmsTemplate::SendExecutor::SendExecutor** (const **SendExecutor** &) [inline, protected]
- 6.711.1.2** **activemq::cmsutil::CmsTemplate::SendExecutor::SendExecutor** (**MessageCreator** * *messageCreator*, **CmsTemplate** * *parent*) [inline]
- 6.711.1.3** virtual **activemq::cmsutil::CmsTemplate::SendExecutor::~~SendExecutor** () [inline, virtual]

6.711.2 Member Function Documentation

- 6.711.2.1** virtual void **activemq::cmsutil::CmsTemplate::SendExecutor::doInCms** (**cms::Session** * *session*, **cms::MessageProducer** * *producer*) throw (**cms::CMSException**) [inline, virtual]

Execute an action given a session and producer.

Parameters:

session the CMS Session

producer the CMS Producer

Exceptions:

cms::CMSException (p. 1160) if thrown by CMS API methods

Implements **activemq::cmsutil::ProducerCallback** (p. 3064).

6.711.2.2 SendExecutor& activemq::cmsutil::CmsTemplate::SendExecutor::operator=(const SendExecutor &) [inline, protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/CmsTemplate.h`

6.712 decaf::net::ServerSocket Class Reference

This class implements server sockets.

#include <src/main/decaf/net/ServerSocket.h> Inheritance diagram for decaf::net::ServerSocket:

Public Member Functions

- **ServerSocket** ()
Creates a non-bound server socket.
- **ServerSocket** (int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*
- **ServerSocket** (int port, int backlog) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*
- **ServerSocket** (int port, int backlog, const InetAddress *address) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*
- virtual ~**ServerSocket** ()
*Releases socket handle if **close()** (p. 3357) hasn't been called.*
- virtual void **bind** (const std::string &host, int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
Bind and listen to given local IPAddress and port, if the address is empty than a valid local address will be chosen, and if the port of 0 than an available open port will be chosen.
- virtual void **bind** (const std::string &host, int port, int backlog) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
Bind and listen to given local IPAddress and port, if the address is empty than a valid local address will be chosen, and if the port of 0 than an available open port will be chosen.
- virtual **Socket** * **accept** () throw (decaf::io::IOException)
*Listens for a connection request on the bound IPAddress and Port for this **ServerSocket** (p. 3352), the caller blocks until a connection is made.*
- virtual void **close** () throw (decaf::io::IOException)
Closes the server socket, causing any Threads blocked on an accept call to throw an Exception.
- virtual bool **isClosed** () const
- virtual bool **isBound** () const
- virtual int **getReceiveBufferSize** () const throw (SocketException)

Gets the receive buffer size for this socket, SO_RCVBUF.

- virtual void **setReceiveBufferSize** (int size) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)

Sets the receive buffer size for this socket, SO_RCVBUF.

- virtual bool **getReuseAddress** () const throw (SocketException)

Gets the reuse address flag, SO_REUSEADDR.

- virtual void **setReuseAddress** (bool reuse) throw (SocketException)

Sets the reuse address flag, SO_REUSEADDR.

- virtual int **getSoTimeout** () const throw (SocketException)

Gets the timeout for socket operations, SO_TIMEOUT.

- virtual void **setSoTimeout** (int timeout) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)

Sets the timeout for socket operations, SO_TIMEOUT.

- virtual int **getLocalPort** () const

*Gets the port number on the Local machine that this **ServerSocket** (p. 3352) is bound to.*

- virtual std::string **toString** () const

Static Public Member Functions

- static void **setSocketImplFactory** (SocketImplFactory *factory) throw (decaf::io::IOException, decaf::net::SocketException)

*Sets the instance of a **SocketImplFactory** (p. 3537) that the **ServerSocket** (p. 3352) class should use when new instances of this class are created.*

Protected Member Functions

- **ServerSocket** (SocketImpl *impl)

*Creates a **ServerSocket** (p. 3352) wrapping the provided **SocketImpl** (p. 3529) instance, this **Socket** (p. 3503) is considered unconnected.*

- virtual void **implAccept** (Socket *socket) throw (decaf::io::IOException)

*Virtual method that allows a **ServerSocket** (p. 3352) subclass to override the accept call and provide its own **SocketImpl** (p. 3529) for the socket.*

- virtual int **getDefaultBacklog** ()

Allows a subclass to override what is considered the default backlog.

- void **checkClosed** () const throw (decaf::io::IOException)
- void **ensureCreated** () const throw (decaf::io::IOException)
- void **setupSocketImpl** (int port, int backlog, const **InetAddress** *ifAddress)

6.712.1 Detailed Description

This class implements server sockets. A server socket waits for requests to come in over the network.

The actual work of the server socket is performed by an instance of the **SocketImpl** (p. 3529) class. An application can change the socket factory that creates the socket implementation to configure itself to create sockets of a particular type.

Since:

1.0

6.712.2 Constructor & Destructor Documentation

6.712.2.1 `decaf::net::ServerSocket::ServerSocket ()`

Creates a non-bound server socket.

6.712.2.2 `decaf::net::ServerSocket::ServerSocket (int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)`

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. When this constructor is called the size of the backlog queue is set at 50, connections that arrive after the backlog has been reached are refused.

If a **SocketImplFactory** (p. 3537) is registered then the `createSocketImpl` method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.712.2.3 `decaf::net::ServerSocket::ServerSocket (int port, int backlog) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)`

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. When this constructor is called the size of the backlog queue is set at backlog, connections that arrive after the backlog has been reached are refused. If backlog is zero or negative then the default backlog value of 50 is used.

If a **SocketImplFactory** (p. 3537) is registered then the `createSocketImpl` method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The the number of incoming connection attempts to queue before connections are refused.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.712.2.4 decaf::net::ServerSocket::ServerSocket (int *port*, int *backlog*, const InetAddress * *address*) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. If the value of the ifAddress is empty or NULL then the ANY address is used.

When this constructor is called the size of the backlog queue is set at backlog, connections that arrive after the backlog has been reached are refused. If backlog is zero or negative then the default backlog value of 50 is used.

If a **SocketImplFactory** (p. 3537) is registered then the createSocketImpl method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The the number of incoming connection attempts to queue before connections are refused.

ifAddress The IP Address to bind to on the local machine.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.712.2.5 virtual decaf::net::ServerSocket::~~ServerSocket () [virtual]

Releases socket handle if **close()** (p. 3357) hasn't been called.

6.712.2.6 decaf::net::ServerSocket::ServerSocket (SocketImpl * *impl*) [protected]

Creates a **ServerSocket** (p. 3352) wrapping the provided **SocketImpl** (p. 3529) instance, this **Socket** (p. 3503) is considered unconnected. The **ServerSocket** (p. 3352) class takes ownership of this **SocketImpl** (p. 3529) pointer and will delete it when the **Socket** (p. 3503) class is destroyed.

Parameters:

impl The **SocketImpl** (p. 3529) instance to wrap.

Exceptions:

NullPointerException if the passed **SocketImpl** (p. 3529) is Null.

6.712.3 Member Function Documentation

6.712.3.1 virtual Socket* decaf::net::ServerSocket::accept () throw (decaf::io::IOException) [virtual]

Listens for a connection request on the bound IPAddress and Port for this **ServerSocket** (p. 3352), the caller blocks until a connection is made. If the SO_TIMEOUT option is set this method could throw a **SocketTimeoutException** (p. 3542) if the operation times out.

Returns:

a new **Socket** (p. 3503) object pointer. Never returns NULL, the returned pointer is owned by the caller and must be explicitly freed by them.

Exceptions:

IOException if an I/O error occurs while binding the socket.

SocketException (p. 3521) if an error occurs while blocking on the accept call.

SocketTimeoutException (p. 3542) if the SO_TIMEOUT option was used and the accept timed out.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2849).

6.712.3.2 virtual void decaf::net::ServerSocket::bind (const std::string & host, int port, int backlog) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Bind and listen to given local IPAddress and port, if the address is empty than a valid local address will be chosen, and if the port of 0 than an available open port will be chosen. If the backlog is greater than zero it will be used instead of the default value, otherwise the default value is used and no error is generated.

Parameters:

host The IP address or host name.

port The TCP port between 1..65535.

backlog The size of listen backlog.

Exceptions:

IOException if an I/O error occurs while binding the socket.

IllegalArgumentException if the parameters are not valid.

6.712.3.3 virtual void decaf::net::ServerSocket::bind (const std::string & host, int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Bind and listen to given local IPAddress and port, if the address is empty than a valid local address will be chosen, and if the port of 0 than an available open port will be chosen.

Parameters:

host The IP address or host name.

port The TCP port between 1..65535.

Exceptions:

IOException if an I/O error occurs while binding the socket.

IllegalArgumentException if the parameters are not valid.

6.712.3.4 void decaf::net::ServerSocket::checkClosed () const throw (decaf::io::IOException) [protected]

6.712.3.5 virtual void decaf::net::ServerSocket::close () throw (decaf::io::IOException) [virtual]

Closes the server socket, causing any Threads blocked on an accept call to throw an Exception.

Exceptions:

IOException if an I/O error occurs while performing this operation.

6.712.3.6 void decaf::net::ServerSocket::ensureCreated () const throw (decaf::io::IOException) [protected]

6.712.3.7 virtual int decaf::net::ServerSocket::getDefaultBacklog () [protected, virtual]

Allows a subclass to override what is considered the default backlog.

Returns:

the default backlog for connections.

6.712.3.8 virtual int decaf::net::ServerSocket::getLocalPort () const [virtual]

Gets the port number on the Local machine that this **ServerSocket** (p. 3352) is bound to.

Returns:

the port number of this machine that is bound, if not bound returns -1.

6.712.3.9 virtual int decaf::net::ServerSocket::getReceiveBufferSize () const throw (SocketException) [virtual]

Gets the receive buffer size for this socket, SO_RCVBUF. This is the buffer used by the underlying platform socket to buffer received data.

Returns:

the receive buffer size in bytes.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.712.3.10 `virtual bool decaf::net::ServerSocket::getReuseAddress () const throw (SocketException) [virtual]`

Gets the reuse address flag, SO_REUSEADDR.

Returns:

True if the address can be reused.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.712.3.11 `virtual int decaf::net::ServerSocket::getSoTimeout () const throw (SocketException) [virtual]`

Gets the timeout for socket operations, SO_TIMEOUT.

Returns:

The timeout in milliseconds for socket operations.

Exceptions:

SocketException (p. 3521) Thrown if unable to retrieve the information.

6.712.3.12 `virtual void decaf::net::ServerSocket::implAccept (Socket * socket) throw (decaf::io::IOException) [protected, virtual]`

Virtual method that allows a **ServerSocket** (p. 3352) subclass to override the accept call and provide its own **SocketImpl** (p. 3529) for the socket.

Parameters:

socket The socket object whose **SocketImpl** (p. 3529) should be used for the accept call.

Exceptions:

IOException if an I/O error occurs while performing this operation.

6.712.3.13 `virtual bool decaf::net::ServerSocket::isBound () const [virtual]`

Returns:

true if the server socket is bound.

6.712.3.14 `virtual bool decaf::net::ServerSocket::isClosed () const [virtual]`

Returns:

true if the close method has been called on the **ServerSocket** (p. 3352).

6.712.3.15 `virtual void decaf::net::ServerSocket::setReceiveBufferSize
 (int size) throw (SocketException, de-
 caf::lang::exceptions::IllegalArgumentException)
 [virtual]`

Sets the receive buffer size for this socket, SO_RCVBUF.

Parameters:

size Number of bytes to set the receive buffer to.

Exceptions:

SocketException (p. 3521) if the operation fails.

IllegalArgumentException if the value is zero or negative.

6.712.3.16 `virtual void decaf::net::ServerSocket::setReuseAddress (bool reuse)
 throw (SocketException) [virtual]`

Sets the reuse address flag, SO_REUSEADDR.

Parameters:

reuse If true, sets the flag.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.712.3.17 `static void decaf::net::ServerSocket::setSocketImplFactory
 (SocketImplFactory * factory) throw (decaf::io::IOException,
 decaf::net::SocketException) [static]`

Sets the instance of a **SocketImplFactory** (p. 3537) that the **ServerSocket** (p. 3352) class should use when new instances of this class are created. This method is only allowed to be used once during the lifetime of the application.

Parameters:

factory The instance of a **SocketImplFactory** (p. 3537) to use when new **SocketImpl** (p. 3529) objects are created.

Exceptions:

IOException if an I/O error occurs while performing this operation.

SocketException (p. 3521) if this method has already been called with a valid factory.

6.712.3.18 `virtual void decaf::net::ServerSocket::setSoTimeout (int timeout) throw
 (SocketException, decaf::lang::exceptions::IllegalArgumentException)
 [virtual]`

Sets the timeout for socket operations, SO_TIMEOUT. A value of zero indicates that timeout is infinite for operations on this socket.

Parameters:

timeout The timeout in milliseconds for socket operations.

Exceptions:

SocketException (p. 3521) Thrown if unable to set the information.

IllegalArgumentException if the timeout value is negative.

6.712.3.19 `void decaf::net::ServerSocket::setupSocketImpl (int port, int backlog,
 const InetAddress * ifAddress)` [protected]

6.712.3.20 `virtual std::string decaf::net::ServerSocket::toString () const` [virtual]

Returns:

a string representing this **ServerSocket** (p. 3352).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ServerSocket.h`

6.713 decaf::net::ServerSocketFactory Class Reference

Class used to create Server Sockets, subclasses can be created that create certain types of server sockets according to specific policies.

#include <src/main/decaf/net/ServerSocketFactory.h> Inheritance diagram for decaf::net::ServerSocketFactory:

Public Member Functions

- virtual `~ServerSocketFactory ()`
- virtual `ServerSocket * createServerSocket ()`
*Create a new **ServerSocket** (p. 3352) that is unbound.*
- virtual `ServerSocket * createServerSocket (int port)=0`
*Create a new **ServerSocket** (p. 3352) that is bound to the given port.*
- virtual `ServerSocket * createServerSocket (int port, int backlog)=0`
*Create a new **ServerSocket** (p. 3352) that is bound to the given port.*
- virtual `ServerSocket * createServerSocket (int port, int backlog, const InetAddress *address)=0`
*Create a new **ServerSocket** (p. 3352) that is bound to the given port.*

Static Public Member Functions

- static `ServerSocketFactory * getDefault ()`
*Returns the Default **ServerSocket** (p. 3352) factory, the pointer is owned by the Decaf runtime and should not be deleted by the caller.*

Protected Member Functions

- `ServerSocketFactory ()`

6.713.1 Detailed Description

Class used to create Server Sockets, subclasses can be created that create certain types of server sockets according to specific policies.

Since:

1.0

6.713.2 Constructor & Destructor Documentation

6.713.2.1 `decaf::net::ServerSocketFactory::ServerSocketFactory ()` [protected]

6.713.2.2 `virtual decaf::net::ServerSocketFactory::~~ServerSocketFactory ()`
[virtual]

6.713.3 Member Function Documentation

6.713.3.1 `virtual ServerSocket* decaf::net::ServerSocketFactory::createServerSocket (int port, int backlog, const InetAddress * address)` [pure virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will bind to the specified interface on the local host, and accept connections only on that interface. If the address parameter is NULL than the **ServerSocket** (p. 3352) will listen on all interfaces.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

address The address of the interface on the local machine to bind to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implemented in **decaf::internal::net::DefaultServerSocketFactory** (p. 1683), **decaf::internal::net::ssl::DefaultSSLServerSocketFactory** (p. 1694), and **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory** (p. 2855).

6.713.3.2 `virtual ServerSocket* decaf::net::ServerSocketFactory::createServerSocket (int port, int backlog)` [pure virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory. The **ServerSocket** (p. 3352) will use the specified connection backlog setting.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The number of pending connect request the **ServerSocket** (p. 3352) can queue.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implemented in **decaf::internal::net::DefaultServerSocketFactory** (p. 1684), **decaf::internal::net::ssl::DefaultSSLServerSocketFactory** (p. 1694), and **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory** (p. 2855).

6.713.3.3 virtual ServerSocket* decaf::net::ServerSocketFactory::createServerSocket(int *port*) [pure virtual]

Create a new **ServerSocket** (p. 3352) that is bound to the given port. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Implemented in **decaf::internal::net::DefaultServerSocketFactory** (p. 1684), **decaf::internal::net::ssl::DefaultSSLServerSocketFactory** (p. 1695), and **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory** (p. 2856).

6.713.3.4 virtual ServerSocket* decaf::net::ServerSocketFactory::createServerSocket() [virtual]

Create a new **ServerSocket** (p. 3352) that is unbound. The **ServerSocket** (p. 3352) will have been configured with the defaults from the factory.

Returns:

new **ServerSocket** (p. 3352) pointer that is owned by the caller.

Exceptions:

IOException if the **ServerSocket** (p. 3352) cannot be created for some reason.

Reimplemented in **decaf::internal::net::DefaultServerSocketFactory** (p. 1685), **decaf::internal::net::ssl::DefaultSSLServerSocketFactory** (p. 1695), and **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory** (p. 2856).

6.713.3.5 static ServerSocketFactory* decaf::net::ServerSocketFactory::getDefault() [static]

Returns the Default **ServerSocket** (p. 3352) factory, the pointer is owned by the Decaf runtime and should not be deleted by the caller. Only one default **ServerSocketFactory** (p. 3361) exists for the lifetime of the Application.

Returns:

the default **ServerSocketFactory** (p. 3361) for this application.

Reimplemented in **decaf::net::ssl::SSLServerSocketFactory** (p. 3561).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ServerSocketFactory.h`

6.714 cms::Session Class Reference

A **Session** (p.3365) object is a single-threaded context for producing and consuming messages.

#include <src/main/cms/Session.h> Inheritance diagram for cms::Session:

Public Types

- enum **AcknowledgeMode** {
AUTO_ACKNOWLEDGE, **DUPS_OK_ACKNOWLEDGE**, **CLIENT_-ACKNOWLEDGE**, **SESSION_TRANSACTIONED**,
INDIVIDUAL_ACKNOWLEDGE }

Public Member Functions

- virtual **~Session** ()
- virtual void **close** ()=0 throw (CMSEException)
Closes this session as well as any active child consumers or producers.
- virtual void **commit** ()=0 throw (CMSEException)
Commits all messages done in this transaction and releases any locks currently held.
- virtual void **rollback** ()=0 throw (CMSEException)
Rolls back all messages done in this transaction and releases any locks currently held.
- virtual void **recover** ()=0 throw (CMSEException)
Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message.
- virtual **MessageConsumer** * **createConsumer** (const **Destination** *destination)=0 throw (CMSEException)
*Creates a **MessageConsumer** (p. 2589) for the specified destination.*
- virtual **MessageConsumer** * **createConsumer** (const **Destination** *destination, const std::string &selector)=0 throw (CMSEException)
*Creates a **MessageConsumer** (p. 2589) for the specified destination, using a message selector.*
- virtual **MessageConsumer** * **createConsumer** (const **Destination** *destination, const std::string &selector, bool noLocal)=0 throw (CMSEException)
*Creates a **MessageConsumer** (p. 2589) for the specified destination, using a message selector.*
- virtual **MessageConsumer** * **createDurableConsumer** (const **Topic** *destination, const std::string &name, const std::string &selector, bool noLocal=false)=0 throw (CMSEException)
*Creates a durable subscriber to the specified topic, using a **Message** (p. 2534) selector.*
- virtual **MessageProducer** * **createProducer** (const **Destination** *destination)=0 throw (CMSEException)

*Creates a **MessageProducer** (p. 2725) to send messages to the specified destination.*

- virtual **QueueBrowser** * **createBrowser** (const **cms::Queue** *queue)=0 throw (CMSException)

*Creates a new **QueueBrowser** (p. 3153) to peek at Messages on the given **Queue** (p. 3148).*

- virtual **QueueBrowser** * **createBrowser** (const **cms::Queue** *queue, const std::string &selector)=0 throw (CMSException)

*Creates a new **QueueBrowser** (p. 3153) to peek at Messages on the given **Queue** (p. 3148).*

- virtual **Queue** * **createQueue** (const std::string &queueName)=0 throw (CMSException)

*Creates a queue identity given a **Queue** (p. 3148) name.*

- virtual **Topic** * **createTopic** (const std::string &topicName)=0 throw (CMSException)

*Creates a topic identity given a **Queue** (p. 3148) name.*

- virtual **TemporaryQueue** * **createTemporaryQueue** ()=0 throw (CMSException)

*Creates a **TemporaryQueue** (p. 3759) object.*

- virtual **TemporaryTopic** * **createTemporaryTopic** ()=0 throw (CMSException)

*Creates a **TemporaryTopic** (p. 3761) object.*

- virtual **Message** * **createMessage** ()=0 throw (CMSException)

*Creates a new **Message** (p. 2534).*

- virtual **BytesMessage** * **createBytesMessage** ()=0 throw (CMSException)

*Creates a **BytesMessage** (p. 1056).*

- virtual **BytesMessage** * **createBytesMessage** (const unsigned char *bytes, int bytes-Size)=0 throw (CMSException)

*Creates a **BytesMessage** (p. 1056) and sets the payload to the passed value.*

- virtual **StreamMessage** * **createStreamMessage** ()=0 throw (CMSException)

*Creates a new **StreamMessage** (p. 3652).*

- virtual **TextMessage** * **createTextMessage** ()=0 throw (CMSException)

*Creates a new **TextMessage** (p. 3763).*

- virtual **TextMessage** * **createTextMessage** (const std::string &text)=0 throw (CMSException)

*Creates a new **TextMessage** (p. 3763) and set the text to the value given.*

- virtual **MapMessage** * **createMapMessage** ()=0 throw (CMSException)

*Creates a new **MapMessage** (p. 2472).*

- virtual **AcknowledgeMode** **getAcknowledgeMode** () const =0 throw (CMSException)

Returns the acknowledgment mode of the session.

- virtual bool **isTransacted** () const =0 throw (CMSEException)
*Gets if the Session is a Transacted **Session** (p. 3365).*
- virtual void **unsubscribe** (const std::string &name)=0 throw (CMSEException)
Unsubscribes a durable subscription that has been created by a client.

6.714.1 Detailed Description

A **Session** (p. 3365) object is a single-threaded context for producing and consuming messages. A session serves several purposes:

- It is a factory for its message producers and consumers.
- It supplies provider-optimized message factories.
- It is a factory for TemporaryTopics and TemporaryQueues.
- It provides a way to create **Queue** (p. 3148) or **Topic** (p. 3817) objects for those clients that need to dynamically manipulate provider-specific destination names.
- It supports a single series of transactions that combine work spanning its producers and consumers into atomic units.
- It defines a serial order for the messages it consumes and the messages it produces.
- It retains messages it consumes until they have been acknowledged.
- It serializes execution of message listeners registered with its message consumers.

A session can create and service multiple message producers and consumers.

One typical use is to have a thread block on a synchronous **MessageConsumer** (p. 2589) until a message arrives. The thread may then use one or more of the Session's MessageProducers.

If a client desires to have one thread produce messages while others consume them, the client should use a separate session for its producing thread.

Certain rules apply to a session's **close** method and are detailed below.

- There is no need to close the producers and consumers of a closed session.
- The close call will block until a receive call or message listener in progress has completed. A blocked message consumer receive call returns null when this session is closed.
- Closing a transacted session must roll back the transaction in progress.
- The close method is the only **Session** (p. 3365) method that can be called concurrently.
- Invoking any other **Session** (p. 3365) method on a closed session must throw an **IllegalStateException** (p. 1997). Closing a closed session must not throw any exceptions.

Transacted Sessions

When a **Session** (p. 3365) is created it can be set to operate in a Transaction based mode. Each **Session** (p. 3365) then operates in a single transaction for all Producers and Consumers of that **Session** (p. 3365). Messages sent and received within a Transaction are grouped into an atomic unit that is committed or rolled back together.

For a **MessageProducer** (p. 2725) this implies that all messages sent by the producer are not sent to the Provider until the commit call is made. Rolling back the Transaction results in all produced Messages being dropped.

For a **MessageConsumer** (p. 2589) this implies that all received messages are not Acknowledged until the Commit call is made. Rolling back the Transaction results in all Consumed **Message** (p. 2534) being redelivered to the client, the Provider may allow configuration that limits the Maximum number of redeliveries for a **Message** (p. 2534).

Since:

1.0

6.714.2 Member Enumeration Documentation

6.714.2.1 enum cms::Session::AcknowledgeMode

Enumerator:

AUTO_ACKNOWLEDGE With this acknowledgment mode, the session automatically acknowledges a client's receipt of a message either when the session has successfully returned from a call to receive or when the message listener the session has called to process the message successfully returns.

DUPS_OK_ACKNOWLEDGE With this acknowledgment mode, the session automatically acknowledges a client's receipt of a message either when the session has successfully returned from a call to receive or when the message listener the session has called to process the message successfully returns. Acknowledgments may be delayed in this mode to increase performance at the cost of the message being redelivered this client fails.

CLIENT_ACKNOWLEDGE With this acknowledgment mode, the client acknowledges a consumed message by calling the message's acknowledge method.

SESSION_TRANSACTED Messages will be consumed when the transaction commits.

INDIVIDUAL_ACKNOWLEDGE **Message** (p. 2534) will be acknowledged individually. Normally the acks sent acknowledge the given message and all messages received before it, this mode only acknowledges one message.

6.714.3 Constructor & Destructor Documentation

6.714.3.1 virtual cms::Session::~~Session () [inline, virtual]

6.714.4 Member Function Documentation

6.714.4.1 virtual void cms::Session::close () throw (CMSEException) [pure virtual]

Closes this session as well as any active child consumers or producers.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implements **cms::Closeable** (p. 1148).

Implemented in **activemq::cmsutil::PooledSession** (p. 2957), and **activemq::core::ActiveMQSession** (p. 520).

6.714.4.2 `virtual void cms::Session::commit () throw (CMSExcption) [pure virtual]`

Commits all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSExcption (p. 1160) - If an internal error occurs.

IllegalStateException (p. 1997) - if the method is not called by a transacted session.

Implemented in **activemq::cmsutil::PooledSession** (p. 2958), and **activemq::core::ActiveMQSession** (p. 520).

Referenced by **activemq::cmsutil::PooledSession::commit()**.

6.714.4.3 `virtual QueueBrowser* cms::Session::createBrowser (const cms::Queue * queue, const std::string & selector) throw (CMSExcption) [pure virtual]`

Creates a new **QueueBrowser** (p. 3153) to peek at Messages on the given **Queue** (p. 3148).

Parameters:

queue the **Queue** (p. 3148) to browse

selector the **Message** (p. 2534) selector to filter which messages are browsed.

Returns:

New **QueueBrowser** (p. 3153) that is owned by the caller.

Exceptions:

CMSExcption (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if the destination given is invalid.

Implemented in **activemq::cmsutil::PooledSession** (p. 2958), and **activemq::core::ActiveMQSession** (p. 520).

6.714.4.4 `virtual QueueBrowser* cms::Session::createBrowser (const cms::Queue * queue) throw (CMSExcption) [pure virtual]`

Creates a new **QueueBrowser** (p. 3153) to peek at Messages on the given **Queue** (p. 3148).

Parameters:

queue the **Queue** (p. 3148) to browse

Returns:

New **QueueBrowser** (p. 3153) that is owned by the caller.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if the destination given is invalid.

Implemented in **activemq::cmsutil::PooledSession** (p. 2958), and **activemq::core::ActiveMQSession** (p. 521).

6.714.4.5 `virtual BytesMessage* cms::Session::createBytesMessage (const unsigned char * bytes, int bytesSize) throw (CMSEException) [pure virtual]`

Creates a **BytesMessage** (p. 1056) and sets the payload to the passed value.

Parameters:

bytes an array of bytes to set in the message

bytesSize the size of the bytes array, or number of bytes to use

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2959), and **activemq::core::ActiveMQSession** (p. 521).

6.714.4.6 `virtual BytesMessage* cms::Session::createBytesMessage () throw (CMSEException) [pure virtual]`

Creates a **BytesMessage** (p. 1056).

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2959), and **activemq::core::ActiveMQSession** (p. 521).

6.714.4.7 `virtual MessageConsumer* cms::Session::createConsumer (const Destination * destination, const std::string & selector, bool noLocal) throw (CMSEException) [pure virtual]`

Creates a **MessageConsumer** (p. 2589) for the specified destination, using a message selector.

Parameters:

destination the **Destination** (p. 1723) that this consumer receiving messages for.

selector the **Message** (p. 2534) Selector to use

noLocal if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Returns:

pointer to a new **MessageConsumer** (p. 2589) that is owned by the caller (caller deletes)

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if an invalid destination is specified.

InvalidSelectorException (p. 2138) - if the message selector is invalid.

Implemented in **activemq::cmsutil::PooledSession** (p. 2960), and **activemq::core::ActiveMQSession** (p. 522).

6.714.4.8 virtual `MessageConsumer* cms::Session::createConsumer (const Destination * destination, const std::string & selector) throw (CMSEException)` [pure virtual]

Creates a **MessageConsumer** (p. 2589) for the specified destination, using a message selector.

Parameters:

destination the **Destination** (p. 1723) that this consumer receiving messages for.

selector the **Message** (p. 2534) Selector to use

Returns:

pointer to a new **MessageConsumer** (p. 2589) that is owned by the caller (caller deletes)

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if an invalid destination is specified.

InvalidSelectorException (p. 2138) - if the message selector is invalid.

Implemented in **activemq::cmsutil::PooledSession** (p. 2961), and **activemq::core::ActiveMQSession** (p. 522).

6.714.4.9 virtual `MessageConsumer* cms::Session::createConsumer (const Destination * destination) throw (CMSEException)` [pure virtual]

Creates a **MessageConsumer** (p. 2589) for the specified destination.

Parameters:

destination the **Destination** (p. 1723) that this consumer receiving messages for.

Returns:

pointer to a new **MessageConsumer** (p. 2589) that is owned by the caller (caller deletes)

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if an invalid destination is specified.

Implemented in **activemq::cmsutil::PooledSession** (p. 2961), and **activemq::core::ActiveMQSession** (p. 522).

6.714.4.10 `virtual MessageConsumer* cms::Session::createDurableConsumer (const Topic * destination, const std::string & name, const std::string & selector, bool noLocal = false) throw (CMSEException) [pure virtual]`

Creates a durable subscriber to the specified topic, using a **Message** (p. 2534) selector. Sessions that create durable consumers must use the same client Id as was used the last time the subscription was created in order to receive all messages that were delivered while the client was offline.

Parameters:

destination the topic to subscribe to

name The name used to identify the subscription

selector the **Message** (p. 2534) Selector to use

noLocal if true, and the destination is a topic, inhibits the delivery of messages published by its own connection. The behavior for NoLocal is not specified if the destination is a queue.

Returns:

pointer to a new durable **MessageConsumer** (p. 2589) that is owned by the caller (caller deletes)

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if an invalid destination is specified.

InvalidSelectorException (p. 2138) - if the message selector is invalid.

Implemented in **activemq::cmsutil::PooledSession** (p. 2961), and **activemq::core::ActiveMQSession** (p. 523).

6.714.4.11 `virtual MapMessage* cms::Session::createMapMessage () throw (CMSEException) [pure virtual]`

Creates a new **MapMessage** (p. 2472).

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2962), and **activemq::core::ActiveMQSession** (p. 523).

6.714.4.12 `virtual Message* cms::Session::createMessage () throw (CMSEException) [pure virtual]`

Creates a new **Message** (p. 2534).

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2962), and **activemq::core::ActiveMQSession** (p. 523).

6.714.4.13 virtual MessageProducer* cms::Session::createProducer (const Destination * *destination*) throw (CMSEException) [pure virtual]

Creates a MessageProducer (p. 2725) to send messages to the specified destination.

Parameters:

destination the Destination (p. 1723) to send on

Returns:

New MessageProducer (p. 2725) that is owned by the caller.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

InvalidDestinationException (p. 2131) - if an invalid destination is specified.

Implemented in **activemq::cmsutil::PooledSession** (p. 2962), and **activemq::core::ActiveMQSession** (p. 524).

6.714.4.14 virtual Queue* cms::Session::createQueue (const std::string & *queueName*) throw (CMSEException) [pure virtual]

Creates a queue identity given a Queue (p. 3148) name.

Parameters:

queueName the name of the new Queue (p. 3148)

Returns:

new Queue (p. 3148) pointer that is owned by the caller.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2963), and **activemq::core::ActiveMQSession** (p. 524).

6.714.4.15 virtual StreamMessage* cms::Session::createStreamMessage () throw (CMSEException) [pure virtual]

Creates a new StreamMessage (p. 3652).

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2963), and **activemq::core::ActiveMQSession** (p. 524).

6.714.4.16 `virtual TemporaryQueue* cms::Session::createTemporaryQueue ()
throw (CMSEException) [pure virtual]`

Creates a `TemporaryQueue` (p. 3759) object.

Returns:

new `TemporaryQueue` (p. 3759) pointer that is owned by the caller.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::PooledSession` (p. 2963), and `activemq::core::ActiveMQSession` (p. 524).

6.714.4.17 `virtual TemporaryTopic* cms::Session::createTemporaryTopic () throw
(CMSEException) [pure virtual]`

Creates a `TemporaryTopic` (p. 3761) object.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::PooledSession` (p. 2964), and `activemq::core::ActiveMQSession` (p. 525).

6.714.4.18 `virtual TextMessage* cms::Session::createTextMessage (const std::string
& text) throw (CMSEException) [pure virtual]`

Creates a new `TextMessage` (p. 3763) and set the text to the value given.

Parameters:

text the initial text for the message

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::PooledSession` (p. 2964), and `activemq::core::ActiveMQSession` (p. 525).

6.714.4.19 `virtual TextMessage* cms::Session::createTextMessage () throw (
CMSEException) [pure virtual]`

Creates a new `TextMessage` (p. 3763).

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in `activemq::cmsutil::PooledSession` (p. 2964), and `activemq::core::ActiveMQSession` (p. 525).

6.714.4.20 `virtual Topic* cms::Session::createTopic (const std::string & topicName)
throw (CMSEException)` [pure virtual]

Creates a topic identity given a **Queue** (p. 3148) name.

Parameters:

topicName the name of the new **Topic** (p. 3817)

Returns:

new **Topic** (p. 3817) pointer that is owned by the caller.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2964), and **activemq::core::ActiveMQSession** (p. 526).

6.714.4.21 `virtual AcknowledgeMode cms::Session::getAcknowledgeMode () const
throw (CMSEException)` [pure virtual]

Returns the acknowledgment mode of the session.

Returns:

the Sessions Acknowledge Mode

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2965), and **activemq::core::ActiveMQSession** (p. 526).

6.714.4.22 `virtual bool cms::Session::isTransacted () const throw (CMSEException)` [pure virtual]

Gets if the Sessions is a Transacted **Session** (p. 3365).

Returns:

transacted true - false.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2965), and **activemq::core::ActiveMQSession** (p. 529).

6.714.4.23 `virtual void cms::Session::recover () throw (CMSEException) [pure virtual]`

Stops message delivery in this session, and restarts message delivery with the oldest unacknowledged message. All consumers deliver messages in a serial order. Acknowledging a received message automatically acknowledges all messages that have been delivered to the client.

Restarting a session causes it to take the following actions:

- Stop message delivery
- Mark all messages that might have been delivered but not acknowledged as "redelivered"
- Restart the delivery sequence including all unacknowledged messages that had been previously delivered. Redelivered messages do not have to be delivered in exactly their original delivery order.

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to stop and restart message delivery due to some internal error.

IllegalStateException (p. 1997) - if the method is called by a transacted session.

Implemented in `activemq::cmsutil::PooledSession` (p. 2966), and `activemq::core::ActiveMQSession` (p. 529).

6.714.4.24 `virtual void cms::Session::rollback () throw (CMSEException) [pure virtual]`

Rolls back all messages done in this transaction and releases any locks currently held.

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

IllegalStateException (p. 1997) - if the method is not called by a transacted session.

Implemented in `activemq::cmsutil::PooledSession` (p. 2966), and `activemq::core::ActiveMQSession` (p. 530).

6.714.4.25 `virtual void cms::Session::unsubscribe (const std::string & name) throw (CMSEException) [pure virtual]`

Unsubscribes a durable subscription that has been created by a client. This method deletes the state being maintained on behalf of the subscriber by its provider. It is erroneous for a client to delete a durable subscription while there is an active `MessageConsumer` (p. 2589) or `Subscriber` for the subscription, or while a consumed message is part of a pending transaction or has not been acknowledged in the session.

Parameters:

name The name used to identify this subscription

Exceptions:

CMSEException (p. 1160) - If an internal error occurs.

Implemented in **activemq::cmsutil::PooledSession** (p. 2966), and **activemq::core::ActiveMQSession** (p. 532).

The documentation for this class was generated from the following file:

- `src/main/cms/Session.h`

6.715 activemq::cmsutil::SessionCallback Class Reference

Callback for executing any number of operations on a provided CMS Session.

#include <src/main/activemq/cmsutil/SessionCallback.h> Inheritance diagram for activemq::cmsutil::SessionCallback:

Public Member Functions

- virtual `~SessionCallback ()`
- virtual void `doInCms (cms::Session *session)=0` throw (cms::CMSEException)
Execute any number of operations against the supplied CMS session.

6.715.1 Detailed Description

Callback for executing any number of operations on a provided CMS Session.

6.715.2 Constructor & Destructor Documentation

- 6.715.2.1 virtual `activemq::cmsutil::SessionCallback::~~SessionCallback ()` [inline, virtual]

6.715.3 Member Function Documentation

- 6.715.3.1 virtual void `activemq::cmsutil::SessionCallback::doInCms (cms::Session * session)` throw (cms::CMSEException) [pure virtual]

Execute any number of operations against the supplied CMS session.

Parameters:

session the CMS Session

Exceptions:

cms::CMSEException (p. 1160) if thrown by CMS API methods

Implemented in `activemq::cmsutil::CmsTemplate::ProducerExecutor` (p. 3065), and `activemq::cmsutil::CmsTemplate::ReceiveExecutor` (p. 3175).

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/SessionCallback.h`

6.716 activemq::commands::SessionId Class Reference

#include <src/main/activemq/commands/SessionId.h> Inheritance diagram for activemq::commands::SessionId:

Public Types

- typedef decaf::lang::PointerComparator< SessionId > COMPARATOR

Public Member Functions

- SessionId ()
- SessionId (const SessionId &other)
- SessionId (const ConnectionId *connectionId, long long sessionId)
- SessionId (const ProducerId *producerId)
- SessionId (const ConsumerId *consumerId)
- virtual ~SessionId ()
- virtual unsigned char getDataStructureType () const
Get the unique identifier that this object and its own Marshaler share.
- virtual SessionId * cloneDataStructure () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void copyDataStructure (const DataStructure *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string toString () const
Returns a string containing the information for this DataStructure (p. 1660) such as its type and value of its elements.
- virtual bool equals (const DataStructure *value) const
Compares the DataStructure (p. 1660) passed in to this one, and returns if they are equivalent.
- const Pointer< ConnectionId > & getParentId () const
- virtual const std::string & getConnectionId () const
- virtual std::string & getConnectionId ()
- virtual void setConnectionId (const std::string &connectionId)
- virtual long long getValue () const
- virtual void setValue (long long value)
- virtual int compareTo (const SessionId &value) const
- virtual bool equals (const SessionId &value) const
- virtual bool operator== (const SessionId &value) const
- virtual bool operator< (const SessionId &value) const
- SessionId & operator= (const SessionId &other)

Static Public Attributes

- static const unsigned char **ID_SESSIONID** = 121

Protected Attributes

- std::string **connectionId**
- long long **value**

6.716.1 Member Typedef Documentation

- 6.716.1.1** `typedef decaf::lang::PointerComparator<SessionId>
activemq::commands::SessionId::COMPARATOR`

6.716.2 Constructor & Destructor Documentation

- 6.716.2.1** `activemq::commands::SessionId::SessionId ()`
- 6.716.2.2** `activemq::commands::SessionId::SessionId (const SessionId & other)`
- 6.716.2.3** `activemq::commands::SessionId::SessionId (const ConnectionId *
connectionId, long long sessionId)`
- 6.716.2.4** `activemq::commands::SessionId::SessionId (const ProducerId *
producerId)`
- 6.716.2.5** `activemq::commands::SessionId::SessionId (const ConsumerId *
consumerId)`
- 6.716.2.6** `virtual activemq::commands::SessionId::~~SessionId () [virtual]`

6.716.3 Member Function Documentation

- 6.716.3.1** `virtual SessionId* activemq::commands::SessionId::cloneDataStructure ()
const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

- 6.716.3.2** `virtual int activemq::commands::SessionId::compareTo (const SessionId
& value) const [virtual]`
- 6.716.3.3** `virtual void activemq::commands::SessionId::copyDataStructure (const
DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.716.3.4 `virtual bool activemq::commands::SessionId::equals (const SessionId & value) const` [virtual]

6.716.3.5 `virtual bool activemq::commands::SessionId::equals (const DataStructure * value) const` [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.716.3.6 `virtual std::string& activemq::commands::SessionId::getConnectionId ()` [virtual]

6.716.3.7 `virtual const std::string& activemq::commands::SessionId::getConnectionId () const` [virtual]

6.716.3.8 `virtual unsigned char activemq::commands::SessionId::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.716.3.9 `const Pointer<ConnectionId>& activemq::commands::SessionId::getParentId () const`
- 6.716.3.10 `virtual long long activemq::commands::SessionId::getValue () const [virtual]`
- 6.716.3.11 `virtual bool activemq::commands::SessionId::operator< (const SessionId & value) const [virtual]`
- 6.716.3.12 `SessionId& activemq::commands::SessionId::operator= (const SessionId & other)`
- 6.716.3.13 `virtual bool activemq::commands::SessionId::operator== (const SessionId & value) const [virtual]`
- 6.716.3.14 `virtual void activemq::commands::SessionId::setConnectionId (const std::string & connectionId) [virtual]`
- 6.716.3.15 `virtual void activemq::commands::SessionId::setValue (long long value) [virtual]`
- 6.716.3.16 `virtual std::string activemq::commands::SessionId::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p.833).

6.716.4 Field Documentation

- 6.716.4.1 `std::string activemq::commands::SessionId::connectionId [protected]`
- 6.716.4.2 `const unsigned char activemq::commands::SessionId::ID_SESSIONID = 121 [static]`

Referenced by `activemq::state::CommandVisitorAdapter::processRemoveInfo()`.

- 6.716.4.3 `long long activemq::commands::SessionId::value [protected]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/SessionId.h`

6.717 activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3383).

#include <src/main/activemq/wireformat/openwire/marshal/v2/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.717.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3383). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.717.2 Constructor & Destructor Documentation

6.717.2.1 `activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.717.2.2 `virtual activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.717.3 Member Function Documentation

6.717.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.717.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.717.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.717.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.717.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.717.3.6 virtual void activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.717.3.7 virtual void activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/SessionIdMarshaller.h

6.718 activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3387).

#include <src/main/activemq/wireformat/openwire/marshal/v4/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.718.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3387). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.718.2 Constructor & Destructor Documentation

6.718.2.1 `activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.718.2.2 `virtual activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.718.3 Member Function Documentation

6.718.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.718.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.718.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.718.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.718.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.718.3.6 virtual void activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.718.3.7 virtual void activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**SessionIdMarshaller.h**

6.719 activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3391).

#include <src/main/activemq/wireformat/openwire/marshal/v6/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.719.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3391). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.719.2 Constructor & Destructor Documentation

6.719.2.1 `activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.719.2.2 `virtual activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.719.3 Member Function Documentation

6.719.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.719.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.719.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.719.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.719.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.719.3.6 virtual void activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.719.3.7 virtual void activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**SessionIdMarshaller.h**

6.720 activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3395).

#include <src/main/activemq/wireformat/openwire/marshal/v5/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.720.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3395). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.720.2 Constructor & Destructor Documentation

6.720.2.1 `activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.720.2.2 `virtual activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.720.3 Member Function Documentation

6.720.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.720.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.720.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.720.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.720.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.720.3.6 virtual void activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.720.3.7 virtual void activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**SessionIdMarshaller.h**

6.721 activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3399).

#include <src/main/activemq/wireformat/openwire/marshal/v3/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.721.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3399). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.721.2 Constructor & Destructor Documentation

6.721.2.1 `activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.721.2.2 `virtual activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.721.3 Member Function Documentation

6.721.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.721.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::getDataSetType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.721.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.721.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.721.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.721.3.6 virtual void activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.721.3.7 virtual void activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/SessionIdMarshaller.h

6.722 activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3403).

#include <src/main/activemq/wireformat/openwire/marshal/v1/SessionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller:

Public Member Functions

- `SessionIdMarshaller ()`
- `virtual ~SessionIdMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.722.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionIdMarshaller` (p. 3403). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.722.2 Constructor & Destructor Documentation

6.722.2.1 `activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::SessionIdMarshaller()` [inline]

6.722.2.2 `virtual activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::~~SessionIdMarshaller()` [inline, virtual]

6.722.3 Member Function Documentation

6.722.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.722.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.722.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.722.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.722.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.722.3.6 virtual void activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.722.3.7 virtual void activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**SessionIdMarshaller.h**

6.723 activemq::commands::SessionInfo Class Reference

#include <src/main/activemq/commands/SessionInfo.h> Inheritance diagram for activemq::commands::SessionInfo:

Public Member Functions

- **SessionInfo** ()
- virtual **~SessionInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **SessionInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- unsigned int **getAckMode** () const
- void **setAckMode** (unsigned int mode)
- **Pointer**< **RemoveInfo** > **createRemoveCommand** () const
- virtual const **Pointer**< **SessionId** > & **getSessionId** () const
- virtual **Pointer**< **SessionId** > & **getSessionId** ()
- virtual void **setSessionId** (const **Pointer**< **SessionId** > &sessionId)
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor)
throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_SESSIONINFO** = 4

Protected Attributes

- **Pointer**< **SessionId** > **sessionId**

6.723.1 Constructor & Destructor Documentation

6.723.1.1 `activemq::commands::SessionInfo::SessionInfo ()`

6.723.1.2 `virtual activemq::commands::SessionInfo::~~SessionInfo ()` [virtual]

6.723.2 Member Function Documentation

6.723.2.1 `virtual SessionInfo* activemq::commands::SessionInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.723.2.2 `virtual void activemq::commands::SessionInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.723.2.3 `Pointer<RemoveInfo> activemq::commands::SessionInfo::createRemoveCommand ()` `const`

6.723.2.4 `virtual bool activemq::commands::SessionInfo::equals (const DataStructure * value)` `const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.723.2.5 `unsigned int activemq::commands::SessionInfo::getAckMode () const`
 [inline]

6.723.2.6 `virtual unsigned char ac-`
 `tivemq::commands::SessionInfo::getDataStructureType ()`
 `const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.723.2.7 `virtual Pointer<SessionId>& ac-`
 `tivemq::commands::SessionInfo::getSessionId ()`
 [virtual]

6.723.2.8 `virtual const Pointer<SessionId>& ac-`
 `tivemq::commands::SessionInfo::getSessionId () const`
 [virtual]

6.723.2.9 `void activemq::commands::SessionInfo::setAckMode (unsigned int mode)`
 [inline]

6.723.2.10 `virtual void activemq::commands::SessionInfo::setSessionId (const`
 `Pointer< SessionId > & sessionId)` [virtual]

6.723.2.11 `virtual std::string activemq::commands::SessionInfo::toString () const`
 [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.723.2.12 `virtual Pointer<Command> activemq::commands::SessionInfo::visit`
 `(activemq::state::CommandVisitor * visitor) throw (`
 `exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.723.3 Field Documentation

6.723.3.1 `const unsigned char activemq::commands::SessionInfo::ID_SESSIONINFO = 4` [static]

6.723.3.2 `Pointer<SessionId> activemq::commands::SessionInfo::sessionId` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/SessionInfo.h`

6.724 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3411).

#include <src/main/activemq/wireformat/openwire/marshal/v6/SessionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller:

Public Member Functions

- `SessionInfoMarshaller ()`
- `virtual ~SessionInfoMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.724.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3411). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.724.2 Constructor & Destructor Documentation

6.724.2.1 `activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.724.2.2 `virtual activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.724.3 Member Function Documentation

6.724.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.724.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.724.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.724.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.724.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.724.3.6 virtual void activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.724.3.7 virtual void activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/SessionInfoMarshaller.h

6.725 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3415).

#include <src/main/activemq/wireformat/openwire/marshal/v5/SessionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller:

Public Member Functions

- `SessionInfoMarshaller ()`
- `virtual ~SessionInfoMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.725.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3415). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.725.2 Constructor & Destructor Documentation

6.725.2.1 `activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.725.2.2 `virtual activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.725.3 Member Function Documentation

6.725.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.725.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.725.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.725.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.725.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.725.3.6 virtual void activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.725.3.7 virtual void activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/SessionInfoMarshaller.h

6.726 activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3419).

#include <src/main/activemq/wireformat/openwire/marshal/v1/SessionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller:

Public Member Functions

- `SessionInfoMarshaller ()`
- `virtual ~SessionInfoMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshall an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.726.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3419). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.726.2 Constructor & Destructor Documentation

6.726.2.1 `activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.726.2.2 `virtual activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.726.3 Member Function Documentation

6.726.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.726.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.726.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

6.726.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

6.726.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

6.726.3.6 virtual void activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.726.3.7 virtual void activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**SessionInfoMarshaller.h**

6.727 activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3423).

#include <src/main/activemq/wireformat/openwire/marshal/v3/SessionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller:

Public Member Functions

- **SessionInfoMarshaller** ()
- virtual **~SessionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.727.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3423). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.727.2 Constructor & Destructor Documentation

6.727.2.1 `activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.727.2.2 `virtual activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.727.3 Member Function Documentation

6.727.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.727.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.727.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.727.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.727.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.727.3.6 virtual void activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.727.3.7 virtual void activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/SessionInfoMarshaller.h

6.728 activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3427).

#include <src/main/activemq/wireformat/openwire/marshal/v2/SessionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller:

Public Member Functions

- `SessionInfoMarshaller ()`
- `virtual ~SessionInfoMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.728.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3427). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.728.2 Constructor & Destructor Documentation

6.728.2.1 `activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.728.2.2 `virtual activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.728.3 Member Function Documentation

6.728.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.728.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.728.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.728.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.728.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.728.3.6 virtual void activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.728.3.7 virtual void activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**SessionInfoMarshaller.h**

6.729 activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3431).

#include <src/main/activemq/wireformat/openwire/marshal/v4/SessionInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller:

Public Member Functions

- `SessionInfoMarshaller ()`
- `virtual ~SessionInfoMarshaller ()`
- `virtual commands::DataStructure * createObject () const`
Creates a new instance of this marshalable type.
- `virtual unsigned char getDataStructureType () const`
Get the Data Structure Type that identifies this Marshaler.
- `virtual void tightUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual int tightMarshal1 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write the booleans that this object uses to a BooleanStream.
- `virtual void tightMarshal2 (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut, utils::BooleanStream *bs) throw (decaf::io::IOException)`
Write a object instance to data output stream.
- `virtual void looseUnmarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataInputStream *dataIn) throw (decaf::io::IOException)`
Un-marshal an object instance from the data input stream.
- `virtual void looseMarshal (OpenWireFormat *wireFormat, commands::DataStructure *dataStructure, decaf::io::DataOutputStream *dataOut) throw (decaf::io::IOException)`
Write a object instance to data output stream.

6.729.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for `SessionInfoMarshaller` (p. 3431). NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.729.2 Constructor & Destructor Documentation

6.729.2.1 `activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::SessionInfoMarshaller()` [inline]

6.729.2.2 `virtual activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::~~SessionInfoMarshaller()` [inline, virtual]

6.729.3 Member Function Documentation

6.729.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.729.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.729.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.729.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.729.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.729.3.6 virtual void activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.729.3.7 virtual void activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/SessionInfoMarshaller.h

6.730 activemq::cmsutil::SessionPool Class Reference

A pool of CMS sessions from the same connection and with the same acknowledge mode.

```
#include <src/main/activemq/cmsutil/SessionPool.h>
```

Public Member Functions

- **SessionPool** (**cms::Connection** *connection, **cms::Session::AcknowledgeMode** ackMode, **ResourceLifecycleManager** *resourceLifecycleManager)
Constructs a session pool.
- virtual **~SessionPool** ()
Destroys the pooled session objects, but not the underlying session resources.
- virtual **PooledSession** * **takeSession** () throw (cms::CMSException)
Takes a session from the pool, creating one if necessary.
- virtual void **returnSession** (**PooledSession** *session)
Returns a session to the pool.
- **ResourceLifecycleManager** * **getResourceLifecycleManager** ()

Protected Member Functions

- **SessionPool** (const **SessionPool** &)
- **SessionPool** & **operator=** (const **SessionPool** &)

6.730.1 Detailed Description

A pool of CMS sessions from the same connection and with the same acknowledge mode. Internal session resources are managed through a provided **ResourceLifecycleManager** (p. 3282), not by this pool. This class is thread-safe.

6.730.2 Constructor & Destructor Documentation

- 6.730.2.1** **activemq::cmsutil::SessionPool::SessionPool** (const **SessionPool** &)
[inline, protected]
- 6.730.2.2** **activemq::cmsutil::SessionPool::SessionPool** (**cms::Connection** * connection, **cms::Session::AcknowledgeMode** ackMode, **ResourceLifecycleManager** * resourceLifecycleManager)

Constructs a session pool.

Parameters:

connection the connection to be used for creating all sessions.

ackMode the acknowledge mode to be used for all sessions

resourceLifecycleManager the object responsible for managing the lifecycle of any allocated **cms::Session** (p. 3365) resources.

6.730.2.3 virtual `activemq::cmsutil::SessionPool::~~SessionPool ()` [virtual]

Destroys the pooled session objects, but not the underlying session resources. That is the job of the `ResourceLifecycleManager` (p. 3282).

6.730.3 Member Function Documentation**6.730.3.1** `ResourceLifecycleManager* activemq::cmsutil::SessionPool::getResourceLifecycleManager ()` [inline]**6.730.3.2** `SessionPool& activemq::cmsutil::SessionPool::operator= (const SessionPool &)` [inline, protected]**6.730.3.3** virtual void `activemq::cmsutil::SessionPool::returnSession (PooledSession * session)` [virtual]

Returns a session to the pool.

Parameters:

session the session to be returned.

6.730.3.4 virtual `PooledSession* activemq::cmsutil::SessionPool::takeSession ()` throw (`cms::CMSEException`) [virtual]

Takes a session from the pool, creating one if necessary.

Returns:

the pooled session object

Exceptions:

`cms::CMSEException` (p. 1160) if an error occurred

The documentation for this class was generated from the following file:

- `src/main/activemq/cmsutil/SessionPool.h`

6.731 activemq::state::SessionState Class Reference

```
#include <src/main/activemq/state/SessionState.h>
```

Public Member Functions

- **SessionState** (const **Pointer**< **SessionInfo** > &info)
- virtual ~**SessionState** ()
- std::string **toString** () const
- const **Pointer**< **SessionInfo** > **getInfo** () const
- void **addProducer** (const **Pointer**< **ProducerInfo** > &info)
- **Pointer**< **ProducerState** > **removeProducer** (const **Pointer**< **ProducerId** > &id)
- void **addConsumer** (const **Pointer**< **ConsumerInfo** > &info)
- **Pointer**< **ConsumerState** > **removeConsumer** (const **Pointer**< **ConsumerId** > &id)
- std::vector< **Pointer**< **ProducerState** > > **getProducerStates** () const
- **Pointer**< **ProducerState** > **getProducerState** (const **Pointer**< **ProducerId** > &id)
- std::vector< **Pointer**< **ConsumerState** > > **getConsumerStates** () const
- **Pointer**< **ConsumerState** > **getConsumerState** (const **Pointer**< **ConsumerId** > &id)
- void **checkShutdown** () const
- void **shutdown** ()

6.731.1 Constructor & Destructor Documentation

6.731.1.1 `activemq::state::SessionState::SessionState (const Pointer< SessionInfo > & info)`

6.731.1.2 `virtual activemq::state::SessionState::~~SessionState ()` [virtual]

6.731.2 Member Function Documentation

6.731.2.1 `void activemq::state::SessionState::addConsumer (const Pointer< ConsumerInfo > & info)` [inline]

6.731.2.2 `void activemq::state::SessionState::addProducer (const Pointer< ProducerInfo > & info)`

6.731.2.3 `void activemq::state::SessionState::checkShutdown ()` const

6.731.2.4 `Pointer<ConsumerState> activemq::state::SessionState::getConsumerState (const Pointer< ConsumerId > & id)` [inline]

6.731.2.5 `std::vector< Pointer<ConsumerState> > activemq::state::SessionState::getConsumerStates ()` const [inline]

6.731.2.6 `const Pointer<SessionInfo> activemq::state::SessionState::getInfo ()` const [inline]

6.731.2.7 `Pointer<ProducerState> activemq::state::SessionState::getProducerState (const Pointer< ProducerId > & id)` [inline]

6.731.2.8 `std::vector< Pointer<ProducerState> > activemq::state::SessionState::getProducerStates ()` const [inline]

6.731.2.9 `Pointer<ConsumerState> activemq::state::SessionState::removeConsumer (const Pointer< ConsumerId > & id)` [inline]

6.731.2.10 `Pointer<ProducerState> activemq::state::SessionState::removeProducer (const Pointer< ProducerId > & id)`

6.731.2.11 `void activemq::state::SessionState::shutdown ()` [inline]

6.731.2.12 `std::string activemq::state::SessionState::toString ()` const

The documentation for this class was generated from the following file:

- `src/main/activemq/state/SessionState.h`

6.732 decaf::util::Set< E > Class Template Reference

A collection that contains no duplicate elements.

#include <src/main/decaf/util/Set.h> Inheritance diagram for decaf::util::Set< E >:

Public Member Functions

- virtual `~Set ()`

6.732.1 Detailed Description

`template<typename E> class decaf::util::Set< E >`

A collection that contains no duplicate elements. More formally, sets contain no pair of elements `e1` and `e2` such that `e1 == e2`, and at most one null element. As implied by its name, this interface models the mathematical set abstraction.

The additional stipulation on constructors is, not surprisingly, that all constructors must create a set that contains no duplicate elements (as defined above).

Note: Great care must be exercised if mutable objects are used as set elements. The behavior of a set is not specified if the value of an object is changed in a manner that affects equals comparisons while the object is an element in the set.

Since:

1.0

6.732.2 Constructor & Destructor Documentation

6.732.2.1 `template<typename E> virtual decaf::util::Set< E >::~~Set () [inline, virtual]`

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Set.h`

6.733 decaf::lang::Short Class Reference

#include <src/main/decaf/lang/Short.h> Inheritance diagram for decaf::lang::Short:

Public Member Functions

- **Short** (short value)
- **Short** (const std::string &value) throw (exceptions::NumberFormatException)
- virtual ~**Short** ()
- virtual int **compareTo** (const **Short** &s) const
*Compares this **Short** (p. 3440) instance with another.*
- bool **equals** (const **Short** &s) const
- virtual bool **operator==** (const **Short** &s) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **Short** &s) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual int **compareTo** (const short &s) const
*Compares this **Short** (p. 3440) instance with another.*
- bool **equals** (const short &s) const
- virtual bool **operator==** (const short &s) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const short &s) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **toString** () const
- virtual double **doubleValue** () const
Answers the double value which the receiver represents.
- virtual float **floatValue** () const
Answers the float value which the receiver represents.
- virtual unsigned char **byteValue** () const
Answers the byte value which the receiver represents.
- virtual short **shortValue** () const
Answers the short value which the receiver represents.
- virtual int **intValue** () const
Answers the int value which the receiver represents.
- virtual long long **longValue** () const
Answers the long value which the receiver represents.

Static Public Member Functions

- static std::string **toString** (short value)
- static **Short decode** (const std::string &value) throw (exceptions::NumberFormatException)
*Decodes a **String** (p. 3665) into a **Short** (p. 3440).*
- static short **reverseBytes** (short value)
Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified short value.
- static short **parseShort** (const std::string &s, int radix) throw (exceptions::NumberFormatException)
Parses the string argument as a signed short in the radix specified by the second argument.
- static short **parseShort** (const std::string &s) throw (exceptions::NumberFormatException)
Parses the string argument as a signed decimal short.
- static **Short valueOf** (short value)
*Returns a **Short** (p. 3440) instance representing the specified short value.*
- static **Short valueOf** (const std::string &value) throw (exceptions::NumberFormatException)
*Returns a **Short** (p. 3440) object holding the value given by the specified std::string.*
- static **Short valueOf** (const std::string &value, int radix) throw (exceptions::NumberFormatException)
*Returns a **Short** (p. 3440) object holding the value extracted from the specified std::string when parsed with the radix given by the second argument.*

Static Public Attributes

- static const int **SIZE** = 16
Size of this objects primitive type in bits.
- static const short **MAX_VALUE** = (short)0x7FFF
Max Value for this Object's primitive type.
- static const short **MIN_VALUE** = (short)0x8000
Max Value for this Object's primitive type.

6.733.1 Constructor & Destructor Documentation

6.733.1.1 decaf::lang::Short::Short (short value)

Parameters:

value - short to wrap

6.733.1.2 `decaf::lang::Short::Short (const std::string & value) throw (exceptions::NumberFormatException)`

Parameters:

value - string value to convert to short and wrap

Exceptions:

NumberFormatException

6.733.1.3 `virtual decaf::lang::Short::~~Short () [inline, virtual]`

6.733.2 Member Function Documentation

6.733.2.1 `virtual unsigned char decaf::lang::Short::byteValue () const [inline, virtual]`

Answers the byte value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from `decaf::lang::Number` (p. 2835).

6.733.2.2 `virtual int decaf::lang::Short::compareTo (const short & s) const [virtual]`

Compares this **Short** (p. 3440) instance with another.

Parameters:

s - the **Short** (p. 3440) instance to be compared

Returns:

zero if this object represents the same short value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

Implements `decaf::lang::Comparable< short >` (p. 1214).

6.733.2.3 `virtual int decaf::lang::Short::compareTo (const Short & s) const [virtual]`

Compares this **Short** (p. 3440) instance with another.

Parameters:

s - the **Short** (p. 3440) instance to be compared

Returns:

zero if this object represents the same short value as the argument; a positive value if this object represents a value greater than the passed in value, and -1 if this object represents a value less than the passed in value.

6.733.2.4 static Short decaf::lang::Short::decode (const std::string & *value*) throw (exceptions::NumberFormatException) [static]

Decodes a **String** (p.3665) into a **Short** (p.3440). Accepts decimal, hexadecimal, and octal numbers given by the following grammar:

The sequence of characters following an (optional) negative sign and/or radix specifier ("0x", "0X", "#", or leading zero) is parsed as by the **Short.parseShort** (p.3446) method with the indicated radix (10, 16, or 8). This sequence of characters must represent a positive value or a **NumberFormatException** will be thrown. The result is negated if first character of the specified **String** (p.3665) is the minus sign. No whitespace characters are permitted in the string.

Parameters:

value - The string to decode

Returns:

a **Short** (p.3440) object containing the decoded value

Exceptions:

NumberFormatException if the string is not formatted correctly.

6.733.2.5 virtual double decaf::lang::Short::doubleValue () const [inline, virtual]

Answers the double value which the receiver represents.

Returns:

double the value of the receiver.

Implements **decaf::lang::Number** (p.2836).

6.733.2.6 bool decaf::lang::Short::equals (const short & *s*) const [inline, virtual]**Returns:**

true if the two **Short** (p.3440) Objects have the same value.

Implements **decaf::lang::Comparable< short >** (p.1215).

6.733.2.7 bool decaf::lang::Short::equals (const Short & *s*) const [inline]**Returns:**

true if the two **Short** (p.3440) Objects have the same value.

6.733.2.8 `virtual float decaf::lang::Short::floatValue () const [inline, virtual]`

Answers the float value which the receiver represents.

Returns:

float the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.733.2.9 `virtual int decaf::lang::Short::intValue () const [inline, virtual]`

Answers the int value which the receiver represents.

Returns:

int the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.733.2.10 `virtual long long decaf::lang::Short::longValue () const [inline, virtual]`

Answers the long value which the receiver represents.

Returns:

long the value of the receiver.

Implements **decaf::lang::Number** (p. 2836).

6.733.2.11 `virtual bool decaf::lang::Short::operator< (const short & s) const [inline, virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

s - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements **decaf::lang::Comparable< short >** (p. 1215).

6.733.2.12 `virtual bool decaf::lang::Short::operator< (const Short & s) const [inline, virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

s - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.733.2.13 `virtual bool decaf::lang::Short::operator==(const short & s) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

s - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

Implements `decaf::lang::Comparable< short >` (p.1215).

6.733.2.14 `virtual bool decaf::lang::Short::operator==(const Short & s) const`
[inline, virtual]

Compares equality between this object and the one passed.

Parameters:

s - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.733.2.15 `static short decaf::lang::Short::parseShort(const std::string & s) throw`
`(exceptions::NumberFormatException) [static]`

Parses the string argument as a signed decimal short. The characters in the string must all be decimal digits, except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting short value is returned, exactly as if the argument and the radix 10 were given as arguments to the `parseShort(const std::string, int)` method.

Parameters:

s - `String` (p.3665) to convert to a short

Returns:

the converted short value

Exceptions:

NumberFormatException if the string is not a short.

6.733.2.16 `static short decaf::lang::Short::parseShort (const std::string & s, int radix) throw (exceptions::NumberFormatException) [static]`

Parses the string argument as a signed short in the radix specified by the second argument. The characters in the string must all be digits, of the specified radix (as determined by whether **Character.digit(char, int)** (p. 1103) returns a nonnegative value) except that the first character may be an ASCII minus sign '-' to indicate a negative value. The resulting byte value is returned.

An exception of type `NumberFormatException` is thrown if any of the following situations occurs:
 * The first argument is null or is a string of length zero. * The radix is either smaller than **Character.MIN_RADIX** (p. 1107) or larger than **Character.MAX_RADIX** (p. 1106). * Any character of the string is not a digit of the specified radix, except that the first character may be a minus sign '-' provided that the string is longer than length 1. * The value represented by the string is not a value of type short.

Parameters:

s - the **String** (p. 3665) containing the short representation to be parsed
radix - the radix to be used while parsing *s*

Returns:

the short represented by the string argument in the specified radix.

Exceptions:

NumberFormatException - If **String** (p. 3665) does not contain a parsable short.

6.733.2.17 `static short decaf::lang::Short::reverseBytes (short value) [static]`

Returns the value obtained by reversing the order of the bytes in the two's complement representation of the specified short value.

Parameters:

value - the short whose bytes we are to reverse

Returns:

the reversed short.

6.733.2.18 `virtual short decaf::lang::Short::shortValue () const [inline, virtual]`

Answers the short value which the receiver represents.

Returns:

int the value of the receiver.

Reimplemented from **decaf::lang::Number** (p. 2837).

6.733.2.19 `static std::string decaf::lang::Short::toString (short value) [static]`

Returns:

a string representing the primitive value as Base 10

6.733.2.20 `std::string decaf::lang::Short::toString () const`**Returns:**

this **Short** (p. 3440) Object as a **String** (p. 3665) Representation

6.733.2.21 `static Short decaf::lang::Short::valueOf (const std::string & value, int radix) throw (exceptions::NumberFormatException) [static]`

Returns a **Short** (p. 3440) object holding the value extracted from the specified `std::string` when parsed with the radix given by the second argument. The first argument is interpreted as representing a signed short in the radix specified by the second argument, exactly as if the argument were given to the `parseShort(std::string, int)` method. The result is a **Short** (p. 3440) object that represents the short value specified by the string.

Parameters:

value - `std::string` to parse as base (radix)

radix - base of the string to parse.

Returns:

new **Short** (p. 3440) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a valid short.

6.733.2.22 `static Short decaf::lang::Short::valueOf (const std::string & value) throw (exceptions::NumberFormatException) [static]`

Returns a **Short** (p. 3440) object holding the value given by the specified `std::string`. The argument is interpreted as representing a signed decimal short, exactly as if the argument were given to the `parseShort(std::string)` method. The result is a **Short** (p. 3440) object that represents the short value specified by the string.

Parameters:

value - `std::string` to parse as base 10

Returns:

new **Short** (p. 3440) Object wrapping the primitive

Exceptions:

NumberFormatException if the string is not a decimal short.

6.733.2.23 `static Short decaf::lang::Short::valueOf (short value) [static]`

Returns a **Short** (p. 3440) instance representing the specified short value.

Parameters:

value - the short to wrap

Returns:

the new **Short** (p. 3440) object wrapping value.

6.733.3 Field Documentation

6.733.3.1 `const short decaf::lang::Short::MAX_VALUE = (short)0x7FFF`
[static]

Max Value for this Object's primitive type.

6.733.3.2 `const short decaf::lang::Short::MIN_VALUE = (short)0x8000` [static]

Max Value for this Object's primitive type.

6.733.3.3 `const int decaf::lang::Short::SIZE = 16` [static]

Size of this objects primitive type in bits.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Short.h`

6.734 decaf::internal::nio::ShortArrayBuffer Class Reference

#include <src/main/decaf/internal/nio/ShortArrayBuffer.h> Inheritance diagram for decaf::internal::nio::ShortArrayBuffer:

Public Member Functions

- **ShortArrayBuffer** (int size, bool readOnly=false) throw (decaf::lang::exceptions::IllegalArgumentException)

*Creates a **ShortArrayBuffer** (p. 3449) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

- **ShortArrayBuffer** (short *array, int size, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Creates a **ShortArrayBuffer** (p. 3449) object that wraps the given array.*

- **ShortArrayBuffer** (const decaf::lang::Pointer< ByteArrayAdapter > &array, int offset, int length, bool readOnly=false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset.

- **ShortArrayBuffer** (const ShortArrayBuffer &other)

*Create a **ShortArrayBuffer** (p. 3449) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.*

- virtual ~**ShortArrayBuffer** ()
- virtual short * **array** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the short array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

*the array that backs this **Buffer** (p. 928)*

Exceptions:

***ReadOnlyBufferException** (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.*

- virtual int **arrayOffset** () throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::nio::ReadOnlyBufferException)

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the hasArray method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.
UnsupportedOperationException if the underlying store has no array.

- virtual **ShortBuffer** * **asReadOnlyBuffer** () const

Creates a new, read-only short buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the duplicate method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only short buffer which the caller then owns.

- virtual **ShortBuffer** & **compact** () throw (decaf::nio::ReadOnlyBufferException)

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

*a reference to this **ShortBuffer** (p. 3459).*

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual **ShortBuffer** * **duplicate** ()

Creates a new short buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

*a new short **Buffer** (p. 928) which the caller owns.*

- virtual short **get** () throw (decaf::nio::BufferUnderflowException)

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the short at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

- virtual short **get** (int index) const throw (lang::exceptions::IndexOutOfBoundsException)

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the short is to be read.

Returns:

the short that is located at the given index.

Exceptions:

IndexOutOfBoundsException if *index* is not smaller than the buffer's limit, or the index is negative.

- virtual bool **hasArray** () const

Tells whether or not this buffer is backed by an accessible short array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

- virtual bool **isReadOnly** () const

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

- virtual ShortBuffer & **put** (short value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)

Writes the given shorts into this buffer at the current position, and then increments the position.

Parameters:

value The shorts value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual ShortBuffer & **put** (int index, short value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException)

Writes the given shorts into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The shorts to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if *index* greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

- virtual ShortBuffer * **slice** () const

Creates a new **ShortBuffer** (p. 3459) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **ShortBuffer** (p. 3459) which the caller owns.

Protected Member Functions

- virtual void **setReadOnly** (bool value)

Sets this **ShortArrayBuffer** (p. 3449) as Read-Only.

6.734.1 Constructor & Destructor Documentation

6.734.1.1 `decaf::internal::nio::ShortArrayBuffer::ShortArrayBuffer (int size, bool readOnly = false) throw (decaf::lang::exceptions::IllegalArgumentException)`

Creates a **ShortArrayBuffer** (p. 3449) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

size The size of the array, this is the limit we read and write to.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

IllegalArgumentException if the capacity value is negative.

6.734.1.2 `decaf::internal::nio::ShortArrayBuffer::ShortArrayBuffer (short * array, int size, int offset, int length, bool readOnly = false) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)`

Creates a **ShortArrayBuffer** (p. 3449) object that wraps the given array. If the own flag is set then it will delete this array when this object is deleted.

Parameters:

array The actual array to wrap.

size The size of the given array.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if buffer is NULL

IndexOutOfBoundsException if offset is greater than array capacity.

6.734.1.3 decaf::internal::nio::ShortArrayBuffer::ShortArrayBuffer
 (const decaf::lang::Pointer< ByteArrayAdapter > &
array, int *offset*, int *length*, bool *readOnly* = false)
 throw (decaf::lang::exceptions::NullPointerException,
 decaf::lang::exceptions::IndexOutOfBoundsException)

Creates a byte buffer that wraps the passed ByteArrayAdapter and start at the given offset. The capacity and limit of the new **ShortArrayBuffer** (p. 3449) will be that of the remaining capacity of the passed buffer.

Parameters:

array The ByteArrayAdapter to wrap.

offset The position that is this buffers start position.

length The limit of how many bytes into the array this Buffer can write.

readOnly Boolean indicating if this buffer should be read-only, default as false.

Exceptions:

NullPointerException if array is NULL

IndexOutOfBoundsException if offset + length is greater than array size.

6.734.1.4 decaf::internal::nio::ShortArrayBuffer::ShortArrayBuffer (const
 ShortArrayBuffer & *other*)

Create a **ShortArrayBuffer** (p. 3449) that mirrors this one, meaning it shares a reference to this buffers ByteArrayAdapter and when changes are made to that data it is reflected in both.

Parameters:

other The **ShortArrayBuffer** (p. 3449) this one is to mirror.

6.734.1.5 virtual decaf::internal::nio::ShortArrayBuffer::~~ShortArrayBuffer ()
 [virtual]

6.734.2 Member Function Documentation

6.734.2.1 virtual short* decaf::internal::nio::ShortArrayBuffer::array ()
 throw (decaf::lang::exceptions::UnsupportedOperationException,
 decaf::nio::ReadOnlyBufferException) [virtual]

Returns the short array that backs this buffer (optional operation).

Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928)

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::ShortBuffer** (p. 3462).

6.734.2.2 `virtual int decaf::internal::nio::ShortArrayBuffer::arrayOffset ()
throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::nio::ReadOnlyBufferException) [virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implements **decaf::nio::ShortBuffer** (p. 3462).

6.734.2.3 `virtual ShortBuffer* de-
caf::internal::nio::ShortArrayBuffer::asReadOnlyBuffer ()
const [virtual]`

Creates a new, read-only short buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only short buffer which the caller then owns.

Implements **decaf::nio::ShortBuffer** (p. 3462).

**6.734.2.4 virtual ShortBuffer& decaf::internal::nio::ShortArrayBuffer::compact ()
throw (decaf::nio::ReadOnlyBufferException) [virtual]**

Compacts this buffer.

The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n+1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **ShortBuffer** (p. 3459).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ShortBuffer** (p. 3463).

**6.734.2.5 virtual ShortBuffer* decaf::internal::nio::ShortArrayBuffer::duplicate ()
[virtual]**

Creates a new short buffer that shares this buffer's content.

The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new short **Buffer** (p. 928) which the caller owns.

Implements **decaf::nio::ShortBuffer** (p. 3463).

**6.734.2.6 virtual short decaf::internal::nio::ShortArrayBuffer::get (int *index*) const
throw (lang::exceptions::IndexOutOfBoundsException) [virtual]**

Absolute get method.

Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the short is to be read.

Returns:

the short that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or the index is negative.

Implements **decaf::nio::ShortBuffer** (p. 3464).

6.734.2.7 `virtual short decaf::internal::nio::ShortArrayBuffer::get () throw (decaf::nio::BufferUnderflowException) [virtual]`

Relative get method.

Reads the value at this buffer's current position, and then increments the position.

Returns:

the short at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implements **decaf::nio::ShortBuffer** (p. 3465).

6.734.2.8 `virtual bool decaf::internal::nio::ShortArrayBuffer::hasArray () const [inline, virtual]`

Tells whether or not this buffer is backed by an accessible short array.

If this method returns true then the array and arrayOffset methods may safely be invoked. Sub-classes should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implements **decaf::nio::ShortBuffer** (p. 3465).

6.734.2.9 `virtual bool decaf::internal::nio::ShortArrayBuffer::isReadOnly () const [inline, virtual]`

Tells whether or not this buffer is read-only.

Returns:

true if, and only if, this buffer is read-only.

Implements **decaf::nio::Buffer** (p. 931).

6.734.2.10 `virtual ShortBuffer& decaf::internal::nio::ShortArrayBuffer::put (int index, short value) throw (lang::exceptions::IndexOutOfBoundsException, decaf::nio::ReadOnlyBufferException) [virtual]`

Writes the given shorts into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The shorts to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ShortBuffer** (p. 3465).

6.734.2.11 `virtual ShortBuffer& decaf::internal::nio::ShortArrayBuffer::put (short value) throw (decaf::nio::BufferOverflowException, decaf::nio::ReadOnlyBufferException)` [virtual]

Writes the given shorts into this buffer at the current position, and then increments the position.

Parameters:

value The shorts value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implements **decaf::nio::ShortBuffer** (p. 3466).

6.734.2.12 `virtual void decaf::internal::nio::ShortArrayBuffer::setReadOnly (bool value)` [inline, protected, virtual]

Sets this **ShortArrayBuffer** (p. 3449) as Read-Only.

Parameters:

value Boolean value, true if this buffer is to be read-only, false otherwise.

6.734.2.13 `virtual ShortBuffer* decaf::internal::nio::ShortArrayBuffer::slice () const` [virtual]

Creates a new **ShortBuffer** (p. 3459) whose content is a shared subsequence of this buffer's content.

The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **ShortBuffer** (p. 3459) which the caller owns.

Implements **decaf::nio::ShortBuffer** (p. 3468).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/nio/ShortArrayBuffer.h`

6.735 decaf::nio::ShortBuffer Class Reference

This class defines four categories of operations upon short buffers:.

#include <src/main/decaf/nio/ShortBuffer.h> Inheritance diagram for decaf::nio::ShortBuffer:

Public Member Functions

- virtual **~ShortBuffer** ()
- virtual std::string **toString** () const
- virtual short * **array** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the short array that backs this buffer (optional operation).
- virtual int **arrayOffset** ()=0 throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException)
Returns the offset within this buffer's backing array of the first element of the buffer (optional operation).
- virtual **ShortBuffer** * **asReadOnlyBuffer** () const =0
Creates a new, read-only short buffer that shares this buffer's content.
- virtual **ShortBuffer** & **compact** ()=0 throw (ReadOnlyBufferException)
Compacts this buffer.
- virtual **ShortBuffer** * **duplicate** ()=0
Creates a new short buffer that shares this buffer's content.
- virtual short **get** ()=0 throw (BufferUnderflowException)
Relative get method.
- virtual short **get** (int index) const =0 throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Absolute get method.
- **ShortBuffer** & **get** (std::vector< short > buffer) throw (BufferUnderflowException)
Relative bulk get method.
- **ShortBuffer** & **get** (short *buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)
Relative bulk get method.
- virtual bool **hasArray** () const =0
Tells whether or not this buffer is backed by an accessible short array.
- **ShortBuffer** & **put** (**ShortBuffer** &src) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the shorts remaining in the given source buffer into this buffer.

- **ShortBuffer** & **put** (const short *buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

This method transfers shorts into this buffer from the given source array.

- **ShortBuffer** & **put** (std::vector< short > &buffer) throw (BufferOverflowException, ReadOnlyBufferException)

This method transfers the entire content of the given source shorts array into this buffer.

- virtual **ShortBuffer** & **put** (short value)=0 throw (BufferOverflowException, ReadOnlyBufferException)

Writes the given shorts into this buffer at the current position, and then increments the position.

- virtual **ShortBuffer** & **put** (int index, short value)=0 throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException)

Writes the given shorts into this buffer at the given index.

- virtual **ShortBuffer** * **slice** () const =0

*Creates a new **ShortBuffer** (p. 3459) whose content is a shared subsequence of this buffer's content.*

- virtual int **compareTo** (const **ShortBuffer** &value) const

- virtual bool **equals** (const **ShortBuffer** &value) const

- virtual bool **operator==** (const **ShortBuffer** &value) const

- virtual bool **operator<** (const **ShortBuffer** &value) const

Static Public Member Functions

- static **ShortBuffer** * **allocate** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)

Allocates a new Double buffer.

- static **ShortBuffer** * **wrap** (short *array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

*Wraps the passed buffer with a new **ShortBuffer** (p. 3459).*

- static **ShortBuffer** * **wrap** (std::vector< short > &buffer)

*Wraps the passed STL short Vector in a **ShortBuffer** (p. 3459).*

Protected Member Functions

- **ShortBuffer** (int capacity) throw (decaf::lang::exceptions::IllegalArgumentException)
*Creates a **ShortBuffer** (p. 3459) object that has its backing array allocated internally and is then owned and deleted when this object is deleted.*

6.735.1 Detailed Description

This class defines four categories of operations upon short buffers:

- o Absolute and relative get and put methods that read and write single shorts;
- o Relative bulk get methods that transfer contiguous sequences of shorts from this buffer into an array; and
- o Relative bulk put methods that transfer contiguous sequences of shorts from a short array or some other short buffer into this buffer

 o Methods for compacting, duplicating, and slicing a short buffer.

Double buffers can be created either by allocation, which allocates space for the buffer's content, by wrapping an existing short array into a buffer, or by creating a view of an existing byte buffer

Methods in this class that do not otherwise have a value to return are specified to return the buffer upon which they are invoked. This allows method invocations to be chained.

6.735.2 Constructor & Destructor Documentation

- 6.735.2.1** decaf::nio::ShortBuffer::ShortBuffer (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [protected]

Creates a **ShortBuffer** (p. 3459) object that has its backing array allocated internally and is then owned and deleted when this object is deleted. The array is initially created with all elements initialized to zero.

Parameters:

capacity The size and limit of the **Buffer** (p. 928) in doubles

Exceptions:

IllegalArgumentException if capacity is negative.

- 6.735.2.2** virtual decaf::nio::ShortBuffer::~~ShortBuffer () [inline, virtual]

6.735.3 Member Function Documentation

- 6.735.3.1** static ShortBuffer* decaf::nio::ShortBuffer::allocate (int *capacity*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Allocates a new Double buffer. The new buffer's position will be zero, its limit will be its capacity, and its mark will be undefined. It will have a backing array, and its array offset will be zero.

Parameters:

capacity The size of the Double buffer in shorts.

Returns:

the **ShortBuffer** (p. 3459) that was allocated, caller owns.

6.735.3.2 `virtual short* decaf::nio::ShortBuffer::array () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the short array that backs this buffer (optional operation). Modifications to this buffer's content will cause the returned array's content to be modified, and vice versa.

Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

the array that backs this **Buffer** (p. 928)

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::ShortArrayBuffer` (p. 3453).

6.735.3.3 `virtual int decaf::nio::ShortBuffer::arrayOffset () throw (decaf::lang::exceptions::UnsupportedOperationException, ReadOnlyBufferException) [pure virtual]`

Returns the offset within this buffer's backing array of the first element of the buffer (optional operation). Invoke the `hasArray` method before invoking this method in order to ensure that this buffer has an accessible backing array.

Returns:

The offset into the backing array where index zero starts.

Exceptions:

ReadOnlyBufferException (p. 3169) if this **Buffer** (p. 928) is read only.

UnsupportedOperationException if the underlying store has no array.

Implemented in `decaf::internal::nio::ShortArrayBuffer` (p. 3454).

6.735.3.4 `virtual ShortBuffer* decaf::nio::ShortBuffer::asReadOnlyBuffer () const [pure virtual]`

Creates a new, read-only short buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer; the new buffer itself, however, will be read-only and will not allow the shared content to be modified. The two buffers' position, limit, and mark values will be independent.

If this buffer is itself read-only then this method behaves in exactly the same way as the `duplicate` method.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer.

Returns:

The new, read-only short buffer which the caller then owns.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3454).

6.735.3.5 virtual ShortBuffer& decaf::nio::ShortBuffer::compact () throw (ReadOnlyBufferException) [pure virtual]

Compacts this buffer. The bytes between the buffer's current position and its limit, if any, are copied to the beginning of the buffer. That is, the byte at index $p = \text{position}()$ (p. 932) is copied to index zero, the byte at index $p + 1$ is copied to index one, and so forth until the byte at index $\text{limit}()$ (p. 932) - 1 is copied to index $n = \text{limit}()$ (p. 932) - 1 - p . The buffer's position is then set to $n + 1$ and its limit is set to its capacity. The mark, if defined, is discarded.

The buffer's position is set to the number of bytes copied, rather than to zero, so that an invocation of this method can be followed immediately by an invocation of another relative put method.

Returns:

a reference to this **ShortBuffer** (p. 3459).

Exceptions:

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3455).

6.735.3.6 virtual int decaf::nio::ShortBuffer::compareTo (const ShortBuffer & value) const [virtual]

6.735.3.7 virtual ShortBuffer* decaf::nio::ShortBuffer::duplicate () [pure virtual]

Creates a new short buffer that shares this buffer's content. The content of the new buffer will be that of this buffer. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's capacity, limit, position, and mark values will be identical to those of this buffer. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

a new short **Buffer** (p. 928) which the caller owns.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3455).

6.735.3.8 virtual bool decaf::nio::ShortBuffer::equals (const ShortBuffer & value) const [virtual]

6.735.3.9 ShortBuffer& decaf::nio::ShortBuffer::get (short * buffer, int size, int offset, int length) throw (BufferUnderflowException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

Relative bulk get method. This method transfers shorts from this buffer into the given destination array. If there are fewer shorts remaining in the buffer than are required to satisfy the request, that is, if $\text{length} > \text{remaining}()$ (p. 933), then no bytes are transferred and a **BufferUnderflowException** (p. 957) is thrown.

Otherwise, this method copies length shorts from this buffer into the given array, starting at the current position of this buffer and at the given offset in the array. The position of this buffer is then incremented by length.

Parameters:

buffer The pointer to an allocated buffer to fill.
size The size of the buffer provided.
offset The position in the buffer to start filling.
length The amount of data to put in the passed buffer.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length shorts remaining in this buffer
NullPointerException if the passed buffer is null.
IndexOutOfBoundsException if the preconditions of size, offset, or length are not met.

6.735.3.10 ShortBuffer& decaf::nio::ShortBuffer::get (std::vector< short > *buffer*) throw (BufferUnderflowException)

Relative bulk get method. This method transfers values from this buffer into the given destination vector. An invocation of this method of the form `src.get(a)` behaves in exactly the same way as the invocation. The vector must be sized to the amount of data that is to be read, that is to say, the caller should call `buffer.resize(N)` before calling this get method.

Returns:

a reference to this **Buffer** (p. 928).

Exceptions:

BufferUnderflowException (p. 957) if there are fewer than length shorts remaining in this buffer.

6.735.3.11 virtual short decaf::nio::ShortBuffer::get (int *index*) const throw (decaf::lang::exceptions::IndexOutOfBoundsException) [pure virtual]

Absolute get method. Reads the value at the given index.

Parameters:

index The index in the **Buffer** (p. 928) where the short is to be read.

Returns:

the short that is located at the given index.

Exceptions:

IndexOutOfBoundsException if index is not smaller than the buffer's limit, or the index is negative.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3455).

6.735.3.12 virtual short decaf::nio::ShortBuffer::get () throw (BufferUnderflowException) [pure virtual]

Relative get method. Reads the value at this buffer's current position, and then increments the position.

Returns:

the short at the current position.

Exceptions:

BufferUnderflowException (p. 957) if there no more data to return.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3456).

6.735.3.13 virtual bool decaf::nio::ShortBuffer::hasArray () const [pure virtual]

Tells whether or not this buffer is backed by an accessible short array. If this method returns true then the array and arrayOffset methods may safely be invoked. Subclasses should override this method if they do not have a backing array as this class always returns true.

Returns:

true if, and only if, this buffer is backed by an array and is not read-only.

Implemented in **decaf::internal::nio::ShortArrayBuffer** (p. 3456).

6.735.3.14 virtual bool decaf::nio::ShortBuffer::operator< (const ShortBuffer & value) const [virtual]

6.735.3.15 virtual bool decaf::nio::ShortBuffer::operator== (const ShortBuffer & value) const [virtual]

6.735.3.16 virtual ShortBuffer& decaf::nio::ShortBuffer::put (int index, short value) throw (decaf::lang::exceptions::IndexOutOfBoundsException, ReadOnlyBufferException) [pure virtual]

Writes the given shorts into this buffer at the given index.

Parameters:

index The position in the **Buffer** (p. 928) to write the data.

value The shorts to write.

Returns:

a reference to this buffer.

Exceptions:

IndexOutOfBoundsException if index greater than the buffer's limit minus the size of the type being written.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ShortArrayBuffer` (p. 3456).

6.735.3.17 `virtual ShortBuffer& decaf::nio::ShortBuffer::put (short value) throw (BufferOverflowException, ReadOnlyBufferException)` [pure virtual]

Writes the given shorts into this buffer at the current position, and then increments the position.

Parameters:

value The shorts value to be written.

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if this buffer's current position is not smaller than its limit.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

Implemented in `decaf::internal::nio::ShortArrayBuffer` (p. 3457).

6.735.3.18 `ShortBuffer& decaf::nio::ShortBuffer::put (std::vector< short > & buffer) throw (BufferOverflowException, ReadOnlyBufferException)`

This method transfers the entire content of the given source shorts array into this buffer. This is the same as calling `put(&buffer[0], 0, buffer.size()`.

Parameters:

buffer The buffer whose contents are copied to this **ShortBuffer** (p. 3459).

Returns:

a reference to this buffer.

Exceptions:

BufferOverflowException (p. 954) if there is insufficient space in this buffer.

ReadOnlyBufferException (p. 3169) if this buffer is read-only.

6.735.3.19 `ShortBuffer& decaf::nio::ShortBuffer::put (const short * buffer, int size, int offset, int length) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)`

This method transfers shorts into this buffer from the given source array. If there are more shorts to be copied from the array than remain in this buffer, that is, if `length > remaining()` (p. 933), then no shorts are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `length` bytes from the given array into this buffer, starting at the given offset in the array and at the current position of this buffer. The position of this buffer is then incremented by `length`.

Parameters:

- buffer* The array from which shorts are to be read.
- size* The size of the buffer passed.
- offset* The offset within the array of the first char to be read.
- length* The number of shorts to be read from the given array.

Returns:

a reference to this buffer.

Exceptions:

- BufferOverflowException** (p. 954) if there is insufficient space in this buffer
- ReadOnlyBufferException** (p. 3169) if this buffer is read-only
- NullPointerException** if the passed buffer is null.
- IndexOutOfBoundsException** if the preconditions of size, offset, or length are not met.

6.735.3.20 ShortBuffer& decaf::nio::ShortBuffer::put (ShortBuffer & *src*) throw (BufferOverflowException, ReadOnlyBufferException, decaf::lang::exceptions::IllegalArgumentException)

This method transfers the shorts remaining in the given source buffer into this buffer. If there are more shorts remaining in the source buffer than in this buffer, that is, if `src.remaining() > remaining()` (p. 933), then no shorts are transferred and a **BufferOverflowException** (p. 954) is thrown.

Otherwise, this method copies `n = src.remaining()` shorts from the given buffer into this buffer, starting at each buffer's current position. The positions of both buffers are then incremented by `n`.

Parameters:

- src* The buffer to take shorts from an place in this one.

Returns:

a reference to this buffer.

Exceptions:

- BufferOverflowException** (p. 954) if there is insufficient space in this buffer for the remaining shorts in the source buffer.
- IllegalArgumentException** if the source buffer is this buffer.
- ReadOnlyBufferException** (p. 3169) if this buffer is read-only.

6.735.3.21 `virtual ShortBuffer* decaf::nio::ShortBuffer::slice () const` [pure virtual]

Creates a new **ShortBuffer** (p.3459) whose content is a shared subsequence of this buffer's content. The content of the new buffer will start at this buffer's current position. Changes to this buffer's content will be visible in the new buffer, and vice versa; the two buffers' position, limit, and mark values will be independent.

The new buffer's position will be zero, its capacity and its limit will be the number of bytes remaining in this buffer, and its mark will be undefined. The new buffer will be read-only if, and only if, this buffer is read-only.

Returns:

the newly create **ShortBuffer** (p.3459) which the caller owns.

Implemented in `decaf::internal::nio::ShortArrayBuffer` (p.3457).

6.735.3.22 `virtual std::string decaf::nio::ShortBuffer::toString () const` [virtual]

Returns:

a `std::string` describing this object

6.735.3.23 `static ShortBuffer* decaf::nio::ShortBuffer::wrap (std::vector< short > & buffer)` [static]

Wraps the passed STL short Vector in a **ShortBuffer** (p.3459). The new buffer will be backed by the given short array; modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity and limit will be `buffer.size()`, its position will be zero, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

buffer The vector that will back the new buffer, the vector must have been sized to the desired size already by calling `vector.resize(N)`.

Returns:

a new **ShortBuffer** (p.3459) that is backed by *buffer*, caller owns.

6.735.3.24 `static ShortBuffer* decaf::nio::ShortBuffer::wrap (short * array, int size, int offset, int length) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [static]

Wraps the passed buffer with a new **ShortBuffer** (p.3459). The new buffer will be backed by the given short array; that is, modifications to the buffer will cause the array to be modified and vice versa. The new buffer's capacity will be `array.length`, its position will be `offset`, its limit will be `offset + length`, and its mark will be undefined. Its backing array will be the given array, and its array offset will be zero.

Parameters:

- array* The array that will back the new buffer.
- size* The size of the passed in array.
- offset* The offset of the subarray to be used.
- length* The length of the subarray to be used.

Returns:

- a new **ShortBuffer** (p.3459) that is backed by buffer, caller owns.

Exceptions:

- NullPointerException* if the array pointer is NULL.
- IndexOutOfBoundsException* if the preconditions of size, offset, or length are not met.

The documentation for this class was generated from the following file:

- src/main/decaf/nio/**ShortBuffer.h**

6.736 activemq::commands::ShutdownInfo Class Reference

#include <src/main/activemq/commands/ShutdownInfo.h> Inheritance diagram for activemq::commands::ShutdownInfo:

Public Member Functions

- **ShutdownInfo** ()
- virtual **~ShutdownInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **ShutdownInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual bool **isShutdownInfo** () const
- virtual **Pointer< Command > visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_SHUTDOWNINFO** = 11

6.736.1 Constructor & Destructor Documentation

6.736.1.1 `activemq::commands::ShutdownInfo::ShutdownInfo ()`

6.736.1.2 `virtual activemq::commands::ShutdownInfo::~~ShutdownInfo ()`
[virtual]

6.736.2 Member Function Documentation

6.736.2.1 `virtual ShutdownInfo* activemq::commands::ShutdownInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.736.2.2 `virtual void activemq::commands::ShutdownInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.736.2.3 `virtual bool activemq::commands::ShutdownInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.736.2.4 `virtual unsigned char activemq::commands::ShutdownInfo::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new `DataStructure` (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

6.736.2.5 `virtual bool activemq::commands::ShutdownInfo::isShutdownInfo () const [inline, virtual]`

Returns:

an answer of true to the **isShutdownInfo()** (p. 3472) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 762).

6.736.2.6 `virtual std::string activemq::commands::ShutdownInfo::toString () const [virtual]`

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.736.2.7 `virtual Pointer<Command> activemq::commands::ShutdownInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException) [virtual]`

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p. 1198).

6.736.3 Field Documentation

6.736.3.1 `const unsigned char activemq::commands::ShutdownInfo::ID__ - SHUTDOWNINFO = 11 [static]`

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/ShutdownInfo.h`

6.737 activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3473).

#include <src/main/activemq/wireformat/openwire/marshal/v6/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.737.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3473).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.737.2 Constructor & Destructor Documentation

6.737.2.1 `activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.737.2.2 `virtual activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.737.3 Member Function Documentation

6.737.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.737.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.737.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 794).

6.737.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 795).

6.737.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 796).

6.737.3.6 virtual void activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.737.3.7 virtual void activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**ShutdownInfoMarshaller.h**

6.738 activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3477).

#include <src/main/activemq/wireformat/openwire/marshal/v2/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.738.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3477).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.738.2 Constructor & Destructor Documentation

6.738.2.1 `activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.738.2.2 `virtual activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.738.3 Member Function Documentation

6.738.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.738.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.738.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 801).

6.738.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 802).

6.738.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 803).

6.738.3.6 virtual void activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.738.3.7 virtual void activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**ShutdownInfoMarshaller.h**

6.739 activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3481).

#include <src/main/activemq/wireformat/openwire/marshal/v1/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.739.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3481).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.739.2 Constructor & Destructor Documentation

6.739.2.1 `activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.739.2.2 `virtual activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.739.3 Member Function Documentation

6.739.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.739.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.739.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 780).

6.739.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 781).

6.739.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 782).

6.739.3.6 virtual void activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.739.3.7 virtual void activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**ShutdownInfoMarshaller.h**

6.740 activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3485).

#include <src/main/activemq/wireformat/openwire/marshal/v5/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.740.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3485).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.740.2 Constructor & Destructor Documentation

6.740.2.1 `activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.740.2.2 `virtual activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.740.3 Member Function Documentation

6.740.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.740.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.740.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.740.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.740.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.740.3.6 virtual void activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.740.3.7 virtual void activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**ShutdownInfoMarshaller.h**

6.741 activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3489).

#include <src/main/activemq/wireformat/openwire/marshal/v3/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.741.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3489).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.741.2 Constructor & Destructor Documentation

6.741.2.1 `activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.741.2.2 `virtual activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.741.3 Member Function Documentation

6.741.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.741.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.741.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.741.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.741.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.741.3.6 virtual void activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.741.3.7 virtual void activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**ShutdownInfoMarshaller.h**

6.742 activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3493).

#include <src/main/activemq/wireformat/openwire/marshal/v4/ShutdownInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller:

Public Member Functions

- **ShutdownInfoMarshaller** ()
- virtual **~ShutdownInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.742.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3493).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.742.2 Constructor & Destructor Documentation

6.742.2.1 `activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::ShutdownInfoMarshaller()` [inline]

6.742.2.2 `virtual activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::~~ShutdownInfoMarshaller()` [inline, virtual]

6.742.3 Member Function Documentation

6.742.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.742.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.742.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.742.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.742.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.742.3.6 virtual void activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.742.3.7 virtual void activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**ShutdownInfoMarshaller.h**

6.743 decaf::security::SignatureException Class Reference

#include <src/main/decaf/security/SignatureException.h> Inheritance diagram for decaf::security::SignatureException:

Public Member Functions

- **SignatureException** () throw ()
Default Constructor.
- **SignatureException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **SignatureException** (const **SignatureException** &ex) throw ()
Copy Constructor.
- **SignatureException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **SignatureException** (const std::exception *cause) throw ()
Constructor.
- **SignatureException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **SignatureException** * clone () const
Clones this exception.
- virtual ~**SignatureException** () throw ()

6.743.1 Constructor & Destructor Documentation

6.743.1.1 decaf::security::SignatureException::SignatureException () throw () [inline]

Default Constructor.

6.743.1.2 decaf::security::SignatureException::SignatureException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.743.1.3 decaf::security::SignatureException::SignatureException (const SignatureException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.743.1.4 decaf::security::SignatureException::SignatureException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.743.1.5 decaf::security::SignatureException::SignatureException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.743.1.6 decaf::security::SignatureException::SignatureException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file name where exception occurs

lineNumber line number where the exception occurred.

msg message to report

... list of primitives that are formatted into the message

6.743.1.7 virtual decaf::security::SignatureException::~SignatureException ()
throw () [inline, virtual]

6.743.2 Member Function Documentation

6.743.2.1 virtual SignatureException* decaf::security::SignatureException::clone ()
const [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A deep copy of this exception.

Reimplemented from **decaf::security::GeneralSecurityException** (p. 1973).

The documentation for this class was generated from the following file:

- src/main/decaf/security/**SignatureException.h**

6.744 decaf::util::logging::SimpleFormatter Class Reference

Print a brief summary of the **LogRecord** (p. 2413) in a human readable format.

#include <src/main/decaf/util/logging/SimpleFormatter.h> Inheritance diagram for decaf::util::logging::SimpleFormatter:

Public Member Functions

- **SimpleFormatter** ()
- virtual **~SimpleFormatter** ()
- virtual std::string **format** (const **LogRecord** &record) const

Format the given log record and return the formatted string.

6.744.1 Detailed Description

Print a brief summary of the **LogRecord** (p. 2413) in a human readable format. The summary will typically be 1 or 2 lines.

Since:

1.0

6.744.2 Constructor & Destructor Documentation

6.744.2.1 decaf::util::logging::SimpleFormatter::SimpleFormatter ()

6.744.2.2 virtual decaf::util::logging::SimpleFormatter::~~SimpleFormatter ()
[virtual]

6.744.3 Member Function Documentation

6.744.3.1 virtual std::string decaf::util::logging::SimpleFormatter::format (const **LogRecord & *record*) const** [virtual]

Format the given log record and return the formatted string.

Parameters:

record The Log Record to Format.

Implements **decaf::util::logging::Formatter** (p. 1964).

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**SimpleFormatter.h**

6.745 decaf::util::logging::SimpleLogger Class Reference

```
#include <src/main/decaf/util/logging/SimpleLogger.h>
```

Public Member Functions

- **SimpleLogger** (const std::string &name)
Constructor.
- virtual **~SimpleLogger** ()
Destructor.
- virtual void **mark** (const std::string &message)
*Log a Mark Block **Level** (p. 2332) Log.*
- virtual void **debug** (const std::string &file, const int line, const std::string &message)
*Log a Debug **Level** (p. 2332) Log.*
- virtual void **info** (const std::string &file, const int line, const std::string &message)
*Log a Informational **Level** (p. 2332) Log.*
- virtual void **warn** (const std::string &file, const int line, const std::string &message)
*Log a Warning **Level** (p. 2332) Log.*
- virtual void **error** (const std::string &file, const int line, const std::string &message)
*Log a Error **Level** (p. 2332) Log.*
- virtual void **fatal** (const std::string &file, const int line, const std::string &message)
*Log a Fatal **Level** (p. 2332) Log.*
- virtual void **log** (const std::string &message)
No-frills log.

6.745.1 Constructor & Destructor Documentation

6.745.1.1 decaf::util::logging::SimpleLogger::SimpleLogger (const std::string &name)

Constructor.

6.745.1.2 virtual decaf::util::logging::SimpleLogger::~~SimpleLogger () [virtual]

Destructor.

6.745.2 Member Function Documentation

6.745.2.1 `virtual void decaf::util::logging::SimpleLogger::debug (const std::string & file, const int line, const std::string & message) [virtual]`

Log a Debug **Level** (p. 2332) Log.

6.745.2.2 `virtual void decaf::util::logging::SimpleLogger::error (const std::string & file, const int line, const std::string & message) [virtual]`

Log a Error **Level** (p. 2332) Log.

6.745.2.3 `virtual void decaf::util::logging::SimpleLogger::fatal (const std::string & file, const int line, const std::string & message) [virtual]`

Log a Fatal **Level** (p. 2332) Log.

6.745.2.4 `virtual void decaf::util::logging::SimpleLogger::info (const std::string & file, const int line, const std::string & message) [virtual]`

Log a Informational **Level** (p. 2332) Log.

6.745.2.5 `virtual void decaf::util::logging::SimpleLogger::log (const std::string & message) [virtual]`

No-frills log.

6.745.2.6 `virtual void decaf::util::logging::SimpleLogger::mark (const std::string & message) [virtual]`

Log a Mark Block **Level** (p. 2332) Log.

6.745.2.7 `virtual void decaf::util::logging::SimpleLogger::warn (const std::string & file, const int line, const std::string & message) [virtual]`

Log a Warning **Level** (p. 2332) Log.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/SimpleLogger.h`

6.746 decaf::net::Socket Class Reference

#include <src/main/decaf/net/Socket.h> Inheritance diagram for decaf::net::Socket:

Public Member Functions

- **Socket** ()
*Creates an unconnected **Socket** (p. 3503) using the set **SocketImplFactory** (p. 3537) or if none is set than the default **SocketImpl** type is created.*
- **Socket** (**SocketImpl** *impl)
*Creates a **Socket** (p. 3503) wrapping the provided **SocketImpl** (p. 3529) instance, this **Socket** (p. 3503) is considered unconnected.*
- **Socket** (const **InetAddress** *address, int port)
*Creates a new **Socket** (p. 3503) instance and connects it to the given address and port.*
- **Socket** (const **InetAddress** *address, int port, const **InetAddress** *localAddress, int localPort)
*Creates a new **Socket** (p. 3503) instance and connects it to the given address and port.*
- **Socket** (const std::string &host, int port)
*Creates a new **Socket** (p. 3503) instance and connects it to the given host and port.*
- **Socket** (const std::string &host, int port, const **InetAddress** *localAddress, int localPort)
*Creates a new **Socket** (p. 3503) instance and connects it to the given host and port.*
- virtual ~**Socket** ()
- virtual void **bind** (const std::string &ipaddress, int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
*Binds this **Socket** (p. 3503) to the given local address and port.*
- virtual void **close** () throw (decaf::io::IOException)
*Closes the **Socket** (p. 3503).*
- virtual void **connect** (const std::string &host, int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
Connects to the specified destination.
- virtual void **connect** (const std::string &host, int port, int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)
Connects to the specified destination, with a specified timeout value.
- bool **isConnected** () const
Indicates whether or not this socket is connected to an end point.
- bool **isClosed** () const
- bool **isBound** () const

- **bool isInputShutdown () const**
- **bool isOutputShutdown () const**
- **virtual decaf::io::InputStream * getInputStream () throw (decaf::io::IOException)**
Gets the InputStream for this socket if its connected.
- **virtual decaf::io::OutputStream * getOutputStream () throw (decaf::io::IOException)**
Gets the OutputStream for this socket if it is connected.
- **int getPort () const**
*Gets the on the remote host this **Socket** (p. 3503) is connected to.*
- **int getLocalPort () const**
Gets the local port the socket is bound to.
- **std::string getInetAddress () const**
Returns the address to which the socket is connected.
- **std::string getLocalAddress () const**
Gets the local address to which the socket is bound.
- **virtual void shutdownInput () throw (decaf::io::IOException)**
Shuts down the InputStream for this socket essentially marking it as EOF.
- **virtual void shutdownOutput () throw (decaf::io::IOException)**
Shuts down the OutputStream for this socket, any data already written to the socket will be sent, any further calls to OutputStream::write will throw an IOException.
- **virtual int getSoLinger () const throw (SocketException)**
Gets the linger time for the socket, SO_LINGER.
- **virtual void setSoLinger (bool state, int timeout) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)**
Sets the linger time (SO_LINGER) using a specified time value, this limits of this value are platform specific.
- **virtual bool getKeepAlive () const throw (SocketException)**
Gets the keep alive flag for this socket, SO_KEEPALIVE.
- **virtual void setKeepAlive (bool keepAlive) throw (SocketException)**
Enables/disables the keep alive flag for this socket, SO_KEEPALIVE.
- **virtual int getReceiveBufferSize () const throw (SocketException)**
Gets the receive buffer size for this socket, SO_RCVBUF.
- **virtual void setReceiveBufferSize (int size) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)**
Sets the receive buffer size for this socket, SO_RCVBUF.
- **virtual bool getReuseAddress () const throw (SocketException)**

Gets the reuse address flag, SO_REUSEADDR.

- virtual void **setReuseAddress** (bool reuse) throw (SocketException)

Sets the reuse address flag, SO_REUSEADDR.

- virtual int **getSendBufferSize** () const throw (SocketException)

Gets the send buffer size for this socket, SO_SNDBUF, this value is used by the platform socket to buffer data written to the socket.

- virtual void **setSendBufferSize** (int size) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)

Gets the send buffer size for this socket, SO_SNDBUF, this value is used by the platform socket to buffer data written to the socket.

- virtual int **getSoTimeout** () const throw (SocketException)

Gets the timeout for socket operations, SO_TIMEOUT.

- virtual void **setSoTimeout** (int timeout) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)

Sets the timeout for socket operations, SO_TIMEOUT.

- virtual bool **getTcpNoDelay** () const throw (SocketException)

Gets the Status of the TCP_NODELAY setting for this socket.

- virtual void **setTcpNoDelay** (bool value) throw (SocketException)

*Sets the Status of the TCP_NODELAY param for this socket., this setting is used to disable or enable Nagle's algorithm on the **Socket** (p. 3503).*

- virtual int **getTrafficClass** () const throw (SocketException)

*Gets the Traffic Class setting for this **Socket** (p. 3503), sometimes referred to as Type of Service setting.*

- virtual void **setTrafficClass** (int value) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException)

*Gets the Traffic Class setting for this **Socket** (p. 3503), sometimes referred to as Type of Service setting.*

- virtual bool **getOOBInline** () const throw (SocketException)

Gets the value of the OOBINLINE for this socket.

- virtual void **setOOBInline** (bool value) throw (SocketException)

Sets the value of the OOBINLINE for this socket, by default this option is disabled.

- virtual void **sendUrgentData** (int data) throw (decaf::io::IOException)

*Sends on byte of urgent data to the **Socket** (p. 3503).*

- virtual std::string **toString** () const

Static Public Member Functions

- static void **setSocketImplFactory** (**SocketImplFactory** *factory) throw (decaf::io::IOException, decaf::net::SocketException)

*Sets the instance of a **SocketImplFactory** (p. 3537) that the **Socket** (p. 3503) class should use when new instances of this class are created.*

Protected Member Functions

- void **accepted** ()
- void **initSocketImpl** (const std::string &address, int port, const **InetAddress** *localAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)
- void **checkClosed** () const throw (decaf::io::IOException)
- void **ensureCreated** () const throw (decaf::io::IOException)

Protected Attributes

- **SocketImpl** * impl

Friends

- class **ServerSocket**

6.746.1 Detailed Description

Since:

1.0

6.746.2 Constructor & Destructor Documentation

6.746.2.1 decaf::net::Socket::Socket ()

Creates an unconnected **Socket** (p. 3503) using the set **SocketImplFactory** (p. 3537) or if non is set than the default **SocketImpl** type is created.

6.746.2.2 decaf::net::Socket::Socket (**SocketImpl** * impl)

Creates a **Socket** (p. 3503) wrapping the provided **SocketImpl** (p. 3529) instance, this **Socket** (p. 3503) is considered unconnected. The **Socket** (p. 3503) class takes ownership of this **SocketImpl** (p. 3529) pointer and will delete it when the **Socket** (p. 3503) class is destroyed.

Parameters:

impl The **SocketImpl** (p. 3529) instance to wrap.

Exceptions:

NullPointerException if the passed **SocketImpl** (p. 3529) is Null.

6.746.2.3 decaf::net::Socket::Socket (const InetAddress * *address*, int *port*)

Creates a new **Socket** (p. 3503) instance and connects it to the given address and port. If there is a **SocketImplFactory** (p. 3537) set then the SocketImpl is created using the factory otherwise the default **Socket** (p. 3503) implementation is used.

If the host parameter is empty then the loop back address is used.

Parameters:

address The address to connect to.

port The port number to connect to [0...65535]

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

NullPointerException if the **InetAddress** (p. 2016) instance is NULL.

IllegalArgumentException if the port is not in range [0...65535]

6.746.2.4 decaf::net::Socket::Socket (const InetAddress * *address*, int *port*, const InetAddress * *localAddress*, int *localPort*)

Creates a new **Socket** (p. 3503) instance and connects it to the given address and port. If there is a **SocketImplFactory** (p. 3537) set then the SocketImpl is created using the factory otherwise the default **Socket** (p. 3503) implementation is used. The **Socket** (p. 3503) will also bind to the local address and port specified.

Parameters:

address The address to connect to.

port The port number to connect to [0...65535]

localAddress The IP address on the local machine to bind to.

localPort The port on the local machine to bind to.

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

NullPointerException if the **InetAddress** (p. 2016) instance is NULL.

IllegalArgumentException if the port is not in range [0...65535]

6.746.2.5 decaf::net::Socket::Socket (const std::string & *host*, int *port*)

Creates a new **Socket** (p. 3503) instance and connects it to the given host and port. If there is a **SocketImplFactory** (p. 3537) set then the SocketImpl is created using the factory otherwise the default **Socket** (p. 3503) implementation is used.

If the host parameter is empty then the loop back address is used.

Parameters:

host The host name or IP address to connect to, empty string means loopback.

port The port number to connect to [0...65535]

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

IllegalArgumentException if the port if not in range [0...65535]

6.746.2.6 decaf::net::Socket::Socket (const std::string & *host*, int *port*, const InetAddress * *localAddress*, int *localPort*)

Creates a new **Socket** (p. 3503) instance and connects it to the given host and port. If there is a **SocketImplFactory** (p. 3537) set then the SocketImpl is created using the factory otherwise the default **Socket** (p. 3503) implementation is used.

If the host parameter is empty then the loop back address is used.

Parameters:

host The host name or IP address to connect to, empty string means loopback.

port The port number to connect to [0...65535]

localAddress The IP address on the local machine to bind to.

localPort The port on the local machine to bind to.

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

IllegalArgumentException if the port if not in range [0...65535]

6.746.2.7 virtual decaf::net::Socket::~~Socket () [virtual]

6.746.3 Member Function Documentation

6.746.3.1 void decaf::net::Socket::accepted () [protected]

6.746.3.2 virtual void decaf::net::Socket::bind (const std::string & *ipaddress*, int *port*) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Binds this **Socket** (p. 3503) to the given local address and port. If the **SocketAddress** (p. 3519) value is NULL then the **Socket** (p. 3503) will be bound to an available local address and port.

Parameters:

ipaddress The local address and port to bind the socket to.

port The port on the local machine to bind to.

Exceptions:

IOException if an error occurs during the bind operation.

IllegalArgumentException if the **Socket** (p. 3503) can't process the subclass of **SocketAddress** (p. 3519) that has been provided.

6.746.3.3 `void decaf::net::Socket::checkClosed () const throw (decaf::io::IOException)` [protected]

6.746.3.4 `virtual void decaf::net::Socket::close () throw (decaf::io::IOException)` [virtual]

Closes the **Socket** (p. 3503). Once closed a **Socket** (p. 3503) cannot be connected or otherwise operated upon, a new **Socket** (p. 3503) instance must be created.

Exceptions:

IOException if an I/O error occurs while closing the **Socket** (p. 3503).

Implements **decaf::io::Closeable** (p. 1149).

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2863).

6.746.3.5 `virtual void decaf::net::Socket::connect (const std::string & host, int port, int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)` [virtual]

Connects to the specified destination, with a specified timeout value. If a connection to the remote host is not established within the specified timeout interval than an **SocketTimeoutException** (p. 3542) is thrown. A timeout value of zero is treated as an infinite timeout.

Parameters:

host The host name or IP address of the remote host to connect to.

port The port on the remote host to connect to.

timeout The number of Milliseconds to wait before treating the connection as failed.

Exceptions:

IOException Thrown if a failure occurred in the connect.

SocketTimeoutException (p. 3542) if the timeout for connection is exceeded.

IllegalArgumentException if the timeout value is negative or the endpoint is invalid.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2863).

6.746.3.6 `virtual void decaf::net::Socket::connect (const std::string & host, int port) throw (decaf::io::IOException, decaf::lang::exceptions::IllegalArgumentException)` [virtual]

Connects to the specified destination.

Parameters:

host The host name or IP address of the remote host to connect to.

port The port on the remote host to connect to.

Exceptions:

IOException Thrown if a failure occurred in the connect.

IllegalArgumentException if the timeout value is negative or the endpoint is invalid.

6.746.3.7 `void decaf::net::Socket::ensureCreated () const throw (decaf::io::IOException)` [protected]

6.746.3.8 `std::string decaf::net::Socket::getInetAddress () const`

Returns the address to which the socket is connected.

Returns:

the remote IP address to which this socket is connected, or null if the socket is not connected.

6.746.3.9 `virtual decaf::io::InputStream* decaf::net::Socket::getInputStream () throw (decaf::io::IOException)` [virtual]

Gets the InputStream for this socket if its connected. The pointer returned is the property of the associated **Socket** (p. 3503) and should not be deleted by the caller.

When the returned InputStream is performing a blocking operation and the underlying connection is closed or otherwise broken the read calls will normally throw an exception to indicate the failure.

Closing the InputStream will also close the underlying **Socket** (p. 3503).

Returns:

The InputStream for this socket.

Exceptions:

IOException if an error occurs during creation of the InputStream, also if the **Socket** (p. 3503) is not connected or the input has been shutdown previously.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2864).

6.746.3.10 `virtual bool decaf::net::Socket::getKeepAlive () const throw (SocketException)` [virtual]

Gets the keep alive flag for this socket, SO_KEEPALIVE.

Returns:

true if keep alive is enabled for this socket.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.11 `std::string decaf::net::Socket::getLocalAddress () const`

Gets the local address to which the socket is bound.

Returns:

the local address to which the socket is bound or `InetAddress.anyLocalAddress()` if the socket is not bound yet.

6.746.3.12 `int decaf::net::Socket::getLocalPort () const`

Gets the local port the socket is bound to.

Returns:

the local port the socket was bound to, or -1 if the socket is not bound.

6.746.3.13 `virtual bool decaf::net::Socket::getOOBInline () const throw (SocketException) [virtual]`

Gets the value of the OOBINLINE for this socket.

Returns:

true if OOBINLINE is enabled, false otherwise.

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

6.746.3.14 `virtual decaf::io::OutputStream* decaf::net::Socket::getOutputStream () throw (decaf::io::IOException) [virtual]`

Gets the OutputStream for this socket if it is connected. The pointer returned is the property of the **Socket** (p. 3503) instance and should not be deleted by the caller.

Closing the returned **Socket** (p. 3503) will also close the underlying **Socket** (p. 3503).

Returns:

the OutputStream for this socket.

Exceptions:

IOException if an error occurs during the creation of this OutputStream, or if the **Socket** (p. 3503) is closed or the output has been shutdown previously.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2865).

6.746.3.15 `int decaf::net::Socket::getPort () const`

Gets the on the remote host this **Socket** (p. 3503) is connected to.

Returns:

the port on the remote host the socket is connected to, or 0 if not connected.

6.746.3.16 `virtual int decaf::net::Socket::getReceiveBufferSize () const throw (SocketException) [virtual]`

Gets the receive buffer size for this socket, SO_RCVBUF. This is the buffer used by the underlying platform socket to buffer received data.

Returns:

the receive buffer size in bytes.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.17 `virtual bool decaf::net::Socket::getReuseAddress () const throw (SocketException) [virtual]`

Gets the reuse address flag, SO_REUSEADDR.

Returns:

True if the address can be reused.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.18 `virtual int decaf::net::Socket::getSendBufferSize () const throw (SocketException) [virtual]`

Gets the send buffer size for this socket, SO_SNDBUF, this value is used by the platform socket to buffer data written to the socket.

Returns:

the size in bytes of the send buffer.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.19 `virtual int decaf::net::Socket::getSoLinger () const throw (SocketException) [virtual]`

Gets the linger time for the socket, SO_LINGER. A return value of -1 indicates that the option is disabled.

Returns:

The linger time in seconds.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.20 `virtual int decaf::net::Socket::getSoTimeout () const throw (SocketException) [virtual]`

Gets the timeout for socket operations, SO_TIMEOUT.

Returns:

The timeout in milliseconds for socket operations.

Exceptions:

SocketException (p. 3521) Thrown if unable to retrieve the information.

6.746.3.21 `virtual bool decaf::net::Socket::getTcpNoDelay () const throw (SocketException) [virtual]`

Gets the Status of the TCP_NODELAY setting for this socket.

Returns:

true if TCP_NODELAY is enabled for the socket.

Exceptions:

SocketException (p. 3521) Thrown if unable to set the information.

6.746.3.22 `virtual int decaf::net::Socket::getTrafficClass () const throw (SocketException) [virtual]`

Gets the Traffic Class setting for this **Socket** (p. 3503), sometimes referred to as Type of Service setting. This setting is dependent on the underlying network implementation for the platform this **Socket** (p. 3503) runs on and is not guaranteed to have any effect.

Refer to your platforms network documentation regarding support for this setting.

Returns:

the bitset result of querying the traffic class setting.

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

6.746.3.23 `void decaf::net::Socket::initSocketImpl (const std::string & address, int port, const InetAddress * localAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException) [protected]`

6.746.3.24 `bool decaf::net::Socket::isBound () const [inline]`

Returns:

true if this **Socket** (p. 3503) has been bound to a Local address.

6.746.3.25 `bool decaf::net::Socket::isClosed () const [inline]`**Returns:**

true if the **Socket** (p. 3503) has been closed.

6.746.3.26 `bool decaf::net::Socket::isConnected () const [inline]`

Indicates whether or not this socket is connected to an end point.

Returns:

true if connected, false otherwise.

6.746.3.27 `bool decaf::net::Socket::isInputShutdown () const [inline]`**Returns:**

true if input on this **Socket** (p. 3503) has been shutdown.

6.746.3.28 `bool decaf::net::Socket::isOutputShutdown () const [inline]`**Returns:**

true if output on this **Socket** (p. 3503) has been shutdown.

6.746.3.29 `virtual void decaf::net::Socket::sendUrgentData (int data) throw (decaf::io::IOException) [virtual]`

Sends one byte of urgent data to the **Socket** (p. 3503).

Parameters:

data The value to write as urgent data, only the lower eight bits are sent.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2866).

6.746.3.30 `virtual void decaf::net::Socket::setKeepAlive (bool keepAlive) throw (SocketException) [virtual]`

Enables/disables the keep alive flag for this socket, SO_KEEPALIVE.

Parameters:

keepAlive If true, enables the flag.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.31 virtual void decaf::net::Socket::setOOBInline (bool *value*) throw (SocketException) [virtual]

Sets the value of the OOBINLINE for this socket, by default this option is disabled. If enabled the urgent data is read inline on the Socket's InputStream, no notification is give.

Returns:

true if OOBINLINE is enabled, false otherwise.

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

Reimplemented in decaf::internal::net::ssl::openssl::OpenSSLSocket (p. 2868).

6.746.3.32 virtual void decaf::net::Socket::setReceiveBufferSize (int *size*) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Sets the receive buffer size for this socket, SO_RCVBUF.

Parameters:

size Number of bytes to set the receive buffer to.

Exceptions:

SocketException (p. 3521) if the operation fails.

IllegalArgumentException if the value is zero or negative.

6.746.3.33 virtual void decaf::net::Socket::setReuseAddress (bool *reuse*) throw (SocketException) [virtual]

Sets the reuse address flag, SO_REUSEADDR.

Parameters:

reuse If true, sets the flag.

Exceptions:

SocketException (p. 3521) if the operation fails.

6.746.3.34 virtual void decaf::net::Socket::setSendBufferSize (int *size*) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Gets the send buffer size for this socket, SO_SNDBUF, this value is used by the platform socket to buffer data written to the socket.

Parameters:

size The number of bytes to set the send buffer to, must be larger than zero.

Exceptions:

SocketException (p. 3521) if the operation fails.

IllegalArgumentException if the value is zero or negative.

```
6.746.3.35 static void decaf::net::Socket::setSocketImplFactory (SocketImplFactory
* factory) throw ( decaf::io::IOException, decaf::net::SocketException )
[static]
```

Sets the instance of a **SocketImplFactory** (p. 3537) that the **Socket** (p. 3503) class should use when new instances of this class are created. This method is only allowed to be used once during the lifetime of the application.

Parameters:

factory The instance of a **SocketImplFactory** (p. 3537) to use when new **Socket** (p. 3503) objects are created.

Exceptions:

IOException if an I/O error occurs while performing this operation.

SocketException (p. 3521) if this method has already been called with a valid factory.

```
6.746.3.36 virtual void decaf::net::Socket::setSoLinger (bool
state, int timeout) throw ( SocketException,
decaf::lang::exceptions::IllegalArgumentException ) [virtual]
```

Sets the linger time (SO_LINGER) using a specified time value, this limits of this value are platform specific.

Parameters:

state The state of SO_LINGER, true is on.

timeout The linger time in seconds, must be non-negative.

Exceptions:

SocketException (p. 3521) if the operation fails.

IllegalArgumentException if state is true and timeout is negative.

```

6.746.3.37  virtual void decaf::net::Socket::setSoTimeout (int timeout) throw (
    SocketException, decaf::lang::exceptions::IllegalArgumentException )
    [virtual]

```

Sets the timeout for socket operations, `SO_TIMEOUT`. A value of zero indicates that timeout is infinite for operations on this socket.

Parameters:

timeout The timeout in milliseconds for socket operations.

Exceptions:

SocketException (p. 3521) Thrown if unable to set the information.

IllegalArgumentException if the timeout value is negative.

6.746.3.38 virtual void decaf::net::Socket::setTcpNoDelay (bool *value*) throw (SocketException) [virtual]

Sets the Status of the TCP_NODELAY param for this socket., this setting is used to disable or enable Nagle's algorithm on the **Socket** (p. 3503).

Parameters:

value The setting for the socket's TCP_NODELAY option, true to enable.

Exceptions:

SocketException (p. 3521) Thrown if unable to set the information.

6.746.3.39 virtual void decaf::net::Socket::setTrafficClass (int *value*) throw (SocketException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Gets the Traffic Class setting for this **Socket** (p. 3503), sometimes referred to as Type of Service setting. This setting is dependent on the underlying network implementation for the platform this **Socket** (p. 3503) runs on and is not guaranteed to have any effect.

Refer to your platforms network documentation regarding support for this setting.

Parameters:

value The integer value representing the traffic class setting bitset.

Exceptions:

SocketException (p. 3521) if an error is encountered while performing this operation.

IllegalArgumentException if the value is not in the range [0..255].

6.746.3.40 virtual void decaf::net::Socket::shutdownInput () throw (decaf::io::IOException) [virtual]

Shuts down the InputStream for this socket essentially marking it as EOF. The stream returns EOF for any calls to read after this method has been called.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented in decaf::internal::net::ssl::openssl::OpenSSLSocket (p. 2869).

6.746.3.41 `virtual void decaf::net::Socket::shutdownOutput () throw (decaf::io::IOException) [virtual]`

Shuts down the OutputStream for this socket, any data already written to the socket will be sent, any further calls to `OutputStream::write` will throw an `IOException`.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Reimplemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2869).

6.746.3.42 `virtual std::string decaf::net::Socket::toString () const [virtual]`

Returns:

a string representing this `Socket` (p. 3503).

6.746.4 Friends And Related Function Documentation

6.746.4.1 `friend class ServerSocket [friend]`

6.746.5 Field Documentation

6.746.5.1 `SocketImpl* decaf::net::Socket::impl [mutable, protected]`

The documentation for this class was generated from the following file:

- `src/main/decaf/net/Socket.h`

6.747 decaf::net::SocketAddress Class Reference

Base class for protocol specific **Socket** (p. 3503) addresses.

`#include <src/main/decaf/net/SocketAddress.h>`Inheritance diagram for decaf::net::SocketAddress:

Public Member Functions

- virtual `~SocketAddress ()`

6.747.1 Detailed Description

Base class for protocol specific **Socket** (p. 3503) addresses. These classes provide an immutable address object that is used by the **Socket** (p. 3503) classes.

Since:

1.0

6.747.2 Constructor & Destructor Documentation

6.747.2.1 virtual decaf::net::SocketAddress::~~SocketAddress () [inline, virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketAddress.h`

6.748 decaf::net::SocketError Class Reference

Static utility class to simplify handling of error codes for socket operations.

```
#include <src/main/decaf/net/SocketError.h>
```

Static Public Member Functions

- static int **getErrorCode** ()
Gets the last error appropriate for the platform.
- static std::string **getErrorString** ()
Gets the string description for the last error.

6.748.1 Detailed Description

Static utility class to simplify handling of error codes for socket operations.

6.748.2 Member Function Documentation

6.748.2.1 static int decaf::net::SocketError::getErrorCode () [static]

Gets the last error appropriate for the platform.

6.748.2.2 static std::string decaf::net::SocketError::getErrorString () [static]

Gets the string description for the last error.

The documentation for this class was generated from the following file:

- src/main/decaf/net/**SocketError.h**

6.749 decaf::net::SocketException Class Reference

Exception for errors when manipulating sockets.

#include <src/main/decaf/net/SocketException.h> Inheritance diagram for decaf::net::SocketException:

Public Member Functions

- **SocketException** () throw ()
- **SocketException** (const lang::Exception &ex) throw ()
- **SocketException** (const SocketException &ex) throw ()
- **SocketException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **SocketException** (const std::exception *cause) throw ()
Constructor.
- **SocketException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **SocketException** * clone () const
Clones this exception.
- virtual ~**SocketException** () throw ()

6.749.1 Detailed Description

Exception for errors when manipulating sockets.

6.749.2 Constructor & Destructor Documentation

- 6.749.2.1 decaf::net::SocketException::SocketException () throw () [inline]
- 6.749.2.2 decaf::net::SocketException::SocketException (const lang::Exception &ex) throw () [inline]
- 6.749.2.3 decaf::net::SocketException::SocketException (const SocketException &ex) throw () [inline]
- 6.749.2.4 decaf::net::SocketException::SocketException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs
lineNumber The line number where the exception occurred.
cause The exception that was the cause for this one to be thrown.
msg The message to report
... list of primitives that are formatted into the message

6.749.2.5 `decaf::net::SocketException::SocketException (const std::exception *
cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.749.2.6 `decaf::net::SocketException::SocketException (const char * file, const int
lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs
lineNumber The line number where the exception occurred.
msg The message to report
... list of primitives that are formatted into the message

6.749.2.7 `virtual decaf::net::SocketException::~~SocketException () throw ()
[inline, virtual]`

6.749.3 Member Function Documentation

6.749.3.1 `virtual SocketException* decaf::net::SocketException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from `decaf::io::IOException` (p. 2144).

Reimplemented in `decaf::internal::net::ssl::openssl::OpenSSLSocketException` (p. 2873), `decaf::net::BindException` (p. 838), `decaf::net::ConnectException`

(p. 1261), [decaf::net::NoRouteToHostException](#) (p. 2822), and [decaf::net::PortUnreachableException](#) (p. 2975).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketException.h`

6.750 decaf::net::SocketFactory Class Reference

The **SocketFactory** (p. 3524) is used to create **Socket** (p. 3503) objects and can be sub-classed to provide other types of Sockets or Sockets with varying configurations.

#include <src/main/decaf/net/SocketFactory.h> Inheritance diagram for decaf::net::SocketFactory:

Public Member Functions

- virtual **~SocketFactory** ()
- virtual **Socket * createSocket** () throw (decaf::io::IOException)
*Creates an unconnected **Socket** (p. 3503) object.*
- virtual **Socket * createSocket** (const **InetAddress** *host, int port)=0 throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
- virtual **Socket * createSocket** (const **InetAddress** *host, int port, const **InetAddress** *ifAddress, int localPort)=0 throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
- virtual **Socket * createSocket** (const std::string &name, int port)=0 throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*
- virtual **Socket * createSocket** (const std::string &name, int port, const **InetAddress** *ifAddress, int localPort)=0 throw (decaf::io::IOException, decaf::net::UnknownHostException)
*Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).*

Static Public Member Functions

- static **SocketFactory * getDefault** ()
*Returns an pointer to the default **SocketFactory** (p. 3524) for this Application, there is only one default **SocketFactory** (p. 3524) per application, the pointer returned by this method is owned by the **SocketFactory** (p. 3524) class and in not to be deleted by the caller.*

Protected Member Functions

- **SocketFactory** ()

6.750.1 Detailed Description

The **SocketFactory** (p. 3524) is used to create **Socket** (p. 3503) objects and can be sub-classed to provide other types of Sockets or Sockets with varying configurations.

See also:

`decaf.net.Socket` (p. 3503)

Since:

1.0

6.750.2 Constructor & Destructor Documentation

6.750.2.1 `decaf::net::SocketFactory::SocketFactory ()` [protected]

6.750.2.2 `virtual decaf::net::SocketFactory::~~SocketFactory ()` [virtual]

6.750.3 Member Function Documentation

6.750.3.1 `virtual Socket* decaf::net::SocketFactory::createSocket (const std::string & name, int port, const InetAddress * ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException)` [pure virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implemented in `decaf::internal::net::DefaultSocketFactory` (p. 1688), `decaf::internal::net::ssl::DefaultSSLSocketFactory` (p. 1700), and `decaf::internal::net::ssl::openssl::OpenSSLSocketFactory` (p. 2878).

6.750.3.2 `virtual Socket* decaf::net::SocketFactory::createSocket (const std::string & name, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException)` [pure virtual]

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host name or IP address to connect the socket to.

port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implemented in **decaf::internal::net::DefaultSocketFactory** (p. 1688), **decaf::internal::net::ssl::DefaultSSLSocketFactory** (p. 1700), and **decaf::internal::net::ssl::openssl::OpenSSLSocketFactory** (p. 2878).

6.750.3.3 `virtual Socket* decaf::net::SocketFactory::createSocket (const InetAddress * host, int port, const InetAddress * ifAddress, int localPort) throw (decaf::io::IOException, decaf::net::UnknownHostException) [pure virtual]`

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524). The **Socket** (p. 3503) will be bound to the specified local address and port.

Parameters:

host The host to connect the socket to.

port The port on the remote host to connect to.

ifAddress The address on the local machine to bind the **Socket** (p. 3503) to.

localPort The local port to bind the **Socket** (p. 3503) to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.

UnknownHostException (p. 3907) if the host name is not known.

Implemented in **decaf::internal::net::DefaultSocketFactory** (p. 1689), **decaf::internal::net::ssl::DefaultSSLSocketFactory** (p. 1701), and **decaf::internal::net::ssl::openssl::OpenSSLSocketFactory** (p. 2879).

6.750.3.4 `virtual Socket* decaf::net::SocketFactory::createSocket (const InetAddress * host, int port) throw (decaf::io::IOException, decaf::net::UnknownHostException) [pure virtual]`

Creates a new **Socket** (p. 3503) object and connects it to the specified remote host and port using the configuration of this **SocketFactory** (p. 3524).

Parameters:

host The host to connect the socket to.
port The port on the remote host to connect to.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if an I/O error occurs while creating the **Socket** (p. 3503) object.
UnknownHostException (p. 3907) if the host name is not known.

Implemented in **decaf::internal::net::DefaultSocketFactory** (p. 1689), **decaf::internal::net::ssl::DefaultSSLSocketFactory** (p. 1701), and **decaf::internal::net::ssl::openssl::OpenSSLSocketFactory** (p. 2879).

6.750.3.5 virtual Socket* decaf::net::SocketFactory::createSocket () throw (decaf::io::IOException) [virtual]

Creates an unconnected **Socket** (p. 3503) object.

Returns:

a new **Socket** (p. 3503) object, caller must free this object when done.

Exceptions:

IOException if the **Socket** (p. 3503) cannot be created.

Reimplemented in **decaf::internal::net::DefaultSocketFactory** (p. 1690), **decaf::internal::net::ssl::DefaultSSLSocketFactory** (p. 1702), and **decaf::internal::net::ssl::openssl::OpenSSLSocketFactory** (p. 2880).

6.750.3.6 static SocketFactory* decaf::net::SocketFactory::getDefault () [static]

Returns an pointer to the default **SocketFactory** (p. 3524) for this Application, there is only one default **SocketFactory** (p. 3524) per application, the pointer returned by this method is owned by the **SocketFactory** (p. 3524) class and in not to be deleted by the caller.

Returns:

pointer to the applications default **SocketFactory** (p. 3524).

Exceptions:

SocketException (p. 3521) if an error occurs while getting the default instance.

Reimplemented in **decaf::net::ssl::SSLSocketFactory** (p. 3572).

The documentation for this class was generated from the following file:

- src/main/decaf/net/**SocketFactory.h**

6.751 decaf::internal::net::SocketFileDescriptor Class Reference

File Descriptor type used internally by Decaf Socket objects.

#include <src/main/decaf/internal/net/SocketFileDescriptor.h>Inheritance diagram for decaf::internal::net::SocketFileDescriptor:

Public Member Functions

- **SocketFileDescriptor** (long value)
- virtual **~SocketFileDescriptor** ()
- long **getValue** () const

Gets the OS Level FileDescriptor.

6.751.1 Detailed Description

File Descriptor type used internally by Decaf Socket objects.

Since:

1.0

6.751.2 Constructor & Destructor Documentation

6.751.2.1 decaf::internal::net::SocketFileDescriptor::SocketFileDescriptor (long *value*)

6.751.2.2 virtual decaf::internal::net::SocketFileDescriptor::~~SocketFileDescriptor () [virtual]

6.751.3 Member Function Documentation

6.751.3.1 long decaf::internal::net::SocketFileDescriptor::getValue () const

Gets the OS Level FileDescriptor.

Returns:

a FileDescriptor value.

The documentation for this class was generated from the following file:

- src/main/decaf/internal/net/**SocketFileDescriptor.h**

6.752 decaf::net::SocketImpl Class Reference

Acts as a base class for all physical **Socket** (p. 3503) implementations.

```
#include <src/main/decaf/net/SocketImpl.h> Inheritance diagram for decaf::net::SocketImpl:
```

Public Member Functions

- **SocketImpl** ()
- virtual **~SocketImpl** ()
- virtual void **create** ()=0 throw (decaf::io::IOException)
*Creates the underlying platform **Socket** (p. 3503) data structures which allows for **Socket** (p. 3503) options to be applied.*
- virtual void **accept** (**SocketImpl** *socket)=0 throw (decaf::io::IOException, decaf::net::SocketException, decaf::net::SocketTimeoutException)
*Accepts a new connection on the given **Socket** (p. 3503).*
- virtual void **connect** (const std::string &hostname, int **port**, int timeout)=0 throw (decaf::io::IOException, decaf::net::SocketTimeoutException, decaf::lang::exceptions::IllegalArgumentException)
Connects this socket to the given host and port.
- virtual void **bind** (const std::string &ipaddress, int **port**)=0 throw (decaf::io::IOException)
*Binds this **Socket** (p. 3503) instance to the local ip address and port number given.*
- virtual void **listen** (int backlog)=0 throw (decaf::io::IOException)
Sets the maximum queue length for incoming connection indications (a request to connect) to the count argument.
- virtual decaf::io::InputStream * **getInputStream** ()=0 throw (decaf::io::IOException)
*Gets the InputStream linked to this **Socket** (p. 3503).*
- virtual decaf::io::OutputStream * **getOutputStream** ()=0 throw (decaf::io::IOException)
*Gets the OutputStream linked to this **Socket** (p. 3503).*
- virtual int **available** ()=0 throw (decaf::io::IOException)
*Gets the number of bytes that can be read from the **Socket** (p. 3503) without blocking.*
- virtual void **close** ()=0 throw (decaf::io::IOException)
Closes the socket, terminating any blocked reads or writes.
- virtual void **shutdownInput** ()=0 throw (decaf::io::IOException)
Places the input stream for this socket at "end of stream".

- virtual void **shutdownOutput** ()=0 throw (decaf::io::IOException)
Disables the output stream for this socket.
- virtual int **getOption** (int option) const =0 throw (decaf::io::IOException)
*Gets the specified **Socket** (p. 3503) option.*
- virtual void **setOption** (int option, int value)=0 throw (decaf::io::IOException)
*Sets the specified option on the **Socket** (p. 3503) if supported.*
- int **getPort** () const
Gets the port that this socket has been assigned.
- int **getLocalPort** () const
Gets the value of this SocketImpl's local port field.
- std::string **getInetAddress** () const
Gets the value of this SocketImpl's address field.
- const decaf::io::FileDescriptor * **getFileDescriptor** () const
*Gets the FileDescriptor for this **Socket** (p. 3503), the Object is owned by this **Socket** (p. 3503) and should not be deleted by the caller.*
- virtual std::string **getLocalAddress** () const =0
*Gets the value of the local Inet address the **Socket** (p. 3503) is bound to if bound, otherwise return the **InetAddress** (p. 2016) ANY value "0.0.0.0".*
- std::string **toString** () const
*Returns a string containing the address and port of this **Socket** (p. 3503) instance.*
- virtual bool **supportsUrgentData** () const
- virtual void **sendUrgentData** (int data) throw (decaf::io::IOException)
*Sends on byte of urgent data to the **Socket** (p. 3503).*

Protected Attributes

- int **port**
*The remote port that this **Socket** (p. 3503) is connected to.*
- int **localPort**
*The port on the Local Machine that this **Socket** (p. 3503) is Bound to.*
- std::string **address**
*The Remote Address that the **Socket** (p. 3503) is connected to.*
- io::FileDescriptor * **fd**
*The File Descriptor for this **Socket** (p. 3503).*

6.752.1 Detailed Description

Acts as a base class for all physical **Socket** (p. 3503) implementations.

Since:

1.0

6.752.2 Constructor & Destructor Documentation

6.752.2.1 decaf::net::SocketImpl::SocketImpl ()

6.752.2.2 virtual decaf::net::SocketImpl::~~SocketImpl () [virtual]

6.752.3 Member Function Documentation

6.752.3.1 virtual void decaf::net::SocketImpl::accept (SocketImpl * *socket*)
throw (decaf::io::IOException, decaf::net::SocketException,
decaf::net::SocketTimeoutException) [pure virtual]

Accepts a new connection on the given **Socket** (p. 3503).

Parameters:

socket The accepted connection.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

SocketException (p. 3521) if an error occurs while performing an Accept on the socket.

SocketTimeoutException (p. 3542) if the accept call times out due to SO_TIMEOUT being set.

6.752.3.2 virtual int decaf::net::SocketImpl::available () throw (
decaf::io::IOException) [pure virtual]

Gets the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Returns:

the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3741).

6.752.3.3 virtual void decaf::net::SocketImpl::bind (const std::string & *ipaddress*,
int *port*) throw (decaf::io::IOException) [pure virtual]

Binds this **Socket** (p. 3503) instance to the local ip address and port number given.

Parameters:

ipaddress The address of local ip to bind to.
port The port number on the host to bind to.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3741).

6.752.3.4 virtual void decaf::net::SocketImpl::close () throw (decaf::io::IOException) [pure virtual]

Closes the socket, terminating any blocked reads or writes.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3742).

6.752.3.5 virtual void decaf::net::SocketImpl::connect (const std::string & hostname, int port, int timeout) throw (decaf::io::IOException, decaf::net::SocketTimeoutException, decaf::lang::exceptions::IllegalArgumentException) [pure virtual]

Connects this socket to the given host and port.

Parameters:

hostname The name of the host to connect to, or IP address.
port The port number on the host to connect to.
timeout Time in milliseconds to wait for a connection, 0 indicates forever.

Exceptions:

IOException if an I/O error occurs while attempting this operation.
SocketTimeoutException (p. 3542) if the connect call times out due to timeout being set.
IllegalArgumentException if a parameter has an illegal value.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3742).

6.752.3.6 virtual void decaf::net::SocketImpl::create () throw (decaf::io::IOException) [pure virtual]

Creates the underlying platform **Socket** (p. 3503) data structures which allows for **Socket** (p. 3503) options to be applied. The created socket is in an unconnected state.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3742).

6.752.3.7 `const decaf::io::FileDescriptor* decaf::net::SocketImpl::getFileDescriptor () const [inline]`

Gets the FileDescriptor for this **Socket** (p. 3503), the Object is owned by this **Socket** (p. 3503) and should not be deleted by the caller.

Returns:

a pointer to this Socket's FileDescriptor object.

6.752.3.8 `std::string decaf::net::SocketImpl::getInetAddress () const [inline]`

Gets the value of this SocketImpl's address field.

Returns:

the value of the address field.

6.752.3.9 `virtual decaf::io::InputStream* decaf::net::SocketImpl::getInputStream () throw (decaf::io::IOException) [pure virtual]`

Gets the InputStream linked to this **Socket** (p. 3503).

Returns:

an InputStream pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3743).

6.752.3.10 `virtual std::string decaf::net::SocketImpl::getLocalAddress () const [pure virtual]`

Gets the value of the local Inet address the **Socket** (p. 3503) is bound to if bound, otherwise return the **InetAddress** (p. 2016) ANY value "0.0.0.0".

Returns:

the local address bound to, or ANY.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3743).

6.752.3.11 `int decaf::net::SocketImpl::getLocalPort () const [inline]`

Gets the value of this SocketImpl's local port field.

Returns:

the value of localPort.

6.752.3.12 `virtual int decaf::net::SocketImpl::getOption (int option) const throw (decaf::io::IOException)` [pure virtual]

Gets the specified **Socket** (p. 3503) option.

Parameters:

option The **Socket** (p. 3503) options whose value is to be retrieved.

Returns:

the value of the given socket option.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3743).

6.752.3.13 `virtual decaf::io::OutputStream* decaf::net::SocketImpl::getOutputStream () throw (decaf::io::IOException)` [pure virtual]

Gets the OutputStream linked to this **Socket** (p. 3503).

Returns:

an OutputStream pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3743).

6.752.3.14 `int decaf::net::SocketImpl::getPort () const` [inline]

Gets the port that this socket has been assigned.

Returns:

the Socket's port number.

6.752.3.15 `virtual void decaf::net::SocketImpl::listen (int backlog) throw (decaf::io::IOException)` [pure virtual]

Sets the maximum queue length for incoming connection indications (a request to connect) to the count argument. If a connection indication arrives when the queue is full, the connection is refused.

Parameters:

backlog The maximum length of the connection queue.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3744).

6.752.3.16 virtual void decaf::net::SocketImpl::sendUrgentData (int *data*) throw (decaf::io::IOException) [virtual]

Sends on byte of urgent data to the **Socket** (p. 3503).

Parameters:

data The value to write as urgent data, only the lower eight bits are sent.

Exceptions:

IOException if an I/O error occurs while performing this operation.

6.752.3.17 virtual void decaf::net::SocketImpl::setOption (int *option*, int *value*) throw (decaf::io::IOException) [pure virtual]

Sets the specified option on the **Socket** (p. 3503) if supported.

Parameters:

option The **Socket** (p. 3503) option to set.

value The value of the socket option to apply to the socket.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3745).

6.752.3.18 virtual void decaf::net::SocketImpl::shutdownInput () throw (decaf::io::IOException) [pure virtual]

Places the input stream for this socket at "end of stream". Any data sent to this socket is acknowledged and then silently discarded. If you read from a socket input stream after invoking **shutdownInput()** (p. 3535) on the socket, the stream will return EOF.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in **decaf::internal::net::tcp::TcpSocket** (p. 3745).

6.752.3.19 `virtual void decaf::net::SocketImpl::shutdownOutput () throw (decaf::io::IOException)` [pure virtual]

Disables the output stream for this socket. For a TCP socket, any previously written data will be sent followed by TCP's normal connection termination sequence. If you write to a socket output stream after invoking `shutdownOutput()` (p. 3536) on the socket, the stream will throw an `IOException`.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implemented in `decaf::internal::net::tcp::TcpSocket` (p. 3746).

6.752.3.20 `virtual bool decaf::net::SocketImpl::supportsUrgentData () const` [inline, virtual]

Returns:

true if this **SocketImpl** (p. 3529) supports sending Urgent Data. The default implementation always returns false.

6.752.3.21 `std::string decaf::net::SocketImpl::toString () const`

Returns a string containing the address and port of this **Socket** (p. 3503) instance.

Returns:

a string containing the address and port of this socket.

6.752.4 Field Documentation

6.752.4.1 `std::string decaf::net::SocketImpl::address` [protected]

The Remote Address that the **Socket** (p. 3503) is connected to.

6.752.4.2 `io::FileDescriptor* decaf::net::SocketImpl::fd` [protected]

The File Descriptor for this **Socket** (p. 3503).

6.752.4.3 `int decaf::net::SocketImpl::localPort` [protected]

The port on the Local Machine that this **Socket** (p. 3503) is Bound to.

6.752.4.4 `int decaf::net::SocketImpl::port` [protected]

The remote port that this **Socket** (p. 3503) is connected to.

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketImpl.h`

6.753 decaf::net::SocketImplFactory Class Reference

Factory class interface for a Factory that creates SocketImpl objects.

```
#include <src/main/decaf/net/SocketImplFactory.h>
```

Public Member Functions

- virtual `~SocketImplFactory ()`
- virtual `SocketImpl * createSocketImpl ()=0`

*Creates a new SocketImpl instance and returns it, the caller then owns the instance and must delete it when finished with the **SocketImpl** (p. 3529).*

6.753.1 Detailed Description

Factory class interface for a Factory that creates SocketImpl objects. These factories can be used to create various types of Sockets, e.g. Streaming, Multicast, SSL, or platform specific variations of these types.

See also:

`decaf::net::Socket` (p. 3503)
`decaf::net::ServerSocket` (p. 3352)

Since:

1.0

6.753.2 Constructor & Destructor Documentation

6.753.2.1 virtual `decaf::net::SocketImplFactory::~~SocketImplFactory ()` [inline, virtual]

6.753.3 Member Function Documentation

6.753.3.1 virtual `SocketImpl* decaf::net::SocketImplFactory::createSocketImpl ()` [pure virtual]

Creates a new SocketImpl instance and returns it, the caller then owns the instance and must delete it when finished with the **SocketImpl** (p. 3529).

Returns:

new **SocketImpl** (p. 3529) instance that is owned by the caller.

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketImplFactory.h`

6.754 decaf::net::SocketOptions Class Reference

#include <src/main/decaf/net/SocketOptions.h> Inheritance diagram for decaf::net::SocketOptions:

Public Member Functions

- virtual `~SocketOptions()`

Static Public Attributes

- static const int **SOCKET_OPTION_TCP_NODELAY**
Disable Nagle's algorithm for this connection.
- static const int **SOCKET_OPTION_BINDADDR**
Fetch the local address binding of a socket (this option cannot be "set" only "gotten", since sockets are bound at creation time, and so the locally bound address cannot be changed).
- static const int **SOCKET_OPTION_REUSEADDR**
Sets SO_REUSEADDR for a socket.
- static const int **SOCKET_OPTION_BROADCAST**
Sets SO_BROADCAST for a socket.
- static const int **SOCKET_OPTION_IP_MULTICAST_IF**
Set which outgoing interface on which to send multicast packets.
- static const int **SOCKET_OPTION_IP_MULTICAST_IF2**
Same as above.
- static const int **SOCKET_OPTION_IP_MULTICAST_LOOP**
This option enables or disables local loopback of multicast datagrams.
- static const int **SOCKET_OPTION_IP_TOS**
This option sets the type-of-service or traffic class field in the IP header for a TCP or UDP socket.
- static const int **SOCKET_OPTION_LINGER**
Specify a linger-on-close timeout.
- static const int **SOCKET_OPTION_TIMEOUT**
*Set a timeout on blocking **Socket** (p. 3503) operations.*
- static const int **SOCKET_OPTION_SNDBUF**
Set a hint the size of the underlying buffers used by the platform for outgoing network I/O.
- static const int **SOCKET_OPTION_RCVBUF**

Set a hint the size of the underlying buffers used by the platform for incoming network I/O.

- static const int **SOCKET_OPTION_KEEPAKALIVE**

When the keepalive option is set for a TCP socket and no data has been exchanged across the socket in either direction for 2 hours (NOTE: the actual value is implementation dependent), TCP automatically sends a keepalive probe to the peer.

- static const int **SOCKET_OPTION_OOBNLINE**

When the OOBINLINE option is set, any TCP urgent data received on the socket will be received through the socket input stream.

6.754.1 Detailed Description

Since:

1.0

6.754.2 Constructor & Destructor Documentation

6.754.2.1 virtual decaf::net::SocketOptions::~SocketOptions () [virtual]

6.754.3 Field Documentation

6.754.3.1 const int decaf::net::SocketOptions::SOCKET_OPTION_BINDADDR [static]

Fetch the local address binding of a socket (this option cannot be "set" only "gotten", since sockets are bound at creation time, and so the locally bound address cannot be changed). The default local address of a socket is INADDR_ANY, meaning any local address on a multi-homed host. A multi-homed host can use this option to accept connections to only one of its addresses (in the case of a **ServerSocket** (p. 3352) or DatagramSocket), or to specify its return address to the peer (for a **Socket** (p. 3503) or DatagramSocket). The parameter of this option is an **InetAddress** (p. 2016).

6.754.3.2 const int decaf::net::SocketOptions::SOCKET_OPTION_BROADCAST [static]

Sets SO_BROADCAST for a socket. This option enables and disables the ability of the process to send broadcast messages. It is supported for only datagram sockets and only on networks that support the concept of a broadcast message (e.g. Ethernet, token ring, etc.), and it is set by default for DatagramSockets.

6.754.3.3 const int decaf::net::SocketOptions::SOCKET_OPTION_IP_MULTICAST_IF [static]

Set which outgoing interface on which to send multicast packets. Useful on hosts with multiple network interfaces, where applications want to use other than the system default. Takes/returns an **InetAddress** (p. 2016).

Valid for Multicast: DatagramSocketImpl.

6.754.3.4 `const int decaf::net::SocketOptions::SOCKET_OPTION_IP_MULTICAST_IF2` [static]

Same as above. This option is introduced so that the behaviour with `IP_MULTICAST_IF` will be kept the same as before, while this new option can support setting outgoing interfaces with either IPv4 and IPv6 addresses.

6.754.3.5 `const int decaf::net::SocketOptions::SOCKET_OPTION_IP_MULTICAST_LOOP` [static]

This option enables or disables local loopback of multicast datagrams. This option is enabled by default for Multicast Sockets.

6.754.3.6 `const int decaf::net::SocketOptions::SOCKET_OPTION_IP_TOS` [static]

This option sets the type-of-service or traffic class field in the IP header for a TCP or UDP socket.

6.754.3.7 `const int decaf::net::SocketOptions::SOCKET_OPTION_KEEPAKALIVE` [static]

When the keepalive option is set for a TCP socket and no data has been exchanged across the socket in either direction for 2 hours (NOTE: the actual value is implementation dependent), TCP automatically sends a keepalive probe to the peer. This probe is a TCP segment to which the peer must respond. One of three responses is expected: 1. The peer responds with the expected ACK. The application is not notified (since everything is OK). TCP will send another probe following another 2 hours of inactivity. 2. The peer responds with an RST, which tells the local TCP that the peer host has crashed and rebooted. The socket is closed. 3. There is no response from the peer. The socket is closed. The purpose of this option is to detect if the peer host crashes.

Valid only for TCP socket: **SocketImpl** (p. 3529)

6.754.3.8 `const int decaf::net::SocketOptions::SOCKET_OPTION_LINGER` [static]

Specify a linger-on-close timeout. This option disables/enables immediate return from a `close()` of a TCP **Socket** (p.3503). Enabling this option with a non-zero Integer timeout means that a `close()` will block pending the transmission and acknowledgment of all data written to the peer, at which point the socket is closed gracefully. Upon reaching the linger timeout, the socket is closed forcefully, with a TCP RST. Enabling the option with a timeout of zero does a forceful close immediately. If the specified timeout value exceeds 65,535 it will be reduced to 65,535.

Valid only for TCP: **SocketImpl** (p. 3529)

6.754.3.9 `const int decaf::net::SocketOptions::SOCKET_OPTION_OOBLINE` [static]

When the OOBLINE option is set, any TCP urgent data received on the socket will be received through the socket input stream. When the option is disabled (which is the default) urgent data is silently discarded.

6.754.3.10 `const int decaf::net::SocketOptions::SOCKET_OPTION_RCVBUF`
[static]

Set a hint the size of the underlying buffers used by the platform for incoming network I/O. When used in set, this is a suggestion to the kernel from the application about the size of buffers to use for the data to be received over the socket. When used in get, this must return the size of the buffer actually used by the platform when receiving in data on this socket. Valid for all sockets: **SocketImpl** (p. 3529), **DatagramSocketImpl**.

6.754.3.11 `const int decaf::net::SocketOptions::SOCKET_OPTION_SO_REUSEADDR` [static]

Sets SO_REUSEADDR for a socket. This is used only for MulticastSockets in **decaf** (p. 143), and it is set by default for MulticastSockets.

6.754.3.12 `const int decaf::net::SocketOptions::SOCKET_OPTION_SNDBUF`
[static]

Set a hint the size of the underlying buffers used by the platform for outgoing network I/O. When used in set, this is a suggestion to the kernel from the application about the size of buffers to use for the data to be sent over the socket. When used in get, this must return the size of the buffer actually used by the platform when sending out data on this socket. Valid for all sockets: **SocketImpl** (p. 3529), **DatagramSocketImpl**.

6.754.3.13 `const int decaf::net::SocketOptions::SOCKET_OPTION_TCP_NODELAY` [static]

Disable Nagle's algorithm for this connection. Written data to the network is not buffered pending acknowledgment of previously written data. Valid for TCP sockets.

6.754.3.14 `const int decaf::net::SocketOptions::SOCKET_OPTION_TIMEOUT`
[static]

Set a timeout on blocking **Socket** (p. 3503) operations. The option must be set prior to entering a blocking operation to take effect.

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketOptions.h`

6.755 decaf::net::SocketTimeoutException Class Reference

#include <src/main/decaf/net/SocketTimeoutException.h> Inheritance diagram for decaf::net::SocketTimeoutException:

Public Member Functions

- **SocketTimeoutException** () throw ()
Default Constructor.
- **SocketTimeoutException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **SocketTimeoutException** (const **SocketTimeoutException** &ex) throw ()
Copy Constructor.
- **SocketTimeoutException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **SocketTimeoutException** (const std::exception *cause) throw ()
Constructor.
- **SocketTimeoutException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **SocketTimeoutException** * **clone** () const
Clones this exception.
- virtual ~**SocketTimeoutException** () throw ()

6.755.1 Constructor & Destructor Documentation

6.755.1.1 decaf::net::SocketTimeoutException::SocketTimeoutException () throw () [inline]

Default Constructor.

6.755.1.2 decaf::net::SocketTimeoutException::SocketTimeoutException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.755.1.3 decaf::net::SocketTimeoutException::SocketTimeoutException (const SocketTimeoutException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.755.1.4 decaf::net::SocketTimeoutException::SocketTimeoutException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.755.1.5 decaf::net::SocketTimeoutException::SocketTimeoutException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.755.1.6 decaf::net::SocketTimeoutException::SocketTimeoutException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.755.1.7 `virtual decaf::net::SocketTimeoutException::~~SocketTimeoutException
() throw () [inline, virtual]`

6.755.2 Member Function Documentation

6.755.2.1 `virtual SocketTimeoutException* de-
caf::net::SocketTimeoutException::clone () const [inline,
virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::InterruptedIOException** (p. 2129).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/SocketTimeoutException.h`

6.756 decaf::net::ssl::SSLContext Class Reference

Represents on implementation of the Secure **Socket** (p. 3503) Layer for streaming based sockets.

```
#include <src/main/decaf/net/ssl/SSLContext.h>
```

Public Member Functions

- **SSLContext** (**SSLContextSpi** *contextImpl)
- virtual **~SSLContext** ()
- **SocketFactory** * **getSocketFactory** ()
*Returns an **SocketFactory** (p. 3524) instance for use with this Context, the **SocketFactory** (p. 3524) is owned by the Context and should not be deleted by the caller.*
- **ServerSocketFactory** * **getServerSocketFactory** ()
*Returns an **ServerSocketFactory** (p. 3361) instance for use with this Context, the **ServerSocketFactory** (p. 3361) is owned by the Context and should not be deleted by the caller.*
- **SSLParameters** * **getDefaultSSLParameters** ()
- **SSLParameters** * **getSupportedSSLParameters** ()

Static Public Member Functions

- static **SSLContext** * **getDefault** ()
*Gets the Default **SSLContext** (p. 3545).*
- static void **setDefault** (**SSLContext** *context)
*Sets the default **SSLContext** (p. 3545) to be returned from future calls to **getDefault**.*

6.756.1 Detailed Description

Represents on implementation of the Secure **Socket** (p. 3503) Layer for streaming based sockets. This class servers a a source of factories to be used to create new SSL **Socket** (p. 3503) instances.

Since:

1.0

6.756.2 Constructor & Destructor Documentation

6.756.2.1 decaf::net::ssl::SSLContext::SSLContext (**SSLContextSpi** * contextImpl)

6.756.2.2 virtual decaf::net::ssl::SSLContext::~~SSLContext () [virtual]

6.756.3 Member Function Documentation

6.756.3.1 static **SSLContext*** decaf::net::ssl::SSLContext::getDefault () [static]

Gets the Default **SSLContext** (p. 3545). The default instance of the **SSLContext** (p. 3545) should be immediately usable without any need for the client to initialize this context.

Returns:

a pointer to the Default **SSLContext** (p. 3545) instance.

6.756.3.2 SSLParameters* decaf::net::ssl::SSLContext::getDefaultSSLParameters ()**Returns:**

a new instance of an **SSLParameters** (p. 3551) object containing the default set of settings for this **SSLContext** (p. 3545).

Exceptions:

UnsupportedOperationException if the parameters cannot be retrieved.

6.756.3.3 ServerSocketFactory* decaf::net::ssl::SSLContext::getServerSocketFactory ()

Returns an **ServerSocketFactory** (p. 3361) instance for use with this Context, the **ServerSocketFactory** (p. 3361) is owned by the Context and should not be deleted by the caller.

Returns:

a pointer to this **SSLContext**'s **ServerSocketFactory** (p. 3361) for creating **SSLServerSocket** (p. 3554) objects.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) requires initialization but it has not yet been initialized.

6.756.3.4 SocketFactory* decaf::net::ssl::SSLContext::getSocketFactory ()

Returns an **SocketFactory** (p. 3524) instance for use with this Context, the **SocketFactory** (p. 3524) is owned by the Context and should not be deleted by the caller.

Returns:

a pointer to this **SSLContext**'s **SocketFactory** (p. 3524) for creating **SSLSocket** (p. 3563) objects.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) requires initialization but it has not yet been initialized.

6.756.3.5 SSLParameters* decaf::net::ssl::SSLContext::getSupportedSSLParameters ()**Returns:**

a new instance of an **SSLParameters** (p. 3551) object containing the complete set of settings for this **SSLContext** (p. 3545).

Exceptions:

UnsupportedOperationException if the parameters cannot be retrieved.

6.756.3.6 static void decaf::net::ssl::SSLContext::setDefault (SSLContext * *context*)
[static]

Sets the default **SSLContext** (p. 3545) to be returned from future calls to getDefault. The set **SSLContext** (p. 3545) must be fully initialized and usable. The caller is responsible for deleting this object before the Library shutdown methods are called.

Exceptions:

NullPointerException if the context passed is NULL.

The documentation for this class was generated from the following file:

- src/main/decaf/net/ssl/**SSLContext.h**

6.757 decaf::net::ssl::SSLContextSpi Class Reference

Defines the interface that should be provided by an **SSLContext** (p. 3545) provider.

#include <src/main/decaf/net/ssl/SSLContextSpi.h> Inheritance diagram for decaf::net::ssl::SSLContextSpi:

Public Member Functions

- virtual **~SSLContextSpi** ()
- virtual void **providerInit** (**security::SecureRandom** *random)=0
Perform the initialization of this Context.
- virtual **SSLParameters** * **providerGetDefaultSSLParameters** ()
*Creates a returns a new **SSLParameters** (p. 3551) instance that contains the default settings for this Providers **SSLContext** (p. 3545).*
- virtual **SSLParameters** * **providerGetSupportedSSLParameters** ()
*Creates and returns a new **SSLParameters** (p. 3551) instance that contains the full set of supported parameters for this SSL Context.*
- virtual **SocketFactory** * **providerGetSocketFactory** ()=0
*Returns a **SocketFactory** (p. 3524) instance that can be used to create new **SSLSocket** (p. 3563) objects.*
- virtual **ServerSocketFactory** * **providerGetServerSocketFactory** ()=0
*Returns a **ServerSocketFactory** (p. 3361) instance that can be used to create new **SSLServerSocket** (p. 3554) objects.*

6.757.1 Detailed Description

Defines the interface that should be provided by an **SSLContext** (p. 3545) provider.

Since:

1.0

6.757.2 Constructor & Destructor Documentation

6.757.2.1 virtual decaf::net::ssl::SSLContextSpi::~~SSLContextSpi () [virtual]

6.757.3 Member Function Documentation

6.757.3.1 virtual **SSLParameters*** decaf::net::ssl::SSLContextSpi::providerGetDefaultSSLParameters () [virtual]

Creates a returns a new **SSLParameters** (p. 3551) instance that contains the default settings for this Providers **SSLContext** (p. 3545). The returned **SSLParameters** (p. 3551) instance is

requires to have non-empty values in its ciphersuites and protocols.

Returns:

new **SSLParameters** (p. 3551) instance with the **SSLContext** (p. 3545) defaults.

Exceptions:

UnsupportedOperationException if the defaults cannot be obtained.

6.757.3.2 virtual ServerSocketFactory* decaf::net::ssl::SSLContextSpi::providerGetServerSocketFactory () [pure virtual]

Returns a **ServerSocketFactory** (p. 3361) instance that can be used to create new **SSLServerSocket** (p. 3554) objects. The **ServerSocketFactory** (p. 3361) is owned by the Service Provider and should not be destroyed by the caller.

Returns:

SocketFactory (p. 3524) instance that can be used to create new SSLServerSockets.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLContextSpi** (p. 2843).

6.757.3.3 virtual SocketFactory* decaf::net::ssl::SSLContextSpi::providerGetSocketFactory () [pure virtual]

Returns a **SocketFactory** (p. 3524) instance that can be used to create new **SSLSocket** (p. 3563) objects. The **SocketFactory** (p. 3524) is owned by the Service Provider and should not be destroyed by the caller.

Returns:

SocketFactory (p. 3524) instance that can be used to create new SSLSockets.

Exceptions:

IllegalStateException if the **SSLContextSpi** (p. 3548) object requires initialization but has not been initialized yet.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLContextSpi** (p. 2843).

6.757.3.4 virtual SSLParameters* decaf::net::ssl::SSLContextSpi::providerGetSupportedSSLParameters () [virtual]

Creates and returns a new **SSLParameters** (p. 3551) instance that contains the full set of supported parameters for this SSL Context. The returned **SSLParameters** (p. 3551) instance is requires to have non-empty values in its ciphersuites and protocols.

Returns:

a new **SSLParameters** (p. 3551) instance with the full set of settings that are supported.

Exceptions:

UnsupportedOperationException if the supported parameters cannot be obtained.

6.757.3.5 **virtual void decaf::net::ssl::SSLContextSpi::providerInit**
(security::SecureRandom * *random*) [pure virtual]

Perform the initialization of this Context.

Parameters:

random Pointer to an instance of a secure random number generator.

Exceptions:

NullPointerException if the SecureRandom instance is NULL.

KeyManagementException if an error occurs while initializing the context.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLContextSpi** (p. 2844).

The documentation for this class was generated from the following file:

- src/main/decaf/net/ssl/SSLContextSpi.h

6.758 decaf::net::ssl::SSLParameters Class Reference

```
#include <src/main/decaf/net/ssl/SSLParameters.h>
```

Public Member Functions

- **SSLParameters** ()

*Creates a new **SSLParameters** (p. 3551) instance with empty vectors for the protocols and the cipherSuites, the wantClientAuth and needClientAuth flags are set to false.*

- **SSLParameters** (const std::vector< std::string > &cipherSuites)

*Creates a new **SSLParameters** (p. 3551) instance with the given cipherSuites value, the protocols vector is empty and the wantClientAuth and needClientAuth flags are set to false.*

- **SSLParameters** (const std::vector< std::string > &cipherSuites, const std::vector< std::string > &protocols)

*Creates a new **SSLParameters** (p. 3551) instance with the given cipherSuites value and protocols value, the wantClientAuth and needClientAuth flags are set to false.*

- virtual ~**SSLParameters** ()

- std::vector< std::string > **getCipherSuites** () const

- void **setCipherSuites** (const std::vector< std::string > &cipherSuites)

Sets the vector of ciphersuites.

- std::vector< std::string > **getProtocols** () const

- void **setProtocols** (const std::vector< std::string > &protocols)

Sets the vector of protocols.

- bool **getWantClientAuth** () const

- void **setWantClientAuth** (bool wantClientAuth)

Sets whether client authentication should be requested.

- bool **getNeedClientAuth** () const

- void **setNeedClientAuth** (bool needClientAuth)

Sets whether client authentication should be required.

6.758.1 Constructor & Destructor Documentation

6.758.1.1 decaf::net::ssl::SSLParameters::SSLParameters ()

Creates a new **SSLParameters** (p. 3551) instance with empty vectors for the protocols and the cipherSuites, the wantClientAuth and needClientAuth flags are set to false.

6.758.1.2 decaf::net::ssl::SSLParameters::SSLParameters (const std::vector< std::string > & cipherSuites)

Creates a new **SSLParameters** (p. 3551) instance with the given cipherSuites value, the protocols vector is empty and the wantClientAuth and needClientAuth flags are set to false.

Parameters:

cipherSuites The vector of cipherSuites for this **SSLParameters** (p. 3551) instance (can be empty).

6.758.1.3 `decaf::net::ssl::SSLParameters::SSLParameters (const std::vector< std::string > & cipherSuites, const std::vector< std::string > & protocols)`

Creates a new **SSLParameters** (p. 3551) instance with the given cipherSuites value and protocols value, the wantClientAuth and needClientAuth flags are set to false.

Parameters:

cipherSuites The vector of cipherSuites for this **SSLParameters** (p. 3551) instance (can be empty).

protocols The vector of protocols for this **SSLParameters** (p. 3551) instance (can be empty).

6.758.1.4 `virtual decaf::net::ssl::SSLParameters::~~SSLParameters () [virtual]`

6.758.2 Member Function Documentation

6.758.2.1 `std::vector<std::string> decaf::net::ssl::SSLParameters::getCipherSuites () const [inline]`

Returns:

a copy of the vector of ciphersuites or an empty vector if none have been set.

6.758.2.2 `bool decaf::net::ssl::SSLParameters::getNeedClientAuth () const [inline]`

Returns:

whether client authentication should be required.

6.758.2.3 `std::vector<std::string> decaf::net::ssl::SSLParameters::getProtocols () const [inline]`

Returns:

a copy of the vector of protocols or an empty vector if none have been set.

6.758.2.4 `bool decaf::net::ssl::SSLParameters::getWantClientAuth () const [inline]`

Returns:

whether client authentication should be requested.

6.758.2.5 void decaf::net::ssl::SSLParameters::setCipherSuites (const std::vector< std::string > & *cipherSuites*) [inline]

Sets the vector of ciphersuites.

Parameters:

cipherSuites The vector of cipherSuites (can be an empty vector).

6.758.2.6 void decaf::net::ssl::SSLParameters::setNeedClientAuth (bool *needClientAuth*) [inline]

Sets whether client authentication should be required. Calling this method clears the wantClientAuth flag.

Parameters:

needClientAuth whether client authentication should be required.

6.758.2.7 void decaf::net::ssl::SSLParameters::setProtocols (const std::vector< std::string > & *protocols*) [inline]

Sets the vector of protocols.

Parameters:

protocols the vector of protocols (or an empty vector)

6.758.2.8 void decaf::net::ssl::SSLParameters::setWantClientAuth (bool *wantClientAuth*) [inline]

Sets whether client authentication should be requested. Calling this method clears the needClientAuth flag.

Parameters:

whether client authentication should be requested.

The documentation for this class was generated from the following file:

- src/main/decaf/net/ssl/SSLParameters.h

6.759 decaf::net::ssl::SSLServerSocket Class Reference

Represents a server socket that is used to accept connections from clients using the Secure Sockets protocol or the Top Level Security protocol.

#include <src/main/decaf/net/ssl/SSLServerSocket.h> Inheritance diagram for decaf::net::ssl::SSLServerSocket:

Public Member Functions

- virtual `~SSLServerSocket ()`
- virtual `std::vector< std::string > getSupportedCipherSuites () const =0`
*Gets a vector containing the names of all the cipher suites that are supported by this **SSLServerSocket** (p. 3554).*
- virtual `std::vector< std::string > getSupportedProtocols () const =0`
*Gets a vector containing the names of all the protocols that could be enabled for this **SSLServerSocket** (p. 3554) instance.*
- virtual `std::vector< std::string > getEnabledCipherSuites () const =0`
*Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSLServerSocket** (p. 3554).*
- virtual `void setEnabledCipherSuites (const std::vector< std::string > &suites)=0`
*Sets the Cipher Suites that are to be enabled on the **SSLServerSocket** (p. 3554) connection.*
- virtual `std::vector< std::string > getEnabledProtocols () const =0`
*Returns a vector containing the names of all the currently enabled Protocols for this **SSLServerSocket** (p. 3554).*
- virtual `void setEnabledProtocols (const std::vector< std::string > &protocols)=0`
*Sets the Protocols that are to be enabled on the **SSLServerSocket** (p. 3554) connection.*
- virtual `bool getWantClientAuth () const =0`
- virtual `void setWantClientAuth (bool value)=0`
*Sets whether or not this **Socket** (p. 3503) will request Client Authentication.*
- virtual `bool getNeedClientAuth () const =0`
- virtual `void setNeedClientAuth (bool value)=0`
*Sets whether or not this **Socket** (p. 3503) will require Client Authentication.*

Protected Member Functions

- `SSLServerSocket ()`
Creates a non-bound server socket.
- `SSLServerSocket (int port)`

*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*

- **SSLServerSocket** (int port, int backlog)

*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*

- **SSLServerSocket** (int port, int backlog, const **decaf::net::InetAddress** *address)

*Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen.*

6.759.1 Detailed Description

Represents a server socket that is used to accept connections from clients using the Secure Sockets protocol or the Top Level Security protocol. The main function of this class is to create **SSLSocket** (p. 3563) objects by accepting connections from client sockets over SSL.

Since:

1.0

6.759.2 Constructor & Destructor Documentation

6.759.2.1 decaf::net::ssl::SSLServerSocket::SSLServerSocket () [protected]

Creates a non-bound server socket.

6.759.2.2 decaf::net::ssl::SSLServerSocket::SSLServerSocket (int port) [protected]

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. When this constructor is called the size of the backlog queue is set at 50, connections that arrive after the backlog has been reached are refused.

If a **SocketImplFactory** (p. 3537) is registered then the createSocketImpl method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.759.2.3 decaf::net::ssl::SSLServerSocket::SSLServerSocket (int port, int backlog) [protected]

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. When this constructor is called the size of the backlog queue is set at

backlog, connections that arrive after the backlog has been reached are refused. If backlog is zero or negative then the default backlog value of 50 is used.

If a **SocketImplFactory** (p. 3537) is registered then the createSocketImpl method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The the number of incoming connection attempts to queue before connections are refused.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.759.2.4 decaf::net::ssl::SSLServerSocket::SSLServerSocket (int *port*, int *backlog*, const decaf::net::InetAddress * *address*) [protected]

Creates a new **ServerSocket** (p. 3352) bound to the specified port, if the value of port is 0, then any free port is chosen. If the value of the ifAddress is empty or NULL then the ANY address is used.

When this constructor is called the size of the backlog queue is set at backlog, connections that arrive after the backlog has been reached are refused. If backlog is zero or negative then the default backlog value of 50 is used.

If a **SocketImplFactory** (p. 3537) is registered then the createSocketImpl method on the factory will be called otherwise a default **SocketImpl** (p. 3529) is created.

Parameters:

port The port to bind the **ServerSocket** (p. 3352) to.

backlog The the number of incoming connection attempts to queue before connections are refused.

ifAddress The IP Address to bind to on the local machine.

Exceptions:

IOException if there is an I/O error while performing this operation.

IllegalArgumentException if the port value is negative or greater than 65535.

6.759.2.5 virtual decaf::net::ssl::SSLServerSocket::~~SSLServerSocket () [virtual]

6.759.3 Member Function Documentation

6.759.3.1 virtual std::vector<std::string> decaf::net::ssl::SSLServerSocket::getEnabledCipherSuites () const [pure virtual]

Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSLServerSocket** (p. 3554).

Returns:

vector of the names of all enabled Cipher Suites.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2849).

6.759.3.2 `virtual std::vector<std::string> decaf::net::ssl::SSLServerSocket::getEnabledProtocols () const [pure virtual]`

Returns a vector containing the names of all the currently enabled Protocols for this **SSLServerSocket** (p. 3554).

Returns:

vector of the names of all enabled Protocols.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2850).

6.759.3.3 `virtual bool decaf::net::ssl::SSLServerSocket::getNeedClientAuth () const [pure virtual]`

Returns:

true if the **Socket** (p. 3503) requires client Authentication.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2850).

6.759.3.4 `virtual std::vector<std::string> decaf::net::ssl::SSLServerSocket::getSupportedCipherSuites () const [pure virtual]`

Gets a vector containing the names of all the cipher suites that are supported by this **SSLServerSocket** (p. 3554). Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).

Returns:

a vector containing the names of all the supported cipher suites.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2850).

6.759.3.5 `virtual std::vector<std::string> decaf::net::ssl::SSLServerSocket::getSupportedProtocols () const [pure virtual]`

Gets a vector containing the names of all the protocols that could be enabled for this **SSLServerSocket** (p. 3554) instance.

Returns:

a vector containing the names of all the supported protocols.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2850).

6.759.3.6 `virtual bool decaf::net::ssl::SSLServerSocket::getWantClientAuth () const`
[pure virtual]

Returns:

true if the **Socket** (p. 3503) request client Authentication.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2851).

6.759.3.7 `virtual void decaf::net::ssl::SSLServerSocket::setEnabledCipherSuites`
(const std::vector< std::string > & *suites*) [pure virtual]

Sets the Cipher Suites that are to be enabled on the **SSLServerSocket** (p. 3554) connection. Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.

Parameters:

suites An Vector of names for all the Cipher Suites that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2851).

6.759.3.8 `virtual void decaf::net::ssl::SSLServerSocket::setEnabledProtocols` (const
std::vector< std::string > & *protocols*) [pure virtual]

Sets the Protocols that are to be enabled on the **SSLServerSocket** (p. 3554) connection. Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.

Parameters:

protocols An Vector of names for all the Protocols that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2851).

6.759.3.9 `virtual void decaf::net::ssl::SSLServerSocket::setNeedClientAuth` (bool
value) [pure virtual]

Sets whether or not this **Socket** (p. 3503) will require Client Authentication. If set to true the **Socket** (p. 3503) (when used in server mode) will require that the client authenticate itself, if the client doesn't send authentication the socket will not allow negotiation to continue.

Parameters:

value Whether the server socket should require client authentication.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2851).

6.759.3.10 virtual void decaf::net::ssl::SSLServerSocket::setWantClientAuth (bool *value*) [pure virtual]

Sets whether or not this **Socket** (p. 3503) will request Client Authentication. If set to true the **Socket** (p. 3503) (when used in server mode) will request that the client authenticate itself, if the client doesn't send authentication the socket will still allow negotiation to continue.

Parameters:

value Whether the server socket should request client authentication.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLServerSocket** (p. 2852).

The documentation for this class was generated from the following file:

- src/main/decaf/net/ssl/**SSLServerSocket.h**

6.760 decaf::net::ssl::SSLServerSocketFactory Class Reference

Factory class interface that provides methods to create SSL Server Sockets.

`#include <src/main/decaf/net/ssl/SSLServerSocketFactory.h>`Inheritance diagram for decaf::net::ssl::SSLServerSocketFactory:

Public Member Functions

- virtual `~SSLServerSocketFactory ()`
- virtual `std::vector< std::string > getDefaultCipherSuites ()=0`

Returns the list of cipher suites which are enabled by default.

- virtual `std::vector< std::string > getSupportedCipherSuites ()=0`

Returns the names of the cipher suites which could be enabled for use on an SSL connection.

Static Public Member Functions

- static `ServerSocketFactory * getDefault ()`

*Returns the current default SSL **ServerSocketFactory** (p. 3361), the factory is returned as a pointer however the caller does not own this pointer and should not delete it.*

Protected Member Functions

- `SSLServerSocketFactory ()`

6.760.1 Detailed Description

Factory class interface that provides methods to create SSL Server Sockets.

Since:

1.0

6.760.2 Constructor & Destructor Documentation

6.760.2.1 `decaf::net::ssl::SSLServerSocketFactory::SSLServerSocketFactory ()`
[protected]

6.760.2.2 `virtual decaf::net::ssl::SSLServerSocketFactory::~~SSLServerSocketFactory ()` [virtual]

6.760.3 Member Function Documentation

6.760.3.1 `static ServerSocketFactory* decaf::net::ssl::SSLServerSocketFactory::getDefault ()`
[static]

Returns the current default SSL `ServerSocketFactory` (p.3361), the factory is returned as a pointer however the caller does not own this pointer and should not delete it. This method returns `SSLContext::getDefault()` (p.3545)->`getServerSocketFactory()`. If that call fails, a non-functional factory is returned.

Returns:

the default SSL `ServerSocketFactory` (p.3361) pointer.

See also:

`decaf::net::ssl::SSLContext::getDefault()` (p.3545)

Reimplemented from `decaf::net::ServerSocketFactory` (p.3363).

6.760.3.2 `virtual std::vector<std::string> decaf::net::ssl::SSLServerSocketFactory::getDefaultCipherSuites ()` [pure virtual]

Returns the list of cipher suites which are enabled by default. Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

`getSupportedCipherSuites()` (p.3561)

Implemented in `decaf::internal::net::ssl::DefaultSSLServerSocketFactory` (p.1695), and `decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory` (p.2856).

6.760.3.3 `virtual std::vector<std::string> decaf::net::ssl::SSLServerSocketFactory::getSupportedCipherSuites ()`
[pure virtual]

Returns the names of the cipher suites which could be enabled for use on an SSL connection. Normally, only a subset of these will actually be enabled by default, since this list may include

cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

getDefaultCipherSuites() (p. 3561)

Implemented in **decaf::internal::net::ssl::DefaultSSLServerSocketFactory** (p. 1696), and **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory** (p. 2857).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ssl/SSLServerSocketFactory.h`

6.761 decaf::net::ssl::SSLSocket Class Reference

#include <src/main/decaf/net/ssl/SSLSocket.h> Inheritance diagram for decaf::net::ssl::SSLSocket:

Public Member Functions

- **SSLSocket** ()
- **SSLSocket** (const **InetAddress** *address, int port)
*Creates a new **SSLSocket** (p. 3563) instance and connects it to the given address and port.*
- **SSLSocket** (const **InetAddress** *address, int port, const **InetAddress** *localAddress, int localPort)
*Creates a new **SSLSocket** (p. 3563) instance and connects it to the given address and port.*
- **SSLSocket** (const std::string &host, int port)
*Creates a new **SSLSocket** (p. 3563) instance and connects it to the given host and port.*
- **SSLSocket** (const std::string &host, int port, const **InetAddress** *localAddress, int localPort)
*Creates a new **SSLSocket** (p. 3563) instance and connects it to the given host and port.*
- virtual ~**SSLSocket** ()
- virtual std::vector< std::string > **getSupportedCipherSuites** () const =0
*Gets a vector containing the names of all the cipher suites that are supported by this **SSLSocket** (p. 3563).*
- virtual std::vector< std::string > **getSupportedProtocols** () const =0
*Gets a vector containing the names of all the protocols that could be enabled for this **SSLSocket** (p. 3563) instance.*
- virtual std::vector< std::string > **getEnabledCipherSuites** () const =0
*Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSL Socket** (p. 3503).*
- virtual void **setEnabledCipherSuites** (const std::vector< std::string > &suites)=0
*Sets the Cipher Suites that are to be enabled on the **SSL Socket** (p. 3503) connection.*
- virtual std::vector< std::string > **getEnabledProtocols** () const =0
*Returns a vector containing the names of all the currently enabled Protocols for this **SSL Socket** (p. 3503).*
- virtual void **setEnabledProtocols** (const std::vector< std::string > &protocols)=0
*Sets the Protocols that are to be enabled on the **SSL Socket** (p. 3503) connection.*
- virtual **SSLParameters** **getSSLParameters** () const
*Returns an **SSLParameters** (p. 3551) object for this **SSLSocket** (p. 3563) instance.*

- virtual void **setSSLParameters** (const **SSLParameters** &value)
*Sets the **SSLParameters** (p. 3551) for this **SSLSocket** (p. 3563) using the supplied **SSLParameters** (p. 3551) instance.*
- virtual void **startHandshake** ()=0
Initiates a handshake for this SSL Connection, this can be necessary for several reasons such as using new encryption keys, or starting a new session.
- virtual void **setUseClientMode** (bool value)=0
Determines the mode that the socket uses when a handshake is initiated, client or server.
- virtual bool **getUseClientMode** () const =0
*Gets whether this **Socket** (p. 3503) is in Client or Server mode, true indicates that the mode is set to Client.*
- virtual void **setNeedClientAuth** (bool value)=0
*Sets the **Socket** (p. 3503) to require that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.*
- virtual bool **getNeedClientAuth** () const =0
Returns if this socket is configured to require client authentication, true means that it has and that clients that failed to authenticate will be rejected.
- virtual void **setWantClientAuth** (bool value)=0
*Sets the **Socket** (p. 3503) to request that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket.*
- virtual bool **getWantClientAuth** () const =0
Returns if this socket is configured to request client authentication, true means that it has and that clients that failed to authenticate will be rejected but that clients that do not send a certificate are not considered to have failed authentication.

6.761.1 Detailed Description

Since:

1.0

6.761.2 Constructor & Destructor Documentation

6.761.2.1 `decaf::net::ssl::SSLSocket::SSLSocket ()`

6.761.2.2 `decaf::net::ssl::SSLSocket::SSLSocket (const InetAddress * address, int port)`

Creates a new **SSLSocket** (p. 3563) instance and connects it to the given address and port. If the host parameter is empty then the loop back address is used.

Parameters:

address The address to connect to.

port The port number to connect to [0...65535]

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

NullPointerException if the **InetAddress** (p. 2016) instance is NULL.

IllegalArgumentException if the port is not in range [0...65535]

6.761.2.3 decaf::net::ssl::SSLSocket::SSLSocket (const InetAddress * address, int port, const InetAddress * localAddress, int localPort)

Creates a new **SSLSocket** (p. 3563) instance and connects it to the given address and port. The **Socket** (p. 3503) will also bind to the local address and port specified.

Parameters:

address The address to connect to.

port The port number to connect to [0...65535]

localAddress The IP address on the local machine to bind to.

localPort The port on the local machine to bind to.

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

NullPointerException if the **InetAddress** (p. 2016) instance is NULL.

IllegalArgumentException if the port is not in range [0...65535]

6.761.2.4 decaf::net::ssl::SSLSocket::SSLSocket (const std::string & host, int port)

Creates a new **SSLSocket** (p. 3563) instance and connects it to the given host and port. If the host parameter is empty then the loop back address is used.

Parameters:

host The host name or IP address to connect to, empty string means loopback.

port The port number to connect to [0...65535]

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

IllegalArgumentException if the port is not in range [0...65535]

6.761.2.5 decaf::net::ssl::SSLSocket::SSLSocket (const std::string & *host*, int *port*, const InetAddress * *localAddress*, int *localPort*)

Creates a new **SSLSocket** (p. 3563) instance and connects it to the given host and port. If the host parameter is empty then the loop back address is used.

Parameters:

host The host name or IP address to connect to, empty string means loopback.

port The port number to connect to [0...65535]

localAddress The IP address on the local machine to bind to.

localPort The port on the local machine to bind to.

Exceptions:

UnknownHostException (p. 3907) if the host cannot be resolved.

IOException if an I/O error occurs while connecting the **Socket** (p. 3503).

IllegalArgumentException if the port is not in range [0...65535]

6.761.2.6 virtual decaf::net::ssl::SSLSocket::~SSLSocket () [virtual]

6.761.3 Member Function Documentation

6.761.3.1 virtual std::vector<std::string> decaf::net::ssl::SSLSocket::getEnabledCipherSuites () const [pure virtual]

Returns a vector containing the names of all the currently enabled Cipher Suites for this **SSL Socket** (p. 3503).

Returns:

vector of the names of all enabled Cipher Suites.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2863).

6.761.3.2 virtual std::vector<std::string> decaf::net::ssl::SSLSocket::getEnabledProtocols () const [pure virtual]

Returns a vector containing the names of all the currently enabled Protocols for this **SSL Socket** (p. 3503).

Returns:

vector of the names of all enabled Protocols.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2864).

6.761.3.3 virtual bool decaf::net::ssl::SSLSocket::getNeedClientAuth () const
[pure virtual]

Returns if this socket is configured to require client authentication, true means that it has and that clients that failed to authenticate will be rejected. This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2864).

6.761.3.4 virtual SSLParameters decaf::net::ssl::SSLSocket::getSSLParameters () const [virtual]

Returns an **SSLParameters** (p. 3551) object for this **SSLSocket** (p. 3563) instance. The cipher-Suites and protocols vectors in the returned **SSLParameters** (p. 3551) reference will never be empty.

Returns:

an **SSLParameters** (p. 3551) object with the settings in use for the **SSLSocket** (p. 3563).

6.761.3.5 virtual std::vector<std::string> decaf::net::ssl::SSLSocket::getSupportedCipherSuites () const [pure virtual]

Gets a vector containing the names of all the cipher suites that are supported by this **SSLSocket** (p. 3563). Normally not all of these cipher suites will be enabled on the **Socket** (p. 3503).

Returns:

a vector containing the names of all the supported cipher suites.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2865).

6.761.3.6 virtual std::vector<std::string> decaf::net::ssl::SSLSocket::getSupportedProtocols () const [pure virtual]

Gets a vector containing the names of all the protocols that could be enabled for this **SSLSocket** (p. 3563) instance.

Returns:

a vector containing the names of all the supported protocols.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2865).

6.761.3.7 virtual bool decaf::net::ssl::SSLSocket::getUseClientMode () const [pure virtual]

Gets whether this **Socket** (p. 3503) is in Client or Server mode, true indicates that the mode is set to Client.

Returns:

true if the **Socket** (p. 3503) is in Client mode, false otherwise.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2865).

6.761.3.8 virtual bool decaf::net::ssl::SSLSocket::getWantClientAuth () const [pure virtual]

Returns if this socket is configured to request client authentication, true means that it has and that clients that failed to authenticate will be rejected but that clients that do not send a certificate are not considered to have failed authentication. This option is only useful when the socket is operating in server mode.

Returns:

true if client authentication is required.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2866).

6.761.3.9 virtual void decaf::net::ssl::SSLSocket::setEnabledCipherSuites (const std::vector< std::string > & suites) [pure virtual]

Sets the Cipher Suites that are to be enabled on the SSL **Socket** (p. 3503) connection. Each of the named Cipher Suites must appear in the list of supported cipher suites for this connection or an exception will be thrown.

Parameters:

suites An Vector of names for all the Cipher Suites that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implemented in **decaf::internal::net::ssl::openssl::OpenSSLSocket** (p. 2867).

6.761.3.10 virtual void decaf::net::ssl::SSLSocket::setEnabledProtocols (const std::vector< std::string > & protocols) [pure virtual]

Sets the Protocols that are to be enabled on the SSL **Socket** (p. 3503) connection. Each of the named Protocols must appear in the list of supported protocols suites for this connection or an exception will be thrown.

Parameters:

protocols An Vector of names for all the Protocols that are to be enabled.

Exceptions:

IllegalArgumentException if the vector is empty or one of the names is invalid.

Implemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2867).

6.761.3.11 virtual void decaf::net::ssl::SSLSocket::setNeedClientAuth (bool *value*)
[pure virtual]

Sets the **Socket** (p. 3503) to require that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket. This option only applies to sockets in the Server mode.

If the option is enabled and the client does not provide a certificate then the handshake is considered failed and the connection is refused. Calling this method resets any previous value for this option as well as clears any value set in the `setWantClientAuth` method.

Parameters:

value The value indicating if a client is required to authenticate itself or not.

Implemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2867).

6.761.3.12 virtual void decaf::net::ssl::SSLSocket::setSSLParameters (const SSLParameters & *value*) [virtual]

Sets the **SSLParameters** (p. 3551) for this **SSLSocket** (p. 3563) using the supplied **SSLParameters** (p. 3551) instance. If the `cipherSuites` vector in the **SSLParameters** (p. 3551) instance is not empty then the `setEnabledCipherSuites` method is called with that vector, if the `protocols` vector in the **SSLParameters** (p. 3551) instance is not empty then the `setEnabledProtocols` method is called with that vector. If the `needClientAuth` value or the `wantClientAuth` value is true then the `setNeedClientAuth` and `setWantClientAuth` methods are called respectively with a value of true, otherwise the `setWantClientAuth` method is called with a value of false.

Parameters:

value The **SSLParameters** (p. 3551) instance that is used to update this **SSLSocket**'s settings.

Exceptions:

IllegalArgumentException if an error occurs while calling `setEnabledCipherSuites` or `setEnabledProtocols`.

6.761.3.13 virtual void decaf::net::ssl::SSLSocket::setUseClientMode (bool *value*)
[pure virtual]

Determines the mode that the socket uses when a handshake is initiated, client or server. This method must be called prior to any handshake attempts on this **Socket** (p. 3503), once a handshake has been initiated this socket remains in the set mode; client or server, for the life of this object.

Parameters:

value The mode setting, true for client or false for server.

Exceptions:

IllegalArgumentException if the handshake process has begun and mode is locked.

Implemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2868).

6.761.3.14 `virtual void decaf::net::ssl::SSLSocket::setWantClientAuth (bool value)`
[pure virtual]

Sets the **Socket** (p. 3503) to request that a client authenticate itself by sending a valid Certificate that is trusted by this Server mode socket. This option only applies to sockets in the Server mode.

If the option is enabled and the client does not provide a certificate then the handshake is considered to have succeeded, if it does send a certificate and that certificate is invalid the handshake will fail. Calling this method resets any previous value for this option as well as clears any value set in the `setNeedClientAuth` method.

Parameters:

value The value indicating if a client is requested to authenticate itself or not.

Implemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2868).

6.761.3.15 `virtual void decaf::net::ssl::SSLSocket::startHandshake ()` [pure virtual]

Initiates a handshake for this SSL Connection, this can be necessary for several reasons such as using new encryption keys, or starting a new session. When called for the first time after the socket connects this method blocks until the handshake is completed. The provider is not required to support multiple handshakes and can throw an `IOException` to indicate an error.

Exceptions:

IOException if an I/O error occurs while performing the Handshake

Implemented in `decaf::internal::net::ssl::openssl::OpenSSLSocket` (p. 2869).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ssl/SSLSocket.h`

6.762 decaf::net::ssl::SSLSocketFactory Class Reference

Factory class interface for a **SocketFactory** (p. 3524) that can create **SSLSocket** (p. 3563) objects.

#include <src/main/decaf/net/ssl/SSLSocketFactory.h>Inheritance diagram for decaf::net::ssl::SSLSocketFactory:

Public Member Functions

- virtual **~SSLSocketFactory** ()
- virtual std::vector< std::string > **getDefaultCipherSuites** ()=0
Returns the list of cipher suites which are enabled by default.
- virtual std::vector< std::string > **getSupportedCipherSuites** ()=0
Returns the names of the cipher suites which could be enabled for use on an SSL connection.
- virtual **Socket** * **createSocket** (**Socket** *socket, std::string host, int port, bool autoClose)=0
Returns a socket layered over an existing socket connected to the named host, at the given port.

Static Public Member Functions

- static **SocketFactory** * **getDefault** ()
*Returns the current default SSL **SocketFactory** (p. 3524), the factory is returned as a pointer however the caller does not own this pointer and should not delete it.*

Protected Member Functions

- **SSLSocketFactory** ()

6.762.1 Detailed Description

Factory class interface for a **SocketFactory** (p. 3524) that can create **SSLSocket** (p. 3563) objects.

Since:

1.0

6.762.2 Constructor & Destructor Documentation

6.762.2.1 `decaf::net::ssl::SSLSocketFactory::SSLSocketFactory ()` [protected]

6.762.2.2 `virtual decaf::net::ssl::SSLSocketFactory::~~SSLSocketFactory ()`
[virtual]

6.762.3 Member Function Documentation

6.762.3.1 `virtual Socket* decaf::net::ssl::SSLSocketFactory::createSocket (Socket *
socket, std::string host, int port, bool autoClose)` [pure virtual]

Returns a socket layered over an existing socket connected to the named host, at the given port. This constructor can be used when tunneling SSL through a proxy or when negotiating the use of SSL over an existing socket. The host and port refer to the logical peer destination. This socket is configured using the socket options established for this factory.

Parameters:

socket The existing socket to layer over.

host The server host the original **Socket** (p. 3503) is connected to.

port The server port the original **Socket** (p. 3503) is connected to.

autoClose Should the layered over **Socket** (p. 3503) be closed when the topmost socket is closed.

Returns:

a new **Socket** (p. 3503) instance that wraps the given **Socket** (p. 3503).

Exceptions:

IOException if an I/O exception occurs while performing this operation.

UnknownHostException (p. 3907) if the host is unknown.

Implemented in `decaf::internal::net::ssl::DefaultSSLSocketFactory` (p. 1699), and `decaf::internal::net::ssl::openssl::OpenSSLSocketFactory` (p. 2877).

6.762.3.2 `static SocketFactory* decaf::net::ssl::SSLSocketFactory::getDefault ()`
[static]

Returns the current default SSL **SocketFactory** (p. 3524), the factory is returned as a pointer however the caller does not own this pointer and should not delete it. This method returns `SSLContext::getDefault()` (p. 3545)->getSocketFactory(). If that call fails, a non-functional factory is returned.

Returns:

the default SSL **SocketFactory** (p. 3524) pointer.

See also:

`decaf::net::ssl::SSLContext::getDefault()` (p. 3545)

Reimplemented from `decaf::net::SocketFactory` (p. 3527).

6.762.3.3 virtual std::vector<std::string> decaf::net::ssl::SSLSocketFactory::getDefaultCipherSuites () [pure virtual]

Returns the list of cipher suites which are enabled by default. Unless a different list is enabled, handshaking on an SSL connection will use one of these cipher suites. The minimum quality of service for these defaults requires confidentiality protection and server authentication (that is, no anonymous cipher suites).

Returns:

an STL vector containing the list of cipher suites enabled by default.

See also:

`getSupportedCipherSuites()` (p. 3573)

Implemented in `decaf::internal::net::ssl::DefaultSSLSocketFactory` (p.1702), and `decaf::internal::net::ssl::openssl::OpenSSLSocketFactory` (p. 2880).

6.762.3.4 virtual std::vector<std::string> decaf::net::ssl::SSLSocketFactory::getSupportedCipherSuites () [pure virtual]

Returns the names of the cipher suites which could be enabled for use on an SSL connection. Normally, only a subset of these will actually be enabled by default, since this list may include cipher suites which do not meet quality of service requirements for those defaults. Such cipher suites are useful in specialized applications.

Returns:

an STL vector containing the list of supported cipher suites.

See also:

`getDefaultCipherSuites()` (p. 3573)

Implemented in `decaf::internal::net::ssl::DefaultSSLSocketFactory` (p.1703), and `decaf::internal::net::ssl::openssl::OpenSSLSocketFactory` (p. 2880).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/ssl/SSLSocketFactory.h`

6.763 activemq::transport::tcp::SslTransport Class Reference

Transport (p. 3883) for connecting to a Broker using an SSL Socket.

#include <src/main/activemq/transport/tcp/SslTransport.h> Inheritance diagram for activemq::transport::tcp::SslTransport:

Public Member Functions

- **SslTransport** (const **Pointer**< **Transport** > &next)
*Creates a new instance of the **SslTransport** (p. 3574), the **transport** (p. 97) will not attempt to connect to a remote host until the connect method is called.*
- virtual ~**SslTransport** ()

Protected Member Functions

- virtual **decaf::net::Socket** * **createSocket** ()
*Create an unconnected Socket instance to be used by the **transport** (p. 97) to communicate with the broker.*
Returns:
a newly created unconnected Socket instance.
Exceptions:
***IOException** if there is an error while creating the unconnected Socket.*
- virtual void **configureSocket** (**decaf::net::Socket** *socket, **decaf::util::Properties** &properties)

6.763.1 Detailed Description

Transport (p. 3883) for connecting to a Broker using an SSL Socket. This **transport** (p. 97) simply wraps the **TcpTransport** (p. 3752) and provides the **TcpTransport** (p. 3752) an SSL based Socket pointer allowing the **core** (p. 89) **TcpTransport** (p. 3752) logic to be reused.

Since:

3.2.0

6.763.2 Constructor & Destructor Documentation

6.763.2.1 activemq::transport::tcp::SslTransport::SslTransport (const **Pointer**< **Transport** > & next)

Creates a new instance of the **SslTransport** (p. 3574), the **transport** (p. 97) will not attempt to connect to a remote host until the connect method is called.

Parameters:

next the next **transport** (p. 97) in the chain

6.763.2.2 virtual **activemq::transport::tcp::SslTransport::~SslTransport** ()
[virtual]

6.763.3 Member Function Documentation

6.763.3.1 virtual void **activemq::transport::tcp::SslTransport::configureSocket**
(**decaf::net::Socket** * *socket*, **decaf::util::Properties** & *properties*)
[protected, virtual]

6.763.3.2 virtual **decaf::net::Socket*** **activemq::transport::tcp::SslTransport::createSocket** ()
[protected, virtual]

Create an unconnected **Socket** instance to be used by the **transport** (p. 97) to communicate with the broker.

Returns:

a newly created unconnected **Socket** instance.

Exceptions:

IOException if there is an error while creating the unconnected **Socket**.

Reimplemented from **activemq::transport::tcp::TcpTransport** (p. 3754).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/tcp/SslTransport.h`

6.764 activemq::transport::tcp::SslTransportFactory Class Reference

#include <src/main/activemq/transport/tcp/SslTransportFactory.h> Inheritance diagram for activemq::transport::tcp::SslTransportFactory:

Public Member Functions

- virtual `~SslTransportFactory ()`

Protected Member Functions

- virtual `Pointer< Transport > doCreateComposite (const decaf::net::URI &location, const Pointer< wireformat::WireFormat > &wireFormat, const decaf::util::Properties &properties) throw (exceptions::ActiveMQException)`
*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

6.764.1 Constructor & Destructor Documentation

- 6.764.1.1 virtual `activemq::transport::tcp::SslTransportFactory::~~SslTransportFactory ()` [virtual]

6.764.2 Member Function Documentation

- 6.764.2.1 virtual `Pointer<Transport> activemq::transport::tcp::SslTransportFactory::doCreateComposite (const decaf::net::URI & location, const Pointer< wireformat::WireFormat > & wireFormat, const decaf::util::Properties & properties) throw (exceptions::ActiveMQException)` [protected, virtual]

Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.

Parameters:

location - URI location to connect to.

wireFormat - the assigned WireFormat for the new **Transport** (p. 3883).

properties - Properties to apply to the **transport** (p. 97).

Returns:

new Pointer to a **SslTransport** (p. 3574).

Exceptions:

ActiveMQException if an error occurs

Reimplemented from **activemq::transport::tcp::TcpTransportFactory** (p. 3757).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/tcp/SslTransportFactory.h`

6.765 activemq::commands::BrokerError::StackTraceElement Struct Reference

```
#include <src/main/activemq/commands/BrokerError.h>
```

Data Fields

- `std::string` **ClassName**
- `std::string` **FileName**
- `std::string` **MethodName**
- `int` **LineNumber**

6.765.1 Field Documentation

6.765.1.1 `std::string` `activemq::commands::BrokerError::StackTraceElement::ClassName`

6.765.1.2 `std::string` `activemq::commands::BrokerError::StackTraceElement::FileName`

6.765.1.3 `int` `activemq::commands::BrokerError::StackTraceElement::LineNumber`

6.765.1.4 `std::string` `activemq::commands::BrokerError::StackTraceElement::MethodName`

The documentation for this struct was generated from the following file:

- `src/main/activemq/commands/BrokerError.h`

6.766 decaf::internal::io::StandardErrorOutputStream Class Reference

Wrapper Around the Standard error Output facility on the current platform.

`#include <src/main/decaf/internal/io/StandardErrorOutputStream.h>`Inheritance diagram for decaf::internal::io::StandardErrorOutputStream:

Public Member Functions

- **StandardErrorOutputStream** ()
- virtual **~StandardErrorOutputStream** ()
- virtual void **flush** () throw (decaf::io::IOException)

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The default implementation of this method does nothing.

- virtual void **close** () throw (decaf::io::IOException)

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing.

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.766.1 Detailed Description

Wrapper Around the Standard error Output facility on the current platform. This allows for the use of alternate output methods on platforms or compilers that do not support `std::cerr`.

6.766.2 Constructor & Destructor Documentation

6.766.2.1 `decaf::internal::io::StandardErrorOutputStream::StandardErrorOutputStream()`

6.766.2.2 `virtual decaf::internal::io::StandardErrorOutputStream::~~StandardErrorOutputStream()` [virtual]

6.766.3 Member Function Documentation

6.766.3.1 `virtual void decaf::internal::io::StandardErrorOutputStream::close()`
`throw (decaf::io::IOException)` [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from `decaf::io::OutputStream` (p. 2909).

6.766.3.2 `virtual void decaf::internal::io::StandardErrorOutputStream::doWriteArrayBounded`
`(const unsigned char * buffer, int size, int offset, int length) throw (`
`decaf::io::IOException, decaf::lang::exceptions::NullPointerException,`
`decaf::lang::exceptions::IndexOutOfBoundsException)` [protected, virtual]

Reimplemented from `decaf::io::OutputStream` (p. 2909).

6.766.3.3 `virtual void decaf::internal::io::StandardErrorOutputStream::doWriteByte`
`(unsigned char value) throw (decaf::io::IOException)` [protected, virtual]

Implements `decaf::io::OutputStream` (p. 2910).

6.766.3.4 `virtual void decaf::internal::io::StandardErrorOutputStream::flush()`
`throw (decaf::io::IOException)` [virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from **decaf::io::OutputStream** (p. 2910).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/io/StandardErrorOutputStream.h`

6.767 decaf::internal::io::StandardInputStream Class Reference

#include <src/main/decaf/internal/io/StandardInputStream.h> Inheritance diagram for decaf::internal::io::StandardInputStream:

Public Member Functions

- **StandardInputStream** ()
- virtual **~StandardInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)

Indicates the number of bytes available.

Protected Member Functions

- virtual int **doReadByte** () throw (decaf::io::IOException)

6.767.1 Constructor & Destructor Documentation

6.767.1.1 decaf::internal::io::StandardInputStream::StandardInputStream ()

6.767.1.2 virtual decaf::internal::io::StandardInputStream::~~StandardInputStream () [virtual]

6.767.2 Member Function Documentation

6.767.2.1 virtual int decaf::internal::io::StandardInputStream::available () const throw (decaf::io::IOException) [virtual]

Indicates the number of bytes available. The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException if an I/O error occurs.

Reimplemented from **decaf::io::InputStream** (p. 2045).

6.767.2.2 virtual int decaf::internal::io::StandardInputStream::doReadByte ()
throw (decaf::io::IOException) [protected, virtual]

Implements **decaf::io::InputStream** (p. 2046).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/io/**StandardInputStream.h**

6.768 decaf::internal::io::StandardOutputStream Class Reference

#include <src/main/decaf/internal/io/StandardOutputStream.h> Inheritance diagram for decaf::internal::io::StandardOutputStream:

Public Member Functions

- **StandardOutputStream** ()
- virtual **~StandardOutputStream** ()
- virtual void **flush** () throw (decaf::io::IOException)
Flushes this stream by writing any buffered output to the underlying stream.
Exceptions:
IOException (p. 2142) if an I/O error occurs.
The default implementation of this method does nothing.
- virtual void **close** () throw (decaf::io::IOException)
Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.
Exceptions:
IOException (p. 2142) if an error occurs while closing.
The default implementation of this method does nothing.

Protected Member Functions

- virtual void **doWriteByte** (unsigned char value) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.768.1 Constructor & Destructor Documentation

6.768.1.1 decaf::internal::io::StandardOutputStream::StandardOutputStream ()

6.768.1.2 virtual
decaf::internal::io::StandardOutputStream::~~StandardOutputStream ()
[virtual]

6.768.2 Member Function Documentation

6.768.2.1 virtual void decaf::internal::io::StandardOutputStream::close () throw (decaf::io::IOException) [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from **decaf::io::OutputStream** (p. 2909).

6.768.2.2 virtual void decaf::internal::io::StandardOutputStream::doWriteArrayBounded (const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]

Reimplemented from **decaf::io::OutputStream** (p. 2909).

6.768.2.3 virtual void decaf::internal::io::StandardOutputStream::doWriteByte (unsigned char *value*) throw (decaf::io::IOException) [protected, virtual]

Implements **decaf::io::OutputStream** (p. 2910).

6.768.2.4 virtual void decaf::internal::io::StandardOutputStream::flush () throw (decaf::io::IOException) [virtual]

Flushes this stream by writing any buffered output to the underlying stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from **decaf::io::OutputStream** (p. 2910).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/io/**StandardOutputStream.h**

6.769 cms::Startable Class Reference

Interface for a class that implements the start method.

#include <src/main/cms/Startable.h> Inheritance diagram for cms::Startable:

Public Member Functions

- virtual `~Startable()`
- virtual void `start()` throw (CMSEException)
Starts the service.

6.769.1 Detailed Description

Interface for a class that implements the start method. An object that implements the **Startable** (p. 3586) interface implies that until its start method is called it will be considered to be in a closed or stopped state and will throw an Exception to indicate that it is not in an started state if one of its methods is called.

Since:

1.0

6.769.2 Constructor & Destructor Documentation

6.769.2.1 virtual cms::Startable::~~Startable() [inline, virtual]

6.769.3 Member Function Documentation

6.769.3.1 virtual void cms::Startable::start() throw (CMSEException) [pure virtual]

Starts the service.

Exceptions:

CMSEException (p. 1160) if an internal error occurs while starting.

Implemented in **activemq::core::ActiveMQConnection** (p. 290).

The documentation for this class was generated from the following file:

- src/main/cms/Startable.h

6.770 decaf::lang::STATIC_CAST_TOKEN Struct Reference

```
#include <src/main/decaf/lang/Pointer.h>
```

The documentation for this struct was generated from the following file:

- `src/main/decaf/lang/Pointer.h`

6.771 activemq::core::ActiveMQConstants::StaticInitializer Class Reference

```
#include <src/main/activemq/core/ActiveMQConstants.h>
```

Public Member Functions

- **StaticInitializer** ()
- virtual **~StaticInitializer** ()

Static Public Attributes

- static std::string **destOptions** [NUM_OPTIONS]
- static std::string **uriParams** [NUM_PARAMS]
- static std::map< std::string, **DestinationOption** > **destOptionMap**
- static std::map< std::string, **URIParam** > **uriParamsMap**

6.771.1 Constructor & Destructor Documentation

6.771.1.1 **activemq::core::ActiveMQConstants::StaticInitializer::StaticInitializer** ()

6.771.1.2 virtual **activemq::core::ActiveMQConstants::StaticInitializer::~~StaticInitializer** () [inline, virtual]

6.771.2 Field Documentation

6.771.2.1 std::map<std::string, **DestinationOption**> **activemq::core::ActiveMQConstants::StaticInitializer::destOptionMap** [static]

6.771.2.2 std::string **activemq::core::ActiveMQConstants::StaticInitializer::destOptions**[NUM_OPTIONS] [static]

6.771.2.3 std::string **activemq::core::ActiveMQConstants::StaticInitializer::uriParams**[NUM_PARAMS] [static]

6.771.2.4 std::map<std::string, **URIParam**> **activemq::core::ActiveMQConstants::StaticInitializer::uriParamsMap** [static]

The documentation for this class was generated from the following file:

- src/main/activemq/core/**ActiveMQConstants.h**

6.772 decaf::util::StlList< E > Class Template Reference

List (p.2337) class that wraps the STL list object to provide a simpler interface and additional methods not provided by the STL type.

#include <src/main/decaf/util/StlList.h>Inheritance diagram for decaf::util::StlList< E >:

Data Structures

- class **ConstStlListIterator**
- class **StlListIterator**

Public Member Functions

- **StlList** ()
Default constructor - does nothing.
- **StlList** (const **StlList** &source)
Copy constructor - copies the content of the given set into this one.
- **StlList** (const **Collection**< E > &source)
Copy constructor - copies the content of the given set into this one.
- virtual ~**StlList** ()
- virtual bool **equals** (const **StlList** &source) const
Compares the passed collection to this one, if they contain the same elements, i.e. all their elements are equivalent, then it returns true.
Returns:
true if the Collections contain the same elements.
- virtual **Iterator**< E > * **iterator** ()
Returns:
an iterator over a set of elements of type T.
- virtual **Iterator**< E > * **iterator** () const
- virtual **ListIterator**< E > * **listIterator** ()
Returns:
a list iterator over the elements in this list (in proper sequence).
- virtual **ListIterator**< E > * **listIterator** () const
- virtual **ListIterator**< E > * **listIterator** (std::size_t index) throw (decaf::lang::exceptions::IndexOutOfBoundsException)
Parameters:
index index of first element to be returned from the list iterator (by a call to the next method).

Returns:

a list iterator of the elements in this list (in proper sequence), starting at the specified position in this list. The specified index indicates the first element that would be returned by an initial call to `next`. An initial call to `previous` would return the element with the specified index minus one.

Exceptions:

IndexOutOfBoundsException if the index is out of range (`index < 0 || index > size()` (p. 1192))

- virtual **ListIterator**< E > * **listIterator** (std::size_t index) const throw (default::lang::exceptions::IndexOutOfBoundsException)
- virtual void **copy** (const **StlList** &source)

- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)

Removes all of the elements from this collection (optional operation).

The collection will be empty after this method returns.

*This implementation iterates over this collection, removing each element using the **Iterator.remove** (p. 2155) operation. Most implementations will probably choose to override this method for efficiency.*

*Note that this implementation will throw an **UnsupportedOperationException** if the iterator returned by this collection's iterator method does not implement the remove method and this collection is non-empty.*

Exceptions:

UnsupportedOperationException if the clear operation is not supported by this collection

- virtual bool **contains** (const E &value) const throw (lang::Exception)

Returns true if this collection contains the specified element.

This implementation iterates over the elements in the collection, checking each element in turn for equality with the specified element.

Parameters:

value - the value whose presence is to be queried for in this **Collection** (p. 1184).

Returns:

true if the value is contained in this collection

Exceptions:

Exception if an error occurs,

- virtual std::size_t **indexOf** (const E &value) throw (default::lang::exceptions::NoSuchElementException)

Returns the index of the first occurrence of the specified element in this list, or -1 if this list does not contain the element.

*More formally, returns the lowest index *i* such that `get(i) == value`, or -1 if there is no such index.*

Parameters:

value - element to search for

Returns:

the index of the first occurrence of the specified element in this list,

Exceptions:

NoSuchElementException if value is not in the list

- virtual std::size_t **lastIndexOf** (const E &value) throw (decaf::lang::exceptions::NoSuchElementException)

Returns the index of the last occurrence of the specified element in this list, or -1 if this list does not contain the element.

More formally, returns the highest index i such that $get(i) == value$ or -1 if there is no such index.

Parameters:

value - element to search for

Returns:

the index of the last occurrence of the specified element in this list.

Exceptions:

NoSuchElementException if value is not in the list

- virtual bool **isEmpty** () const

Returns true if this collection contains no elements.

*This implementation returns **size()** (p. 1192) == 0.*

Returns:

true if the size method return 0.

- virtual std::size_t **size** () const

Returns the number of elements in this collection.

If this collection contains more than Integer.MAX_VALUE elements, returns Integer.MAX_VALUE.

Returns:

the number of elements in this collection

- virtual E **get** (std::size_t index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Gets the element contained at position passed.

Parameters:

index - position to get

Returns:

value at index

- virtual E **set** (std::size_t index, const E &element) throw (decaf::lang::exceptions::IndexOutOfBoundsException)

Replaces the element at the specified position in this list with the specified element.

Parameters:

index - index of the element to replace

element - element to be stored at the specified position

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

- virtual bool **add** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)

Returns true if this collection changed as a result of the call.

(Returns false if this collection does not permit duplicates and already contains the specified element.)

Collections that support this operation may place limitations on what elements may be added to this collection. In particular, some collections will refuse to add null elements, and others will impose restrictions on the type of elements that may be added. **Collection** (p. 1184) classes should clearly specify in their documentation any restrictions on what elements may be added.

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

For non-pointer values, i.e. class instances or string's the object will be copied into the collection, thus the object must support being copied, must not hide the copy constructor and assignment operator.

Parameters:

value - reference to the element to add.

Returns:

true if the element was added

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

- virtual void **add** (std::size_t index, const E &element) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IndexOutOfBoundsException)

Inserts the specified element at the specified position in this list.

Shifts the element currently at that position (if any) and any subsequent elements to the right (adds one to their indices).

Parameters:

index - index at which the specified element is to be inserted

element - element to be inserted

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

- virtual bool **addAll** (std::size_t index, const **Collection**< E > &source) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException)

Inserts all of the elements in the specified collection into this list at the specified position (optional operation).

Shifts the element currently at that position (if any) and any subsequent elements to the right (increases their indices). The new elements will appear in this list in the order that they are returned by the specified collection's iterator. The behavior of this operation is undefined if the specified collection is modified while the operation is in progress. (Note that this will occur if the specified collection is this list, and it's nonempty.)

Parameters:

index The index at which to insert the first element from the specified collection

source The **Collection** (p. 1184) containing elements to be added to this list

Returns:

true if this list changed as a result of the call

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

- virtual bool **remove** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)

Removes a single instance of the specified element from this collection, if it is present (optional operation).

More formally, removes the first element e such that e == o, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an UnsupportedOperationException if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection.

IllegalArgumentException If the value is not a valid entry for this **Collection** (p. 1184).

- virtual E **remove** (std::size_t index) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IndexOutOfBoundsException)

Removes the element at the specified position in this list.

Shifts any subsequent elements to the left (subtracts one from their indices). Returns the element that was removed from the list.

Parameters:

index - the index of the element to be removed

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

6.772.1 Detailed Description

```
template<typename E> class decaf::util::StlList< E >
```

List (p. 2337) class that wraps the STL list object to provide a simpler interface and additional methods not provided by the STL type.

6.772.2 Constructor & Destructor Documentation

6.772.2.1 `template<typename E> decaf::util::StlList< E >::StlList () [inline]`

Default constructor - does nothing.

6.772.2.2 `template<typename E> decaf::util::StlList< E >::StlList (const StlList< E > & source) [inline]`

Copy constructor - copies the content of the given set into this one.

Parameters:

source The source set.

6.772.2.3 `template<typename E> decaf::util::StlList< E >::StlList (const Collection< E > & source) [inline]`

Copy constructor - copies the content of the given set into this one.

Parameters:

source The source set.

6.772.2.4 `template<typename E> virtual decaf::util::StlList< E >::~StlList () [inline, virtual]`

6.772.3 Member Function Documentation

6.772.3.1 `template<typename E> virtual void decaf::util::StlList< E >::add (std::size_t index, const E & element) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IndexOutOfBoundsException) [inline, virtual]`

Inserts the specified element at the specified position in this list.

Shifts the element currently at that position (if any) and any subsequent elements to the right (adds one to their indices).

Parameters:

index - index at which the specified element is to be inserted

element - element to be inserted

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

Implements `decaf::util::List< E >` (p. 2338).

6.772.3.2 `template<typename E> virtual bool decaf::util::StlList< E >::add (const E & value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException) [inline, virtual]`

Returns true if this collection changed as a result of the call.

(Returns false if this collection does not permit duplicates and already contains the specified element.)

Collections that support this operation may place limitations on what elements may be added to this collection. In particular, some collections will refuse to add null elements, and others will impose restrictions on the type of elements that may be added. **Collection** (p.1184) classes should clearly specify in their documentation any restrictions on what elements may be added.

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

For non-pointer values, i.e. class instances or string's the object will be copied into the collection, thus the object must support being copied, must not hide the copy constructor and assignment operator.

Parameters:

value - reference to the element to add.

Returns:

true if the element was added

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

Implements **decaf::util::Collection< E >** (p.1186).

Referenced by decaf::util::StlList< cms::Connection * >::addAll().

```
6.772.3.3  template<typename E> virtual bool decaf::util::StlList< E
>::addAll (std::size_t index, const Collection< E > & source)
throw ( decaf::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IndexOutOfBoundsException ) [inline,
virtual]
```

Inserts all of the elements in the specified collection into this list at the specified position (optional operation).

Shifts the element currently at that position (if any) and any subsequent elements to the right (increases their indices). The new elements will appear in this list in the order that they are returned by the specified collection's iterator. The behavior of this operation is undefined if the specified collection is modified while the operation is in progress. (Note that this will occur if the specified collection is this list, and it's nonempty.)

Parameters:

index The index at which to insert the first element from the specified collection

source The **Collection** (p.1184) containing elements to be added to this list

Returns:

true if this list changed as a result of the call

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

Implements **decaf::util::List< E >** (p. 2339).

6.772.3.4 `template<typename E> virtual void decaf::util::StlList< E >::clear ()
throw (lang::exceptions::UnsupportedOperationException) [inline,
virtual]`

Removes all of the elements from this collection (optional operation).

The collection will be empty after this method returns.

This implementation iterates over this collection, removing each element using the **Iterator.remove** (p. 2155) operation. Most implementations will probably choose to override this method for efficiency.

Note that this implementation will throw an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the remove method and this collection is non-empty.

Exceptions:

UnsupportedOperationException if the clear operation is not supported by this collection

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 183).

6.772.3.5 `template<typename E> virtual bool decaf::util::StlList< E >::contains
(const E & value) const throw (lang::Exception) [inline, virtual]`

Returns true if this collection contains the specified element.

This implementation iterates over the elements in the collection, checking each element in turn for equality with the specified element.

Parameters:

value - the value whose presence is to be queried for in this **Collection** (p. 1184).

Returns:

true if the value is contained in this collection

Exceptions:

Exception if an error occurs,

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 184).

6.772.3.6 `template<typename E> virtual void decaf::util::StlList< E >::copy (const
StlList< E > & source) [inline, virtual]`

Referenced by `decaf::util::StlList< cms::Connection * >::StlList()`.

6.772.3.7 `template<typename E> virtual bool decaf::util::StlList< E >::equals
(const StlList< E > & source) const [inline, virtual]`

Compares the passed collection to this one, if they contain the same elements, i.e.
all their elements are equivalent, then it returns true.

Returns:

true if the Collections contain the same elements.

Implements **decaf::util::Collection< E >** (p. 1189).

6.772.3.8 `template<typename E> virtual E decaf::util::StlList< E >::get (std::size_t
index) const throw (decaf::lang::exceptions::IndexOutOfBoundsException
) [inline, virtual]`

Gets the element contained at position passed.

Parameters:

index - position to get

Returns:

value at index

Implements **decaf::util::List< E >** (p. 2339).

6.772.3.9 `template<typename E> virtual std::size_t decaf::util::StlList<
E >::indexOf (const E & value) throw (de-
caf::lang::exceptions::NoSuchElementException) [inline,
virtual]`

Returns the index of the first occurrence of the specified element in this list, or -1 if this list does
not contain the element.

More formally, returns the lowest index *i* such that `get(i) == value`, or -1 if there is no such index.

Parameters:

value - element to search for

Returns:

the index of the first occurrence of the specified element in this list,

Exceptions:

NoSuchElementException if *value* is not in the list

Implements **decaf::util::List< E >** (p. 2340).

6.772.3.10 `template<typename E> virtual bool decaf::util::StlList< E >::isEmpty
() const [inline, virtual]`

Returns true if this collection contains no elements.

This implementation returns `size()` (p. 1192) == 0.

Returns:

true if the size method return 0.

Reimplemented from `decaf::util::AbstractCollection< E >` (p. 186).

6.772.3.11 `template<typename E> virtual Iterator<E>* decaf::util::StlList< E
>::iterator () const [inline, virtual]`

Implements `decaf::lang::Iterable< E >` (p. 2152).

6.772.3.12 `template<typename E> virtual Iterator<E>* decaf::util::StlList< E
>::iterator () [inline, virtual]`

Returns:

an iterator over a set of elements of type T.

Implements `decaf::lang::Iterable< E >` (p. 2152).

6.772.3.13 `template<typename E> virtual std::size_t decaf::util::StlList<
E >::lastIndexOf (const E & value) throw (
decaf::lang::exceptions::NoSuchElementException) [inline, virtual]`

Returns the index of the last occurrence of the specified element in this list, or -1 if this list does not contain the element.

More formally, returns the highest index i such that `get(i) == value` or -1 if there is no such index.

Parameters:

value - element to search for

Returns:

the index of the last occurrence of the specified element in this list.

Exceptions:

NoSuchElementException if value is not in the list

Implements `decaf::util::List< E >` (p. 2340).

6.772.3.14 `template<typename E> virtual ListIterator<E>* decaf::util::StlList<
E >::listIterator (std::size_t index) const throw (
decaf::lang::exceptions::IndexOutOfBoundsException) [inline,
virtual]`

Implements `decaf::util::List< E >` (p. 2341).

6.772.3.15 `template<typename E> virtual ListIterator<E>*
decaf::util::StlList< E >::listIterator (std::size_t index) throw (
decaf::lang::exceptions::IndexOutOfBoundsException) [inline,
virtual]`

Parameters:

index index of first element to be returned from the list iterator (by a call to the next method).

Returns:

a list iterator of the elements in this list (in proper sequence), starting at the specified position in this list. The specified index indicates the first element that would be returned by an initial call to next. An initial call to previous would return the element with the specified index minus one.

Exceptions:

IndexOutOfBoundsException if the index is out of range ($\text{index} < 0 \parallel \text{index} > \text{size}()$ (p. 1192))

Implements `decaf::util::List< E >` (p. 2341).

6.772.3.16 `template<typename E> virtual ListIterator<E>* decaf::util::StlList< E
>::listIterator () const [inline, virtual]`

Implements `decaf::util::List< E >` (p. 2341).

6.772.3.17 `template<typename E> virtual ListIterator<E>* decaf::util::StlList< E
>::listIterator () [inline, virtual]`

Returns:

a list iterator over the elements in this list (in proper sequence).

Implements `decaf::util::List< E >` (p. 2342).

6.772.3.18 `template<typename E> virtual E decaf::util::StlList<
E >::remove (std::size_t index) throw (de-
cafe::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IndexOutOfBoundsException) [inline,
virtual]`

Removes the element at the specified position in this list.

Shifts any subsequent elements to the left (subtracts one from their indices). Returns the element that was removed from the list.

Parameters:

index - the index of the element to be removed

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

UnsupportedOperationException - If the collection is non-modifiable.

Implements **decaf::util::List**< E > (p. 2342).

```
6.772.3.19  template<typename E> virtual bool decaf::util::StlList<
               E >::remove (const E & value) throw (
               lang::exceptions::UnsupportedOperationException,
               lang::exceptions::IllegalArgumentException ) [inline, virtual]
```

Removes a single instance of the specified element from this collection, if it is present (optional operation).

More formally, removes the first element *e* such that *e* == *o*, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an *UnsupportedOperationException* if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection.

IllegalArgumentException If the value is not a valid entry for this **Collection** (p. 1184).

Reimplemented from **decaf::util::AbstractCollection**< E > (p. 187).

```
6.772.3.20  template<typename E> virtual E decaf::util::StlList< E
               >::set (std::size_t index, const E & element) throw (
               decaf::lang::exceptions::IndexOutOfBoundsException ) [inline,
               virtual]
```

Replaces the element at the specified position in this list with the specified element.

Parameters:

index - index of the element to replace

element - element to be stored at the specified position

Returns:

the element previously at the specified position

Exceptions:

IndexOutOfBoundsException - if the index is greater than size

Implements **decaf::util::List< E >** (p. 2342).

6.772.3.21 `template<typename E> virtual std::size_t decaf::util::StlList< E >::size()
() const [inline, virtual]`

Returns the number of elements in this collection.

If this collection contains more than Integer.MAX_VALUE elements, returns Integer.MAX_VALUE.

Returns:

the number of elements in this collection

Implements **decaf::util::Collection< E >** (p. 1192).

Referenced by `decaf::util::StlList< cms::Connection * >::add()`, `decaf::util::StlList< cms::Connection * >::addAll()`, `decaf::util::StlList< cms::Connection * >::get()`, `decaf::util::StlList< cms::Connection * >::lastIndexOf()`, `decaf::util::StlList< cms::Connection * >::listIterator()`, `decaf::util::StlList< cms::Connection * >::remove()`, and `decaf::util::StlList< cms::Connection * >::set()`.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/StlList.h`

6.773 decaf::util::StlMap< K, V, COMPARATOR > Class Template Reference

Map (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.

#include <src/main/decaf/util/StlMap.h> Inheritance diagram for `decaf::util::StlMap< K, V, COMPARATOR >`:

Public Member Functions

- **StlMap** ()
Default constructor - does nothing.
- **StlMap** (const **StlMap** &source)
Copy constructor - copies the content of the given map into this one.
- **StlMap** (const **Map**< K, V, COMPARATOR > &source)
Copy constructor - copies the content of the given map into this one.
- virtual ~**StlMap** ()
- virtual bool **equals** (const **StlMap** &source) const
Comparison, equality is dependent on the method of determining if the element are equal.
Parameters:
source - **Map** (p. 2459) to compare to this one.
Returns:
*true if the **Map** (p. 2459) passed is equal in value to this one.*
- virtual bool **equals** (const **Map**< K, V, COMPARATOR > &source) const
- virtual void **copy** (const **StlMap** &source)
Copies the content of the source map into this map.
Erases all existing data in this map.
Parameters:
source The source object to copy from.
- virtual void **copy** (const **Map**< K, V, COMPARATOR > &source)
- virtual void **clear** () throw (decaf::lang::exceptions::UnsupportedOperationException)
Removes all keys and values from this map.
Exceptions:
UnsupportedOperationException if this map is unmodifiable.
- virtual bool **containsKey** (const K &key) const
Indicates whether or this map contains a value for the given key.

Parameters:

key The key to look up.

Returns:

true if this map contains the value, otherwise false.

- virtual bool **containsValue** (const V &value) const

Indicates whether or this map contains a value for the given value, i.e. they are equal, this is done by operator== so the types must pass equivalence testing in this manner.

Parameters:

value The Value to look up.

Returns:

true if this map contains the value, otherwise false.

- virtual bool **isEmpty** () const

Returns:

*if the **Map** (p. 2459) contains any element or not, TRUE or FALSE*

- virtual std::size_t **size** () const

Returns:

The number of elements (key/value pairs) in this map.

- virtual V & **get** (const K &key) throw (lang::exceptions::NoSuchElementException)

*Gets the value mapped to the specified key in the **Map** (p. 2459).*

*If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.*

Parameters:

key The search key.

Returns:

A reference to the value for the given key.

Exceptions:

***NoSuchElementException** if the key requests doesn't exist in the **Map** (p. 2459).*

- virtual const V & **get** (const K &key) const throw (lang::exceptions::NoSuchElementException)

*Gets the value mapped to the specified key in the **Map** (p. 2459).*

*If there is no element in the map whose key is equivalent to the key provided then a *NoSuchElementException* is thrown.*

Parameters:

key The search key.

Returns:

A {const} reference to the value for the given key.

Exceptions:

***NoSuchElementException** if the key requests doesn't exist in the **Map** (p. 2459).*

- virtual void **put** (const K &key, const V &value) throw (decaf::lang::exceptions::UnsupportedOperationException)

Sets the value for the specified key.

Parameters:

key The target key.
value The value to be set.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

- virtual void **putAll** (const **StlMap**< K, V, COMPARATOR > &other) throw (decaf::lang::exceptions::UnsupportedOperationException)

*Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.*

Parameters:

other A **Map** (p. 2459) instance whose elements are to all be inserted in this **Map** (p. 2459).

Exceptions:

UnsupportedOperationException If the implementing class does not support the putAll operation.

- virtual void **putAll** (const **Map**< K, V, COMPARATOR > &other) throw (decaf::lang::exceptions::UnsupportedOperationException)

- virtual V **remove** (const K &key) throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException)

Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.

Parameters:

key The search key.

Returns:

a copy of the element that was previously mapped to the given key

Exceptions:

NoSuchElementException if this key is not in the **Map** (p. 2459).
UnsupportedOperationException if this map is unmodifiable.

- virtual std::vector< K > **keySet** () const

*Returns a **Set** (p. 3439) view of the mappings contained in this map.*

*The set is backed by the map, so changes to the map are reflected in the set, and vice-versa. If the map is modified while an iteration over the set is in progress (except through the iterator's own remove operation, or through the setValue operation on a map entry returned by the iterator) the results of the iteration are undefined. The set supports element removal, which removes the corresponding mapping from the map, via the **Iterator.remove** (p. 2155), **Set.remove** (p. 187), **removeAll**, **retainAll** and **clear** operations. It does not support the **add** or **addAll** operations.*

Returns:

the entire set of keys in this map as a std::vector.

- virtual std::vector< V > **values** () const

Returns:

the entire set of values in this map as a std::vector.

- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)

Locks the object.

- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

6.773.1 Detailed Description

```
template<typename K, typename V, typename COMPARATOR = std::less<K>>
class decaf::util::StlMap< K, V, COMPARATOR >
```

Map (p. 2459) template that wraps around a std::map to provide a more user-friendly interface and to provide common functions that do not exist in std::map.

Since:

1.0

6.773.2 Constructor & Destructor Documentation

6.773.2.1 `template<typename K, typename V, typename COMPARATOR = std::less<K>> decaf::util::StlMap< K, V, COMPARATOR >::StlMap () [inline]`

Default constructor - does nothing.

6.773.2.2 `template<typename K, typename V, typename COMPARATOR = std::less<K>> decaf::util::StlMap< K, V, COMPARATOR >::StlMap (const StlMap< K, V, COMPARATOR > & source) [inline]`

Copy constructor - copies the content of the given map into this one.

Parameters:

source The source map.

6.773.2.3 `template<typename K, typename V, typename COMPARATOR = std::less<K>> decaf::util::StlMap< K, V, COMPARATOR >::StlMap (const Map< K, V, COMPARATOR > & source) [inline]`

Copy constructor - copies the content of the given map into this one.

Parameters:

source The source map.

6.773.2.4 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual decaf::util::StlMap< K, V, COMPARATOR >::~StlMap () [inline, virtual]`

6.773.3 Member Function Documentation

6.773.3.1 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::clear () throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Removes all keys and values from this map.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2460).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::copy()`.

6.773.3.2 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR >::containsKey (const K & key) const [inline, virtual]`

Indicates whether or this map contains a value for the given key.

Parameters:

key The key to look up.

Returns:

true if this map contains the value, otherwise false.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2461).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::equals()`.

6.773.3.3 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR
>::containsValue (const V & value) const [inline, virtual]`

Indicates whether or this map contains a value for the given value, i.e.

they are equal, this is done by operator== so the types must pass equivalence testing in this manner.

Parameters:

value The Value to look up.

Returns:

true if this map contains the value, otherwise false.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2462).

6.773.3.4 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR
>::copy (const Map< K, V, COMPARATOR > & source) [inline,
virtual]`

6.773.3.5 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR
>::copy (const StlMap< K, V, COMPARATOR > & source) [inline,
virtual]`

Copies the content of the source map into this map.

Erases all existing data in this map.

Parameters:

source The source object to copy from.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2463).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::StlMap()`.

6.773.3.6 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR >::equals (const Map< K, V, COMPARATOR > & source) const [inline, virtual]`

6.773.3.7 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR >::equals (const StlMap< K, V, COMPARATOR > & source) const [inline, virtual]`

Comparison, equality is dependent on the method of determining if the element are equal.

Parameters:

source - **Map** (p. 2459) to compare to this one.

Returns:

true if the **Map** (p. 2459) passed is equal in value to this one.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2463).

6.773.3.8 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual const V& decaf::util::StlMap< K, V, COMPARATOR >::get (const K & key) const throw (lang::exceptions::NoSuchElementException) [inline, virtual]`

Gets the value mapped to the specified key in the **Map** (p. 2459).

If there is no element in the map whose key is equivalent to the key provided then a **NoSuchElementException** is thrown.

Parameters:

key The search key.

Returns:

A {const} reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2463).

6.773.3.9 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual V& decaf::util::StlMap< K, V, COMPARATOR >::get (const K & key) throw (lang::exceptions::NoSuchElementException) [inline, virtual]`

Gets the value mapped to the specified key in the **Map** (p. 2459).

If there is no element in the map whose key is equivalent to the key provided then a **NoSuchElementException** is thrown.

Parameters:

key The search key.

Returns:

A reference to the value for the given key.

Exceptions:

NoSuchElementException if the key requests doesn't exist in the **Map** (p. 2459).

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2464).

6.773.3.10 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR >::isEmpty () const [inline, virtual]`

Returns:

if the **Map** (p. 2459) contains any element or not, TRUE or FALSE

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2465).

6.773.3.11 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual std::vector<K> decaf::util::StlMap< K, V, COMPARATOR >::keySet () const [inline, virtual]`

Returns a **Set** (p. 3439) view of the mappings contained in this map.

The set is backed by the map, so changes to the map are reflected in the set, and vice-versa. If the map is modified while an iteration over the set is in progress (except through the iterator's own remove operation, or through the setValue operation on a map entry returned by the iterator) the results of the iteration are undefined. The set supports element removal, which removes the corresponding mapping from the map, via the **Iterator.remove** (p. 2155), **Set.remove** (p. 187), **removeAll**, **retainAll** and **clear** operations. It does not support the **add** or **addAll** operations.

Returns:

the entire set of keys in this map as a std::vector.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2466).

6.773.3.12 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::lock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3701).

6.773.3.13 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::notify () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [inline, virtual]`

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3702).

6.773.3.14 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::notifyAll () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException) [inline, virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.773.3.15 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::put (const K & key, const V & value) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Sets the value for the specified key.

Parameters:

key The target key.

value The value to be set.

Exceptions:

UnsupportedOperationException if this map is unmodifiable.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2467).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::putAll()`.

6.773.3.16 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::putAll (const Map< K, V, COMPARATOR > & other) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

6.773.3.17 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::putAll (const StlMap< K, V, COMPARATOR > & other) throw (decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Stores a copy of the Mappings contained in the other **Map** (p. 2459) in this one.

Parameters:

other A **Map** (p. 2459) instance whose elements are to all be inserted in this **Map** (p. 2459).

Exceptions:

UnsupportedOperationException If the implementing class does not support the putAll operation.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2468).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::copy()`.

6.773.3.18 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual V decaf::util::StlMap< K, V, COMPARATOR >::remove (const K & key) throw (decaf::lang::exceptions::NoSuchElementException, decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Removes the value (key/value pair) for the specified key from the map, returns a copy of the value that was mapped to the key.

Parameters:

key The search key.

Returns:

a copy of the element that was previously mapped to the given key

Exceptions:

NoSuchElementException if this key is not in the **Map** (p. 2459).

UnsupportedOperationException if this map is unmodifiable.

Implements **decaf::util::Map< K, V, COMPARATOR >** (p. 2468).

6.773.3.19 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual std::size_t decaf::util::StlMap< K, V, COMPARATOR >::size () const [inline, virtual]`

Returns:

The number of elements (key/value pairs) in this map.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2469).

6.773.3.20 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual bool decaf::util::StlMap< K, V, COMPARATOR >::tryLock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3704).

6.773.3.21 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR >::unlock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements `decaf::util::concurrent::Synchronizable` (p. 3705).

6.773.3.22 `template<typename K, typename V, typename COMPARATOR = std::less<K>> virtual std::vector<V> decaf::util::StlMap< K, V, COMPARATOR >::values () const [inline, virtual]`

Returns:

the entire set of values in this map as a `std::vector`.

Implements `decaf::util::Map< K, V, COMPARATOR >` (p. 2470).

Referenced by `decaf::util::StlMap< std::string, cms::Topic * >::values()`.

6.773.3.23 `template<typename K, typename V, typename COMPARATOR
= std::less<K>> virtual void decaf::util::StlMap< K,
V, COMPARATOR >::wait (long long millisecs, int
nanos) throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE
nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]
RuntimeException if an error occurs while waiting on the object.
InterruptedException if the wait is interrupted before it completes.
IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.773.3.24 `template<typename K, typename V, typename COMPARATOR
= std::less<K>> virtual void decaf::util::StlMap<
K, V, COMPARATOR >::wait (long long millisecs)
throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.
InterruptedException if the wait is interrupted before it completes.
IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

6.773.3.25 `template<typename K, typename V, typename COMPARATOR =
std::less<K>> virtual void decaf::util::StlMap< K, V, COMPARATOR
>::wait () throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/StlMap.h`

6.774 decaf::util::StlQueue< T > Class Template Reference

The **Queue** (p. 3149) class accepts messages with an `psuh(m)` command where `m` is the message to be queued.

#include <src/main/decaf/util/StlQueue.h> Inheritance diagram for decaf::util::StlQueue< T >:

Data Structures

- class **QueueIterator**

Public Member Functions

- **StlQueue** ()
- virtual **~StlQueue** ()
- **Iterator**< T > * **iterator** ()
*Gets an **Iterator** (p. 2154) over this **Queue** (p. 3149).*
- void **clear** ()
Empties this queue.
- T & **front** ()
Returns a Reference to the element at the head of the queue.
- const T & **front** () const
Returns a Reference to the element at the head of the queue.
- T & **back** ()
Returns a Reference to the element at the tail of the queue.
- const T & **back** () const
Returns a Reference to the element at the tail of the queue.
- void **push** (const T &t)
Places a new Object at the Tail of the queue.
- void **enqueueFront** (const T &t)
Places a new Object at the front of the queue.
- T **pop** ()
Removes and returns the element that is at the Head of the queue.
- size_t **size** () const
*Gets the Number of elements currently in the **Queue** (p. 3149).*
- bool **empty** () const
*Checks if this **Queue** (p. 3149) is currently empty.*

- virtual `std::vector< T > toArray () const`
- void **reverse** (`StlQueue< T > &target`) const
Reverses the order of the contents of this queue and stores them in the target queue.
- virtual void **lock** () throw (`decaf::lang::exceptions::RuntimeException`)
Locks the object.
- virtual bool **tryLock** () throw (`decaf::lang::exceptions::RuntimeException`)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (`decaf::lang::exceptions::RuntimeException`)
Unlocks the object.
- virtual void **wait** () throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalMonitorStateException`, `decaf::lang::exceptions::InterruptedException`)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalMonitorStateException`, `decaf::lang::exceptions::InterruptedException`)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalArgumentException`, `decaf::lang::exceptions::IllegalMonitorStateException`, `decaf::lang::exceptions::InterruptedException`)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalMonitorStateException`)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (`decaf::lang::exceptions::RuntimeException`, `decaf::lang::exceptions::IllegalMonitorStateException`)
Signals the waiters on this object that it can now wake up and continue.
- T & **getSafeValue** ()
Fetch a reference to the safe value this object will return when there is nothing to fetch from the queue.

6.774.1 Detailed Description

`template<typename T> class decaf::util::StlQueue< T >`

The **Queue** (p. 3149) class accepts messages with an `psuh(m)` command where m is the message to be queued. It destructively returns the message with **pop()** (p. 3619). **pop()** (p. 3619) returns messages in the order they were enqueued.

Queue (p.3149) is implemented with an instance of the STL queue object. The interface is essentially the same as that of the STL queue except that the pop method actually returns a reference to the element popped. This frees the app from having to call the **front** method before calling pop.

```
Queue<string> sq; // make a queue to hold string messages sq.push(s); // enqueues a message
m string s = sq.pop(); // dequeues a message
```

= DESIGN CONSIDERATIONS

The **Queue** (p.3149) class inherits from the Synchronizable interface and provides methods for locking and unlocking this queue as well as waiting on this queue. In a multi-threaded app this can allow for multiple threads to be reading from and writing to the same **Queue** (p.3149).

Clients should consider that in a multiple threaded app it is possible that items could be placed on the queue faster than you are taking them off, so protection should be placed in your polling loop to ensure that you don't get stuck there.

6.774.2 Constructor & Destructor Documentation

6.774.2.1 `template<typename T> decaf::util::StlQueue< T >::StlQueue ()`
[inline]

6.774.2.2 `template<typename T> virtual decaf::util::StlQueue< T >::~~StlQueue ()`
[inline, virtual]

6.774.3 Member Function Documentation

6.774.3.1 `template<typename T> const T& decaf::util::StlQueue< T >::back ()`
const [inline]

Returns a Reference to the element at the tail of the queue.

Returns:

reference to a queue type object or (safe)

6.774.3.2 `template<typename T> T& decaf::util::StlQueue< T >::back ()` [inline]

Returns a Reference to the element at the tail of the queue.

Returns:

reference to a queue type object or (safe)

6.774.3.3 `template<typename T> void decaf::util::StlQueue< T >::clear ()`
[inline]

Empties this queue.

6.774.3.4 `template<typename T> bool decaf::util::StlQueue< T >::empty () const`
[inline]

Checks if this **Queue** (p.3149) is currently empty.

Returns:

boolean indicating queue emptiness

6.774.3.5 `template<typename T> void decaf::util::StlQueue< T >::enqueueFront (const T & t) [inline]`

Places a new Object at the front of the queue.

Parameters:

t - **Queue** (p. 3149) Object Type reference.

6.774.3.6 `template<typename T> const T& decaf::util::StlQueue< T >::front () const [inline]`

Returns a Reference to the element at the head of the queue.

Returns:

reference to a queue type object or (safe)

6.774.3.7 `template<typename T> T& decaf::util::StlQueue< T >::front () [inline]`

Returns a Reference to the element at the head of the queue.

Returns:

reference to a queue type object or (safe)

6.774.3.8 `template<typename T> T& decaf::util::StlQueue< T >::getSafeValue () [inline]`

Fetch a reference to the safe value this object will return when there is nothing to fetch from the queue.

Returns:

Reference to this Queues safe object

Referenced by `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::back()`, `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::front()`, and `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >::pop()`.

6.774.3.9 `template<typename T> Iterator<T>* decaf::util::StlQueue< T >::iterator () [inline]`

Gets an **Iterator** (p. 2154) over this **Queue** (p. 3149).

Returns:

new iterator pointer that is owned by the caller.

6.774.3.10 `template<typename T> virtual void decaf::util::StlQueue< T >::lock ()
 throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3701).

6.774.3.11 `template<typename T> virtual void decaf::util::StlQueue< T
 >::notify () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [inline,
 virtual]`

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3702).

6.774.3.12 `template<typename T> virtual void decaf::util::StlQueue< T
 >::notifyAll () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [inline,
 virtual]`

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.774.3.13 `template<typename T> T decaf::util::StlQueue< T >::pop () [inline]`

Removes and returns the element that is at the Head of the queue.

Returns:

reference to a queue type object or (safe)

6.774.3.14 `template<typename T> void decaf::util::StlQueue< T >::push (const T & t) [inline]`

Places a new Object at the Tail of the queue.

Parameters:

t - **Queue** (p. 3149) Object Type reference.

6.774.3.15 `template<typename T> void decaf::util::StlQueue< T >::reverse (StlQueue< T > & target) const [inline]`

Reverses the order of the contents of this queue and stores them in the target queue.

Parameters:

target - The target queue that will receive the contents of this queue in reverse order.

6.774.3.16 `template<typename T> size_t decaf::util::StlQueue< T >::size () const [inline]`

Gets the Number of elements currently in the **Queue** (p. 3149).

Returns:

Queue (p. 3149) Size

6.774.3.17 `template<typename T> virtual std::vector<T> decaf::util::StlQueue< T >::toArray () const [inline, virtual]`

Returns:

the all values in this queue as a std::vector.

6.774.3.18 `template<typename T> virtual bool decaf::util::StlQueue< T >::tryLock () throw (decaf::lang::exceptions::RuntimeException) [inline, virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

6.774.3.19 `template<typename T> virtual void decaf::util::StlQueue< T >::unlock
() throw (decaf::lang::exceptions::RuntimeException) [inline,
virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

6.774.3.20 `template<typename T> virtual void decaf::util::StlQueue<
T >::wait (long long millisecs, int nanos) throw
(decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.774.3.21 `template<typename T> virtual void decaf::util::StlQueue< T >::wait
(long long millisecs) throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

```
6.774.3.22  template<typename T> virtual void decaf::util::StlQueue< T
>::wait () throw ( decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- src/main/decaf/util/StlQueue.h

6.775 decaf::util::StlSet< E > Class Template Reference

Set (p. 3439) template that wraps around a `std::set` to provide a more user-friendly interface and to provide common functions that do not exist in `std::set`.

#include <src/main/decaf/util/StlSet.h> Inheritance diagram for `decaf::util::StlSet< E >`:

Data Structures

- class **ConstSetIterator**
- class **SetIterator**

Public Member Functions

- **StlSet** ()
Default constructor - does nothing.
- **StlSet** (const **StlSet** &source)
Copy constructor - copies the content of the given set into this one.
- **StlSet** (const **Collection**< E > &source)
Copy constructor - copies the content of the given set into this one.
- virtual ~**StlSet** ()
- **Iterator**< E > * **iterator** ()
Returns:
an iterator over a set of elements of type T.
- **Iterator**< E > * **iterator** () const
- virtual bool **equals** (const **StlSet** &source) const
Compares the passed collection to this one, if they contain the same elements, i.e. all their elements are equivalent, then it returns true.
Returns:
true if the Collections contain the same elements.
- virtual void **copy** (const **StlSet** &source)
- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)
*Removes all of the elements from this collection (optional operation).
The collection will be empty after this method returns.
This implementation iterates over this collection, removing each element using the **Iterator.remove** (p. 2155) operation. Most implementations will probably choose to override this method for efficiency.
Note that this implementation will throw an **UnsupportedOperationException** if the iterator returned by this collection's iterator method does not implement the remove method and this collection is non-empty.*
Exceptions:
***UnsupportedOperationException** if the clear operation is not supported by this collection*

- virtual bool **contains** (const E &value) const throw (lang::Exception)

Returns true if this collection contains the specified element.

This implementation iterates over the elements in the collection, checking each element in turn for equality with the specified element.

Parameters:

value - the value whose presence is to be queried for in this **Collection** (p. 1184).

Returns:

true if the value is contained in this collection

Exceptions:

Exception if an error occurs,

- virtual bool **isEmpty** () const
- virtual std::size_t **size** () const
- virtual bool **add** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException, lang::exceptions::IllegalStateException)

Returns true if this collection changed as a result of the call.

(Returns false if this collection does not permit duplicates and already contains the specified element.)

*Collections that support this operation may place limitations on what elements may be added to this collection. In particular, some collections will refuse to add null elements, and others will impose restrictions on the type of elements that may be added. **Collection** (p. 1184) classes should clearly specify in their documentation any restrictions on what elements may be added.*

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

For non-pointer values, i.e. class instances or string's the object will be copied into the collection, thus the object must support being copied, must not hide the copy constructor and assignment operator.

Parameters:

value - reference to the element to add.

Returns:

true if the element was added

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

- virtual bool **remove** (const E &value) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)

Removes a single instance of the specified element from this collection, if it is present (optional operation).

More formally, removes the first element e such that e == o, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an UnsupportedOperationException if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

***UnsupportedOperationException** if the remove operation is not supported by this collection.*

***IllegalArgumentException** If the value is not a valid entry for this **Collection** (p. 1184).*

6.775.1 Detailed Description

```
template<typename E> class decaf::util::StlSet< E >
```

Set (p. 3439) template that wraps around a std::set to provide a more user-friendly interface and to provide common functions that do not exist in std::set.

6.775.2 Constructor & Destructor Documentation

```
6.775.2.1 template<typename E> decaf::util::StlSet< E >::StlSet () [inline]
```

Default constructor - does nothing.

```
6.775.2.2 template<typename E> decaf::util::StlSet< E >::StlSet (const StlSet< E  
> & source) [inline]
```

Copy constructor - copies the content of the given set into this one.

Parameters:

source The source set.

```
6.775.2.3 template<typename E> decaf::util::StlSet< E >::StlSet (const  
Collection< E > & source) [inline]
```

Copy constructor - copies the content of the given set into this one.

Parameters:

source The source set.

```
6.775.2.4 template<typename E> virtual decaf::util::StlSet< E >::~~StlSet ()  
[inline, virtual]
```

6.775.3 Member Function Documentation

```
6.775.3.1 template<typename E> virtual bool decaf::util::StlSet< E >::add (const  
E & value) throw ( lang::exceptions::UnsupportedOperationException,  
lang::exceptions::IllegalArgumentException,  
lang::exceptions::IllegalStateException ) [inline,  
virtual]
```

Returns true if this collection changed as a result of the call.

(Returns false if this collection does not permit duplicates and already contains the specified element.)

Collections that support this operation may place limitations on what elements may be added to this collection. In particular, some collections will refuse to add null elements, and others will impose restrictions on the type of elements that may be added. **Collection** (p.1184) classes should clearly specify in their documentation any restrictions on what elements may be added.

If a collection refuses to add a particular element for any reason other than that it already contains the element, it must throw an exception (rather than returning false). This preserves the invariant that a collection always contains the specified element after this call returns.

For non-pointer values, i.e. class instances or string's the object will be copied into the collection, thus the object must support being copied, must not hide the copy constructor and assignment operator.

Parameters:

value - reference to the element to add.

Returns:

true if the element was added

Exceptions:

UnsupportedOperationException

IllegalArgumentException

IllegalStateException if the element cannot be added at this time due to insertion restrictions

Implements **decaf::util::Collection< E >** (p.1186).

6.775.3.2 `template<typename E> virtual void decaf::util::StlSet< E >::clear ()
throw (lang::exceptions::UnsupportedOperationException) [inline,
virtual]`

Removes all of the elements from this collection (optional operation).

The collection will be empty after this method returns.

This implementation iterates over this collection, removing each element using the **Iterator.remove** (p.2155) operation. Most implementations will probably choose to override this method for efficiency.

Note that this implementation will throw an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the remove method and this collection is non-empty.

Exceptions:

UnsupportedOperationException if the clear operation is not supported by this collection

Reimplemented from **decaf::util::AbstractCollection< E >** (p.183).

6.775.3.3 `template<typename E> virtual bool decaf::util::StlSet< E >::contains
(const E & value) const throw (lang::Exception) [inline, virtual]`

Returns true if this collection contains the specified element.

This implementation iterates over the elements in the collection, checking each element in turn for equality with the specified element.

Parameters:

value - the value whose presence is to be queried for in this **Collection** (p.1184).

Returns:

true if the value is contained in this collection

Exceptions:

Exception if an error occurs,

Reimplemented from **decaf::util::AbstractCollection< E >** (p.184).

6.775.3.4 `template<typename E> virtual void decaf::util::StlSet< E >::copy (const
StlSet< E > & source) [inline, virtual]`

Referenced by `decaf::util::StlSet< ActiveMQSession * >::StlSet()`.

6.775.3.5 `template<typename E> virtual bool decaf::util::StlSet< E >::equals
(const StlSet< E > & source) const [inline, virtual]`

Compares the passed collection to this one, if they contain the same elements, i.e.

all their elements are equivalent, then it returns true.

Returns:

true if the Collections contain the same elements.

Implements **decaf::util::Collection< E >** (p.1189).

6.775.3.6 `template<typename E> virtual bool decaf::util::StlSet< E >::isEmpty ()
const [inline, virtual]`

Returns:

if the set contains any element or not, TRUE or FALSE

Reimplemented from **decaf::util::AbstractCollection< E >** (p.186).

6.775.3.7 `template<typename E> Iterator<E>* decaf::util::StlSet< E >::iterator ()
const [inline, virtual]`

Implements **decaf::lang::Iterable< E >** (p.2152).

6.775.3.8 `template<typename E> Iterator<E>* decaf::util::StlSet< E >::iterator ()`
`[inline, virtual]`

Returns:

an iterator over a set of elements of type T.

Implements **decaf::lang::Iterable< E >** (p. 2152).

6.775.3.9 `template<typename E> virtual bool decaf::util::StlSet<`
`E >::remove (const E & value) throw (`
`lang::exceptions::UnsupportedOperationException,`
`lang::exceptions::IllegalArgumentException) [inline, virtual]`

Removes a single instance of the specified element from this collection, if it is present (optional operation).

More formally, removes the first element *e* such that *e* == *o*, if this collection contains one or more such elements. Returns true if this collection contained the specified element (or equivalently, if this collection changed as a result of the call).

This implementation iterates over the collection looking for the specified element. If it finds the element, it removes the element from the collection using the iterator's remove method.

Note that this implementation throws an `UnsupportedOperationException` if the iterator returned by this collection's iterator method does not implement the remove method and this collection contains the specified object.

Parameters:

value - element to be removed from this collection, if present

Returns:

true if an element was removed as a result of this call

Exceptions:

UnsupportedOperationException if the remove operation is not supported by this collection.

IllegalArgumentException If the value is not a valid entry for this **Collection** (p. 1184).

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 187).

6.775.3.10 `template<typename E> virtual std::size_t decaf::util::StlSet< E >::size`
`() const [inline, virtual]`

Returns:

The number of elements in this set.

Implements **decaf::util::Collection< E >** (p. 1192).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/StlSet.h`

6.776 activemq::wireformat::stomp::StompCommandConstants Class Reference

```
#include <src/main/activemq/wireformat/stomp/StompCommandConstants.h>
```

Static Public Attributes

- static const std::string **CONNECT**
- static const std::string **CONNECTED**
- static const std::string **DISCONNECT**
- static const std::string **SUBSCRIBE**
- static const std::string **UNSUBSCRIBE**
- static const std::string **MESSAGE**
- static const std::string **SEND**
- static const std::string **BEGIN**
- static const std::string **COMMIT**
- static const std::string **ABORT**
- static const std::string **ACK**
- static const std::string **ERROR_CMD**
- static const std::string **RECEIPT**
- static const std::string **HEADER_DESTINATION**
- static const std::string **HEADER_TRANSACTIONID**
- static const std::string **HEADER_CONTENTLENGTH**
- static const std::string **HEADER_SESSIONID**
- static const std::string **HEADER_RECEIPT_REQUIRED**
- static const std::string **HEADER_RECEIPTID**
- static const std::string **HEADER_MESSAGEID**
- static const std::string **HEADER_ACK**
- static const std::string **HEADER_LOGIN**
- static const std::string **HEADER_PASSWORD**
- static const std::string **HEADER_CLIENT_ID**
- static const std::string **HEADER_MESSAGE**
- static const std::string **HEADER_CORRELATIONID**
- static const std::string **HEADER_REQUESTID**
- static const std::string **HEADER_RESPONSEID**
- static const std::string **HEADER_EXPIRES**
- static const std::string **HEADER_PERSISTENT**
- static const std::string **HEADER_REPLYTO**
- static const std::string **HEADER_TYPE**
- static const std::string **HEADER_DISPATCH_ASYNC**
- static const std::string **HEADER_EXCLUSIVE**
- static const std::string **HEADER_MAXPENDINGMSGLIMIT**
- static const std::string **HEADER_NOLOCAL**
- static const std::string **HEADER_PREFETCHSIZE**
- static const std::string **HEADER_JMSPRIORITY**
- static const std::string **HEADER_CONSUMERPRIORITY**
- static const std::string **HEADER_RETROACTIVE**
- static const std::string **HEADER_SUBSCRIPTIONNAME**
- static const std::string **HEADER_OLDSUBSCRIPTIONNAME**

- static const std::string **HEADER_TIMESTAMP**
- static const std::string **HEADER_REDELIVERED**
- static const std::string **HEADER_REDELIVERYCOUNT**
- static const std::string **HEADER_SELECTOR**
- static const std::string **HEADER_ID**
- static const std::string **HEADER_SUBSCRIPTION**
- static const std::string **HEADER_TRANSFORMATION**
- static const std::string **HEADER_TRANSFORMATION_ERROR**
- static const std::string **ACK_CLIENT**
- static const std::string **ACK_AUTO**
- static const std::string **ACK_INDIVIDUAL**
- static const std::string **TEXT**
- static const std::string **BYTES**
- static const std::string **QUEUE_PREFIX**
- static const std::string **TOPIC_PREFIX**
- static const std::string **TEMPQUEUE_PREFIX**
- static const std::string **TEMPTOPIC_PREFIX**

6.776.1 Field Documentation

- 6.776.1.1** `const std::string activemq::wireformat::stomp::StompCommandConstants::ABORT`
[static]
- 6.776.1.2** `const std::string activemq::wireformat::stomp::StompCommandConstants::ACK`
[static]
- 6.776.1.3** `const std::string activemq::wireformat::stomp::StompCommandConstants::ACK_AUTO`
[static]
- 6.776.1.4** `const std::string activemq::wireformat::stomp::StompCommandConstants::ACK_CLIENT` [static]
- 6.776.1.5** `const std::string activemq::wireformat::stomp::StompCommandConstants::ACK_INDIVIDUAL` [static]
- 6.776.1.6** `const std::string activemq::wireformat::stomp::StompCommandConstants::BEGIN`
[static]
- 6.776.1.7** `const std::string activemq::wireformat::stomp::StompCommandConstants::BYTES`
[static]
- 6.776.1.8** `const std::string activemq::wireformat::stomp::StompCommandConstants::COMMIT`
[static]
- 6.776.1.9** `const std::string activemq::wireformat::stomp::StompCommandConstants::CONNECT`
[static]
- 6.776.1.10** `const std::string activemq::wireformat::stomp::StompCommandConstants::CONNECTED`
[static]
- 6.776.1.11** `const std::string activemq::wireformat::stomp::StompCommandConstants::DISCONNECT`
[static]
- 6.776.1.12** `const std::string activemq::wireformat::stomp::StompCommandConstants::ERROR_CMD` [static]
- 6.776.1.13** `const std::string activemq::wireformat::stomp::StompCommandConstants::HEADER_ACK` [static]
- 6.776.1.14** `const std::string activemq::wireformat::stomp::StompCommandConstants::HEADER_CLIENT_ID` [static]
- 6.776.1.15** `const std::string activemq::wireformat::stomp::StompCommandConstants::HEADER_CONSUMERPRIORITY` [static]

- `src/main/activemq/wireformat/stomp/StompCommandConstants.h`

6.777 activemq::wireformat::stomp::StompFrame Class Reference

A Stomp-level message frame that encloses all messages to and from the broker.

```
#include <src/main/activemq/wireformat/stomp/StompFrame.h>
```

Public Member Functions

- **StompFrame** ()
Default constructor.
- virtual **~StompFrame** ()
Destruction.
- **StompFrame * clone** () const
Clone this message exactly, returns a new instance that the caller is required to delete.
- void **copy** (const **StompFrame** *src)
Copies the contents of the passed Frame to this one.
- void **setCommand** (const std::string &cmd)
*Sets the command for this **stomp** (p. 139) frame.*
- const std::string & **getCommand** () const
Accessor for this frame's command field.
- bool **hasProperty** (const std::string &name) const
Checks if the given property is present in the Frame.
- std::string **getProperty** (const std::string &name, const std::string &fallback="") const
Gets a property from this Frame's properties and returns it, or the default value given.
- std::string **removeProperty** (const std::string &name)
Gets and remove the property specified, if the property is not set, this method returns the empty string.
- void **setProperty** (const std::string &name, const std::string &value)
Sets the property given to the value specified in this Frame's Properties.
- **decaf::util::Properties** & **getProperties** ()
Gets access to the header properties for this frame.
- const **decaf::util::Properties** & **getProperties** () const
- const std::vector< unsigned char > & **getBody** () const
Accessor for the body data of this frame.
- std::vector< unsigned char > & **getBody** ()
Non-const version of the body accessor.

- `std::size_t getBodyLength () const`
Return the number of bytes contained in this frames body.
- `void setBody (const unsigned char *bytes, std::size_t numBytes)`
Sets the body data of this frame as a byte sequence.
- `void toStream (decaf::io::DataOutputStream *stream) const throw (decaf::io::IOException)`
Writes this Frame to an OuputStream in the Stomp Wire Format.
- `void fromStream (decaf::io::DataInputStream *stream) throw (decaf::io::IOException)`
Reads a Stop Frame from a DataInputStream in the Stomp Wire format.

6.777.1 Detailed Description

A Stomp-level message frame that encloses all messages to and from the broker.

6.777.2 Constructor & Destructor Documentation

6.777.2.1 `activemq::wireformat::stomp::StompFrame::StompFrame () [inline]`

Default constructor.

6.777.2.2 `virtual activemq::wireformat::stomp::StompFrame::~~StompFrame () [inline, virtual]`

Destruction.

6.777.3 Member Function Documentation

6.777.3.1 `StompFrame* activemq::wireformat::stomp::StompFrame::clone () const`

Clone this message exactly, returns a new instance that the caller is required to delete.

Returns:

new copy of this message

6.777.3.2 `void activemq::wireformat::stomp::StompFrame::copy (const StompFrame * src)`

Copies the contents of the passed Frame to this one.

Parameters:

src - Frame to copy

6.777.3.3 void activemq::wireformat::stomp::StompFrame::fromStream
(decaf::io::DataInputStream * *stream*) throw (decaf::io::IOException)

Reads a Stop Frame from a DataInputStream in the Stomp Wire format.

Parameters:

stream - The stream to read the Frame from.

Exceptions:

IOException if an error occurs while writing the Frame.

6.777.3.4 std::vector<unsigned char>& activemq::wireformat::stomp::StompFrame::getBody ()
[inline]

Non-const version of the body accessor.

6.777.3.5 const std::vector<unsigned char>& activemq::wireformat::stomp::StompFrame::getBody () const
[inline]

Accessor for the body data of this frame.

Returns:

char pointer to body data

6.777.3.6 std::size_t activemq::wireformat::stomp::StompFrame::getBodyLength ()
const [inline]

Return the number of bytes contained in this frames body.

Returns:

Body bytes length.

6.777.3.7 const std::string& activemq::wireformat::stomp::StompFrame::getCommand ()
const [inline]

Accessor for this frame's command field.

6.777.3.8 const decaf::util::Properties& activemq::wireformat::stomp::StompFrame::getProperties ()
const [inline]

6.777.3.9 decaf::util::Properties& activemq::wireformat::stomp::StompFrame::getProperties ()
[inline]

Gets access to the header properties for this frame.

Returns:

the Properties object owned by this Frame

6.777.3.10 `std::string activemq::wireformat::stomp::StompFrame::getProperty
(const std::string & name, const std::string & fallback = "") const` `[inline]`

Gets a property from this Frame's properties and returns it, or the default value given.

Parameters:

name - The name of the property to lookup

fallback - The default value to return if this value isn't set

Returns:

string value of the property asked for.

6.777.3.11 `bool activemq::wireformat::stomp::StompFrame::hasProperty (const
std::string & name) const` `[inline]`

Checks if the given property is present in the Frame.

Parameters:

name - The name of the property to check for.

6.777.3.12 `std::string activemq::wireformat::stomp::StompFrame::removeProperty
(const std::string & name)` `[inline]`

Gets and remove the property specified, if the property is not set, this method returns the empty string.

Parameters:

name - the Name of the property to get and return.

6.777.3.13 `void activemq::wireformat::stomp::StompFrame::setBody (const
unsigned char * bytes, std::size_t numBytes)`

Sets the body data of this frame as a byte sequence.

Parameters:

bytes The byte buffer to be set in the body.

numBytes The number of bytes in the buffer.

6.777.3.14 void activemq::wireformat::stomp::StompFrame::setCommand (const std::string & *cmd*) [inline]

Sets the command for this **stomp** (p. 139) frame.

Parameters:

cmd command The command to be set.

6.777.3.15 void activemq::wireformat::stomp::StompFrame::setProperty (const std::string & *name*, const std::string & *value*) [inline]

Sets the property given to the value specified in this Frame's Properties.

Parameters:

name - Name of the property.

value - Value to set the property to.

6.777.3.16 void activemq::wireformat::stomp::StompFrame::toStream (decaf::io::DataOutputStream * *stream*) const throw (decaf::io::IOException)

Writes this Frame to an OuputStream in the Stomp Wire Format.

Parameters:

stream - The stream to write the Frame to.

Exceptions:

IOException if an error occurs while reading the Frame.

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/stomp/**StompFrame.h**

6.778 activemq::wireformat::stomp::StompHelper Class Reference

Utility Methods used when marshaling to and from StompFrame's.

```
#include <src/main/activemq/wireformat/stomp/StompHelper.h>
```

Public Member Functions

- **StompHelper** ()
- virtual **~StompHelper** ()
- void **convertProperties** (const **Pointer**< **StompFrame** > &frame, const **Pointer**< **Message** > &message)

Converts the Headers in a Stomp Frame into Headers in the given Message Command.
- void **convertProperties** (const **Pointer**< **Message** > &message, const **Pointer**< **StompFrame** > &frame)

*Converts the Properties in a Message Command to Valid Headers and Properties in the **StompFrame** (p. 3633).*
- **Pointer**< **ActiveMQDestination** > **convertDestination** (const std::string &destination)

Converts from a Stomp Destination to an ActiveMQDestination.
- std::string **convertDestination** (const **Pointer**< **ActiveMQDestination** > &destination)

Converts from a ActiveMQDestination to a Stomp Destination Name.
- std::string **convertMessageId** (const **Pointer**< **MessageId** > &messageId)

Converts a MessageId instance to a Stomp MessageId String.
- **Pointer**< **MessageId** > **convertMessageId** (const std::string &messageId)

Converts a Stomp MessageId string to a MessageId.
- std::string **convertConsumerId** (const **Pointer**< **ConsumerId** > &consumerId)

Converts a ConsumerId instance to a Stomp ConsumerId String.
- **Pointer**< **ConsumerId** > **convertConsumerId** (const std::string &consumerId)

Converts a Stomp ConsumerId string to a ConsumerId.
- std::string **convertProducerId** (const **Pointer**< **ProducerId** > &producerId)

Converts a ProducerId instance to a Stomp ProducerId String.
- **Pointer**< **ProducerId** > **convertProducerId** (const std::string &producerId)

Converts a Stomp ProducerId string to a ProducerId.
- std::string **convertTransactionId** (const **Pointer**< **TransactionId** > &transactionId)

Converts a TransactionId instance to a Stomp TransactionId String.
- **Pointer**< **TransactionId** > **convertTransactionId** (const std::string &transactionId)

Converts a Stomp TransactionId string to a TransactionId.

6.778.1 Detailed Description

Utility Methods used when marshaling to and from StompFrame's.

Since:

3.0

6.778.2 Constructor & Destructor Documentation

6.778.2.1 `activemq::wireformat::stomp::StompHelper::StompHelper ()` `[inline]`

6.778.2.2 `virtual activemq::wireformat::stomp::StompHelper::~~StompHelper ()`
`[inline, virtual]`

6.778.3 Member Function Documentation

6.778.3.1 `Pointer<ConsumerId> activemq::wireformat::stomp::StompHelper::convertConsumerId (const std::string & consumerId)`

Converts a Stomp ConsumerId string to a ConsumerId.

Parameters:

consumerId - the String Consumer Id to convert.

Returns:

Pointer to a new ConsumerId.

6.778.3.2 `std::string activemq::wireformat::stomp::StompHelper::convertConsumerId (const Pointer< ConsumerId > & consumerId)`

Converts a ConsumerId instance to a Stomp ConsumerId String.

Parameters:

consumerId - the Consumer instance to convert.

Returns:

a Stomp Consumer Id String.

6.778.3.3 `std::string activemq::wireformat::stomp::StompHelper::convertDestination (const Pointer< ActiveMQDestination > & destination)`

Converts from a ActiveMQDestination to a Stomp Destination Name.

Parameters:

destination - The ActiveMQDestination to Convert

Returns:

the Stomp String name that defines the destination.

6.778.3.4 `Pointer<ActiveMQDestination> activemq::wireformat::stomp::StompHelper::convertDestination (const std::string & destination)`

Converts from a Stomp Destination to an ActiveMQDestination.

Parameters:

destination - The Stomp Destination name string.

Returns:

Pointer to a new ActiveMQDestination.

6.778.3.5 `Pointer<MessageId> activemq::wireformat::stomp::StompHelper::convertMessageId (const std::string & messageId)`

Converts a Stomp MessageId string to a MessageId.

Parameters:

messageId - the String message Id to convert.

Returns:

Pointer to a new MessageId.

6.778.3.6 `std::string activemq::wireformat::stomp::StompHelper::convertMessageId (const Pointer< MessageId > & messageId)`

Converts a MessageId instance to a Stomp MessageId String.

Parameters:

messageId - the MessageId instance to convert.

Returns:

a Stomp Message Id String.

6.778.3.7 `Pointer<ProducerId> activemq::wireformat::stomp::StompHelper::convertProducerId (const std::string & producerId)`

Converts a Stomp ProducerId string to a ProducerId.

Parameters:

producerId - the String Producer Id to convert.

Returns:

Pointer to a new ProducerId.

6.778.3.8 `std::string activemq::wireformat::stomp::StompHelper::convertProducerId (const Pointer< ProducerId > & producerId)`

Converts a ProducerId instance to a Stomp ProducerId String.

Parameters:

producerId - the Producer instance to convert.

Returns:

a Stomp Producer Id String.

6.778.3.9 `void activemq::wireformat::stomp::StompHelper::convertProperties (const Pointer< Message > & message, const Pointer< StompFrame > & frame)`

Converts the Properties in a Message Command to Valid Headers and Properties in the **StompFrame** (p. 3633).

Parameters:

message - The message to move the Headers to.

frame - The frame to extract headers from.

6.778.3.10 `void activemq::wireformat::stomp::StompHelper::convertProperties (const Pointer< StompFrame > & frame, const Pointer< Message > & message)`

Converts the Headers in a Stomp Frame into Headers in the given Message Command.

Parameters:

frame - The frame to extract headers from.

message - The message to move the Headers to.

6.778.3.11 `Pointer<TransactionId> activemq::wireformat::stomp::StompHelper::convertTransactionId (const std::string & transactionId)`

Converts a Stomp TransactionId string to a TransactionId.

Parameters:

transactionId - the String Transaction Id to convert.

Returns:

Pointer to a new TransactionId.

6.778.3.12 `std::string activemq::wireformat::stomp::StompHelper::convertTransactionId (const Pointer< TransactionId > & transactionId)`

Converts a TransactionId instance to a Stomp TransactionId String.

Parameters:

transactionId - the Transaction instance to convert.

Returns:

a Stomp Transaction Id String.

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/stomp/StompHelper.h`

6.779 activemq::wireformat::stomp::StompWireFormat Class Reference

#include <src/main/activemq/wireformat/stomp/StompWireFormat.h> Inheritance diagram for activemq::wireformat::stomp::StompWireFormat:

Public Member Functions

- **StompWireFormat** ()
- virtual **~StompWireFormat** ()
- virtual void **marshal** (const **Pointer**< **commands::Command** > &command, const **activemq::transport::Transport** *transport, **decaf::io::DataOutputStream** *out) throw (**decaf::io::IOException**)

Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.

- virtual **Pointer**< **commands::Command** > **unmarshal** (const **activemq::transport::Transport** *transport, **decaf::io::DataInputStream** *in) throw (**decaf::io::IOException**)

Stream based un-marshaling, blocks on reads on the input stream until a complete command has been read and unmarshaled into the correct form.

- virtual void **setVersion** (int version **AMQCPP_UNUSED**)

Set the Version.

- virtual int **getVersion** () const

Get the Version.

- virtual bool **inReceive** () const

Is there a Message being unmarshaled?

- virtual bool **hasNegotiator** () const

*Returns true if this **WireFormat** (p. 3976) has a Negotiator that needs to wrap the Transport that uses it.*

- virtual **Pointer**< **transport::Transport** > **createNegotiator** (const **Pointer**< **transport::Transport** > &transport) throw (**decaf::lang::exceptions::UnsupportedOperationException**)

If the Transport Provides a Negotiator this method will create and return a news instance of the Negotiator.

6.779.1 Constructor & Destructor Documentation

6.779.1.1 `activemq::wireformat::stomp::StompWireFormat::StompWireFormat ()`

6.779.1.2 `virtual
activemq::wireformat::stomp::StompWireFormat::~~StompWireFormat ()
[virtual]`

6.779.2 Member Function Documentation

6.779.2.1 `virtual Pointer<transport::Transport> ac-
tivemq::wireformat::stomp::StompWireFormat::createNegotiator
(const Pointer< transport::Transport > & transport) throw (
decaf::lang::exceptions::UnsupportedOperationException) [virtual]`

If the Transport Provides a Negotiator this method will create and return a news instance of the Negotiator.

Returns:

new instance of a **WireFormatNegotiator** (p. 4016).

Exceptions:

UnsupportedOperationException if the **WireFormat** (p. 3976) doesn't have a Negotiator.

Implements **activemq::wireformat::WireFormat** (p. 3977).

6.779.2.2 `virtual int activemq::wireformat::stomp::StompWireFormat::getVersion
() const [inline, virtual]`

Get the Version.

Returns:

the version of the wire format

Implements **activemq::wireformat::WireFormat** (p. 3977).

6.779.2.3 `virtual bool ac-
tivemq::wireformat::stomp::StompWireFormat::hasNegotiator () const
[inline, virtual]`

Returns true if this **WireFormat** (p. 3976) has a Negotiator that needs to wrap the Transport that uses it.

Returns:

true if the **WireFormat** (p. 3976) provides a Negotiator.

Implements **activemq::wireformat::WireFormat** (p. 3977).

6.779.2.4 virtual bool activemq::wireformat::stomp::StompWireFormat::inReceive
() const [inline, virtual]

Is there a Message being unmarshaled?

Returns:

true while in the doUnmarshal method.

Implements **activemq::wireformat::WireFormat** (p. 3978).

6.779.2.5 virtual void activemq::wireformat::stomp::StompWireFormat::marshal
(const Pointer< commands::Command > & *command*, const
activemq::transport::Transport * *transport*, decaf::io::DataOutputStream
* *out*) throw (decaf::io::IOException) [virtual]

Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.

Parameters:

command The Command to Marshal to the output stream.

transport (p. 97) The Transport that initiated this marshal call.

out The output stream to write the command to.

Exceptions:

IOException

Implements **activemq::wireformat::WireFormat** (p. 3978).

6.779.2.6 virtual void activemq::wireformat::stomp::StompWireFormat::setVersion
(int version *AMQCPP_UNUSED*) [inline, virtual]

Set the Version.

Parameters:

the version of the wire format

Implements **activemq::wireformat::WireFormat** (p. 3978).

6.779.2.7 virtual Pointer<commands::Command> ac-
tivemq::wireformat::stomp::StompWireFormat::unmarshal
(const activemq::transport::Transport * *transport*,
decaf::io::DataInputStream * *in*) throw (decaf::io::IOException)
[virtual]

Stream based un-marshaling, blocks on reads on the input stream until a complete command has been read and unmarshaled into the correct form. Returns a Pointer to the newly unmarshaled Command.

Parameters:

transport (p. 97) - Pointer to the **transport** (p. 97) that is making this request.

in - the input stream to read the command from.

Returns:

the newly marshaled Command, caller owns the pointer

Exceptions:

IOException

Implements **activemq::wireformat::WireFormat** (p. 3979).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/stomp/StompWireFormat.h`

6.780 activemq::wireformat::stomp::StompWireFormatFactory Class Reference

Factory used to create the Stomp Wire Format instance.

#include <src/main/activemq/wireformat/stomp/StompWireFormatFactory.h> Inheritance diagram for activemq::wireformat::stomp::StompWireFormatFactory:

Public Member Functions

- **StompWireFormatFactory** ()
- virtual **~StompWireFormatFactory** ()
- virtual **Pointer< WireFormat > createWireFormat** (const **decaf::util::Properties** &properties) throw (**decaf::lang::exceptions::IllegalStateException**)
*Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.*

6.780.1 Detailed Description

Factory used to create the Stomp Wire Format instance.

6.780.2 Constructor & Destructor Documentation

6.780.2.1 **activemq::wireformat::stomp::StompWireFormatFactory::StompWireFormatFactory** () [inline]

6.780.2.2 **virtual**
activemq::wireformat::stomp::StompWireFormatFactory::~~StompWireFormatFactory () [inline, virtual]

6.780.3 Member Function Documentation

6.780.3.1 **virtual Pointer<WireFormat> activemq::wireformat::stomp::StompWireFormatFactory::createWireFormat** (const **decaf::util::Properties** & *properties*) throw (**decaf::lang::exceptions::IllegalStateException**) [virtual]

Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.

Parameters:

properties - the Properties for this **WireFormat** (p. 3976)

Implements **activemq::wireformat::WireFormatFactory** (p. 3980).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/stomp/**StompWireFormatFactory.h**

6.781 cms::Stoppable Class Reference

Interface for a class that implements the stop method.

#include <src/main/cms/Stoppable.h> Inheritance diagram for cms::Stoppable:

Public Member Functions

- virtual **~Stoppable** ()
- virtual void **stop** ()=0 throw (CMSEException)
Stops this service.

6.781.1 Detailed Description

Interface for a class that implements the stop method. An object that implements this interface implies that it will halt all operations that result in events being propagated to external users, internally the Object can continue to process data but not events will be generated to clients and methods that return data will not return valid results until the object is started again.

Since:

1.0

6.781.2 Constructor & Destructor Documentation

6.781.2.1 virtual cms::Stoppable::~~Stoppable () [inline, virtual]

6.781.3 Member Function Documentation

6.781.3.1 virtual void cms::Stoppable::stop () throw (CMSEException) [pure virtual]

Stops this service.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs while stopping the Service.

Implemented in **activemq::core::ActiveMQConnection** (p. 290).

The documentation for this class was generated from the following file:

- src/main/cms/**Stoppable.h**

6.782 decaf::util::logging::StreamHandler Class Reference

Stream based **logging** (p. 175) **Handler** (p. 1978).

#include <src/main/decaf/util/logging/StreamHandler.h> Inheritance diagram for decaf::util::logging::StreamHandler:

Public Member Functions

- **StreamHandler** ()
*Create a **StreamHandler** (p. 3649), with no current output stream.*
- **StreamHandler** (decaf::io::OutputStream *stream, Formatter *formatter)
*Create a **StreamHandler** (p. 3649), with no current output stream.*
- virtual ~**StreamHandler** ()
- virtual void **close** () throw (decaf::io::IOException)
Close the current output stream.
- virtual void **flush** ()
Flush the Handler's output, clears any buffers.
- virtual void **publish** (const **LogRecord** &record)
*Publish the Log Record to this **Handler** (p. 1978).*
- virtual bool **isLoggable** (const **LogRecord** &record) const
*Check if this **Handler** (p. 1978) would actually log a given **LogRecord** (p. 2413).*

Protected Member Functions

- virtual void **setOutputStream** (decaf::io::OutputStream *stream) throw (decaf::lang::exceptions::NullPointerException)
Change the output stream.
- void **close** (bool closeStream)
Closes this handler, but the underlying output stream is only closed if closeStream is true.

6.782.1 Detailed Description

Stream based **logging** (p. 175) **Handler** (p. 1978). This is primarily intended as a base class or support class to be used in implementing other **logging** (p. 175) Handlers.

LogRecords are published to a given decaf::io::OutputStream (p. 2907).

Configuration: By default each **StreamHandler** (p. 3649) is initialized using the following **Log-Manager** (p. 2406) configuration properties. If properties are not defined (or have invalid values) then the specified default values are used.

* `decaf.util.logging.StreamHandler.level` specifies the default level for the **Handler** (p.1978) (defaults to **Level.INFO** (p.2336)). * `decaf.util.logging.StreamHandler.filter` specifies the name of a **Filter** (p.1893) class to use (defaults to no **Filter** (p.1893)). * `decaf.util.logging.StreamHandler.formatter` specifies the name of a **Formatter** (p.1964) class to use (defaults to **decaf.util.logging.SimpleFormatter** (p.3500)).

Since:

1.0

6.782.2 Constructor & Destructor Documentation

6.782.2.1 `decaf::util::logging::StreamHandler::StreamHandler ()`

Create a **StreamHandler** (p.3649), with no current output stream.

6.782.2.2 `decaf::util::logging::StreamHandler::StreamHandler (decaf::io::OutputStream * stream, Formatter * formatter)`

Create a **StreamHandler** (p.3649), with no current output stream.

6.782.2.3 `virtual decaf::util::logging::StreamHandler::~~StreamHandler ()` [virtual]

6.782.3 Member Function Documentation

6.782.3.1 `void decaf::util::logging::StreamHandler::close (bool closeStream)` [protected]

Closes this handler, but the underlying output stream is only closed if `closeStream` is true.

Parameters:

closeStream whether to close the underlying output stream.

6.782.3.2 `virtual void decaf::util::logging::StreamHandler::close () throw (decaf::io::IOException)` [virtual]

Close the current output stream. The close method will perform a flush and then close the **Handler** (p.1978). After close has been called this **Handler** (p.1978) should no longer be used. Method calls may either be silently ignored or may throw runtime exceptions.

Exceptions:

IOException if an I/O error occurs.

Implements **decaf::io::Closeable** (p.1149).

Reimplemented in **decaf::util::logging::ConsoleHandler** (p.1399).

6.782.3.3 virtual void decaf::util::logging::StreamHandler::flush () [virtual]

Flush the Handler's output, clears any buffers.

Implements **decaf::util::logging::Handler** (p.1979).

6.782.3.4 virtual bool decaf::util::logging::StreamHandler::isLoggable (const LogRecord & *record*) const [virtual]

Check if this **Handler** (p.1978) would actually log a given **LogRecord** (p.2413).

Parameters:

record LogRecord (p.2413) to check

Returns:

true if the record can be logged with current settings.

Reimplemented from **decaf::util::logging::Handler** (p.1980).

6.782.3.5 virtual void decaf::util::logging::StreamHandler::publish (const LogRecord & *record*) [virtual]

Publish the Log Record to this **Handler** (p.1978).

Parameters:

record The LogRecord (p.2413) to Publish

Implements **decaf::util::logging::Handler** (p.1980).

Reimplemented in **decaf::util::logging::ConsoleHandler** (p.1400).

6.782.3.6 virtual void decaf::util::logging::StreamHandler::setOutputStream (decaf::io::OutputStream * *stream*) throw (decaf::lang::exceptions::NullPointerException) [protected, virtual]

Change the output stream. If there is a current output stream then the Formatter's tail string is written and the stream is flushed and closed. Then the output stream is replaced with the new output stream.

Parameters:

stream The new output stream. May not be NULL.

Exceptions:

NullPointerException if the passed stream is NULL.

The documentation for this class was generated from the following file:

- src/main/decaf/util/logging/**StreamHandler.h**

6.783 cms::StreamMessage Class Reference

Interface for a **StreamMessage** (p. 3652).

#include <src/main/cms/StreamMessage.h> Inheritance diagram for cms::StreamMessage:

Public Member Functions

- virtual **~StreamMessage** ()
- virtual bool **readBoolean** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Boolean from the Stream message stream.
- virtual void **writeBoolean** (bool value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a boolean to the Stream message stream as a 1-byte value.
- virtual unsigned char **readByte** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a Byte from the Stream message stream.
- virtual void **writeByte** (unsigned char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte to the Stream message stream as a 1-byte value.
- virtual int **readBytes** (std::vector< unsigned char > &value) const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a byte array from the Stream message stream.
- virtual void **writeBytes** (const std::vector< unsigned char > &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a byte array to the Stream message stream using the vector size as the number of bytes to write.
- virtual int **readBytes** (unsigned char *buffer, int length) const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)
Reads a portion of the Stream message stream.
- virtual void **writeBytes** (const unsigned char *value, int offset, int length)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)
Writes a portion of a byte array to the Stream message stream.
- virtual char **readChar** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a Char from the Stream message stream.

- virtual void **writeChar** (char value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a char to the Stream message stream as a 1-byte value.

- virtual float **readFloat** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 32 bit float from the Stream message stream.

- virtual void **writeFloat** (float value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a float to the Stream message stream as a 4 byte value.

- virtual double **readDouble** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 64 bit double from the Stream message stream.

- virtual void **writeDouble** (double value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a double to the Stream message stream as a 8 byte value.

- virtual short **readShort** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 16 bit signed short from the Stream message stream.

- virtual void **writeShort** (short value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a signed short to the Stream message stream as a 2 byte value.

- virtual unsigned short **readUnsignedShort** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 16 bit unsigned short from the Stream message stream.

- virtual void **writeUnsignedShort** (unsigned short value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a unsigned short to the Stream message stream as a 2 byte value.

- virtual int **readInt** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 32 bit signed integer from the Stream message stream.

- virtual void **writeInt** (int value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a signed int to the Stream message stream as a 4 byte value.

- virtual long long **readLong** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads a 64 bit long from the Stream message stream.

- virtual void **writeLong** (long long value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes a long long to the Stream message stream as a 8 byte value.

- virtual std::string **readString** () const =0 throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)

Reads an ASCII String from the Stream message stream.

- virtual void **writeString** (const std::string &value)=0 throw (cms::MessageNotWriteableException, cms::CMSEException)

Writes an ASCII String to the Stream message stream.

6.783.1 Detailed Description

Interface for a **StreamMessage** (p. 3652). The stream Messages provides a **Message** (p. 2534) type whose body is a stream of self describing primitive types. The primitive values are read and written using accessors specific to the given types.

StreamMessage (p. 3652) objects support the following conversion table. The marked cases must be supported. The unmarked cases must throw a **CMSEException** (p. 1160). The string-to-primitive conversions may throw a runtime exception if the primitive's `valueOf()` method does not accept it as a valid String representation of the primitive.

A value written as the row type can be read as the column type.

	boolean	byte	short	char	int	long	float	double	String	byte[]
boolean	X									X
byte		X	X		X	X				X
short			X		X	X				X
char				X						X
int					X	X				X
long						X				X
float							X	X		X
double								X		X
String	X	X	X		X	X	X	X	X	
byte[]										X

Since:

1.3

6.783.2 Constructor & Destructor Documentation

6.783.2.1 virtual cms::StreamMessage::~StreamMessage () [inline, virtual]

6.783.3 Member Function Documentation

6.783.3.1 virtual bool cms::StreamMessage::readBoolean () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]

Reads a Boolean from the Stream message stream.

Returns:

boolean value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 541).

6.783.3.2 virtual unsigned char cms::StreamMessage::readByte () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]

Reads a Byte from the Stream message stream.

Returns:

unsigned char value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 542).

6.783.3.3 `virtual int cms::StreamMessage::readBytes (unsigned char *
buffer, int length) const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [pure virtual]`

Reads a portion of the Stream message stream. If the length of array value is less than the number of bytes remaining to be read from the stream, the array should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of array value, the bytes should be read into the array. The return value of the total number of bytes read will be less than the length of the array, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

If length is negative, or length is greater than the length of the array value, then an **CMSException** (p. 1160) is thrown. No bytes will be read from the stream for this exception case.

Parameters:

buffer the buffer into which the data is read

length the number of bytes to read; must be less than or equal to value.length

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in **activemq::commands::ActiveMQStreamMessage** (p. 542).

6.783.3.4 `virtual int cms::StreamMessage::readBytes (std::vector< unsigned
char > & value) const throw (cms::MessageEOFException,
cms::MessageFormatException, cms::MessageNotReadableException,
cms::CMSException) [pure virtual]`

Reads a byte array from the Stream message stream. If the length of vector value is less than the number of bytes remaining to be read from the stream, the vector should be filled. A subsequent call reads the next increment, and so on.

If the number of bytes remaining in the stream is less than the length of vector value, the bytes should be read into the vector. The return value of the total number of bytes read will be less than the length of the vector, indicating that there are no more bytes left to be read from the stream. The next read of the stream returns -1.

Parameters:

value buffer to place data in

Returns:

the total number of bytes read into the buffer, or -1 if there is no more data because the end of the stream has been reached

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 543).

6.783.3.5 `virtual char cms::StreamMessage::readChar () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)` [pure virtual]

Reads a Char from the Stream message stream.

Returns:

char value from stream

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 543).

6.783.3.6 `virtual double cms::StreamMessage::readDouble () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException)` [pure virtual]

Reads a 64 bit double from the Stream message stream.

Returns:

double value from stream

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 544).

6.783.3.7 `virtual float cms::StreamMessage::readFloat () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)` [pure virtual]

Reads a 32 bit float from the Stream message stream.

Returns:

double value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 544).

6.783.3.8 `virtual int cms::StreamMessage::readInt () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException)` [pure virtual]

Reads a 32 bit signed integer from the Stream message stream.

Returns:

int value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 545).

6.783.3.9 `virtual long long cms::StreamMessage::readLong () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 64 bit long from the Stream message stream.

Returns:

long long value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 545).

6.783.3.10 `virtual short cms::StreamMessage::readShort () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads a 16 bit signed short from the Stream message stream.

Returns:

short value from stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 545).

6.783.3.11 `virtual std::string cms::StreamMessage::readString () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSException) [pure virtual]`

Reads an ASCII String from the Stream message stream.

Returns:

String from stream

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 546).

6.783.3.12 `virtual unsigned short cms::StreamMessage::readUnsignedShort () const throw (cms::MessageEOFException, cms::MessageFormatException, cms::MessageNotReadableException, cms::CMSEException) [pure virtual]`

Reads a 16 bit unsigned short from the Stream message stream.

Returns:

unsigned short value from stream

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to read the message due to some internal error.

MessageEOFException (p. 2661) - if unexpected end of message stream has been reached.

MessageFormatException (p. 2662) - if this type conversion is invalid.

MessageNotReadableException (p. 2723) - if the message is in write-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 546).

6.783.3.13 `virtual void cms::StreamMessage::writeBoolean (bool value) throw (cms::MessageNotWriteableException, cms::CMSEException) [pure virtual]`

Writes a boolean to the Stream message stream as a 1-byte value. The value true is written as the value (byte)1; the value false is written as the value (byte)0.

Parameters:

value boolean to write to the stream

Exceptions:

CMSEException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 547).

6.783.3.14 `virtual void cms::StreamMessage::writeByte (unsigned char value)
throw (cms::MessageNotWriteableException, cms::CMSException)
[pure virtual]`

Writes a byte to the Stream message stream as a 1-byte value.

Parameters:

value byte to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 547).

6.783.3.15 `virtual void cms::StreamMessage::writeBytes (const
unsigned char * value, int offset, int length) throw (
cms::MessageNotWriteableException, cms::CMSException) [pure
virtual]`

Writes a portion of a byte array to the Stream message stream. size as the number of bytes to write.

Parameters:

value bytes to write to the stream

offset the initial offset within the byte array

length the number of bytes to use

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 548).

6.783.3.16 `virtual void cms::StreamMessage::writeBytes (const std::vector<
unsigned char > & value) throw (cms::MessageNotWriteableException,
cms::CMSException) [pure virtual]`

Writes a byte array to the Stream message stream using the vector size as the number of bytes to write.

Parameters:

value bytes to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 548).

6.783.3.17 `virtual void cms::StreamMessage::writeChar (char value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a char to the Stream message stream as a 1-byte value.

Parameters:

value char to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 548).

6.783.3.18 `virtual void cms::StreamMessage::writeDouble (double value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a double to the Stream message stream as a 8 byte value.

Parameters:

value double to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 549).

6.783.3.19 `virtual void cms::StreamMessage::writeFloat (float value) throw (cms::MessageNotWriteableException, cms::CMSException) [pure virtual]`

Writes a float to the Stream message stream as a 4 byte value.

Parameters:

value float to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 549).

6.783.3.20 `virtual void cms::StreamMessage::writeInt (int value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a signed int to the Stream message stream as a 4 byte value.

Parameters:

value signed int to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 549).

6.783.3.21 `virtual void cms::StreamMessage::writeLong (long long value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a long long to the Stream message stream as a 8 byte value.

Parameters:

value signed long long to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 550).

6.783.3.22 `virtual void cms::StreamMessage::writeShort (short value) throw (cms::MessageNotWriteableException, cms::CMSException)` [pure virtual]

Writes a signed short to the Stream message stream as a 2 byte value.

Parameters:

value signed short to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 550).

6.783.3.23 `virtual void cms::StreamMessage::writeString (const std::string & value)
throw (cms::MessageNotWriteableException, cms::CMSException)
[pure virtual]`

Writes an ASCII String to the Stream message stream.

Parameters:

value String to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 550).

6.783.3.24 `virtual void cms::StreamMessage::writeUnsignedShort (unsigned
short value) throw (cms::MessageNotWriteableException,
cms::CMSException) [pure virtual]`

Writes a unsigned short to the Stream message stream as a 2 byte value.

Parameters:

value unsigned short to write to the stream

Exceptions:

CMSException (p. 1160) - if the CMS provider fails to write the message due to some internal error.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode.

Implemented in `activemq::commands::ActiveMQStreamMessage` (p. 551).

The documentation for this class was generated from the following file:

- `src/main/cms/StreamMessage.h`

6.784 decaf::lang::String Class Reference

The **String** (p. 3665) class represents an immutable sequence of chars.

#include <src/main/decaf/lang/String.h> Inheritance diagram for decaf::lang::String:

Public Member Functions

- **String** ()
*Creates a new empty **String** (p. 3665) object.*
- **String** (const std::string &source)
*Create a new **String** (p. 3665) object that represents the given STL string.*
- virtual ~**String** ()
- bool **isEmpty** () const
- virtual int **length** () const
Returns:
the length of the underlying character sequence.
- virtual char **charAt** (int index) const throw (lang::exceptions::IndexOutOfBoundsException)
Returns the Char at the specified index so long as the index is not greater than the length of the sequence.
Parameters:
index - position to return the char at.
Returns:
the char at the given position
Exceptions:
***IndexOutOfBoundsException** if index is > than **length()** (p. 1136) or negative*
- virtual **CharSequence** * **subSequence** (int start, int end) const throw (lang::exceptions::IndexOutOfBoundsException)
*Returns a new **CharSequence** (p. 1135) that is a subsequence of this sequence.
The subsequence starts with the char value at the specified index and ends with the char value at index end - 1. The length (in chars) of the returned sequence is end - start, so if start == end then an empty sequence is returned.*
Parameters:
*start - the start index, inclusive
end - the end index, exclusive*
Returns:
*a new **CharSequence** (p. 1135)*
Exceptions:
***IndexOutOfBoundsException** if start or end > **length()** (p. 1136) or start or end are negative.*
- virtual std::string **toString** () const

Returns:

*the string representation of this **CharSequence** (p. 1135)*

6.784.1 Detailed Description

The **String** (p. 3665) class represents an immutable sequence of chars.

Since:

1.0

6.784.2 Constructor & Destructor Documentation

6.784.2.1 **decaf::lang::String::String ()**

Creates a new empty **String** (p. 3665) object.

6.784.2.2 **decaf::lang::String::String (const std::string & source)**

Create a new **String** (p. 3665) object that represents the given STL string.

Parameters:

source The string to copy into this new **String** (p. 3665) object.

6.784.2.3 **virtual decaf::lang::String::~~String ()** [virtual]

6.784.3 Member Function Documentation

6.784.3.1 **virtual char decaf::lang::String::charAt (int index) const throw (lang::exceptions::IndexOutOfBoundsException)** [virtual]

Returns the Char at the specified index so long as the index is not greater than the length of the sequence.

Parameters:

index - position to return the char at.

Returns:

the char at the given position

Exceptions:

IndexOutOfBoundsException if index is > than **length()** (p. 1136) or negative

Implements **decaf::lang::CharSequence** (p. 1135).

6.784.3.2 `bool decaf::lang::String::isEmpty () const`**Returns:**

true if the length of this **String** (p. 3665) is zero.

6.784.3.3 `virtual int decaf::lang::String::length () const [virtual]`**Returns:**

the length of the underlying character sequence.

Implements **decaf::lang::CharSequence** (p. 1136).

6.784.3.4 `virtual CharSequence* decaf::lang::String::subSequence (int start, int end) const throw (lang::exceptions::IndexOutOfBoundsException) [virtual]`

Returns a new **CharSequence** (p. 1135) that is a subsequence of this sequence.

The subsequence starts with the char value at the specified index and ends with the char value at index *end* - 1. The length (in chars) of the returned sequence is *end* - *start*, so if *start* == *end* then an empty sequence is returned.

Parameters:

start - the start index, inclusive

end - the end index, exclusive

Returns:

a new **CharSequence** (p. 1135)

Exceptions:

IndexOutOfBoundsException if *start* or *end* > **length()** (p. 1136) or *start* or *end* are negative.

Implements **decaf::lang::CharSequence** (p. 1136).

6.784.3.5 `virtual std::string decaf::lang::String::toString () const [virtual]`**Returns:**

the string representation of this **CharSequence** (p. 1135)

Implements **decaf::lang::CharSequence** (p. 1136).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/String.h`

6.785 decaf::util::StringTokenizer Class Reference

```
#include <src/main/decaf/util/StringTokenizer.h>
```

Public Member Functions

- **StringTokenizer** (const std::string &str, const std::string &delim=" \t\n\r\f", bool returnDelims=false)
Constructs a string tokenizer for the specified string.
- virtual ~**StringTokenizer** ()
- virtual int **countTokens** () const
Calculates the number of times that this tokenizer's nextToken method can be called before it generates an exception.
- virtual bool **hasMoreTokens** () const
Tests if there are more tokens available from this tokenizer's string.
- virtual std::string **nextToken** () throw (lang::exceptions::NoSuchElementException)
Returns the next token from this string tokenizer.
- virtual std::string **nextToken** (const std::string &delim) throw (lang::exceptions::NoSuchElementException)
Returns the next token in this string tokenizer's string.
- virtual unsigned int **toArray** (std::vector< std::string > &array)
Grab all remaining tokens in the String and return them in the vector that is passed in by reference.
- virtual void **reset** (const std::string &str="", const std::string &delim="", bool returnDelims=false)
Resets the Tokenizer's position in the String to the Beginning calls to countToken and nextToken now start back at the beginning.

6.785.1 Constructor & Destructor Documentation

6.785.1.1 decaf::util::StringTokenizer::StringTokenizer (const std::string & str, const std::string & delim = " \t\n\r\f", bool returnDelims = false)

Constructs a string tokenizer for the specified string. All characters in the delim argument are the delimiters for separating tokens.

If the returnDelims flag is true, then the delimiter characters are also returned as tokens. Each delimiter is returned as a string of length one. If the flag is false, the delimiter characters are skipped and only serve as separators between tokens.

Note that if delim is "", this constructor does not throw an exception. However, trying to invoke other methods on the resulting **StringTokenizer** (p. 3668) may result in an Exception.

Parameters:

str - The string to tokenize

delim - String containing the delimiters

returnDelims - boolean indicating if the delimiters are returned as tokens

6.785.1.2 virtual decaf::util::StringTokenizer::~~StringTokenizer () [virtual]

6.785.2 Member Function Documentation

6.785.2.1 virtual int decaf::util::StringTokenizer::countTokens () const [virtual]

Calculates the number of times that this tokenizer's nextToken method can be called before it generates an exception. The current position is not advanced.

Returns:

Count of remaining tokens

6.785.2.2 virtual bool decaf::util::StringTokenizer::hasMoreTokens () const [virtual]

Tests if there are more tokens available from this tokenizer's string.

Returns:

true if there are more tokens remaining

6.785.2.3 virtual std::string decaf::util::StringTokenizer::nextToken (const std::string & *delim*) throw (lang::exceptions::NoSuchElementException) [virtual]

Returns the next token in this string tokenizer's string. First, the set of characters considered to be delimiters by this **StringTokenizer** (p. 3668) object is changed to be the characters in the string *delim*. Then the next token in the string after the current position is returned. The current position is advanced beyond the recognized token. The new delimiter set remains the default after this call.

Parameters:

delim - string containing the new set of delimiters

Returns:

next string in the token list

Exceptions:

NoSuchElementException

6.785.2.4 virtual std::string decaf::util::StringTokenizer::nextToken () throw (lang::exceptions::NoSuchElementException) [virtual]

Returns the next token from this string tokenizer.

Returns:

string value of next token

Exceptions:

NoSuchElementException

6.785.2.5 `virtual void decaf::util::StringTokenizer::reset (const std::string & str = "", const std::string & delim = "", bool returnDelims = false) [virtual]`

Resets the Tokenizer's position in the String to the Beginning calls to countToken and nextToken now start back at the beginning. This allows this object to be reused, the caller need not create a new instance every time a String needs tokenizing. If set the string param will reset the string that this Tokenizer is working on. If set to "" no change is made. If set the delim param will reset the string that this Tokenizer is using to tokenizer the string. If set to "", no change is made If set the return Delims will set if this Tokenizer will return delimiters as tokens. Defaults to false.

Parameters:

str - New String to tokenize or "", defaults to ""

delim - New Delimiter String to use or "", defaults to ""

returnDelims - Should the Tokenizer return delimiters as Tokens, default false

6.785.2.6 `virtual unsigned int decaf::util::StringTokenizer::toArray (std::vector< std::string > & array) [virtual]`

Grab all remaining tokens in the String and return them in the vector that is passed in by reference.

Parameters:

array - vector to place token strings in

Returns:

number of string placed into the vector

The documentation for this class was generated from the following file:

- src/main/decaf/util/**StringTokenizer.h**

6.786 activemq::commands::SubscriptionInfo Class Reference

#include <src/main/activemq/commands/SubscriptionInfo.h> Inheritance diagram for activemq::commands::SubscriptionInfo:

Public Member Functions

- **SubscriptionInfo** ()
- virtual **~SubscriptionInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **SubscriptionInfo * cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const std::string & **getClientId** () const
- virtual std::string & **getClientId** ()
- virtual void **setClientId** (const std::string &clientId)
- virtual const **Pointer**< **ActiveMQDestination** > & **getDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getDestination** ()
- virtual void **setDestination** (const **Pointer**< **ActiveMQDestination** > &destination)
- virtual const std::string & **getSelector** () const
- virtual std::string & **getSelector** ()
- virtual void **setSelector** (const std::string &selector)
- virtual const std::string & **getSubscriptionName** () const
- virtual std::string & **getSubscriptionName** ()
- virtual void **setSubscriptionName** (const std::string &subscriptionName)
- virtual const **Pointer**< **ActiveMQDestination** > & **getSubscribedDestination** () const
- virtual **Pointer**< **ActiveMQDestination** > & **getSubscribedDestination** ()
- virtual void **setSubscribedDestination** (const **Pointer**< **ActiveMQDestination** > &subscribedDestination)

Static Public Attributes

- static const unsigned char **ID_SUBSCRIPTIONINFO** = 55

Protected Attributes

- `std::string clientId`
- `Pointer< ActiveMQDestination > destination`
- `std::string selector`
- `std::string subscriptionName`
- `Pointer< ActiveMQDestination > subscribedDestination`

6.786.1 Constructor & Destructor Documentation

6.786.1.1 `activemq::commands::SubscriptionInfo::SubscriptionInfo ()`

6.786.1.2 `virtual activemq::commands::SubscriptionInfo::~~SubscriptionInfo ()`
[virtual]

6.786.2 Member Function Documentation

6.786.2.1 `virtual SubscriptionInfo* activemq::commands::SubscriptionInfo::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.786.2.2 `virtual void activemq::commands::SubscriptionInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

6.786.2.3 `virtual bool activemq::commands::SubscriptionInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

6.786.2.4 `virtual std::string& activemq::commands::SubscriptionInfo::getClientId () [virtual]`

6.786.2.5 `virtual const std::string& activemq::commands::SubscriptionInfo::getClientId () const [virtual]`

6.786.2.6 `virtual unsigned char activemq::commands::SubscriptionInfo::getDataStructureType () const [virtual]`

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

- 6.786.2.7 virtual Pointer<ActiveMQDestination>& activemq::commands::SubscriptionInfo::getDestination ()
[virtual]
- 6.786.2.8 virtual const Pointer<ActiveMQDestination>& activemq::commands::SubscriptionInfo::getDestination () const
[virtual]
- 6.786.2.9 virtual std::string& activemq::commands::SubscriptionInfo::getSelector ()
[virtual]
- 6.786.2.10 virtual const std::string& activemq::commands::SubscriptionInfo::getSelector () const
[virtual]
- 6.786.2.11 virtual std::string& activemq::commands::SubscriptionInfo::getSubscriptionName ()
[virtual]
- 6.786.2.12 virtual const std::string& activemq::commands::SubscriptionInfo::getSubscriptionName () const
[virtual]
- 6.786.2.13 virtual Pointer<ActiveMQDestination>& activemq::commands::SubscriptionInfo::getSubscribedDestination ()
[virtual]
- 6.786.2.14 virtual const Pointer<ActiveMQDestination>& activemq::commands::SubscriptionInfo::getSubscribedDestination () const
[virtual]
- 6.786.2.15 virtual void activemq::commands::SubscriptionInfo::setClientId (const std::string & *clientId*) [virtual]
- 6.786.2.16 virtual void activemq::commands::SubscriptionInfo::setDestination (const Pointer< ActiveMQDestination > & *destination*) [virtual]
- 6.786.2.17 virtual void activemq::commands::SubscriptionInfo::setSelector (const std::string & *selector*) [virtual]
- 6.786.2.18 virtual void activemq::commands::SubscriptionInfo::setSubscriptionName (const std::string & *subscriptionName*) [virtual]
- 6.786.2.19 virtual void activemq::commands::SubscriptionInfo::setSubscribedDestination (const Pointer< ActiveMQDestination > & *subscribedDestination*) [virtual]
- 6.786.2.20 virtual std::string activemq::commands::SubscriptionInfo::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseDataStructure` (p. 833).

6.786.3 Field Documentation

6.786.3.1 `std::string activemq::commands::SubscriptionInfo::clientId` [protected]

6.786.3.2 `Pointer<ActiveMQDestination> activemq::commands::SubscriptionInfo::destination`
[protected]

6.786.3.3 `const unsigned char activemq::commands::SubscriptionInfo::ID__ - SUBSCRIPTIONINFO = 55` [static]

6.786.3.4 `std::string activemq::commands::SubscriptionInfo::selector` [protected]

6.786.3.5 `std::string activemq::commands::SubscriptionInfo::subscriptionName`
[protected]

6.786.3.6 `Pointer<ActiveMQDestination> activemq::commands::SubscriptionInfo::subscribedDestination`
[protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/SubscriptionInfo.h`

6.787 activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3676).

#include <src/main/activemq/wireformat/openwire/marshal/v3/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.787.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3676).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.787.2 Constructor & Destructor Documentation

6.787.2.1 `activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` [inline]

6.787.2.2 `virtual activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` [inline, virtual]

6.787.3 Member Function Documentation

6.787.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.787.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.787.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.787.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.787.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.787.3.6 virtual void activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.787.3.7 virtual void activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/SubscriptionInfoMarshaller.h

6.788 activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3680).

#include <src/main/activemq/wireformat/openwire/marshal/v1/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.788.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3680).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.788.2 Constructor & Destructor Documentation

6.788.2.1 `activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` `[inline]`

6.788.2.2 `virtual activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` `[inline, virtual]`

6.788.3 Member Function Documentation

6.788.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.788.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.788.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.788.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - **BinaryReader** that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.788.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a **BooleanStream**.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - **BooleanStream** stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.788.3.6 virtual void activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.788.3.7 virtual void activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**SubscriptionInfoMarshaller.h**

6.789 activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3684).

#include <src/main/activemq/wireformat/openwire/marshal/v5/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.789.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3684).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.789.2 Constructor & Destructor Documentation

6.789.2.1 `activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` [inline]

6.789.2.2 `virtual activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` [inline, virtual]

6.789.3 Member Function Documentation

6.789.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.789.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.789.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.789.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.789.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.789.3.6 virtual void activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.789.3.7 virtual void activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**SubscriptionInfoMarshaller.h**

6.790 activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3688).

#include <src/main/activemq/wireformat/openwire/marshal/v4/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.790.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3688).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.790.2 Constructor & Destructor Documentation

6.790.2.1 `activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` [inline]

6.790.2.2 `virtual activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` [inline, virtual]

6.790.3 Member Function Documentation

6.790.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.790.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.790.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.790.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.790.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.790.3.6 virtual void activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.790.3.7 virtual void activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**SubscriptionInfoMarshaller.h**

6.791 activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3692).

#include <src/main/activemq/wireformat/openwire/marshal/v6/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.791.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3692).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.791.2 Constructor & Destructor Documentation

6.791.2.1 `activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` `[inline]`

6.791.2.2 `virtual activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` `[inline, virtual]`

6.791.3 Member Function Documentation

6.791.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.791.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.791.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.791.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.791.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.791.3.6 virtual void activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.791.3.7 virtual void activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**SubscriptionInfoMarshaller.h**

6.792 activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3696).

#include <src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller:

Public Member Functions

- **SubscriptionInfoMarshaller** ()
- virtual **~SubscriptionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.792.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3696).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.792.2 Constructor & Destructor Documentation

6.792.2.1 `activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::SubscriptionInfoMarshaller()` [inline]

6.792.2.2 `virtual activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::~~SubscriptionInfoMarshaller()` [inline, virtual]

6.792.3 Member Function Documentation

6.792.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.792.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.792.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.792.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::looseUnmarshal** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.792.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::tightMarshal1** (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.792.3.6 virtual void activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.792.3.7 virtual void activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h

6.793 decaf::util::concurrent::Synchronizable Class Reference

The interface for all synchronizable objects (that is, objects that can be locked and unlocked).

#include <src/main/decaf/util/concurrent/Synchronizable.h> Inheritance diagram for decaf::util::concurrent::Synchronizable:

Public Member Functions

- virtual **~Synchronizable** ()
- virtual void **lock** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** ()=0 throw (decaf::lang::exceptions::RuntimeException)
*Attempts to **Lock** (p. 2375) the object, if the lock is already held by another thread than this method returns false.*
- virtual void **unlock** ()=0 throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos)=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentOutOfRangeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** ()=0 throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

6.793.1 Detailed Description

The interface for all synchronizable objects (that is, objects that can be locked and unlocked).

Since:

1.0

6.793.2 Constructor & Destructor Documentation

6.793.2.1 virtual decaf::util::concurrent::Synchronizable::~~Synchronizable ()
[inline, virtual]

6.793.3 Member Function Documentation

6.793.3.1 virtual void decaf::util::concurrent::Synchronizable::lock () throw (
decaf::lang::exceptions::RuntimeException) [pure virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implemented in `activemq::core::MessageDispatchChannel` (p. 2602), `decaf::internal::util::concurrent::SynchronizableImpl` (p. 3712), `decaf::io::InputStream` (p. 2046), `decaf::io::OutputStream` (p. 2910), `decaf::util::AbstractCollection< E >` (p. 186), `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1241), `decaf::util::concurrent::Mutex` (p. 2783), `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3609), `decaf::util::StlQueue< T >` (p. 3619), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 186), `decaf::util::AbstractCollection< Pointer< Synchronization > >` (p. 186), `decaf::util::AbstractCollection< Resource * >` (p. 186), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 186), `decaf::util::AbstractCollection< CompositeTask * >` (p. 186), `decaf::util::AbstractCollection< URI >` (p. 186), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 186), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 186), `decaf::util::AbstractCollection< PrimitiveValueNode >` (p. 186), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 186), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 186), `decaf::util::AbstractCollection< cms::MessageProducer * >` (p. 186), `decaf::util::AbstractCollection< cms::Destination * >` (p. 186), `decaf::util::AbstractCollection< cms::Session * >` (p. 186), `decaf::util::AbstractCollection< cms::Connection * >` (p. 186), `decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR >` (p. 1241), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p. 1241), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p. 1241), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p. 1241), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p. 1241),

decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1241), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3609), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3609), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3609), decaf::util::StlMap< std::string, cms::Queue * > (p. 3609), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3609), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, TransportFactory * > (p. 3609), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< int, Pointer< Command > > (p. 3609), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3609), decaf::util::StlMap< std::string, CachedProducer * > (p. 3609), decaf::util::StlMap< std::string, cms::Topic * > (p. 3609), decaf::util::StlQueue< Pointer< Transport > > (p. 3619), decaf::util::StlQueue< Pointer< MessageDispatch > > (p. 3619), decaf::util::StlQueue< Task > (p. 3619), decaf::util::StlQueue< Pointer< Command > > (p. 3619), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > (p. 3619).

6.793.3.2 virtual void decaf::util::concurrent::Synchronizable::notify
 () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [pure virtual]

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implemented in **activemq::core::MessageDispatchChannel** (p. 2602), **decaf::internal::util::concurrent::SynchronizableImpl** (p. 3712), **decaf::io::InputStream** (p. 2047), **decaf::io::OutputStream** (p. 2910), **decaf::util::AbstractCollection< E >** (p. 186), **decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >** (p. 1241), **decaf::util::concurrent::Mutex** (p. 2783), **decaf::util::StlMap< K, V, COMPARATOR >** (p. 3610), **decaf::util::StlQueue< T >** (p. 3619), **decaf::util::AbstractCollection< transport::TransportListener * >** (p. 186), **decaf::util::AbstractCollection< Pointer< Synchronization > >** (p. 186), **decaf::util::AbstractCollection< Resource * >** (p. 186), **decaf::util::AbstractCollection< cms::MessageConsumer * >** (p. 186), **decaf::util::AbstractCollection< CompositeTask * >** (p. 186), **decaf::util::AbstractCollection< URI >** (p. 186), **decaf::util::AbstractCollection< ActiveMQSession * >** (p. 186), **decaf::util::AbstractCollection< Pointer< DestinationInfo > >** (p. 186), **decaf::util::AbstractCollection< PrimitiveValueNode >** (p. 186), **decaf::util::AbstractCollection< Pointer< Command > >** (p. 186), **decaf::util::AbstractCollection< Pointer< BackupTransport > >** (p. 186), **decaf::util::AbstractCollection< cms::MessageProducer * >** (p. 186), **decaf::util::AbstractCollection< cms::Destination * >** (p. 186), **decaf::util::AbstractCollection< cms::Session**

* > (p. 186), decaf::util::AbstractCollection< cms::Connection * > (p. 186), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1241), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3610), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3610), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3610), decaf::util::StlMap< std::string, cms::Queue * > (p. 3610), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3610), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, TransportFactory * > (p. 3610), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< int, Pointer< Command > > (p. 3610), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3610), decaf::util::StlMap< std::string, CachedProducer * > (p. 3610), decaf::util::StlMap< std::string, cms::Topic * > (p. 3610), decaf::util::StlQueue< Pointer< Transport > > (p. 3619), decaf::util::StlQueue< Pointer< MessageDispatch > > (p. 3619), decaf::util::StlQueue< Task > (p. 3619), decaf::util::StlQueue< Pointer< Command > > (p. 3619), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > (p. 3619).

6.793.3.3 virtual void decaf::util::concurrent::Synchronizable::notifyAll
 () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException) [pure virtual]

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implemented in activemq::core::MessageDispatchChannel (p. 2602), decaf::internal::util::concurrent::SynchronizableImpl (p. 3712), decaf::io::InputStream (p. 2047), decaf::io::OutputStream (p. 2911), decaf::util::AbstractCollection< E > (p. 187), decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1241), decaf::util::concurrent::Mutex (p. 2784), decaf::util::StlMap< K, V, COMPARATOR > (p. 3610), decaf::util::StlQueue< T > (p. 3619), decaf::util::AbstractCollection< transport::TransportListener

```

* > (p.187), decaf::util::AbstractCollection< Pointer< Synchroniza-
tion > > (p.187), decaf::util::AbstractCollection< Resource * >
(p.187), decaf::util::AbstractCollection< cms::MessageConsumer * >
(p.187), decaf::util::AbstractCollection< CompositeTask * > (p.187),
decaf::util::AbstractCollection< URI > (p.187), decaf::util::AbstractCollection<
ActiveMQSession * > (p.187), decaf::util::AbstractCollection< Pointer<
DestinationInfo > > (p.187), decaf::util::AbstractCollection< Prim-
itiveValueNode > > (p.187), decaf::util::AbstractCollection< Pointer<
Command > > (p.187), decaf::util::AbstractCollection< Pointer<
BackupTransport > > (p.187), decaf::util::AbstractCollection<
cms::MessageProducer * > (p.187), decaf::util::AbstractCollection<
cms::Destination * > (p.187), decaf::util::AbstractCollection< cms::Session
* > (p.187), decaf::util::AbstractCollection< cms::Connection * >
(p.187), decaf::util::concurrent::ConcurrentStlMap< Pointer< Mes-
sageId >, Pointer< Message >, MessageId::COMPARATOR >
(p.1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-
tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR
> (p.1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-
sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR
> (p.1241), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId
>, Pointer< SessionState >, SessionId::COMPARATOR > (p.1241),
decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >,
Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p.1241),
decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer<
ProducerState >, ProducerId::COMPARATOR > (p.1241), decaf::util::StlMap<
cms::Session *, SessionResolver * > (p.3610), decaf::util::StlMap< std::string,
WireFormatFactory * > (p.3610), decaf::util::StlMap< std::string, PrimitiveVal-
ueNode > (p.3610), decaf::util::StlMap< std::string, cms::Queue * > (p.3610),
decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com-
mands::ProducerId::COMPARATOR > (p.3610), decaf::util::StlMap< std::string,
CachedConsumer * > (p.3610), decaf::util::StlMap< Pointer< commands::ConsumerId
>, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p.3610),
decaf::util::StlMap< std::string, TransportFactory * > (p.3610), decaf::util::StlMap<
Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR
> (p.3610), decaf::util::StlMap< int, Pointer< Command > > (p.3610),
decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, com-
mands::ConsumerId::COMPARATOR > (p.3610), decaf::util::StlMap< std::string,
CachedProducer * > (p.3610), decaf::util::StlMap< std::string, cms::Topic
* > (p.3610), decaf::util::StlQueue< Pointer< Transport > > (p.3619),
decaf::util::StlQueue< Pointer< MessageDispatch > > (p.3619), decaf::util::StlQueue<
Task > (p.3619), decaf::util::StlQueue< Pointer< Command > > (p.3619), and
decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >
(p.3619).

```

6.793.3.4 virtual bool decaf::util::concurrent::Synchronizable::tryLock () throw (decaf::lang::exceptions::RuntimeException) [pure virtual]

Attempts to **Lock** (p.2375) the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implemented in `activemq::core::MessageDispatchChannel` (p. 2603), `decaf::internal::util::concurrent::SynchronizableImpl` (p. 3713), `decaf::io::InputStream` (p. 2051), `decaf::io::OutputStream` (p. 2911), `decaf::util::AbstractCollection< E >` (p. 189), `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1246), `decaf::util::concurrent::Mutex` (p. 2784), `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3612), `decaf::util::StlQueue< T >` (p. 3620), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 189), `decaf::util::AbstractCollection< Pointer< Synchroniza- tion > >` (p. 189), `decaf::util::AbstractCollection< Resource * >` (p. 189), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 189), `decaf::util::AbstractCollection< CompositeTask * >` (p. 189), `decaf::util::AbstractCollection< URI >` (p. 189), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 189), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 189), `decaf::util::AbstractCollection< Prim- itiveValueNode >` (p. 189), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 189), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 189), `decaf::util::AbstractCollection< cms::MessageProducer * >` (p. 189), `decaf::util::AbstractCollection< cms::Destination * >` (p. 189), `decaf::util::AbstractCollection< cms::Session * >` (p. 189), `decaf::util::AbstractCollection< cms::Connection * >` (p. 189), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Mes- sageId >, Pointer< Message >, MessageId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec- tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Con- sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p. 1246), `decaf::util::StlMap< cms::Session *, SessionResolver * >` (p. 3612), `decaf::util::StlMap< std::string, WireFormatFactory * >` (p. 3612), `decaf::util::StlMap< std::string, PrimitiveVal- ueNode >` (p. 3612), `decaf::util::StlMap< std::string, cms::Queue * >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com- mands::ProducerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, CachedConsumer * >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, TransportFactory * >` (p. 3612), `decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< int, Pointer< Command > >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, com- mands::ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, CachedProducer * >` (p. 3612), `decaf::util::StlMap< std::string, cms::Topic * >` (p. 3612), `decaf::util::StlQueue< Pointer< Transport > >` (p. 3620), `decaf::util::StlQueue< Pointer< MessageDispatch > >` (p. 3620), `decaf::util::StlQueue< Task >` (p. 3620), `decaf::util::StlQueue< Pointer< Command > >` (p. 3620), and `decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > >` (p. 3620).

6.793.3.5 virtual void decaf::util::concurrent::Synchronizable::unlock () throw (decaf::lang::exceptions::RuntimeException) [pure virtual]

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implemented in `activemq::core::MessageDispatchChannel` (p. 2604), `decaf::internal::util::concurrent::SynchronizableImpl` (p. 3713), `decaf::io::InputStream` (p. 2051), `decaf::io::OutputStream` (p. 2911), `decaf::util::AbstractCollection< E >` (p. 190), `decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >` (p. 1246), `decaf::util::concurrent::Mutex` (p. 2784), `decaf::util::StlMap< K, V, COMPARATOR >` (p. 3612), `decaf::util::StlQueue< T >` (p. 3621), `decaf::util::AbstractCollection< transport::TransportListener * >` (p. 190), `decaf::util::AbstractCollection< Pointer< Synchroniza-tion > >` (p. 190), `decaf::util::AbstractCollection< Resource * >` (p. 190), `decaf::util::AbstractCollection< cms::MessageConsumer * >` (p. 190), `decaf::util::AbstractCollection< CompositeTask * >` (p. 190), `decaf::util::AbstractCollection< URI >` (p. 190), `decaf::util::AbstractCollection< ActiveMQSession * >` (p. 190), `decaf::util::AbstractCollection< Pointer< DestinationInfo > >` (p. 190), `decaf::util::AbstractCollection< Prim-itiveValueNode >` (p. 190), `decaf::util::AbstractCollection< Pointer< Command > >` (p. 190), `decaf::util::AbstractCollection< Pointer< BackupTransport > >` (p. 190), `decaf::util::AbstractCollection< cms::MessageProducer * >` (p. 190), `decaf::util::AbstractCollection< cms::Destination * >` (p. 190), `decaf::util::AbstractCollection< cms::Session * >` (p. 190), `decaf::util::AbstractCollection< cms::Connection * >` (p. 190), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Mes-sageId >, Pointer< Message >, MessageId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec-tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< Con-sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >` (p. 1246), `decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >` (p. 1246), `decaf::util::StlMap< cms::Session *, SessionResolver * >` (p. 3612), `decaf::util::StlMap< std::string, WireFormatFactory * >` (p. 3612), `decaf::util::StlMap< std::string, PrimitiveVal-ueNode >` (p. 3612), `decaf::util::StlMap< std::string, cms::Queue * >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com-mands::ProducerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, CachedConsumer * >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, TransportFactory * >` (p. 3612), `decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< int, Pointer< Command > >` (p. 3612), `decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, com-mands::ConsumerId::COMPARATOR >` (p. 3612), `decaf::util::StlMap< std::string, CachedProducer * >` (p. 3612), `decaf::util::StlMap< std::string, cms::Topic`

* > (p. 3612), decaf::util::StlQueue< Pointer< Transport > > (p. 3621), decaf::util::StlQueue< Pointer< MessageDispatch > > (p. 3621), decaf::util::StlQueue< Task > (p. 3621), decaf::util::StlQueue< Pointer< Command > > (p. 3621), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > (p. 3621).

6.793.3.6 virtual void decaf::util::concurrent::Synchronizable::wait (long long *milliseconds*, int *nanos*) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [pure virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

milliseconds the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implemented in **activemq::core::MessageDispatchChannel** (p. 2604), **decaf::internal::util::concurrent::SynchronizableImpl** (p. 3713), **decaf::io::InputStream** (p. 2051), **decaf::io::OutputStream** (p. 2912), **decaf::util::AbstractCollection< E >** (p. 190), **decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >** (p. 1247), **decaf::util::concurrent::Mutex** (p. 2785), **decaf::util::StlMap< K, V, COMPARATOR >** (p. 3613), **decaf::util::StlQueue< T >** (p. 3621), **decaf::util::AbstractCollection< transport::TransportListener * >** (p. 190), **decaf::util::AbstractCollection< Pointer< Synchronization > >** (p. 190), **decaf::util::AbstractCollection< Resource * >** (p. 190), **decaf::util::AbstractCollection< cms::MessageConsumer * >** (p. 190), **decaf::util::AbstractCollection< CompositeTask * >** (p. 190), **decaf::util::AbstractCollection< URI >** (p. 190), **decaf::util::AbstractCollection< ActiveMQSession * >** (p. 190), **decaf::util::AbstractCollection< Pointer< DestinationInfo > >** (p. 190), **decaf::util::AbstractCollection< PrimitiveValueNode >** (p. 190), **decaf::util::AbstractCollection< Pointer< Command > >** (p. 190), **decaf::util::AbstractCollection< Pointer< BackupTransport > >** (p. 190), **decaf::util::AbstractCollection< cms::MessageProducer * >** (p. 190), **decaf::util::AbstractCollection<**

`cms::Destination * > (p. 190), decaf::util::AbstractCollection< cms::Session * > (p. 190), decaf::util::AbstractCollection< cms::Connection * > (p. 190), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > (p. 1247), decaf::util::StlMap< cms::Session *, SessionResolver * > (p. 3613), decaf::util::StlMap< std::string, WireFormatFactory * > (p. 3613), decaf::util::StlMap< std::string, PrimitiveValueNode > (p. 3613), decaf::util::StlMap< std::string, cms::Queue * > (p. 3613), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > (p. 3613), decaf::util::StlMap< std::string, CachedConsumer * > (p. 3613), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3613), decaf::util::StlMap< std::string, TransportFactory * > (p. 3613), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3613), decaf::util::StlMap< int, Pointer< Command > > (p. 3613), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3613), decaf::util::StlMap< std::string, CachedProducer * > (p. 3613), decaf::util::StlMap< std::string, cms::Topic * > (p. 3613), decaf::util::StlQueue< Pointer< Transport > > (p. 3621), decaf::util::StlQueue< Pointer< MessageDispatch > > (p. 3621), decaf::util::StlQueue< Task > (p. 3621), decaf::util::StlQueue< Pointer< Command > > (p. 3621), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > (p. 3621).`

6.793.3.7 `virtual void decaf::util::concurrent::Synchronizable::wait (long long milliseconds) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)` [pure virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

milliseconds the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implemented in `activemq::core::MessageDispatchChannel` (p. 2604), `decaf::internal::util::concurrent::SynchronizableImpl` (p. 3714), `decaf::io::InputStream`

(p. 2052), decaf::io::OutputStream (p. 2912), decaf::util::AbstractCollection< E > (p. 191), decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR > (p. 1247), decaf::util::concurrent::Mutex (p. 2785), decaf::util::StlMap< K, V, COMPARATOR > (p. 3613), decaf::util::StlQueue< T > (p. 3621), decaf::util::AbstractCollection< transport::TransportListener * > (p. 191), decaf::util::AbstractCollection< Pointer< Synchronization > > (p. 191), decaf::util::AbstractCollection< Resource * > (p. 191), decaf::util::AbstractCollection< cms::MessageConsumer * > (p. 191), decaf::util::AbstractCollection< CompositeTask * > (p. 191), decaf::util::AbstractCollection< URI > (p. 191), decaf::util::AbstractCollection< ActiveMQSession * > (p. 191), decaf::util::AbstractCollection< Pointer< DestinationInfo > > (p. 191), decaf::util::AbstractCollection< PrimitiveValueNode > > (p. 191), decaf::util::AbstractCollection< Pointer< Command > > (p. 191), decaf::util::AbstractCollection< Pointer< BackupTransport > > (p. 191), decaf::util::AbstractCollection< cms::MessageProducer * > > (p. 191), decaf::util::AbstractCollection< cms::Destination * > > (p. 191), decaf::util::AbstractCollection< cms::Session * > > (p. 191), decaf::util::AbstractCollection< cms::Connection * > > (p. 191), decaf::util::concurrent::ConcurrentStlMap< Pointer< MessageId >, Pointer< Message >, MessageId::COMPARATOR > > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConnectionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR > > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ConsumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR > > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR > > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR > > (p. 1247), decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR > > (p. 1247), decaf::util::StlMap< cms::Session *, SessionResolver * > > (p. 3613), decaf::util::StlMap< std::string, WireFormatFactory * > > (p. 3613), decaf::util::StlMap< std::string, PrimitiveValueNode > > (p. 3613), decaf::util::StlMap< std::string, cms::Queue * > > (p. 3613), decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, commands::ProducerId::COMPARATOR > > (p. 3613), decaf::util::StlMap< std::string, CachedConsumer * > > (p. 3613), decaf::util::StlMap< Pointer< commands::ConsumerId >, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > > (p. 3613), decaf::util::StlMap< std::string, TransportFactory * > > (p. 3613), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > > (p. 3613), decaf::util::StlMap< int, Pointer< Command > > > (p. 3613), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > > (p. 3613), decaf::util::StlMap< std::string, CachedProducer * > > (p. 3613), decaf::util::StlMap< std::string, cms::Topic * > > (p. 3613), decaf::util::StlQueue< Pointer< Transport > > > (p. 3621), decaf::util::StlQueue< Pointer< MessageDispatch > > > (p. 3621), decaf::util::StlQueue< Task > > > (p. 3621), decaf::util::StlQueue< Pointer< Command > > > (p. 3621), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > > (p. 3621).

6.793.3.8 virtual void decaf::util::concurrent::Synchronizable::wait
 () throw (decaf::lang::exceptions::RuntimeException,
 decaf::lang::exceptions::IllegalMonitorStateException,
 decaf::lang::exceptions::InterruptedException) [pure virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the **Synchronizable** (p. 3700) Object.

Implemented in **activemq::core::MessageDispatchChannel** (p. 2605), **decaf::internal::util::concurrent::SynchronizableImpl** (p. 3714), **decaf::io::InputStream** (p. 2052), **decaf::io::OutputStream** (p. 2913), **decaf::util::AbstractCollection< E >** (p. 191), **decaf::util::concurrent::ConcurrentStlMap< K, V, COMPARATOR >** (p. 1248), **decaf::util::concurrent::Mutex** (p. 2786), **decaf::util::StlMap< K, V, COMPARATOR >** (p. 3614), **decaf::util::StlQueue< T >** (p. 3622), **decaf::util::AbstractCollection< transport::TransportListener * >** (p. 191), **decaf::util::AbstractCollection< Pointer< Synchroniza- tion > >** (p. 191), **decaf::util::AbstractCollection< Resource * >** (p. 191), **decaf::util::AbstractCollection< cms::MessageConsumer * >** (p. 191), **decaf::util::AbstractCollection< CompositeTask * >** (p. 191), **decaf::util::AbstractCollection< URI >** (p. 191), **decaf::util::AbstractCollection< ActiveMQSession * >** (p. 191), **decaf::util::AbstractCollection< Pointer< DestinationInfo > >** (p. 191), **decaf::util::AbstractCollection< Prim- itiveValueNode >** (p. 191), **decaf::util::AbstractCollection< Pointer< Command > >** (p. 191), **decaf::util::AbstractCollection< Pointer< BackupTransport > >** (p. 191), **decaf::util::AbstractCollection< cms::MessageProducer * >** (p. 191), **decaf::util::AbstractCollection< cms::Destination * >** (p. 191), **decaf::util::AbstractCollection< cms::Session * >** (p. 191), **decaf::util::AbstractCollection< cms::Connection * >** (p. 191), **decaf::util::concurrent::ConcurrentStlMap< Pointer< Mes- sageId >, Pointer< Message >, MessageId::COMPARATOR >** (p. 1248), **decaf::util::concurrent::ConcurrentStlMap< Pointer< Connec- tionId >, Pointer< ConnectionState >, ConnectionId::COMPARATOR >** (p. 1248), **decaf::util::concurrent::ConcurrentStlMap< Pointer< Con- sumerId >, Pointer< ConsumerState >, ConsumerId::COMPARATOR >** (p. 1248), **decaf::util::concurrent::ConcurrentStlMap< Pointer< SessionId >, Pointer< SessionState >, SessionId::COMPARATOR >** (p. 1248), **decaf::util::concurrent::ConcurrentStlMap< Pointer< LocalTransactionId >, Pointer< TransactionState >, LocalTransactionId::COMPARATOR >** (p. 1248), **decaf::util::concurrent::ConcurrentStlMap< Pointer< ProducerId >, Pointer< ProducerState >, ProducerId::COMPARATOR >** (p. 1248), **decaf::util::StlMap< cms::Session *, SessionResolver * >** (p. 3614), **decaf::util::StlMap< std::string, WireFormatFactory * >** (p. 3614), **decaf::util::StlMap< std::string, PrimitiveVal- ueNode >** (p. 3614), **decaf::util::StlMap< std::string, cms::Queue * >** (p. 3614), **decaf::util::StlMap< Pointer< commands::ProducerId >, ActiveMQProducer *, com- mands::ProducerId::COMPARATOR >** (p. 3614), **decaf::util::StlMap< std::string, CachedConsumer * >** (p. 3614), **decaf::util::StlMap< Pointer< commands::ConsumerId**

>, ActiveMQConsumer *, commands::ConsumerId::COMPARATOR > (p. 3614), decaf::util::StlMap< std::string, TransportFactory * > (p. 3614), decaf::util::StlMap< Pointer< ConsumerId >, Pointer< ConsumerInfo >, ConsumerId::COMPARATOR > (p. 3614), decaf::util::StlMap< int, Pointer< Command > > (p. 3614), decaf::util::StlMap< Pointer< commands::ConsumerId >, Dispatcher *, commands::ConsumerId::COMPARATOR > (p. 3614), decaf::util::StlMap< std::string, CachedProducer * > (p. 3614), decaf::util::StlMap< std::string, cms::Topic * > (p. 3614), decaf::util::StlQueue< Pointer< Transport > > (p. 3622), decaf::util::StlQueue< Pointer< MessageDispatch > > (p. 3622), decaf::util::StlQueue< Task > (p. 3622), decaf::util::StlQueue< Pointer< Command > > (p. 3622), and decaf::util::StlQueue< decaf::lang::Pointer< commands::MessageDispatch > > (p. 3622).

The documentation for this class was generated from the following file:

- src/main/decaf/util/concurrent/**Synchronizable.h**

6.794 decaf::internal::util::concurrent::SynchronizableImpl Class Reference

A convenience class used by some Decaf classes to implement the Synchronizable interface when there is no issues related to multiple inheritance.

#include <src/main/decaf/internal/util/concurrent/SynchronizableImpl.h> Inheritance diagram for decaf::internal::util::concurrent::SynchronizableImpl:

Public Member Functions

- **SynchronizableImpl** ()
- virtual **~SynchronizableImpl** ()
- virtual void **lock** () throw (decaf::lang::exceptions::RuntimeException)
Locks the object.
- virtual bool **tryLock** () throw (decaf::lang::exceptions::RuntimeException)
Attempts to Lock the object, if the lock is already held by another thread than this method returns false.
- virtual void **unlock** () throw (decaf::lang::exceptions::RuntimeException)
Unlocks the object.
- virtual void **wait** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **wait** (long long millisecs, int nanos) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalArgumentOutOfRangeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException)
Waits on a signal from this object, which is generated by a call to Notify.
- virtual void **notify** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals a waiter on this object that it can now wake up and continue.
- virtual void **notifyAll** () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException)
Signals the waiters on this object that it can now wake up and continue.

6.794.1 Detailed Description

A convenience class used by some Decaf classes to implement the Synchronizable interface when there is no issues related to multiple inheritance.

Since:

1.0

6.794.2 Constructor & Destructor Documentation

6.794.2.1 decaf::internal::util::concurrent::SynchronizableImpl::SynchronizableImpl()
()

6.794.2.2 virtual
decaf::internal::util::concurrent::SynchronizableImpl::~SynchronizableImpl()
() [virtual]

6.794.3 Member Function Documentation

6.794.3.1 virtual void decaf::internal::util::concurrent::SynchronizableImpl::lock ()
throw (decaf::lang::exceptions::RuntimeException) [virtual]

Locks the object.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements decaf::util::concurrent::Synchronizable (p. 3701).

6.794.3.2 virtual void decaf::internal::util::concurrent::SynchronizableImpl::notify()
() throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [virtual]

Signals a waiter on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying one of the waiting threads.

Implements decaf::util::concurrent::Synchronizable (p. 3702).

6.794.3.3 virtual void decaf::internal::util::concurrent::SynchronizableImpl::notifyAll()
() throw (decaf::lang::exceptions::RuntimeException,
decaf::lang::exceptions::IllegalMonitorStateException) [virtual]

Signals the waiters on this object that it can now wake up and continue. Must have this object locked before calling.

Exceptions:

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

RuntimeException if an error occurs while notifying the waiting threads.

Implements **decaf::util::concurrent::Synchronizable** (p. 3703).

6.794.3.4 `virtual bool decaf::internal::util::concurrent::SynchronizableImpl::tryLock
() throw (decaf::lang::exceptions::RuntimeException) [virtual]`

Attempts to Lock the object, if the lock is already held by another thread than this method returns false.

Returns:

true if the lock was acquired, false if it is already held by another thread.

Exceptions:

RuntimeException if an error occurs while locking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3704).

6.794.3.5 `virtual void decaf::internal::util::concurrent::SynchronizableImpl::unlock
() throw (decaf::lang::exceptions::RuntimeException) [virtual]`

Unlocks the object.

Exceptions:

RuntimeException if an error occurs while unlocking the object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3705).

6.794.3.6 `virtual void decaf::internal::util::concurrent::SynchronizableImpl::wait
(long long millisecs, int nanos) throw (de-
caf::lang::exceptions::RuntimeException, de-
caf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalMonitorStateException,
decaf::lang::exceptions::InterruptedException) [virtual]`

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval. This method is similar to the one argument wait function except that it add a finer grained control over the amount of time that it waits by adding in the additional nanosecond argument.

NOTE: The ability to wait accurately at a nanosecond scale depends on the platform and OS that the Decaf API is running on, some systems do not provide an accurate enough clock to provide this level of granularity.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

nanos additional time in nanoseconds with a range of 0-999999

Exceptions:

IllegalArgumentException if an error occurs or the nanos argument is not in the range of [0-999999]

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3707).

6.794.3.7 virtual void decaf::internal::util::concurrent::SynchronizableImpl::wait (long long *millisecs*) throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling. This wait will timeout after the specified time interval.

Parameters:

millisecs the time in milliseconds to wait, or WAIT_INFINITE

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3708).

6.794.3.8 virtual void decaf::internal::util::concurrent::SynchronizableImpl::wait () throw (decaf::lang::exceptions::RuntimeException, decaf::lang::exceptions::IllegalMonitorStateException, decaf::lang::exceptions::InterruptedException) [virtual]

Waits on a signal from this object, which is generated by a call to Notify. Must have this object locked before calling.

Exceptions:

RuntimeException if an error occurs while waiting on the object.

InterruptedException if the wait is interrupted before it completes.

IllegalMonitorStateException - if the current thread is not the owner of the the Synchronizable Object.

Implements **decaf::util::concurrent::Synchronizable** (p. 3709).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/concurrent/**SynchronizableImpl.h**

6.795 activemq::core::Synchronization Class Reference

Transacted Object **Synchronization** (p. 3715), used to sync the events of a Transaction with the items in the Transaction.

```
#include <src/main/activemq/core/Synchronization.h>
```

Public Member Functions

- virtual **~Synchronization** ()
- virtual void **beforeEnd** ()=0 throw (exceptions::ActiveMQException)
- virtual void **afterCommit** ()=0 throw (exceptions::ActiveMQException)
- virtual void **afterRollback** ()=0 throw (exceptions::ActiveMQException)

6.795.1 Detailed Description

Transacted Object **Synchronization** (p. 3715), used to sync the events of a Transaction with the items in the Transaction.

6.795.2 Constructor & Destructor Documentation

6.795.2.1 virtual **activemq::core::Synchronization::~~Synchronization** () [inline, virtual]

6.795.3 Member Function Documentation

6.795.3.1 virtual void **activemq::core::Synchronization::afterCommit** () throw (exceptions::ActiveMQException) [pure virtual]

6.795.3.2 virtual void **activemq::core::Synchronization::afterRollback** () throw (exceptions::ActiveMQException) [pure virtual]

6.795.3.3 virtual void **activemq::core::Synchronization::beforeEnd** () throw (exceptions::ActiveMQException) [pure virtual]

The documentation for this class was generated from the following file:

- src/main/activemq/core/**Synchronization.h**

6.796 decaf::util::concurrent::SynchronousQueue< E > Class Template Reference

A **blocking queue** (p. 843) in which each insert operation must wait for a corresponding remove operation by another thread, and vice versa.

#include <src/main/decaf/util/concurrent/SynchronousQueue.h> Inheritance diagram for decaf::util::concurrent::SynchronousQueue< E >:

Data Structures

- class **EmptyIterator**

Public Member Functions

- **SynchronousQueue** ()
- virtual **~SynchronousQueue** ()
- virtual void **put** (const E &value) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Adds the specified element to this queue, waiting if necessary for another thread to receive it.
- virtual bool **offer** (const E &e, long timeout, const **TimeUnit** &unit) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into this queue, waiting if necessary up to the specified wait time for another thread to receive it.
- virtual bool **offer** (const E &value) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException)
Inserts the specified element into this queue, if another thread is waiting to receive it.
- virtual E **take** () throw (decaf::lang::exceptions::InterruptedException)
Retrieves and removes the head of this queue, waiting if necessary for another thread to insert it.
- virtual bool **poll** (E &result, long long timeout, const **TimeUnit** &unit) throw (decaf::lang::exceptions::InterruptedException)
Retrieves and removes the head of this queue, waiting if necessary up to the specified wait time, for another thread to insert it.
- virtual bool **poll** (E &result)
Retrieves and removes the head of this queue, if another thread is currently making an element available.
- virtual bool **equals** (const **Collection**< E > &value) const
*Answers true if this **Collection** (p. 1184) and the one given are the same size and if each element contained in the **Collection** (p. 1184) given is equal to an element contained in this collection.*

- virtual **decaf::util::Iterator**< E > * **iterator** ()
- virtual **decaf::util::Iterator**< E > * **iterator** () const
- virtual bool **isEmpty** () const
Returns true if this collection contains no elements.
- virtual std::size_t **size** () const
Returns the number of elements in this collection.
- virtual int **remainingCapacity** () const
*Returns the number of additional elements that this queue can ideally (in the absence of memory or resource constraints) accept without blocking, or **Integer::MAX_VALUE** if there is no intrinsic limit.*
- virtual void **clear** () throw (lang::exceptions::UnsupportedOperationException)
Removes all elements of the queue.
- virtual bool **contains** (const E &value DECAF_UNUSED) const throw (lang::Exception)
- virtual bool **containsAll** (const **Collection**< E > &collection) const throw (lang::Exception)
Returns true if this collection contains all of the elements in the specified collection.
- virtual bool **remove** (const E &value DECAF_UNUSED) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
- virtual bool **removeAll** (const **Collection**< E > &collection DECAF_UNUSED) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
- virtual bool **retainAll** (const **Collection**< E > &collection DECAF_UNUSED) throw (lang::exceptions::UnsupportedOperationException, lang::exceptions::IllegalArgumentException)
- virtual bool **peek** (E &result DECAF_UNUSED) const
- virtual std::vector< E > **toArray** () const
*Answers an STL vector containing copies of all elements contained in this **Collection** (p. 1184).*
- virtual std::size_t **drainTo** (**Collection**< E > &c) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException)
Removes all available elements from this queue and adds them to the given collection.
- virtual std::size_t **drainTo** (**Collection**< E > &c, std::size_t maxElements) throw (decaf::lang::exceptions::UnsupportedOperationException, decaf::lang::exceptions::IllegalArgumentException)
Removes at most the given number of available elements from this queue and adds them to the given collection.

6.796.1 Detailed Description

template<typename E> class decaf::util::concurrent::SynchronousQueue< E >

A **blocking queue** (p. 843) in which each insert operation must wait for a corresponding remove operation by another thread, and vice versa. A synchronous queue does not have any **internal**

(p. 144) capacity, not even a capacity of one. You cannot **peek** at a synchronous queue because an element is only present when you try to remove it; you cannot insert an element (using any method) unless another thread is trying to remove it; you cannot iterate as there is nothing to iterate. The *head* of the queue is the element that the first queued inserting thread is trying to add to the queue; if there is no such queued thread then no element is available for removal and **poll()** (p. 3722) will return **null**. For purposes of other **Collection** (p. 1184) methods (for example **contains**), a **SynchronousQueue** (p. 3716) acts as an empty collection. This queue does not permit **null** elements.

Synchronous queues are similar to rendezvous channels used in CSP and Ada. They are well suited for handoff designs, in which an object running in one thread must sync up with an object running in another thread in order to hand it some information, event, or task.

This class supports an optional fairness policy for ordering waiting producer and consumer threads. By default, this ordering is not guaranteed. However, a queue constructed with fairness set to **true** grants threads access in FIFO order.

This class and its iterator implement all of the *optional* methods of the **Collection** (p. 1184) and **Iterator** (p. 2154) interfaces.

Since:

1.0

6.796.2 Constructor & Destructor Documentation

6.796.2.1 `template<typename E> decaf::util::concurrent::SynchronousQueue< E >::SynchronousQueue () [inline]`

6.796.2.2 `template<typename E> virtual decaf::util::concurrent::SynchronousQueue< E >::~~SynchronousQueue () [inline, virtual]`

6.796.3 Member Function Documentation

6.796.3.1 `template<typename E> virtual void decaf::util::concurrent::SynchronousQueue< E >::clear () throw (lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Removes all elements of the queue. This implementation repeatedly invokes **poll** until it returns the empty marker.

Reimplemented from **decaf::util::AbstractQueue< E >** (p. 196).

6.796.3.2 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::contains
(const E &value DECAF_UNUSED) const throw (lang::Exception)
[inline, virtual]`

6.796.3.3 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E
>::containsAll (const Collection< E > & collection) const throw (
lang::Exception) [inline, virtual]`

Returns true if this collection contains all of the elements in the specified collection. This implementation iterates over the specified collection, checking each element returned by the iterator in turn to see if it's contained in this collection. If all elements are so contained true is returned, otherwise false.

Parameters:

collection collection to be checked for containment in this collection

Returns:

true if this collection contains all of the elements in the specified collection.

Exceptions:

Exception if an error occurs,

Reimplemented from `decaf::util::AbstractCollection< E >` (p.185).

6.796.3.4 `template<typename E > virtual std::size_t
decaf::util::concurrent::SynchronousQueue< E >::drainTo
(Collection< E > & c, std::size_t maxElements) throw
(decaf::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IllegalArgumentException) [inline, virtual]`

Removes at most the given number of available elements from this queue and adds them to the given collection. A failure encountered while attempting to add elements to collection *c* may result in elements being in neither, either or both collections when the associated exception is thrown. Attempts to drain a queue to itself result in `IllegalArgumentException`. Further, the behavior of this operation is undefined if the specified collection is modified while the operation is in progress.

Parameters:

c the collection to transfer elements into

maxElements the maximum number of elements to transfer

Returns:

the number of elements transferred

Exceptions:

UnsupportedOperationException if addition of elements is not supported by the specified collection

IllegalArgumentException if the specified collection is this queue, or some property of an element of this queue prevents it from being added to the specified collection

6.796 decaf::util::concurrent::SynchronousQueue< E > Class Template Reference 8723

Implements **decaf::util::concurrent::BlockingQueue< E >** (p. 846).

References **decaf::util::AbstractQueue< E >::element()**, and **decaf::util::concurrent::SynchronousQueue< E >::poll()**.

6.796.3.5 `template<typename E> virtual std::size_t
decaf::util::concurrent::SynchronousQueue< E >::drainTo (Collection< E
> & c) throw (decaf::lang::exceptions::UnsupportedOperationException,
decaf::lang::exceptions::IllegalArgumentException) [inline, virtual]`

Removes all available elements from this queue and adds them to the given collection. This operation may be more efficient than repeatedly polling this queue. A failure encountered while attempting to add elements to collection *c* may result in elements being in neither, either or both collections when the associated exception is thrown. Attempts to drain a queue to itself result in **IllegalArgumentException**. Further, the behavior of this operation is undefined if the specified collection is modified while the operation is in progress.

Parameters:

c the collection to transfer elements into

Returns:

the number of elements transferred

Exceptions:

UnsupportedOperationException if addition of elements is not supported by the specified collection

IllegalArgumentException if the specified collection is this queue, or some property of an element of this queue prevents it from being added to the specified collection

Implements **decaf::util::concurrent::BlockingQueue< E >** (p. 846).

References **decaf::util::AbstractQueue< E >::element()**, and **decaf::util::concurrent::SynchronousQueue< E >::poll()**.

6.796.3.6 `template<typename E> virtual bool
decaf::util::concurrent::SynchronousQueue< E >::equals
(const Collection< E > & collection) const [inline, virtual]`

Answers true if this **Collection** (p. 1184) and the one given are the same size and if each element contained in the **Collection** (p. 1184) given is equal to an element contained in this collection.

Parameters:

collection - The **Collection** (p. 1184) to be compared to this one.

Returns:

true if this **Collection** (p. 1184) is equal to the one given.

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 185).

6.796.3.7 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::isEmpty
() const [inline, virtual]`

Returns true if this collection contains no elements. This implementation returns `size()` (p. 3724) == 0.

Returns:

true if the size method return 0.

Reimplemented from `decaf::util::AbstractCollection< E >` (p. 186).

6.796.3.8 `template<typename E > virtual decaf::util::Iterator<E>*
decaf::util::concurrent::SynchronousQueue< E >::iterator () const
[inline, virtual]`

Implements `decaf::lang::Iterable< E >` (p. 2152).

6.796.3.9 `template<typename E > virtual decaf::util::Iterator<E>*
decaf::util::concurrent::SynchronousQueue< E >::iterator () [inline,
virtual]`

Returns:

an iterator over a set of elements of type T.

Implements `decaf::lang::Iterable< E >` (p. 2152).

6.796.3.10 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::offer
(const E & value) throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException) [inline, virtual]`

Inserts the specified element into this queue, if another thread is waiting to receive it.

Parameters:

value the element to add to the **Queue** (p. 3149)

Returns:

true if the element was added to this queue, else false

Exceptions:

NullPointerException if the **Queue** (p. 3149) implementation does not allow Null values to be inserted into the **Queue** (p. 3149).

IllegalArgumentException if some property of the specified element prevents it from being added to this queue

Implements `decaf::util::Queue< E >` (p. 3150).

6.796.3.11 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::offer
(const E & e, long timeout, const TimeUnit & unit)
throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::exceptions::NullPointerException, de-
caf::lang::exceptions::IllegalArgumentException) [inline,
virtual]`

Inserts the specified element into this queue, waiting if necessary up to the specified wait time for another thread to receive it.

Returns:

`true` if successful, or `false` if the specified waiting time elapses before a consumer appears.

Exceptions:

InterruptedException Inserts the specified element into this queue, waiting up to the specified wait time if necessary for space to become available.

NullPointerException Inserts the specified element into this queue, waiting up to the specified wait time if necessary for space to become available.

IllegalArgumentException Inserts the specified element into this queue, waiting up to the specified wait time if necessary for space to become available.

Implements `decaf::util::concurrent::BlockingQueue< E >` (p. 847).

6.796.3.12 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::peek (E
&result DECAF_UNUSED) const [inline, virtual]`

6.796.3.13 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::poll (E
& result) [inline, virtual]`

Retrieves and removes the head of this queue, if another thread is currently making an element available.

Parameters:

result a reference to the value where the head of the **Queue** (p. 3149) should be copied to.

Returns:

`true` if the head of the **Queue** (p. 3149) was copied to the result param or `false` if no value could be returned.

Implements `decaf::util::Queue< E >` (p. 3151).

6.796.3.14 `template<typename E > virtual bool
decaf::util::concurrent::SynchronousQueue< E >::poll (E
& result, long long timeout, const TimeUnit & unit) throw (
decaf::lang::exceptions::InterruptedException) [inline, virtual]`

Retrieves and removes the head of this queue, waiting if necessary up to the specified wait time, for another thread to insert it.

Parameters:

result a reference to the value where the head of the **Queue** (p. 3149) should be copied to.

timeout the time that the method should block if there is no element available to return.

unit the Time Units that the timeout value represents.

Returns:

true if the head of the **Queue** (p. 3149) was copied to the result param or false if no value could be returned.

Implements **decaf::util::concurrent::BlockingQueue< E >** (p. 847).

Referenced by **decaf::util::concurrent::SynchronousQueue< E >::drainTo()**.

```
6.796.3.15  template<typename E > virtual void
             decaf::util::concurrent::SynchronousQueue< E >::put
             (const E & value) throw ( decaf::lang::exceptions::InterruptedException,
             decaf::lang::exceptions::NullPointerException, de-
             ccaf::lang::exceptions::IllegalArgumentException ) [inline,
             virtual]
```

Adds the specified element to this queue, waiting if necessary for another thread to receive it.

Parameters:

value the element to add to the **Queue** (p. 3149).

Exceptions:

InterruptedException Inserts the specified element into this queue, waiting if necessary for space to become available.

NullPointerException Inserts the specified element into this queue, waiting if necessary for space to become available.

IllegalArgumentException Inserts the specified element into this queue, waiting if necessary for space to become available.

Implements **decaf::util::concurrent::BlockingQueue< E >** (p. 848).

```
6.796.3.16  template<typename E > virtual int
             decaf::util::concurrent::SynchronousQueue< E
             >::remainingCapacity () const [inline, virtual]
```

Returns the number of additional elements that this queue can ideally (in the absence of memory or resource constraints) accept without blocking, or **Integer::MAX_VALUE** if there is no intrinsic limit. Note that you *cannot* always tell if an attempt to insert an element will succeed by inspecting **remainingCapacity** because it may be the case that another thread is about to insert or remove an element.

Returns:

the remaining capacity

Implements **decaf::util::concurrent::BlockingQueue< E >** (p. 848).

- 6.796.3.17** `template<typename E> virtual bool
decaf::util::concurrent::SynchronousQueue< E >::remove
(const E &value DECAF_UNUSED) throw (
lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException) [inline, virtual]`
- 6.796.3.18** `template<typename E> virtual bool
decaf::util::concurrent::SynchronousQueue< E
>::removeAll (const Collection< E > &collection DECAF_UNUSED)
throw (lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException) [inline, virtual]`
- 6.796.3.19** `template<typename E> virtual bool
decaf::util::concurrent::SynchronousQueue< E
>::retainAll (const Collection< E > &collection DECAF_UNUSED)
throw (lang::exceptions::UnsupportedOperationException,
lang::exceptions::IllegalArgumentException) [inline, virtual]`
- 6.796.3.20** `template<typename E> virtual std::size_t
decaf::util::concurrent::SynchronousQueue< E >::size () const [inline,
virtual]`

Returns the number of elements in this collection. If this collection contains more than Integer.MAX_VALUE elements, returns Integer.MAX_VALUE.

Returns:

the number of elements in this collection

Implements `decaf::util::Collection< E >` (p. 1192).

- 6.796.3.21** `template<typename E> virtual E
decaf::util::concurrent::SynchronousQueue< E >::take ()
throw (decaf::lang::exceptions::InterruptedException) [inline,
virtual]`

Retrieves and removes the head of this queue, waiting if necessary for another thread to insert it.

Returns:

the head of this queue

Exceptions:

InterruptedException Retrieves and removes the head of this queue, waiting if necessary until an element becomes available.

Implements `decaf::util::concurrent::BlockingQueue< E >` (p. 849).

- 6.796.3.22** `template<typename E> virtual std::vector<E>
decaf::util::concurrent::SynchronousQueue< E >::toArray () const
[inline, virtual]`

Answers an STL vector containing copies of all elements contained in this **Collection** (p. 1184). All the elements in the array will not be referenced by the collection. The elements in the returned

array will be sorted to the same order as those returned by the iterator of this collection itself if the collection guarantees the order.

Returns:

an vector of copies of all the elements from this **Collection** (p. 1184)

Reimplemented from **decaf::util::AbstractCollection< E >** (p. 189).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/SynchronousQueue.h`

6.797 decaf::lang::System Class Reference

The **System** (p.3726) class provides static methods for accessing system level resources and performing some system dependent tasks such as looking up environment values and copying memory and arrays.

```
#include <src/main/decaf/lang/System.h>
```

Public Member Functions

- virtual **~System** ()

Static Public Member Functions

- static void **arraycopy** (const unsigned char *src, std::size_t srcPos, unsigned char *dest, std::size_t destPos, std::size_t length)
Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.
- static void **arraycopy** (const short *src, std::size_t srcPos, short *dest, std::size_t destPos, std::size_t length)
Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.
- static void **arraycopy** (const int *src, std::size_t srcPos, int *dest, std::size_t destPos, std::size_t length)
Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.
- static void **arraycopy** (const long long *src, std::size_t srcPos, long long *dest, std::size_t destPos, std::size_t length)
Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.
- static const **util::Map**< std::string, std::string > & **getenv** ()
Enumerates the system environment and returns a map of env variable names to the string values they hold.
- static std::string **getenv** (const std::string &name)
Reads an environment value from the system and returns it as a string object.
- static void **unsetenv** (const std::string &name)
Clears a set environment value if one is set.
- static void **setenv** (const std::string &name, const std::string &value)
Sets the specified system property to the value given.
- static long long **currentTimeMillis** ()

Returns the current time in milliseconds.

- static long long **nanoTime** ()

Returns the current value of the most precise available system timer, in nanoseconds.

- static int **availableProcessors** ()

Returns the number of processors available for execution of Decaf Threads.

- static **decaf::util::Properties** & **getProperties** ()

*Gets the Properties object that holds the Properties accessed from calls to **getProperty** and **setProperty**.*

- static std::string **getProperty** (const std::string &key)

*Gets the specified **System** (p. 3726) property if set, otherwise returns an empty string.*

- static std::string **getProperty** (const std::string &key, const std::string &defaultValue)

*Gets the specified **System** (p. 3726) property if set, otherwise returns the specified default value.*

- static std::string **setProperty** (const std::string &key, const std::string &value)

*Sets the **System** (p. 3726) Property to the specified value.*

- static std::string **clearProperty** (const std::string &key)

Clear any value associated with the system property specified.

Protected Member Functions

- **System** ()

Friends

- class **decaf::lang::Runtime**

6.797.1 Detailed Description

The **System** (p. 3726) class provides static methods for accessing system level resources and performing some system dependent tasks such as looking up environment values and copying memory and arrays.

Since:

1.0

6.797.2 Constructor & Destructor Documentation

6.797.2.1 decaf::lang::System::System () [protected]

6.797.2.2 virtual decaf::lang::System::~~System () [inline, virtual]

6.797.3 Member Function Documentation

6.797.3.1 static void decaf::lang::System::arraycopy (const long long * *src*, std::size_t *srcPos*, long long * *dest*, std::size_t *destPos*, std::size_t *length*) [static]

Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.

Parameters:

src The source array to copy from.

srcPos The position in the array to start copying from.

dest The destination array to copy to.

destPos The position in the destination array to start writing at.

length The number of elements to copy from src to dest.

Exceptions:

NullPointerException if src or dest are NULL.

6.797.3.2 static void decaf::lang::System::arraycopy (const int * *src*, std::size_t *srcPos*, int * *dest*, std::size_t *destPos*, std::size_t *length*) [static]

Copies the number of elements specified by length from the source array starting at the given source offset specified by srcPos to the dest array starting at the given destination offset given by destPos.

Parameters:

src The source array to copy from.

srcPos The position in the array to start copying from.

dest The destination array to copy to.

destPos The position in the destination array to start writing at.

length The number of elements to copy from src to dest.

Exceptions:

NullPointerException if src or dest are NULL.

6.797.3.3 `static void decaf::lang::System::arraycopy (const short * src, std::size_t srcPos, short * dest, std::size_t destPos, std::size_t length) [static]`

Copies the number of elements specified by *length* from the source array starting at the given source offset specified by *srcPos* to the dest array starting at the given destination offset given by *destPos*.

Parameters:

src The source array to copy from.
srcPos The position in the array to start copying from.
dest The destination array to copy to.
destPos The position in the destination array to start writing at.
length The number of elements to copy from *src* to *dest*.

Exceptions:

NullPointerException if *src* or *dest* are NULL.

6.797.3.4 `static void decaf::lang::System::arraycopy (const unsigned char * src, std::size_t srcPos, unsigned char * dest, std::size_t destPos, std::size_t length) [static]`

Copies the number of elements specified by *length* from the source array starting at the given source offset specified by *srcPos* to the dest array starting at the given destination offset given by *destPos*.

Parameters:

src The source array to copy from.
srcPos The position in the array to start copying from.
dest The destination array to copy to.
destPos The position in the destination array to start writing at.
length The number of elements to copy from *src* to *dest*.

Exceptions:

NullPointerException if *src* or *dest* are NULL.

Referenced by `decaf::lang::ArrayPointer< unsigned char >::clone()`.

6.797.3.5 `static int decaf::lang::System::availableProcessors () [static]`

Returns the number of processors available for execution of Decaf Threads. This value may change during a particular execution of a Decaf based application. Applications that are sensitive to the number of available processors should therefore occasionally poll this property and adjust their resource usage appropriately.

Returns:

the number of available processors.

6.797.3.6 static std::string decaf::lang::System::clearProperty (const std::string & *key*) [static]

Clear any value associated with the system property specified.

Parameters:

key The key name of the system property to clear.

Returns:

the previous value of the property named by key if there was one, otherwise returns an empty string.

Exceptions:

IllegalArgumentException if key is an empty string.

6.797.3.7 static long long decaf::lang::System::currentTimeMillis () [static]

Returns the current time in milliseconds. Note that while the unit of time of the return value is a millisecond, the granularity of the value depends on the underlying operating system and may be larger. For example, many operating systems measure time in units of tens of milliseconds.

See the description of the class Date for a discussion of slight discrepancies that may arise between "computer time" and coordinated universal time (UTC).

Returns:

the difference, measured in milliseconds, between the current time and midnight, January 1, 1970 UTC.

6.797.3.8 static std::string decaf::lang::System::getenv (const std::string & *name*) [static]

Reads an environment value from the system and returns it as a string object.

Parameters:

name The environment variable to read.

Returns:

a string with the value from the variables or ""

Exceptions:

an Exception (p. 1831) if an error occurs while reading the Env.

6.797.3.9 static const util::Map<std::string, std::string>& decaf::lang::System::getenv () [static]

Enumerates the system environment and returns a map of env variable names to the string values they hold.

Returns:

A Map of all environment variables.

Exceptions:

Exception (p. 1831) if an error occurs while getting the Environment Map.

6.797.3.10 `static decaf::util::Properties& decaf::lang::System::getProperties ()`
[static]

Gets the Properties object that holds the Properties accessed from calls to getProperty and setProperty. If the Properties has not yet been created or are not yet initialized then they will be on the first call to a Properties accessor.

Returns:

a reference to the static system Properties object.

6.797.3.11 `static std::string decaf::lang::System::getProperty (const std::string &key, const std::string & defaultValue)` [static]

Gets the specified **System** (p. 3726) property if set, otherwise returns the specified default value. If the Properties has not yet been created or are not yet initialized then they will be on the first call to a Properties accessor.

Parameters:

key The key name of the desired system property to retrieve.

defaultValue The default value to return if the key is not set in the **System** (p. 3726) properties.

Returns:

the value of the named system property or the defaultValue if the property isn't set..

Exceptions:

IllegalArgumentException if key is an empty string.

6.797.3.12 `static std::string decaf::lang::System::getProperty (const std::string &key)` [static]

Gets the specified **System** (p. 3726) property if set, otherwise returns an empty string. If the Properties has not yet been created or are not yet initialized then they will be on the first call to a Properties accessor.

Parameters:

key The key name of the desired system property to retrieve.

Returns:

an empty string if the named property is not set, otherwise returns the value.

Exceptions:

IllegalArgumentException if key is an empty string.

6.797.3.13 static long long decaf::lang::System::nanoTime () [static]

Returns the current value of the most precise available system timer, in nanoseconds. This method can only be used to measure elapsed time and is not related to any other notion of system or wall-clock time. The value returned represents nanoseconds since some fixed but arbitrary time (perhaps in the future, so values may be negative). This method provides nanosecond precision, but not necessarily nanosecond accuracy. No guarantees are made about how frequently values change. Differences in successive calls that span greater than approximately 292 years (263 nanoseconds) will not accurately compute elapsed time due to numerical overflow.

For example, to measure how long some **code** (p. 1183) takes to execute:

```
long long startTime = System::nanoTime() (p. 3732); // ... the code (p. 1183) being measured
... long long estimatedTime = System::nanoTime() (p. 3732) - startTime;
```

Returns:

The current value of the system timer, in nanoseconds.

6.797.3.14 static void decaf::lang::System::setenv (const std::string & name, const std::string & value) [static]

Sets the specified system property to the value given.

Parameters:

name The name of the environment variables to set.

value The value to assign to name.

Exceptions:

an Exception (p. 1831) if an error occurs when setting the environment variable.

6.797.3.15 static std::string decaf::lang::System::setProperty (const std::string & key, const std::string & value) [static]

Sets the **System** (p. 3726) Property to the specified value.

Parameters:

key The key name of the system property to set to the given value.

value The value to assign to the key.

Returns:

the previous value of the property named by key if there was one, otherwise returns an empty string.

Exceptions:

IllegalArgumentException if key is an empty string.

6.797.3.16 `static void decaf::lang::System::unsetenv (const std::string & name)`
 `[static]`

Clears a set environment value if one is set.

Parameters:

name The environment variables to clear.

Exceptions:

an Exception (p. 1831) if an error occurs while reading the environment.

6.797.4 Friends And Related Function Documentation

6.797.4.1 `friend class decaf::lang::Runtime` `[friend]`

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/System.h`

6.798 activemq::threads::Task Class Reference

Represents a unit of work that requires one or more iterations to complete.

#include <src/main/activemq/threads/Task.h> Inheritance diagram for activemq::threads::Task:

Public Member Functions

- virtual `~Task ()`
- virtual bool `iterate ()=0`

Perform one iteration of work, returns true if the task needs to run again to complete or false to indicate that the task is now complete.

6.798.1 Detailed Description

Represents a unit of work that requires one or more iterations to complete.

Since:

3.0

6.798.2 Constructor & Destructor Documentation

6.798.2.1 virtual `activemq::threads::Task::~~Task ()` [inline, virtual]

6.798.3 Member Function Documentation

6.798.3.1 virtual bool `activemq::threads::Task::iterate ()` [pure virtual]

Perform one iteration of work, returns true if the task needs to run again to complete or false to indicate that the task is now complete.

Returns:

true if the task should be run again or false if the task has completed and the runner should wait for a wakeup call.

Implemented in `activemq::core::ActiveMQSessionExecutor` (p. 535), `activemq::threads::CompositeTaskRunner` (p. 1224), `activemq::transport::failover::BackupTransportPool` (p. 757), `activemq::transport::failover::CloseTransportsTask` (p. 1152), and `activemq::transport::failover::FailoverTransport` (p. 1879).

The documentation for this class was generated from the following file:

- `src/main/activemq/threads/Task.h`

6.799 decaf::util::concurrent::TaskListener Class Reference

```
#include <src/main/decaf/util/concurrent/TaskListener.h>
```

Public Member Functions

- virtual `~TaskListener ()`
- virtual void `onTaskComplete (lang::Runnable *task)=0`
Called when a queued task has completed, the task that finished is passed along for user consumption.
- virtual void `onTaskException (lang::Runnable *task, lang::Exception &ex)=0`
Called when a queued task has thrown an exception while being run.

6.799.1 Constructor & Destructor Documentation

- 6.799.1.1** virtual `decaf::util::concurrent::TaskListener::~~TaskListener ()` [inline, virtual]

6.799.2 Member Function Documentation

- 6.799.2.1** virtual void `decaf::util::concurrent::TaskListener::onTaskComplete (lang::Runnable * task)` [pure virtual]

Called when a queued task has completed, the task that finished is passed along for user consumption.

Parameters:

task Runnable Pointer to the task that finished

- 6.799.2.2** virtual void `decaf::util::concurrent::TaskListener::onTaskException (lang::Runnable * task, lang::Exception & ex)` [pure virtual]

Called when a queued task has thrown an exception while being run. The Callee should assume that this was an unrecoverable exception and that this task is now defunct.

Parameters:

task Runnable Pointer to the task

ex The ActiveMQException that was thrown.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/TaskListener.h`

6.800 activemq::threads::TaskRunner Class Reference

#include <src/main/activemq/threads/TaskRunner.h> Inheritance diagram for activemq::threads::TaskRunner:

Public Member Functions

- virtual `~TaskRunner ()`
- virtual void `shutdown (unsigned int timeout)=0`
Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.
- virtual void `shutdown ()=0`
Shutdown once the task has finished and the TaskRunner's thread has exited.
- virtual void `wakeup ()=0`
*Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.*

6.800.1 Constructor & Destructor Documentation

6.800.1.1 virtual `activemq::threads::TaskRunner::~~TaskRunner ()` [inline, virtual]

6.800.2 Member Function Documentation

6.800.2.1 virtual void `activemq::threads::TaskRunner::shutdown ()` [pure virtual]

Shutdown once the task has finished and the TaskRunner's thread has exited.

Implemented in `activemq::threads::CompositeTaskRunner` (p. 1224), and `activemq::threads::DedicatedTaskRunner` (p. 1672).

6.800.2.2 virtual void `activemq::threads::TaskRunner::shutdown (unsigned int timeout)` [pure virtual]

Shutdown after a timeout, does not guarantee that the task's iterate method has completed and the thread halted.

Parameters:

timeout - Time in Milliseconds to wait for the task to stop.

Implemented in `activemq::threads::CompositeTaskRunner` (p. 1225), and `activemq::threads::DedicatedTaskRunner` (p. 1672).

6.800.2.3 virtual void activemq::threads::TaskRunner::wakeup () [pure virtual]

Signal the **TaskRunner** (p. 3736) to wakeup and execute another iteration cycle on the task, the **Task** (p. 3734) instance will be run until its iterate method has returned false indicating it is done.

Implemented in **activemq::threads::CompositeTaskRunner** (p. 1225), and **activemq::threads::DedicatedTaskRunner** (p. 1672).

The documentation for this class was generated from the following file:

- src/main/activemq/threads/**TaskRunner.h**

6.801 decaf::internal::net::tcp::TcpSocket Class Reference

Platform-independent implementation of the socket interface.

#include <src/main/decaf/internal/net/tcp/TcpSocket.h> Inheritance diagram for decaf::internal::net::tcp::TcpSocket:

Public Member Functions

- **TcpSocket** () throw (decaf::net::SocketException)
Construct a non-connected socket.
- virtual ~**TcpSocket** ()
Releases the socket handle but not gracefully shut down the connection.
- SocketHandle **getSocketHandle** ()
Gets the handle for the socket.
- bool **isConnected** () const
- bool **isClosed** () const
- virtual std::string **getLocalAddress** () const
*Gets the value of the local Inet address the **Socket** (p. 3503) is bound to if bound, otherwise return the **InetAddress** (p. 2016) ANY value "0.0.0.0".*
Returns:
the local address bound to, or ANY.
- virtual void **create** () throw (decaf::io::IOException)
*Creates the underlying platform **Socket** (p. 3503) data structures which allows for **Socket** (p. 3503) options to be applied.*
The created socket is in an unconnected state.
Exceptions:
***IOException** if an I/O error occurs while attempting this operation.*
- virtual void **accept** (SocketImpl *socket) throw (decaf::io::IOException)
- virtual void **bind** (const std::string &ipaddress, int **port**) throw (decaf::io::IOException)
*Binds this **Socket** (p. 3503) instance to the local ip address and port number given.*
Parameters:
***ipaddress** The address of local ip to bind to.*
***port** The port number on the host to bind to.*
Exceptions:
***IOException** if an I/O error occurs while attempting this operation.*
- virtual void **connect** (const std::string &hostname, int **port**, int timeout) throw (decaf::io::IOException, decaf::net::SocketException, decaf::lang::exceptions::IllegalArgumentException)
Connects this socket to the given host and port.

Parameters:

hostname The name of the host to connect to, or IP address.
port The port number on the host to connect to.
timeout Time in milliseconds to wait for a connection, 0 indicates forever.

Exceptions:

IOException if an I/O error occurs while attempting this operation.
SocketTimeoutException (p. 3542) if the connect call times out due to timeout being
^{set.}
IllegalArgumentException if a parameter has an illegal value.

- virtual void **listen** (int backlog) throw (decaf::io::IOException)

Sets the maximum queue length for incoming connection indications (a request to connect) to the count argument.

If a connection indication arrives when the queue is full, the connection is refused.

Parameters:

backlog The maximum length of the connection queue.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

- virtual decaf::io::InputStream * **getInputStream** () throw (decaf::io::IOException)

Gets the InputStream linked to this **Socket** (p. 3503).

Returns:

an InputStream pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

- virtual decaf::io::OutputStream * **getOutputStream** () throw (decaf::io::IOException)

Gets the OutputStream linked to this **Socket** (p. 3503).

Returns:

an OutputStream pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

- virtual int **available** () throw (decaf::io::IOException)

Gets the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Returns:

the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

- virtual void **close** () throw (decaf::io::IOException)

Closes the socket, terminating any blocked reads or writes.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

- virtual void **shutdownInput** () throw (decaf::io::IOException)

Places the input stream for this socket at "end of stream".

*Any data sent to this socket is acknowledged and then silently discarded. If you read from a socket input stream after invoking **shutdownInput()** (p. 3535) on the socket, the stream will return *EOF*.*

Exceptions:

***IOException** if an I/O error occurs while attempting this operation.*

- virtual void **shutdownOutput** () throw (decaf::io::IOException)

Disables the output stream for this socket.

*For a TCP socket, any previously written data will be sent followed by TCP's normal connection termination sequence. If you write to a socket output stream after invoking **shutdownOutput()** (p. 3536) on the socket, the stream will throw an **IOException**.*

Exceptions:

***IOException** if an I/O error occurs while attempting this operation.*

- virtual int **getOption** (int option) const throw (decaf::io::IOException)

*Gets the specified **Socket** (p. 3503) option.*

Parameters:

***option** The **Socket** (p. 3503) options whose value is to be retrieved.*

Returns:

the value of the given socket option.

Exceptions:

***IOException** if an I/O error occurs while performing this operation.*

- virtual void **setOption** (int option, int value) throw (decaf::io::IOException)

*Sets the specified option on the **Socket** (p. 3503) if supported.*

Parameters:

***option** The **Socket** (p. 3503) option to set.*

***value** The value of the socket option to apply to the socket.*

Exceptions:

***IOException** if an I/O error occurs while performing this operation.*

- int **read** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

*Reads the requested data from the **Socket** and write it into the passed in buffer.*

- void **write** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

*Writes the specified data in the passed in buffer to the **Socket**.*

Protected Member Functions

- void **checkResult** (apr_status_t value) const throw (decaf::net::SocketException)

6.801.1 Detailed Description

Platform-independent implementation of the socket interface.

6.801.2 Constructor & Destructor Documentation

6.801.2.1 `decaf::internal::net::tcp::TcpSocket::TcpSocket () throw (decaf::net::SocketException)`

Construct a non-connected socket.

Exceptions:

SocketException thrown if an error occurs while creating the Socket.

6.801.2.2 `virtual decaf::internal::net::tcp::TcpSocket::~~TcpSocket () [virtual]`

Releases the socket handle but not gracefully shut down the connection.

6.801.3 Member Function Documentation

6.801.3.1 `virtual void decaf::internal::net::tcp::TcpSocket::accept (SocketImpl * socket) throw (decaf::io::IOException) [virtual]`

6.801.3.2 `virtual int decaf::internal::net::tcp::TcpSocket::available () throw (decaf::io::IOException) [virtual]`

Gets the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Returns:

the number of bytes that can be read from the **Socket** (p. 3503) without blocking.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3531).

6.801.3.3 `virtual void decaf::internal::net::tcp::TcpSocket::bind (const std::string & ipaddress, int port) throw (decaf::io::IOException) [virtual]`

Binds this **Socket** (p. 3503) instance to the local ip address and port number given.

Parameters:

ipaddress The address of local ip to bind to.

port The port number on the host to bind to.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3531).

6.801.3.4 void decaf::internal::net::tcp::TcpSocket::checkResult (apr_status_t value) const throw (decaf::net::SocketException) [protected]

6.801.3.5 virtual void decaf::internal::net::tcp::TcpSocket::close () throw (decaf::io::IOException) [virtual]

Closes the socket, terminating any blocked reads or writes.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements decaf::net::SocketImpl (p. 3532).

6.801.3.6 virtual void decaf::internal::net::tcp::TcpSocket::connect (const std::string & hostname, int port, int timeout) throw (decaf::io::IOException, decaf::net::SocketException, decaf::lang::exceptions::IllegalArgumentException) [virtual]

Connects this socket to the given host and port.

Parameters:

hostname The name of the host to connect to, or IP address.

port The port number on the host to connect to.

timeout Time in milliseconds to wait for a connection, 0 indicates forever.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

SocketTimeoutException (p. 3542) if the connect call times out due to timeout being set.

IllegalArgumentException if a parameter has an illegal value.

Implements decaf::net::SocketImpl (p. 3532).

6.801.3.7 virtual void decaf::internal::net::tcp::TcpSocket::create () throw (decaf::io::IOException) [virtual]

Creates the underlying platform **Socket** (p. 3503) data structures which allows for **Socket** (p. 3503) options to be applied.

The created socket is in an unconnected state.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements decaf::net::SocketImpl (p. 3532).

6.801.3.8 `virtual decaf::io::InputStream* decaf::internal::net::tcp::TcpSocket::getInputStream () throw (decaf::io::IOException) [virtual]`

Gets the `InputStream` linked to this **Socket** (p. 3503).

Returns:

an `InputStream` pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements `decaf::net::SocketImpl` (p. 3533).

6.801.3.9 `virtual std::string decaf::internal::net::tcp::TcpSocket::getLocalAddress () const [virtual]`

Gets the value of the local `Inet` address the **Socket** (p. 3503) is bound to if bound, otherwise return the **InetAddress** (p. 2016) ANY value "0.0.0.0".

Returns:

the local address bound to, or ANY.

Implements `decaf::net::SocketImpl` (p. 3533).

6.801.3.10 `virtual int decaf::internal::net::tcp::TcpSocket::getOption (int option) const throw (decaf::io::IOException) [virtual]`

Gets the specified **Socket** (p. 3503) option.

Parameters:

option The **Socket** (p. 3503) options whose value is to be retrieved.

Returns:

the value of the given socket option.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Implements `decaf::net::SocketImpl` (p. 3534).

6.801.3.11 `virtual decaf::io::OutputStream* decaf::internal::net::tcp::TcpSocket::getOutputStream () throw (decaf::io::IOException) [virtual]`

Gets the `OutputStream` linked to this **Socket** (p. 3503).

Returns:

an OutputStream pointer owned by the **Socket** (p. 3503) object.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3534).

6.801.3.12 SocketHandle decaf::internal::net::tcp::TcpSocket::getSocketHandle ()
[inline]

Gets the handle for the socket.

Returns:

SocketHabler for this Socket, can be NULL

6.801.3.13 bool decaf::internal::net::tcp::TcpSocket::isClosed () const [inline]**Returns:**

true if the close method has been called on this Socket.

6.801.3.14 bool decaf::internal::net::tcp::TcpSocket::isConnected () const [inline]**Returns:**

true if the socketHandle is not in a disconnected state.

6.801.3.15 virtual void decaf::internal::net::tcp::TcpSocket::listen (int *backlog*)
throw (decaf::io::IOException) [virtual]

Sets the maximum queue length for incoming connection indications (a request to connect) to the count argument.

If a connection indication arrives when the queue is full, the connection is refused.

Parameters:

backlog The maximum length of the connection queue.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3534).

6.801.3.16 `int decaf::internal::net::tcp::TcpSocket::read (unsigned char * buffer,
int size, int offset, int length) throw (decaf::io::IOException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException)`

Reads the requested data from the Socket and write it into the passed in buffer.

Parameters:

buffer The buffer to read into
size The size of the specified buffer
offset The offset into the buffer where reading should start filling.
length The number of bytes past offset to fill with data.

Returns:

the actual number of bytes read or -1 if at EOF.

Exceptions:

IOException if an I/O error occurs during the read.
NullPointerException if buffer is Null.
IndexOutOfBoundsException if offset + length is greater than buffer size.

6.801.3.17 `virtual void decaf::internal::net::tcp::TcpSocket::setOption (int option,
int value) throw (decaf::io::IOException) [virtual]`

Sets the specified option on the **Socket** (p. 3503) if supported.

Parameters:

option The **Socket** (p. 3503) option to set.
value The value of the socket option to apply to the socket.

Exceptions:

IOException if an I/O error occurs while performing this operation.

Implements **decaf::net::SocketImpl** (p. 3535).

6.801.3.18 `virtual void decaf::internal::net::tcp::TcpSocket::shutdownInput () throw
(decaf::io::IOException) [virtual]`

Places the input stream for this socket at "end of stream".

Any data sent to this socket is acknowledged and then silently discarded. If you read from a socket input stream after invoking **shutdownInput()** (p. 3535) on the socket, the stream will return EOF.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3535).

**6.801.3.19 virtual void decaf::internal::net::tcp::TcpSocket::shutdownOutput ()
throw (decaf::io::IOException) [virtual]**

Disables the output stream for this socket.

For a TCP socket, any previously written data will be sent followed by TCP's normal connection termination sequence. If you write to a socket output stream after invoking **shutdownOutput()** (p. 3536) on the socket, the stream will throw an **IOException**.

Exceptions:

IOException if an I/O error occurs while attempting this operation.

Implements **decaf::net::SocketImpl** (p. 3536).

**6.801.3.20 void decaf::internal::net::tcp::TcpSocket::write (const unsigned char *
buffer, int size, int offset, int length) throw (decaf::io::IOException,
decaf::lang::exceptions::IndexOutOfBoundsException,
decaf::lang::exceptions::NullPointerException)**

Writes the specified data in the passed in buffer to the Socket.

Parameters:

buffer The buffer to write to the socket.

size The size of the specified buffer.

offset The offset into the buffer where the data to write starts at.

length The number of bytes past offset to write.

Exceptions:

IOException if an I/O error occurs during the write.

NullPointerException if buffer is Null.

IndexOutOfBoundsException if offset + length is greater than buffer size.

The documentation for this class was generated from the following file:

- src/main/decaf/internal/net/tcp/**TcpSocket.h**

6.802 decaf::internal::net::tcp::TcpSocketInputStream Class Reference

Input stream for performing reads on a socket.

#include <src/main/decaf/internal/net/tcp/TcpSocketInputStream.h> Inheritance diagram for decaf::internal::net::tcp::TcpSocketInputStream:

Public Member Functions

- **TcpSocketInputStream** (**TcpSocket** *socket)
Create a new InputStream to use for reading from the TCP/IP socket.
- virtual **~TcpSocketInputStream** ()
- virtual int **available** () const throw (decaf::io::IOException)
*Indicates the number of bytes available.
The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.
The default implementation of this method returns zero.*
Returns:
the number of bytes available on this input stream.
Exceptions:
IOException (p. 2142) if an I/O error occurs.
- virtual void **close** () throw (decaf::io::IOException)
Close - does nothing.
- virtual long long **skip** (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Not supported.

Protected Member Functions

- virtual int **doReadByte** () throw (io::IOException)
- virtual int **doReadArrayBounded** (unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)

6.802.1 Detailed Description

Input stream for performing reads on a socket. This class will only work properly for blocking sockets.

Since:

1.0

6.802.2 Constructor & Destructor Documentation

6.802.2.1 decaf::internal::net::tcp::TcpSocketInputStream::TcpSocketInputStream (TcpSocket * *socket*)

Create a new `InputStream` to use for reading from the TCP/IP socket.

Parameters:

socket The parent `SocketImpl` for this stream.

6.802.2.2 virtual decaf::internal::net::tcp::TcpSocketInputStream::~TcpSocketInputStream () [virtual]

6.802.3 Member Function Documentation

6.802.3.1 virtual int decaf::internal::net::tcp::TcpSocketInputStream::available () const throw (decaf::io::IOException) [virtual]

Indicates the number of bytes available.

The default implementation of this methods returns 0. Classes that override this method may return the total number of bytes that are currently available for reading and others may simply return a value of one indicating that there is some data available. The caller should view the result of this method as an absolute.

The default implementation of this method returns zero.

Returns:

the number of bytes available on this input stream.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

Reimplemented from `decaf::io::InputStream` (p. 2045).

6.802.3.2 virtual void decaf::internal::net::tcp::TcpSocketInputStream::close () throw (decaf::io::IOException) [virtual]

Close - does nothing. It is the responsibility of the owner of the socket object to close it.

Closes the `InputStream` (p. 2043) freeing any resources that might have been aquired during the lifetime of this stream.

The default implementation of this method does nothing.

Reimplemented from `decaf::io::InputStream` (p. 2045).

6.802.3.3 `virtual int decaf::internal::net::tcp::TcpSocketInputStream::doReadArrayBounded (unsigned char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException, decaf::lang::exceptions::NullPointerException)` [protected, virtual]

Reimplemented from `decaf::io::InputStream` (p. 2046).

6.802.3.4 `virtual int decaf::internal::net::tcp::TcpSocketInputStream::doReadByte () throw (io::IOException)` [protected, virtual]

Implements `decaf::io::InputStream` (p. 2046).

6.802.3.5 `virtual long long decaf::internal::net::tcp::TcpSocketInputStream::skip (long long num) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)` [virtual]

Not supported. Skips over and discards n bytes of data from this input stream.

The skip method may, for a variety of reasons, end up skipping over some smaller number of bytes, possibly 0. This may result from any of a number of conditions; reaching end of file before n bytes have been skipped is only one possibility. The actual number of bytes skipped is returned.

The skip method of `InputStream` (p. 2043) creates a byte array and then repeatedly reads into it until num bytes have been read or the end of the stream has been reached. Subclasses are encouraged to provide a more efficient implementation of this method.

Parameters:

num The number of bytes to skip.

Returns:

total bytes skipped

Exceptions:

IOException (p. 2142) if an I/O error occurs.

UnsupportedOperationException if the concrete stream class does not support skipping bytes.

Reimplemented from `decaf::io::InputStream` (p. 2050).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/tcp/TcpSocketInputStream.h`

6.803 decaf::internal::net::tcp::TcpSocketOutputStream Class Reference

Output stream for performing write operations on a socket.

#include <src/main/decaf/internal/net/tcp/TcpSocketOutputStream.h>Inheritance diagram for decaf::internal::net::tcp::TcpSocketOutputStream:

Public Member Functions

- **TcpSocketOutputStream** (**TcpSocket** *socket)
Create a new instance of a Socket OutputStream class.
- virtual ~**TcpSocketOutputStream** ()
- virtual void **close** () throw (decaf::io::IOException)
*Closes this object and deallocates the appropriate resources.
The object is generally no longer usable after calling close.*
Exceptions:
***IOException** (p. 2142) if an error occurs while closing.
The default implementation of this method does nothing.*

Protected Member Functions

- virtual void **doWriteByte** (unsigned char c) throw (decaf::io::IOException)
- virtual void **doWriteArrayBounded** (const unsigned char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.803.1 Detailed Description

Output stream for performing write operations on a socket.

Since:

1.0

6.803.2 Constructor & Destructor Documentation

6.803.2.1 decaf::internal::net::tcp::TcpSocketOutputStream::TcpSocketOutputStream (**TcpSocket** * socket)

Create a new instance of a Socket OutputStream class.

Parameters:

socket The socket to use to write out the data.

6.803.2.2 **virtual**
decaf::internal::net::tcp::TcpSocketOutputStream::~~TcpSocketOutputStream
() [virtual]

6.803.3 Member Function Documentation

6.803.3.1 **virtual void decaf::internal::net::tcp::TcpSocketOutputStream::close ()**
throw (decaf::io::IOException) [virtual]

Closes this object and deallocates the appropriate resources.

The object is generally no longer usable after calling close.

Exceptions:

IOException (p. 2142) if an error occurs while closing.

The default implementation of this method does nothing. The default implementation of this method does nothing.

Reimplemented from **decaf::io::OutputStream** (p. 2909).

6.803.3.2 **virtual void de-**
caf::internal::net::tcp::TcpSocketOutputStream::doWriteArrayBounded
(const unsigned char * *buffer*, int *size*, int *offset*, int *length*) throw (
decaf::io::IOException, decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IndexOutOfBoundsException) [protected,
virtual]

Reimplemented from **decaf::io::OutputStream** (p. 2909).

6.803.3.3 **virtual void de-**
caf::internal::net::tcp::TcpSocketOutputStream::doWriteByte (unsigned
char *c*) throw (decaf::io::IOException) [protected, virtual]

Implements **decaf::io::OutputStream** (p. 2910).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/tcp/TcpSocketOutputStream.h`

6.804 activemq::transport::tcp::TcpTransport Class Reference

Implements a TCP/IP based **transport** (p. 97) filter, this **transport** (p. 97) is meant to wrap an instance of an **IOTransport** (p. 2145).

#include <src/main/activemq/transport/tcp/TcpTransport.h> Inheritance diagram for activemq::transport::tcp::TcpTransport:

Public Member Functions

- **TcpTransport** (const **Pointer**< **Transport** > &next)
*Creates a new instance of a **TcpTransport** (p. 3752), the **transport** (p. 97) is left unconnected and is in a unusable **state** (p. 95) until the connect method is called.*
- virtual ~**TcpTransport** ()
- void **connect** (const **decaf::net::URI** &uri, const **decaf::util::Properties** &properties)
Creates a Socket and configures it before attempting to connect to the location specified by the URI passed in.
- virtual void **close** () throw (**decaf::io::IOException**)
Delegates to the superclass and then closes the socket.
- virtual bool **isFaultTolerant** () const
*Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.*
- virtual bool **isConnected** () const
*Is the **Transport** (p. 3883) Connected to its Broker.*
- virtual bool **isClosed** () const
*Has the **Transport** (p. 3883) been shutdown and no longer usable.*

Protected Member Functions

- virtual **decaf::net::Socket** * **createSocket** ()
*Create an unconnected Socket instance to be used by the **transport** (p. 97) to communicate with the broker.*
- virtual void **configureSocket** (**decaf::net::Socket** *socket, const **decaf::util::Properties** &properties)
Using options from configuration URI, configure the socket options before the Socket instance is connected to the Server.

6.804.1 Detailed Description

Implements a TCP/IP based **transport** (p. 97) filter, this **transport** (p. 97) is meant to wrap an instance of an **IOTransport** (p. 2145). The lower level **transport** (p. 97) should take care of managing stream reads and writes.

6.804.2 Constructor & Destructor Documentation

6.804.2.1 **activemq::transport::tcp::TcpTransport::TcpTransport** (const **Pointer**<**Transport** > & *next*)

Creates a new instance of a **TcpTransport** (p. 3752), the **transport** (p. 97) is left unconnected and is in a unusable **state** (p. 95) until the connect method is called.

Parameters:

next The next **transport** (p. 97) in the chain

6.804.2.2 **virtual activemq::transport::tcp::TcpTransport::~~TcpTransport** () [virtual]

6.804.3 Member Function Documentation

6.804.3.1 **virtual void activemq::transport::tcp::TcpTransport::close** () throw (**decaf::io::IOException**) [virtual]

Delegates to the superclass and then closes the socket.

Exceptions:

IOException if errors occur.

Reimplemented from **activemq::transport::TransportFilter** (p. 3893).

6.804.3.2 **virtual void activemq::transport::tcp::TcpTransport::configureSocket** (**decaf::net::Socket** * *socket*, const **decaf::util::Properties** & *properties*) [protected, virtual]

Using options from configuration URI, configure the socket options before the Socket instance is connected to the Server. Subclasses can override this option to set more configuration options, they should called the base class version to allow the default set of Socket options to also be configured.

Parameters:

socket The Socket instance to configure using options from the given Properties.

Exceptions:

NullPointerException if the Socket instance is null.

IllegalArgumentException if the socket instance is not handled by the class.

SocketException if there is an error while setting one of the Socket options.

6.804.3.3 void activemq::transport::tcp::TcpTransport::connect (const decaf::net::URI & *uri*, const decaf::util::Properties & *properties*)

Creates a Socket and configures it before attempting to connect to the location specified by the URI passed in. The Socket is configured using parameters in the properties that are passed to this method.

Parameters:

uri The URI that the **Transport** (p. 3883) is to connect to once initialized.

properties The Properties that have been parsed from the URI or from configuration files.

6.804.3.4 virtual decaf::net::Socket* activemq::transport::tcp::TcpTransport::createSocket () [protected, virtual]

Create an unconnected Socket instance to be used by the **transport** (p. 97) to communicate with the broker.

Returns:

a newly created unconnected Socket instance.

Exceptions:

IOException if there is an error while creating the unconnected Socket.

Reimplemented in **activemq::transport::tcp::SslTransport** (p. 3575).

6.804.3.5 virtual bool activemq::transport::tcp::TcpTransport::isClosed () const [inline, virtual]

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

Reimplemented from **activemq::transport::TransportFilter** (p. 3894).

6.804.3.6 virtual bool activemq::transport::tcp::TcpTransport::isConnected () const [inline, virtual]

Is the **Transport** (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Reimplemented from **activemq::transport::TransportFilter** (p. 3894).

6.804.3.7 `virtual bool activemq::transport::tcp::TcpTransport::isFaultTolerant ()`
`const [inline, virtual]`

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Reimplemented from **activemq::transport::TransportFilter** (p. 3895).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/tcp/TcpTransport.h`

6.805 activemq::transport::tcp::TcpTransportFactory Class Reference

Factory Responsible for creating the **TcpTransport** (p. 3752).

#include <src/main/activemq/transport/tcp/TcpTransportFactory.h> Inheritance diagram for activemq::transport::tcp::TcpTransportFactory:

Public Member Functions

- virtual **~TcpTransportFactory** ()
- virtual **Pointer< Transport > create** (const **decaf::net::URI** &location) throw (exceptions::ActiveMQException)

*Creates a fully configured **Transport** (p. 3883) instance which could be a chain of filters and transports.*

- virtual **Pointer< Transport > createComposite** (const **decaf::net::URI** &location) throw (exceptions::ActiveMQException)

*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

Protected Member Functions

- virtual **Pointer< Transport > doCreateComposite** (const **decaf::net::URI** &location, const **Pointer< wireformat::WireFormat >** &wireFormat, const **decaf::util::Properties** &properties) throw (exceptions::ActiveMQException)

*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

6.805.1 Detailed Description

Factory Responsible for creating the **TcpTransport** (p. 3752).

6.805.2 Constructor & Destructor Documentation

6.805.2.1 `virtual
activemq::transport::tcp::TcpTransportFactory::~~TcpTransportFactory ()
[inline, virtual]`

6.805.3 Member Function Documentation

6.805.3.1 `virtual Pointer<Transport> ac-
tivismq::transport::tcp::TcpTransportFactory::create (const
decaf::net::URI & location) throw (exceptions::ActiveMQException)
[virtual]`

Creates a fully configured **Transport** (p.3883) instance which could be a chain of filters and transports.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3889).

6.805.3.2 `virtual Pointer<Transport> ac-
tivismq::transport::tcp::TcpTransportFactory::createComposite (const
decaf::net::URI & location) throw (exceptions::ActiveMQException)
[virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implements `activemq::transport::TransportFactory` (p.3890).

6.805.3.3 `virtual Pointer<Transport> ac-
tivismq::transport::tcp::TcpTransportFactory::doCreateComposite (const
decaf::net::URI & location, const Pointer< wireformat::WireFormat
> & wireFormat, const decaf::util::Properties & properties) throw (
exceptions::ActiveMQException) [protected, virtual]`

Creates a slimed down **Transport** (p.3883) instance which can be used in composite **transport** (p.97) instances.

Parameters:

location - URI location to connect to.

wireFormat - the assigned WireFormat for the new **Transport** (p. 3883).

properties - Properties to apply to the **transport** (p. 97).

Returns:

new Pointer to a **TcpTransport** (p. 3752).

Exceptions:

ActiveMQException if an error occurs

Reimplemented in **activemq::transport::tcp::SslTransportFactory** (p. 3576).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/tcp/TcpTransportFactory.h`

6.806 cms::TemporaryQueue Class Reference

Defines a Temporary **Queue** (p. 3148) based **Destination** (p. 1723).

#include <src/main/cms/TemporaryQueue.h> Inheritance diagram for cms::TemporaryQueue:

Public Member Functions

- virtual **~TemporaryQueue** ()
- virtual std::string **getQueueName** () const =0 throw (CMSEException)
Gets the name of this queue.
- virtual void **destroy** ()=0 throw (CMSEException)
*Destroy's the Temporary **Destination** (p. 1723) at the Provider.*

6.806.1 Detailed Description

Defines a Temporary **Queue** (p. 3148) based **Destination** (p. 1723). A **TemporaryQueue** (p. 3759) is a special type of **Queue** (p. 3148) **Destination** (p. 1723) that can only be consumed from the **Connection** (p. 1262) which created it. TemporaryQueues are most commonly used as the reply to address for Message's that implement the request response pattern.

A **TemporaryQueue** (p. 3759) is guaranteed to exist at the Provider only for the lifetime of the **Connection** (p. 1262) that created it.

Since:

1.0

6.806.2 Constructor & Destructor Documentation

6.806.2.1 virtual cms::TemporaryQueue::~~TemporaryQueue () [inline, virtual]

6.806.3 Member Function Documentation

6.806.3.1 virtual void cms::TemporaryQueue::destroy () throw (CMSEException)
 [pure virtual]

Destroy's the Temporary **Destination** (p. 1723) at the Provider.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::commands::ActiveMQTempQueue** (p. 606).

6.806.3.2 virtual std::string cms::TemporaryQueue::getQueueName () const throw (CMSEException) [pure virtual]

Gets the name of this queue.

Returns:

The queue name.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in **activemq::commands::ActiveMQTempQueue** (p. 607).

The documentation for this class was generated from the following file:

- src/main/cms/TemporaryQueue.h

6.807 cms::TemporaryTopic Class Reference

Defines a Temporary **Topic** (p. 3817) based **Destination** (p. 1723).

#include <src/main/cms/TemporaryTopic.h> Inheritance diagram for cms::TemporaryTopic:

Public Member Functions

- virtual **~TemporaryTopic** ()
- virtual std::string **getTopicName** () const =0 throw (CMSEException)
Gets the name of this topic.
- virtual void **destroy** ()=0 throw (CMSEException)
*Destroy's the Temporary **Destination** (p. 1723) at the Provider.*

6.807.1 Detailed Description

Defines a Temporary **Topic** (p. 3817) based **Destination** (p. 1723). A **TemporaryTopic** (p. 3761) is a special type of **Topic** (p. 3817) **Destination** (p. 1723) that can only be consumed from the **Connection** (p. 1262) which created it. TemporaryTopics are most commonly used as the reply to address for Message's that implement the request response pattern.

A **TemporaryTopic** (p. 3761) is guaranteed to exist at the Provider only for the lifetime of the **Connection** (p. 1262) that created it.

Since:

1.0

6.807.2 Constructor & Destructor Documentation

6.807.2.1 virtual cms::TemporaryTopic::~~TemporaryTopic () [inline, virtual]

6.807.3 Member Function Documentation

6.807.3.1 virtual void cms::TemporaryTopic::destroy () throw (CMSEException)
 [pure virtual]

Destroy's the Temporary **Destination** (p. 1723) at the Provider.

Exceptions:

CMSEException (p. 1160)

Implemented in **activemq::commands::ActiveMQTempTopic** (p. 635).

6.807.3.2 virtual std::string cms::TemporaryTopic::getTopicName () const throw (CMSException) [pure virtual]

Gets the name of this topic.

Returns:

The topic name.

Exceptions:

CMSException (p. 1160) - if an internal error occurs.

Implemented in **activemq::commands::ActiveMQTempTopic** (p. 636).

The documentation for this class was generated from the following file:

- src/main/cms/**TemporaryTopic.h**

6.808 cms::TextMessage Class Reference

Interface for a text message.

#include <src/main/cms/TextMessage.h> Inheritance diagram for cms::TextMessage:

Public Member Functions

- virtual `~TextMessage ()`
- virtual `std::string getText () const =0` throw (cms::CMSEException)
Gets the message character buffer.
- virtual void `setText (const char *msg)=0` throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets the message contents, does not take ownership of the passed char, but copies it instead.*
- virtual void `setText (const std::string &msg)=0` throw (cms::MessageNotWriteableException, cms::CMSEException)
Sets the message contents.

6.808.1 Detailed Description

Interface for a text message. A **TextMessage** (p. 3763) can contain any Text based pay load such as an XML Document or other Text based document.

Like all Messages, a **TextMessage** (p. 3763) is received in Read-Only mode, any attempt to write to the **Message** (p. 2534) will result in a `MessageNotWritableException` being thrown until the `clearBody` method is called which will erase the contents and place the message back in a read / write mode.

Since:

1.0

6.808.2 Constructor & Destructor Documentation

6.808.2.1 virtual cms::TextMessage::~TextMessage () [inline, virtual]

6.808.3 Member Function Documentation

6.808.3.1 virtual std::string cms::TextMessage::getText () const throw (cms::CMSEException) [pure virtual]

Gets the message character buffer.

Returns:

The message character buffer.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

Implemented in `activemq::commands::ActiveMQTextMessage` (p. 665).

6.808.3.2 `virtual void cms::TextMessage::setText (const std::string & msg) throw (cms::MessageNotWriteableException, cms::CMSEException) [pure virtual]`

Sets the message contents.

Parameters:

msg The message buffer.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode..

Implemented in `activemq::commands::ActiveMQTextMessage` (p. 665).

6.808.3.3 `virtual void cms::TextMessage::setText (const char * msg) throw (cms::MessageNotWriteableException, cms::CMSEException) [pure virtual]`

Sets the message contents, does not take ownership of the passed char*, but copies it instead.

Parameters:

msg The message buffer.

Exceptions:

CMSEException (p. 1160) - if an internal error occurs.

MessageNotWriteableException (p. 2724) - if the message is in read-only mode..

Implemented in `activemq::commands::ActiveMQTextMessage` (p. 665).

The documentation for this class was generated from the following file:

- `src/main/cms/TextMessage.h`

6.809 decaf::lang::Thread Class Reference

A **Thread** (p. 3765) is a concurrent unit of execution.

#include <src/main/decaf/lang/Thread.h> Inheritance diagram for decaf::lang::Thread:

Data Structures

- class **UncaughtExceptionHandler**

*Interface for handlers invoked when a **Thread** (p. 3765) abruptly terminates due to an uncaught exception.*

Public Types

- enum **State** {
NEW = 0, **RUNNABLE** = 1, **BLOCKED** = 2, **WAITING** = 3,
TIMED_WAITING = 4, **SLEEPING** = 5, **TERMINATED** = 6 }

*Represents the various states that the **Thread** (p. 3765) can be in during its lifetime.*

Public Member Functions

- **Thread** ()
*Constructs a new **Thread** (p. 3765).*
- **Thread** (**Runnable** *task)
*Constructs a new **Thread** (p. 3765) with the given target **Runnable** (p. 3325) task.*
- **Thread** (const std::string &name)
*Constructs a new **Thread** (p. 3765) with the given name.*
- **Thread** (**Runnable** *task, const std::string &name)
*Constructs a new **Thread** (p. 3765) with the given target **Runnable** (p. 3325) task and name.*
- virtual ~**Thread** ()
- virtual void **start** () throw (decaf::lang::exceptions::IllegalThreadStateException, decaf::lang::exceptions::RuntimeException)
Creates a system thread and starts it in a joinable mode.
- virtual void **join** () throw (decaf::lang::exceptions::InterruptedException)
*Forces the Current **Thread** (p. 3765) to wait until the thread exits.*
- virtual void **join** (long long millisecs) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InterruptedException)
*Forces the Current **Thread** (p. 3765) to wait until the thread exits.*

- virtual void **join** (long long millisecs, unsigned int nanos) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InterruptedException)
*Forces the Current **Thread** (p. 3765) to wait until the thread exits.*
- virtual void **run** ()
Default implementation of the run method - does nothing.
- std::string **getName** () const
Returns the Thread's assigned name.
- void **setName** (const std::string &name)
*Sets the name of the **Thread** (p. 3765) to the new Name given by the argument name.*
- int **getPriority** () const
*Gets the currently set priority for this **Thread** (p. 3765).*
- void **setPriority** (int value) throw (decaf::lang::exceptions::IllegalArgumentException)
Sets the current Thread's priority to the newly specified value.
- const **UncaughtExceptionHandler** * **getUncaughtExceptionHandler** () const
Set the handler invoked when this thread abruptly terminates due to an uncaught exception.
- void **setUncaughtExceptionHandler** (**UncaughtExceptionHandler** *handler)
Set the handler invoked when this thread abruptly terminates due to an uncaught exception.
- std::string **toString** () const
*Returns a string that describes the **Thread** (p. 3765).*
- bool **isAlive** () const
*Returns true if the **Thread** (p. 3765) is alive, meaning it has been started and has not yet died.*
- **Thread::State** **getState** () const
*Returns the currently set State of this **Thread** (p. 3765).*

Static Public Member Functions

- static void **sleep** (long long millisecs) throw (lang::exceptions::InterruptedException, lang::exceptions::IllegalArgumentException)
Causes the currently executing thread to halt execution for the specified number of milliseconds, subject to the precision and accuracy of system timers and schedulers.
- static void **sleep** (long long millisecs, unsigned int nanos) throw (lang::exceptions::InterruptedException, lang::exceptions::IllegalArgumentException)
Causes the currently executing thread to halt execution for the specified number of milliseconds plus any additionally specified nanoseconds given, subject to the precision and accuracy of system timers and schedulers.

- static void **yield** ()
Causes the currently executing thread object to temporarily pause and allow other threads to execute.
- static long long **getId** ()
*Obtains the **Thread** (p. 3765) Id of the current thread.*
- static **Thread** * **currentThread** ()
Returns a pointer to the currently executing thread object.

Static Public Attributes

- static const int **MIN_PRIORITY** = 1
The minimum priority that a thread can have.
- static const int **NORM_PRIORITY** = 5
The default priority that a thread is given at create time.
- static const int **MAX_PRIORITY** = 10
The maximum priority that a thread can have.

Friends

- class **decaf::util::concurrent::locks::LockSupport**
- class **decaf::lang::Runtime**

6.809.1 Detailed Description

A **Thread** (p. 3765) is a concurrent unit of execution. It has its own call stack for methods being invoked, their arguments and local variables. Each process has at least one main **Thread** (p. 3765) running when it is started; typically, there are several others for housekeeping. The application might decide to launch additional Threads for specific purposes.

Threads in the same process interact and synchronize by the use of shared objects and monitors associated with these objects.

There are basically two main ways of having a **Thread** (p. 3765) execute application **code** (p. 1183). One is providing a new class that extends **Thread** (p. 3765) and overriding its **run()** (p. 3771) method. The other is providing a new **Thread** (p. 3765) instance with a **Runnable** (p. 3325) object during its creation. In both cases, the **start()** (p. 3772) method must be called to actually execute the new **Thread** (p. 3765).

Each **Thread** (p. 3765) has an integer priority that basically determines the amount of CPU time the **Thread** (p. 3765) gets. It can be set using the **setPriority(int)** (p. 3771) method. A **Thread** (p. 3765) can also be made a daemon, which makes it run in the background. The latter also affects VM termination behavior: the VM does not terminate automatically as long as there are non-daemon threads running.

See also:

decaf.lang.ThreadGroup (p. 3776)

Since:

1.0

6.809.2 Member Enumeration Documentation

6.809.2.1 enum decaf::lang::Thread::State

Represents the various states that the **Thread** (p. 3765) can be in during its lifetime.

Enumerator:

NEW Before a **Thread** (p. 3765) is started it exists in this State.

RUNNABLE While a **Thread** (p. 3765) is running and is not blocked it is in this State.

BLOCKED A **Thread** (p. 3765) that is waiting to acquire a lock is in this state.

WAITING A **Thread** (p. 3765) that is waiting for another **Thread** (p. 3765) to perform an action is in this state.

TIMED_WAITING A **Thread** (p. 3765) that is waiting for another **Thread** (p. 3765) to perform an action up to a specified time interval is in this state.

SLEEPING A **Thread** (p. 3765) that is blocked in a Sleep call is in this state.

TERMINATED A **Thread** (p. 3765) whose run method has exited is in this state.

6.809.3 Constructor & Destructor Documentation

6.809.3.1 decaf::lang::Thread::Thread ()

Constructs a new **Thread** (p. 3765). This constructor has the same effect as Thread(NULL, NULL, GIVEN_NAME), where GIVEN_NAME is a newly generated name. When no name is given the name is automatically generated and are of the form "Thread-"+n, where n is an integer.

6.809.3.2 decaf::lang::Thread::Thread (Runnable * task)

Constructs a new **Thread** (p. 3765) with the given target **Runnable** (p. 3325) task. This constructor has the same effect as Thread(NULL, task, GIVEN_NAME), where GIVEN_NAME is a newly generated name. When no name is given the name is automatically generated and are of the form "Thread-"+n, where n is an integer.

Parameters:

task the **Runnable** (p. 3325) that this thread manages, if the task is NULL the Thread's run method is used instead.

6.809.3.3 decaf::lang::Thread::Thread (const std::string & name)

Constructs a new **Thread** (p. 3765) with the given name. This constructor has the same effect as Thread(NULL, NULL, GIVEN_NAME), where GIVEN_NAME is a newly generated name. When no name is given the name is automatically generated and are of the form "Thread-"+n, where n is an integer.

Parameters:

name the name to assign to this **Thread** (p. 3765).

6.809.3.4 decaf::lang::Thread::Thread (Runnable * *task*, const std::string & *name*)

Constructs a new **Thread** (p. 3765) with the given target **Runnable** (p. 3325) task and name. This constructor has the same effect as Thread(NULL, task, GIVEN_NAME), where GIVEN_NAME is a newly generated name. When no name is given the name is automatically generated and are of the form "Thread-"+n, where n is an integer.

Parameters:

task the **Runnable** (p. 3325) that this thread manages, if the task is NULL the Thread's run method is used instead.

name the name to assign to this **Thread** (p. 3765).

6.809.3.5 virtual decaf::lang::Thread::~~Thread () [virtual]**6.809.4 Member Function Documentation****6.809.4.1 static Thread* decaf::lang::Thread::currentThread () [static]**

Returns a pointer to the currently executing thread object.

Returns:

Pointer (p. 2946) to the **Thread** (p. 3765) object representing the currently running **Thread** (p. 3765).

6.809.4.2 static long long decaf::lang::Thread::getId () [static]

Obtains the **Thread** (p. 3765) Id of the current thread.

Returns:

Thread (p. 3765) Id

6.809.4.3 std::string decaf::lang::Thread::getName () const

Returns the Thread's assigned name.

Returns:

the Name of the **Thread** (p. 3765).

6.809.4.4 int decaf::lang::Thread::getPriority () const

Gets the currently set priority for this **Thread** (p. 3765).

Returns:

an int value representing the Thread's current priority.

6.809.4.5 Thread::State decaf::lang::Thread::getState () const

Returns the currently set State of this **Thread** (p. 3765).

Returns:

the Thread's current state.

6.809.4.6 const UncaughtExceptionHandler* decaf::lang::Thread::getUncaughtExceptionHandler () const

Set the handler invoked when this thread abruptly terminates due to an uncaught exception.

Returns:

a pointer to the set **UncaughtExceptionHandler** (p. 3906).

6.809.4.7 bool decaf::lang::Thread::isAlive () const

Returns true if the **Thread** (p. 3765) is alive, meaning it has been started and has not yet died.

Returns:

true if the thread is alive.

6.809.4.8 virtual void decaf::lang::Thread::join (long long *millisecs*, unsigned int *nanos*) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InterruptedException) [virtual]

Forces the Current **Thread** (p. 3765) to wait until the thread exits.

Parameters:

millisecs the time in Milliseconds before the thread resumes

nanos 0-999999 extra nanoseconds to sleep.

Exceptions:

IllegalArgumentException if the nanoseconds parameter is out of range or the milliseconds paramter is negative.

InterruptedException if any thread has interrupted the current thread. The interrupted status of the current thread is cleared when this exception is thrown.

6.809.4.9 virtual void decaf::lang::Thread::join (long long *millisecs*) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::InterruptedException) [virtual]

Forces the Current **Thread** (p. 3765) to wait until the thread exits.

Parameters:

milliseconds the time in Milliseconds before the thread resumes

Exceptions:

IllegalArgumentException if the milliseconds parameter is negative.

InterruptedException if any thread has interrupted the current thread. The interrupted status of the current thread is cleared when this exception is thrown.

6.809.4.10 `virtual void decaf::lang::Thread::join () throw (decaf::lang::exceptions::InterruptedException) [virtual]`

Forces the Current **Thread** (p. 3765) to wait until the thread exits.

Exceptions:

InterruptedException if any thread has interrupted the current thread. The interrupted status of the current thread is cleared when this exception is thrown.

6.809.4.11 `virtual void decaf::lang::Thread::run () [virtual]`

Default implementation of the run method - does nothing.

Implements **decaf::lang::Runnable** (p. 3325).

Reimplemented in **activemq::transport::mock::InternalCommandListener** (p. 2123), and **decaf::util::concurrent::PooledThread** (p. 2969).

6.809.4.12 `void decaf::lang::Thread::setName (const std::string & name)`

Sets the name of the **Thread** (p. 3765) to the new Name given by the argument *name*. name the new name of the **Thread** (p. 3765).

6.809.4.13 `void decaf::lang::Thread::setPriority (int value) throw (decaf::lang::exceptions::IllegalArgumentException)`

Sets the current Thread's priority to the newly specified value. The given value must be within the range **Thread::MIN_PRIORITY** (p. 3773) and **Thread::MAX_PRIORITY** (p. 3773).

Parameters:

value the new priority value to assign to this **Thread** (p. 3765).

Exceptions:

IllegalArgumentException if the value is out of range.

**6.809.4.14 void decaf::lang::Thread::setUncaughtExceptionHandler
(UncaughtExceptionHandler * *handler*)**

Set the handler invoked when this thread abruptly terminates due to an uncaught exception.

Parameters:

handler the UncaughtExceptionHandler to invoke when the **Thread** (p. 3765) terminates due to an uncaught exception.

**6.809.4.15 static void decaf::lang::Thread::sleep (long long *milliseconds*, unsigned
int *nanos*) throw (lang::exceptions::InterruptedException,
lang::exceptions::IllegalArgumentException) [static]**

Causes the currently executing thread to halt execution for the specified number of milliseconds plus any additionally specified nanoseconds given, subject to the precision and accuracy of system timers and schedulers. Note that this method is a static method that applies to the calling thread and not to the thread object.

Parameters:

milliseconds time in milliseconds to halt execution.

nanos 0-999999 extra nanoseconds to sleep.

Exceptions:

IllegalArgumentException if the nanoseconds parameter is out of range or the milliseconds parameter is negative.

InterruptedException if the **Thread** (p. 3765) was interrupted while sleeping.

**6.809.4.16 static void decaf::lang::Thread::sleep (long long
milliseconds) throw (lang::exceptions::InterruptedException,
lang::exceptions::IllegalArgumentException) [static]**

Causes the currently executing thread to halt execution for the specified number of milliseconds, subject to the precision and accuracy of system timers and schedulers. Note that this method is a static method that applies to the calling thread and not to the thread object.

Parameters:

milliseconds time in milliseconds to halt execution.

Exceptions:

IllegalArgumentException if the milliseconds parameter is negative.

InterruptedException if the **Thread** (p. 3765) was interrupted while sleeping.

**6.809.4.17 virtual void decaf::lang::Thread::start () throw (
decaf::lang::exceptions::IllegalThreadStateException,
decaf::lang::exceptions::RuntimeException) [virtual]**

Creates a system thread and starts it in a joinable mode. Upon creation, the **run()** (p. 3771) method of either this object or the provided **Runnable** (p. 3325) object will be invoked in the context of this thread.

Exceptions:

IllegalThreadStateException if the thread has already been started.

RuntimeException if the **Thread** (p. 3765) cannot be created for some reason.

6.809.4.18 `std::string decaf::lang::Thread::toString () const`

Returns a string that describes the **Thread** (p. 3765).

Returns:

string describing the **Thread** (p. 3765).

6.809.4.19 `static void decaf::lang::Thread::yield () [static]`

Causes the currently executing thread object to temporarily pause and allow other threads to execute.

6.809.5 Friends And Related Function Documentation**6.809.5.1** `friend class decaf::lang::Runtime [friend]`**6.809.5.2** `friend class decaf::util::concurrent::locks::LockSupport [friend]`**6.809.6 Field Documentation****6.809.6.1** `const int decaf::lang::Thread::MAX_PRIORITY = 10 [static]`

The maximum priority that a thread can have.

6.809.6.2 `const int decaf::lang::Thread::MIN_PRIORITY = 1 [static]`

The minimum priority that a thread can have.

6.809.6.3 `const int decaf::lang::Thread::NORM_PRIORITY = 5 [static]`

The default priority that a thread is given at create time.

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Thread.h`

6.810 decaf::util::concurrent::ThreadFactory Class Reference

public interface **ThreadFactory** (p. 3774)

```
#include <src/main/decaf/util/concurrent/ThreadFactory.h>
```

Public Member Functions

- virtual **~ThreadFactory** ()
- virtual **decaf::lang::Thread * newThread** (decaf::lang::Runnable *r)=0
Constructs a new Thread.

6.810.1 Detailed Description

public interface **ThreadFactory** (p. 3774) An object that creates new threads on demand. Using thread factories removes hardwiring of calls to new Thread, enabling applications to use special thread subclasses, priorities, etc.

The simplest implementation of this interface is just:

```
class SimpleThreadFactory : public ThreadFactory (p. 3774) { public: Thread* newThread(  
Runnable* r ) { return new Thread(r); } }
```

The Executors.defaultThreadFactory() method provides a more useful simple implementation, that sets the created thread context to known values before returning it.

Since:

1.0

6.810.2 Constructor & Destructor Documentation

6.810.2.1 virtual decaf::util::concurrent::ThreadFactory::~~ThreadFactory ()
[inline, virtual]

6.810.3 Member Function Documentation

6.810.3.1 virtual decaf::lang::Thread* decaf::util::concurrent::ThreadFactory::newThread (decaf::lang::Runnable * r) [pure virtual]

Constructs a new Thread. Implementations may also initialize priority, name, daemon status, ThreadGroup, etc. The pointer passed is still owned by the caller and is not deleted by the Thread object. The caller owns the returned Thread object and must delete it when finished.

Parameters:

r A pointer to a Runnable instance to be executed by new Thread instance returned.

Returns:

constructed thread, or NULL if the request to create a thread is rejected the caller owns the returned pointer.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/ThreadFactory.h`

6.811 decaf::lang::ThreadGroup Class Reference

```
#include <src/main/decaf/lang/ThreadGroup.h>
```

Public Member Functions

- **ThreadGroup** ()
- virtual **~ThreadGroup** ()

6.811.1 Detailed Description

Since:

1.0

6.811.2 Constructor & Destructor Documentation

6.811.2.1 decaf::lang::ThreadGroup::ThreadGroup ()

6.811.2.2 virtual decaf::lang::ThreadGroup::~~ThreadGroup () [virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/ThreadGroup.h`

6.812 decaf::util::concurrent::ThreadPool Class Reference

Defines a Thread Pool object that implements the functionality of pooling threads to perform user tasks.

#include <src/main/decaf/util/concurrent/ThreadPool.h> Inheritance diagram for decaf::util::concurrent::ThreadPool:

Public Types

- typedef std::pair< lang::Runnable *, TaskListener * > Task

Public Member Functions

- **ThreadPool** ()
- virtual **~ThreadPool** ()
- virtual void **queueTask** (Task task) throw (lang::Exception)
Queue (p. 3149) a task to be completed by one of the Pooled Threads.
- virtual **Task deQueueTask** () throw (lang::Exception)
DeQueue a task to be completed by one of the Pooled Threads.
- virtual std::size_t **getPoolSize** () const
Returns the current number of Threads in the Pool, this is how many there are now, not how many are active or the max number that might exist.
- virtual std::size_t **getBacklog** () const
Returns the current backlog of items in the tasks queue, this is how much work is still waiting to get done.
- virtual void **reserve** (std::size_t size)
Ensures that there is at least the specified number of Threads allocated to the pool.
- virtual std::size_t **getMaxThreads** () const
Get the Max Number of Threads this Pool can contain.
- virtual void **setMaxThreads** (std::size_t maxThreads)
Sets the Max number of threads this pool can contain.
- virtual std::size_t **getBlockSize** () const
Gets the Max number of threads that can be allocated at a time when new threads are needed.
- virtual void **setBlockSize** (std::size_t blockSize)
Sets the Max number of Threads that can be allocated at a time when the Thread Pool determines that more Threads are needed.
- virtual std::size_t **getFreeThreadCount** () const
Returns the current number of available threads in the pool, threads that are performing a user task are considered unavailable.

- virtual void **onTaskStarted** (**PooledThread** *thread)

Called by a pooled thread when it is about to begin executing a new task.

- virtual void **onTaskCompleted** (**PooledThread** *thread)

Called by a pooled thread when it has completed a task and is going back to waiting for another task to run, this will increment the free threads counter.

- virtual void **onTaskException** (**PooledThread** *thread, **lang::Exception** &ex)

*Called by a pooled thread when it has encountered an exception while running a user task, after receiving this notification the callee should assume that the **PooledThread** (p. 2968) is now no longer running.*

Static Public Member Functions

- static **ThreadPool** * **getInstance** ()

Return the one and only Thread Pool instance.

Static Public Attributes

- static const size_t **DEFAULT__MAX__POOL__SIZE** = 10
- static const size_t **DEFAULT__MAX__BLOCK__SIZE** = 3

6.812.1 Detailed Description

Defines a Thread Pool object that implements the functionality of pooling threads to perform user tasks. The Thread Pool has max size that it will grow to. The thread pool allocates threads in blocks. When there are no waiting worker threads and a task is queued then a new batch is allocated. The user can specify the size of the blocks, otherwise a default value is used.

When the user queues a task they must also queue a listener to be notified when the task has completed, this provides the user with a mechanism to know when a task object can be freed.

To have the Thread Pool perform a task, the user enqueue's an object that implements the **Runnable** interface and one of the worker threads will execute it in its thread context.

6.812.2 Member Typedef Documentation

6.812.2.1 `typedef std::pair<lang::Runnable*, TaskListener*>
decaf::util::concurrent::ThreadPool::Task`

6.812.3 Constructor & Destructor Documentation

6.812.3.1 `decaf::util::concurrent::ThreadPool::ThreadPool ()`

6.812.3.2 `virtual decaf::util::concurrent::ThreadPool::~~ThreadPool ()` [virtual]

6.812.4 Member Function Documentation

6.812.4.1 `virtual Task decaf::util::concurrent::ThreadPool::deQueueTask () throw (
lang::Exception)` [virtual]

DeQueue a task to be completed by one of the Pooled Threads. A caller of this method will block until there is something in the tasks queue, therefore care must be taken when calling this function. Normally clients of **ThreadPool** (p.3777) don't use this, only the **PooledThread** (p.2968) objects owned by this **ThreadPool** (p.3777).

Returns:

object that derives from Runnable

Exceptions:

ActiveMQException

6.812.4.2 `virtual std::size_t decaf::util::concurrent::ThreadPool::getBacklog ()
const` [inline, virtual]

Returns the current backlog of items in the tasks queue, this is how much work is still waiting to get done.

Returns:

number of outstanding tasks.

6.812.4.3 `virtual std::size_t decaf::util::concurrent::ThreadPool::getBlockSize ()
const` [inline, virtual]

Gets the Max number of threads that can be allocated at a time when new threads are needed.

Returns:

max Thread Block Size

6.812.4.4 `virtual std::size_t de-
caf::util::concurrent::ThreadPool::getFreeThreadCount ()
const` [inline, virtual]

Returns the current number of available threads in the pool, threads that are performing a user task are considered unavailable. This value could change immediately after calling as Threads

could finish right after and be available again. This is informational only.

Returns:

total free threads

6.812.4.5 static ThreadPool* decaf::util::concurrent::ThreadPool::getInstance ()
[static]

Return the one and only Thread Pool instance.

Returns:

The Thread Pool Pointer

6.812.4.6 virtual std::size_t decaf::util::concurrent::ThreadPool::getMaxThreads ()
const [inline, virtual]

Get the Max Number of Threads this Pool can contain.

Returns:

max size

6.812.4.7 virtual std::size_t decaf::util::concurrent::ThreadPool::getPoolSize ()
const [inline, virtual]

Returns the current number of Threads in the Pool, this is how many there are now, not how many are active or the max number that might exist.

Returns:

integer number of threads in existence.

6.812.4.8 virtual void decaf::util::concurrent::ThreadPool::onTaskCompleted
(PooledThread * *thread*) [virtual]

Called by a pooled thread when it has completed a task and is going back to waiting for another task to run, this will increment the free threads counter.

Parameters:

thread Pointer the the Pooled Thread that is making this call.

Implements **decaf::util::concurrent::PooledThreadListener** (p. 2971).

6.812.4.9 virtual void decaf::util::concurrent::ThreadPool::onTaskException
(PooledThread * *thread*, lang::Exception & *ex*) [virtual]

Called by a pooled thread when it has encountered an exception while running a user task, after receiving this notification the callee should assume that the **PooledThread** (p. 2968) is now no longer running.

Parameters:

thread Pointer to the Pooled Thread that is making this call

ex The Exception that occurred.

Implements **decaf::util::concurrent::PooledThreadListener** (p. 2972).

6.812.4.10 **virtual void decaf::util::concurrent::ThreadPool::onTaskStarted** (PooledThread * *thread*) [virtual]

Called by a pooled thread when it is about to begin executing a new task. This will decrement the available threads counter so that this object knows when there are no more free threads and must create new ones.

Parameters:

thread Pointer to the Pooled Thread that is making this call

Implements **decaf::util::concurrent::PooledThreadListener** (p. 2972).

6.812.4.11 **virtual void decaf::util::concurrent::ThreadPool::queueTask** (Task *task*) throw (lang::Exception) [virtual]

Queue (p. 3149) a task to be completed by one of the Pooled Threads. tasks are serviced as soon as a PooledThread (p. 2968) is available to run it.

Parameters:

task object that derives from Runnable

Exceptions:

ActiveMQException

6.812.4.12 **virtual void decaf::util::concurrent::ThreadPool::reserve** (std::size_t *size*) [virtual]

Ensures that there is at least the specified number of Threads allocated to the pool. If the size is greater than the MAX number of threads in the pool, then only MAX threads are reserved. If the size is smaller than the number of threads currently in the pool, than nothing is done.

Parameters:

size the number of threads to reserve.

6.812.4.13 **virtual void decaf::util::concurrent::ThreadPool::setBlockSize** (std::size_t *blockSize*) [virtual]

Sets the Max number of Threads that can be allocated at a time when the Thread Pool determines that more Threads are needed.

Parameters:

blockSize Max Thread Block Size

6.812.4.14 `virtual void decaf::util::concurrent::ThreadPool::setMaxThreads`
 (`std::size_t maxThreads`) [virtual]

Sets the Max number of threads this pool can contain. if this value is smaller than the current size of the pool nothing is done.

Parameters:

maxThreads total number of threads that can be pooled

6.812.5 Field Documentation

6.812.5.1 `const size_t decaf::util::concurrent::ThreadPool::DEFAULT_MAX_BLOCK_SIZE = 3` [static]

6.812.5.2 `const size_t decaf::util::concurrent::ThreadPool::DEFAULT_MAX_POOL_SIZE = 10` [static]

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/ThreadPool.h`

6.813 decaf::lang::Throwable Class Reference

This class represents an error that has occurred.

#include <src/main/decaf/lang/Throwable.h> Inheritance diagram for decaf::lang::Throwable:

Public Member Functions

- **Throwable** () throw ()
- virtual ~**Throwable** () throw ()
- virtual std::string **getMessage** () const =0
Gets the cause of the error, if no message was provided to the instance of this interface but a cause was then the value cause.getMessage is then returned.
- virtual const std::exception * **getCause** () const =0
*Gets the exception that caused this one to be thrown, this allows for chaining of **exceptions** (p. 159) in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.*
- virtual void **initCause** (const std::exception *cause)=0
Initializes the contained cause exception with the one given.
- virtual void **setMark** (const char *file, const int lineNumber)=0
Adds a file/line number to the stack trace.
- virtual **Throwable** * **clone** () const =0
Clones this exception.
- virtual std::vector< std::pair< std::string, int > > **getStackTrace** () const =0
Provides the stack trace for every point where this exception was caught, marked, and rethrown.
- virtual void **printStackTrace** () const =0
Prints the stack trace to std::err.
- virtual void **printStackTrace** (std::ostream &stream) const =0
Prints the stack trace to the given output stream.
- virtual std::string **getStackTraceString** () const =0
Gets the stack trace as one contiguous string.

6.813.1 Detailed Description

This class represents an error that has occurred. All Exceptions in the Decaf library should extend from this or from the **Exception** (p. 1831) class in order to ensure that all Decaf Exceptions are interchangeable with the std::exception class.

Throwable (p. 3783) can wrap another **Throwable** (p. 3783) as the cause if the error being thrown. The user can inspect the cause by calling `getCause`, the pointer returned is the property of the **Throwable** (p. 3783) instance and will be deleted when it is deleted or goes out of scope.

Since:

1.0

6.813.2 Constructor & Destructor Documentation

6.813.2.1 `decaf::lang::Throwable::Throwable () throw () [inline]`

6.813.2.2 `virtual decaf::lang::Throwable::~~Throwable () throw () [inline, virtual]`

6.813.3 Member Function Documentation

6.813.3.1 `virtual Throwable* decaf::lang::Throwable::clone () const [pure virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

Copy of this **Exception** (p. 1831) object

Implemented	in	activemq::exceptions::ActiveMQException
(p. 358),	activemq::exceptions::BrokerException	(p. 867), de-
caf::internal::net::ssl::openssl::OpenSSLSocketException	(p. 2873),	de-
caf::io::EOFException	(p. 1827), decaf::io::InterruptedIOException	(p. 2129),
decaf::io::IOException	(p. 2144), decaf::io::UnsupportedEncodingException	(p. 3968),
(p. 3915),	decaf::io::UTFDataFormatException	(p. 3968),
decaf::lang::Exception	(p. 1834), decaf::lang::exceptions::ClassCastException	(p. 1993),
(p. 1147),	decaf::lang::exceptions::IllegalArgumentException	(p. 1993),
decaf::lang::exceptions::IllegalMonitorStateException	(p. 1996),	
decaf::lang::exceptions::IllegalStateException	(p. 2000),	de-
caf::lang::exceptions::IllegalThreadStateException	(p. 2003),	de-
caf::lang::exceptions::IndexOutOfBoundsException	(p. 2010),	de-
caf::lang::exceptions::InterruptedException	(p. 2126),	de-
caf::lang::exceptions::InvalidStateException	(p. 2141),	de-
caf::lang::exceptions::NoSuchElementException	(p. 2828),	de-
caf::lang::exceptions::NullPointerException	(p. 2834),	de-
caf::lang::exceptions::NumberFormatException	(p. 2840),	
decaf::lang::exceptions::RuntimeException	(p. 3330),	de-
caf::lang::exceptions::UnsupportedOperationException	(p. 3918),	de-
caf::net::BindException	(p. 838), decaf::net::ConnectException	(p. 1261), de-
caf::net::HttpRetryException	(p. 1988), decaf::net::MalformedURLException	(p. 2458),
decaf::net::NoRouteToHostException	(p. 2822), decaf::net::PortUnreachableException	(p. 3522),
(p. 2975), decaf::net::ProtocolException	(p. 3139), decaf::net::SocketException	(p. 3522),
decaf::net::SocketTimeoutException	(p. 3544), decaf::net::UnknownHostException	(p. 3909),
decaf::net::UnknownServiceException	(p. 3912),	de-
caf::net::URISyntaxException	(p. 3950), decaf::nio::BufferOverflowException	(p. 956),
decaf::nio::BufferUnderflowException	(p. 959),	de-
decaf::nio::InvalidMarkException	(p. 2137), decaf::nio::ReadOnlyBufferException	

(p. 3171), **decaf::security::cert::CertificateEncodingException**
 (p. 1091), **decaf::security::cert::CertificateException** (p. 1093), **de-**
caf::security::cert::CertificateExpiredException (p. 1095), **de-**
caf::security::cert::CertificateNotYetValidException (p. 1097),
decaf::security::cert::CertificateParsingException (p. 1099),
decaf::security::GeneralSecurityException (p. 1973), **de-**
caf::security::InvalidKeyException (p. 2134), **decaf::security::KeyException**
 (p. 2297), **decaf::security::KeyManagementException** (p. 2300),
decaf::security::NoSuchAlgorithmException (p. 2825), **de-**
caf::security::NoSuchProviderException (p. 2831), **decaf::security::SignatureException**
 (p. 3499), **decaf::util::concurrent::BrokenBarrierException** (p. 862),
decaf::util::concurrent::CancellationException (p. 1085), **de-**
caf::util::concurrent::ExecutionException (p. 1868), **de-**
caf::util::concurrent::RejectedExecutionException (p. 3191),
decaf::util::concurrent::TimeoutException (p. 3789), **de-**
caf::util::zip::DataFormatException (p. 1557), and **decaf::util::zip::ZipException**
 (p. 4066).

6.813.3.2 virtual const std::exception* decaf::lang::Throwable::getCause () const
 [pure virtual]

Gets the exception that caused this one to be thrown, this allows for chaining of **exceptions** (p. 159) in the case of a method that throws only a particular exception but wishes to allow for the real causal exception to be passed only in case the caller knows about that type of exception and wishes to respond to it.

Returns:

a const pointer reference to the causal exception, if there was no cause associated with this exception then NULL is returned.

Implemented in **decaf::lang::Exception** (p. 1835).

6.813.3.3 virtual std::string decaf::lang::Throwable::getMessage () const [pure virtual]

Gets the cause of the error, if no message was provided to the instance of this interface but a cause was then the value cause.getMessage is then returned.

Returns:

string errors message

Implemented in **decaf::lang::Exception** (p. 1835).

6.813.3.4 virtual std::vector< std::pair< std::string, int> >
decaf::lang::Throwable::getStackTrace () const [pure virtual]

Provides the stack trace for every point where this exception was caught, marked, and rethrown.

Returns:

vector containing stack trace strings

Implemented in **decaf::lang::Exception** (p. 1835).

6.813.3.5 virtual std::string decaf::lang::Throwable::getStackTraceString () const [pure virtual]

Gets the stack trace as one contiguous string.

Returns:

string with formatted stack trace data

Implemented in **decaf::lang::Exception** (p. 1835).

6.813.3.6 virtual void decaf::lang::Throwable::initCause (const std::exception * *cause*) [pure virtual]

Initializes the contained cause exception with the one given. A copy is made to avoid ownership issues.

Parameters:

cause The exception that was the cause of this one.

Implemented in **decaf::lang::Exception** (p. 1836).

6.813.3.7 virtual void decaf::lang::Throwable::printStackTrace (std::ostream & *stream*) const [pure virtual]

Prints the stack trace to the given output stream.

Parameters:

stream the target output stream.

Implemented in **decaf::lang::Exception** (p. 1836).

6.813.3.8 virtual void decaf::lang::Throwable::printStackTrace () const [pure virtual]

Prints the stack trace to std::err.

Implemented in **decaf::lang::Exception** (p. 1836).

6.813.3.9 virtual void decaf::lang::Throwable::setMark (const char * *file*, const int *lineNumber*) [pure virtual]

Adds a file/line number to the stack trace.

Parameters:

file The name of the file calling this method (use `__FILE__`).

lineNumber The line number in the calling file (use `__LINE__`).

Implemented in **decaf::lang::Exception** (p. 1836).

The documentation for this class was generated from the following file:

- `src/main/decaf/lang/Throwable.h`

6.814 decaf::util::concurrent::TimeoutException Class Reference

#include <src/main/decaf/util/concurrent/TimeoutException.h> Inheritance diagram for decaf::util::concurrent::TimeoutException:

Public Member Functions

- **TimeoutException** () throw ()
Default Constructor.
- **TimeoutException** (const **decaf::lang::Exception** &ex) throw ()
Conversion Constructor from some other Exception.
- **TimeoutException** (const **TimeoutException** &ex) throw ()
Copy Constructor.
- **TimeoutException** (const std::exception *cause) throw ()
Constructor.
- **TimeoutException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **TimeoutException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **TimeoutException** * clone () const
Clones this exception.
- virtual ~**TimeoutException** () throw ()

6.814.1 Constructor & Destructor Documentation

6.814.1.1 decaf::util::concurrent::TimeoutException::TimeoutException () throw () [inline]

Default Constructor.

6.814.1.2 decaf::util::concurrent::TimeoutException::TimeoutException (const decaf::lang::Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.814.1.3 decaf::util::concurrent::TimeoutException::TimeoutException (const TimeoutException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex The exception to copy from.

References decaf::lang::Exception::Exception().

6.814.1.4 decaf::util::concurrent::TimeoutException::TimeoutException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.814.1.5 decaf::util::concurrent::TimeoutException::TimeoutException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The string message to report

... list of primitives that are formatted into the message

6.814.1.6 decaf::util::concurrent::TimeoutException::TimeoutException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The string message to report

... list of primitives that are formatted into the message

6.814.1.7 `virtual decaf::util::concurrent::TimeoutException::~~TimeoutException ()
throw () [inline, virtual]`

6.814.2 Member Function Documentation

6.814.2.1 `virtual TimeoutException* decaf::util::concurrent::TimeoutException::clone () const
[inline, virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new **TimeoutException** (p.3787) that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p.1834).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/TimeoutException.h`

6.815 decaf::util::Timer Class Reference

A facility for threads to schedule tasks for future execution in a background thread.

```
#include <src/main/decaf/util/Timer.h>
```

Public Member Functions

- **Timer** ()
- virtual **~Timer** ()
- void **cancel** ()
Terminates this timer, discarding any currently scheduled tasks.
- std::size_t **purge** ()
Removes all canceled tasks from this timer's task queue.
- void **schedule** (**TimerTask** *task, long long delay) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for execution after the specified delay.
- void **schedule** (const **decaf::lang::Pointer**< **TimerTask** > &task, long long delay) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for execution after the specified delay.
- void **schedule** (**TimerTask** *task, const **Date** &time) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for execution at the specified time.
- void **schedule** (const **decaf::lang::Pointer**< **TimerTask** > &task, const **Date** &time) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for execution at the specified time.
- void **schedule** (**TimerTask** *task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for repeated fixed-delay execution, beginning after the specified delay.
- void **schedule** (const **decaf::lang::Pointer**< **TimerTask** > &task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)
Schedules the specified task for repeated fixed-delay execution, beginning after the specified delay.

- void **schedule** (**TimerTask** *task, const **Date** &firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-delay execution, beginning at the specified time.

- void **schedule** (const decaf::lang::Pointer< **TimerTask** > &task, const **Date** &firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-delay execution, beginning at the specified time.

- void **scheduleAtFixedRate** (**TimerTask** *task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-rate execution, beginning after the specified delay.

- void **scheduleAtFixedRate** (const decaf::lang::Pointer< **TimerTask** > &task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-rate execution, beginning after the specified delay.

- void **scheduleAtFixedRate** (**TimerTask** *task, const **Date** &firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-rate execution, beginning at the specified time.

- void **scheduleAtFixedRate** (const decaf::lang::Pointer< **TimerTask** > &task, const **Date** &firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-rate execution, beginning at the specified time.

6.815.1 Detailed Description

A facility for threads to schedule tasks for future execution in a background thread. Tasks may be scheduled for one-time execution, or for repeated execution at regular intervals.

Corresponding to each **Timer** (p. 3790) object is a single background thread that is used to execute all of the timer's tasks, sequentially. **Timer** (p. 3790) tasks should complete quickly. If a timer task takes excessive time to complete, it "hogs" the timer's task execution thread. This can, in turn, delay the execution of subsequent tasks, which may "bunch up" and execute in rapid succession when (and if) the offending task finally completes.

This class is thread-safe: multiple threads can share a single **Timer** (p. 3790) object without the need for external synchronization.

This class does not offer real-time guarantees: it schedules tasks using the wait(long) method.

Since:

1.0

6.815.2 Constructor & Destructor Documentation

6.815.2.1 `decaf::util::Timer::Timer ()`

6.815.2.2 `virtual decaf::util::Timer::~~Timer () [virtual]`

6.815.3 Member Function Documentation

6.815.3.1 `void decaf::util::Timer::cancel ()`

Terminates this timer, discarding any currently scheduled tasks. Does not interfere with a currently executing task (if it exists). Once a timer has been terminated, its execution thread terminates gracefully, and no more tasks may be scheduled on it.

Note that calling this method from within the run method of a timer task that was invoked by this timer absolutely guarantees that the ongoing task execution is the last task execution that will ever be performed by this timer.

This method may be called repeatedly; the second and subsequent calls have no effect.

6.815.3.2 `std::size_t decaf::util::Timer::purge ()`

Removes all canceled tasks from this timer's task queue. Calling this method has no effect on the behavior of the timer, but eliminates the canceled tasks from the queue causing the **Timer** (p. 3790) to destroy the **TimerTask** (p. 3801) pointer it was originally given, the caller should ensure that they no longer have any references to TimerTasks that were previously scheduled.

Most programs will have no need to call this method. It is designed for use by the rare application that cancels a large number of tasks. Calling this method trades time for space: the runtime of the method may be proportional to $n + c \log n$, where n is the number of tasks in the queue and c is the number of canceled tasks.

This method can be called on a **Timer** (p. 3790) object that has no scheduled tasks without error.

Returns:

the number of tasks removed from the queue.

6.815.3.3 `void decaf::util::Timer::schedule (const decaf::lang::Pointer< TimerTask > & task, const Date & firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for repeated fixed-delay execution, beginning at the specified time. Subsequent executions take place at approximately regular intervals separated by the specified period.

In fixed-delay execution, each execution is scheduled relative to the actual execution time of the previous execution. If an execution is delayed for any reason (such as other background activity),

subsequent executions will be delayed as well. In the long run, the frequency of execution will generally be slightly lower than the reciprocal of the specified period (assuming the system clock underlying `Object.wait(long long)` is accurate).

Fixed-delay execution is appropriate for recurring activities that require "smoothness." In other words, it is appropriate for activities where it is more important to keep the frequency accurate in the short run than in the long run. This includes most animation tasks, such as blinking a cursor at regular intervals. It also includes tasks wherein regular activity is performed in response to human input, such as automatically repeating a character as long as a key is held down.

Parameters:

task - task to be scheduled.

firstTime - First time at which task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if `time.getTime()` is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.4 `void decaf::util::Timer::schedule (TimerTask * task,
const Date & firstTime, long long period) throw
(decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for repeated fixed-delay execution, beginning at the specified time. Subsequent executions take place at approximately regular intervals separated by the specified period.

The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its **TimerTask**'s once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

In fixed-delay execution, each execution is scheduled relative to the actual execution time of the previous execution. If an execution is delayed for any reason (such as other background activity), subsequent executions will be delayed as well. In the long run, the frequency of execution will generally be slightly lower than the reciprocal of the specified period (assuming the system clock underlying `Object.wait(long long)` is accurate).

Fixed-delay execution is appropriate for recurring activities that require "smoothness." In other words, it is appropriate for activities where it is more important to keep the frequency accurate in the short run than in the long run. This includes most animation tasks, such as blinking a cursor at regular intervals. It also includes tasks wherein regular activity is performed in response to human input, such as automatically repeating a character as long as a key is held down.

Parameters:

task - task to be scheduled.

firstTime - First time at which task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if time.getTime() is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

```
6.815.3.5 void decaf::util::Timer::schedule (const decaf::lang::Pointer<
TimerTask > & task, long long delay, long long period)
throw ( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException )
```

Schedules the specified task for repeated fixed-delay execution, beginning after the specified delay. Subsequent executions take place at approximately regular intervals separated by the specified period.

In fixed-delay execution, each execution is scheduled relative to the actual execution time of the previous execution. If an execution is delayed for any reason (such as other background activity), subsequent executions will be delayed as well. In the long run, the frequency of execution will generally be slightly lower than the reciprocal of the specified period (assuming the system clock underlying Object.wait(long long) is accurate).

Fixed-delay execution is appropriate for recurring activities that require "smoothness." In other words, it is appropriate for activities where it is more important to keep the frequency accurate in the short run than in the long run. This includes most animation tasks, such as blinking a cursor at regular intervals. It also includes tasks wherein regular activity is performed in response to human input, such as automatically repeating a character as long as a key is held down.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + System.currentTimeMillis() is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

```
6.815.3.6 void decaf::util::Timer::schedule (TimerTask * task, long long delay,
long long period) throw ( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException )
```

Schedules the specified task for repeated fixed-delay execution, beginning after the specified delay. Subsequent executions take place at approximately regular intervals separated by the specified

period.

The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its **TimerTask**'s once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

In fixed-delay execution, each execution is scheduled relative to the actual execution time of the previous execution. If an execution is delayed for any reason (such as other background activity), subsequent executions will be delayed as well. In the long run, the frequency of execution will generally be slightly lower than the reciprocal of the specified period (assuming the system clock underlying `Object.wait(long long)` is accurate).

Fixed-delay execution is appropriate for recurring activities that require "smoothness." In other words, it is appropriate for activities where it is more important to keep the frequency accurate in the short run than in the long run. This includes most animation tasks, such as blinking a cursor at regular intervals. It also includes tasks wherein regular activity is performed in response to human input, such as automatically repeating a character as long as a key is held down.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + `System.currentTimeMillis()` is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

```
6.815.3.7 void decaf::util::Timer::schedule (const decaf::lang::Pointer<
TimerTask > & task, const Date & time) throw
( decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException )
```

Schedules the specified task for execution at the specified time. If the time is in the past, the task is scheduled for immediate execution.

Parameters:

task - task to be scheduled.

time - time at which task is to be executed.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if `time.getTime()` is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.8 void decaf::util::Timer::schedule (TimerTask * *task*, const Date & *time*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for execution at the specified time. If the time is in the past, the task is scheduled for immediate execution.

The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its TimerTask's once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

Parameters:

task - task to be scheduled.

time - time at which task is to be executed.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if time.getTime() is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.9 void decaf::util::Timer::schedule (const decaf::lang::Pointer< TimerTask > & *task*, long long *delay*) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for execution after the specified delay.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + System.currentTimeMillis() is negative.

IllegalStateException - if task was already scheduled or cancelled, or timer was cancelled.

6.815.3.10 `void decaf::util::Timer::schedule (TimerTask * task, long long delay) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for execution after the specified delay. The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its **TimerTask**'s once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + System.currentTimeMillis() is negative.

IllegalStateException - if task was already scheduled or cancelled, or timer was cancelled.

6.815.3.11 `void decaf::util::Timer::scheduleAtFixedRate (const decaf::lang::Pointer< TimerTask > & task, const Date & firstTime, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for repeated fixed-rate execution, beginning at the specified time. Subsequent executions take place at approximately regular intervals, separated by the specified period.

In fixed-rate execution, each execution is scheduled relative to the scheduled execution time of the initial execution. If an execution is delayed for any reason (such as garbage collection or other background activity), two or more executions will occur in rapid succession to "catch up." In the long run, the frequency of execution will be exactly the reciprocal of the specified period (assuming the system clock underlying Object.wait(long) is accurate).

Fixed-rate execution is appropriate for recurring activities that are sensitive to absolute time, such as ringing a chime every hour on the hour, or running scheduled maintenance every day at a particular time. It is also appropriate for recurring activities where the total time to perform a fixed number of executions is important, such as a countdown timer that ticks once every second for ten seconds. Finally, fixed-rate execution is appropriate for scheduling multiple repeating timer tasks that must remain synchronized with respect to one another.

Parameters:

task - task to be scheduled.

firstTime - First time at which task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if time.getTime() is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.12 void decaf::util::Timer::scheduleAtFixedRate (TimerTask
* task, const Date & firstTime, long long period)
throw (decaf::lang::exceptions::NullPointerException,
decaf::lang::exceptions::IllegalArgumentException,
decaf::lang::exceptions::IllegalStateException)

Schedules the specified task for repeated fixed-rate execution, beginning at the specified time. Subsequent executions take place at approximately regular intervals, separated by the specified period.

The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its TimerTask's once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

In fixed-rate execution, each execution is scheduled relative to the scheduled execution time of the initial execution. If an execution is delayed for any reason (such as garbage collection or other background activity), two or more executions will occur in rapid succession to "catch up." In the long run, the frequency of execution will be exactly the reciprocal of the specified period (assuming the system clock underlying Object.wait(long) is accurate).

Fixed-rate execution is appropriate for recurring activities that are sensitive to absolute time, such as ringing a chime every hour on the hour, or running scheduled maintenance every day at a particular time. It is also appropriate for recurring activities where the total time to perform a fixed number of executions is important, such as a countdown timer that ticks once every second for ten seconds. Finally, fixed-rate execution is appropriate for scheduling multiple repeating timer tasks that must remain synchronized with respect to one another.

Parameters:

task - task to be scheduled.

firstTime - First time at which task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if time.getTime() is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.13 `void decaf::util::Timer::scheduleAtFixedRate (const decaf::lang::Pointer< TimerTask > & task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for repeated fixed-rate execution, beginning after the specified delay. Subsequent executions take place at approximately regular intervals, separated by the specified period.

In fixed-rate execution, each execution is scheduled relative to the scheduled execution time of the initial execution. If an execution is delayed for any reason (such as garbage collection or other background activity), two or more executions will occur in rapid succession to "catch up." In the long run, the frequency of execution will be exactly the reciprocal of the specified period (assuming the system clock underlying `Object.wait(long)` is accurate).

Fixed-rate execution is appropriate for recurring activities that are sensitive to absolute time, such as ringing a chime every hour on the hour, or running scheduled maintenance every day at a particular time. It is also appropriate for recurring activities where the total time to perform a fixed number of executions is important, such as a countdown timer that ticks once every second for ten seconds. Finally, fixed-rate execution is appropriate for scheduling multiple repeating timer tasks that must remain synchronized with respect to one another.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + `System.currentTimeMillis()` is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

6.815.3.14 `void decaf::util::Timer::scheduleAtFixedRate (TimerTask * task, long long delay, long long period) throw (decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::IllegalStateException)`

Schedules the specified task for repeated fixed-rate execution, beginning after the specified delay. Subsequent executions take place at approximately regular intervals, separated by the specified period.

The **TimerTask** (p. 3801) pointer is considered to be owned by the **Timer** (p. 3790) class once it has been scheduled, the **Timer** (p. 3790) will destroy its **TimerTask**'s once they have been cancelled or the **Timer** (p. 3790) itself is cancelled. A **TimerTask** (p. 3801) is considered scheduled only when this method return without throwing an exception, until that time ownership is not considered to have been transferred to the **Timer** (p. 3790) and the caller should ensure that the **TimerTask** (p. 3801) gets deleted if an exception is thrown and no further attempts to schedule that **TimerTask** (p. 3801) instance are planned.

In fixed-rate execution, each execution is scheduled relative to the scheduled execution time of the initial execution. If an execution is delayed for any reason (such as garbage collection or other background activity), two or more executions will occur in rapid succession to "catch up." In the long run, the frequency of execution will be exactly the reciprocal of the specified period (assuming the system clock underlying `Object.wait(long)` is accurate).

Fixed-rate execution is appropriate for recurring activities that are sensitive to absolute time, such as ringing a chime every hour on the hour, or running scheduled maintenance every day at a particular time. It is also appropriate for recurring activities where the total time to perform a fixed number of executions is important, such as a countdown timer that ticks once every second for ten seconds. Finally, fixed-rate execution is appropriate for scheduling multiple repeating timer tasks that must remain synchronized with respect to one another.

Parameters:

task - task to be scheduled.

delay - delay in milliseconds before task is to be executed.

period - time in milliseconds between successive task executions.

Exceptions:

NullPointerException - if the **TimerTask** (p. 3801) value is Null.

IllegalArgumentException - if delay is negative, or delay + `System.currentTimeMillis()` is negative.

IllegalStateException - if task was already scheduled or cancelled, timer was cancelled, or timer thread terminated.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/Timer.h`

6.816 decaf::util::TimerTask Class Reference

A Base class for a task object that can be scheduled for one-time or repeated execution by a **Timer** (p. 3790).

```
#include <src/main/decaf/util/TimerTask.h>Inheritance diagram for decaf::util::TimerTask:
```

Public Member Functions

- **TimerTask** ()
- virtual **~TimerTask** ()
- bool **cancel** ()
Cancels this timer task.
- long long **scheduledExecutionTime** () const
Returns the scheduled execution time of the most recent actual execution of this task.

Protected Member Functions

- bool **isScheduled** () const
- void **setScheduledTime** (long long time)
- long long **getWhen** () const

Friends

- class **Timer**
- class **TimerImpl**
- class **decaf::internal::util::TimerTaskHeap**

6.816.1 Detailed Description

A Base class for a task object that can be scheduled for one-time or repeated execution by a **Timer** (p. 3790).

Since:

1.0

6.816.2 Constructor & Destructor Documentation

6.816.2.1 decaf::util::TimerTask::TimerTask ()

6.816.2.2 virtual decaf::util::TimerTask::~~TimerTask () [inline, virtual]

6.816.3 Member Function Documentation

6.816.3.1 bool decaf::util::TimerTask::cancel ()

Cancels this timer task. If the task has been scheduled for one-time execution and has not yet run, or has not yet been scheduled, it will never run. If the task has been scheduled for repeated execution, it will never run again. (If the task is running when this call occurs, the task will run to completion, but will never run again.)

Note that calling this method from within the run method of a repeating timer task absolutely guarantees that the timer task will not run again.

This method may be called repeatedly; the second and subsequent calls have no effect.

Returns:

true if this task is scheduled for one-time execution and has not yet run, or this task is scheduled for repeated execution. Returns false if the task was scheduled for one-time execution and has already run, or if the task was never scheduled, or if the task was already canceled. (Loosely speaking, this method returns true if it prevents one or more scheduled executions from taking place.)

6.816.3.2 long long decaf::util::TimerTask::getWhen () const [protected]

6.816.3.3 bool decaf::util::TimerTask::isScheduled () const [protected]

6.816.3.4 long long decaf::util::TimerTask::scheduledExecutionTime () const

Returns the scheduled execution time of the most recent actual execution of this task. (If this method is invoked while task execution is in progress, the return value is the scheduled execution time of the ongoing task execution.)

This method is typically invoked from within a task's run method, to determine whether the current execution of the task is sufficiently timely to warrant performing the scheduled activity:

```
void run() (p. 3325) { if( System::currentTimeMillis() - scheduledExecutionTime() (p. 3802)
>= MAX_TARDINESS) return; // Too late; skip this execution. // Perform the task }
```

This method is typically not used in conjunction with fixed-delay execution repeating tasks, as their scheduled execution times are allowed to drift over time, and so are not terribly significant.

Returns:

the time at which the most recent execution of this task was scheduled to occur, in the format returned by **Date.getTime()** (p. 1667). The return value is undefined if the task has yet to commence its first execution.

6.816.3.5 void decaf::util::TimerTask::setScheduledTime (long long *time*)
[protected]

6.816.4 Friends And Related Function Documentation

6.816.4.1 friend class decaf::internal::util::TimerTaskHeap [friend]

6.816.4.2 friend class Timer [friend]

6.816.4.3 friend class TimerImpl [friend]

The documentation for this class was generated from the following file:

- src/main/decaf/util/**TimerTask.h**

6.817 decaf::internal::util::TimerTaskHeap Class Reference

A Binary Heap implemented specifically for the Timer class in Decaf Util.

```
#include <src/main/decaf/internal/util/TimerTaskHeap.h>
```

Public Member Functions

- **TimerTaskHeap** ()
- virtual **~TimerTaskHeap** ()
- **Pointer**< **TimerTask** > **peek** ()

Peaks at the Head of the Heap, returns the task with the nearest scheduled run time.

- bool **isEmpty** () const
- std::size_t **size** () const
- void **insert** (const **Pointer**< **TimerTask** > &task)

Inserts the specified Task into the heap, heap is reordered to reflect the addition of a new element.

- void **remove** (std::size_t pos)

Removes the Task at the specified position from the heap, resorts the heap from the position down to the bottom.

- void **reset** ()

Clear all contents from the heap.

- void **adjustMinimum** ()

Resorts the heap starting at the top.

- std::size_t **deleteIfCancelled** ()

Runs through the heap removing all cancelled Tasks from it, this is not normally used but in case a cancellation of a large number of tasks the user can perform this purge.

- std::size_t **find** (const **Pointer**< **TimerTask** > &task) const

Searches the heap for the specified TimerTask element and returns its position in the heap.

6.817.1 Detailed Description

A Binary Heap implemented specifically for the Timer class in Decaf Util.

Since:

1.0

6.817.2 Constructor & Destructor Documentation

6.817.2.1 `decaf::internal::util::TimerTaskHeap::TimerTaskHeap ()`

6.817.2.2 `virtual decaf::internal::util::TimerTaskHeap::~~TimerTaskHeap ()`
[virtual]

6.817.3 Member Function Documentation

6.817.3.1 `void decaf::internal::util::TimerTaskHeap::adjustMinimum ()`

Resorts the heap starting at the top.

6.817.3.2 `std::size_t decaf::internal::util::TimerTaskHeap::deleteIfCancelled ()`

Runs through the heap removing all cancelled Tasks from it, this is not normally used but in case a cancellation of a large number of tasks the user can perform this purge.

Returns:

the number of task that were removed from the heap because they were cancelled.

6.817.3.3 `std::size_t decaf::internal::util::TimerTaskHeap::find (const Pointer< TimerTask > & task) const`

Searches the heap for the specified TimerTask element and returns its position in the heap. Returns the unsigned equivalent of -1 if the element is not found.

Returns:

the position in the Heap where the Task is stored, or npos.

6.817.3.4 `void decaf::internal::util::TimerTaskHeap::insert (const Pointer< TimerTask > & task)`

Inserts the specified Task into the heap, heap is reordered to reflect the addition of a new element.

Parameters:

task The TimerTask to insert into the heap.

6.817.3.5 `bool decaf::internal::util::TimerTaskHeap::isEmpty () const`

Returns:

true if the heap is empty.

6.817.3.6 `Pointer<TimerTask> decaf::internal::util::TimerTaskHeap::peek ()`

Peaks at the Head of the Heap, returns the task with the nearest scheduled run time.

Returns:

The TimerTask that is scheduled to be executed next if the Heap is empty a Null Pointer value is returned.

6.817.3.7 `void decaf::internal::util::TimerTaskHeap::remove (std::size_t pos)`

Removes the Task at the specified position from the heap, resorts the heap from the position down to the bottom.

Parameters:

pos The position at which to remove the TimerTask and begin a resort of the heap.

6.817.3.8 `void decaf::internal::util::TimerTaskHeap::reset ()`

Clear all contents from the heap.

6.817.3.9 `std::size_t decaf::internal::util::TimerTaskHeap::size () const`**Returns:**

the size of the heap.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/TimerTaskHeap.h`

6.818 decaf::util::concurrent::TimeUnit Class Reference

A **TimeUnit** (p. 3807) represents time durations at a given unit of granularity and provides utility methods to convert across units, and to perform timing and delay operations in these units.

#include <src/main/decaf/util/concurrent/TimeUnit.h> Inheritance diagram for decaf::util::concurrent::TimeUnit:

Public Member Functions

- virtual **~TimeUnit** ()
- long long **convert** (long long sourceDuration, const **TimeUnit** &sourceUnit) const
Convert the given time duration in the given unit to this unit.
- long long **toNanos** (long long duration) const
Equivalent to `NANOSECONDS.convert(duration, this)`.
- long long **toMicros** (long long duration) const
Equivalent to `MICROSECONDS.convert(duration, this)`.
- long long **toMillis** (long long duration) const
Equivalent to `MILLISECONDS.convert(duration, this)`.
- long long **toSeconds** (long long duration) const
Equivalent to `SECONDS.convert(duration, this)`.
- long long **toMinutes** (long long duration) const
Equivalent to `MINUTES.convert(duration, this)`.
- long long **toHours** (long long duration) const
Equivalent to `HOURS.convert(duration, this)`.
- long long **toDays** (long long duration) const
Equivalent to `DAYS.convert(duration, this)`.
- void **timedWait** (**Synchronizable** *obj, long long timeout) const throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException)
Perform a timed `Object.wait` using this time unit.
- void **timedJoin** (decaf::lang::Thread *thread, long long timeout) throw (decaf::lang::exceptions::InterruptedException, decaf::lang::exceptions::NullPointerException)
Perform a timed `Thread.join` using this time unit.
- void **sleep** (long long timeout) const throw (decaf::lang::exceptions::InterruptedException)
Perform a `Thread.sleep` using this unit.

- virtual std::string **toString** () const
*Converts the **TimeUnit** (p. 3807) type to the Name of the **TimeUnit** (p. 3807).*
- virtual int **compareTo** (const **TimeUnit** &value) const
Compares this object with the specified object for order.
- virtual bool **equals** (const **TimeUnit** &value) const
- virtual bool **operator==** (const **TimeUnit** &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **TimeUnit** &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.

Static Public Member Functions

- static const **TimeUnit** & **valueOf** (const std::string &name) throw (decaf::lang::exceptions::IllegalArgumentException)
*Returns the **TimeUnit** (p. 3807) constant of this type with the specified name.*

Static Public Attributes

- static const **TimeUnit** NANoseconds
*The Actual **TimeUnit** (p. 3807) enumerations.*
- static const **TimeUnit** MICROseconds
- static const **TimeUnit** MILLIseconds
- static const **TimeUnit** SECONDS
- static const **TimeUnit** MINUTES
- static const **TimeUnit** HOURS
- static const **TimeUnit** DAYS
- static const **TimeUnit** *const **values** []
*The An Array of **TimeUnit** (p. 3807) Instances.*

Protected Member Functions

- **TimeUnit** (int index, const std::string &name)
Hidden Constructor, this class can not be instantiated directly.

6.818.1 Detailed Description

A **TimeUnit** (p. 3807) represents time durations at a given unit of granularity and provides utility methods to convert across units, and to perform timing and delay operations in these units. A **TimeUnit** (p. 3807) does not maintain time information, but only helps organize and use time representations that may be maintained separately across various contexts. A nanosecond is

defined as one thousandth of a microsecond, a microsecond as one thousandth of a millisecond, a millisecond as one thousandth of a second, a minute as sixty seconds, an hour as sixty minutes, and a day as twenty four hours.

A **TimeUnit** (p. 3807) is mainly used to inform time-based methods how a given timing parameter should be interpreted. For example, the following **code** (p. 1183) will timeout in 50 milliseconds if the lock is not available:

Lock (p. 2375) lock = ...; if (lock.tryLock(50, **TimeUnit.MILLISECONDS** (p. 3815))) ...

while this **code** (p. 1183) will timeout in 50 seconds:

Lock (p. 2375) lock = ...; if (lock.tryLock(50, **TimeUnit.SECONDS** (p. 3816))) ...

Note however, that there is no guarantee that a particular timeout implementation will be able to notice the passage of time at the same granularity as the given **TimeUnit** (p. 3807).

6.818.2 Constructor & Destructor Documentation

6.818.2.1 `decaf::util::concurrent::TimeUnit::TimeUnit (int index, const std::string & name)` [protected]

Hidden Constructor, this class can not be instantiated directly.

Parameters:

index - Index into the Time Unit set.

name - Name of the unit type being represented.

6.818.2.2 `virtual decaf::util::concurrent::TimeUnit::~~TimeUnit ()` [inline, virtual]

6.818.3 Member Function Documentation

6.818.3.1 `virtual int decaf::util::concurrent::TimeUnit::compareTo (const TimeUnit & value) const` [virtual]

Compares this object with the specified object for order. Returns a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than the specified object.

In the foregoing description, the notation `sgn(expression)` designates the mathematical signum function, which is defined to return one of -1, 0, or 1 according to whether the value of expression is negative, zero or positive. The implementor must ensure `sgn(x.compareTo(y)) == -sgn(y.compareTo(x))` for all x and y. (This implies that `x.compareTo(y)` must throw an exception iff `y.compareTo(x)` throws an exception.)

The implementor must also ensure that the relation is transitive: `(x.compareTo(y)>0 && y.compareTo(z)>0)` implies `x.compareTo(z)>0`.

Finally, the implementor must ensure that `x.compareTo(y)==0` implies that `sgn(x.compareTo(z)) == sgn(y.compareTo(z))`, for all z.

It is strongly recommended, but not strictly required that `(x.compareTo(y)==0) == (x.equals(y))`. Generally speaking, any class that implements the Comparable interface and violates this condition should clearly indicate this fact. The recommended language is "Note: this class has a natural ordering that is inconsistent with equals."

Parameters:

value - the Object to be compared.

Returns:

a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than the specified object.

6.818.3.2 long long decaf::util::concurrent::TimeUnit::convert (long long *sourceDuration*, const TimeUnit & *sourceUnit*) const

Convert the given time duration in the given unit to this unit. Conversions from finer to coarser granularities truncate, so lose precision. For example converting 999 milliseconds to seconds results in 0. Conversions from coarser to finer granularities with arguments that would numerically overflow saturate to Long.MIN_VALUE if negative or Long.MAX_VALUE if positive.

For example, to convert 10 minutes to milliseconds, use: TimeUnit.MILLISECONDS.convert(10L, TimeUnit.MINUTES (p. 3815))

Parameters:

sourceDuration - Duration value to convert.

sourceUnit - Unit type of the source duration.

Returns:

the converted duration in this unit, or Long.MIN_VALUE if conversion would negatively overflow, or Long.MAX_VALUE if it would positively overflow.

6.818.3.3 virtual bool decaf::util::concurrent::TimeUnit::equals (const TimeUnit & *value*) const [virtual]**Returns:**

true if this value is considered equal to the passed value.

6.818.3.4 virtual bool decaf::util::concurrent::TimeUnit::operator< (const TimeUnit & *value*) const [virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.818.3.5 `virtual bool decaf::util::concurrent::TimeUnit::operator==(const
TimeUnit & value) const` [virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.818.3.6 `void decaf::util::concurrent::TimeUnit::sleep (long long timeout) const
throw (decaf::lang::exceptions::InterruptedException)`

Perform a `Thread.sleep` using this unit. This is a convenience method that converts time arguments into the form required by the `Thread.sleep` method.

Parameters:

timeout the minimum time to sleep

See also:

`Thread::sleep`

6.818.3.7 `void decaf::util::concurrent::TimeUnit::timedJoin
(decaf::lang::Thread * thread, long long timeout)
throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::exceptions::NullPointerException)`

Perform a timed `Thread.join` using this time unit. This is a convenience method that converts time arguments into the form required by the `Thread.join` method.

Parameters:

thread the thread to wait for

timeout the maximum time to wait

Exceptions:

InterruptedException if interrupted while waiting.

NullPointerException if the thread object is null.

See also:

`Thread::join(long long, long long)`

6.818.3.8 void decaf::util::concurrent::TimeUnit::timedWait
(Synchronizable * *obj*, long long *timeout*) const
throw (decaf::lang::exceptions::InterruptedException,
decaf::lang::exceptions::NullPointerException)

Perform a timed `Object.wait` using this time unit. This is a convenience method that converts timeout arguments into the form required by the `Object.wait` method.

For example, you could implement a blocking `poll` method (see `BlockingQueue.poll` (p. 847)) using:

```
Object poll( long long timeout, const TimeUnit& unit )  
    throw( InterruptedException ) {  
  
    while( empty ) {  
        unit.timedWait(this, timeout);  
        ...  
    }  
}
```

Parameters:

obj the object to wait on

timeout the maximum time to wait.

Exceptions:

InterruptedException if interrupted while waiting.

NullPointerException if the `Synchronizable` (p. 3700) object is null.

See also:

`Synchronizable::wait(long long, long long)`

6.818.3.9 long long decaf::util::concurrent::TimeUnit::toDays (long long *duration*)
const [inline]

Equivalent to `DAYS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration.

See also:

`convert` (p. 3810)

6.818.3.10 `long long decaf::util::concurrent::TimeUnit::toHours (long long duration) const [inline]`

Equivalent to `HOURS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration.

See also:

`convert` (p. 3810)

6.818.3.11 `long long decaf::util::concurrent::TimeUnit::toMicros (long long duration) const [inline]`

Equivalent to `MICROSECONDS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration, or `Long.MIN_VALUE` if conversion would negatively overflow, or `Long.MAX_VALUE` if it would positively overflow.

See also:

`convert` (p. 3810)

6.818.3.12 `long long decaf::util::concurrent::TimeUnit::toMillis (long long duration) const [inline]`

Equivalent to `MILLISECONDS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration, or `Long.MIN_VALUE` if conversion would negatively overflow, or `Long.MAX_VALUE` if it would positively overflow.

See also:

`convert` (p. 3810)

6.818.3.13 `long long decaf::util::concurrent::TimeUnit::toMinutes (long long duration) const [inline]`

Equivalent to `MINUTES.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration.

See also:

`convert` (p. 3810)

6.818.3.14 `long long decaf::util::concurrent::TimeUnit::toNanos (long long duration) const [inline]`

Equivalent to `NANOSECONDS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration, or `Long.MIN_VALUE` if conversion would negatively overflow, or `Long.MAX_VALUE` if it would positively overflow.

See also:

`convert` (p. 3810)

6.818.3.15 `long long decaf::util::concurrent::TimeUnit::toSeconds (long long duration) const [inline]`

Equivalent to `SECONDS.convert(duration, this)`.

Parameters:

duration the duration

Returns:

the converted duration.

See also:

`convert` (p. 3810)

6.818.3.16 `virtual std::string decaf::util::concurrent::TimeUnit::toString () const`
[virtual]

Converts the **TimeUnit** (p. 3807) type to the Name of the **TimeUnit** (p. 3807).

Returns:

String name of the **TimeUnit** (p. 3807)

6.818.3.17 `static const TimeUnit& decaf::util::concurrent::TimeUnit::valueOf`
(const std::string & *name*) throw (de-
caf::lang::exceptions::IllegalArgumentException)
[static]

Returns the **TimeUnit** (p. 3807) constant of this type with the specified name. The string must match exactly an identifier used to declare an **TimeUnit** (p. 3807) constant in this type. (Extraaneous whitespace characters are not permitted.)

Parameters:

name The Name of the **TimeUnit** (p. 3807) constant to be returned.

Returns:

A constant reference to the **TimeUnit** (p. 3807) Constant with the given name.

Exceptions:

IllegalArgumentException if this enum type has no constant with the specified name

6.818.4 Field Documentation

6.818.4.1 `const TimeUnit decaf::util::concurrent::TimeUnit::DAYS` [static]

6.818.4.2 `const TimeUnit decaf::util::concurrent::TimeUnit::HOURS` [static]

6.818.4.3 `const TimeUnit decaf::util::concurrent::TimeUnit::MICROSECONDS`
[static]

6.818.4.4 `const TimeUnit decaf::util::concurrent::TimeUnit::MILLISECONDS`
[static]

6.818.4.5 `const TimeUnit decaf::util::concurrent::TimeUnit::MINUTES` [static]

6.818.4.6 `const TimeUnit decaf::util::concurrent::TimeUnit::NANOSECONDS`
[static]

The Actual **TimeUnit** (p. 3807) enumerations.

6.818.4.7 `const TimeUnit decaf::util::concurrent::TimeUnit::SECONDS` [static]

6.818.4.8 `const TimeUnit* const decaf::util::concurrent::TimeUnit::values[]`
[static]

The An Array of **TimeUnit** (p. 3807) Instances.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/concurrent/TimeUnit.h`

6.819 cms::Topic Class Reference

An interface encapsulating a provider-specific topic name.

#include <src/main/cms/Topic.h> Inheritance diagram for cms::Topic:

Public Member Functions

- virtual `~Topic ()`
- virtual `std::string getTopicName () const =0 throw (CMSEException)`
Gets the name of this topic.

6.819.1 Detailed Description

An interface encapsulating a provider-specific topic name. A **Topic** (p.3817) is a Publish / Subscribe type **Destination** (p.1723). All Messages sent to a **Topic** (p.3817) are broadcast to all Subscribers of that **Topic** (p.3817) unless the Subscriber defines a **Message** (p.2534) selector that filters out that **Message** (p.2534).

Since:

1.0

6.819.2 Constructor & Destructor Documentation

6.819.2.1 virtual `cms::Topic::~~Topic ()` [inline, virtual]

6.819.3 Member Function Documentation

6.819.3.1 virtual `std::string cms::Topic::getTopicName () const throw (CMSEException)` [pure virtual]

Gets the name of this topic.

Returns:

The topic name.

Exceptions:

CMSEException (p.1160) - If an internal error occurs.

Implemented in `activemq::commands::ActiveMQTopic` (p.694).

The documentation for this class was generated from the following file:

- `src/main/cms/Topic.h`

6.820 activemq::state::Tracked Class Reference

#include <src/main/activemq/state/Tracked.h> Inheritance diagram for activemq::state::Tracked:

Public Member Functions

- **Tracked** ()
- **Tracked** (const **Pointer**< **decaf::lang::Runnable** > &runnable)
- virtual **~Tracked** ()
- void **onResponse** ()
- bool **isWaitingForResponse** () const

6.820.1 Constructor & Destructor Documentation

6.820.1.1 **activemq::state::Tracked::Tracked** () [inline]

6.820.1.2 **activemq::state::Tracked::Tracked** (const **Pointer**< **decaf::lang::Runnable** > & *runnable*)

6.820.1.3 virtual **activemq::state::Tracked::~~Tracked** () [inline, virtual]

6.820.2 Member Function Documentation

6.820.2.1 bool **activemq::state::Tracked::isWaitingForResponse** () const [inline]

6.820.2.2 void **activemq::state::Tracked::onResponse** ()

The documentation for this class was generated from the following file:

- src/main/activemq/state/**Tracked.h**

6.821 activemq::commands::TransactionId Class Reference

#include <src/main/activemq/commands/TransactionId.h> Inheritance diagram for activemq::commands::TransactionId:

Public Types

- typedef decaf::lang::PointerComparator< TransactionId > COMPARATOR

Public Member Functions

- TransactionId ()
- TransactionId (const TransactionId &other)
- virtual ~TransactionId ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual TransactionId * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const DataStructure *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const DataStructure *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual int **compareTo** (const TransactionId &value) const
- virtual bool **equals** (const TransactionId &value) const
- virtual bool **operator==** (const TransactionId &value) const
- virtual bool **operator<** (const TransactionId &value) const
- TransactionId & **operator=** (const TransactionId &other)

Static Public Attributes

- static const unsigned char ID_TRANSACTIONID = 0

6.821.1 Member Typedef Documentation

6.821.1.1 typedef decaf::lang::PointerComparator<TransactionId>
activemq::commands::TransactionId::COMPARATOR

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2348), and **activemq::commands::XATransactionId** (p. 4032).

6.821.2 Constructor & Destructor Documentation

6.821.2.1 `activemq::commands::TransactionId::TransactionId ()`

6.821.2.2 `activemq::commands::TransactionId::TransactionId (const TransactionId & other)`

6.821.2.3 `virtual activemq::commands::TransactionId::~~TransactionId ()` [virtual]

6.821.3 Member Function Documentation

6.821.3.1 `virtual TransactionId* activemq::commands::TransactionId::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

Reimplemented in `activemq::commands::LocalTransactionId` (p. 2348), and `activemq::commands::XATransactionId` (p. 4032).

6.821.3.2 `virtual int activemq::commands::TransactionId::compareTo (const TransactionId & value) const` [virtual]

Reimplemented in `activemq::commands::LocalTransactionId` (p. 2348), and `activemq::commands::XATransactionId` (p. 4032).

6.821.3.3 `virtual void activemq::commands::TransactionId::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented in `activemq::commands::LocalTransactionId` (p. 2348), and `activemq::commands::XATransactionId` (p. 4032).

6.821.3.4 `virtual bool activemq::commands::TransactionId::equals (const TransactionId & value) const` [virtual]

Reimplemented in `activemq::commands::LocalTransactionId` (p. 2349), and `activemq::commands::XATransactionId` (p. 4033).

6.821.3.5 virtual bool activemq::commands::TransactionId::equals (const DataStructure * *value*) const [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2349), and **activemq::commands::XATransactionId** (p. 4033).

6.821.3.6 virtual unsigned char activemq::commands::TransactionId::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Implements **activemq::commands::DataStructure** (p. 1662).

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2349), and **activemq::commands::XATransactionId** (p. 4033).

6.821.3.7 virtual bool activemq::commands::TransactionId::operator< (const TransactionId & *value*) const [virtual]

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2349), and **activemq::commands::XATransactionId** (p. 4034).

6.821.3.8 TransactionId& activemq::commands::TransactionId::operator= (const TransactionId & *other*)

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2349), and **activemq::commands::XATransactionId** (p. 4034).

6.821.3.9 virtual bool activemq::commands::TransactionId::operator== (const TransactionId & *value*) const [virtual]

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2350), and **activemq::commands::XATransactionId** (p. 4034).

6.821.3.10 virtual std::string activemq::commands::TransactionId::toString () const [virtual]

Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseDataStructure** (p. 833).

Reimplemented in **activemq::commands::LocalTransactionId** (p. 2350), and **activemq::commands::XATransactionId** (p. 4034).

6.821.4 Field Documentation

6.821.4.1 `const unsigned char activemq::commands::TransactionId::ID_TRANSACTIONID = 0` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/TransactionId.h`

6.822 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3823).

#include <src/main/activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.822.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3823).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.822.2 Constructor & Destructor Documentation

6.822.2.1 `activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.822.2.2 `virtual activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.822.3 Member Function Documentation

6.822.3.1 `virtual void activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller` (p. 2364), and `activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller` (p. 4057).

6.822.3.2 `virtual void activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller` (p. 2365), and `activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller` (p. 4058).

6.822.3.3 `virtual int activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller` (p. 2365), and `activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller` (p. 4058).

6.822.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller** (p. 2365), and **activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller** (p. 4058).

6.822.3.5 **virtual void ac-**
 tivemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller::tightUnmarshal
 (OpenWireFormat * wireFormat, commands::DataStructure
 *** dataStructure, decaf::io::DataInputStream * dataIn,**
 utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller** (p. 2366), and **activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller** (p. 4059).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h`

6.823 activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3827).

#include <src/main/activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.823.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3827).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.823.2 Constructor & Destructor Documentation

6.823.2.1 `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.823.2.2 `virtual activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.823.3 Member Function Documentation

6.823.3.1 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller` (p. 2372), and `activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller` (p. 4049).

6.823.3.2 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller` (p. 2373), and `activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller` (p. 4050).

6.823.3.3 `virtual int activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller` (p. 2373), and `activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller` (p. 4050).

6.823.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.823 activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller Class Reference 3833

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller** (p. 2373), and **activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller** (p. 4050).

6.823.3.5 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException) [virtual]`

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller** (p. 2374), and **activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller** (p. 4051).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h`

6.824 activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3831).

#include <src/main/activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.824.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3831).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.824.2 Constructor & Destructor Documentation

6.824.2.1 `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.824.2.2 `virtual activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.824.3 Member Function Documentation

6.824.3.1 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller` (p. 2356), and `activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller` (p. 4041).

6.824.3.2 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller` (p. 2357), and `activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller` (p. 4042).

6.824.3.3 `virtual int activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller` (p. 2357), and `activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller` (p. 4042).

6.824.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller** (p. 2357), and **activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller** (p. 4042).

6.824.3.5 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller::tightUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

- wireFormat* - describes the wire format of the broker.
- dataStructure* - Object to be un-marshaled.
- dataIn* - BinaryReader that provides that data.
- bs* - BooleanStream stream used to unpack bits from the wire.

Exceptions:

- IOException* if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller** (p. 2358), and **activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller** (p. 4043).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h`

6.825 activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3835).

#include <src/main/activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.825.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3835).
 NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.825.2 Constructor & Destructor Documentation

6.825.2.1 `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.825.2.2 `virtual activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.825.3 Member Function Documentation

6.825.3.1 `virtual void activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller` (p. 2360), and `activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller` (p. 4053).

6.825.3.2 `virtual void activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller** (p. 2361), and **activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller** (p. 4054).

6.825.3.3 `virtual int activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller** (p. 2361), and **activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller** (p. 4054).

6.825.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller** (p. 2361), and **activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller** (p. 4054).

6.825.3.5 **virtual void ac-**
tivemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller::tightUnmarshal
(**OpenWireFormat** * *wireFormat*, **commands::DataStructure**
* *dataStructure*, **decaf::io::DataInputStream** * *dataIn*,
utils::BooleanStream * *bs*) **throw (decaf::io::IOException)** [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller** (p. 2362), and **activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller** (p. 4055).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h`

6.826 activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3839).

#include <src/main/activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)

Write a object instance to data output stream.

6.826.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3839).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.826.2 Constructor & Destructor Documentation

6.826.2.1 `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.826.2.2 `virtual activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.826.3 Member Function Documentation

6.826.3.1 `virtual void activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller` (p. 2368), and `activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller` (p. 4045).

6.826.3.2 `virtual void activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller` (p. 2369), and `activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller` (p. 4046).

6.826.3.3 `virtual int activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller` (p. 2369), and `activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller` (p. 4046).

6.826.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

6.826 activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller Class Reference 3845

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller** (p. 2369), and **activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller** (p. 4046).

```
6.826.3.5 virtual void ac-
      tivemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller::tightUnmarshal
      (OpenWireFormat * wireFormat, commands::DataStructure
      * dataStructure, decaf::io::DataInputStream * dataIn,
      utils::BooleanStream * bs) throw ( decaf::io::IOException ) [virtual]
```

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller** (p. 2370), and **activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller** (p. 4047).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h`

6.827 activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3843).

#include <src/main/activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller:

Public Member Functions

- **TransactionIdMarshaller** ()
- virtual **~TransactionIdMarshaller** ()
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write the booleans that this object uses to a BooleanStream.

- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)

Un-marshal an object instance from the data input stream.

- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)

Write a object instance to data output stream.

6.827.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3843).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.827.2 Constructor & Destructor Documentation

6.827.2.1 `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::TransactionIdMarshaller()` [inline]

6.827.2.2 `virtual activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::~~TransactionIdMarshaller()` [inline, virtual]

6.827.3 Member Function Documentation

6.827.3.1 `virtual void activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1624).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller` (p. 2352), and `activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller` (p. 4037).

6.827.3.2 `virtual void activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::looseUnmarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the `unmarshal`.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1631).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller` (p. 2353), and `activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller` (p. 4038).

6.827.3.3 `virtual int activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1638).

Reimplemented in `activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller` (p. 2353), and `activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller` (p. 4038).

6.827.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::tightMarshal2 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryReader that provides that data sink

bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1645).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller** (p. 2353), and **activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller** (p. 4038).

6.827.3.5 **virtual void ac-**
 tivemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller::tightUnmarshal
 (OpenWireFormat * *wireFormat*, commands::DataStructure
 *** *dataStructure*, decaf::io::DataInputStream * *dataIn*,**
 utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.

dataStructure - Object to be un-marshaled.

dataIn - BinaryReader that provides that data.

bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1652).

Reimplemented in **activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller** (p. 2354), and **activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller** (p. 4039).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h`

6.828 activemq::commands::TransactionInfo Class Reference

#include <src/main/activemq/commands/TransactionInfo.h> Inheritance diagram for activemq::commands::TransactionInfo:

Public Member Functions

- **TransactionInfo** ()
- virtual **~TransactionInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **TransactionInfo** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual const **Pointer**< **ConnectionId** > & **getConnectionId** () const
- virtual **Pointer**< **ConnectionId** > & **getConnectionId** ()
- virtual void **setConnectionId** (const **Pointer**< **ConnectionId** > &connectionId)
- virtual const **Pointer**< **TransactionId** > & **getTransactionId** () const
- virtual **Pointer**< **TransactionId** > & **getTransactionId** ()
- virtual void **setTransactionId** (const **Pointer**< **TransactionId** > &transactionId)
- virtual unsigned char **getType** () const
- virtual void **setType** (unsigned char type)
- virtual bool **isTransactionInfo** () const
- virtual **Pointer**< **Command** > **visit** (activemq::state::CommandVisitor *visitor) throw (exceptions::ActiveMQException)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.

Static Public Attributes

- static const unsigned char **ID_TRANSACTIONINFO** = 7

Protected Attributes

- `Pointer< ConnectionId > connectionId`
- `Pointer< TransactionId > transactionId`
- unsigned char `type`

6.828.1 Constructor & Destructor Documentation

6.828.1.1 `activemq::commands::TransactionInfo::TransactionInfo ()`

6.828.1.2 `virtual activemq::commands::TransactionInfo::~~TransactionInfo ()`
[virtual]

6.828.2 Member Function Documentation

6.828.2.1 `virtual TransactionInfo* activemq::commands::TransactionInfo::cloneDataStructure ()`
`const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.828.2.2 `virtual void activemq::commands::TransactionInfo::copyDataStructure (const DataStructure * src)` [virtual]

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.828.2.3 `virtual bool activemq::commands::TransactionInfo::equals (const DataStructure * value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if `DataStructure`'s are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

- 6.828.2.4** `virtual Pointer<ConnectionId>& activemq::commands::TransactionInfo::getConnectionId ()`
[virtual]
- 6.828.2.5** `virtual const Pointer<ConnectionId>& activemq::commands::TransactionInfo::getConnectionId ()`
const [virtual]
- 6.828.2.6** `virtual unsigned char activemq::commands::TransactionInfo::getDataSetType () const`
[virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSet** (p. 1660) type copy.

Implements **activemq::commands::DataSet** (p. 1662).

- 6.828.2.7** `virtual Pointer<TransactionId>& activemq::commands::TransactionInfo::getTransactionId ()`
[virtual]
- 6.828.2.8** `virtual const Pointer<TransactionId>& activemq::commands::TransactionInfo::getTransactionId ()`
const [virtual]
- 6.828.2.9** `virtual unsigned char activemq::commands::TransactionInfo::getType ()`
const [virtual]
- 6.828.2.10** `virtual bool activemq::commands::TransactionInfo::isTransactionInfo ()`
const [inline, virtual]

Returns:

an answer of true to the **isTransactionInfo()** (p. 3849) query.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

- 6.828.2.11** `virtual void activemq::commands::TransactionInfo::setConnectionId (const Pointer< ConnectionId > & connectionId)` [virtual]
- 6.828.2.12** `virtual void activemq::commands::TransactionInfo::setTransactionId (const Pointer< TransactionId > & transactionId)` [virtual]
- 6.828.2.13** `virtual void activemq::commands::TransactionInfo::setType (unsigned char type)` [virtual]
- 6.828.2.14** `virtual std::string activemq::commands::TransactionInfo::toString ()`
const [virtual]

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

6.828.2.15 `virtual Pointer<Command> activemq::commands::TransactionInfo::visit (activemq::state::CommandVisitor * visitor) throw (exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements `activemq::commands::Command` (p. 1198).

6.828.3 Field Documentation

6.828.3.1 `Pointer<ConnectionId> activemq::commands::TransactionInfo::connectionId` [protected]

6.828.3.2 `const unsigned char activemq::commands::TransactionInfo::ID_TRANSACTIONINFO = 7` [static]

6.828.3.3 `Pointer<TransactionId> activemq::commands::TransactionInfo::transactionId` [protected]

6.828.3.4 `unsigned char activemq::commands::TransactionInfo::type` [protected]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/TransactionInfo.h`

6.829 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3851).

#include <src/main/activemq/wireformat/openwire/marshal/v5/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.829.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3851).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.829.2 Constructor & Destructor Documentation

6.829.2.1 `activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::TransactionInfoMarshaller()` [inline]

6.829.2.2 `virtual activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` [inline, virtual]

6.829.3 Member Function Documentation

6.829.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.829.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.829.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 787).

6.829.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 788).

6.829.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller` (p. 789).

6.829.3.6 virtual void activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 790).

6.829.3.7 virtual void activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller** (p. 791).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**TransactionInfoMarshaller.h**

6.830 activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **TransactionInfoMarshaller** (p.3855).

#include <src/main/activemq/wireformat/openwire/marshal/v1/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.830.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **TransactionInfoMarshaller** (p.3855).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.830.2 Constructor & Destructor Documentation

6.830.2.1 `activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::TransactionInfoMarshaller()` [inline]

6.830.2.2 `virtual activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` [inline, virtual]

6.830.3 Member Function Documentation

6.830.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.830.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.830.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 780).

6.830.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 781).

6.830.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller` (p. 782).

6.830.3.6 virtual void activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 783).

6.830.3.7 virtual void activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller** (p. 784).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**TransactionInfoMarshaller.h**

6.831 activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller Class Reference

Marshaling `code` (p.1183) for Open Wire Format for **TransactionInfoMarshaller** (p.3859).

#include <src/main/activemq/wireformat/openwire/marshal/v3/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.831.1 Detailed Description

Marshaling `code` (p.1183) for Open Wire Format for **TransactionInfoMarshaller** (p.3859).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.831.2 Constructor & Destructor Documentation

6.831.2.1 `activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::TransactionInfoMarshaller()` `[inline]`

6.831.2.2 `virtual activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` `[inline, virtual]`

6.831.3 Member Function Documentation

6.831.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.831.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.831.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 766).

6.831.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 767).

6.831.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller` (p. 768).

6.831.3.6 virtual void activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 769).

6.831.3.7 virtual void activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller** (p. 770).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/TransactionInfoMarshaller.h

6.832 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3863).

#include <src/main/activemq/wireformat/openwire/marshal/v6/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.832.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3863).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.832.2 Constructor & Destructor Documentation

6.832.2.1 `activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::TransactionInfoMarshaller()` [inline]

6.832.2.2 `virtual activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` [inline, virtual]

6.832.3 Member Function Documentation

6.832.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.832.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.832.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 794).

6.832.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 795).

6.832.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller` (p. 796).

6.832.3.6 virtual void activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 797).

6.832.3.7 virtual void activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller** (p. 798).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/TransactionInfoMarshaller.h

6.833 activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3867).

#include <src/main/activemq/wireformat/openwire/marshal/v4/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.833.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3867).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.833.2 Constructor & Destructor Documentation

6.833.2.1 `activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::TransactionInfoMarshaller()` `[inline]`

6.833.2.2 `virtual activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` `[inline, virtual]`

6.833.3 Member Function Documentation

6.833.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::createObject()` `const` `[virtual]`

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.833.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::getDataStructureType()` `const` `[virtual]`

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.833.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` `[virtual]`

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 773).

6.833.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 774).

6.833.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller` (p. 775).

6.833.3.6 virtual void activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 776).

6.833.3.7 virtual void activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller** (p. 777).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/TransactionInfoMarshaller.h

6.834 activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3871).

#include <src/main/activemq/wireformat/openwire/marshal/v2/TransactionInfoMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller:

Public Member Functions

- **TransactionInfoMarshaller** ()
- virtual **~TransactionInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat** *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.834.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3871).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.834.2 Constructor & Destructor Documentation

6.834.2.1 `activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::TransactionInfoMarshaller()` [inline]

6.834.2.2 `virtual activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::~~TransactionInfoMarshaller()` [inline, virtual]

6.834.3 Member Function Documentation

6.834.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.834.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.834.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 801).

6.834.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 802).

6.834.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::tightMarshal1 (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller` (p. 803).

6.834.3.6 virtual void activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 804).

6.834.3.7 virtual void activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller** (p. 805).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/TransactionInfoMarshaller.h

6.835 activemq::state::TransactionState Class Reference

```
#include <src/main/activemq/state/TransactionState.h>
```

Public Member Functions

- **TransactionState** (const **Pointer**< **TransactionId** > &id)
- virtual **~TransactionState** ()
- **std::string toString** () const
- void **addCommand** (const **Pointer**< **Command** > &operation)
- void **checkShutdown** () const
- void **shutdown** ()
- const **StlList**< **Pointer**< **Command** > > & **getCommands** () const
- const **Pointer**< **TransactionId** > & **getId** () const
- void **setPrepared** (bool prepared)
- bool **isPrepared** () const
- void **setPreparedResult** (int preparedResult)
- int **getPreparedResult** () const
- void **addProducerState** (const **Pointer**< **ProducerState** > &producerState)
- **std::vector**< **Pointer**< **ProducerState** > > **getProducerStates** ()

6.835.1 Constructor & Destructor Documentation

6.835.1.1 `activemq::state::TransactionState::TransactionState (const Pointer< TransactionId > & id)`

6.835.1.2 `virtual activemq::state::TransactionState::~~TransactionState ()`
[virtual]

6.835.2 Member Function Documentation

6.835.2.1 `void activemq::state::TransactionState::addCommand (const Pointer< Command > & operation)`

6.835.2.2 `void activemq::state::TransactionState::addProducerState (const Pointer< ProducerState > & producerState)`

6.835.2.3 `void activemq::state::TransactionState::checkShutdown () const`

6.835.2.4 `const StlList< Pointer<Command> >& activemq::state::TransactionState::getCommands () const`
[inline]

6.835.2.5 `const Pointer<TransactionId>& activemq::state::TransactionState::getId () const` [inline]

6.835.2.6 `int activemq::state::TransactionState::getPreparedResult () const`
[inline]

6.835.2.7 `std::vector< Pointer<ProducerState> > activemq::state::TransactionState::getProducerStates ()`

6.835.2.8 `bool activemq::state::TransactionState::isPrepared () const` [inline]

6.835.2.9 `void activemq::state::TransactionState::setPrepared (bool prepared)`
[inline]

6.835.2.10 `void activemq::state::TransactionState::setPreparedResult (int preparedResult)` [inline]

6.835.2.11 `void activemq::state::TransactionState::shutdown ()` [inline]

6.835.2.12 `std::string activemq::state::TransactionState::toString () const`

The documentation for this class was generated from the following file:

- `src/main/activemq/state/TransactionState.h`

6.836 `decaf::internal::util::concurrent::Transferer< E >` Class Template Reference

Shared **internal** (p. 144) API for dual stacks and queues.

`#include <src/main/decaf/internal/util/concurrent/Transferer.h>`Inheritance diagram for `decaf::internal::util::concurrent::Transferer< E >`:

6.836.1 Detailed Description

`template<typename E> class decaf::internal::util::concurrent::Transferer< E >`

Shared **internal** (p. 144) API for dual stacks and queues.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/concurrent/Transferer.h`

6.837 decaf::internal::util::concurrent::TransferQueue< E > Class Template Reference

This extends Scherer-Scott dual queue algorithm, differing, among other ways, by using modes within nodes rather than marked pointers.

#include <src/main/decaf/internal/util/concurrent/TransferQueue.h> Inheritance diagram for decaf::internal::util::concurrent::TransferQueue< E >:

Public Member Functions

- **TransferQueue** ()

*Node class for **TransferQueue** (p. 3878).*

- virtual ~**TransferQueue** ()
- virtual void **transfer** (E *e, bool timed, long long nanos) throw (decaf::util::concurrent::TimeoutException, decaf::lang::exceptions::InterruptedException)

Performs a put.

- virtual E * **transfer** (bool timed, long long nanos) throw (decaf::util::concurrent::TimeoutException, decaf::lang::exceptions::InterruptedException)

Performs a take.

6.837.1 Detailed Description

```
template<typename E> class decaf::internal::util::concurrent::TransferQueue< E >
```

This extends Scherer-Scott dual queue algorithm, differing, among other ways, by using modes within nodes rather than marked pointers. The algorithm is a little simpler than that for stacks because fulfillers do not need explicit nodes, and matching is done by CAS'ing QNode.item field from non-null to null (for put) or vice versa (for take).

6.837.2 Constructor & Destructor Documentation

6.837.2.1 template<typename E > decaf::internal::util::concurrent::TransferQueue< E >::TransferQueue () [inline]

Node class for **TransferQueue** (p. 3878). Tries to cancel by CAS'ing ref to NULL if that succeeds then we mark as cancelled. Returns true if this node is known to be off the queue because its next pointer has been forgotten due to an advanceHead operation.

```
6.837.2.2  template<typename E > virtual
           decaf::internal::util::concurrent::TransferQueue< E
           >::~~TransferQueue () [inline, virtual]
```

6.837.3 Member Function Documentation

```
6.837.3.1  template<typename E > virtual E*
           decaf::internal::util::concurrent::TransferQueue< E
           >::transfer (bool timed, long long nanos) throw
           ( decaf::util::concurrent::TimeoutException, de-
           caf::lang::exceptions::InterruptedException ) [inline,
           virtual]
```

Performs a take.

Parameters:

timed if this operation should timeout
nanos the timeout, in nanoseconds

Returns:

the item provided or received;

Exceptions:

TimeoutException if the operation timed out waiting for the producer to offer an item.
InterruptedException if the thread was interrupted while waiting for the producer to offer an item.

Implements **decaf::internal::util::concurrent::Transferer< E >** (p. 3877).

```
6.837.3.2  template<typename E > virtual void
           decaf::internal::util::concurrent::TransferQueue< E
           >::transfer (E * e, bool timed, long long nanos)
           throw ( decaf::util::concurrent::TimeoutException,
           decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Performs a put.

Parameters:

e the item to be handed to a consumer;
timed if this operation should timeout
nanos the timeout, in nanoseconds

Exceptions:

TimeoutException if the operation timed out waiting for the consumer to accept the item offered.
InterruptedException if the thread was interrupted while waiting for the consumer to accept the item offered.

Implements **decaf::internal::util::concurrent::Transferer< E >** (p. 3877).

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/util/concurrent/TransferQueue.h`

6.838 decaf::internal::util::concurrent::TransferStack< E > Class Template Reference

#include <src/main/decaf/internal/util/concurrent/TransferStack.h> Inheritance diagram for decaf::internal::util::concurrent::TransferStack< E >:

Public Member Functions

- **TransferStack** ()
- virtual **~TransferStack** ()
- virtual void **transfer** (E *e, bool timed, long long nanos) throw (decaf::util::concurrent::TimeoutException, decaf::lang::exceptions::InterruptedException)
Performs a put.
- virtual E * **transfer** (bool timed, long long nanos) throw (decaf::util::concurrent::TimeoutException, decaf::lang::exceptions::InterruptedException)
Performs a take.

```
template<typename E> class decaf::internal::util::concurrent::TransferStack< E >
```

6.838.1 Constructor & Destructor Documentation

6.838.1.1 template<typename E > decaf::internal::util::concurrent::TransferStack< E >::TransferStack () [inline]

6.838.1.2 template<typename E > virtual decaf::internal::util::concurrent::TransferStack< E >::~~TransferStack () [inline, virtual]

6.838.2 Member Function Documentation

6.838.2.1 template<typename E > virtual E* decaf::internal::util::concurrent::TransferStack< E >::transfer (bool *timed*, long long *nanos*) throw (decaf::util::concurrent::TimeoutException, decaf::lang::exceptions::InterruptedException) [inline, virtual]

Performs a take.

Parameters:

timed if this operation should timeout
nanos the timeout, in nanoseconds

Returns:

the item provided or received;

Exceptions:

TimeoutException if the operation timed out waiting for the producer to offer an item.

InterruptedException if the thread was interrupted while waiting for the producer to offer an item.

Implements **decaf::internal::util::concurrent::Transferer< E >** (p. 3877).

```
6.838.2.2  template<typename E > virtual void
           decaf::internal::util::concurrent::TransferStack< E
           >::transfer (E * e,  bool timed,  long long nanos)
           throw ( decaf::util::concurrent::TimeoutException,
           decaf::lang::exceptions::InterruptedException ) [inline, virtual]
```

Performs a put.

Parameters:

e the item to be handed to a consumer;

timed if this operation should timeout

nanos the timeout, in nanoseconds

Exceptions:

TimeoutException if the operation timed out waiting for the consumer to accept the item offered.

InterruptedException if the thread was interrupted while waiting for the consumer to accept the item offered.

Implements **decaf::internal::util::concurrent::Transferer< E >** (p. 3877).

The documentation for this class was generated from the following file:

- src/main/decaf/internal/util/concurrent/**TransferStack.h**

6.839 activemq::transport::Transport Class Reference

Interface for a **transport** (p. 97) layer for command objects.

#include <src/main/activemq/transport/Transport.h> Inheritance diagram for activemq::transport::Transport:

Public Member Functions

- virtual **~Transport** ()
- virtual void **start** ()=0 throw (decaf::io::IOException)
*Starts the **Transport** (p. 3883), the send methods of a **Transport** (p. 3883) will throw an exception if used before the **Transport** (p. 3883) is started.*
- virtual void **stop** ()=0 throw (decaf::io::IOException)
*Stops the **Transport** (p. 3883).*
- virtual void **oneway** (const **Pointer**< **Command** > &command)=0 throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command)=0 throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout)=0 throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)
Sends the given command to the broker and then waits for the response.
- virtual void **setWireFormat** (const **Pointer**< **wireformat::WireFormat** > &wireFormat)=0
*Sets the **WireFormat** instance to use.*
- virtual void **setTransportListener** (**TransportListener** *listener)=0
*Sets the observer of asynchronous events from this **transport** (p. 97).*
- virtual **TransportListener** * **getTransportListener** () const =0
*Gets the observer of asynchronous events from this **transport** (p. 97).*
- virtual **Transport** * **narrow** (const std::type_info &typeId)=0
*Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.*
- virtual bool **isFaultTolerant** () const =0
*Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.*
- virtual bool **isConnected** () const =0

Is the **Transport** (p. 3883) Connected to its Broker.

- virtual bool **isClosed** () const =0

Has the **Transport** (p. 3883) been shutdown and no longer usable.

- virtual std::string **getRemoteAddress** () const =0
- virtual void **reconnect** (const **decaf::net::URI** &uri)=0 throw (decaf::io::IOException)
reconnect to another location

6.839.1 Detailed Description

Interface for a **transport** (p. 97) layer for command objects. Callers can send oneway messages or make synchronous requests. Non-response messages will be delivered to the specified listener object upon receipt. A user of the **Transport** (p. 3883) can set an exception listener to be notified of errors that occurs in Threads that the **Transport** (p. 3883) layer runs. Transports should be given an instance of a WireFormat object when created so that they can turn the built in Commands to / from the required wire format encoding.

6.839.2 Constructor & Destructor Documentation

6.839.2.1 virtual **activemq::transport::Transport::~~Transport** () [inline, virtual]

6.839.3 Member Function Documentation

6.839.3.1 virtual std::string **activemq::transport::Transport::getRemoteAddress** ()
const [pure virtual]

Returns:

the remote address for this connection

Implemented in **activemq::transport::failover::FailoverTransport** (p.1877), **activemq::transport::IOTransport** (p.2147), **activemq::transport::mock::MockTransport** (p.2771), and **activemq::transport::TransportFilter** (p. 3894).

6.839.3.2 virtual **TransportListener*** **activemq::transport::Transport::getTransportListener** ()
const [pure virtual]

Gets the observer of asynchronous events from this **transport** (p. 97).

Returns:

the listener of **transport** (p. 97) events.

Implemented in **activemq::transport::failover::FailoverTransport** (p.1877), **activemq::transport::IOTransport** (p.2147), **activemq::transport::mock::MockTransport** (p.2772), and **activemq::transport::TransportFilter** (p. 3894).

6.839.3.3 virtual bool activemq::transport::Transport::isClosed () const [pure virtual]

Has the **Transport** (p. 3883) been shutdown and no longer usable.

Returns:

true if the **Transport** (p. 3883)

Implemented in **activemq::transport::failover::FailoverTransport** (p.1878), **activemq::transport::IOTransport** (p.2147), **activemq::transport::mock::MockTransport** (p.2772), **activemq::transport::tcp::TcpTransport** (p.3754), and **activemq::transport::TransportFilter** (p.3894).

6.839.3.4 virtual bool activemq::transport::Transport::isConnected () const [pure virtual]

Is the **Transport** (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Implemented in **activemq::transport::failover::FailoverTransport** (p.1878), **activemq::transport::IOTransport** (p.2148), **activemq::transport::mock::MockTransport** (p.2772), **activemq::transport::tcp::TcpTransport** (p.3754), and **activemq::transport::TransportFilter** (p.3894).

6.839.3.5 virtual bool activemq::transport::Transport::isFaultTolerant () const [pure virtual]

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Implemented in **activemq::transport::failover::FailoverTransport** (p.1878), **activemq::transport::IOTransport** (p.2148), **activemq::transport::mock::MockTransport** (p.2773), **activemq::transport::tcp::TcpTransport** (p.3755), and **activemq::transport::TransportFilter** (p.3895).

6.839.3.6 virtual Transport* activemq::transport::Transport::narrow (const std::type_info & *typeId*) [pure virtual]

Narrows down a Chain of Transports to a specific **Transport** (p.3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.

Parameters:

typeId - The type_info of the Object we are searching for.

Returns:

the requested Object. or NULL if its not in this chain.

Implemented in `activemq::transport::failover::FailoverTransport` (p.1879), `activemq::transport::IOTransport` (p.2148), `activemq::transport::mock::MockTransport` (p.2773), and `activemq::transport::TransportFilter` (p.3895).

Referenced by `activemq::transport::failover::FailoverTransport::narrow()`.

6.839.3.7 `virtual void activemq::transport::Transport::oneway (const Pointer< Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]`

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this `transport` (p.97).

Implemented in `activemq::transport::correlator::ResponseCorrelator` (p.3292), `activemq::transport::failover::FailoverTransport` (p.1880), `activemq::transport::inactivity::InactivityMonitor` (p.2006), `activemq::transport::IOTransport` (p.2148), `activemq::transport::logging::LoggingTransport` (p.2404), `activemq::transport::mock::MockTransport` (p.2773), `activemq::transport::TransportFilter` (p.3895), and `activemq::wireformat::openwire::OpenWireFormatNegotiator` (p.2902).

6.839.3.8 `virtual void activemq::transport::Transport::reconnect (const decaf::net::URI & uri) throw (decaf::io::IOException) [pure virtual]`

reconnect to another location

Parameters:

uri

Exceptions:

IOException on failure of if not supported

Implemented in `activemq::transport::failover::FailoverTransport` (p.1880), and `activemq::transport::TransportFilter` (p.3896).

6.839.3.9 `virtual Pointer<Response> activemq::transport::Transport::request (const Pointer< Command > & command, unsigned int timeout) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]`

Sends the given command to the broker and then waits for the response.

Parameters:

command - The command to be sent.
timeout - The time to wait for this response.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.
UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3293), **activemq::transport::failover::FailoverTransport** (p. 1881), **activemq::transport::IOTransport** (p. 2149), **activemq::transport::logging::LoggingTransport** (p. 2404), **activemq::transport::mock::MockTransport** (p. 2774), **activemq::transport::TransportFilter** (p. 3896), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2903).

```
6.839.3.10 virtual Pointer<Response> activemq::transport::Transport::request
            (const Pointer< Command > & command)
            throw ( decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException )
            [pure virtual]
```

Sends the given command to the broker and then waits for the response.

Parameters:

command the command to be sent.

Returns:

the response from the broker.

Exceptions:

IOException if an exception occurs during the read of the command.
UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3293), **activemq::transport::failover::FailoverTransport** (p. 1881), **activemq::transport::IOTransport** (p. 2149), **activemq::transport::logging::LoggingTransport** (p. 2405), **activemq::transport::mock::MockTransport** (p. 2775), **activemq::transport::TransportFilter** (p. 3897), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2903).

```
6.839.3.11 virtual void activemq::transport::Transport::setTransportListener
            (TransportListener * listener) [pure virtual]
```

Sets the observer of asynchronous events from this **transport** (p. 97).

Parameters:

listener the listener of **transport** (p. 97) events.

Implemented in **activemq::transport::failover::FailoverTransport** (p. 1883), **activemq::transport::IOTransport** (p. 2150), **activemq::transport::mock::MockTransport** (p. 2777), and **activemq::transport::TransportFilter** (p. 3897).

6.839.3.12 virtual void activemq::transport::Transport::setWireFormat (const Pointer< wireformat::WireFormat > & *wireFormat*) [pure virtual]

Sets the WireFormat instance to use.

Parameters:

wireFormat The WireFormat the object used to encode / decode **commands** (p. 87).

Implemented in **activemq::transport::IOTransport** (p. 2150), and **activemq::transport::TransportFilter** (p. 3897).

6.839.3.13 virtual void activemq::transport::Transport::start () throw (decaf::io::IOException) [pure virtual]

Starts the **Transport** (p. 3883), the send methods of a **Transport** (p. 3883) will throw an exception if used before the **Transport** (p. 3883) is started.

Exceptions:

IOException if and error occurs while starting the **Transport** (p. 3883).

Implemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3294), **activemq::transport::failover::FailoverTransport** (p. 1884), **activemq::transport::IOTransport** (p. 2150), **activemq::transport::mock::MockTransport** (p. 2777), **activemq::transport::TransportFilter** (p. 3898), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2904).

6.839.3.14 virtual void activemq::transport::Transport::stop () throw (decaf::io::IOException) [pure virtual]

Stops the **Transport** (p. 3883).

Exceptions:

IOException if an error occurs while stopping the **transport** (p. 97).

Implemented in **activemq::transport::failover::FailoverTransport** (p. 1884), **activemq::transport::IOTransport** (p. 2151), **activemq::transport::mock::MockTransport** (p. 2777), and **activemq::transport::TransportFilter** (p. 3898).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/**Transport.h**

6.840 activemq::transport::TransportFactory Class Reference

Defines the interface for Factories that create Transports or TransportFilters.

#include <src/main/activemq/transport/TransportFactory.h> Inheritance diagram for activemq::transport::TransportFactory:

Public Member Functions

- virtual **~TransportFactory** ()
- virtual **Pointer< Transport > create** (const **decaf::net::URI** &location)=0 throw (exceptions::ActiveMQException)
*Creates a fully configured **Transport** (p. 3883) instance which could be a chain of filters and transports.*
- virtual **Pointer< Transport > createComposite** (const **decaf::net::URI** &location)=0 throw (exceptions::ActiveMQException)
*Creates a slimed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.*

6.840.1 Detailed Description

Defines the interface for Factories that create Transports or TransportFilters. The factory should be able to create either a completely configured **Transport** (p. 3883) meaning that it has all the appropriate filters wrapping it, or it should be able to create a slimed down version that is used in composite transports like Failover or Fanout.

Since:

3.0

6.840.2 Constructor & Destructor Documentation

- 6.840.2.1 **virtual activemq::transport::TransportFactory::~~TransportFactory** ()
 [inline, virtual]

6.840.3 Member Function Documentation

- 6.840.3.1 **virtual Pointer<Transport> activemq::transport::TransportFactory::create** (const **decaf::net::URI** & *location*) throw (exceptions::ActiveMQException)
 [pure virtual]

Creates a fully configured **Transport** (p. 3883) instance which could be a chain of filters and transports.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implemented in **activemq::transport::failover::FailoverTransportFactory** (p. 1886), **activemq::transport::mock::MockTransportFactory** (p. 2780), and **activemq::transport::tcp::TcpTransportFactory** (p. 3757).

6.840.3.2 `virtual Pointer<Transport> activemq::transport::TransportFactory::createComposite (const decaf::net::URI & location) throw (exceptions::ActiveMQException)`
[pure virtual]

Creates a slimmed down **Transport** (p. 3883) instance which can be used in composite **transport** (p. 97) instances.

Parameters:

location - URI location to connect to plus any properties to assign.

Exceptions:

ActiveMQException if an error occurs

Implemented in **activemq::transport::failover::FailoverTransportFactory** (p. 1886), **activemq::transport::mock::MockTransportFactory** (p. 2780), and **activemq::transport::tcp::TcpTransportFactory** (p. 3757).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/TransportFactory.h`

6.841 activemq::transport::TransportFilter Class Reference

A filter on the **transport** (p. 97) layer.

#include <src/main/activemq/transport/TransportFilter.h> Inheritance diagram for activemq::transport::TransportFilter:

Public Member Functions

- **TransportFilter** (const **Pointer**< **Transport** > &next)
Constructor.
- virtual ~**TransportFilter** ()
- virtual void **onCommand** (const **Pointer**< **Command** > &command)
Event handler for the receipt of a command.
- virtual void **onException** (const **decaf::lang::Exception** &ex)
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **transportInterrupted** ()
*The **transport** (p. 97) has suffered an interruption from which it hopes to recover.*
- virtual void **transportResumed** ()
*The **transport** (p. 97) has resumed after an interruption.*
- virtual void **oneway** (const **Pointer**< **Command** > &command) throw (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**)
Sends a one-way command.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command) throw (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**)
Not supported by this class - throws an exception.
- virtual **Pointer**< **Response** > **request** (const **Pointer**< **Command** > &command, unsigned int timeout) throw (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**)
Not supported by this class - throws an exception.
- virtual void **setTransportListener** (**TransportListener** *listener)
*Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual **TransportListener** * **getTransportListener** () const
*Gets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).*
- virtual void **setWireFormat** (const **Pointer**< **wireformat::WireFormat** > &wireFormat)
*Sets the **WireFormat** instance to use.*
- virtual void **start** () throw (**decaf::io::IOException**)

Starts this *transport* (p. 97) object and creates the thread for polling on the input stream for *commands* (p. 87).

- virtual void **stop** () throw (decaf::io::IOException)
Stops the Transport (p. 3883).
- virtual void **close** () throw (decaf::io::IOException)
Stops the polling thread and closes the streams.
- virtual **Transport * narrow** (const std::type_info &typeId)
Narrows down a Chain of Transports to a specific Transport (p. 3883) *to allow a higher level transport* (p. 97) *to skip intermediate Transports in certain circumstances.*
- virtual bool **isFaultTolerant** () const
Is this Transport (p. 3883) *fault tolerant, meaning that it will reconnect to a broker on disconnect.*
- virtual bool **isConnected** () const
Is the Transport (p. 3883) *Connected to its Broker.*
- virtual bool **isClosed** () const
Has the Transport (p. 3883) *been shutdown and no longer usable.*
- virtual std::string **getRemoteAddress** () const
- virtual void **reconnect** (const decaf::net::URI &uri) throw (decaf::io::IOException)
reconnect to another location

Protected Member Functions

- void **fire** (const decaf::lang::Exception &ex)
Notify the listener of the thrown Exception.
- void **fire** (const Pointer< Command > &command)
Notify the listener of the new incoming Command.

Protected Attributes

- **Pointer< Transport > next**
The transport (p. 97) *that this filter wraps around.*
- **TransportListener * listener**
Listener of this transport (p. 97).

6.841.1 Detailed Description

A filter on the **transport** (p. 97) layer. **Transport** (p. 3883) filters implement the **Transport** (p. 3883) interface and optionally delegate calls to another **Transport** (p. 3883) object.

Since:

1.0

6.841.2 Constructor & Destructor Documentation

6.841.2.1 `activemq::transport::TransportFilter::TransportFilter (const Pointer< Transport > & next)`

Constructor.

Parameters:

next - the next **Transport** (p. 3883) in the chain

6.841.2.2 `virtual activemq::transport::TransportFilter::~~TransportFilter ()` [inline, virtual]

6.841.3 Member Function Documentation

6.841.3.1 `virtual void activemq::transport::TransportFilter::close () throw (decaf::io::IOException)` [virtual]

Stops the polling thread and closes the streams. This can be called explicitly, but is also called in the destructor. Once this object has been closed, it cannot be restarted.

Exceptions:

IOException if an error occurs while closing the **Transport** (p. 3883).

Implements `decaf::io::Closeable` (p. 1149).

Reimplemented in `activemq::transport::correlator::ResponseCorrelator` (p. 3292), `activemq::transport::inactivity::InactivityMonitor` (p. 2005), `activemq::transport::tcp::TcpTransport` (p. 3753), and `activemq::wireformat::openwire::OpenWireFormatNegotiator` (p. 2902).

6.841.3.2 `void activemq::transport::TransportFilter::fire (const Pointer< Command > & command)` [protected]

Notify the listener of the new incoming Command.

Parameters:

command - the command to send to the listener

6.841.3.3 `void activemq::transport::TransportFilter::fire (const decaf::lang::Exception & ex)` [protected]

Notify the listener of the thrown Exception.

Parameters:

ex - the exception to send to listeners

6.841.3.4 `virtual std::string activemq::transport::TransportFilter::getRemoteAddress ()`
`const` [inline, virtual]

Returns:

the remote address for this connection

Implements `activemq::transport::Transport` (p. 3884).

6.841.3.5 `virtual TransportListener* activemq::transport::TransportFilter::getTransportListener ()`
`const` [inline, virtual]

Gets the observer of asynchronous exceptions (p. 92) from this `transport` (p. 97).

Returns:

The listener of `transport` (p. 97) events.

Implements `activemq::transport::Transport` (p. 3884).

6.841.3.6 `virtual bool activemq::transport::TransportFilter::isClosed ()`
`const` [inline, virtual]

Has the `Transport` (p. 3883) been shutdown and no longer usable.

Returns:

true if the `Transport` (p. 3883)

Implements `activemq::transport::Transport` (p. 3885).

Reimplemented in `activemq::transport::tcp::TcpTransport` (p. 3754).

6.841.3.7 `virtual bool activemq::transport::TransportFilter::isConnected ()`
`const` [inline, virtual]

Is the `Transport` (p. 3883) Connected to its Broker.

Returns:

true if a connection has been made.

Implements `activemq::transport::Transport` (p. 3885).

Reimplemented in `activemq::transport::tcp::TcpTransport` (p. 3754).

6.841.3.8 `virtual bool activemq::transport::TransportFilter::isFaultTolerant () const [inline, virtual]`

Is this **Transport** (p. 3883) fault tolerant, meaning that it will reconnect to a broker on disconnect.

Returns:

true if the **Transport** (p. 3883) is fault tolerant.

Implements **activemq::transport::Transport** (p. 3885).

Reimplemented in **activemq::transport::tcp::TcpTransport** (p. 3755).

6.841.3.9 `virtual Transport* activemq::transport::TransportFilter::narrow (const std::type_info & typeId) [virtual]`

Narrows down a Chain of Transports to a specific **Transport** (p. 3883) to allow a higher level **transport** (p. 97) to skip intermediate Transports in certain circumstances.

Parameters:

typeId - The type_info of the Object we are searching for.

Returns:

the requested Object. or NULL if its not in this chain.

Implements **activemq::transport::Transport** (p. 3885).

6.841.3.10 `virtual void activemq::transport::TransportFilter::onCommand (const Pointer< Command > & command) [virtual]`

Event handler for the receipt of a command.

Parameters:

command - the received command object.

Implements **activemq::transport::TransportListener** (p. 3900).

Reimplemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3292), **activemq::transport::inactivity::InactivityMonitor** (p. 2005), **activemq::transport::logging::LoggingTransport** (p. 2404), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2902).

6.841.3.11 `virtual void activemq::transport::TransportFilter::oneway (const Pointer< Command > & command) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException) [inline, virtual]`

Sends a one-way command. Does not wait for any response from the broker.

Parameters:

command the command to be sent.

Exceptions:

IOException if an exception occurs during writing of the command.

UnsupportedOperationException if this method is not implemented by this **transport** (p. 97).

Implements **activemq::transport::Transport** (p. 3886).

Reimplemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3292), **activemq::transport::inactivity::InactivityMonitor** (p. 2006), **activemq::transport::logging::LoggingTransport** (p. 2404), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2902).

6.841.3.12 **virtual void activemq::transport::TransportFilter::onException (const decaf::lang::Exception & *ex*)** [virtual]

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception to handle.

Implements **activemq::transport::TransportListener** (p. 3901).

Reimplemented in **activemq::transport::inactivity::InactivityMonitor** (p. 2006).

6.841.3.13 **virtual void activemq::transport::TransportFilter::reconnect (const decaf::net::URI & *uri*) throw (decaf::io::IOException)** [virtual]

reconnect to another location

Parameters:

uri

Exceptions:

IOException on failure of if not supported

Implements **activemq::transport::Transport** (p. 3886).

6.841.3.14 **virtual Pointer<Response> activemq::transport::TransportFilter::request (const Pointer< Command > & *command*, unsigned int *timeout*) throw (decaf::io::IOException, decaf::lang::exceptions::UnsupportedOperationException)** [inline, virtual]

Not supported by this class - throws an exception.

Parameters:

command - The command that is sent as a request

timeout - The the time to wait for a response.

Exceptions:*IOException**UnsupportedOperationException.*Implements **activemq::transport::Transport** (p. 3886).Reimplemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3293), **activemq::transport::logging::LoggingTransport** (p. 2404), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2903).

6.841.3.15 **virtual** **Pointer<Response>** **activemq::transport::TransportFilter::request** (**const** **Pointer< Command >** *& command*) **throw** (**decaf::io::IOException**, **decaf::lang::exceptions::UnsupportedOperationException**) [**inline**, **virtual**]

Not supported by this class - throws an exception.

Parameters:*command* the command that is sent as a request**Exceptions:***IOException**UnsupportedOperationException.*Implements **activemq::transport::Transport** (p. 3887).Reimplemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3293), **activemq::transport::logging::LoggingTransport** (p. 2405), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2903).

6.841.3.16 **virtual void** **activemq::transport::TransportFilter::setTransportListener** (**TransportListener *** *listener*) [**inline**, **virtual**]

Sets the observer of asynchronous **exceptions** (p. 92) from this **transport** (p. 97).**Parameters:***listener* the listener of **transport** (p. 97) events.Implements **activemq::transport::Transport** (p. 3887).

6.841.3.17 **virtual void** **activemq::transport::TransportFilter::setWireFormat** (**const** **Pointer< wireformat::WireFormat >** *& wireFormat*) [**inline**, **virtual**]

Sets the WireFormat instance to use.

Parameters:*wireFormat* The WireFormat the object used to encode / decode **commands** (p. 87).Implements **activemq::transport::Transport** (p. 3888).

6.841.3.18 `virtual void activemq::transport::TransportFilter::start () throw (decaf::io::IOException) [virtual]`

Starts this **transport** (p. 97) object and creates the thread for polling on the input stream for **commands** (p. 87). If this object has been closed, throws an exception. Before calling start, the caller must set the IO streams and the reader and writer objects.

Exceptions:

IOException if an error occurs or if this **transport** (p. 97) has already been closed.

Implements **activemq::transport::Transport** (p. 3888).

Reimplemented in **activemq::transport::correlator::ResponseCorrelator** (p. 3294), and **activemq::wireformat::openwire::OpenWireFormatNegotiator** (p. 2904).

6.841.3.19 `virtual void activemq::transport::TransportFilter::stop () throw (decaf::io::IOException) [virtual]`

Stops the **Transport** (p. 3883).

Exceptions:

IOException if an error occurs while stopping the **Transport** (p. 3883).

Implements **activemq::transport::Transport** (p. 3888).

6.841.3.20 `virtual void activemq::transport::TransportFilter::transportInterrupted () [virtual]`

The **transport** (p. 97) has suffered an interruption from which it hopes to recover.

Implements **activemq::transport::TransportListener** (p. 3901).

6.841.3.21 `virtual void activemq::transport::TransportFilter::transportResumed () [virtual]`

The **transport** (p. 97) has resumed after an interruption.

Implements **activemq::transport::TransportListener** (p. 3901).

6.841.4 Field Documentation

6.841.4.1 `TransportListener* activemq::transport::TransportFilter::listener [protected]`

Listener of this **transport** (p. 97).

6.841.4.2 `Pointer<Transport> activemq::transport::TransportFilter::next [protected]`

The **transport** (p. 97) that this filter wraps around.

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/TransportFilter.h`

6.842 activemq::transport::TransportListener Class Reference

A listener of asynchronous **exceptions** (p. 92) from a command **transport** (p. 97) object.

#include <src/main/activemq/transport/TransportListener.h> Inheritance diagram for activemq::transport::TransportListener:

Public Member Functions

- virtual **~TransportListener** ()
- virtual void **onCommand** (const **Pointer**< **Command** > &command)=0
Event handler for the receipt of a command.
- virtual void **onException** (const **decaf::lang::Exception** &ex)=0
*Event handler for an exception from a command **transport** (p. 97).*
- virtual void **transportInterrupted** ()=0
*The **transport** (p. 97) has suffered an interruption from which it hopes to recover.*
- virtual void **transportResumed** ()=0
*The **transport** (p. 97) has resumed after an interruption.*

6.842.1 Detailed Description

A listener of asynchronous **exceptions** (p. 92) from a command **transport** (p. 97) object.

6.842.2 Constructor & Destructor Documentation

- 6.842.2.1 **virtual activemq::transport::TransportListener::~~TransportListener** ()
[inline, virtual]

6.842.3 Member Function Documentation

- 6.842.3.1 **virtual void activemq::transport::TransportListener::onCommand** (const **Pointer**< **Command** > & *command*) [pure virtual]

Event handler for the receipt of a command. The **transport** (p. 97) passes off all received **commands** (p. 87) to its listeners, the listener then owns the Object. If there is no registered listener the **Transport** (p. 3883) deletes the command upon receipt.

Parameters:

command the received command object.

Implemented in **activemq::core::ActiveMQConnection** (p. 285), **ac-**
tivemq::transport::correlator::ResponseCorrelator (p. 3292), **ac-**
tivemq::transport::failover::FailoverTransportListener (p. 1889), **ac-**
tivemq::transport::inactivity::InactivityMonitor (p. 2005), **ac-**
tivemq::transport::logging::LoggingTransport (p. 2404), **ac-**
tivemq::transport::mock::InternalCommandListener (p. 2122),
activemq::transport::TransportFilter (p. 3895), and **ac-**
tivemq::wireformat::openwire::OpenWireFormatNegotiator (p. 2902).

6.842.3.2 virtual void activemq::transport::TransportListener::onException (const decaf::lang::Exception & *ex*) [pure virtual]

Event handler for an exception from a command **transport** (p. 97).

Parameters:

ex The exception being propagated to this listener to handle.

Implemented in **activemq::core::ActiveMQConnection** (p. 286),
activemq::transport::failover::BackupTransport (p. 753), **ac-**
tivemq::transport::failover::FailoverTransportListener (p. 1889), **ac-**
tivemq::transport::inactivity::InactivityMonitor (p. 2006), and **ac-**
tivemq::transport::TransportFilter (p. 3896).

6.842.3.3 virtual void activemq::transport::TransportListener::transportInterrupted () [pure virtual]

The **transport** (p. 97) has suffered an interruption from which it hopes to recover.

Implemented in **activemq::core::ActiveMQConnection** (p. 291),
activemq::transport::DefaultTransportListener (p. 1705), **ac-**
tivemq::transport::failover::FailoverTransportListener (p. 1889), and **ac-**
tivemq::transport::TransportFilter (p. 3898).

6.842.3.4 virtual void activemq::transport::TransportListener::transportResumed () [pure virtual]

The **transport** (p. 97) has resumed after an interruption.

Implemented in **activemq::core::ActiveMQConnection** (p. 291),
activemq::transport::DefaultTransportListener (p. 1705), **ac-**
tivemq::transport::failover::FailoverTransportListener (p. 1889), and **ac-**
tivemq::transport::TransportFilter (p. 3898).

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/TransportListener.h`

6.843 activemq::transport::TransportRegistry Class Reference

Registry of all **Transport** (p. 3883) Factories that are available to the client at runtime.

```
#include <src/main/activemq/transport/TransportRegistry.h>
```

Public Member Functions

- virtual **~TransportRegistry** ()
- **TransportFactory** * **findFactory** (const std::string &name) const throw (decaf::lang::exceptions::NoSuchElementException)

*Gets a Registered **TransportFactory** (p. 3889) from the Registry and returns it if there is not a registered format factory with the given name an exception is thrown.*

- void **registerFactory** (const std::string &name, **TransportFactory** *factory) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)

*Registers a new **TransportFactory** (p. 3889) with this Registry.*

- void **unregisterFactory** (const std::string &name)

Unregisters the Factory with the given name and deletes that instance of the Factory.

- std::vector< std::string > **getTransportNames** () const

Retrieves a list of the names of all the Registered Transport's in this Registry.

Static Public Member Functions

- static **TransportRegistry** & **getInstance** ()

*Gets the single instance of the **TransportRegistry** (p. 3902).*

6.843.1 Detailed Description

Registry of all **Transport** (p. 3883) Factories that are available to the client at runtime. New Transport's must have a factory registered here before a connection attempt is made.

Since:

3.0

6.843.2 Constructor & Destructor Documentation

6.843.2.1 `virtual activemq::transport::TransportRegistry::~~TransportRegistry ()`
[virtual]

6.843.3 Member Function Documentation

6.843.3.1 `TransportFactory* activemq::transport::TransportRegistry::findFactory (const std::string & name) const throw (decaf::lang::exceptions::NoSuchElementException)`

Gets a Registered **TransportFactory** (p. 3889) from the Registry and returns it if there is not a registered format factory with the given name an exception is thrown.

Parameters:

name The name of the Factory to find in the Registry.

Returns:

the Factory registered under the given name.

Exceptions:

NoSuchElementException if no factory is registered with that name.

6.843.3.2 `static TransportRegistry& activemq::transport::TransportRegistry::getInstance ()`
[static]

Gets the single instance of the **TransportRegistry** (p. 3902).

Returns:

reference to the single instance of this Registry

6.843.3.3 `std::vector<std::string> activemq::transport::TransportRegistry::getTransportNames () const`

Retrieves a list of the names of all the Registered Transport's in this Registry.

Returns:

std vector of strings with all the **Transport** (p. 3883) names registered.

6.843.3.4 `void activemq::transport::TransportRegistry::registerFactory (const std::string & name, TransportFactory * factory) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)`

Registers a new **TransportFactory** (p. 3889) with this Registry. If a Factory with the given name is already registered it is overwritten with the new one. Once a factory is added to the Registry its lifetime is controlled by the Registry, it will be deleted once the Registry has been deleted.

Parameters:

- name* The name of the new Factory to register.
factory The new Factory to add to the Registry.

Exceptions:

- IllegalArgumentException* if name is the empty string.
NullPointerException if the Factory is Null.

6.843.3.5 void activemq::transport::TransportRegistry::unregisterFactory (const std::string & name)

Unregisters the Factory with the given name and deletes that instance of the Factory.

Parameters:

- name* Name of the Factory to unregister and destroy

The documentation for this class was generated from the following file:

- src/main/activemq/transport/**TransportRegistry.h**

6.844 tree_desc_s Struct Reference

```
#include <src/main/decaf/internal/util/zip/deflate.h>
```

Data Fields

- `ct_data * dyn_tree`
- `int max_code`
- `static_tree_desc * stat_desc`

6.844.1 Field Documentation

6.844.1.1 `ct_data* tree_desc_s::dyn_tree`

6.844.1.2 `int tree_desc_s::max_code`

6.844.1.3 `static_tree_desc* tree_desc_s::stat_desc`

The documentation for this struct was generated from the following file:

- `src/main/decaf/internal/util/zip/deflate.h`

6.845 decaf::lang::Thread::UncaughtExceptionHandler Class Reference

Interface for handlers invoked when a **Thread** (p. 3765) abruptly terminates due to an uncaught exception.

```
#include <src/main/decaf/lang/Thread.h>
```

Public Member Functions

- virtual **~UncaughtExceptionHandler** ()
- virtual void **uncaughtException** (const **Thread** *thread, const **Throwable** &error)=0
throw ()

Method invoked when the given thread terminates due to the given uncaught exception.

6.845.1 Detailed Description

Interface for handlers invoked when a **Thread** (p. 3765) abruptly terminates due to an uncaught exception.

6.845.2 Constructor & Destructor Documentation

- 6.845.2.1 virtual
decaf::lang::Thread::UncaughtExceptionHandler::~UncaughtExceptionHandler
() [inline, virtual]

6.845.3 Member Function Documentation

- 6.845.3.1 virtual void de-
caf::lang::Thread::UncaughtExceptionHandler::uncaughtException (const
Thread * *thread*, const **Throwable** & *error*) throw () [pure virtual]

Method invoked when the given thread terminates due to the given uncaught exception. This method is defined to indicate that it will not throw an exception, throwing an exception from this method will on most systems result in a segmentation fault.

The documentation for this class was generated from the following file:

- src/main/decaf/lang/**Thread.h**

6.846 decaf::net::UnknownHostException Class Reference

#include <src/main/decaf/net/UnknownHostException.h> Inheritance diagram for decaf::net::UnknownHostException:

Public Member Functions

- **UnknownHostException** () throw ()
Default Constructor.
- **UnknownHostException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **UnknownHostException** (const **UnknownHostException** &ex) throw ()
Copy Constructor.
- **UnknownHostException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **UnknownHostException** (const std::exception *cause) throw ()
Constructor.
- **UnknownHostException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **UnknownHostException** * clone () const
Clones this exception.
- virtual ~**UnknownHostException** () throw ()

6.846.1 Constructor & Destructor Documentation

6.846.1.1 decaf::net::UnknownHostException::UnknownHostException () throw () [inline]

Default Constructor.

6.846.1.2 decaf::net::UnknownHostException::UnknownHostException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.846.1.3 decaf::net::UnknownHostException::UnknownHostException (const UnknownHostException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.846.1.4 decaf::net::UnknownHostException::UnknownHostException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.846.1.5 decaf::net::UnknownHostException::UnknownHostException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.846.1.6 decaf::net::UnknownHostException::UnknownHostException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.846.1.7 `virtual decaf::net::UnknownHostException::~~UnknownHostException ()
throw () [inline, virtual]`

6.846.2 Member Function Documentation

6.846.2.1 `virtual UnknownHostException* decaf::net::UnknownHostException::clone () const [inline,
virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/net/UnknownHostException.h`

6.847 decaf::net::UnknownServiceException Class Reference

#include <src/main/decaf/net/UnknownServiceException.h> Inheritance diagram for decaf::net::UnknownServiceException:

Public Member Functions

- **UnknownServiceException** () throw ()
Default Constructor.
- **UnknownServiceException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **UnknownServiceException** (const **UnknownServiceException** &ex) throw ()
Copy Constructor.
- **UnknownServiceException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **UnknownServiceException** (const std::exception *cause) throw ()
Constructor.
- **UnknownServiceException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **UnknownServiceException** * clone () const
Clones this exception.
- virtual ~**UnknownServiceException** () throw ()

6.847.1 Constructor & Destructor Documentation

6.847.1.1 decaf::net::UnknownServiceException::UnknownServiceException () throw () [inline]

Default Constructor.

6.847.1.2 decaf::net::UnknownServiceException::UnknownServiceException (const Exception & ex) throw () [inline]

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

References decaf::lang::Exception::Exception().

6.847.1.3 `decaf::net::UnknownServiceException::UnknownServiceException (const UnknownServiceException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

References `decaf::lang::Exception::Exception()`.

6.847.1.4 `decaf::net::UnknownServiceException::UnknownServiceException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.847.1.5 `decaf::net::UnknownServiceException::UnknownServiceException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.847.1.6 `decaf::net::UnknownServiceException::UnknownServiceException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.847.1.7 **virtual**
decaf::net::UnknownServiceException::~UnknownServiceException ()
throw () [inline, virtual]

6.847.2 Member Function Documentation

6.847.2.1 **virtual UnknownServiceException* de-**
caf::net::UnknownServiceException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- src/main/decaf/net/**UnknownServiceException.h**

6.848 decaf::io::UnsupportedEncodingException Class Reference

Thrown when the the Character Encoding is not supported.

#include <src/main/decaf/io/UnsupportedEncodingException.h> Inheritance diagram for decaf::io::UnsupportedEncodingException:

Public Member Functions

- **UnsupportedEncodingException** () throw ()
Default Constructor.
- **UnsupportedEncodingException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **UnsupportedEncodingException** (const **UnsupportedEncodingException** &ex) throw ()
Copy Constructor.
- **UnsupportedEncodingException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **UnsupportedEncodingException** (const std::exception *cause) throw ()
Constructor.
- **UnsupportedEncodingException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **UnsupportedEncodingException** * clone () const
Clones this exception.
- virtual ~**UnsupportedEncodingException** () throw ()

6.848.1 Detailed Description

Thrown when the the Character Encoding is not supported.

Since:

1.0

6.848.2 Constructor & Destructor Documentation

6.848.2.1 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException () throw () [inline]

Default Constructor.

6.848.2.2 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException (const lang::Exception & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.848.2.3 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException (const UnsupportedEncodingException & *ex*) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.848.2.4 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException (const char * *file*, const int *lineNumber*, const std::exception * *cause*, const char * *msg*, ...) throw () [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.848.2.5 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException (const std::exception * *cause*) throw () [inline]

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.848.2.6 decaf::io::UnsupportedEncodingException::UnsupportedEncodingException (const char * *file*, const int *lineNumber*, const char * *msg*, ...) throw () [inline]

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.848.2.7 `virtual`
`decaf::io::UnsupportedEncodingException::~~UnsupportedEncodingException`
`() throw () [inline, virtual]`

6.848.3 Member Function Documentation

6.848.3.1 `virtual UnsupportedEncodingException* de-`
`caf::io::UnsupportedEncodingException::clone () const [inline,`
`virtual]`

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A new instance of an Exception object that is a copy of this instance.

Reimplemented from `decaf::io::IOException` (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/io/UnsupportedEncodingException.h`

6.849 decaf::lang::exceptions::UnsupportedOperationException Class Reference

#include <src/main/decaf/lang/exceptions/UnsupportedOperationException.h> Inheritance diagram for decaf::lang::exceptions::UnsupportedOperationException:

Public Member Functions

- **UnsupportedOperationException** () throw ()
Default Constructor.
- **UnsupportedOperationException** (const **Exception** &ex) throw ()
*Conversion Constructor from some other **Exception** (p. 1831).*
- **UnsupportedOperationException** (const **UnsupportedOperationException** &ex) throw ()
Copy Constructor.
- **UnsupportedOperationException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **UnsupportedOperationException** (const std::exception *cause) throw ()
Constructor.
- **UnsupportedOperationException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **UnsupportedOperationException** * clone () const
Clones this exception.
- virtual ~**UnsupportedOperationException** () throw ()

6.849.1 Constructor & Destructor Documentation

6.849.1.1 decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException () throw () [inline]

Default Constructor.

6.849.1.2 decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException (const **Exception** & ex) throw () [inline]

Conversion Constructor from some other **Exception** (p. 1831).

Parameters:

ex An exception that should become this type of **Exception** (p. 1831)

6.849.1.3 `decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException(const UnsupportedOperationException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex An exception that should become this type of **Exception** (p. 1831)

6.849.1.4 `decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException(const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.849.1.5 `decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException(const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause **Pointer** (p. 2946) to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.849.1.6 `decaf::lang::exceptions::UnsupportedOperationException::UnsupportedOperationException(const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.849.1.7 virtual
decaf::lang::exceptions::UnsupportedOperationException::~UnsupportedOperationException
() throw () [inline, virtual]

6.849.2 Member Function Documentation

6.849.2.1 virtual UnsupportedOperationException* decaf::lang::exceptions::UnsupportedOperationException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

an new **Exception** (p. 1831) instance that is a copy of this one.

Reimplemented from **decaf::lang::Exception** (p. 1834).

Reimplemented in **decaf::nio::ReadOnlyBufferException** (p. 3171).

The documentation for this class was generated from the following file:

- src/main/decaf/lang/exceptions/**UnsupportedOperationException.h**

6.850 cms::UnsupportedOperationException Class Reference

This exception must be thrown when a CMS client attempts use a CMS method that is not implemented or not supported by the CMS Provider in use.

#include <src/main/cms/UnsupportedOperationException.h> Inheritance diagram for cms::UnsupportedOperationException:

Public Member Functions

- **UnsupportedOperationException** () throw ()
- **UnsupportedOperationException** (const **UnsupportedOperationException** &ex) throw ()
- **UnsupportedOperationException** (const std::string &message, const std::exception *cause) throw ()
- **UnsupportedOperationException** (const std::string &message, const std::exception *cause, const std::vector< std::pair< std::string, int > > &stackTrace) throw ()
- virtual ~**UnsupportedOperationException** () throw ()

6.850.1 Detailed Description

This exception must be thrown when a CMS client attempts use a CMS method that is not implemented or not supported by the CMS Provider in use.

Since:

2.0

6.850.2 Constructor & Destructor Documentation

- 6.850.2.1 **cms::UnsupportedOperationException::UnsupportedOperationException** () throw ()
- 6.850.2.2 **cms::UnsupportedOperationException::UnsupportedOperationException** (const **UnsupportedOperationException** & *ex*) throw ()
- 6.850.2.3 **cms::UnsupportedOperationException::UnsupportedOperationException** (const std::string & *message*, const std::exception * *cause*) throw ()
- 6.850.2.4 **cms::UnsupportedOperationException::UnsupportedOperationException** (const std::string & *message*, const std::exception * *cause*, const std::vector< std::pair< std::string, int > > & *stackTrace*) throw ()
- 6.850.2.5 virtual **cms::UnsupportedOperationException::~~UnsupportedOperationException** () throw () [virtual]

The documentation for this class was generated from the following file:

- `src/main/cms/UnsupportedOperationException.h`

6.851 decaf::net::URI Class Reference

This class represents an instance of a **URI** (p. 3921) as defined by RFC 2396.

#include <src/main/decaf/net/URI.h> Inheritance diagram for decaf::net::URI:

Public Member Functions

- **URI** ()
Default Constructor, same as calling a Constructor with all fields empty.
- **URI** (const **URI** &uri) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) as a copy of another **URI** (p. 3921).*
- **URI** (const std::string &uri) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) from the given string.*
- **URI** (const std::string &scheme, const std::string &ssp, const std::string &fragment) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) from the given components.*
- **URI** (const std::string &scheme, const std::string &userInfo, const std::string &host, int port, const std::string &path, const std::string &query, const std::string &fragment) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) from the given components.*
- **URI** (const std::string &scheme, const std::string &host, const std::string &path, const std::string &fragment) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) from the given components.*
- **URI** (const std::string &scheme, const std::string &authority, const std::string &path, const std::string &query, const std::string &fragment) throw (URISyntaxException)
*Constructs a **URI** (p. 3921) from the given components.*
- virtual ~**URI** ()
- virtual int **compareTo** (const **URI** &value) const
Compares this object with the specified object for order.
- virtual bool **equals** (const **URI** &value) const
- virtual bool **operator==** (const **URI** &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **URI** &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- std::string **getAuthority** () const
- std::string **getFragment** () const
- std::string **getHost** () const

- `std::string getPath () const`
- `int getPort () const`
- `std::string getQuery () const`
- `std::string getScheme () const`
- `std::string getUserInfo () const`
- `std::string getRawAuthority () const`
*Returns the raw authority component of this **URI** (p. 3921).*
- `std::string getRawFragment () const`
*Returns the raw fragment component of this **URI** (p. 3921).*
- `std::string getRawPath () const`
*Returns the raw path component of this **URI** (p. 3921).*
- `std::string getRawQuery () const`
*Returns the raw query component of this **URI** (p. 3921).*
- `std::string getRawSchemeSpecificPart () const`
*Returns the raw scheme-specific part of this **URI** (p. 3921).*
- `std::string getSchemeSpecificPart () const`
*Returns the decoded scheme-specific part of this **URI** (p. 3921).*
- `std::string getRawUserInfo () const`
*Returns the raw user-information component of this **URI** (p. 3921).*
- `bool isAbsolute () const`
*Tells whether or not this **URI** (p. 3921) is absolute.*
- `bool isOpaque () const`
*Tells whether or not this **URI** (p. 3921) is opaque.*
- `URI normalize () const`
*Normalizes this **URI**'s path.*
- `URI parseServerAuthority () const throw (URISyntaxException)`
*Attempts to parse this **URI**'s authority component, if defined, into user-information, host, and port components.*
- `URI relativize (const URI &uri) const`
*Relativizes the given **URI** (p. 3921) against this **URI** (p. 3921).*
- `URI resolve (const std::string &str) const throw (lang::exceptions::IllegalArgumentException)`
*Constructs a new **URI** (p. 3921) by parsing the given string and then resolving it against this **URI** (p. 3921).*
- `URI resolve (const URI &uri) const`
*Resolves the given **URI** (p. 3921) against this **URI** (p. 3921).*

- `std::string toString () const`
*Returns the content of this **URI** (p. 3921) as a string.*
- `URL toURL () const throw (MalformedURLException, lang::exceptions::IllegalArgumentException)`
*Constructs a **URL** (p. 3960) from this **URI** (p. 3921).*

Static Public Member Functions

- `static URI create (const std::string uri) throw (lang::exceptions::IllegalArgumentException)`
*Creates a **URI** (p. 3921) by parsing the given string.*

6.851.1 Detailed Description

This class represents an instance of a **URI** (p. 3921) as defined by RFC 2396.

6.851.2 Constructor & Destructor Documentation

6.851.2.1 `decaf::net::URI::URI ()`

Default Constructor, same as calling a Constructor with all fields empty.

6.851.2.2 `decaf::net::URI::URI (const URI & uri) throw (URISyntaxException)`

Constructs a **URI** (p. 3921) as a copy of another **URI** (p. 3921).

Parameters:

uri - uri to copy

6.851.2.3 `decaf::net::URI::URI (const std::string & uri) throw (URISyntaxException)`

Constructs a **URI** (p. 3921) from the given string.

Parameters:

uri - string uri to parse.

6.851.2.4 `decaf::net::URI::URI (const std::string & scheme, const std::string & ssp, const std::string & fragment) throw (URISyntaxException)`

Constructs a **URI** (p. 3921) from the given components.

Parameters:

scheme - the uri scheme

ssp - Scheme specific part

fragment - Fragment

6.851.2.5 decaf::net::URI::URI (const std::string & *scheme*, const std::string & *userInfo*, const std::string & *host*, int *port*, const std::string & *path*, const std::string & *query*, const std::string & *fragment*) throw (URISyntaxException)

Constructs a **URI** (p. 3921) from the given components.

Parameters:

scheme - Scheme name

userInfo - User name and authorization information

host - Host name

port - Port number

path - Path

query - Query

fragment - Fragment

6.851.2.6 decaf::net::URI::URI (const std::string & *scheme*, const std::string & *host*, const std::string & *path*, const std::string & *fragment*) throw (URISyntaxException)

Constructs a **URI** (p. 3921) from the given components.

Parameters:

scheme - Scheme name

host - Host name

path - Path

fragment - Fragment

6.851.2.7 decaf::net::URI::URI (const std::string & *scheme*, const std::string & *authority*, const std::string & *path*, const std::string & *query*, const std::string & *fragment*) throw (URISyntaxException)

Constructs a **URI** (p. 3921) from the given components.

Parameters:

scheme - Scheme name

authority - Authority

path - Path

query - Query

fragment - Fragment

6.851.2.8 `virtual decaf::net::URI::~~URI ()` [inline, virtual]

6.851.3 Member Function Documentation

6.851.3.1 `virtual int decaf::net::URI::compareTo (const URI & value) const`
[virtual]

Compares this object with the specified object for order. Returns a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than the specified object.

Parameters:

value - the value to compare to this one.

Returns:

zero if equal minus one if less than and one if greater than.

6.851.3.2 `static URI decaf::net::URI::create (const std::string uri) throw (`
`lang::exceptions::IllegalArgumentException)` [static]

Creates a **URI** (p. 3921) by parsing the given string. This convenience factory method works as if by invoking the `URI(string)` constructor; any **URISyntaxException** (p. 3948) thrown by the constructor is caught and wrapped in a new `IllegalArgumentException` object, which is then thrown.

Parameters:

uri - **URI** (p. 3921) string to parse

Exceptions:

IllegalArgumentException

6.851.3.3 `virtual bool decaf::net::URI::equals (const URI & value) const` [virtual]

Returns:

true if this value is considered equal to the passed value.

6.851.3.4 `std::string decaf::net::URI::getAuthority () const`

Returns:

the decoded authority component of this **URI** (p. 3921).

6.851.3.5 `std::string decaf::net::URI::getFragment () const`

Returns:

the decoded fragment component of this **URI** (p. 3921).

6.851.3.6 std::string decaf::net::URI::getHost () const**Returns:**

the host component of this **URI** (p. 3921).

6.851.3.7 std::string decaf::net::URI::getPath () const**Returns:**

the path component of this **URI** (p. 3921).

6.851.3.8 int decaf::net::URI::getPort () const**Returns:**

the port component of this **URI** (p. 3921).

6.851.3.9 std::string decaf::net::URI::getQuery () const**Returns:**

the query component of this **URI** (p. 3921).

6.851.3.10 std::string decaf::net::URI::getRawAuthority () const

Returns the raw authority component of this **URI** (p. 3921). The authority component of a **URI** (p. 3921), if defined, only contains the commercial-at character ('@') and characters in the unreserved, punct, escaped, and other categories. If the authority is server-based then it is further constrained to have valid user-information, host, and port components.

Returns:

the raw authority component of the **URI** (p. 3921)

6.851.3.11 std::string decaf::net::URI::getRawFragment () const

Returns the raw fragment component of this **URI** (p. 3921). The fragment component of a **URI** (p. 3921), if defined, only contains legal **URI** (p. 3921) characters.

Returns:

the raw fragment component of this **URI** (p. 3921)

6.851.3.12 std::string decaf::net::URI::getRawPath () const

Returns the raw path component of this **URI** (p. 3921). The path component of a **URI** (p. 3921), if defined, only contains the slash character ('/'), the commercial-at character ('@'), and characters in the unreserved, punct, escaped, and other categories.

Returns:

the raw path component of this **URI** (p. 3921)

6.851.3.13 `std::string decaf::net::URI::getRawQuery () const`

Returns the raw query component of this **URI** (p. 3921). The query component of a **URI** (p. 3921), if defined, only contains legal **URI** (p. 3921) characters.

Returns:

the raw query component of the **URI** (p. 3921).

6.851.3.14 `std::string decaf::net::URI::getRawSchemeSpecificPart () const`

Returns the raw scheme-specific part of this **URI** (p. 3921). The scheme-specific part is never undefined, though it may be empty. The scheme-specific part of a **URI** (p. 3921) only contains legal **URI** (p. 3921) characters.

Returns:

the raw scheme special part of the uri

6.851.3.15 `std::string decaf::net::URI::getRawUserInfo () const`

Returns the raw user-information component of this **URI** (p. 3921). The user-information component of a **URI** (p. 3921), if defined, only contains characters in the unreserved, punct, escaped, and other categories.

Returns:

the raw user-information component of the **URI** (p. 3921)

6.851.3.16 `std::string decaf::net::URI::getScheme () const`**Returns:**

the scheme component of this **URI** (p. 3921)

6.851.3.17 `std::string decaf::net::URI::getSchemeSpecificPart () const`

Returns the decoded scheme-specific part of this **URI** (p. 3921). The string returned by this method is equal to that returned by the `getRawSchemeSpecificPart` method except that all sequences of escaped octets are decoded.

Returns:

the raw scheme specific part of the uri.

6.851.3.18 `std::string decaf::net::URI::getUserInfo () const`**Returns:**

the user info component of this **URI** (p. 3921)

6.851.3.19 `bool decaf::net::URI::isAbsolute () const`

Tells whether or not this **URI** (p. 3921) is absolute. A **URI** (p. 3921) is absolute if, and only if, it has a scheme component.

Returns:

true if, and only if, this **URI** (p. 3921) is absolute

6.851.3.20 `bool decaf::net::URI::isOpaque () const`

Tells whether or not this **URI** (p. 3921) is opaque. A **URI** (p. 3921) is opaque if, and only if, it is absolute and its scheme-specific part does not begin with a slash character ('/'). An opaque **URI** (p. 3921) has a scheme, a scheme-specific part, and possibly a fragment; all other components are undefined.

Returns:

true if, and only if, this **URI** (p. 3921) is opaque

6.851.3.21 `URI decaf::net::URI::normalize () const`

Normalizes this **URI**'s path. If this **URI** (p. 3921) is opaque, or if its path is already in normal form, then this **URI** (p. 3921) is returned. Otherwise a new **URI** (p. 3921) is constructed that is identical to this **URI** (p. 3921) except that its path is computed by normalizing this **URI**'s path in a manner consistent with RFC 2396, section 5.2, step 6, sub-steps c through f; that is:

1. All "." segments are removed. 2. If a ".." segment is preceded by a non-".." segment then both of these segments are removed. This step is repeated until it is no longer applicable. 3. If the path is relative, and if its first segment contains a colon character (':'), then a "." segment is prepended. This prevents a relative **URI** (p. 3921) with a path such as "a:b/c/d" from later being re-parsed as an opaque **URI** (p. 3921) with a scheme of "a" and a scheme-specific part of "b/c/d". (Deviation from RFC 2396)

A normalized path will begin with one or more "." segments if there were insufficient non-".." segments preceding them to allow their removal. A normalized path will begin with a "." segment if one was inserted by step 3 above. Otherwise, a normalized path will not contain any "." or ".." segments.

Returns:

A **URI** (p. 3921) equivalent to this **URI** (p. 3921), but whose path is in normal form

6.851.3.22 `virtual bool decaf::net::URI::operator< (const URI & value) const`
[virtual]

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.851.3.23 `virtual bool decaf::net::URI::operator==(const URI & value) const`
[virtual]

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.851.3.24 `URI decaf::net::URI::parseServerAuthority () const throw (`
`URISyntaxException)`

Attempts to parse this URI's authority component, if defined, into user-information, host, and port components. If this URI's authority component has already been recognized as being server-based then it will already have been parsed into user-information, host, and port components. In this case, or if this **URI** (p. 3921) has no authority component, this method simply returns this **URI** (p. 3921).

Otherwise this method attempts once more to parse the authority component into user-information, host, and port components, and throws an exception describing why the authority component could not be parsed in that way.

Returns:

A **URI** (p. 3921) whose authority field has been parsed as a server-based authority

Exceptions:

URISyntaxException (p. 3948) - If the authority component of this **URI** (p. 3921) is defined but cannot be parsed as a server-based authority.

6.851.3.25 `URI decaf::net::URI::relativize (const URI & uri) const`

Relativizes the given **URI** (p. 3921) against this **URI** (p. 3921). The relativization of the given **URI** (p. 3921) against this **URI** (p. 3921) is computed as follows:

1. If either this **URI** (p. 3921) or the given **URI** (p. 3921) are opaque, or if the scheme and authority components of the two URIs are not identical, or if the path of this **URI** (p. 3921) is not a prefix of the path of the given **URI** (p. 3921), then the given **URI** (p. 3921) is returned.
2. Otherwise a new relative hierarchical **URI** (p. 3921) is constructed with query and fragment components taken from the given **URI** (p. 3921) and with a path component computed by removing this URI's path from the beginning of the given URI's path.

Parameters:

uri - The **URI** (p. 3921) to be relativized against this **URI** (p. 3921)

Returns:

The resulting **URI** (p. 3921)

6.851.3.26 URI decaf::net::URI::resolve (const URI & uri) const

Resolves the given **URI** (p. 3921) against this **URI** (p. 3921). If the given **URI** (p. 3921) is already absolute, or if this **URI** (p. 3921) is opaque, then a copy of the given **URI** (p. 3921) is returned.

If the given **URI**'s fragment component is defined, its path component is empty, and its scheme, authority, and query components are undefined, then a **URI** (p. 3921) with the given fragment but with all other components equal to those of this **URI** (p. 3921) is returned. This allows a **URI** (p. 3921) representing a standalone fragment reference, such as "#foo", to be usefully resolved against a base **URI** (p. 3921).

Otherwise this method constructs a new hierarchical **URI** (p. 3921) in a manner consistent with RFC 2396, section 5.2; that is:

1. A new **URI** (p. 3921) is constructed with this **URI**'s scheme and the given **URI**'s query and fragment components.
2. If the given **URI** (p. 3921) has an authority component then the new **URI**'s authority and path are taken from the given **URI** (p. 3921).
3. Otherwise the new **URI**'s authority component is copied from this **URI** (p. 3921), and its path is computed as follows:

1. If the given **URI**'s path is absolute then the new **URI**'s path is taken from the given **URI** (p. 3921).
2. Otherwise the given **URI**'s path is relative, and so the new **URI**'s path is computed by resolving the path of the given **URI** (p. 3921) against the path of this **URI** (p. 3921). This is done by concatenating all but the last segment of this **URI**'s path, if any, with the given **URI**'s path and then normalizing the result as if by invoking the `normalize` method.

The result of this method is absolute if, and only if, either this **URI** (p. 3921) is absolute or the given **URI** (p. 3921) is absolute.

Parameters:

uri - The **URI** (p. 3921) to be resolved against this **URI** (p. 3921)

Returns:

The resulting **URI** (p. 3921)

6.851.3.27 URI decaf::net::URI::resolve (const std::string & str) const throw (lang::exceptions::IllegalArgumentException)

Constructs a new **URI** (p. 3921) by parsing the given string and then resolving it against this **URI** (p. 3921). This convenience method works as if invoking it were equivalent to evaluating the expression `resolve(URI::create(str))`.

Parameters:

str - The string to be parsed into a **URI** (p. 3921)

Returns:

The resulting **URI** (p. 3921)

Exceptions:

IllegalArgumentException - If the given string violates RFC 2396

6.851.3.28 `std::string decaf::net::URI::toString () const`

Returns the content of this **URI** (p. 3921) as a string. If this **URI** (p. 3921) was created by invoking one of the constructors in this class then a string equivalent to the original input string, or to the string computed from the originally-given components, as appropriate, is returned. Otherwise this **URI** (p. 3921) was created by normalization, resolution, or relativization, and so a string is constructed from this **URI**'s components according to the rules specified in RFC 2396, section 5.2, step 7.

Returns:

the string form of this **URI** (p. 3921)

6.851.3.29 `URL decaf::net::URI::toURL () const throw (MalformedURLException, lang::exceptions::IllegalArgumentException)`

Constructs a **URL** (p. 3960) from this **URI** (p. 3921). This convenience method works as if invoking it were equivalent to evaluating the expression `new URL (p. 3960)(this.toString())` after first checking that this **URI** (p. 3921) is absolute.

Returns:

A **URL** (p. 3960) constructed from this **URI** (p. 3921)

Exceptions:

IllegalArgumentException - If this **URL** (p. 3960) is not absolute

MalformedURLException (p. 2456) - If a protocol handler for the **URL** (p. 3960) could not be found, or if some other error occurred while constructing the **URL** (p. 3960)

The documentation for this class was generated from the following file:

- `src/main/decaf/net/URI.h`

6.852 decaf::internal::net::URIEncoderDecoder Class Reference

```
#include <src/main/decaf/internal/net/URIEncoderDecoder.h>
```

Public Member Functions

- **URIEncoderDecoder** ()
- virtual **~URIEncoderDecoder** ()

Static Public Member Functions

- static void **validate** (const std::string &s, const std::string &legal) throw (decaf::net::URISyntaxException)
Validate a string by checking if it contains any characters other than:.
- static void **validateSimple** (const std::string &s, const std::string &legal) throw (decaf::net::URISyntaxException)
Validate a string by checking if it contains any characters other than:.
- static std::string **quoteIllegal** (const std::string &s, const std::string &legal)
All characters except letters ('a').
- static std::string **encodeOthers** (const std::string &s)
Other characters, which are chars that are not US-ASCII, and are not ISO Control or are not ISO Space chars are not preserved.
- static std::string **decode** (const std::string &s)
Decodes the string argument which is assumed to be encoded in the x-www-form-urlencoded MIME content type using the UTF-8 encoding scheme.

6.852.1 Constructor & Destructor Documentation

6.852.1.1 decaf::internal::net::URIEncoderDecoder::URIEncoderDecoder ()

6.852.1.2 virtual decaf::internal::net::URIEncoderDecoder::~~URIEncoderDecoder () [inline, virtual]

6.852.2 Member Function Documentation

6.852.2.1 static std::string decaf::internal::net::URIEncoderDecoder::decode (const std::string & s) [static]

Decodes the string argument which is assumed to be encoded in the x-www-form-urlencoded MIME content type using the UTF-8 encoding scheme. " and two following hex digit characters are converted to the equivalent byte value. All other characters are passed through unmodified.

e.g. "A%20B%20C %24%25" -> "A B C \$%"

Parameters:

s - The encoded string.

Returns:

The decoded version.

6.852.2.2 `static std::string decaf::internal::net::URIEncoderDecoder::encodeOthers
(const std::string & s) [static]`

Other characters, which are chars that are not US-ASCII, and are not ISO Control or are not ISO Space chars are not preserved. They are converted into their hexadecimal value prepended by ”.

For example: Euro currency symbol -> "%E2%82%AC".

Parameters:

s - the string to be converted

Returns:

the converted string

6.852.2.3 `static std::string decaf::internal::net::URIEncoderDecoder::quoteIllegal
(const std::string & s, const std::string & legal) [static]`

All characters except letters ('a'..'z', 'A'..'Z') and numbers ('0'..'9') and legal characters are converted into their hexadecimal value prepended by ”.

For example: '#' -> 23

Other characters, which are chars that are not US-ASCII, and are not ISO Control or are not ISO Space chars, are preserved.

Parameters:

s - the string to be converted

legal - the characters allowed to be preserved in the string *s*

Returns:

converted string

6.852.2.4 `static void decaf::internal::net::URIEncoderDecoder::validate
(const std::string & s, const std::string & legal) throw (
decaf::net::URISyntaxException) [static]`

Validate a string by checking if it contains any characters other than: 1. letters ('a'..'z', 'A'..'Z') 2. numbers ('0'..'9') 3. characters in the legalset parameter 4. characters that are not ISO Control or are not ISO Space characters)

Parameters:

s - the string to be validated

legal - the characters allowed in the string *s*

6.852.2.5 static void decaf::internal::net::URIEncoderDecoder::validateSimple
(const std::string & *s*, const std::string & *legal*) throw (
decaf::net::URISyntaxException) [static]

Validate a string by checking if it contains any characters other than: 1. letters ('a'..'z', 'A'..'Z')
2. numbers ('0'..'9') 3. characters in the legalset parameter

Parameters:

- s* - the string to be validated
- legal* - the characters allowed in the string *s*

The documentation for this class was generated from the following file:

- src/main/decaf/internal/net/**URIEncoderDecoder.h**

6.853 decaf::internal::net::URIHelper Class Reference

Helper class used by the URI classes in encoding and decoding of URI's.

```
#include <src/main/decaf/internal/net/URIHelper.h>
```

Public Member Functions

- **URIHelper** (const std::string &unreserved, const std::string &punct, const std::string &reserved, const std::string &someLegal, const std::string &allLegal)

*Setup the **URIHelper** (p. 3935) with values assigned to the various fields that are used in the validation process.*

- **URIHelper** ()

Sets up the filter strings with sane defaults.

- virtual ~**URIHelper** ()

- **URIType parseURI** (const std::string &uri, bool forceServer) throw (decaf::net::URISyntaxException)

Parse the passed in URI.

- void **validateScheme** (const std::string &uri, const std::string &scheme, int index) throw (decaf::net::URISyntaxException)

Validate the schema portin of the URI.

- void **validateSsp** (const std::string &uri, const std::string &ssp, std::size_t index) throw (decaf::net::URISyntaxException)

Validate that the URI Ssp Segment contains no invalid encodings.

- void **validateAuthority** (const std::string &uri, const std::string &authority, std::size_t index) throw (decaf::net::URISyntaxException)

Validate that the URI Authority Segment contains no invalid encodings.

- void **validatePath** (const std::string &uri, const std::string &path, std::size_t index) throw (decaf::net::URISyntaxException)

Validate that the URI Path Segment contains no invalid encodings.

- void **validateQuery** (const std::string &uri, const std::string &query, std::size_t index) throw (decaf::net::URISyntaxException)

Validate that the URI Query Segment contains no invalid encodings.

- void **validateFragment** (const std::string &uri, const std::string &fragment, std::size_t index) throw (decaf::net::URISyntaxException)

Validate that the URI fragment contains no invalid encodings.

- **URIType parseAuthority** (bool forceServer, const std::string &authority) throw (decaf::net::URISyntaxException)

determine the host, port and user-info if the authority parses successfully to a server based authority

- void **validateUserinfo** (const std::string &uri, const std::string &userinfo, std::size_t index) throw (decaf::net::URISyntaxException)
Check the supplied user info for validity.
- bool **isValidHost** (bool forceServer, const std::string &host) throw (decaf::net::URISyntaxException)
distinguish between IPv4, IPv6, domain name and validate it based on its type
- bool **isValidDomainName** (const std::string &host)
Validates the string past to determine if it is a well formed domain name.
- bool **isValidIPv4Address** (const std::string &host)
Validate if the host value is a well formed IPv4 address, this is the form XXX.XXX.XXX.XXX were X is any number 0-9.
- bool **isValidIPv6Address** (const std::string &ipAddress)
Determines if the given address is valid according to the IPv6 spec.
- bool **isValidIPv4Word** (const std::string &word)
Check is the string passed contains a Valid IPv4 word, which is an integer in the range of 0 to 255.
- bool **isValidHexChar** (char c)
Determines if the given char is a valid Hex char.

6.853.1 Detailed Description

Helper class used by the URI classes in encoding and decoding of URI's.

6.853.2 Constructor & Destructor Documentation

6.853.2.1 decaf::internal::net::URIHelper::URIHelper (const std::string & *unreserved*, const std::string & *punct*, const std::string & *reserved*, const std::string & *someLegal*, const std::string & *allLegal*)

Setup the **URIHelper** (p. 3935) with values assigned to the various fields that are used in the validation process. The defaults are overridden by these values.

Parameters:

- unreserved* - characters not reserved for use.
- punct* - allowable punctuation symbols.
- reserved* - characters not allowed for general use in the URI.
- someLegal* - characters that are legal in certain cases.
- allLegal* - characters that are always legal.

6.853.2.2 decaf::internal::net::URIHelper::URIHelper ()

Sets up the filter strings with sane defaults.

6.853.2.3 `virtual decaf::internal::net::URIHelper::~~URIHelper () [inline, virtual]`

6.853.3 Member Function Documentation

6.853.3.1 `bool decaf::internal::net::URIHelper::isValidDomainName (const std::string & host)`

Validates the string past to determine if it is a well formed domain name.

Parameters:

host - domain name to validate.

Returns:

true if host is well formed.

6.853.3.2 `bool decaf::internal::net::URIHelper::isValidHexChar (char c)`

Determines if the given char is a valid Hex char. Valid chars are A-F (upper or lower case) and 0-9.

Parameters:

c - char to inspect

Returns:

true if *c* is a valid hex char.

6.853.3.3 `bool decaf::internal::net::URIHelper::isValidHost (bool forceServer, const std::string & host) throw (decaf::net::URISyntaxException)`

distinguish between IPv4, IPv6, domain name and validate it based on its type

Parameters:

forceServer - true if the forceServer mode should be active.

host - Host string to validate.

Returns:

true if the host value if a valid domain name.

Exceptions:

URISyntaxException if the host is invalid and forceServer is true.

6.853.3.4 `bool decaf::internal::net::URIHelper::isValidIP4Word (const std::string & word)`

Check is the string passed contains a Valid IPv4 word, which is an integer in the range of 0 to 255.

Parameters:

word - string value to check.

Returns:

true if the word is a valid IPv4 word.

6.853.3.5 bool decaf::internal::net::URIHelper::IsValidIP6Address (const std::string & *ipAddress*)

Determines if the given address is valid according to the IPv6 spec.

Parameters:

ipAddress - string ip address value to validate.

Returns:

true if the address string is valid.

6.853.3.6 bool decaf::internal::net::URIHelper::IsValidIPv4Address (const std::string & *host*)

Validate if the host value is a well formed IPv4 address, this is the form XXX.XXX.XXX.XXX were X is any number 0-9. and XXX is not greater than 255.

Parameters:

host - IPv4 address string to parse.

Returns:

true if host is a well formed IPv4 address.

6.853.3.7 URIType decaf::internal::net::URIHelper::parseAuthority (bool *forceServer*, const std::string & *authority*) throw (decaf::net::URISyntaxException)

determine the host, port and user-info if the authority parses successfully to a server based authority behavior in error cases: if forceServer is true, throw URISyntaxException with the proper diagnostic messages. if forceServer is false assume this is a registry based uri, and just return leaving the host, port and user-info fields undefined.

and there are some error cases where URISyntaxException is thrown regardless of the forceServer parameter e.g. mal-formed ipv6 address

Parameters:

forceServer
authority

Returns:

a URIType (p. 3952) instance containing the parsed data.

Exceptions:

URISyntaxException

6.853.3.8 `URIType decaf::internal::net::URIHelper::parseURI (const std::string & uri, bool forceServer) throw (decaf::net::URISyntaxException)`

Parse the passed in URI.

Parameters:

uri - the URI to Parse

forceServer - if true invalid URI data throws an Exception

Returns:

a `URIType` (p. 3952) instance containing the parsed data.

Exceptions:

URISyntaxException if forceServer is true and the URI is invalid.

6.853.3.9 `void decaf::internal::net::URIHelper::validateAuthority (const std::string & uri, const std::string & authority, std::size_t index) throw (decaf::net::URISyntaxException)`

Validate that the URI Authority Segment contains no invalid encodings.

Parameters:

uri - the full uri.

authority - the Authority to check.

index - position in the uri where Authority starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.10 `void decaf::internal::net::URIHelper::validateFragment (const std::string & uri, const std::string & fragment, std::size_t index) throw (decaf::net::URISyntaxException)`

Validate that the URI fragment contains no invalid encodings.

Parameters:

uri - the full uri.

fragment - the fragment to check.

index - position in the uri where fragment starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.11 void decaf::internal::net::URIHelper::validatePath (const std::string & *uri*, const std::string & *path*, std::size_t *index*) throw (decaf::net::URISyntaxException)

Validate that the URI Path Segment contains no invalid encodings.

Parameters:

uri - the full uri.

path - the path to check.

index - position in the uri where path starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.12 void decaf::internal::net::URIHelper::validateQuery (const std::string & *uri*, const std::string & *query*, std::size_t *index*) throw (decaf::net::URISyntaxException)

Validate that the URI Query Segment contains no invalid encodings.

Parameters:

uri - the full uri.

query - the query to check.

index - position in the uri where fragment starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.13 void decaf::internal::net::URIHelper::validateScheme (const std::string & *uri*, const std::string & *scheme*, int *index*) throw (decaf::net::URISyntaxException)

Validate the schema portin of the URI.

Parameters:

uri - the URI to check.

scheme - the schema section of the URI.

index - index in uri where schema starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.14 `void decaf::internal::net::URIHelper::validateSsp (const std::string
 & uri, const std::string & ssp, std::size_t index) throw (`
 `decaf::net::URISyntaxException)`

Validate that the URI Ssp Segment contains no invalid encodings.

Parameters:

uri - the full uri.

ssp - the SSP to check.

index - position in the uri where Ssp starts.

Exceptions:

URISyntaxException if the fragment has errors.

6.853.3.15 `void decaf::internal::net::URIHelper::validateUserinfo (const std::string
 & uri, const std::string & userinfo, std::size_t index) throw (`
 `decaf::net::URISyntaxException)`

Check the supplied user info for validity.

Parameters:

uri - the uri to parse.

userinfo - supplied user info

index - index into the URI string where the data is located.

Returns:

true if valid

Exceptions:

URISyntaxException if an error occurs

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/URIHelper.h`

6.854 activemq::transport::failover::URIPool Class Reference

```
#include <src/main/activemq/transport/failover/URIPool.h>
```

Public Member Functions

- **URIPool** ()
Create an Empty URI Pool.
- **URIPool** (const **decaf::util::List**< **URI** > &uris)
Creates a new URI Pool using the given list as the initial Free List.
- **~URIPool** ()
- **URI** **getURI** () throw (**decaf::lang::exceptions::NoSuchElementException**)
Fetches the next available URI from the pool, if there are no more URIs free when this method is called it throws a `NoSuchElementException`.
- void **addURI** (const **URI** &uri)
Adds a URI to the free list, callers that have previously taken one using the `getURI` method should always return the URI when they close the resource that was connected to that URI.
- void **addURIs** (const **StlList**< **URI** > &uris)
Adds a List of URIs to this Pool, the method checks for duplicates already in the pool and does not add those.
- void **removeURI** (const **URI** &uri)
Remove a given URI from the Free List.
- bool **isRandomize** () const
Is the URI that is given randomly picked from the pool or is each one taken in sequence.
- void **setRandomize** (bool value)
Sets if the URI's that are taken from the pool are chosen Randomly or are taken in the order they are in the list.

6.854.1 Constructor & Destructor Documentation

6.854.1.1 activemq::transport::failover::URIPool::URIPool ()

Create an Empty URI Pool.

6.854.1.2 activemq::transport::failover::URIPool::URIPool (const **decaf::util::List**< **URI** > & *uris*)

Creates a new URI Pool using the given list as the initial Free List.

Parameters:

uris - List of URI to place in the Pool.

6.854.1.3 `activemq::transport::failover::URIPool::~~URIPool ()`**6.854.2 Member Function Documentation****6.854.2.1 `void activemq::transport::failover::URIPool::addURI (const URI & uri)`**

Adds a URI to the free list, callers that have previously taken one using the `getURI` method should always return the URI when they close the resource that was connected to that URI.

Parameters:

uri - a URI previously taken from the pool.

6.854.2.2 `void activemq::transport::failover::URIPool::addURIs (const StlList< URI > & uris)`

Adds a List of URIs to this Pool, the method checks for duplicates already in the pool and does not add those.

Parameters:

uris - List of URIs to add into the Pool.

6.854.2.3 `URI activemq::transport::failover::URIPool::getURI () throw (decaf::lang::exceptions::NoSuchElementException)`

Fetches the next available URI from the pool, if there are no more URIs free when this method is called it throws a `NoSuchElementException`. Receiving the exception is not an indication that a URI won't be available in the future, the caller should react accordingly.

Returns:

the next free URI in the Pool.

Exceptions:

NoSuchElementException if there are none free currently.

6.854.2.4 `bool activemq::transport::failover::URIPool::isRandomize () const [inline]`

Is the URI that is given randomly picked from the pool or is each one taken in sequence.

Returns:

true if URI gets are random.

6.854.2.5 `void activemq::transport::failover::URIPool::removeURI (const URI & uri)`

Remove a given URI from the Free List.

Parameters:

uri - the URI to find and remove from the free list

6.854.2.6 void activemq::transport::failover::URIPool::setRandomize (bool *value*) [inline]

Sets if the URI's that are taken from the pool are chosen Randomly or are taken in the order they are in the list.

Parameters:

value - true indicates URI gets are random.

The documentation for this class was generated from the following file:

- `src/main/activemq/transport/failover/URIPool.h`

6.855 activemq::util::URISupport Class Reference

```
#include <src/main/activemq/util/URISupport.h>
```

Static Public Member Functions

- static void **parseURL** (const std::string &URI, **decaf::util::Properties** &properties) throw (**decaf::lang::exceptions::IllegalArgumentException**)
Parses the properties out of the provided Broker URI and sets them in the passed Properties Object.
- static **CompositeData** **parseComposite** (const **URI** &uri) throw (**decaf::net::URISyntaxException**)
Parses a Composite URI into a Composite Data instance, the Composite URI takes the for scheme://(uri1,uri2,...uriN)?param1=value1, each of the composite URIs is stored in the CompositeData's internal list.
- static **decaf::util::Properties** **parseQuery** (std::string query) throw (**decaf::lang::exceptions::IllegalArgumentException**)
Parse the Query portion of a URI String and return a Simple Properties object containing the parameter names as keys, and the parameter values and values of the Properties.
- static void **parseQuery** (std::string query, **decaf::util::Properties** *properties) throw (**decaf::lang::exceptions::IllegalArgumentException**)
Parse the Query portion of a URI String and return a Simple Properties object containing the parameter names as keys, and the parameter values and values of the Properties.
- static std::string **createQueryString** (const **Properties** &options) throw (**decaf::net::URISyntaxException**)
Given a properties object create a string that can be appended to a URI as a valid Query string.

6.855.1 Member Function Documentation

6.855.1.1 static std::string **activemq::util::URISupport::createQueryString** (const **Properties** & *options*) throw (**decaf::net::URISyntaxException**)
 [static]

Given a properties object create a string that can be appended to a URI as a valid Query string.

Parameters:

options Properties object containing key / value query values.

Returns:

a valid URI query string.

Exceptions:

URISyntaxException if the string in the Properties object can't be encoded into a valid URI Query string.

6.855.1.2 static CompositeData activemq::util::URISupport::parseComposite (const URI & *uri*) throw (decaf::net::URISyntaxException) [static]

Parses a Composite URI into a Composite Data instance, the Composite URI takes the for scheme://(uri1,uri2,...uriN)?param1=value1, each of the composite URIs is stored in the CompositeData's internal list.

Parameters:

uri - The Composite URI to parse.

Returns:

a new **CompositeData** (p. 1219) object with the parsed data

Exceptions:

URISyntaxException if the URI is not well formed.

6.855.1.3 static void activemq::util::URISupport::parseQuery (std::string *query*, decaf::util::Properties * *properties*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Parse the Query portion of a URI String and return a Simple Properties object containing the parameter names as keys, and the parameter values and values of the Properties.

Parameters:

query - the query string to parse.

properties - object pointer to get the parsed output.

Exceptions:

IllegalArgumentException if the Query string is not well formed.

6.855.1.4 static decaf::util::Properties activemq::util::URISupport::parseQuery (std::string *query*) throw (decaf::lang::exceptions::IllegalArgumentException) [static]

Parse the Query portion of a URI String and return a Simple Properties object containing the parameter names as keys, and the parameter values and values of the Properties.

Parameters:

query The query string to parse and extract the encoded properties.

Returns:

Properties object with the parsed output.

Exceptions:

IllegalArgumentException if the Query string is not well formed.

6.855.1.5 `static void activemq::util::URISupport::parseURL (const
std::string & URI, decaf::util::Properties & properties) throw (
decaf::lang::exceptions::IllegalArgumentException) [static]`

Parses the properties out of the provided Broker URI and sets them in the passed Properties Object.

Parameters:

URI a Broker URI to parse

properties a Properties object to set the parsed values in

Exceptions:

IllegalArgumentException if the passed URI is invalid

The documentation for this class was generated from the following file:

- `src/main/activemq/util/URISupport.h`

6.856 decaf::net::URISyntaxException Class Reference

#include <src/main/decaf/net/URISyntaxException.h> Inheritance diagram for decaf::net::URISyntaxException:

Public Member Functions

- **URISyntaxException** () throw ()
Default Constructor.
- **URISyntaxException** (const Exception &ex) throw ()
Conversion Constructor from some other Exception.
- **URISyntaxException** (const **URISyntaxException** &ex) throw ()
Copy Constructor.
- **URISyntaxException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **URISyntaxException** (const std::exception *cause) throw ()
Constructor.
- **URISyntaxException** (const char *file, const int lineNumber, const char *msg DECAF_ - UNUSED) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **URISyntaxException** (const char *file, const int lineNumber, const std::string &input, const std::string &reason) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **URISyntaxException** (const char *file, const int lineNumber, const std::string &input, const std::string &reason, int index) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- virtual **URISyntaxException** * **clone** () const
Clones this exception.
- virtual ~**URISyntaxException** () throw ()
- std::string **getInput** () const
- std::string **getReason** () const
- int **getIndex** () const

6.856.1 Constructor & Destructor Documentation

6.856.1.1 decaf::net::URISyntaxException::URISyntaxException () throw () [inline]

Default Constructor.

6.856.1.2 `decaf::net::URISyntaxException::URISyntaxException (const Exception & ex) throw () [inline]`

Conversion Constructor from some other Exception.

Parameters:

ex An exception that should become this type of Exception

6.856.1.3 `decaf::net::URISyntaxException::URISyntaxException (const URISyntaxException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex An exception that should become this type of Exception

6.856.1.4 `decaf::net::URISyntaxException::URISyntaxException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.856.1.5 `decaf::net::URISyntaxException::URISyntaxException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.856.1.6 `decaf::net::URISyntaxException::URISyntaxException (const char * file, const int lineNumber, const char *msg DECAF_UNUSED) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs
lineNumber The line number where the exception occurred.
msg The message to report
... list of primitives that are formatted into the message

6.856.1.7 `decaf::net::URISyntaxException::URISyntaxException (const char * file,
const int lineNumber, const std::string & input, const std::string & reason) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the input string that caused the error and the reason for the error.

Parameters:

file The file name where exception occurs.
lineNumber The line number where the exception occurred.
input The **URL** (p.3960) that caused the exception.
reason The reason for the failure.

6.856.1.8 `decaf::net::URISyntaxException::URISyntaxException (const char * file,
const int lineNumber, const std::string & input, const std::string & reason, int index) throw ()` [inline]

Constructor - Initializes the file name and line number where this message occurred. Sets the input string that caused the error and the reason for the error.

Parameters:

file The file name where exception occurs
lineNumber The line number where the exception occurred.
input The input **URI** (p.3921) that caused the exception
reason The reason for the failure.
index The index in the **URI** (p.3921) string where the error occurred.

6.856.1.9 `virtual decaf::net::URISyntaxException::~~URISyntaxException () throw
()` [inline, virtual]

6.856.2 Member Function Documentation

6.856.2.1 `virtual URISyntaxException* decaf::net::URISyntaxException::clone ()
const` [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new Exception instance that is a copy of this Exception object.

Reimplemented from **decaf::lang::Exception** (p.1834).

6.856.2.2 `int decaf::net::URISyntaxException::getIndex () const [inline]`

Returns:

the index in the input string where the error occurred or -1

6.856.2.3 `std::string decaf::net::URISyntaxException::getInput () const [inline]`

Returns:

the Input string that cause this exception or ""

6.856.2.4 `std::string decaf::net::URISyntaxException::getReason () const [inline]`

Returns:

the Reason given for this failure, or ""

The documentation for this class was generated from the following file:

- `src/main/decaf/net/URISyntaxException.h`

6.857 decaf::internal::net::URIType Class Reference

Basic type object that holds data that composes a given URI.

```
#include <src/main/decaf/internal/net/URIType.h>
```

Public Member Functions

- **URIType** (const std::string &source)
- **URIType** ()
- virtual ~**URIType** ()
- std::string **getSource** () const
*Gets the source URI string that was parsed to obtain this **URIType** (p. 3952) instance and the resulting data,.*
- void **setSource** (const std::string &source)
*Sets the source URI string that was parsed to obtain this **URIType** (p. 3952) instance and the resulting data,.*
- std::string **getScheme** () const
Gets the Scheme of the URI, e.g.
- void **setScheme** (const std::string &scheme)
Sets the Scheme of the URI, e.g.
- std::string **getSchemeSpecificPart** () const
Gets the Scheme Specific Part of the URI.
- void **setSchemeSpecificPart** (const std::string &schemeSpecificPart)
Sets the Scheme Specific Part of the URI.
- std::string **getAuthority** () const
Gets the Authority of the URI.
- void **setAuthority** (const std::string &authority)
Sets the Authority of the URI.
- std::string **getUserInfo** () const
Gets the user info part of the URI, e.g.
- void **setUserInfo** (const std::string &userinfo)
Sets the user info part of the URI, e.g.
- std::string **getHost** () const
Gets the Host name part of the URI.
- void **setHost** (const std::string &host)
Sets the Host name part of the URI.
- int **getPort** () const

Gets the port part of the URI.

- void **setPort** (int port)
Sets the port part of the URI.
- std::string **getPath** () const
Gets the Path part of the URI.
- void **setPath** (const std::string &path)
Sets the Path part of the URI.
- std::string **getQuery** () const
Gets the Query part of the URI.
- void **setQuery** (const std::string &query)
Sets the Query part of the URI.
- std::string **getFragment** () const
Gets the Fragment part of the URI.
- void **setFragment** (const std::string &fragment)
Sets the Fragment part of the URI.
- bool **isOpaque** () const
Gets if the URI is Opaque.
- void **setOpaque** (bool opaque)
Sets if the URI is Opaque.
- bool **isAbsolute** () const
Gets if the URI is Absolute.
- void **setAbsolute** (bool absolute)
Sets if the URI is Absolute.
- bool **isServerAuthority** () const
Gets if the URI is a Server Authority.
- void **setServerAuthority** (bool serverAuthority)
Sets if the URI is a Server Authority.
- bool **isValid** () const
Gets if the URI is valid, meaning that the source has been set and parsed and all relevant data fields have been set.
- void **setValid** (bool valid)
Sets if the URI is valid, meaning that the source has been set and parsed and all relevant data fields have been set.

6.857.1 Detailed Description

Basic type object that holds data that composes a given URI.

6.857.2 Constructor & Destructor Documentation

6.857.2.1 `decaf::internal::net::URIType::URIType (const std::string & source)` `[inline]`

6.857.2.2 `decaf::internal::net::URIType::URIType ()` `[inline]`

6.857.2.3 `virtual decaf::internal::net::URIType::~~URIType ()` `[inline, virtual]`

6.857.3 Member Function Documentation

6.857.3.1 `std::string decaf::internal::net::URIType::getAuthority () const` `[inline]`

Gets the Authority of the URI.

Returns:

Authority part string.

6.857.3.2 `std::string decaf::internal::net::URIType::getFragment () const` `[inline]`

Gets the Fragment part of the URI.

Returns:

Fragment part string.

6.857.3.3 `std::string decaf::internal::net::URIType::getHost () const` `[inline]`

Gets the Host name part of the URI.

Returns:

Host name part string.

6.857.3.4 `std::string decaf::internal::net::URIType::getPath () const` `[inline]`

Gets the Path part of the URI.

Returns:

Path part string.

6.857.3.5 `int decaf::internal::net::URIType::getPort () const [inline]`

Gets the port part of the URL.

Returns:

port part string, -1 if not set.

6.857.3.6 `std::string decaf::internal::net::URIType::getQuery () const [inline]`

Gets the Query part of the URL.

Returns:

Query part string.

6.857.3.7 `std::string decaf::internal::net::URIType::getScheme () const [inline]`

Gets the Scheme of the URL, e.g. scheme ("http"/"ftp"/...).

Returns:

scheme part string.

6.857.3.8 `std::string decaf::internal::net::URIType::getSchemeSpecificPart () const [inline]`

Gets the Scheme Specific Part of the URL.

Returns:

scheme specific part string.

6.857.3.9 `std::string decaf::internal::net::URIType::getSource () const [inline]`

Gets the source URI string that was parsed to obtain this **URIType** (p. 3952) instance and the resulting data,.

Returns:

the source URI string

6.857.3.10 `std::string decaf::internal::net::URIType::getUserInfo () const [inline]`

Gets the user info part of the URL, e.g. user name, as in `http://user:passwd@host:port/`

Returns:

user info part string.

6.857.3.11 `bool decaf::internal::net::URIType::isAbsolute () const [inline]`

Gets if the URI is Absolute.

Returns:

true if Absolute.

6.857.3.12 `bool decaf::internal::net::URIType::isOpaque () const [inline]`

Gets if the URI is Opaque.

Returns:

true if opaque.

6.857.3.13 `bool decaf::internal::net::URIType::isServerAuthority () const [inline]`

Gets if the URI is a Server Authority.

Returns:

true if Server Authority.

6.857.3.14 `bool decaf::internal::net::URIType::isValid () const [inline]`

Gets if the URI is valid, meaning that the source has been set and parsed and all relevant data fields have been set.

Returns:

true if the **URIType** (p. 3952) contains valid data.

6.857.3.15 `void decaf::internal::net::URIType::setAbsolute (bool absolute) [inline]`

Sets if the URI is Absolute.

Parameters:

absolute - true if Absolute.

6.857.3.16 `void decaf::internal::net::URIType::setAuthority (const std::string &authority) [inline]`

Sets the Authority of the URI.

Parameters:

authority Authority part string.

6.857.3.17 `void decaf::internal::net::URIType::setFragment (const std::string & fragment)` [inline]

Sets the Fragment part of the URI.

Parameters:

fragment - Fragment part string.

6.857.3.18 `void decaf::internal::net::URIType::setHost (const std::string & host)` [inline]

Sets the Host name part of the URI.

Parameters:

host - Host name part string.

6.857.3.19 `void decaf::internal::net::URIType::setOpaque (bool opaque)` [inline]

Sets if the URI is Opaque.

Parameters:

opaque true if opaque.

6.857.3.20 `void decaf::internal::net::URIType::setPath (const std::string & path)` [inline]

Sets the Path part of the URI.

Parameters:

path - Path part string.

6.857.3.21 `void decaf::internal::net::URIType::setPort (int port)` [inline]

Sets the port part of the URI.

Parameters:

port - port part string, -1 if not set.

6.857.3.22 `void decaf::internal::net::URIType::setQuery (const std::string & query)` [inline]

Sets the Query part of the URI.

Parameters:

query - Query part string.

6.857.3.23 void decaf::internal::net::URIType::setScheme (const std::string & *scheme*) [inline]

Sets the Scheme of the URI, e.g. scheme ("http"/"ftp"/...).

Parameters:

scheme - scheme part string.

6.857.3.24 void decaf::internal::net::URIType::setSchemeSpecificPart (const std::string & *schemeSpecificPart*) [inline]

Sets the Scheme Specific Part of the URI.

Parameters:

schemeSpecificPart - scheme specific part string.

6.857.3.25 void decaf::internal::net::URIType::setServerAuthority (bool *serverAuthority*) [inline]

Sets if the URI is a Server Authority.

Parameters:

serverAuthority - true if Server Authority.

6.857.3.26 void decaf::internal::net::URIType::setSource (const std::string & *source*) [inline]

Sets the source URI string that was parsed to obtain this **URIType** (p. 3952) instance and the resulting data,.

Parameters:

source - the source URI string

6.857.3.27 void decaf::internal::net::URIType::setUserInfo (const std::string & *userinfo*) [inline]

Sets the user info part of the URI, e.g. user name, as in http://user:passwd@host:port/

Parameters:

userinfo - user info part string.

6.857.3.28 void decaf::internal::net::URIType::setValid (bool *valid*) [inline]

Sets if the URI is valid, meaning that the source has been set and parsed and all relevant data fields have been set.

Parameters:

valid - true if the **URIType** (p. 3952) contains valid data.

The documentation for this class was generated from the following file:

- `src/main/decaf/internal/net/URIType.h`

6.858 decaf::net::URL Class Reference

Class **URL** (p.3960) represents a Uniform Resource Locator, a pointer to a "resource" on the World Wide Web.

```
#include <src/main/decaf/net/URL.h>
```

Public Member Functions

- **URL** ()
- **URL** (const std::string &url)
- virtual ~**URL** ()

6.858.1 Detailed Description

Class **URL** (p.3960) represents a Uniform Resource Locator, a pointer to a "resource" on the World Wide Web. A resource can be something as simple as a file or a directory, or it can be a reference to a more complicated object, such as a query to a database or to a search engine. More information on the types of URLs and their formats can be found at:

```
http://www.ksc.nasa.gov/facts/internet/url-primer.html
```

In general, a **URL** (p.3960) can be broken into several parts. The previous example of a **URL** (p.3960) indicates that the protocol to use is http (HyperText Transfer Protocol) and that the information resides on a host machine named www.ksc.nasa.gov. The information on that host machine is named /facts/internet/url-primer.html. The exact meaning of this name on the host machine is both protocol dependent and host dependent. The information normally resides in a file, but it could be generated on the fly. This component of the **URL** (p.3960) is called the path component.

A **URL** (p.3960) can optionally specify a "port", which is the port number to which the TCP connection is made on the remote host machine. If the port is not specified, the default port for the protocol is used instead. For example, the default port for http is 80. An alternative port could be specified as:

```
http://www.ksc.nasa.gov:80/facts/internet/url-primer.html
```

The syntax of **URL** (p.3960) is defined by RFC 2396: Uniform Resource Identifiers (**URI** (p.3921)): Generic Syntax, amended by RFC 2732: Format for Literal IPv6 Addresses in URLs. The Literal IPv6 address format also supports scope_ids. The syntax and usage of scope_ids is described here.

A **URL** (p.3960) may have appended to it a "fragment", also known as a "ref" or a "reference". The fragment is indicated by the sharp sign character "#" followed by more characters. For example,

```
http://www.apache.org/cms/index.html#chapter1
```

This fragment is not technically part of the **URL** (p.3960). Rather, it indicates that after the specified resource is retrieved, the application is specifically interested in that part of the document that has the tag chapter1 attached to it. The meaning of a tag is resource specific.

An application can also specify a "relative URL", which contains only enough information to reach the resource relative to another **URL** (p.3960). Relative URLs are frequently used within HTML pages. For example, if the contents of the **URL** (p.3960):

```
http://www.apache.org/cms/index.html
```

contained within it the relative **URL** (p. 3960):

FAQ.html

it would be a shorthand for:

`http://www.apache.org/cms/FAQ.html`

The relative **URL** (p. 3960) need not specify all the components of a **URL** (p. 3960). If the protocol, host name, or port number is missing, the value is inherited from the fully specified **URL** (p. 3960). The file component must be specified. The optional fragment is not inherited.

The **URL** (p. 3960) class does not itself encode or decode any **URL** (p. 3960) components according to the escaping mechanism defined in RFC2396. It is the responsibility of the caller to encode any fields, which need to be escaped prior to calling **URL** (p. 3960), and also to decode any escaped fields, that are returned from **URL** (p. 3960). Furthermore, because **URL** (p. 3960) has no knowledge of **URL** (p. 3960) escaping, it does not recognise equivalence between the encoded or decoded form of the same **URL** (p. 3960). For example, the two URLs:

`http://foo.com/hello world/` and `http://foo.com/hello%20world`

would be considered not equal to each other.

Note, the **URI** (p. 3921) class does perform escaping of its component fields in certain circumstances. The recommended way to manage the encoding and decoding of URLs is to use **URI** (p. 3921), and to convert between these two classes using `toURI()` and `URI.toURL()` (p. 3931).

The **URLEncoder** (p. 3963) and **URLDecoder** (p. 3962) classes can also be used, but only for HTML form encoding, which is not the same as the encoding scheme defined in RFC2396.

6.858.2 Constructor & Destructor Documentation

6.858.2.1 `decaf::net::URL::URL ()`

6.858.2.2 `decaf::net::URL::URL (const std::string & url)`

6.858.2.3 `virtual decaf::net::URL::~~URL ()` [inline, virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/net/URL.h`

6.859 decaf::net::URLDecoder Class Reference

```
#include <src/main/decaf/net/URLDecoder.h>
```

Public Member Functions

- virtual `~URLDecoder ()`

Static Public Member Functions

- static `std::string decode (const std::string &value)`
Decodes the string argument which is assumed to be encoded in the `x-www-form-urlencoded` MIME content type.

6.859.1 Constructor & Destructor Documentation

6.859.1.1 virtual `decaf::net::URLDecoder::~~URLDecoder ()` [inline, virtual]

6.859.2 Member Function Documentation

6.859.2.1 static `std::string decaf::net::URLDecoder::decode (const std::string &value)` [static]

Decodes the string argument which is assumed to be encoded in the `x-www-form-urlencoded` MIME content type. '+' will be converted to space, '%' and two following hex digit characters are converted to the equivalent byte value. All other characters are passed through unmodified.

e.g. "A+B+C %24%25" -> "A B C \$%"

Parameters:

value - string The encoded string.

Returns:

The decoded version as a string.

The documentation for this class was generated from the following file:

- `src/main/decaf/net/URLDecoder.h`

6.860 decaf::net::URLEncoder Class Reference

```
#include <src/main/decaf/net/URLEncoder.h>
```

Public Member Functions

- virtual `~URLEncoder()`

Static Public Member Functions

- static `std::string encode(const std::string &value)`

This class contains a utility method for converting a string to the format required by the `application/x-www-form-urlencoded` MIME content type.

6.860.1 Constructor & Destructor Documentation

6.860.1.1 virtual `decaf::net::URLEncoder::~~URLEncoder()` [inline, virtual]

6.860.2 Member Function Documentation

6.860.2.1 static `std::string decaf::net::URLEncoder::encode(const std::string &value)` [static]

This class contains a utility method for converting a string to the format required by the `application/x-www-form-urlencoded` MIME content type. All characters except letters ('a'..'z', 'A'..'Z') and numbers ('0'..'9') and characters '.', '-', '*', '_' are converted into their hexadecimal value prepended by ".

For example: '#' -> 23

In addition, spaces are substituted by '+'

Parameters:

value - the string to be converted

Returns:

the converted string

The documentation for this class was generated from the following file:

- `src/main/decaf/net/URLEncoder.h`

6.861 activemq::util::Usage Class Reference

#include <src/main/activemq/util/Usage.h> Inheritance diagram for activemq::util::Usage:

Public Member Functions

- virtual `~Usage ()`
- virtual void `waitForSpace ()=0`
*Waits forever for more space to be returned to this **Usage** (p. 3964) Manager.*
- virtual void `waitForSpace (unsigned int timeout)=0`
*Waits for more space to be returned to this **Usage** (p. 3964) Manager, times out when the given time span in milliseconds elapses.*
- virtual void `enqueueUsage (unsigned long long value)=0`
Tries to increase the usage by value amount but blocks if this object is currently full.
- virtual void `increaseUsage (unsigned long long value)=0`
Increases the usage by the value amount.
- virtual void `decreaseUsage (unsigned long long value)=0`
Decreases the usage by the value amount.
- virtual bool `isFull () const =0`
*Returns true if this **Usage** (p. 3964) instance is full, i.e.*

6.861.1 Constructor & Destructor Documentation

6.861.1.1 virtual `activemq::util::Usage::~~Usage ()` [inline, virtual]

6.861.2 Member Function Documentation

6.861.2.1 virtual void `activemq::util::Usage::decreaseUsage (unsigned long long value)` [pure virtual]

Decreases the usage by the value amount.

Parameters:

value Amount of space to return to the pool

Implemented in `activemq::util::MemoryUsage` (p. 2513).

6.861.2.2 virtual void `activemq::util::Usage::enqueueUsage (unsigned long long value)` [pure virtual]

Tries to increase the usage by value amount but blocks if this object is currently full.

Parameters:

value Amount of usage in bytes to add.

Implemented in **activemq::util::MemoryUsage** (p. 2513).

6.861.2.3 virtual void activemq::util::Usage::increaseUsage (unsigned long long *value*) [pure virtual]

Increases the usage by the value amount.

Parameters:

value Amount of usage to add.

Implemented in **activemq::util::MemoryUsage** (p. 2514).

6.861.2.4 virtual bool activemq::util::Usage::isFull () const [pure virtual]

Returns true if this **Usage** (p. 3964) instance is full, i.e. **Usage** (p. 3964) $\geq 100\%$

Returns:

true if **Usage** (p. 3964) is at the Full point.

Implemented in **activemq::util::MemoryUsage** (p. 2514).

6.861.2.5 virtual void activemq::util::Usage::waitForSpace (unsigned int *timeout*) [pure virtual]

Waits for more space to be returned to this **Usage** (p. 3964) Manager, times out when the given time span in milliseconds elapses.

Parameters:

timeout The time to wait for more space.

Implemented in **activemq::util::MemoryUsage** (p. 2514).

6.861.2.6 virtual void activemq::util::Usage::waitForSpace () [pure virtual]

Waits forever for more space to be returned to this **Usage** (p. 3964) Manager.

Implemented in **activemq::util::MemoryUsage** (p. 2515).

The documentation for this class was generated from the following file:

- `src/main/activemq/util/Usage.h`

6.862 decaf::io::UTFDataFormatException Class Reference

Thrown from classes that attempt to read or write a UTF-8 encoded string and an encoding error is encountered.

#include <src/main/decaf/io/UTFDataFormatException.h>Inheritance diagram for decaf::io::UTFDataFormatException:

Public Member Functions

- **UTFDataFormatException** () throw ()
Default Constructor.
- **UTFDataFormatException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **UTFDataFormatException** (const UTFDataFormatException &ex) throw ()
Copy Constructor.
- **UTFDataFormatException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **UTFDataFormatException** (const std::exception *cause) throw ()
Constructor.
- **UTFDataFormatException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **UTFDataFormatException * clone** () const
Clones this exception.
- virtual ~**UTFDataFormatException** () throw ()

6.862.1 Detailed Description

Thrown from classes that attempt to read or write a UTF-8 encoded string and an encoding error is encountered.

Since:

1.0

6.862.2 Constructor & Destructor Documentation

6.862.2.1 decaf::io::UTFDataFormatException::UTFDataFormatException () throw () [inline]

Default Constructor.

6.862.2.2 `decaf::io::UTFDataFormatException::UTFDataFormatException (const lang::Exception & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy

6.862.2.3 `decaf::io::UTFDataFormatException::UTFDataFormatException (const UTFDataFormatException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.862.2.4 `decaf::io::UTFDataFormatException::UTFDataFormatException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.862.2.5 `decaf::io::UTFDataFormatException::UTFDataFormatException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.862.2.6 `decaf::io::UTFDataFormatException::UTFDataFormatException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.862.2.7 virtual decaf::io::UTFDataFormatException::~~UTFDataFormatException
() throw () [inline, virtual]

6.862.3 Member Function Documentation

6.862.3.1 virtual UTFDataFormatException* decaf::io::UTFDataFormatException::clone () const
[inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

A new instance of an Exception object that is a copy of this instance.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- src/main/decaf/io/UTFDataFormatException.h

6.863 decaf::util::UUID Class Reference

A class that represents an immutable universally unique identifier (**UUID** (p. 3969)).

#include <src/main/decaf/util/UUID.h> Inheritance diagram for decaf::util::UUID:

Public Member Functions

- **UUID** (long long mostSigBits, long long leastSigBits)
*Constructs a new **UUID** (p. 3969) using the specified data.*
- virtual ~**UUID** ()
- virtual int **compareTo** (const **UUID** &value) const
*Compare the given **UUID** (p. 3969) to this one.*
- virtual bool **equals** (const **UUID** &value) const
*Compares this **UUID** (p. 3969) to the one given, returns true if they are equal.*
- virtual bool **operator==** (const **UUID** &value) const
Compares equality between this object and the one passed.
- virtual bool **operator<** (const **UUID** &value) const
Compares this object to another and returns true if this object is considered to be less than the one passed.
- virtual std::string **toString** () const
*Returns a String object representing this **UUID** (p. 3969).*
- virtual long long **getLeastSignificantBits** () const
- virtual long long **getMostSignificantBits** () const
- virtual long long **node** () throw (lang::exceptions::UnsupportedOperationException)
*The node value associated with this **UUID** (p. 3969).*
- virtual long long **timestamp** () throw (lang::exceptions::UnsupportedOperationException)
*The timestamp value associated with this **UUID** (p. 3969).*
- virtual int **clockSequence** () throw (lang::exceptions::UnsupportedOperationException)
*The clock sequence value associated with this **UUID** (p. 3969).*
- virtual int **variant** () throw (lang::exceptions::UnsupportedOperationException)
*The variant number associated with this **UUID** (p. 3969).*
- virtual int **version** () throw (lang::exceptions::UnsupportedOperationException)
*The version number associated with this **UUID** (p. 3969).*

Static Public Member Functions

- static **UUID** **randomUUID** ()
*Static factory to retrieve a type 4 (pseudo randomly generated) **UUID** (p. 3969).*
- static **UUID** **nameUUIDFromBytes** (const std::vector< char > &name)
*Static factory to retrieve a type 3 (name based) **UUID** (p. 3969) based on the specified byte array.*
- static **UUID** **nameUUIDFromBytes** (const char *name, std::size_t size)
*Static factory to retrieve a type 3 (name based) **UUID** (p. 3969) based on the specified byte array.*
- static **UUID** **fromString** (const std::string &name) throw (lang::exceptions::IllegalArgumentException)
*Creates a **UUID** (p. 3969) from the string standard representation as described in the **toString()** (p. 3974) method.*

6.863.1 Detailed Description

A class that represents an immutable universally unique identifier (**UUID** (p. 3969)). A **UUID** (p. 3969) represents a 128-bit value.

There exist different variants of these global identifiers. The methods of this class are for manipulating the Leach-Salz variant, although the constructors allow the creation of any variant of **UUID** (p. 3969) (described below).

The layout of a variant 2 (Leach-Salz) **UUID** (p. 3969) is as follows: The most significant long consists of the following unsigned fields:

```
0xFFFFFFFF00000000 time_low 0x00000000FFFF0000 time_mid 0x000000000000F000 version
0x00000000000000FF time_hi
```

The least significant long consists of the following unsigned fields:

```
0xC000000000000000 variant 0x3FFF000000000000 clock_seq 0x0000FFFFFFFFFFFF node
```

The variant field contains a value which identifies the layout of the **UUID** (p. 3969). The bit layout described above is valid only for a **UUID** (p. 3969) with a variant value of 2, which indicates the Leach-Salz variant.

The version field holds a value that describes the type of this **UUID** (p. 3969). There are four different basic types of UUIDs: time-based, DCE **security** (p. 164), name-based, and randomly generated UUIDs. These types have a version value of 1, 2, 3 and 4, respectively.

For more information including algorithms used to create UUIDs, see the Internet-Draft UUIDs and GUIDs or the standards body definition at ISO/IEC 11578:1996.

6.863.2 Constructor & Destructor Documentation

6.863.2.1 decaf::util::UUID::UUID (long long *mostSigBits*, long long *leastSigBits*)

Constructs a new **UUID** (p. 3969) using the specified data. *mostSigBits* is used for the most significant 64 bits of the **UUID** (p. 3969) and *leastSigBits* becomes the least significant 64 bits of the **UUID** (p. 3969).

Parameters:*mostSigBits**leastSigBits***6.863.2.2** `virtual decaf::util::UUID::~~UUID ()` [virtual]**6.863.3 Member Function Documentation****6.863.3.1** `virtual int decaf::util::UUID::clockSequence () throw (lang::exceptions::UnsupportedOperationException)` [virtual]

The clock sequence value associated with this **UUID** (p. 3969). The 14 bit clock sequence value is constructed from the clock sequence field of this **UUID** (p. 3969). The clock sequence field is used to guarantee temporal uniqueness in a time-based **UUID** (p. 3969).

The clockSequence value is only meaningful in a time-based **UUID** (p. 3969), which has version type 1. If this **UUID** (p. 3969) is not a time-based **UUID** (p. 3969) then this method throws `UnsupportedOperationException`.

Returns:

the clockSequence associated with a V1 **UUID** (p. 3969)

Exceptions:*UnsupportedOperationException***6.863.3.2** `virtual int decaf::util::UUID::compareTo (const UUID & value) const` [virtual]

Compare the given **UUID** (p. 3969) to this one.

Parameters:*value* - the **UUID** (p. 3969) to compare to**6.863.3.3** `virtual bool decaf::util::UUID::equals (const UUID & value) const` [virtual]

Compares this **UUID** (p. 3969) to the one given, returns true if they are equal.

Parameters:*value* - the **UUID** (p. 3969) to compare to.**Returns:**

true if UUIDs are the same.

6.863.3.4 `static UUID decaf::util::UUID::fromString (const std::string & name)
 throw (lang::exceptions::IllegalArgumentException) [static]`

Creates a **UUID** (p. 3969) from the string standard representation as described in the **toString()** (p. 3974) method.

Parameters:

name - a string to be used to construct a **UUID** (p. 3969).

Returns:

type 3 **UUID** (p. 3969)

6.863.3.5 `virtual long long decaf::util::UUID::getLeastSignificantBits () const
 [virtual]`

Returns:

the most significant 64 bits of this UUID's 128 bit value.

6.863.3.6 `virtual long long decaf::util::UUID::getMostSignificantBits () const
 [virtual]`

Returns:

the most significant 64 bits of this UUID's 128 bit value.

6.863.3.7 `static UUID decaf::util::UUID::nameUUIDFromBytes (const char *
 name, std::size_t size) [static]`

Static factory to retrieve a type 3 (name based) **UUID** (p. 3969) based on the specified byte array.

Parameters:

name - a byte array to be used to construct a **UUID** (p. 3969).

size - the size of the byte array, or number of bytes to use.

Returns:

type 3 **UUID** (p. 3969)

6.863.3.8 `static UUID decaf::util::UUID::nameUUIDFromBytes (const std::vector<
 char > & name) [static]`

Static factory to retrieve a type 3 (name based) **UUID** (p. 3969) based on the specified byte array.

Parameters:

name - a byte array to be used to construct a **UUID** (p. 3969).

Returns:

type 3 **UUID** (p. 3969)

6.863.3.9 `virtual long long decaf::util::UUID::node () throw (lang::exceptions::UnsupportedOperationException) [virtual]`

The node value associated with this **UUID** (p. 3969). The 48 bit node value is constructed from the node field of this **UUID** (p. 3969). This field is intended to hold the IEEE 802 address of the machine that generated this **UUID** (p. 3969) to guarantee spatial uniqueness.

The node value is only meaningful in a time-based **UUID** (p. 3969), which has version type 1. If this **UUID** (p. 3969) is not a time-based **UUID** (p. 3969) then this method throws `UnsupportedOperationException`.

Returns:

the node value of this **UUID** (p. 3969)

Exceptions:

`UnsupportedOperationException`

6.863.3.10 `virtual bool decaf::util::UUID::operator< (const UUID & value) const [virtual]`

Compares this object to another and returns true if this object is considered to be less than the one passed. This

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.863.3.11 `virtual bool decaf::util::UUID::operator== (const UUID & value) const [virtual]`

Compares equality between this object and the one passed.

Parameters:

value - the value to be compared to this one.

Returns:

true if this object is equal to the one passed.

6.863.3.12 `static UUID decaf::util::UUID::randomUUID () [static]`

Static factory to retrieve a type 4 (pseudo randomly generated) **UUID** (p. 3969). The **UUID** (p. 3969) is generated using a cryptographically strong pseudo random number generator.

Returns:

type 4 **UUID** (p. 3969)

6.863.3.13 `virtual long long decaf::util::UUID::timestamp () throw (lang::exceptions::UnsupportedOperationException) [virtual]`

The timestamp value associated with this **UUID** (p. 3969). The 60 bit timestamp value is constructed from the `time_low`, `time_mid`, and `time_hi` fields of this **UUID** (p. 3969). The resulting timestamp is measured in 100-nanosecond units since midnight, October 15, 1582 UTC.

The timestamp value is only meaningful in a time-based **UUID** (p. 3969), which has version type 1. If this **UUID** (p. 3969) is not a time-based **UUID** (p. 3969) then this method throws `UnsupportedOperationException`.

Returns:

the timestamp associated with a V1 **UUID** (p. 3969)

Exceptions:

UnsupportedOperationException

6.863.3.14 `virtual std::string decaf::util::UUID::toString () const [virtual]`

Returns a `String` object representing this **UUID** (p. 3969). **UUID**'s are formatted as: 00112233-4455-6677-8899-AABBCCDDEEFF whose length is 36.

Returns:

formatted string for this **UUID** (p. 3969)

6.863.3.15 `virtual int decaf::util::UUID::variant () throw (lang::exceptions::UnsupportedOperationException) [virtual]`

The variant number associated with this **UUID** (p. 3969). The variant number describes the layout of the **UUID** (p. 3969). The variant number has the following meaning:

* 0 Reserved for NCS backward compatibility * 2 The Leach-Salz variant (used by this class) * 6 Reserved, Microsoft Corporation backward compatibility * 7 Reserved for future definition

Returns:

the variant associated with a V1 **UUID** (p. 3969)

Exceptions:

UnsupportedOperationException

6.863.3.16 `virtual int decaf::util::UUID::version () throw (lang::exceptions::UnsupportedOperationException) [virtual]`

The version number associated with this **UUID** (p. 3969). The version number describes how this **UUID** (p. 3969) was generated. The version number has the following meaning:

* 1 Time-based **UUID** (p. 3969) * 2 DCE security (p. 164) **UUID** (p. 3969) * 3 Name-based **UUID** (p. 3969) * 4 Randomly generated **UUID** (p. 3969)

Returns:

the version associated with a V1 **UUID** (p. 3969)

Exceptions:

UnsupportedOperationException

The documentation for this class was generated from the following file:

- `src/main/decaf/util/UUID.h`

6.864 activemq::wireformat::WireFormat Class Reference

Provides a mechanism to marshal **commands** (p.87) into and out of packets or into and out of streams, Channels and Datagrams.

#include <src/main/activemq/wireformat/WireFormat.h> Inheritance diagram for activemq::wireformat::WireFormat:

Public Member Functions

- virtual **~WireFormat** ()
- virtual void **marshal** (const **Pointer**< **commands::Command** > &command, const **activemq::transport::Transport** *transport, **decaf::io::DataOutputStream** *out)=0
throw (**decaf::io::IOException**)
Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.
- virtual **Pointer**< **commands::Command** > **unmarshal** (const **activemq::transport::Transport** *transport, **decaf::io::DataInputStream** *in)=0
throw (**decaf::io::IOException**)
Stream based unmarshaling, blocks on reads on the input stream until a complete command has been read and unmarshaled into the correct form.
- virtual void **setVersion** (int version)=0
Set the Version.
- virtual int **getVersion** () const =0
Get the Version.
- virtual bool **hasNegotiator** () const =0
*Returns true if this **WireFormat** (p.3976) has a Negotiator that needs to wrap the Transport that uses it.*
- virtual bool **inReceive** () const =0
Indicates if the WireFormat object is in the process of receiving a message.
- virtual **Pointer**< **transport::Transport** > **createNegotiator** (const **Pointer**< **transport::Transport** > &transport)=0 throw (**decaf::lang::exceptions::UnsupportedOperationException**)
If the Transport Provides a Negotiator this method will create and return a new instance of the Negotiator.

6.864.1 Detailed Description

Provides a mechanism to marshal **commands** (p.87) into and out of packets or into and out of streams, Channels and Datagrams.

Version:

Revision 1.1

6.864.2 Constructor & Destructor Documentation

6.864.2.1 `virtual activemq::wireformat::WireFormat::~~WireFormat () [inline, virtual]`

6.864.3 Member Function Documentation

6.864.3.1 `virtual Pointer<transport::Transport> activemq::wireformat::WireFormat::createNegotiator (const Pointer< transport::Transport > & transport) throw (decaf::lang::exceptions::UnsupportedOperationException) [pure virtual]`

If the Transport Provides a Negotiator this method will create and return a new instance of the Negotiator.

Parameters:

transport (p. 97) - the Transport to Wrap the Negotiator around.

Returns:

new instance of a **WireFormatNegotiator** (p. 4016) as a **Pointer<Transport>** (p. 2946).

Exceptions:

UnsupportedOperationException if the **WireFormat** (p. 3976) doesn't have a Negotiator.

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2890), and **activemq::wireformat::stomp::StompWireFormat** (p. 3644).

6.864.3.2 `virtual int activemq::wireformat::WireFormat::getVersion () const [pure virtual]`

Get the Version.

Returns:

the version of the wire format

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2892), and **activemq::wireformat::stomp::StompWireFormat** (p. 3644).

6.864.3.3 `virtual bool activemq::wireformat::WireFormat::hasNegotiator () const [pure virtual]`

Returns true if this **WireFormat** (p. 3976) has a Negotiator that needs to wrap the Transport that uses it.

Returns:

true if the **WireFormat** (p. 3976) provides a Negotiator.

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2892), and **activemq::wireformat::stomp::StompWireFormat** (p. 3644).

6.864.3.4 virtual bool activemq::wireformat::WireFormat::inReceive () const [pure virtual]

Indicates if the WireFormat object is in the process of receiving a message. This is useful for monitoring inactivity and the **WireFormat** (p. 3976) is processing a large message which takes longer than some configured timeout to unmarshal, the inactivity monitor can query the **WireFormat** (p. 3976) instance to determine if its busy or not and not mark the connection as inactive if so.

Returns:

true if the **WireFormat** (p. 3976) object is unmarshaling a message.

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2892), and **activemq::wireformat::stomp::StompWireFormat** (p. 3645).

6.864.3.5 virtual void activemq::wireformat::WireFormat::marshal (const Pointer< commands::Command > & *command*, const activemq::transport::Transport * *transport*, decaf::io::DataOutputStream * *out*) throw (decaf::io::IOException) [pure virtual]

Stream based marshaling of a Command, this method blocks until the entire Command has been written out to the output stream.

Parameters:

command The Command to Marshal

transport (p. 97) The Transport that called this method.

out The output stream to write the command to.

Exceptions:

IOException

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2894), and **activemq::wireformat::stomp::StompWireFormat** (p. 3645).

6.864.3.6 virtual void activemq::wireformat::WireFormat::setVersion (int *version*) [pure virtual]

Set the Version.

Parameters:

version the version of the wire format

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2896), and **activemq::wireformat::stomp::StompWireFormat** (p. 3645).

6.864.3.7 `virtual Pointer<commands::Command> activemq::wireformat::WireFormat::unmarshal (const activemq::transport::Transport * transport, decaf::io::DataInputStream * in) throw (decaf::io::IOException)` [pure virtual]

Stream based unmarshaling, blocks on reads on the input stream until a complete command has been read and unmarshaled into the correct form. Returns a Pointer to the newly unmarshaled Command.

Parameters:

transport (p. 97) - Pointer to the **transport** (p. 97) that is making this request.

in - the input stream to read the command from.

Returns:

the newly marshaled Command, caller owns the pointer

Exceptions:

IOException

Implemented in **activemq::wireformat::openwire::OpenWireFormat** (p. 2898), and **activemq::wireformat::stomp::StompWireFormat** (p. 3645).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/WireFormat.h`

6.865 activemq::wireformat::WireFormatFactory Class Reference

The **WireFormatFactory** (p. 3980) is the interface that all **WireFormatFactory** (p. 3980) classes must extend.

#include <src/main/activemq/wireformat/WireFormatFactory.h> Inheritance diagram for activemq::wireformat::WireFormatFactory:

Public Member Functions

- virtual **~WireFormatFactory** ()
- virtual **Pointer< WireFormat > createWireFormat** (const **decaf::util::Properties** &properties)=0 throw (**decaf::lang::exceptions::IllegalStateException**)
*Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.*

6.865.1 Detailed Description

The **WireFormatFactory** (p. 3980) is the interface that all **WireFormatFactory** (p. 3980) classes must extend. The Factory creates a **WireFormat** (p. 3976) Object based on the properties that are set in the passed **Properties** object.

6.865.2 Constructor & Destructor Documentation

6.865.2.1 virtual **activemq::wireformat::WireFormatFactory::~~WireFormatFactory** () [inline, virtual]

6.865.3 Member Function Documentation

6.865.3.1 virtual **Pointer<WireFormat> activemq::wireformat::WireFormatFactory::createWireFormat** (const **decaf::util::Properties** & *properties*) throw (**decaf::lang::exceptions::IllegalStateException**) [pure virtual]

Creates a new **WireFormat** (p. 3976) Object passing it a set of properties from which it can obtain any optional settings.

Parameters:

properties - the **Properties** for this **WireFormat** (p. 3976)

Returns:

Pointer to a new instance of a **WireFormat** (p. 3976) object.

Implemented in **activemq::wireformat::openwire::OpenWireFormatFactory** (p. 2899), and **activemq::wireformat::stomp::StompWireFormatFactory** (p. 3647).

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/WireFormatFactory.h`

6.866 activemq::commands::WireFormatInfo Class Reference

#include <src/main/activemq/commands/WireFormatInfo.h> Inheritance diagram for activemq::commands::WireFormatInfo:

Public Member Functions

- **WireFormatInfo** ()
- virtual **~WireFormatInfo** ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual **DataStructure** * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const **DataStructure** *src)
Copy the contents of the passed object into this objects members, overwriting any existing data.
- virtual std::string **toString** () const
*Returns a string containing the information for this **DataStructure** (p. 1660) such as its type and value of its elements.*
- virtual bool **equals** (const **DataStructure** *value) const
*Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent.*
- virtual bool **isMarshalAware** () const
Indicates that this command is aware of Marshaling, and needs to have its Marshaling methods invoked.
- virtual **decaf::lang::Pointer**< **commands::Command** > **visit** (**activemq::state::CommandVisitor** *visitor) throw (**exceptions::ActiveMQException**)
Allows a Visitor to visit this command and return a response to the command based on the command type being visited.
- int **getVersion** () const
Get the current Wireformat Version.
- void **setVersion** (int version)
Set the current Wireformat Version.
- long long **getMaxInactivityDuration** () const
Returns the currently configured Max Inactivity duration.
- void **setMaxInactivityDuration** (long long maxInactivityDuration)
Sets the Max inactivity duration value.

- long long **getMaxInactivityDurationInitialDelay** () const
Returns the currently configured Max Inactivity Initial Delay duration.
- void **setMaxInactivityDurationInitialDelay** (long long maxInactivityDurationInitialDelay)
Sets the Max inactivity initial delay duration value.
- bool **isStackTraceEnabled** () const
Checks if the stackTraceEnabled flag is on.
- void **setStackTraceEnabled** (bool stackTraceEnabled)
Sets if the stackTraceEnabled flag is on.
- bool **isTcpNoDelayEnabled** () const
Checks if the tcpNoDelayEnabled flag is on.
- void **setTcpNoDelayEnabled** (bool tcpNoDelayEnabled)
Sets if the tcpNoDelayEnabled flag is on.
- bool **isCacheEnabled** () const
Checks if the cacheEnabled flag is on.
- void **setCacheEnabled** (bool cacheEnabled)
Sets if the cacheEnabled flag is on.
- int **getCacheSize** () const
Gets the Cache Size setting.
- void **setCacheSize** (int value)
Sets the Cache Size setting.
- bool **isTightEncodingEnabled** () const
Checks if the tightEncodingEnabled flag is on.
- void **setTightEncodingEnabled** (bool tightEncodingEnabled)
Sets if the tightEncodingEnabled flag is on.
- bool **isSizePrefixDisabled** () const
Checks if the sizePrefixDisabled flag is on.
- void **setSizePrefixDisabled** (bool sizePrefixDisabled)
Sets if the sizePrefixDisabled flag is on.
- const std::vector< unsigned char > &**getMagic** () const
Get the Magic field.
- void **setMagic** (const std::vector< unsigned char > &magic)
Sets the value of the magic field.

- `const std::vector< unsigned char > & getMarshalledProperties () const`
Get the marshalledProperties field.
- `void setMarshalledProperties (const std::vector< unsigned char > &marshalledProperties)`
Sets the value of the marshalledProperties field.
- `virtual const util::PrimitiveMap & getProperties () const`
*Gets the Properties for this **Command** (p. 1194).*
- `virtual util::PrimitiveMap & getProperties ()`
*Gets the Properties for this **Command** (p. 1194).*
- `virtual void setProperties (const util::PrimitiveMap &map)`
*Sets the Properties for this **Command** (p. 1194).*
- `bool isValid () const`
*Determines if we think this is a Valid **WireFormatInfo** (p. 3982) command.*
- `virtual bool isWireFormatInfo () const`
- `virtual void beforeMarshal (wireformat::WireFormat *wireFormat AMQCPP_ - UNUSED) throw (decaf::io::IOException)`
Handles the marshaling of the objects properties into the internal byte array before the object is marshalled to the wire.
- `virtual void afterUnmarshal (wireformat::WireFormat *wireFormat AMQCPP_ - UNUSED) throw (decaf::io::IOException)`
Called after unmarshaling is started to cleanup the object being unmarshaled.

Static Public Attributes

- `static const unsigned char ID_ WIREFORMATINFO = 1`

6.866.1 Constructor & Destructor Documentation

6.866.1.1 `activemq::commands::WireFormatInfo::WireFormatInfo ()`

6.866.1.2 `virtual activemq::commands::WireFormatInfo::~~WireFormatInfo ()`
[virtual]

6.866.2 Member Function Documentation

6.866.2.1 `virtual void activemq::commands::WireFormatInfo::afterUnmarshal (wireformat::WireFormat *wireFormat AMQCPP_ UNUSED) throw (decaf::io::IOException)` [virtual]

Called after unmarshaling is started to cleanup the object being unmarshaled.

Parameters:

wireFormat - the **wireformat** (p. 105) object to control unmarshaling

Reimplemented from `activemq::commands::BaseDataStructure` (p. 831).

6.866.2.2 `virtual void activemq::commands::WireFormatInfo::beforeMarshal (wireformat::WireFormat *wireFormat AMQCPP_UNUSED) throw (decaf::io::IOException)` [virtual]

Handles the marshaling of the objects properties into the internal byte array before the object is marshalled to the wire.

Parameters:

wireFormat - the wire formatting controller

Reimplemented from `activemq::commands::BaseDataStructure` (p. 831).

6.866.2.3 `virtual DataStructure* activemq::commands::WireFormatInfo::cloneDataStructure () const` [virtual]

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Implements `activemq::commands::DataStructure` (p. 1660).

6.866.2.4 `virtual void activemq::commands::WireFormatInfo::copyDataStructure (const DataStructure *src)` [virtual]

Copy the contents of the passed object into this objects members, overwriting any existing data.

Returns:

src - Source Object

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.866.2.5 `virtual bool activemq::commands::WireFormatInfo::equals (const DataStructure *value) const` [virtual]

Compares the `DataStructure` (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::BaseCommand` (p. 759).

6.866.2.6 int activemq::commands::WireFormatInfo::getCacheSize () const

Gets the Cache Size setting.

Returns:

currently set cache size.

6.866.2.7 virtual unsigned char activemq::commands::WireFormatInfo::getDataStructureType () const [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataSetructure** (p. 1660) type copy.

Implements **activemq::commands::DataSetructure** (p. 1662).

6.866.2.8 const std::vector<unsigned char>& activemq::commands::WireFormatInfo::getMagic () const [inline]

Get the Magic field.

Returns:

const reference to a std::vector<char>

6.866.2.9 const std::vector<unsigned char>& activemq::commands::WireFormatInfo::getMarshaledProperties () const [inline]

Get the marshalledProperties field.

Returns:

const reference to a std::vector<char>

6.866.2.10 long long activemq::commands::WireFormatInfo::getMaxInactivityDuration () const

Returns the currently configured Max Inactivity duration.

Returns:

the set inactivity duration value.

6.866.2.11 `long long activemq::commands::WireFormatInfo::getMaxInactivityDurationInitialDelay () const`

Returns the currently configured Max Inactivity Initial Delay duration.

Returns:

the set inactivity duration initial delay value.

6.866.2.12 `virtual util::PrimitiveMap& activemq::commands::WireFormatInfo::getProperties () [inline, virtual]`

Gets the Properties for this **Command** (p. 1194).

Returns:

the Properties object for this **Command** (p. 1194).

6.866.2.13 `virtual const util::PrimitiveMap& activemq::commands::WireFormatInfo::getProperties () const [inline, virtual]`

Gets the Properties for this **Command** (p. 1194).

Returns:

the Properties object for this **Command** (p. 1194).

6.866.2.14 `int activemq::commands::WireFormatInfo::getVersion () const [inline]`

Get the current Wireformat Version.

Returns:

int that identifies the version

6.866.2.15 `bool activemq::commands::WireFormatInfo::isCacheEnabled () const`

Checks if the cacheEnabled flag is on.

Returns:

true if the flag is on.

6.866.2.16 `virtual bool activemq::commands::WireFormatInfo::isMarshalAware () const [inline, virtual]`

Indicates that this command is aware of Marshaling, and needs to have its Marshaling methods invoked.

Returns:

boolean indicating desire to be in marshaling stages

Reimplemented from **activemq::commands::BaseDataStructure** (p. 832).

6.866.2.17 bool activemq::commands::WireFormatInfo::isSizePrefixDisabled () const

Checks if the sizePrefixDisabled flag is on.

Returns:

true if the flag is on.

6.866.2.18 bool activemq::commands::WireFormatInfo::isStackTraceEnabled () const

Checks if the stackTraceEnabled flag is on.

Returns:

true if the flag is on.

6.866.2.19 bool activemq::commands::WireFormatInfo::isTcpNoDelayEnabled () const

Checks if the tcpNoDelayEnabled flag is on.

Returns:

true if the flag is on.

6.866.2.20 bool activemq::commands::WireFormatInfo::isTightEncodingEnabled () const

Checks if the tightEncodingEnabled flag is on.

Returns:

true if the flag is on.

6.866.2.21 bool activemq::commands::WireFormatInfo::isValid () const

Determines if we think this is a Valid **WireFormatInfo** (p. 3982) command.

Returns:

true if its valid.

6.866.2.22 `virtual bool activemq::commands::WireFormatInfo::isWireFormatInfo ()`
`const [inline, virtual]`

Returns:

answers true to the isWireFormatInfo query

Reimplemented from `activemq::commands::BaseCommand` (p. 763).

6.866.2.23 `void activemq::commands::WireFormatInfo::setCacheEnabled (bool`
`cacheEnabled)`

Sets if the cacheEnabled flag is on.

Parameters:

cacheEnabled - true to turn flag is on

6.866.2.24 `void activemq::commands::WireFormatInfo::setCacheSize (int value)`

Sets the Cache Size setting.

Parameters:

value - value to set to the cache size.

6.866.2.25 `void activemq::commands::WireFormatInfo::setMagic (const`
`std::vector< unsigned char > & magic) [inline]`

Sets the value of the magic field.

Parameters:

magic - const std::vector<char>

6.866.2.26 `void activemq::commands::WireFormatInfo::setMarshaledProperties`
`(const std::vector< unsigned char > & marshalledProperties) [inline]`

Sets the value of the marshalledProperties field.

Parameters:

marshalledProperties The Byte Array vector that contains the marshaled form of the Message (p. 2516) properties, this is the data sent over the wire.

6.866.2.27 `void activemq::commands::WireFormatInfo::setMaxInactivityDuration`
`(long long maxInactivityDuration)`

Sets the Max inactivity duration value.

Parameters:

maxInactivityDuration - max time a client can be inactive.

6.866.2.28 void activemq::commands::WireFormatInfo::setMaxInactivityDurationInitialDelay (long long *maxInactivityDurationInitialDelay*)

Sets the Max inactivity initial delay duration value.

Parameters:

maxInactivityDurationInitialDelay - time before the inactivity delay is checked.

6.866.2.29 virtual void activemq::commands::WireFormatInfo::setProperties (const util::PrimitiveMap & *map*) [inline, virtual]

Sets the Properties for this **Command** (p. 1194).

Parameters:

map - PrimitiveMap to copy

6.866.2.30 void activemq::commands::WireFormatInfo::setSizePrefixDisabled (bool *sizePrefixDisabled*)

Sets if the sizePrefixDisabled flag is on.

Parameters:

sizePrefixDisabled - true to turn flag is on

6.866.2.31 void activemq::commands::WireFormatInfo::setStackTraceEnabled (bool *stackTraceEnabled*)

Sets if the stackTraceEnabled flag is on.

Parameters:

stackTraceEnabled - ture to turn flag is on

6.866.2.32 void activemq::commands::WireFormatInfo::setTcpNoDelayEnabled (bool *tcpNoDelayEnabled*)

Sets if the tcpNoDelayEnabled flag is on.

Parameters:

tcpNoDelayEnabled - ture to turn flag is on

6.866.2.33 void activemq::commands::WireFormatInfo::setTightEncodingEnabled (bool *tightEncodingEnabled*)

Sets if the tightEncodingEnabled flag is on.

Parameters:

tightEncodingEnabled - true to turn flag is on

6.866.2.34 `void activemq::commands::WireFormatInfo::setVersion (int version)`
[inline]

Set the current Wireformat Version.

Parameters:

version - int that identifies the version

6.866.2.35 `virtual std::string activemq::commands::WireFormatInfo::toString ()`
`const` [virtual]

Returns a string containing the information for this **DataSet** (p.1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from **activemq::commands::BaseCommand** (p. 763).

6.866.2.36 `virtual decaf::lang::Pointer<commands::Command>`
`activemq::commands::WireFormatInfo::visit (ac-`
`tivemq::state::CommandVisitor * visitor) throw (`
`exceptions::ActiveMQException)` [virtual]

Allows a Visitor to visit this command and return a response to the command based on the command type being visited. The command will call the proper processXXX method in the visitor.

Returns:

a **Response** (p. 3285) to the visitor being called or NULL if no response.

Implements **activemq::commands::Command** (p.1198).

6.866.3 Field Documentation

6.866.3.1 `const unsigned char activemq::commands::WireFormatInfo::ID _-`
`WIREFORMATINFO = 1` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/WireFormatInfo.h`

6.867 activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3992).

#include <src/main/activemq/wireformat/openwire/marshal/v5/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.867.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3992).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.867.2 Constructor & Destructor Documentation

6.867.2.1 `activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.867.2.2 `virtual activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.867.3 Member Function Documentation

6.867.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.867.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.867.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.867.3.4 virtual void **activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.867.3.5 virtual int **activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.867.3.6 virtual void activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.867.3.7 virtual void activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/**WireFormatInfoMarshaller.h**

6.868 activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3996).

#include <src/main/activemq/wireformat/openwire/marshal/v6/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.868.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3996).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.868.2 Constructor & Destructor Documentation

6.868.2.1 `activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.868.2.2 `virtual activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.868.3 Member Function Documentation

6.868.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::createObject() const` [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.868.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::getDataStructureType() const` [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.868.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.868.3.4 virtual void **activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.868.3.5 virtual int **activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.868.3.6 virtual void activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.868.3.7 virtual void activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/**WireFormatInfoMarshaller.h**

6.869 activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4000).

#include <src/main/activemq/wireformat/openwire/marshal/v2/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.869.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4000).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.869.2 Constructor & Destructor Documentation

6.869.2.1 `activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.869.2.2 `virtual activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.869.3 Member Function Documentation

6.869.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.869.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.869.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.869.3.4 virtual void **activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.869.3.5 virtual int **activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.869.3.6 virtual void activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.869.3.7 virtual void activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/**WireFormatInfoMarshaller.h**

6.870 activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4004).

#include <src/main/activemq/wireformat/openwire/marshal/v4/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal1** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.870.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4004).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.870.2 Constructor & Destructor Documentation

6.870.2.1 `activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.870.2.2 `virtual activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.870.3 Member Function Documentation

6.870.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.870.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.870.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.870.3.4 virtual void **activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.870.3.5 virtual int **activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.870.3.6 virtual void activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.870.3.7 virtual void activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/**WireFormatInfoMarshaller.h**

6.871 activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4008).

#include <src/main/activemq/wireformat/openwire/marshal/v1/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.871.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4008).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.871.2 Constructor & Destructor Documentation

6.871.2.1 `activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.871.2.2 `virtual activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.871.3 Member Function Documentation

6.871.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.871.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.871.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.871.3.4 virtual void **activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.871.3.5 virtual int **activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.871.3.6 virtual void activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.871.3.7 virtual void activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/**WireFormatInfoMarshaller.h**

6.872 activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4012).

#include <src/main/activemq/wireformat/openwire/marshal/v3/WireFormatInfoMarshaller.h>Inheritance diagram for activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller:

Public Member Functions

- **WireFormatInfoMarshaller** ()
- virtual **~WireFormatInfoMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**, **utils::BooleanStream *bs**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataInputStream *dataIn**) throw (**decaf::io::IOException**)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (**OpenWireFormat *wireFormat**, **commands::DataStructure *dataStructure**, **decaf::io::DataOutputStream *dataOut**) throw (**decaf::io::IOException**)
Write a object instance to data output stream.

6.872.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4012).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.872.2 Constructor & Destructor Documentation

6.872.2.1 `activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::WireFormatInfoMarshaller()` [inline]

6.872.2.2 `virtual activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::~~WireFormatInfoMarshaller()` [inline, virtual]

6.872.3 Member Function Documentation

6.872.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.872.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.872.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1624).

6.872.3.4 virtual void **activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::looseUnmarshal** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **decaf::io::DataInputStream** * *dataIn*) throw (**decaf::io::IOException**) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1631).

6.872.3.5 virtual int **activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::tightMarshal1** (**OpenWireFormat** * *wireFormat*, **commands::DataStructure** * *dataStructure*, **utils::BooleanStream** * *bs*) throw (**decaf::io::IOException**) [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p. 1638).

6.872.3.6 virtual void activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p.107).

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1645).

6.872.3.7 virtual void activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Implements **activemq::wireformat::openwire::marshal::DataStreamMarshaller** (p.1652).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/**WireFormatInfoMarshaller.h**

6.873 activemq::wireformat::WireFormatNegotiator Class Reference

Defines a **WireFormatNegotiator** (p. 4016) which allows a **WireFormat** (p. 3976) to.

#include <src/main/activemq/wireformat/WireFormatNegotiator.h>Inheritance diagram for activemq::wireformat::WireFormatNegotiator:

Public Member Functions

- **WireFormatNegotiator** (const **Pointer**< **transport::Transport** > &next)
Constructor.
- virtual ~**WireFormatNegotiator** ()

6.873.1 Detailed Description

Defines a **WireFormatNegotiator** (p. 4016) which allows a **WireFormat** (p. 3976) to.

6.873.2 Constructor & Destructor Documentation

- 6.873.2.1** **activemq::wireformat::WireFormatNegotiator::WireFormatNegotiator**
(const **Pointer**< **transport::Transport** > & *next*) [inline]

Constructor.

Parameters:

- next* - the next Transport in the chain

- 6.873.2.2** **virtual**
activemq::wireformat::WireFormatNegotiator::~~WireFormatNegotiator
() [inline, virtual]

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/**WireFormatNegotiator.h**

6.874 activemq::wireformat::WireFormatRegistry Class Reference

Registry of all **WireFormat** (p. 3976) Factories that are available to the client at runtime.

```
#include <src/main/activemq/wireformat/WireFormatRegistry.h>
```

Public Member Functions

- virtual **~WireFormatRegistry** ()
- **WireFormatFactory** * **findFactory** (const std::string &name) const throw (decaf::lang::exceptions::NoSuchElementException)

*Gets a Registered **WireFormatFactory** (p. 3980) from the Registry and returns it if there is not a registered format factory with the given name an exception is thrown.*

- void **registerFactory** (const std::string &name, **WireFormatFactory** *factory) throw (decaf::lang::exceptions::IllegalArgumentException, decaf::lang::exceptions::NullPointerException)

*Registers a new **WireFormatFactory** (p. 3980) with this Registry.*

- void **unregisterFactory** (const std::string &name)

Unregisters the Factory with the given name and deletes that instance of the Factory.

- std::vector< std::string > **getWireFormatNames** () const

Retrieves a list of the names of all the Registered WireFormat's in this Registry.

Static Public Member Functions

- static **WireFormatRegistry** & **getInstance** ()

*Gets the single instance of the **WireFormatRegistry** (p. 4017).*

6.874.1 Detailed Description

Registry of all **WireFormat** (p. 3976) Factories that are available to the client at runtime. New WireFormat's must have a factory registered here before a connection attempt is made.

Since:

3.0

6.874.2 Constructor & Destructor Documentation

6.874.2.1 virtual
activemq::wireformat::WireFormatRegistry::~~WireFormatRegistry ()
[virtual]

6.874.3 Member Function Documentation

6.874.3.1 WireFormatFactory* ac-
tivemq::wireformat::WireFormatRegistry::findFactory (const std::string
& *name*) const throw (decaf::lang::exceptions::NoSuchElementException
)

Gets a Registered **WireFormatFactory** (p. 3980) from the Registry and returns it if there is not a registered format factory with the given name an exception is thrown.

Parameters:

name The name of the Factory to find in the Registry.

Returns:

the Factory registered under the given name.

Exceptions:

NoSuchElementException if no factory is registered with that name.

6.874.3.2 static WireFormatRegistry& ac-
tivemq::wireformat::WireFormatRegistry::getInstance ()
[static]

Gets the single instance of the **WireFormatRegistry** (p. 4017).

Returns:

reference to the single instance of this Registry

6.874.3.3 std::vector<std::string> ac-
tivemq::wireformat::WireFormatRegistry::getWireFormatNames ()
const

Retrieves a list of the names of all the Registered WireFormat's in this Registry.

Returns:

stl vector of strings with all the **WireFormat** (p. 3976) names registered.

6.874.3.4 `void activemq::wireformat::WireFormatRegistry::registerFactory`
 `(const std::string & name, WireFormatFactory * factory)`
 `throw (decaf::lang::exceptions::IllegalArgumentException,`
 `decaf::lang::exceptions::NullPointerException)`

Registers a new **WireFormatFactory** (p. 3980) with this Registry. If a Factory with the given name is already registered it is overwritten with the new one. Once a factory is added to the Registry its lifetime is controlled by the Registry, it will be deleted once the Registry has been deleted.

Parameters:

name The name of the new Factory to register.
 factory The new Factory to add to the Registry.

Exceptions:

IllegalArgumentException if name is the empty string.
 NullPointerException if the Factory is Null.

6.874.3.5 `void activemq::wireformat::WireFormatRegistry::unregisterFactory`
 `(const std::string & name)`

Unregisters the Factory with the given name and deletes that instance of the Factory.

Parameters:

name Name of the Factory to unregister and destroy

The documentation for this class was generated from the following file:

- `src/main/activemq/wireformat/WireFormatRegistry.h`

6.875 activemq::transport::inactivity::WriteChecker Class Reference

Runnable class used by the {.

#include <src/main/activemq/transport/inactivity/WriteChecker.h>Inheritance diagram for activemq::transport::inactivity::WriteChecker:

Public Member Functions

- **WriteChecker** (**InactivityMonitor** *parent)
- virtual ~**WriteChecker** ()
- virtual void **run** ()

Run method - called by the Thread class in the context of the thread.

6.875.1 Detailed Description

Runnable class used by the {.

See also:

InactivityMonitor (p. 2004)} to make periodic writes to the underlying **transport** (p. 97) if no other write activity is going on in order to more quickly detect failures of the connection to the broker.

Since:

3.1.0

6.875.2 Constructor & Destructor Documentation

6.875.2.1 **activemq::transport::inactivity::WriteChecker::WriteChecker** (**InactivityMonitor** * *parent*)

6.875.2.2 **virtual activemq::transport::inactivity::WriteChecker::~~WriteChecker** ()
[virtual]

6.875.3 Member Function Documentation

6.875.3.1 **virtual void activemq::transport::inactivity::WriteChecker::run** ()
[virtual]

Run method - called by the Thread class in the context of the thread.

Implements **decaf::lang::Runnable** (p. 3325).

The documentation for this class was generated from the following file:

- src/main/activemq/transport/inactivity/**WriteChecker.h**

6.876 decaf::io::Writer Class Reference

#include <src/main/decaf/io/Writer.h> Inheritance diagram for decaf::io::Writer:

Public Member Functions

- **Writer** ()
- virtual **~Writer** ()
- virtual void **write** (char v) throw (decaf::io::IOException)
Writes an single byte char value.
- virtual void **write** (const std::vector< char > &buffer) throw (decaf::io::IOException)
Writes an array of Chars.
- virtual void **write** (const char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
Writes a byte array to the output stream.
- virtual void **write** (const char *buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)
Writes a byte array to the output stream.
- virtual void **write** (const std::string &str) throw (decaf::io::IOException)
Writes a string.
- virtual void **write** (const std::string &str, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException)
Writes a string.
- virtual **decaf::lang::Appendable** & **append** (char value) throw (decaf::io::IOException)
Appends the specified character to this Appendable.
- virtual **decaf::lang::Appendable** & **append** (const **decaf::lang::CharSequence** *csq) throw (decaf::io::IOException)
Appends the specified character sequence to this Appendable.
- virtual **decaf::lang::Appendable** & **append** (const **decaf::lang::CharSequence** *csq, int start, int end) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException)
Appends a subsequence of the specified character sequence to this Appendable.

Protected Member Functions

- virtual void **doWriteArrayBounded** (const char *buffer, int size, int offset, int length)=0 throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)

Override this method to customize the functionality of the method `write(char buffer, int size, int offset, int length)`.*

- virtual void **doWriteChar** (char v) throw (decaf::io::IOException)
- virtual void **doWriteVector** (const std::vector< char > &buffer) throw (decaf::io::IOException)
- virtual void **doWriteArray** (const char *buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)
- virtual void **doWriteString** (const std::string &str) throw (decaf::io::IOException)
- virtual void **doWriteStringBounded** (const std::string &str, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException)
- virtual **decaf::lang::Appendable** & **doAppendChar** (char value) throw (decaf::io::IOException)
- virtual **decaf::lang::Appendable** & **doAppendCharSequence** (const **decaf::lang::CharSequence** *csq) throw (decaf::io::IOException)
- virtual **decaf::lang::Appendable** & **doAppendCharSequenceStartEnd** (const **decaf::lang::CharSequence** *csq, int start, int end) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException)

6.876.1 Constructor & Destructor Documentation

6.876.1.1 decaf::io::Writer::Writer ()

6.876.1.2 virtual decaf::io::Writer::~~Writer () [virtual]

6.876.2 Member Function Documentation

6.876.2.1 virtual decaf::lang::Appendable& decaf::io::Writer::append (const decaf::lang::CharSequence * *csq*, int *start*, int *end*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Appends a subsequence of the specified character sequence to this Appendable.

Parameters:

csq - The character sequence from which a subsequence will be appended. If *csq* is NULL, then characters will be appended as if *csq* contained the string "null".

start The index of the first character in the subsequence.

end The index of the character following the last character in the subsequence.

Returns:

a Reference to this Appendable

Exceptions:

Exception if an error occurs.

IndexOutOfBoundsException *start* is greater than *end*, or *end* is greater than *csq.length()*

Implements **decaf::lang::Appendable** (p. 726).

6.876.2.2 `virtual decaf::lang::Appendable& decaf::io::Writer::append (const decaf::lang::CharSequence * csq) throw (decaf::io::IOException)`
[virtual]

Appends the specified character sequence to this Appendable.

Parameters:

csq The character sequence from which a subsequence will be appended. If *csq* is NULL, then characters will be appended as if *csq* contained the string "null".

Returns:

a Reference to this Appendable.

Exceptions:

Exception if an error occurs.

Implements **decaf::lang::Appendable** (p. 726).

6.876.2.3 `virtual decaf::lang::Appendable& decaf::io::Writer::append (char value)`
`throw (decaf::io::IOException)` [virtual]

Appends the specified character to this Appendable.

Parameters:

value The character to append.

Returns:

a Reference to this Appendable

Exceptions:

Exception if an error occurs.

Implements **decaf::lang::Appendable** (p. 726).

- 6.876.2.4 virtual decaf::lang::Appendable& decaf::io::Writer::doAppendChar (char *value*) throw (decaf::io::IOException) [protected, virtual]
- 6.876.2.5 virtual decaf::lang::Appendable& decaf::io::Writer::doAppendCharSequence (const decaf::lang::CharSequence * *csq*) throw (decaf::io::IOException) [protected, virtual]
- 6.876.2.6 virtual decaf::lang::Appendable& decaf::io::Writer::doAppendCharSequenceStartEnd (const decaf::lang::CharSequence * *csq*, int *start*, int *end*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]
- 6.876.2.7 virtual void decaf::io::Writer::doWriteArray (const char * *buffer*, int *size*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException) [protected, virtual]
- 6.876.2.8 virtual void decaf::io::Writer::doWriteArrayBounded (const char * *buffer*, int *size*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, pure virtual]

Override this method to customize the functionality of the method write(char* buffer, int size, int offset, int length). All subclasses must override this method to provide the basic **Writer** (p. 4021) functionality.

Implemented in **decaf::io::OutputStreamWriter** (p. 2916).

- 6.876.2.9 virtual void decaf::io::Writer::doWriteChar (char *v*) throw (decaf::io::IOException) [protected, virtual]
- 6.876.2.10 virtual void decaf::io::Writer::doWriteString (const std::string & *str*) throw (decaf::io::IOException) [protected, virtual]
- 6.876.2.11 virtual void decaf::io::Writer::doWriteStringBounded (const std::string & *str*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException) [protected, virtual]
- 6.876.2.12 virtual void decaf::io::Writer::doWriteVector (const std::vector< char > & *buffer*) throw (decaf::io::IOException) [protected, virtual]
- 6.876.2.13 virtual void decaf::io::Writer::write (const std::string & *str*, int *offset*, int *length*) throw (decaf::io::IOException, decaf::lang::exceptions::IndexOutOfBoundsException) [virtual]

Writes a string.

Parameters:

str The string to be written.

offset The position in the array to start writing from.

length The number of bytes in the array to write.

Exceptions:

IOException (p. 2142) thrown if an error occurs.

IndexOutOfBoundsException if offset+length is greater than the string length.

6.876.2.14 `virtual void decaf::io::Writer::write (const std::string & str) throw (decaf::io::IOException)` [virtual]

Writes a string.

Parameters:

str The string to be written.

Exceptions:

IOException (p. 2142) thrown if an error occurs.

6.876.2.15 `virtual void decaf::io::Writer::write (const char * buffer, int size, int offset, int length) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException, decaf::lang::exceptions::IndexOutOfBoundsException)` [virtual]

Writes a byte array to the output stream.

Parameters:

buffer The byte array to write (cannot be NULL).

size The size in bytes of the buffer passed.

offset The position in the array to start writing from.

length The number of bytes in the array to write.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

NullPointerException if buffer is NULL.

IndexOutOfBoundsException if offset + length > size of the buffer.

6.876.2.16 `virtual void decaf::io::Writer::write (const char * buffer, int size) throw (decaf::io::IOException, decaf::lang::exceptions::NullPointerException)` [virtual]

Writes a byte array to the output stream.

Parameters:

buffer The byte array to write (cannot be NULL).

size The size in bytes of the buffer passed.

Exceptions:

IOException (p. 2142) if an I/O error occurs.

NullPointerException if buffer is NULL.

6.876.2.17 `virtual void decaf::io::Writer::write (const std::vector< char > & buffer)
throw (decaf::io::IOException) [virtual]`

Writes an array of Chars.

Parameters:

buffer The array to be written.

Exceptions:

IOException (p. 2142) thrown if an error occurs.

6.876.2.18 `virtual void decaf::io::Writer::write (char v) throw (
decaf::io::IOException) [virtual]`

Writes an single byte char value.

Parameters:

v The value to be written.

Exceptions:

IOException (p. 2142) thrown if an error occurs.

The documentation for this class was generated from the following file:

- src/main/decaf/io/**Writer.h**

6.877 decaf::security::auth::x500::X500Principal Class Reference

`#include <src/main/decaf/security/auth/x500/X500Principal.h>` Inheritance diagram for `decaf::security::auth::x500::X500Principal`:

Public Member Functions

- virtual `~X500Principal ()`
- virtual `std::string getName () const =0`
Provides the name of this principal.
- virtual void `getEncoded (std::vector< unsigned char > &output) const =0`
- virtual int `hashCode () const =0`

6.877.1 Constructor & Destructor Documentation

6.877.1.1 virtual `decaf::security::auth::x500::X500Principal::~X500Principal ()`
[inline, virtual]

6.877.2 Member Function Documentation

6.877.2.1 virtual void `decaf::security::auth::x500::X500Principal::getEncoded (std::vector< unsigned char > & output) const` [pure virtual]

6.877.2.2 virtual `std::string decaf::security::auth::x500::X500Principal::getName () const` [pure virtual]

Provides the name of this principal.

Returns:

the name of this principal.

Implements `decaf::security::Principal` (p. 3026).

6.877.2.3 virtual int `decaf::security::auth::x500::X500Principal::hashCode () const`
[pure virtual]

The documentation for this class was generated from the following file:

- `src/main/decaf/security/auth/x500/X500Principal.h`

6.878 decaf::security::cert::X509Certificate Class Reference

Base interface for all identity certificates.

`#include <src/main/decaf/security/cert/X509Certificate.h>` Inheritance diagram for decaf::security::cert::X509Certificate:

Public Member Functions

- virtual `~X509Certificate ()`
- virtual void `checkValidity ()` const =0 throw (CertificateExpiredException, CertificateNotYetValidException)
- virtual void `checkValidity (const decaf::util::Date &date)` const =0 throw (CertificateExpiredException, CertificateNotYetValidException)
- virtual int `getBasicConstraints ()` const =0
- virtual void `getIssuerUniqueID (std::vector< bool > &output)` const =0
- virtual const X500Principal * `getIssuerX500Principal ()` const =0
- virtual void `getKeyUsage (std::vector< unsigned char > &output)` const =0
- virtual Date `getNotAfter ()` const =0
- virtual Date `getNotBefore ()` const =0
- virtual std::string `getSigAlgName ()` const =0
- virtual std::string `getSigAlgOID ()` const =0
- virtual void `getSigAlgParams (std::vector< unsigned char > &output)` const =0
- virtual void `getSignature (std::vector< unsigned char > &output)` const =0
- virtual void `getSubjectUniqueID (std::vector< bool > &output)` const =0
- virtual const X500Principal * `getSubjectX500Principal ()` const =0
- virtual void `getTBSCertificate (std::vector< unsigned char > &output)` const =0 throw (CertificateEncodingException)
- virtual int `getVersion ()` const =0

6.878.1 Detailed Description

Base interface for all identity certificates.

6.878.2 Constructor & Destructor Documentation

6.878.2.1 virtual decaf::security::cert::X509Certificate::~X509Certificate ()
[inline, virtual]

6.878.3 Member Function Documentation

6.878.3.1 virtual void decaf::security::cert::X509Certificate::checkValidity (const decaf::util::Date & *date*) const throw (CertificateExpiredException, CertificateNotYetValidException) [pure virtual]

6.878.3.2 virtual void decaf::security::cert::X509Certificate::checkValidity () const throw (CertificateExpiredException, CertificateNotYetValidException) [pure virtual]

6.878.3.3 virtual int decaf::security::cert::X509Certificate::getBasicConstraints () const [pure virtual]

6.878.3.4 virtual void decaf::security::cert::X509Certificate::getIssuerUniqueID (std::vector< bool > & *output*) const [pure virtual]

6.878.3.5 virtual const X500Principal* decaf::security::cert::X509Certificate::getIssuerX500Principal () const [pure virtual]

6.878.3.6 virtual void decaf::security::cert::X509Certificate::getKeyUsage (std::vector< unsigned char > & *output*) const [pure virtual]

6.878.3.7 virtual Date decaf::security::cert::X509Certificate::getNotAfter () const [pure virtual]

6.878.3.8 virtual Date decaf::security::cert::X509Certificate::getNotBefore () const [pure virtual]

6.878.3.9 virtual std::string decaf::security::cert::X509Certificate::getSigAlgName () const [pure virtual]

6.878.3.10 virtual std::string decaf::security::cert::X509Certificate::getSigAlgOID () const [pure virtual]

6.878.3.11 virtual void decaf::security::cert::X509Certificate::getSigAlgParams (std::vector< unsigned char > & *output*) const [pure virtual]

6.878.3.12 virtual void decaf::security::cert::X509Certificate::getSignature (std::vector< unsigned char > & *output*) const [pure virtual]

6.878.3.13 virtual void decaf::security::cert::X509Certificate::getSubjectUniqueID (std::vector< bool > & *output*) const [pure virtual]

6.878.3.14 virtual const X500Principal* decaf::security::cert::X509Certificate::getSubjectX500Principal () const [pure virtual]

6.878.3.15 virtual void decaf::security::cert::X509Certificate::getTBSCertificate (std::vector< unsigned char > & *output*) const throw (CertificateEncodingException) [pure virtual]

6.878.3.16 virtual int decaf::security::cert::X509Certificate::getVersion () const [pure virtual]

- `src/main/decaf/security/cert/X509Certificate.h`

6.879 activemq::commands::XATransactionId Class Reference

#include <src/main/activemq/commands/XATransactionId.h> Inheritance diagram for activemq::commands::XATransactionId:

Public Types

- typedef decaf::lang::PointerComparator< XATransactionId > COMPARATOR

Public Member Functions

- XATransactionId ()
- XATransactionId (const XATransactionId &other)
- virtual ~XATransactionId ()
- virtual unsigned char **getDataStructureType** () const
Get the unique identifier that this object and its own Marshaler share.
- virtual XATransactionId * **cloneDataStructure** () const
Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.
- virtual void **copyDataStructure** (const DataStructure *src)
Copy the contents of the passed object into this object's members, overwriting any existing data.
- virtual std::string **toString** () const
Returns a string containing the information for this DataStructure (p. 1660) such as its type and value of its elements.
- virtual bool **equals** (const DataStructure *value) const
Compares the DataStructure (p. 1660) passed in to this one, and returns if they are equivalent.
- virtual int **getFormatId** () const
- virtual void **setFormatId** (int formatId)
- virtual const std::vector< unsigned char > & **getGlobalTransactionId** () const
- virtual std::vector< unsigned char > & **getGlobalTransactionId** ()
- virtual void **setGlobalTransactionId** (const std::vector< unsigned char > &globalTransactionId)
- virtual const std::vector< unsigned char > & **getBranchQualifier** () const
- virtual std::vector< unsigned char > & **getBranchQualifier** ()
- virtual void **setBranchQualifier** (const std::vector< unsigned char > &branchQualifier)
- virtual int **compareTo** (const XATransactionId &value) const
- virtual bool **equals** (const XATransactionId &value) const
- virtual bool **operator==** (const XATransactionId &value) const
- virtual bool **operator<** (const XATransactionId &value) const
- XATransactionId & **operator=** (const XATransactionId &other)

Static Public Attributes

- static const unsigned char **ID_XATRANSACTIONID** = 112

Protected Attributes

- int **formatId**
- std::vector< unsigned char > **globalTransactionId**
- std::vector< unsigned char > **branchQualifier**

6.879.1 Member Typedef Documentation

- 6.879.1.1** `typedef decaf::lang::PointerComparator<XATransactionId>
activemq::commands::XATransactionId::COMPARATOR`

Reimplemented from `activemq::commands::TransactionId` (p. 3819).

6.879.2 Constructor & Destructor Documentation

- 6.879.2.1** `activemq::commands::XATransactionId::XATransactionId ()`
- 6.879.2.2** `activemq::commands::XATransactionId::XATransactionId (const
XATransactionId & other)`
- 6.879.2.3** `virtual activemq::commands::XATransactionId::~~XATransactionId ()
[virtual]`

6.879.3 Member Function Documentation

- 6.879.3.1** `virtual XATransactionId* ac-
tivemq::commands::XATransactionId::cloneDataStructure
() const [virtual]`

Clone this object and return a new instance that the caller now owns, this will be an exact copy of this one.

Returns:

new copy of this object.

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

- 6.879.3.2** `virtual int activemq::commands::XATransactionId::compareTo (const
XATransactionId & value) const [virtual]`

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

- 6.879.3.3** `virtual void activemq::commands::XATransactionId::copyDataStructure
(const DataStructure * src) [virtual]`

Copy the contents of the passed object into this object's members, overwriting any existing data.

Parameters:

src - Source Object

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.879.3.4 `virtual bool activemq::commands::XATransactionId::equals (const XATransactionId & value) const` [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3820).

6.879.3.5 `virtual bool activemq::commands::XATransactionId::equals (const DataStructure * value) const` [virtual]

Compares the **DataStructure** (p. 1660) passed in to this one, and returns if they are equivalent. Equivalent here means that they are of the same type, and that each element of the objects are the same.

Returns:

true if DataStructure's are Equal.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.3.6 `virtual std::vector<unsigned char>& activemq::commands::XATransactionId::getBranchQualifier ()` [virtual]

6.879.3.7 `virtual const std::vector<unsigned char>& activemq::commands::XATransactionId::getBranchQualifier () const` [virtual]

6.879.3.8 `virtual unsigned char activemq::commands::XATransactionId::getDataStructureType () const` [virtual]

Get the unique identifier that this object and its own Marshaler share.

Returns:

new **DataStructure** (p. 1660) type copy.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.3.9 virtual int activemq::commands::XATransactionId::getFormatId () const [virtual]

6.879.3.10 virtual std::vector<unsigned char>& activemq::commands::XATransactionId::getGlobalTransactionId () [virtual]

6.879.3.11 virtual const std::vector<unsigned char>& activemq::commands::XATransactionId::getGlobalTransactionId () const [virtual]

6.879.3.12 virtual bool activemq::commands::XATransactionId::operator< (const XATransactionId & *value*) const [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.3.13 XATransactionId& activemq::commands::XATransactionId::operator= (const XATransactionId & *other*)

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.3.14 virtual bool activemq::commands::XATransactionId::operator== (const XATransactionId & *value*) const [virtual]

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.3.15 virtual void activemq::commands::XATransactionId::setBranchQualifier (const std::vector< unsigned char > & *branchQualifier*) [virtual]

6.879.3.16 virtual void activemq::commands::XATransactionId::setFormatId (int *formatId*) [virtual]

6.879.3.17 virtual void activemq::commands::XATransactionId::setGlobalTransactionId (const std::vector< unsigned char > & *globalTransactionId*) [virtual]

6.879.3.18 virtual std::string activemq::commands::XATransactionId::toString () const [virtual]

Returns a string containing the information for this **DataSet** (p. 1660) such as its type and value of its elements.

Returns:

formatted string useful for debugging.

Reimplemented from `activemq::commands::TransactionId` (p. 3821).

6.879.4 Field Documentation

- 6.879.4.1 `std::vector<unsigned char> activemq::commands::XATransactionId::branchQualifier` [protected]
- 6.879.4.2 `int activemq::commands::XATransactionId::formatId` [protected]
- 6.879.4.3 `std::vector<unsigned char> activemq::commands::XATransactionId::globalTransactionId` [protected]
- 6.879.4.4 `const unsigned char activemq::commands::XATransactionId::ID_ - XATRANSACTIONID = 112` [static]

The documentation for this class was generated from the following file:

- `src/main/activemq/commands/XATransactionId.h`

6.880 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller Class Reference

Marshaling **code** (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4036).

#include <src/main/activemq/wireformat/openwire/marshal/v6/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.880.1 Detailed Description

Marshaling **code** (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4036).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.880.2 Constructor & Destructor Documentation

6.880.2.1 `activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.880.2.2 `virtual activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.880.3 Member Function Documentation

6.880.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.880.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.880.3.3 `virtual void activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3844).

6.880.3.4 `virtual void activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3844).

6.880.3.5 `virtual int activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller` (p. 3845).

6.880.3.6 virtual void activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller** (p. 3845).

6.880.3.7 virtual void activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller** (p. 3846).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v6/XATransactionIdMarshaller.h

6.881 activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4040).

#include <src/main/activemq/wireformat/openwire/marshal/v2/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.881.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4040).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.881.2 Constructor & Destructor Documentation

6.881.2.1 `activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.881.2.2 `virtual activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.881.3 Member Function Documentation

6.881.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.881.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.881.3.3 `virtual void activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3832).

6.881.3.4 `virtual void activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3832).

6.881.3.5 `virtual int activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller` (p. 3833).

6.881.3.6 virtual void activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller** (p. 3833).

6.881.3.7 virtual void activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller** (p. 3834).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v2/XATransactionIdMarshaller.h

6.882 activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4044).

#include <src/main/activemq/wireformat/openwire/marshal/v4/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.882.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4044).

NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.882.2 Constructor & Destructor Documentation

6.882.2.1 `activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.882.2.2 `virtual activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.882.3 Member Function Documentation

6.882.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.882.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.882.3.3 `virtual void activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3840).

6.882.3.4 `virtual void activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3840).

6.882.3.5 `virtual int activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller` (p. 3841).

6.882.3.6 virtual void activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller** (p. 3841).

6.882.3.7 virtual void activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller** (p. 3842).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v4/XATransactionIdMarshaller.h

6.883 activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4048).

#include <src/main/activemq/wireformat/openwire/marshal/v1/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.883.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4048).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.883.2 Constructor & Destructor Documentation

6.883.2.1 `activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.883.2.2 `virtual activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.883.3 Member Function Documentation

6.883.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.883.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.883.3.3 `virtual void activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3828).

6.883.3.4 `virtual void activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3828).

6.883.3.5 `virtual int activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller` (p. 3829).

6.883.3.6 virtual void activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller** (p. 3829).

6.883.3.7 virtual void activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller** (p. 3830).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v1/XATransactionIdMarshaller.h

6.884 activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4052).

#include <src/main/activemq/wireformat/openwire/marshal/v3/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.884.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4052).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.884.2 Constructor & Destructor Documentation

6.884.2.1 `activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.884.2.2 `virtual activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.884.3 Member Function Documentation

6.884.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.884.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.884.3.3 `virtual void activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3836).

6.884.3.4 `virtual void activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3836).

6.884.3.5 `virtual int activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller` (p. 3837).

6.884.3.6 virtual void activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller** (p. 3837).

6.884.3.7 virtual void activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller** (p. 3838).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v3/XATransactionIdMarshaller.h

6.885 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller Class Reference

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4056).

#include <src/main/activemq/wireformat/openwire/marshal/v5/XATransactionIdMarshaller.h> Inheritance diagram for activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller:

Public Member Functions

- **XATransactionIdMarshaller** ()
- virtual **~XATransactionIdMarshaller** ()
- virtual **commands::DataStructure * createObject** () const
Creates a new instance of this marshalable type.
- virtual unsigned char **getDataStructureType** () const
Get the Data Structure Type that identifies this Marshaler.
- virtual void **tightUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual int **tightMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write the booleans that this object uses to a BooleanStream.
- virtual void **tightMarshal2** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut, **utils::BooleanStream** *bs) throw (decaf::io::IOException)
Write a object instance to data output stream.
- virtual void **looseUnmarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataInputStream** *dataIn) throw (decaf::io::IOException)
Un-marshal an object instance from the data input stream.
- virtual void **looseMarshal** (OpenWireFormat *wireFormat, **commands::DataStructure** *dataStructure, **decaf::io::DataOutputStream** *dataOut) throw (decaf::io::IOException)
Write a object instance to data output stream.

6.885.1 Detailed Description

Marshaling `code` (p. 1183) for Open Wire Format for **XATransactionIdMarshaller** (p. 4056).
NOTE!: This file is auto generated - do not modify! if you need to make a change, please see the Java Classes in the activemq-openwire-generator module

6.885.2 Constructor & Destructor Documentation

6.885.2.1 `activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::XATransactionIdMarshaller()` [inline]

6.885.2.2 `virtual activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::~~XATransactionIdMarshaller()` [inline, virtual]

6.885.3 Member Function Documentation

6.885.3.1 `virtual commands::DataStructure* activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::createObject()` const [virtual]

Creates a new instance of this marshalable type.

Returns:

new DataStructure object pointer caller owns it.

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1611).

6.885.3.2 `virtual unsigned char activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::getDataStructureType()` const [virtual]

Get the Data Structure Type that identifies this Marshaler.

Returns:

byte holding the data structure type value

Implements `activemq::wireformat::openwire::marshal::DataStreamMarshaller` (p. 1617).

6.885.3.3 `virtual void activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::looseMarshal(OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataOutputStream * dataOut) throw (decaf::io::IOException)` [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataOut - BinaryWriter that provides that data sink

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller` (p. 3824).

6.885.3.4 `virtual void activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::looseUnmarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, decaf::io::DataInputStream * dataIn) throw (decaf::io::IOException)` [virtual]

Un-marshal an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

dataIn - BinaryReader that provides that data source

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from `activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller` (p. 3824).

6.885.3.5 `virtual int activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::tightMarshal (OpenWireFormat * wireFormat, commands::DataStructure * dataStructure, utils::BooleanStream * bs) throw (decaf::io::IOException)` [virtual]

Write the booleans that this object uses to a BooleanStream.

Parameters:

wireFormat - describes the wire format of the broker

dataStructure - Object to be marshaled

bs - BooleanStream stream used to pack bits from the wire.

Returns:

int value indicating the size of the marshaled object.

Exceptions:

IOException if an error occurs during the `marshal` (p. 107).

Reimplemented from `activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller` (p. 3825).

6.885.3.6 virtual void activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::tightMarshal2 (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataOutputStream * *dataOut*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Write a object instance to data output stream.

Parameters:

wireFormat - describes the wire format of the broker
dataStructure - Object to be marshaled
dataOut - BinaryReader that provides that data sink
bs - BooleanStream stream used to pack bits from the wire.

Exceptions:

IOException if an error occurs during the **marshal** (p. 107).

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3825).

6.885.3.7 virtual void activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller::tightUnmarshal (OpenWireFormat * *wireFormat*, commands::DataStructure * *dataStructure*, decaf::io::DataInputStream * *dataIn*, utils::BooleanStream * *bs*) throw (decaf::io::IOException) [virtual]

Un-marshall an object instance from the data input stream.

Parameters:

wireFormat - describes the wire format of the broker.
dataStructure - Object to be un-marshaled.
dataIn - BinaryReader that provides that data.
bs - BooleanStream stream used to unpack bits from the wire.

Exceptions:

IOException if an error occurs during the unmarshal.

Reimplemented from **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller** (p. 3826).

The documentation for this class was generated from the following file:

- src/main/activemq/wireformat/openwire/marshal/v5/XATransactionIdMarshaller.h

6.886 decaf::util::logging::XMLFormatter Class Reference

Format a **LogRecord** (p. 2413) into a standard XML format.

#include <src/main/decaf/util/logging/XMLFormatter.h> Inheritance diagram for decaf::util::logging::XMLFormatter:

Public Member Functions

- **XMLFormatter** ()
- virtual **~XMLFormatter** ()
- virtual std::string **format** (const **LogRecord** &record) const
*Converts a **LogRecord** (p. 2413) into an XML string.*
- virtual std::string **getHead** (const **Handler** *handler)
Returns the header string for a set of log records formatted as XML strings, using the output handler's encoding if it is defined, otherwise using the default platform encoding.
- virtual std::string **getTail** (const **Handler** *handler)
Returns the tail string for a set of log records formatted as XML strings.

6.886.1 Detailed Description

Format a **LogRecord** (p. 2413) into a standard XML format. TODO - Currently only outputs UTF-8 The **XMLFormatter** (p. 4060) can be used with arbitrary character encodings, but it is recommended that it normally be used with UTF-8. The character encoding can be set on the output **Handler** (p. 1978).

Since:

1.0

6.886.2 Constructor & Destructor Documentation

6.886.2.1 decaf::util::logging::XMLFormatter::XMLFormatter ()

6.886.2.2 virtual decaf::util::logging::XMLFormatter::~~XMLFormatter ()
 [virtual]

6.886.3 Member Function Documentation

6.886.3.1 virtual std::string decaf::util::logging::XMLFormatter::format (const **LogRecord** & record) const [virtual]

Converts a **LogRecord** (p. 2413) into an XML string.

Parameters:

record The log record to be formatted.

Returns:

the log record formatted as an XML string.

Implements **decaf::util::logging::Formatter** (p. 1964).

6.886.3.2 virtual std::string decaf::util::logging::XMLFormatter::getHead (const Handler * *handler*) [virtual]

Returns the header string for a set of log records formatted as XML strings, using the output handler's encoding if it is defined, otherwise using the default platform encoding.

Parameters:

handler The output handler, may be NULL.

Returns:

the header string for log records formatted as XML strings.

6.886.3.3 virtual std::string decaf::util::logging::XMLFormatter::getTail (const Handler * *handler*) [virtual]

Returns the tail string for a set of log records formatted as XML strings.

Parameters:

handler The output handler, may be NULL.

Returns:

the tail string for log records formatted as XML strings.

The documentation for this class was generated from the following file:

- `src/main/decaf/util/logging/XMLFormatter.h`

6.887 z_stream_s Struct Reference

```
#include <src/main/decaf/internal/util/zip/zlib.h>
```

Data Fields

- `Bytef * next_in`
- `uInt avail_in`
- `uLong total_in`
- `Bytef * next_out`
- `uInt avail_out`
- `uLong total_out`
- `char * msg`
- `struct internal_state FAR * state`
- `alloc_func zalloc`
- `free_func zfree`
- `voidpf opaque`
- `int data_type`
- `uLong Adler`
- `uLong reserved`

6.887.1 Field Documentation

6.887.1.1 `uLong z_stream_s::Adler`

6.887.1.2 `uInt z_stream_s::avail_in`

6.887.1.3 `uInt z_stream_s::avail_out`

6.887.1.4 `int z_stream_s::data_type`

6.887.1.5 `char* z_stream_s::msg`

6.887.1.6 `Bytef* z_stream_s::next_in`

6.887.1.7 `Bytef* z_stream_s::next_out`

6.887.1.8 `voidpf z_stream_s::opaque`

6.887.1.9 `uLong z_stream_s::reserved`

6.887.1.10 `struct internal_state FAR* z_stream_s::state` [read]

6.887.1.11 `uLong z_stream_s::total_in`

6.887.1.12 `uLong z_stream_s::total_out`

6.887.1.13 `alloc_func z_stream_s::zalloc`

6.887.1.14 `free_func z_stream_s::zfree`

The documentation for this struct was generated from the following file:

- `src/main/decaf/internal/util/zip/zlib.h`

6.888 decaf::util::zip::ZipException Class Reference

#include <src/main/decaf/util/zip/ZipException.h> Inheritance diagram for decaf::util::zip::ZipException:

Public Member Functions

- **ZipException** () throw ()
Default Constructor.
- **ZipException** (const lang::Exception &ex) throw ()
Copy Constructor.
- **ZipException** (const ZipException &ex) throw ()
Copy Constructor.
- **ZipException** (const char *file, const int lineNumber, const std::exception *cause, const char *msg,...) throw ()
Constructor - Initializes the file name and line number where this message occurred.
- **ZipException** (const std::exception *cause) throw ()
Constructor.
- **ZipException** (const char *file, const int lineNumber, const char *msg,...) throw ()
Constructor.
- virtual **ZipException** * clone () const
Clones this exception.
- virtual ~**ZipException** () throw ()

6.888.1 Constructor & Destructor Documentation

6.888.1.1 decaf::util::zip::ZipException::ZipException () throw () [inline]

Default Constructor.

6.888.1.2 decaf::util::zip::ZipException::ZipException (const lang::Exception & ex) throw () [inline]

Copy Constructor.

Parameters:

ex the exception to copy

6.888.1.3 `decaf::util::zip::ZipException::ZipException (const ZipException & ex) throw () [inline]`

Copy Constructor.

Parameters:

ex the exception to copy, which is an instance of this type

6.888.1.4 `decaf::util::zip::ZipException::ZipException (const char * file, const int lineNumber, const std::exception * cause, const char * msg, ...) throw () [inline]`

Constructor - Initializes the file name and line number where this message occurred. Sets the message to report, using an optional list of arguments to parse into the message

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

cause The exception that was the cause for this one to be thrown.

msg The message to report

... list of primitives that are formatted into the message

6.888.1.5 `decaf::util::zip::ZipException::ZipException (const std::exception * cause) throw () [inline]`

Constructor.

Parameters:

cause Pointer to the exception that caused this one to be thrown, the object is cloned caller retains ownership.

6.888.1.6 `decaf::util::zip::ZipException::ZipException (const char * file, const int lineNumber, const char * msg, ...) throw () [inline]`

Constructor.

Parameters:

file The file name where exception occurs

lineNumber The line number where the exception occurred.

msg The message to report

... list of primitives that are formatted into the message

6.888.1.7 `virtual decaf::util::zip::ZipException::~~ZipException () throw ()`
 [inline, virtual]

6.888.2 Member Function Documentation

6.888.2.1 `virtual ZipException* decaf::util::zip::ZipException::clone () const`
 [inline, virtual]

Clones this exception. This is useful for cases where you need to preserve the type of the original exception as well as the message. All subclasses should override.

Returns:

a new instance of an Exception that is a copy of this one.

Reimplemented from **decaf::io::IOException** (p. 2144).

The documentation for this class was generated from the following file:

- `src/main/decaf/util/zip/ZipException.h`

Chapter 7

File Documentation

7.1 src/main/activemq/cmsutil/CachedConsumer.h File Reference

```
#include <cms/MessageConsumer.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::CachedConsumer**
A cached message consumer contained within a pooled session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.2 src/main/activemq/cmsutil/CachedProducer.h File Reference

```
#include <cms/MessageProducer.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::CachedProducer**
A cached message producer contained within a pooled session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.3 src/main/activemq/cmsutil/CmsAccessor.h File Reference

```
#include <cms/ConnectionFactory.h>
#include <activemq/cmsutil/ResourceLifecycleManager.h>
#include <activemq/util/Config.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
```

Data Structures

- class **activemq::cmsutil::CmsAccessor**

*Base class for **activemq.cmsutil.CmsTemplate** (p. 1170) and other CMS-accessing gateway helpers, defining common properties such as the CMS **cms.ConnectionFactory** (p. 1324) to operate on.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::cmsutil**

7.4 src/main/activemq/cmsutil/CmsDestinationAccessor.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/cmsutil/CmsAccessor.h>
#include <activemq/cmsutil/DynamicDestinationResolver.h>
```

Data Structures

- class **activemq::cmsutil::CmsDestinationAccessor**
Extends the `CmsAccessor` (p. 1153) to add support for resolving destination names.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.5 src/main/activemq/cmsutil/CmsTemplate.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/cmsutil/CmsDestinationAccessor.h>
#include <activemq/cmsutil/SessionCallback.h>
#include <activemq/cmsutil/ProducerCallback.h>
#include <activemq/cmsutil/SessionPool.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <cms/ConnectionFactory.h>
#include <cms/DeliveryMode.h>
#include <string>
```

Data Structures

- class **activemq::cmsutil::CmsTemplate**
CmsTemplate (p. 1170) simplifies performing synchronous CMS operations.
- class **activemq::cmsutil::CmsTemplate::ProducerExecutor**
- class **activemq::cmsutil::CmsTemplate::ResolveProducerExecutor**
- class **activemq::cmsutil::CmsTemplate::SendExecutor**
- class **activemq::cmsutil::CmsTemplate::ReceiveExecutor**
- class **activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.6 src/main/activemq/cmsutil/DestinationResolver.h File Reference

```
#include <cms/Session.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::DestinationResolver**
*Resolves a CMS destination name to a *Destination*.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.7 src/main/activemq/cmsutil/DynamicDestinationResolver.h File Reference

```
#include <activemq/cmsutil/DestinationResolver.h>
#include <cms/Session.h>
#include <decaf/util/StlMap.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::DynamicDestinationResolver**
*Resolves a CMS destination name to a *Destination*.*
- class **activemq::cmsutil::DynamicDestinationResolver::SessionResolver**
Manages maps of names to topics and queues for a single session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.8 src/main/activemq/cmsutil/MessageCreator.h File Reference

```
#include <cms/Session.h>
#include <cms/Message.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::MessageCreator**
Creates the user-defined message to be sent by the `CmsTemplate` (p. 1170).

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.9 src/main/activemq/cmsutil/PooledSession.h File Reference

```
#include <cms/Session.h>
#include <decaf/util/STLMap.h>
#include <activemq/cmsutil/CachedProducer.h>
#include <activemq/cmsutil/CachedConsumer.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::PooledSession**
A pooled session object that wraps around a delegate session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.10 src/main/activemq/cmsutil/ProducerCallback.h File Reference

```
#include <cms/Session.h>
#include <cms/MessageProducer.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::ProducerCallback**
Callback for sending a message to a CMS destination.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.11 src/main/activemq/cmsutil/ResourceLifecycleManager.h File Reference

```
#include <cms/Connection.h>
#include <cms/Session.h>
#include <cms/Destination.h>
#include <cms/MessageProducer.h>
#include <cms/MessageConsumer.h>
#include <activemq/util/Config.h>
#include <decaf/util/StlList.h>
```

Data Structures

- class **activemq::cmsutil::ResourceLifecycleManager**
Manages the lifecycle of a set of CMS resources.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.12 src/main/decaf/internal/util/ResourceLifecycleManager.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/StlSet.h>
#include <decaf/internal/util/Resource.h>
```

Data Structures

- class **decaf::internal::util::ResourceLifecycleManager**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.13 src/main/activemq/cmsutil/SessionCallback.h File Reference

```
#include <cms/Session.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::SessionCallback**
Callback for executing any number of operations on a provided CMS Session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.14 src/main/activemq/cmsutil/SessionPool.h File Reference

```
#include <activemq/cmsutil/PooledSession.h>
#include <decaf/util/concurrent/Mutex.h>
#include <cms/Connection.h>
#include <list>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::cmsutil::SessionPool**
A pool of CMS sessions from the same connection and with the same acknowledge mode.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::cmsutil**

7.15 src/main/activemq/commands/ActiveMQBlobMessage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <cms/Message.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQBlobMessage`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.16 src/main/activemq/commands/ActiveMQBytesMessage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <decaf/io/ByteArrayOutputStream.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <cms/BytesMessage.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class **activemq::commands::ActiveMQBytesMessage**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**

7.17 src/main/activemq/commands/ActiveMQDestination.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/ActiveMQProperties.h>
#include <cms/Destination.h>
#include <decaf/lang/Pointer.h>
#include <vector>
#include <string>
#include <map>
```

Data Structures

- class **activemq::commands::ActiveMQDestination**
- struct **activemq::commands::ActiveMQDestination::DestinationFilter**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.18 src/main/activemq/commands/ActiveMQMapMessage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <activemq/util/PrimitiveMap.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <cms/MapMessage.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQMapMessage`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.19 src/main/activemq/commands/ActiveMQMessage.h File Reference

```
#include <cms/Message.h>
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
```

Data Structures

- class **activemq::commands::ActiveMQMessage**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.20 src/main/activemq/commands/ActiveMQMessageTemplate.h File Reference

```
#include <cms/DeliveryMode.h>
#include <activemq/util/Config.h>
#include <activemq/commands/Message.h>
#include <activemq/core/ActiveMQAckHandler.h>
#include <activemq/core/ActiveMQConnection.h>
#include <activemq/wireformat/openwire/utils/MessagePropertyInterceptor.h>
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <activemq/util/CMSExceptionSupport.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <cms/IllegalStateException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageNotReadableException.h>
#include <cms/MessageNotWriteableException.h>
```

Data Structures

- class `activemq::commands::ActiveMQMessageTemplate< T >`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.21 src/main/activemq/commands/ActiveMQObjectMessage.h File Reference

```
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <cms/ObjectMessage.h>
#include <activemq/util/Config.h>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQObjectMessage`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.22 src/main/activemq/commands/ActiveMQQueue.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <decaf/lang/Exception.h>
#include <cms/Queue.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQQueue`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.23 src/main/activemq/commands/ActiveMQStreamMessage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessage.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <cms/StreamMessage.h>
#include <cms/MessageNotWriteableException.h>
#include <cms/MessageNotReadableException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageEOFException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/ByteArrayOutputStream.h>
#include <string>
#include <memory>
```

Data Structures

- class **activemq::commands::ActiveMQStreamMessage**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**

7.24 src/main/activemq/commands/ActiveMQTempDestination.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <cms/Closeable.h>
#include <vector>
#include <string>
```

Data Structures

- class **activemq::commands::ActiveMQTempDestination**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**
- namespace **activemq::commands**

7.25 src/main/activemq/commands/ActiveMQTempQueue.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQTempDestination.h>
#include <cms/TemporaryQueue.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQTempQueue`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.26 src/main/activemq/commands/ActiveMQTempTopic.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQTempDestination.h>
#include <cms/TemporaryTopic.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQTempTopic`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.27 src/main/activemq/commands/ActiveMQTextMessage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQMessageTemplate.h>
#include <cms/TextMessage.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQTextMessage`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.28 src/main/activemq/commands/ActiveMQTopic.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <decaf/lang/Exception.h>
#include <cms/Topic.h>
#include <vector>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::commands::ActiveMQTopic`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.29 src/main/activemq/commands/BaseCommand.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
```

Data Structures

- class **activemq::commands::BaseCommand**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.30 src/main/activemq/commands/BaseDataStructure.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <string>
#include <sstream>
```

Data Structures

- class **activemq::commands::BaseDataStructure**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::commands**

7.31 src/main/activemq/commands/BooleanExpression.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::commands::BooleanExpression**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**

7.32 src/main/activemq/commands/BrokerError.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/BaseCommand.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::BrokerError**
This class represents an Exception sent from the Broker.
- struct **activemq::commands::BrokerError::StackTraceElement**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.33 src/main/activemq/commands/BrokerId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::BrokerId`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.34 src/main/activemq/commands/BrokerInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/BrokerInfo.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::BrokerInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.35 src/main/activemq/commands/Command.h File Reference

```
#include <string>
#include <activemq/util/Config.h>
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class `activemq::commands::Command`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`
- namespace `activemq::commands`

7.36 src/main/activemq/commands/ConnectionControl.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ConnectionControl`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.37 src/main/activemq/commands/ConnectionError.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerError.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ConnectionError**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.38 src/main/activemq/commands/ConnectionId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ConnectionId`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.39 src/main/activemq/commands/ConnectionInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/commands/RemoveInfo.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ConnectionInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.40 src/main/activemq/commands/ConsumerControl.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ConsumerControl**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.41 src/main/activemq/commands/ConsumerId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/SessionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ConsumerId**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.42 src/main/activemq/commands/ConsumerInfo.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BooleanExpression.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/RemoveInfo.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ConsumerInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.43 src/main/activemq/commands/ControlCommand.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ControlCommand`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.44 src/main/activemq/commands/DataArrayResponse.h File Reference

```
#include <activemq/commands/DataStructure.h>
#include <activemq/commands/Response.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::DataArrayResponse**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.45 src/main/activemq/commands/DataResponse.h File Reference

```
#include <activemq/commands/DataSet.h>
#include <activemq/commands/Response.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::DataResponse`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.46 src/main/activemq/commands/DataStructure.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/wireformat/MarshalAware.h>
```

Data Structures

- class **activemq::commands::DataStructure**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.47 src/main/activemq/commands/DestinationInfo.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::DestinationInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.48 src/main/activemq/commands/DiscoveryEvent.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::DiscoveryEvent`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.49 src/main/activemq/commands/ExceptionResponse.h File Reference

```
#include <activemq/commands/BrokerError.h>
#include <activemq/commands/Response.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ExceptionResponse`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.50 src/main/activemq/commands/FlushCommand.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::FlushCommand**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.51 src/main/activemq/commands/IntegerResponse.h File Reference

```
#include <activemq/commands/Response.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::IntegerResponse`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.52 src/main/activemq/commands/JournalQueueAck.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/MessageAck.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::JournalQueueAck**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.53 src/main/activemq/commands/JournalTopicAck.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/MessageId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::JournalTopicAck`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.54 src/main/activemq/commands/JournalTrace.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::JournalTrace**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.55 src/main/activemq/commands/JournalTransaction.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::JournalTransaction**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.56 src/main/activemq/commands/KeepAliveInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::KeepAliveInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.57 src/main/activemq/commands/LastPartialCommand.h File Reference

```
#include <activemq/commands/PartialCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::LastPartialCommand`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.58 src/main/activemq/commands/LocalTransactionId.h File Reference

```
#include <activemq/commands/ConnectionId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::LocalTransactionId**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.59 src/main/activemq/commands/Message.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/DataSet.h>
#include <activemq/commands/MessageId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/core/ActiveMQAckHandler.h>
#include <activemq/util/Config.h>
#include <activemq/util/PrimitiveMap.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::Message**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**
- namespace **activemq::commands**

7.60 src/main/cms/Message.h File Reference

```
#include <cms/Config.h>
#include <cms/Destination.h>
#include <cms/DeliveryMode.h>
#include <cms/CMSException.h>
#include <cms/IllegalStateException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageNotWriteableException.h>
```

Data Structures

- class **cms::Message**
Root of all messages.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.61 src/main/activemq/commands/MessageAck.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/MessageId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::MessageAck**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**

7.62 src/main/activemq/commands/MessageDispatch.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/Message.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::MessageDispatch`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.63 src/main/activemq/commands/MessageDispatchNotification.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/MessageId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::MessageDispatchNotification`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.64 src/main/activemq/commands/MessageId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/ProducerInfo.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::MessageId`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.65 src/main/activemq/commands/MessagePull.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/MessageId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::MessagePull`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.66 src/main/activemq/commands/NetworkBridgeFilter.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::NetworkBridgeFilter`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.67 src/main/activemq/commands/PartialCommand.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::PartialCommand`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.68 src/main/activemq/commands/ProducerAck.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ProducerAck**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.69 src/main/activemq/commands/ProducerId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/SessionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ProducerId**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.70 src/main/activemq/commands/ProducerInfo.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/BrokerId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/RemoveInfo.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::ProducerInfo**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**

7.71 src/main/activemq/commands/RemoveInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/DataSet.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::RemoveInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.72 src/main/activemq/commands/RemoveSubscriptionInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::RemoveSubscriptionInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.73 src/main/activemq/commands/ReplayCommand.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ReplayCommand`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.74 src/main/activemq/commands/Response.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::Response**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.75 src/main/activemq/commands/SessionId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::SessionId**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.76 src/main/activemq/commands/SessionInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/RemoveInfo.h>
#include <activemq/commands/SessionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::SessionInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.77 src/main/activemq/commands/ShutdownInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::ShutdownInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.78 src/main/activemq/commands/SubscriptionInfo.h File Reference

```
#include <activemq/commands/ActiveMQDestination.h>
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::SubscriptionInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.79 src/main/activemq/commands/TransactionId.h File Reference

```
#include <activemq/commands/BaseDataStructure.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class `activemq::commands::TransactionId`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.80 src/main/activemq/commands/TransactionInfo.h File Reference

```
#include <activemq/commands/BaseCommand.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::TransactionInfo**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.81 src/main/activemq/commands/WireFormatInfo.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/BaseCommand.h>
#include <activemq/util/PrimitiveMap.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <vector>
```

Data Structures

- class `activemq::commands::WireFormatInfo`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::commands`

7.82 src/main/activemq/commands/XATransactionId.h File Reference

```
#include <activemq/commands/TransactionId.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <vector>
```

Data Structures

- class **activemq::commands::XATransactionId**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**

7.83 src/main/activemq/core/ActiveMQAckHandler.h File Reference

```
#include <cms/CMSException.h>  
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::core::ActiveMQAckHandler**
Interface class that is used to give CMS Messages an interface to Ack themselves with.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::commands**
- namespace **activemq::core**

7.84 src/main/activemq/core/ActiveMQConnection.h File Reference

```
#include <cms/Connection.h>
#include <activemq/util/Config.h>
#include <activemq/core/ActiveMQConnectionMetaData.h>
#include <activemq/core/Dispatcher.h>
#include <activemq/commands/ActiveMQTempDestination.h>
#include <activemq/commands/ConnectionInfo.h>
#include <activemq/commands/ConsumerInfo.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/transport/TransportListener.h>
#include <decaf/util/Properties.h>
#include <decaf/util/StlMap.h>
#include <decaf/util/StlSet.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <string>
#include <memory>
```

Data Structures

- class **activemq::core::ActiveMQConnection**
Concrete connection used for all connectors to the ActiveMQ broker.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.85 src/main/activemq/core/ActiveMQConnectionFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <cms/ConnectionFactory.h>
#include <cms/Connection.h>
```

Data Structures

- class **activemq::core::ActiveMQConnectionFactory**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.86 src/main/activemq/core/ActiveMQConnectionMetaData.h File Reference

```
#include <activemq/util/Config.h>
#include <cms/ConnectionMetaData.h>
```

Data Structures

- class **activemq::core::ActiveMQConnectionMetaData**

*This class houses all the various settings and information that is used by an instance of an **ActiveMQConnection** (p. 273) class.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.87 src/main/activemq/core/ActiveMQConstants.h File Reference

```
#include <string>
#include <map>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::core::ActiveMQConstants**
Class holding constant values for various ActiveMQ specific things Each constant is defined as an enumeration and has functions that convert back and forth between string and enum values.
- class **activemq::core::ActiveMQConstants::StaticInitializer**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.88 src/main/activemq/core/ActiveMQConsumer.h File Reference

```
#include <cms/MessageConsumer.h>
#include <cms/MessageListener.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/commands/ConsumerInfo.h>
#include <activemq/commands/MessageAck.h>
#include <activemq/commands/MessageDispatch.h>
#include <activemq/core/Dispatcher.h>
#include <activemq/core/MessageDispatchChannel.h>
#include <activemq/core/RedeliveryPolicy.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/StlQueue.h>
#include <decaf/util/concurrent/Mutex.h>
#include <memory>
```

Data Structures

- class **activemq::core::ActiveMQConsumer**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.89 src/main/activemq/core/ActiveMQProducer.h File Reference

```
#include <cms/MessageProducer.h>
#include <cms/Message.h>
#include <cms/Destination.h>
#include <cms/DeliveryMode.h>
#include <activemq/util/Config.h>
#include <activemq/util/MemoryUsage.h>
#include <activemq/commands/ProducerInfo.h>
#include <activemq/commands/ProducerAck.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <memory>
```

Data Structures

- class **activemq::core::ActiveMQProducer**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.90 src/main/activemq/core/ActiveMQQueueBrowser.h File Reference

```
#include <activemq/util/Config.h>
#include <cms/Queue.h>
#include <cms/QueueBrowser.h>
#include <cms/MessageEnumeration.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/ActiveMQDestination.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <string>
```

Data Structures

- class **activemq::core::ActiveMQQueueBrowser**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.91 src/main/activemq/core/ActiveMQSession.h File Reference

```
#include <cms/Session.h>
#include <cms/ExceptionListener.h>
#include <activemq/util/Config.h>
#include <activemq/util/Usage.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/core/ActiveMQTransactionContext.h>
#include <activemq/commands/ActiveMQTempDestination.h>
#include <activemq/commands/SessionInfo.h>
#include <activemq/commands/ConsumerInfo.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/core/Dispatcher.h>
#include <activemq/core/MessageDispatchChannel.h>
#include <activemq/util/LongSequenceGenerator.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/STLMap.h>
#include <decaf/util/STLQueue.h>
#include <decaf/util/Properties.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::core::ActiveMQSession`

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::core`

7.92 src/main/activemq/core/ActiveMQSessionExecutor.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/core/MessageDispatchChannel.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/MessageDispatch.h>
#include <activemq/threads/Task.h>
#include <activemq/threads/TaskRunner.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::core::ActiveMQSessionExecutor**
Delegate dispatcher for a single session.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.93 src/main/activemq/core/ActiveMQTransactionContext.h File Reference

```
#include <memory>
#include <cms/Message.h>
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/commands/LocalTransactionId.h>
#include <activemq/core/Synchronization.h>
#include <activemq/util/LongSequenceGenerator.h>
#include <decaf/lang/exceptions/InvalidStateException.h>
#include <decaf/util/StlSet.h>
#include <decaf/util/Properties.h>
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **activemq::core::ActiveMQTransactionContext**
Transaction Management class, hold messages that are to be redelivered upon a request to roll-back.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.94 src/main/activemq/core/DispatchData.h File Reference

```
#include <stdlib.h>
#include <memory>
#include <activemq/util/Config.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/Message.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::core::DispatchData**

Simple POCO that contains the information necessary to route a message to a specified consumer.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.95 src/main/activemq/core/Dispatcher.h File Reference

```
#include <activemq/commands/MessageDispatch.h>
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::core::Dispatcher**
Interface for an object responsible for dispatching messages to consumers.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**

7.96 src/main/activemq/core/MessageDispatchChannel.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/MessageDispatch.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/StlQueue.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class `activemq::core::MessageDispatchChannel`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::core`

7.97 src/main/activemq/core/policies/DefaultPrefetchPolicy.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/core/PrefetchPolicy.h>
```

Data Structures

- class **activemq::core::policies::DefaultPrefetchPolicy**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::core**
- namespace **activemq::core::policies**

7.98 src/main/activemq/core/policies/DefaultRedeliveryPolicy.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/core/RedeliveryPolicy.h>
```

Data Structures

- class **activemq::core::policies::DefaultRedeliveryPolicy**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**
- namespace **activemq::core::policies**

7.99 src/main/activemq/core/PrefetchPolicy.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::core::PrefetchPolicy**

Interface for a Policy object that controls message Prefetching on various destination types in ActiveMQ-CPP.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.100 src/main/activemq/core/RedeliveryPolicy.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::core::RedeliveryPolicy**

*Interface for a **RedeliveryPolicy** (p. 3177) object that controls how message Redelivery is handled in ActiveMQ-CPP when a transaction is rolled back.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.101 src/main/activemq/core/Synchronization.h File Reference

```
#include <activemq/util/Config.h>
```

```
#include <activemq/exceptions/ActiveMQException.h>
```

Data Structures

- class **activemq::core::Synchronization**

*Transacted Object **Synchronization** (p. 3715), used to sync the events of a Transaction with the items in the Transaction.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::core**

7.102 src/main/activemq/exceptions/ActiveMQException.h File Reference

```
#include <activemq/util/Config.h>
#include <cms/CMSException.h>
#include <decaf/lang/Exception.h>
#include <activemq/exceptions/ExceptionDefines.h>
#include <stdarg.h>
#include <sstream>
```

Data Structures

- class `activemq::exceptions::ActiveMQException`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::exceptions`

7.103 src/main/activemq/exceptions/BrokerException.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/commands/BrokerError.h>
#include <sstream>
```

Data Structures

- class `activemq::exceptions::BrokerException`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::exceptions`

7.104 src/main/activemq/exceptions/ExceptionDefines.h File Reference

Defines

- `#define AMQ_CATCH_RETHROW(type)`
Macro for catching and re-throwing an exception of a given type.
- `#define AMQ_CATCH_EXCEPTION_CONVERT(sourceType, targetType)`
Macro for catching an exception of one type and then re-throwing as another type.
- `#define AMQ_CATCHALL_THROW(type)`
A catch-all that throws a known exception.
- `#define AMQ_CATCHALL_NOTHROW()`
A catch-all that does not throw an exception, one use would be to catch any exception in a destructor and mark it, but not throw so that cleanup would continue as normal.
- `#define AMQ_CATCH_NOTHROW(type)`
Macro for catching and re-throwing an exception of a given type.

7.104.1 Define Documentation

7.104.1.1 `#define AMQ_CATCH_EXCEPTION_CONVERT(sourceType, targetType)`

Value:

```
catch( sourceType& ex ){ \
    targetType target( ex ); \
    target.setMark( __FILE__, __LINE__ ); \
    throw target; \
}
```

Macro for catching an exception of one type and then re-throwing as another type.

Parameters:

sourceType the type of the exception to be caught.

targetType the type of the exception to be thrown.

Referenced by `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalObjectArray()`, `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray1()`, and `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray2()`.

7.104.1.2 `#define AMQ_CATCH_NOTHROW(type)`

Value:

```
catch( type& ex ){ \
    ex.setMark( __FILE__, __LINE__ ); \
}
```

Macro for catching and re-throwing an exception of a given type.

Parameters:

type The type of the exception to throw (e.g. ActiveMQException).

7.104.1.3 #define AMQ_CATCH_RETHROW(type)

Value:

```
catch( type& ex ){ \
    ex.setMark( __FILE__, __LINE__ ); \
    throw ex; \
}
```

Macro for catching and re-throwing an exception of a given type.

Parameters:

type The type of the exception to throw (e.g. ActiveMQException).

Referenced by `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalObjectArray()`, `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray1()`, and `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray2()`.

7.104.1.4 #define AMQ_CATCHALL_NOTHROW()

Value:

```
catch( ... ){ \
    activemq::exceptions::ActiveMQException ex( __FILE__, __LINE__, \
    "caught unknown exception, not rethrowing" ); \
}
```

A catch-all that does not throw an exception, one use would be to catch any exception in a destructor and mark it, but not throw so that cleanup would continue as normal.

7.104.1.5 #define AMQ_CATCHALL_THROW(type)

Value:

```
catch( ... ){ \
    type ex( __FILE__, __LINE__, \
    "caught unknown exception" ); \
    throw ex; \
}
```

A catch-all that throws a known exception.

Parameters:

type the type of exception to be thrown.

Referenced by `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::looseMarshalObjectArray()`,
`activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray1()`,
and `activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller::tightMarshalObjectArray2()`.

7.105 src/main/decaf/lang/exceptions/ExceptionDefines.h File Reference

Defines

- `#define DECAF_CATCH_RETHROW(type)`
Macro for catching and rethrowing an exception of a given type.
- `#define DECAF_CATCH_EXCEPTION_CONVERT(sourceType, targetType)`
Macro for catching an exception of one type and then rethrowing as another type.
- `#define DECAF_CATCHALL_THROW(type)`
A catch-all that throws a known exception.
- `#define DECAF_CATCHALL_NOTHROW()`
A catch-all that does not throw an exception, one use would be to catch any exception in a destructor and mark it, but not throw so that cleanup would continue as normal.
- `#define DECAF_CATCH_NOTHROW(type)`
Macro for catching and rethrowing an exception of a given type.

7.105.1 Define Documentation

7.105.1.1 `#define DECAF_CATCH_EXCEPTION_CONVERT(sourceType, targetType)`

Value:

```
catch( sourceType& ex ){ \
    targetType target( &ex ); \
    target.setMark( __FILE__, __LINE__ ); \
    throw target; \
}
```

Macro for catching an exception of one type and then rethrowing as another type.

Parameters:

sourceType the type of the exception to be caught.
targetType the type of the exception to be thrown.

Referenced by `decaf::util::PriorityQueue< E >::add()`.

7.105.1.2 `#define DECAF_CATCH_NOTHROW(type)`

Value:

```
catch( type& ex ){ \
    ex.setMark( __FILE__, __LINE__ ); \
}
```

Macro for catching and rethrowing an exception of a given type.

Parameters:

type The type of the exception to throw (e.g. Exception).

7.105.1.3 #define DECAF_CATCH_RETHROW(type)**Value:**

```
catch( type& ex ){ \
    ex.setMark( __FILE__, __LINE__ ); \
    throw ex; \
}
```

Macro for catching and rethrowing an exception of a given type.

Parameters:

type The type of the exception to throw (e.g. Exception).

Referenced by `decaf::util::PriorityQueue< E >::add()`.

7.105.1.4 #define DECAF_CATCHALL_NOTHROW()**Value:**

```
catch( ... ){ \
    lang::Exception ex( __FILE__, __LINE__, \
        "caught unknown exception, not rethrowing" ); \
}
```

A catch-all that does not throw an exception, one use would be to catch any exception in a destructor and mark it, but not throw so that cleanup would continue as normal.

7.105.1.5 #define DECAF_CATCHALL_THROW(type)**Value:**

```
catch( ... ){ \
    type ex( __FILE__, __LINE__, \
        "caught unknown exception" ); \
    throw ex; \
}
```

A catch-all that throws a known exception.

Parameters:

type the type of exception to be thrown.

Referenced by `decaf::util::PriorityQueue< E >::add()`.

7.106 src/main/activemq/io/LoggingInputStream.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/io/FilterInputStream.h>
#include <decaf/util/logging/LoggerDefines.h>
#include <decaf/lang/exceptions/NullPointerException.h>
```

Data Structures

- class **activemq::io::LoggingInputStream**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::io**

7.107 src/main/activemq/io/LoggingOutputStream.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/io/FilterOutputStream.h>
#include <decaf/util/logging/LoggerDefines.h>
```

Data Structures

- class **activemq::io::LoggingOutputStream**
OutputStream filter that just logs the data being written.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::io**

7.108 src/main/activemq/library/ActiveMQCPP.h File Reference

```
#include <activemq/util/Config.h>
```

Data Structures

- class `activemq::library::ActiveMQCPP`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::library`

7.109 src/main/activemq/state/CommandVisitor.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::state::CommandVisitor**

Interface for an Object that can visit the various Command Objects that are sent from and to this client.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::commands**
- namespace **activemq::state**

7.110 src/main/activemq/state/CommandVisitorAdapter.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/state/CommandVisitor.h>
#include <activemq/core/ActiveMQConstants.h>
#include <activemq/commands/ConnectionInfo.h>
#include <activemq/commands/SessionInfo.h>
#include <activemq/commands/ProducerInfo.h>
#include <activemq/commands/ConsumerInfo.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/commands/SessionId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/DestinationInfo.h>
#include <activemq/commands/RemoveSubscriptionInfo.h>
#include <activemq/commands/Message.h>
#include <activemq/commands/MessageAck.h>
#include <activemq/commands/MessagePull.h>
#include <activemq/commands/TransactionInfo.h>
#include <activemq/commands/WireFormatInfo.h>
#include <activemq/commands/ProducerAck.h>
#include <activemq/commands/MessageDispatch.h>
#include <activemq/commands/MessageDispatchNotification.h>
#include <activemq/commands/ControlCommand.h>
#include <activemq/commands/ConnectionError.h>
#include <activemq/commands/ConnectionControl.h>
#include <activemq/commands/ConsumerControl.h>
#include <activemq/commands/ShutdownInfo.h>
#include <activemq/commands/KeepAliveInfo.h>
#include <activemq/commands/FlushCommand.h>
#include <activemq/commands/BrokerError.h>
#include <activemq/commands/BrokerInfo.h>
#include <activemq/commands/RemoveInfo.h>
#include <activemq/commands/ReplayCommand.h>
#include <activemq/commands/Response.h>
```

Data Structures

- class `activemq::state::CommandVisitorAdapter`

*Default Implementation of a **CommandVisitor** (p. 1200) that returns NULL for all calls.*

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::state`

7.111 src/main/activemq/state/ConnectionState.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ConnectionInfo.h>
#include <activemq/commands/DestinationInfo.h>
#include <activemq/commands/SessionInfo.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/commands/LocalTransactionId.h>
#include <activemq/state/ConsumerState.h>
#include <activemq/state/ProducerState.h>
#include <activemq/state/SessionState.h>
#include <activemq/state/TransactionState.h>
#include <decaf/util/StlMap.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/util/concurrent/ConcurrentStlMap.h>
#include <decaf/util/StlList.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::state::ConnectionState`

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::state`

7.112 src/main/activemq/state/ConnectionStateTracker.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/state/CommandVisitorAdapter.h>
#include <activemq/state/ConnectionState.h>
#include <activemq/state/ConsumerState.h>
#include <activemq/state/ProducerState.h>
#include <activemq/state/SessionState.h>
#include <activemq/state/TransactionState.h>
#include <activemq/state/Tracked.h>
#include <activemq/transport/Transport.h>
#include <decaf/util/concurrent/ConcurrentStlMap.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class `activemq::state::ConnectionStateTracker`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`

7.113 src/main/activemq/state/ConsumerState.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ConsumerInfo.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::state::ConsumerState`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`

7.114 src/main/activemq/state/ProducerState.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/ProducerInfo.h>
#include <decaf/lang/Pointer.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::state::ProducerState`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`

7.115 src/main/activemq/state/SessionState.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/SessionInfo.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/state/ConsumerState.h>
#include <activemq/state/ProducerState.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/util/concurrent/ConcurrentStlMap.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::state::SessionState`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`

7.116 src/main/activemq/state/Tracked.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Response.h>
#include <decaf/lang/Runnable.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::state::Tracked**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::state**

7.117 src/main/activemq/state/TransactionState.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/TransactionId.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/StlList.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/util/concurrent/ConcurrentStlMap.h>
#include <string>
#include <memory>
```

Data Structures

- class `activemq::state::TransactionState`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::state`

7.118 src/main/activemq/threads/CompositeTask.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/threads/Task.h>
```

Data Structures

- class **activemq::threads::CompositeTask**
Represents a single task that can be part of a set of Tasks that are contained in a CompositeTaskRunner (p. 1223).

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::threads**

7.119 src/main/activemq/threads/CompositeTaskRunner.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/threads/TaskRunner.h>
#include <activemq/threads/CompositeTask.h>
#include <decaf/util/StlSet.h>
#include <decaf/util/StlList.h>
#include <decaf/lang/Thread.h>
#include <decaf/lang/Runnable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::threads::CompositeTaskRunner**

A *Task* (p. 3734) Runner that can contain one or more *CompositeTasks* that are each checked for pending work and run if any is present in the order that the tasks were added.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::threads**

7.120 src/main/activemq/threads/DedicatedTaskRunner.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/threads/TaskRunner.h>
#include <activemq/threads/Task.h>
#include <decaf/lang/Thread.h>
#include <decaf/lang/Runnable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::threads::DedicatedTaskRunner**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::threads**

7.121 src/main/activemq/threads/Task.h File Reference

```
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::threads::Task**

Represents a unit of work that requires one or more iterations to complete.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::threads**

7.122 src/main/activemq/threads/TaskRunner.h File Reference

```
#include <activemq/util/Config.h>  
#include <activemq/threads/Task.h>
```

Data Structures

- class **activemq::threads::TaskRunner**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::threads**

7.123 src/main/activemq/transport/AbstractTransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/Transport.h>
#include <activemq/transport/TransportFactory.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::transport::AbstractTransportFactory**
*Abstract implementation of the **TransportFactory** (p. 3889) interface, providing the base functionality that's common to most of the **TransportFactory** (p. 3889) instances.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**

7.124 src/main/activemq/transport/CompositeTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/Transport.h>
#include <decaf/net/URI.h>
#include <decaf/util/List.h>
```

Data Structures

- class **activemq::transport::CompositeTransport**

*A Composite **Transport** (p. 3883) is a **Transport** (p. 3883) implementation that is composed of several **Transports**.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**

7.125 src/main/activemq/transport/correlator/FutureResponse.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/CountDownLatch.h>
#include <activemq/commands/Response.h>
#include <activemq/exceptions/ActiveMQException.h>
```

Data Structures

- class **activemq::transport::correlator::FutureResponse**
A container that holds a response object.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::correlator**

7.126 src/main/activemq/transport/correlator/ResponseCorrelator.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <activemq/transport/correlator/FutureResponse.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/Response.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/util/concurrent/atomic/AtomicInteger.h>
#include <map>
#include <stdio.h>
```

Data Structures

- class **activemq::transport::correlator::ResponseCorrelator**

*This type of **transport** (p. 97) filter is responsible for correlating asynchronous responses with requests.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**
- namespace **activemq::transport::correlator**

7.127 src/main/activemq/transport/DefaultTransportListener.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportListener.h>
#include <activemq/commands/Command.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::transport::DefaultTransportListener**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**

7.128 src/main/activemq/transport/failover/BackupTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/Transport.h>
#include <activemq/transport/DefaultTransportListener.h>
#include <decaf/net/URI.h>
#include <decaf/lang/Pointer.h>
#include <memory>
```

Data Structures

- class `activemq::transport::failover::BackupTransport`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::transport`
- namespace `activemq::transport::failover`

7.129 src/main/activemq/transport/failover/BackupTransportPool.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/threads/CompositeTask.h>
#include <activemq/threads/CompositeTaskRunner.h>
#include <activemq/transport/failover/CloseTransportsTask.h>
#include <activemq/transport/failover/BackupTransport.h>
#include <activemq/transport/failover/URIPool.h>
#include <decaf/lang/Pointer.h>
#include <decaf/io/IOException.h>
#include <decaf/util/StlList.h>
```

Data Structures

- class `activemq::transport::failover::BackupTransportPool`

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::transport`
- namespace `activemq::transport::failover`

7.130 src/main/activemq/transport/failover/CloseTransportsTask.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/threads/CompositeTask.h>
#include <activemq/transport/Transport.h>
#include <decaf/util/StlQueue.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class `activemq::transport::failover::CloseTransportsTask`

Namespaces

- namespace `activemq`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `activemq::transport`
- namespace `activemq::transport::failover`

7.131 src/main/activemq/transport/failover/FailoverTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/ConnectionId.h>
#include <activemq/threads/TaskRunner.h>
#include <activemq/threads/CompositeTaskRunner.h>
#include <activemq/state/ConnectionStateTracker.h>
#include <activemq/transport/CompositeTransport.h>
#include <activemq/transport/failover/BackupTransportPool.h>
#include <activemq/transport/failover/CloseTransportsTask.h>
#include <activemq/transport/failover/FailoverTransportListener.h>
#include <activemq/transport/failover/URIPool.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/util/StlList.h>
#include <decaf/util/StlMap.h>
#include <decaf/util/Properties.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/atomic/AtomicReference.h>
#include <decaf/net/URI.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class `activemq::transport::failover::FailoverTransport`

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::transport`
- namespace `activemq::transport::failover`

7.132 src/main/activemq/transport/failover/FailoverTransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/AbstractTransportFactory.h>
#include <activemq/transport/Transport.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/net/URI.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::transport::failover::FailoverTransportFactory**
*Creates an instance of a **FailoverTransport** (p. 1873).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::failover**

7.133 src/main/activemq/transport/failover/FailoverTransportListener. File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportListener.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::transport::failover::FailoverTransportListener**
*Utility class used by the **Transport** (p. 3883) to perform the work of responding to events from the active **Transport** (p. 3883).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::failover**

7.134 src/main/activemq/transport/failover/URIPool.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/net/URI.h>
#include <decaf/util/StlList.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
```

Data Structures

- class **activemq::transport::failover::URIPool**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::failover**

7.135 src/main/activemq/transport/inactivity/InactivityMonitor.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/Response.h>
#include <activemq/commands/WireFormatInfo.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/Timer.h>
#include <decaf/util/Properties.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
```

Data Structures

- class **activemq::transport::inactivity::InactivityMonitor**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::inactivity**

7.136 src/main/activemq/transport/inactivity/ReadChecker.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/util/TimerTask.h>
```

Data Structures

- class **activemq::transport::inactivity::ReadChecker**
Runnable class that is used by the {}.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::inactivity**

7.137 src/main/activemq/transport/inactivity/WriteChecker.h File Reference

```
#include <activemq/util/Config.h>
```

```
#include <decaf/util/TimerTask.h>
```

Data Structures

- class **activemq::transport::inactivity::WriteChecker**

Runnable class used by the {}.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**
- namespace **activemq::transport::inactivity**

7.138 src/main/activemq/transport/IOTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/Transport.h>
#include <activemq/transport/TransportListener.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/Response.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/lang/Runnable.h>
#include <decaf/lang/Thread.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/util/logging/LoggerDefines.h>
#include <memory>
```

Data Structures

- class **activemq::transport::IOTransport**
*Implementation of the **Transport** (p. 3883) interface that performs marshaling of **commands** (p. 87) to IO streams.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**

7.139 src/main/activemq/transport/logging/LoggingTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::transport::logging::LoggingTransport**
*A **transport** (p. 97) filter that logs **commands** (p. 87) as they are sent/received.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::logging**

7.140 src/main/activemq/transport/mock/InternalCommandListener.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/mock/ResponseBuilder.h>
#include <activemq/transport/DefaultTransportListener.h>
#include <decaf/lang/Thread.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/StlQueue.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/util/concurrent/atomic/AtomicInteger.h>
#include <decaf/util/concurrent/CountDownLatch.h>
```

Data Structures

- class **activemq::transport::mock::InternalCommandListener**
*Listens for Commands sent from the **MockTransport** (p. 2768).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::mock**

7.141 src/main/activemq/transport/mock/MockTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/transport/Transport.h>
#include <activemq/transport/TransportListener.h>
#include <activemq/transport/DefaultTransportListener.h>
#include <activemq/transport/mock/ResponseBuilder.h>
#include <activemq/transport/mock/InternalCommandListener.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/lang/Thread.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/StlQueue.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/util/concurrent/atomic/AtomicInteger.h>
#include <decaf/util/concurrent/CountDownLatch.h>
#include <cms/Message.h>
#include <map>
#include <set>
```

Data Structures

- class **activemq::transport::mock::MockTransport**

*The **MockTransport** (p. 2768) defines a base level **Transport** (p. 3883) class that is intended to be used in place of an a regular protocol **Transport** (p. 3883) such as TCP.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**
- namespace **activemq::transport::mock**

7.142 src/main/activemq/transport/mock/MockTransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/AbstractTransportFactory.h>
```

Data Structures

- class **activemq::transport::mock::MockTransportFactory**
Manufactures MockTransports, which are objects that read from input streams and write to output streams.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::mock**

7.143 src/main/activemq/transport/mock/ResponseBuilder.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/Response.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/StlQueue.h>
```

Data Structures

- class **activemq::transport::mock::ResponseBuilder**
Interface for all Protocols to implement that defines the behavior of the Broker in response to messages of that protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::mock**

7.144 src/main/activemq/transport/tcp/SslTransport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/tcp/TcpTransport.h>
```

Data Structures

- class **activemq::transport::tcp::SslTransport**
Transport (p. 3883) for connecting to a Broker using an SSL Socket.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::tcp**

7.145 src/main/activemq/transport/tcp/SslTransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/tcp/TcpTransportFactory.h>
```

Data Structures

- class **activemq::transport::tcp::SslTransportFactory**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::tcp**

7.146 src/main/activemq/transport/tcp/TcpTransport.h File Reference

```
#include <activemq/io/LoggingInputStream.h>
#include <activemq/io/LoggingOutputStream.h>
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <decaf/net/Socket.h>
#include <decaf/net/URI.h>
#include <decaf/util/Properties.h>
#include <decaf/lang/Pointer.h>
#include <decaf/io/BufferedInputStream.h>
#include <decaf/io/BufferedOutputStream.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <memory>
```

Data Structures

- class **activemq::transport::tcp::TcpTransport**

*Implements a TCP/IP based **transport** (p. 97) filter, this **transport** (p. 97) is meant to wrap an instance of an **IOTransport** (p. 2145).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**
- namespace **activemq::transport::tcp**

7.147 src/main/activemq/transport/tcp/TcpTransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/AbstractTransportFactory.h>
#include <activemq/exceptions/ActiveMQException.h>
```

Data Structures

- class **activemq::transport::tcp::TcpTransportFactory**
*Factory Responsible for creating the **TcpTransport** (p. 3752).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**
- namespace **activemq::transport::tcp**

7.148 src/main/activemq/transport/Transport.h File Reference

```
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/io/Closeable.h>
#include <decaf/net/URI.h>
#include <decaf/lang/Pointer.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <activemq/commands/Response.h>
#include <typeinfo>
```

Data Structures

- class **activemq::transport::Transport**
*Interface for a **transport** (p. 97) layer for command objects.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::transport**

7.149 src/main/activemq/transport/TransportFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/transport/Transport.h>
#include <decaf/net/URI.h>
#include <decaf/util/Properties.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::transport::TransportFactory**
Defines the interface for Factories that create Transports or TransportFilters.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**

7.150 src/main/activemq/transport/TransportFilter.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <activemq/transport/Transport.h>
#include <activemq/commands/Command.h>
#include <activemq/transport/TransportListener.h>
#include <decaf/lang/Pointer.h>
#include <typeinfo>
```

Data Structures

- class **activemq::transport::TransportFilter**

*A filter on the **transport** (p. 97) layer.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**

7.151 src/main/activemq/transport/TransportListener.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <decaf/lang/Exception.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::transport::TransportListener**

*A listener of asynchronous **exceptions** (p. 92) from a command **transport** (p. 97) object.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::transport**

7.152 src/main/activemq/transport/TransportRegistry.h File Reference

```
#include <activemq/util/Config.h>
#include <string>
#include <vector>
#include <activemq/transport/TransportFactory.h>
#include <decaf/util/StlMap.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **activemq::transport::TransportRegistry**
*Registry of all **Transport** (p. 3883) Factories that are available to the client at runtime.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::transport**

7.153 src/main/activemq/util/ActiveMQProperties.h File Reference

```
#include <map>
#include <string>
#include <sstream>
#include <activemq/util/Config.h>
#include <cms/CMSProperties.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::util::ActiveMQProperties**

*Implementation of the CMSProperties interface that delegates to a **decaf::util::Properties** (p. 3126) object.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::util**

7.154 src/main/activemq/util/CMSExceptionSupport.h File Reference

```
#include <activemq/util/Config.h>
#include <cms/CMSException.h>
#include <cms/CMSSecurityException.h>
#include <cms/MessageEOFException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageNotReadableException.h>
#include <cms/MessageNotWriteableException.h>
#include <cms/InvalidClientIdException.h>
#include <cms/InvalidDestinationException.h>
#include <cms/InvalidSelectorException.h>
#include <cms/IllegalStateException.h>
#include <cms/UnsupportedOperationException.h>
#include <decaf/lang/Exception.h>
#include <string>
```

Data Structures

- class **activemq::util::CMSExceptionSupport**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

Defines

- **#define AMQ_CATCH_ALL_THROW_CMSEXCEPTION()**
Macro for catching an exception of one type and then re-throwing as a Basic CMSException, good for cases where the method isn't specific about what CMS Exceptions are thrown, bad if you need to throw an exception of MessageNotReadableException for instance.

7.154.1 Define Documentation

7.154.1.1 #define AMQ_CATCH_ALL_THROW_CMSEXCEPTION()

Macro for catching an exception of one type and then re-throwing as a Basic CMSException, good for cases where the method isn't specific about what CMS Exceptions are thrown, bad if you need

to throw an exception of MessageNotReadableException for instance.

```

Referenced by    activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage
>::acknowledge(), activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage
>::clearBody(),   activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage
>::clearProperties(), activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage
>::equals(),      activemq::commands::ActiveMQMessageTemplate< cms::ObjectMessage
>::getBooleanProperty(),      activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getByteProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getCMSMessageID(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getDoubleProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getFloatProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getIntProperty(),   activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getLongProperty(),  activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getPropertyNames(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getShortProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::getStringProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::propertyExists(),   activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setBooleanProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setByteProperty(),  activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setCMSDestination(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setCMSReplyTo(),    activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setDoubleProperty(), activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setFloatProperty(),  activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setIntProperty(),    activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setLongProperty(),   activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setShortProperty(),  and activemq::commands::ActiveMQMessageTemplate<
cms::ObjectMessage >::setStringProperty().

```

7.155 src/main/activemq/util/CompositeData.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/util/Properties.h>
#include <decaf/util/StlList.h>
#include <decaf/net/URI.h>
#include <decaf/net/URISyntaxException.h>
```

Data Structures

- class **activemq::util::CompositeData**
Represents a Composite URI.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.156 src/main/activemq/util/Config.h File Reference

Defines

- `#define AMQCPP_API`

7.156.1 Define Documentation

7.156.1.1 `#define AMQCPP_API`

7.157 src/main/cms/Config.h File Reference

Defines

- `#define CMS_API`

7.157.1 Define Documentation

7.157.1.1 `#define CMS_API`

7.158 src/main/decaf/util/Config.h File Reference

Defines

- `#define DECAF_API`
- `#define DECAF_UNUSED`

7.158.1 Define Documentation

7.158.1.1 `#define DECAF_API`

7.158.1.2 `#define DECAF_UNUSED`

7.159 src/main/activemq/util/IdGenerator.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/util/concurrent/Mutex.h>
#include <string>
```

Data Structures

- class **activemq::util::IdGenerator**
- class **activemq::util::IdGenerator::StaticData**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.160 src/main/activemq/util/LongSequenceGenerator.h File Reference

```
#include <activemq/util/Config.h>  
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **activemq::util::LongSequenceGenerator**

This class is used to generate a sequence of long long values that are incremented each time a new value is requested.

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::util**

7.161 src/main/activemq/util/MarshallingSupport.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/io/IOException.h>
#include <decaf/io/UTFDataFormatException.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/DataInputStream.h>
#include <string>
```

Data Structures

- class **activemq::util::MarshallingSupport**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.162 src/main/activemq/util/MemoryUsage.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/util/Usage.h>
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **activemq::util::MemoryUsage**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::util**

7.163 src/main/activemq/util/PrimitiveList.h File Reference

```
#include <string>
#include <vector>
#include <decaf/util/StlList.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <stdio.h>
#include <activemq/util/PrimitiveValueNode.h>
#include <activemq/util/PrimitiveValueConverter.h>
```

Data Structures

- class **activemq::util::PrimitiveList**
List of primitives.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.164 src/main/activemq/util/PrimitiveMap.h File Reference

```
#include <string>
#include <vector>
#include <activemq/util/Config.h>
#include <decaf/util/Config.h>
#include <decaf/util/StlMap.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <activemq/util/PrimitiveValueNode.h>
#include <activemq/util/PrimitiveValueConverter.h>
```

Data Structures

- class **activemq::util::PrimitiveMap**
Map of named primitives.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.165 src/main/activemq/util/PrimitiveValueConverter.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/util/PrimitiveValueNode.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <string>
```

Data Structures

- class **activemq::util::PrimitiveValueConverter**

*Class controls the conversion of data contained in a **PrimitiveValueNode** (p. 3012) from one type to another.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::util**

7.166 src/main/activemq/util/PrimitiveValueNode.h File Reference

```
#include <activemq/util/Config.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/Map.h>
#include <decaf/util/List.h>
```

Data Structures

- class **activemq::util::PrimitiveValueNode**
Class that wraps around a single value of one of the many types.
- union **activemq::util::PrimitiveValueNode::PrimitiveValue**
Define a union type comprised of the various types.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.167 src/main/activemq/util/URISupport.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/util/CompositeData.h>
#include <decaf/util/Properties.h>
#include <decaf/util/StlList.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **activemq::util::URISupport**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::util**

7.168 src/main/activemq/util/Usage.h File Reference

```
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::util::Usage**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::util**

7.169 src/main/activemq/wireformat/MarshalAware.h File Reference

```
#include <vector>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::wireformat::MarshalAware**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**

7.170

src/main/activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h

File Reference

7.170 src/main/activemq/wireformat/openwire/marshal/BaseDataStrea⁴²⁴⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/DataStreamMarshaller.h>
```

```
#include <activemq/wireformat/openwire/utils/HexTable.h>
```

```
#include <activemq/commands/MessageId.h>
```

```
#include <activemq/commands/ProducerId.h>
```

```
#include <activemq/commands/TransactionId.h>
```

```
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller**

*Base class for all Marshallers that **marshal** (p. 107) DataStructures to and from the wire using the OpenWire protocol.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**

7.171 src/main/activemq/wireformat/openwire/marshal/DataStreamM File Reference

```
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq:wireformat::openwire::marshal::DataStreamMarshaller**

*Base class for all classes that **marshal** (p. 107) **commands** (p. 87) for Openwire.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq:wireformat**
- namespace **activemq:wireformat::openwire**
- namespace **activemq:wireformat::openwire::marshal**

7.172

src/main/activemq/wireformat/openwire/marshal/PrimitiveTypesMarshaller.h File

Reference

7.172 src/main/activemq/wireformat/openwire/marshal/PrimitiveTypesMarshaller.h File Reference

```
#include <cms/CMSException.h>
#include <activemq/util/Config.h>
#include <activemq/util/PrimitiveValueNode.h>
#include <activemq/util/PrimitiveMap.h>
#include <activemq/util/PrimitiveList.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/IOException.h>
#include <string>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller**

*This class wraps the functionality needed to **marshal** (p. 107) a primitive map to the Openwire Format's expectation of what the map looks like on the wire.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**

7.173 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBlobMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 213).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.174 src/main/activemq/wireformat/openwire/mar-
shal/v2/ActiveMQBlobMessageMarshaller.h File

Reference

~~7.174~~ src/main/activemq/wireformat/openwire/marsh⁴²⁴⁹/v2/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 221).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.175 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBlobMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 209).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.176 src/main/activemq/wireformat/openwire/mar-
shal/v4/ActiveMQBlobMessageMarshaller.h File

Reference

7.176 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁵¹~~al/v4/ActiveMQ~~
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *ActiveMQBlobMessageMarshaller*
(p. 217).

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.177 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBlobMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 225).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.178 src/main/activemq/wireformat/openwire/mar-
shal/v6/ActiveMQBlobMessageMarshaller.h File

Reference

~~7.178~~ ⁴²⁵³ src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBlobMessageMarshaller** (p. 229).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.179 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBytesMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 253).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.180 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQBytesMessageMarshaller.h File

Reference

7.180 ⁴²⁵⁵src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *ActiveMQBytesMessageMarshaller* (p. 269).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.181 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQBytesMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 249).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.182 src/main/activemq/wireformat/openwire/mar-
shal/v4/ActiveMQBytesMessageMarshaller.h File

Reference

7.182 ⁴²⁵⁷src/main/activemq/wireformat/openwire/marsh/v4/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshall/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *ActiveMQBytesMessageMarshaller*
(p. 257).

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.183 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQBytesMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQBytesMessageMarshaller** (p. 261).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.184 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQBytesMessageMarshaller.h File

Reference

7.184 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁵⁹/v6/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *ActiveMQBytesMessageMarshaller* (p. 265).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.185 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 337).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.186 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQDestinationMarshaller.h File

Reference

7.186 ⁴²⁶¹src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 349).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.187 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 333).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.188 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQDestinationMarshaller.h File

Reference

7.188 src/main/activemq/wireformat/openwire/marsh⁴²⁶³
shal/v4/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marsh/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 341).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.189 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 345).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.190 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQDestinationMarshaller.h File

Reference

~~7.190~~ src/main/activemq/wireformat/openwire/marsh⁴²⁶⁵/v6/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshall/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQDestinationMarshaller** (p. 353).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.191 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMapMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 378).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.192 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQMapMessageMarshaller.h File

Reference

~~7.192~~ src/main/activemq/wireformat/openwire/marsh⁴²⁶⁷/v2/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 390).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.193 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMapMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 374).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.194 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQMapMessageMarshaller.h File

Reference

~~7.194~~ src/main/activemq/wireformat/openwire/marsh⁴²⁶⁹al/v4/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 382).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.195 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMapMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQMapMessageMarshaller** (p. 386).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.196 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQMapMessageMarshaller.h File

Reference

7.196 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁷¹/v6/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *ActiveMQMapMessageMarshaller* (p. 394).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.197 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 405).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.198 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQMessageMarshaller.h File

Reference

7.198 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁷³/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 417).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.199 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 401).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.200 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQMessageMarshaller.h File

Reference

~~7.200~~ src/main/activemq/wireformat/openwire/marsh⁴²⁷⁵al/v4/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 409).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.201 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 413).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.202 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQMessageMarshaller.h File

Reference

7.202 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁷⁷/v6/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQMessageMarshaller (p. 421).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.203 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQObjectMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 450).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.204 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQObjectMessageMarshaller.h File

Reference

~~7.204~~ src/main/activemq/wireformat/openwire/marsh⁴²⁷⁹al/v2/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 462).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.205 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQObjectMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 446).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.206 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQObjectMessageMarshaller.h File

Reference

~~7.206~~ src/main/activemq/wireformat/openwire/marsh⁴²⁸¹al/v4/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshall/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 454).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.207 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQObjectMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 458).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.208 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQObjectMessageMarshaller.h File

Reference

7.208 ⁴²⁸³src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQObjectMessageMarshaller** (p. 466).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.209 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 495).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.210

src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQQueueMarshaller.h

File Reference

7.210 src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQQueueMarshaller.h⁴²⁸⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 507).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.211 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 491).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.212

src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h

File Reference

7.212 src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQQueueMarshaller.h⁴²⁸⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 499).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.213 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 503).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.214

src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQQueueMarshaller.h

File Reference

7.214 src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQQueueMarshaller.h⁴²⁸⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQQueueMarshaller** (p. 511).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.215 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQStreamMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 556).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.216 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQStreamMessageMarshaller.h File

Reference

7.216 ~~src/main/activemq/wireformat/openwire/marsh~~⁴²⁹¹/v2/ActiveMQS

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 568).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.217 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQStreamMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 552).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.218 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQStreamMessageMarshaller.h File

Reference

7.218 ⁴²⁹³src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQS

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 560).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.219 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQStreamMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 564).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.220 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQStreamMessageMarshaller.h File

Reference

~~7.220~~ src/main/activemq/wireformat/openwire/marsh⁴²⁹⁵/v6/ActiveMQS
File Reference

```
#include <activemq/wireformat/openwire/marshall/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQStreamMessageMarshaller** (p. 572).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.221 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 584).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.222 src/main/activemq/wireformat/openwire/marsh-
shal/v2/ActiveMQTempDestinationMarshaller.h File

Reference

7.222 ⁴²⁹⁷src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 596).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.223 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 580).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.224 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQTempDestinationMarshaller.h File

Reference

7.224 ⁴²⁹⁹src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h File

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 588).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.225 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class `activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller`

Marshaling `code` (p. 1183) for Open Wire Format for `ActiveMQTempDestinationMarshaller` (p. 592).

Namespaces

- namespace `activemq`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `activemq::wireformat`
- namespace `activemq::wireformat::openwire`
- namespace `activemq::wireformat::openwire::marshal`
- namespace `activemq::wireformat::openwire::marshal::v5`

7.226 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQTempDestinationMarshaller.h File

Reference

7.226 ⁴³⁰¹src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempDestinationMarshaller** (p. 600).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.227 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 613).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.228 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQTempQueueMarshaller.h File

Reference

7.228 ⁴³⁰³src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTempQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 625).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.229 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 609).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.230 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQTempQueueMarshaller.h File

Reference

7.230 ⁴³⁰⁵src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 617).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.231 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempQueueMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 621).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.232 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQTempQueueMarshaller.h File

Reference

7.232 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³⁰⁷/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTempQueueMarshaller** (p. 629).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.233 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 646).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.234 src/main/activemq/wireformat/openwire/mar-
shal/v2/ActiveMQTempTopicMarshaller.h File

Reference

~~7.234~~ src/main/activemq/wireformat/openwire/marsh⁴³⁰⁹al/v2/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshall/v2/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 654).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.235 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTempTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 638).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.236 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQTempTopicMarshaller.h File

Reference

7.236 ⁴³¹¹src/main/activemq/wireformat/openwire/marsh/v4/ActiveMQ
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTempTopicMarshaller (p. 642).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.237 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTempTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 650).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.238 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQTempTopicMarshaller.h File

Reference

7.238 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³¹³/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ActiveMQTempDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ActiveMQTempTopicMarshaller** (p. 658).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.239 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTextMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 675).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.240 src/main/activemq/wireformat/openwire/marsh
shal/v2/ActiveMQTextMessageMarshaller.h File

Reference

~~7.240~~ src/main/activemq/wireformat/openwire/marsh⁴³¹⁵al/v2/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTextMessageMarshaller** (p. 687).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.241 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTextMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 667).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.242 src/main/activemq/wireformat/openwire/marsh
shal/v4/ActiveMQTextMessageMarshaller.h File

Reference

7.242 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³¹⁷/v4/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 671).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.243 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTextMessageMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 679).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.244 src/main/activemq/wireformat/openwire/marsh
shal/v6/ActiveMQTextMessageMarshaller.h File

Reference

~~7.244~~ src/main/activemq/wireformat/openwire/marsh⁴³¹⁹/v6/ActiveMQ

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/MessageMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ActiveMQTextMessageMarshaller (p. 683).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.245 src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 703).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.246

src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQTopicMarshaller.h

File Reference

7.246 src/main/activemq/wireformat/openwire/marshal/v2/ActiveMQ⁴³²¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 715).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.247 src/main/activemq/wireformat/openwire/marshal/v3/ActiveMQTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 695).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.248

src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQTopicMarshaller.h

File Reference

7.248 src/main/activemq/wireformat/openwire/marshal/v4/ActiveMQ⁴³²³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 699).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.249 src/main/activemq/wireformat/openwire/marshal/v5/ActiveMQTopicMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 707).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.250

src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQTopicMarshaller.h

File Reference

7.250 src/main/activemq/wireformat/openwire/marshal/v6/ActiveMQ⁴³²⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ActiveMQDestinationMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ActiveMQTopicMarshaller** (p. 711).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.251 src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 779).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.252

src/main/activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h

File Reference

7.252 src/main/activemq/wireformat/openwire/marshal/v2/BaseComm⁴³²⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 800).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.253 src/main/activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 765).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.254

src/main/activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h

File Reference

7.254 src/main/activemq/wireformat/openwire/marshal/v4/BaseComm⁴³²⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 772).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.255 src/main/activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 786).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.256

src/main/activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h

File Reference

7.256 src/main/activemq/wireformat/openwire/marshal/v6/BaseComm⁴³³¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BaseCommandMarshaller** (p. 793).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.257 src/main/activemq/wireformat/openwire/marshal/v1/BrokerIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 880).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.258 src/main/activemq/wireformat/openwire/marshal/v2/BrokerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 892).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.259 src/main/activemq/wireformat/openwire/marshal/v3/BrokerIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 872).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.260 src/main/activemq/wireformat/openwire/marshal/v4/BrokerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 876).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.261 src/main/activemq/wireformat/openwire/marshal/v5/BrokerIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 884).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.262 src/main/activemq/wireformat/openwire/marshal/v6/BrokerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerIdMarshaller** (p. 888).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.263 src/main/activemq/wireformat/openwire/marshal/v1/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 912).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.264 src/main/activemq/wireformat/openwire/marshal/v2/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 924).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.265 src/main/activemq/wireformat/openwire/marshal/v3/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 904).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.266 src/main/activemq/wireformat/openwire/marshal/v4/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 908).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.267 src/main/activemq/wireformat/openwire/marshal/v5/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 916).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.268 src/main/activemq/wireformat/openwire/marshal/v6/BrokerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **BrokerInfoMarshaller** (p. 920).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.269 src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1280).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.270 src/main/activemq/wireformat/openwire/marsh
shal/v2/ConnectionControlMarshaller.h File

Reference

7.270 ⁴³⁴⁵src/main/activemq/wireformat/openwire/marshal/v2/Connection
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1292).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.271 src/main/activemq/wireformat/openwire/marshal/v3/ConnectionControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1272).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.272 src/main/activemq/wireformat/openwire/marsh
shal/v4/ConnectionControlMarshaller.h File

Reference

7.272 ⁴³⁴⁷src/main/activemq/wireformat/openwire/marsh/v4/Connection
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1276).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.273 src/main/activemq/wireformat/openwire/marshal/v5/ConnectionControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1284).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.274 src/main/activemq/wireformat/openwire/marsh
shal/v6/ConnectionControlMarshaller.h File

Reference

7.274 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³⁴⁹/v6/Connection

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConnectionControlMarshaller (p. 1288).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.275 src/main/activemq/wireformat/openwire/marshal/v1/Connection File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1312).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.276

src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h

File Reference

7.276 ⁴³⁵¹src/main/activemq/wireformat/openwire/marshal/v2/ConnectionErrorMarshaller.h
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
```

```
#include <decaf/io/DataInputStream.h>
```

```
#include <decaf/io/DataOutputStream.h>
```

```
#include <decaf/io/IOException.h>
```

```
#include <activemq/util/Config.h>
```

```
#include <activemq/commands/DataStructure.h>
```

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

```
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1300).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.277 src/main/activemq/wireformat/openwire/marshal/v3/Connection File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1304).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.278

src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h

File Reference

7.278 src/main/activemq/wireformat/openwire/marshal/v4/ConnectionErrorMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1308).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.279 src/main/activemq/wireformat/openwire/marshal/v5/ConnectionErrorMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1316).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.280

src/main/activemq/wireformat/openwire/marshal/v6/ConnectionErrorMarshaller.h

File Reference

7.280 src/main/activemq/wireformat/openwire/marshal/v6/ConnectionErrorMarshaller.h 4355
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
```

```
#include <decaf/io/DataInputStream.h>
```

```
#include <decaf/io/DataOutputStream.h>
```

```
#include <decaf/io/IOException.h>
```

```
#include <activemq/util/Config.h>
```

```
#include <activemq/commands/DataStructure.h>
```

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

```
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionErrorMarshaller** (p. 1320).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.281 src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1343).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.282

src/main/activemq/wireformat/openwire/marshal/v2/ConnectionIdMarshaller.h

File Reference

7.282 src/main/activemq/wireformat/openwire/marshal/v2/Connection⁴³⁵⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
```

```
#include <decaf/io/DataInputStream.h>
```

```
#include <decaf/io/DataOutputStream.h>
```

```
#include <decaf/io/IOException.h>
```

```
#include <activemq/util/Config.h>
```

```
#include <activemq/commands/DataStructure.h>
```

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

```
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1331).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.283 src/main/activemq/wireformat/openwire/marshal/v3/ConnectionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1335).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.284

src/main/activemq/wireformat/openwire/marshal/v4/ConnectionIdMarshaller.h

File Reference

7.284 src/main/activemq/wireformat/openwire/marshal/v4/Connection⁴³⁵⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1339).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.285 src/main/activemq/wireformat/openwire/marshal/v5/ConnectionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1347).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.286

src/main/activemq/wireformat/openwire/marshal/v6/ConnectionIdMarshaller.h

File Reference

7.286 src/main/activemq/wireformat/openwire/marshal/v6/Connection⁴³⁶¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionIdMarshaller** (p. 1351).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.287 src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1373).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.288

src/main/activemq/wireformat/openwire/marshal/v2/ConnectionInfoMarshaller.h

File Reference

7.288 src/main/activemq/wireformat/openwire/marshal/v2/Connection⁴³⁶³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1361).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.289 src/main/activemq/wireformat/openwire/marshal/v3/ConnectionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1365).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.290

src/main/activemq/wireformat/openwire/marshal/v4/ConnectionInfoMarshaller.h

File Reference

7.290 src/main/activemq/wireformat/openwire/marshal/v4/Connection⁴³⁶⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1369).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.291 src/main/activemq/wireformat/openwire/marshal/v5/ConnectionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1377).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.292

src/main/activemq/wireformat/openwire/marshal/v6/ConnectionInfoMarshaller.h

File Reference

7.292 src/main/activemq/wireformat/openwire/marshal/v6/Connection⁴³⁶⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConnectionInfoMarshaller** (p. 1381).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.293 src/main/activemq/wireformat/openwire/marshal/v1/ConsumerControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1418).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.294 src/main/activemq/wireformat/openwire/marsh
shal/v2/ConsumerControlMarshaller.h File

Reference

7.294 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³⁶⁹/v2/ConsumerC

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1406).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.295 src/main/activemq/wireformat/openwire/marshal/v3/ConsumerControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1410).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.296 src/main/activemq/wireformat/openwire/marsh
shal/v4/ConsumerControlMarshaller.h File

Reference

7.296 ⁴³⁷¹src/main/activemq/wireformat/openwire/marsh/v4/ConsumerC

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1414).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.297 src/main/activemq/wireformat/openwire/marshal/v5/ConsumerControlMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ConsumerControlMarshaller** (p. 1422).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.298 src/main/activemq/wireformat/openwire/marsh
shal/v6/ConsumerControlMarshaller.h File

Reference

7.298 ⁴³⁷³src/main/activemq/wireformat/openwire/marshal/v6/ConsumerC
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller**

Marshaling code (p. 1183) for Open Wire Format for ConsumerControlMarshaller (p. 1426).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.299 src/main/activemq/wireformat/openwire/marshal/v1/ConsumerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1447).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.300

src/main/activemq/wireformat/openwire/marshal/v2/ConsumerIdMarshaller.h File

Reference

7.300 src/main/activemq/wireformat/openwire/marshal/v2/ConsumerIdMarshaller.h 4375

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1435).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.301 src/main/activemq/wireformat/openwire/marshal/v3/ConsumerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1439).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.302

src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h File

Reference

7.302 ⁴³⁷⁷src/main/activemq/wireformat/openwire/marshal/v4/ConsumerIdMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1443).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.303 src/main/activemq/wireformat/openwire/marshal/v5/ConsumerIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1451).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.304

src/main/activemq/wireformat/openwire/marshal/v6/ConsumerIdMarshaller.h File

Reference

7.304 src/main/activemq/wireformat/openwire/marshal/v6/ConsumerIdMarshaller.h 4379

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerIdMarshaller** (p. 1455).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.305 src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1480).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.306

src/main/activemq/wireformat/openwire/marshal/v2/ConsumerInfoMarshaller.h

File Reference

~~7.306~~ src/main/activemq/wireformat/openwire/marshal/v2/ConsumerI⁴³⁸¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1468).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.307 src/main/activemq/wireformat/openwire/marshal/v3/ConsumerInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1472).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.308

src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h

File Reference

7.308 src/main/activemq/wireformat/openwire/marshal/v4/ConsumerInfoMarshaller.h⁴³⁸³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1476).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.309 src/main/activemq/wireformat/openwire/marshal/v5/ConsumerInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1484).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.310

src/main/activemq/wireformat/openwire/marshal/v6/ConsumerInfoMarshaller.h

File Reference

~~7.310~~ src/main/activemq/wireformat/openwire/marshal/v6/ConsumerInfoMarshaller.h⁴³⁸⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ConsumerInfoMarshaller** (p. 1488).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.311 src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1509).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.312 src/main/activemq/wireformat/openwire/marsh
shal/v2/ControlCommandMarshaller.h File

Reference

7.312 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³⁸⁷/v2/ControlCo

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1497).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.313 src/main/activemq/wireformat/openwire/marshal/v3/ControlCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1501).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.314 src/main/activemq/wireformat/openwire/mar-
shal/v4/ControlCommandMarshaller.h File

Reference

7.314 ~~src/main/activemq/wireformat/openwire/marsh~~⁴³⁸⁹/v4/ControlCo

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1505).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.315 src/main/activemq/wireformat/openwire/marshal/v5/ControlCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1513).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.316 src/main/activemq/wireformat/openwire/mar-
shal/v6/ControlCommandMarshaller.h File

Reference

7.316 ⁴³⁹¹src/main/activemq/wireformat/openwire/marsh/v6/ControlCo
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **ControlCommandMarshaller** (p. 1517).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.317 src/main/activemq/wireformat/openwire/marshal/v1/DataArray File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1543).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.318 src/main/activemq/wireformat/openwire/marsh
shal/v2/DataArrayResponseMarshaller.h File

Reference

7.318 ⁴³⁹³src/main/activemq/wireformat/openwire/marshal/v2/DataArray
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1531).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.319 src/main/activemq/wireformat/openwire/marshal/v3/DataArray File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1535).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.320 src/main/activemq/wireformat/openwire/marsh
shal/v4/DataArrayResponseMarshaller.h File

Reference

7.320 ⁴³⁹⁵src/main/activemq/wireformat/openwire/marsh/v4/DataArray
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1539).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.321 src/main/activemq/wireformat/openwire/marshal/v5/DataArray File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1547).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.322 src/main/activemq/wireformat/openwire/marsh
shal/v6/DataArrayResponseMarshaller.h File

Reference

7.322 src/main/activemq/wireformat/openwire/marsh⁴³⁹⁷/v6/DataArray
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **DataArrayResponseMarshaller** (p. 1551).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.323 src/main/activemq/wireformat/openwire/marshal/v1/DataResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1606).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.324

src/main/activemq/wireformat/openwire/marshal/v2/DataResponseMarshaller.h

File Reference

7.324 src/main/activemq/wireformat/openwire/marshal/v2/DataResponseMarshaller.h⁴³⁹⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1594).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.325 src/main/activemq/wireformat/openwire/marshal/v3/DataResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1598).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.326

src/main/activemq/wireformat/openwire/marshal/v4/DataResponseMarshaller.h

File Reference

~~7.326~~ src/main/activemq/wireformat/openwire/marshal/v4/DataResponse⁴⁴⁰¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1602).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.327 src/main/activemq/wireformat/openwire/marshal/v5/DataResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1586).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.328

src/main/activemq/wireformat/openwire/marshal/v6/DataResponseMarshaller.h

File Reference

7.328 src/main/activemq/wireformat/openwire/marshal/v6/DataResponseMarshaller.h⁴⁴⁰³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DataResponseMarshaller** (p. 1590).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.329 src/main/activemq/wireformat/openwire/marshal/v1/DestinationInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1744).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.330

src/main/activemq/wireformat/openwire/marshal/v2/DestinationInfoMarshaller.h

File Reference

7.330 src/main/activemq/wireformat/openwire/marshal/v2/DestinationInfoMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1732).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.331 src/main/activemq/wireformat/openwire/marshal/v3/DestinationInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1736).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.332

src/main/activemq/wireformat/openwire/marshal/v4/DestinationInfoMarshaller.h

File Reference

7.332 ⁴⁴⁰⁷src/main/activemq/wireformat/openwire/marshal/v4/DestinationInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1740).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.333 src/main/activemq/wireformat/openwire/marshal/v5/DestinationInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1752).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.334

src/main/activemq/wireformat/openwire/marshal/v6/DestinationInfoMarshaller.h

File Reference

7.334 src/main/activemq/wireformat/openwire/marshal/v6/DestinationInfoMarshaller.h 4409

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DestinationInfoMarshaller** (p. 1748).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.335 src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryEventMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1778).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.336

src/main/activemq/wireformat/openwire/marshal/v2/DiscoveryEventMarshaller.h

File Reference

7.336 src/main/activemq/wireformat/openwire/marshal/v2/DiscoveryE⁴⁴¹¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1766).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.337 src/main/activemq/wireformat/openwire/marshal/v3/DiscoveryEventMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1770).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.338

src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryEventMarshaller.h

File Reference

7.338 src/main/activemq/wireformat/openwire/marshal/v4/DiscoveryE⁴⁴¹³

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1774).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.339 src/main/activemq/wireformat/openwire/marshal/v5/DiscoveryEventMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1782).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.340

src/main/activemq/wireformat/openwire/marshal/v6/DiscoveryEventMarshaller.h

File Reference

7.340 src/main/activemq/wireformat/openwire/marshal/v6/DiscoveryE⁴⁴¹⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **DiscoveryEventMarshaller** (p. 1762).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.341 src/main/activemq/wireformat/openwire/marshal/v1/ExceptionResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1862).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.342 src/main/activemq/wireformat/openwire/marsh
shal/v2/ExceptionResponseMarshaller.h File

Reference

7.342 src/main/activemq/wireformat/openwire/marsh⁴⁴¹⁷/v2/ExceptionR
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1846).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.343 src/main/activemq/wireformat/openwire/marshal/v3/ExceptionResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1850).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.344 src/main/activemq/wireformat/openwire/marsh
shal/v4/ExceptionResponseMarshaller.h File

Reference

7.344 src/main/activemq/wireformat/openwire/marsh⁴⁴¹⁹/v4/ExceptionR

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1858).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.345 src/main/activemq/wireformat/openwire/marshal/v5/ExceptionResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1854).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.346 src/main/activemq/wireformat/openwire/marsh
shal/v6/ExceptionResponseMarshaller.h File

Reference

7.346 src/main/activemq/wireformat/openwire/marsh⁴⁴²¹/v6/ExceptionR

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ExceptionResponseMarshaller** (p. 1842).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.347 src/main/activemq/wireformat/openwire/marshal/v1/FlushCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1956).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.348

src/main/activemq/wireformat/openwire/marshal/v2/FlushCommandMarshaller.h

File Reference

7.348 src/main/activemq/wireformat/openwire/marshal/v2/FlushCom⁴⁴²³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
```

```
#include <decaf/io/DataInputStream.h>
```

```
#include <decaf/io/DataOutputStream.h>
```

```
#include <decaf/io/IOException.h>
```

```
#include <activemq/util/Config.h>
```

```
#include <activemq/commands/DataStructure.h>
```

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

```
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1944).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.349 src/main/activemq/wireformat/openwire/marshal/v3/FlushCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1948).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.350

src/main/activemq/wireformat/openwire/marshal/v4/FlushCommandMarshaller.h

File Reference

7.350 src/main/activemq/wireformat/openwire/marshal/v4/FlushCom⁴⁴²⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1952).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.351 src/main/activemq/wireformat/openwire/marshal/v5/FlushCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1960).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.352

src/main/activemq/wireformat/openwire/marshal/v6/FlushCommandMarshaller.h

File Reference

7.352 src/main/activemq/wireformat/openwire/marshal/v6/FlushCommandMarshaller.h⁴⁴²⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **FlushCommandMarshaller** (p. 1940).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.353 src/main/activemq/wireformat/openwire/marshal/v1/IntegerRes File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller**
*Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2110).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.354

src/main/activemq/wireformat/openwire/marshal/v2/IntegerResponseMarshaller.h

File Reference

7.354 src/main/activemq/wireformat/openwire/marshal/v2/IntegerRes⁴⁴²⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2098).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.355 src/main/activemq/wireformat/openwire/marshal/v3/IntegerRes File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller**
*Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2102).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.356

src/main/activemq/wireformat/openwire/marshal/v4/IntegerResponseMarshaller.h

File Reference

~~7.356~~ src/main/activemq/wireformat/openwire/marshal/v4/IntegerRes⁴⁴³¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2106).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.357 src/main/activemq/wireformat/openwire/marshal/v5/IntegerRes File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller**
*Marshaling `code` (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2114).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.358

src/main/activemq/wireformat/openwire/marshal/v6/IntegerResponseMarshaller.h

File Reference

7.358 src/main/activemq/wireformat/openwire/marshal/v6/IntegerRes⁴⁴³³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **IntegerResponseMarshaller** (p. 2094).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.359 src/main/activemq/wireformat/openwire/marshal/v1/JournalQueueAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2179).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.360 src/main/activemq/wireformat/openwire/marsh
shal/v2/JournalQueueAckMarshaller.h File

Reference

7.360 ⁴⁴³⁵src/main/activemq/wireformat/openwire/marsh/v2/JournalQu
File Reference

```
#include <activemq/wireformat/openwire/marsh/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2163).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.361 src/main/activemq/wireformat/openwire/marshal/v3/JournalQueueAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2171).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.362 src/main/activemq/wireformat/openwire/marsh
shal/v4/JournalQueueAckMarshaller.h File

Reference

7.362 ⁴⁴³⁷src/main/activemq/wireformat/openwire/marsh/v4/JournalQueueAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marsh/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller**

Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2175).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.363 src/main/activemq/wireformat/openwire/marshal/v5/JournalQueueAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **JournalQueueAckMarshaller** (p. 2167).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.364 src/main/activemq/wireformat/openwire/marsh
shal/v6/JournalQueueAckMarshaller.h File

Reference

7.364 ⁴⁴³⁹src/main/activemq/wireformat/openwire/marsh/v6/JournalQueueAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marsh/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller**

Marshaling code (p. 1183) for Open Wire Format for JournalQueueAckMarshaller (p. 2159).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.365 src/main/activemq/wireformat/openwire/marshal/v1/JournalTopicAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2208).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.366 src/main/activemq/wireformat/openwire/marsh
shal/v2/JournalTopicAckMarshaller.h File

Reference

7.366 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁴⁴¹/v2/JournalTopic
File Reference

```
#include <activemq/wireformat/openwire/marshall/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2192).*

Namespaces

- namespace **activemq**
*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.367 src/main/activemq/wireformat/openwire/marshal/v3/JournalTopicAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2196).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.368 src/main/activemq/wireformat/openwire/marsh
shal/v4/JournalTopicAckMarshaller.h File

Reference

7.368 src/main/activemq/wireformat/openwire/marsh⁴⁴⁴³/v4/JournalTopic

File Reference

```
#include <activemq/wireformat/openwire/marshall/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2204).*

Namespaces

- namespace **activemq**
*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.369 src/main/activemq/wireformat/openwire/marshal/v5/JournalTopicAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2188).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.370 src/main/activemq/wireformat/openwire/marsh
shal/v6/JournalTopicAckMarshaller.h File

Reference

7.370 ⁴⁴⁴⁵src/main/activemq/wireformat/openwire/marshal/v6/JournalTopicAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTopicAckMarshaller** (p. 2200).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.371 src/main/activemq/wireformat/openwire/marshal/v1/JournalTraceMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2231).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.372

src/main/activemq/wireformat/openwire/marshal/v2/JournalTraceMarshaller.h

File Reference

7.372 src/main/activemq/wireformat/openwire/marshal/v2/JournalTra⁴⁴⁴⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2215).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-ments.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.373 src/main/activemq/wireformat/openwire/marshal/v3/JournalTraceMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2219).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.374

src/main/activemq/wireformat/openwire/marshal/v4/JournalTraceMarshaller.h

File Reference

7.374 src/main/activemq/wireformat/openwire/marshal/v4/JournalTra⁴⁴⁴⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2227).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.375 src/main/activemq/wireformat/openwire/marshal/v5/JournalTraceMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2235).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.376

src/main/activemq/wireformat/openwire/marshal/v6/JournalTraceMarshaller.h

File Reference

7.376 src/main/activemq/wireformat/openwire/marshal/v6/JournalTra⁴⁴⁵¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **JournalTraceMarshaller** (p. 2223).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.377 src/main/activemq/wireformat/openwire/marshal/v1/JournalTransactionMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2262).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.378 src/main/activemq/wireformat/openwire/marsh-
shal/v2/JournalTransactionMarshaller.h File

Reference

7.378 ⁴⁴⁵³src/main/activemq/wireformat/openwire/marshal/v2/JournalTra
File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2246).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.379 src/main/activemq/wireformat/openwire/marshal/v3/JournalTransactionMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2250).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.380 src/main/activemq/wireformat/openwire/marsh-
shal/v4/JournalTransactionMarshaller.h File

Reference

7.380 ⁴⁴⁵⁵src/main/activemq/wireformat/openwire/marsh/v4/JournalTra
File Reference

```
#include <activemq/wireformat/openwire/marsh/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2258).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.381 src/main/activemq/wireformat/openwire/marshal/v5/JournalTransactionMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2254).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.382 src/main/activemq/wireformat/openwire/marsh
shal/v6/JournalTransactionMarshaller.h File

Reference

7.382 ⁴⁴⁵⁷src/main/activemq/wireformat/openwire/marsh/v6/JournalTra

File Reference

```
#include <activemq/wireformat/openwire/marshall/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **JournalTransactionMarshaller** (p. 2242).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.383 src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2289).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.384

src/main/activemq/wireformat/openwire/marshal/v2/KeepAliveInfoMarshaller.h

File Reference

7.384 src/main/activemq/wireformat/openwire/marshal/v2/KeepAliveInfoMarshaller.h⁴⁴⁵⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2273).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.385 src/main/activemq/wireformat/openwire/marshal/v3/KeepAliveInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2277).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.386

src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h

File Reference

7.386 src/main/activemq/wireformat/openwire/marshal/v4/KeepAliveInfoMarshaller.h⁴⁴⁶¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2281).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.387 src/main/activemq/wireformat/openwire/marshal/v5/KeepAliveInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2285).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.388

src/main/activemq/wireformat/openwire/marshal/v6/KeepAliveInfoMarshaller.h

File Reference

7.388 src/main/activemq/wireformat/openwire/marshal/v6/KeepAliveInfoMarshaller.h⁴⁴⁶³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **KeepAliveInfoMarshaller** (p. 2269).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.389 src/main/activemq/wireformat/openwire/marshal/v1/LastPartial File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2324).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.390 src/main/activemq/wireformat/openwire/marsh
shal/v2/LastPartialCommandMarshaller.h File

Reference

7.390 ⁴⁴⁶⁵src/main/activemq/wireformat/openwire/marsh/v2/LastPartial

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2312).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.391 src/main/activemq/wireformat/openwire/marshal/v3/LastPartialCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2308).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.392 src/main/activemq/wireformat/openwire/marsh
shal/v4/LastPartialCommandMarshaller.h File

Reference

7.392 src/main/activemq/wireformat/openwire/marsh⁴⁴⁶⁷/v4/LastPartial

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2320).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.393 src/main/activemq/wireformat/openwire/marshal/v5/LastPartialCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2316).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.394 src/main/activemq/wireformat/openwire/marsh
shal/v6/LastPartialCommandMarshaller.h File

Reference

7.394 ⁴⁴⁶⁹src/main/activemq/wireformat/openwire/marsh/v6/LastPartial

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/PartialCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **LastPartialCommandMarshaller** (p. 2304).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.395 src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2371).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.396 src/main/activemq/wireformat/openwire/mar-
shal/v2/LocalTransactionIdMarshaller.h File

Reference

7.396 ⁴⁴⁷¹src/main/activemq/wireformat/openwire/marsh/v2/LocalTrans
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2355).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.397 src/main/activemq/wireformat/openwire/marshal/v3/LocalTransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2359).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.398 src/main/activemq/wireformat/openwire/marsh
shal/v4/LocalTransactionIdMarshaller.h File

Reference

7.398 src/main/activemq/wireformat/openwire/marsh⁴⁴⁷³/v4/LocalTrans

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2367).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.399 src/main/activemq/wireformat/openwire/marshal/v5/LocalTransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2363).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.400 src/main/activemq/wireformat/openwire/marsh
shal/v6/LocalTransactionIdMarshaller.h File

Reference

~~7.400~~ src/main/activemq/wireformat/openwire/marsh⁴⁴⁷⁵/v6/LocalTrans
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **LocalTransactionIdMarshaller** (p. 2351).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.401 src/main/activemq/wireformat/openwire/marshal/v1/Marshaller File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MarshallerFactory**

Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.402 src/main/activemq/wireformat/openwire/marshal/v2/MarshallerFactory.h File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MarshallerFactory**
Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.403 src/main/activemq/wireformat/openwire/marshal/v3/Marshaller File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MarshallerFactory**

Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.404 src/main/activemq/wireformat/openwire/marshal/v4/MarshallerFactory.h File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MarshallerFactory**
Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.405 src/main/activemq/wireformat/openwire/marshal/v5/Marshaller File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MarshallerFactory**

Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.406 src/main/activemq/wireformat/openwire/marshal/v6/MarshallerFactory.h File Reference

```
#include <activemq/wireformat/openwire/OpenWireFormat.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MarshallerFactory**
Used to create marshallers for a specific version of the wire protocol.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.407 src/main/activemq/wireformat/openwire/marshal/v1/MessageAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2581).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.408

src/main/activemq/wireformat/openwire/marshal/v2/MessageAckMarshaller.h File

Reference

7.408 src/main/activemq/wireformat/openwire/marshal/v2/MessageAckMarshaller.h 4483

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2569).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.409 src/main/activemq/wireformat/openwire/marshal/v3/MessageAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2573).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.410

src/main/activemq/wireformat/openwire/marshal/v4/MessageAckMarshaller.h File

Reference

7.410⁴⁴⁸⁵ src/main/activemq/wireformat/openwire/marshal/v4/MessageAckMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2577).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.411 src/main/activemq/wireformat/openwire/marshal/v5/MessageAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2585).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.412

src/main/activemq/wireformat/openwire/marshal/v6/MessageAckMarshaller.h File

Reference

7.412⁴⁴⁸⁷ src/main/activemq/wireformat/openwire/marshal/v6/MessageAckMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageAckMarshaller** (p. 2565).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.413 src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchMarshaller (p. 2622).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.414 src/main/activemq/wireformat/openwire/mar-
shal/v2/MessageDispatchMarshaller.h File

Reference

7.414 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁴⁸⁹/v2/MessageDi

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchMarshaller (p. 2606).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.415 src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchMarshaller (p. 2610).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.416 src/main/activemq/wireformat/openwire/marsh
shal/v4/MessageDispatchMarshaller.h File

Reference

7.416 src/main/activemq/wireformat/openwire/marshal⁴⁴⁹¹/v4/MessageDi

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller**

Marshaling code (p.1183) for Open Wire Format for MessageDispatchMarshaller (p.2618).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.417 src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchMarshaller (p. 2614).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.418 src/main/activemq/wireformat/openwire/mar-
shal/v6/MessageDispatchMarshaller.h File

Reference

7.418 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁴⁹³/v6/MessageDi
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchMarshaller (p. 2626).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.419 src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchNotificationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2651).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.420 src/main/activemq/wireformat/openwire/marsh
shal/v2/MessageDispatchNotificationMarshaller.h File

Reference

7.420 ⁴⁴⁹⁵src/main/activemq/wireformat/openwire/marshal/v2/MessageDi
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *MessageDispatchNotificationMarshaller* (p. 2639).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.421 src/main/activemq/wireformat/openwire/marshal/v3/MessageDispatchNotificationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for *Open Wire Format for MessageDispatchNotificationMarshaller* (p. 2643).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.422 src/main/activemq/wireformat/openwire/marsh
shal/v4/MessageDispatchNotificationMarshaller.h File

Reference

7.422 src/main/activemq/wireformat/openwire/marsh⁴⁴⁹⁷/v4/MessageDi
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for *Open Wire Format for MessageDispatchNotificationMarshaller* (p. 2647).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.423 src/main/activemq/wireformat/openwire/marshal/v5/MessageDispatchNotificationMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for Open Wire Format for MessageDispatchNotificationMarshaller (p. 2655).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.424 src/main/activemq/wireformat/openwire/marsh
shal/v6/MessageDispatchNotificationMarshaller.h File

Reference

7.424 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁴⁹⁹/v6/MessageDi
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for *MessageDispatchNotificationMarshaller* (p. 2635).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.425 src/main/activemq/wireformat/openwire/marshal/v1/MessageId. File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2688).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.426 src/main/activemq/wireformat/openwire/marshal/v2/MessageIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2668).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.427 src/main/activemq/wireformat/openwire/marshal/v3/MessageId. File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2680).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.428 src/main/activemq/wireformat/openwire/marshal/v4/MessageIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2672).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.429 src/main/activemq/wireformat/openwire/marshal/v5/MessageId. File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2676).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.430 src/main/activemq/wireformat/openwire/marshal/v6/MessageIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageIdMarshaller** (p. 2684).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.431 src/main/activemq/wireformat/openwire/marshal/v1/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2713).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.432 src/main/activemq/wireformat/openwire/marshal/v2/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2703).*

Namespaces

- namespace **activemq**
*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.433 src/main/activemq/wireformat/openwire/marshal/v3/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2698).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.434 src/main/activemq/wireformat/openwire/marshal/v4/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2708).*

Namespaces

- namespace **activemq**
*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.435 src/main/activemq/wireformat/openwire/marshal/v5/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2693).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.436 src/main/activemq/wireformat/openwire/marshal/v6/MessageM File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessageMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessageMarshaller** (p. 2718).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.437 src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2760).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.438

src/main/activemq/wireformat/openwire/marshal/v2/MessagePullMarshaller.h

File Reference

7.438 src/main/activemq/wireformat/openwire/marshal/v2/MessagePu⁴⁵¹³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2744).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.439 src/main/activemq/wireformat/openwire/marshal/v3/MessagePullMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2752).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.440

src/main/activemq/wireformat/openwire/marshal/v4/MessagePullMarshaller.h

File Reference

7.440 src/main/activemq/wireformat/openwire/marshal/v4/MessagePu⁴⁵¹⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2756).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.441 src/main/activemq/wireformat/openwire/marshal/v5/MessagePullMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2748).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.442

src/main/activemq/wireformat/openwire/marshal/v6/MessagePullMarshaller.h

File Reference

7.442 ⁴⁵¹⁷src/main/activemq/wireformat/openwire/marshal/v6/MessagePullMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **MessagePullMarshaller** (p. 2764).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.443 src/main/activemq/wireformat/openwire/marshal/v1/NetworkBridgeFilterMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2816).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.444 src/main/activemq/wireformat/openwire/marsh
shal/v2/NetworkBridgeFilterMarshaller.h File

Reference

~~7.444~~ src/main/activemq/wireformat/openwire/marsh⁴⁵¹⁹
shal/v2/NetworkBr

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2796).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.445 src/main/activemq/wireformat/openwire/marshal/v3/NetworkBridgeFilterMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2808).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.446 src/main/activemq/wireformat/openwire/marsh
shal/v4/NetworkBridgeFilterMarshaller.h File

Reference

7.446 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁵²¹/v4/NetworkBr

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2812).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.447 src/main/activemq/wireformat/openwire/marshal/v5/NetworkBridgeFilterMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2804).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.448 src/main/activemq/wireformat/openwire/mar-
shal/v6/NetworkBridgeFilterMarshaller.h File

Reference

7.448 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁵²³/v6/NetworkBr

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller**

*Marshaling **code** (p. 1183) for Open Wire Format for **NetworkBridgeFilterMarshaller** (p. 2800).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.449 src/main/activemq/wireformat/openwire/marshal/v1/PartialCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2942).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.450 src/main/activemq/wireformat/openwire/mar-
shal/v2/PartialCommandMarshaller.h File

Reference

~~7.450~~ ⁴⁵²⁵ src/main/activemq/wireformat/openwire/marsh/v2/PartialCon
File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2926).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.451 src/main/activemq/wireformat/openwire/marshal/v3/PartialCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2934).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.452 src/main/activemq/wireformat/openwire/mar-
shal/v4/PartialCommandMarshaller.h File

Reference

7.452 ⁴⁵²⁷src/main/activemq/wireformat/openwire/marsh/v4/PartialCon
File Reference

```
#include <activemq/wireformat/openwire/marshall/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2938).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.453 src/main/activemq/wireformat/openwire/marshal/v5/PartialCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2930).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.454 src/main/activemq/wireformat/openwire/mar-
shal/v6/PartialCommandMarshaller.h File

Reference

~~7.454~~ src/main/activemq/wireformat/openwire/marsh⁴⁵²⁹/v6/PartialCon
File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **PartialCommandMarshaller** (p. 2922).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.455 src/main/activemq/wireformat/openwire/marshal/v1/ProducerAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3060).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.456

src/main/activemq/wireformat/openwire/marshal/v2/ProducerAckMarshaller.h

File Reference

7.456 src/main/activemq/wireformat/openwire/marshal/v2/ProducerA⁴⁵³¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3040).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.457 src/main/activemq/wireformat/openwire/marshal/v3/ProducerAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3048).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.458

src/main/activemq/wireformat/openwire/marshal/v4/ProducerAckMarshaller.h

File Reference

7.458 src/main/activemq/wireformat/openwire/marshal/v4/ProducerA⁴⁵³³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3044).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.459 src/main/activemq/wireformat/openwire/marshal/v5/ProducerAckMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3052).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.460

src/main/activemq/wireformat/openwire/marshal/v6/ProducerAckMarshaller.h

File Reference

7.460 src/main/activemq/wireformat/openwire/marshal/v6/ProducerA⁴⁵³⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerAckMarshaller** (p. 3056).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.461 src/main/activemq/wireformat/openwire/marshal/v1/ProducerId File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3092).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.462

src/main/activemq/wireformat/openwire/marshal/v2/ProducerIdMarshaller.h File

Reference

7.462 ⁴⁵³⁷src/main/activemq/wireformat/openwire/marshal/v2/ProducerId

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3072).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.463 src/main/activemq/wireformat/openwire/marshal/v3/ProducerId File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3080).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.464

src/main/activemq/wireformat/openwire/marshal/v4/ProducerIdMarshaller.h File

Reference

7.464 src/main/activemq/wireformat/openwire/marshal/v4/ProducerId⁴⁵³⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3076).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.465 src/main/activemq/wireformat/openwire/marshal/v5/ProducerId File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3084).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.466

src/main/activemq/wireformat/openwire/marshal/v6/ProducerIdMarshaller.h File

Reference

7.466 src/main/activemq/wireformat/openwire/marshal/v6/ProducerId⁴⁵⁴¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerIdMarshaller** (p. 3088).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.467 src/main/activemq/wireformat/openwire/marshal/v1/ProducerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3109).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.468

src/main/activemq/wireformat/openwire/marshal/v2/ProducerInfoMarshaller.h

File Reference

7.468 src/main/activemq/wireformat/openwire/marshal/v2/ProducerInfoMarshaller.h⁴⁵⁴³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3105).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.469 src/main/activemq/wireformat/openwire/marshal/v3/ProducerInfoMarshall.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3117).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.470

src/main/activemq/wireformat/openwire/marshal/v4/ProducerInfoMarshaller.h

File Reference

7.470 ⁴⁵⁴⁵src/main/activemq/wireformat/openwire/marshal/v4/ProducerInfo

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3101).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.471 src/main/activemq/wireformat/openwire/marshal/v5/ProducerInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3113).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.472

src/main/activemq/wireformat/openwire/marshal/v6/ProducerInfoMarshaller.h

File Reference

7.472 src/main/activemq/wireformat/openwire/marshal/v6/ProducerInfoMarshaller.h⁴⁵⁴⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ProducerInfoMarshaller** (p. 3121).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.473 src/main/activemq/wireformat/openwire/marshal/v1/RemoveInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3210).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.474

src/main/activemq/wireformat/openwire/marshal/v2/RemoveInfoMarshaller.h File

Reference

7.474 ⁴⁵⁴⁹src/main/activemq/wireformat/openwire/marshal/v2/RemoveInfo

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3198).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.475 src/main/activemq/wireformat/openwire/marshal/v3/RemoveInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3206).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.476

src/main/activemq/wireformat/openwire/marshal/v4/RemoveInfoMarshaller.h File

Reference

7.476 src/main/activemq/wireformat/openwire/marshal/v4/RemoveInfo⁴⁵⁵¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3218).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.477 src/main/activemq/wireformat/openwire/marshal/v5/RemoveInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3214).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.478

src/main/activemq/wireformat/openwire/marshal/v6/RemoveInfoMarshaller.h File

Reference

7.478 ⁴⁵⁵³src/main/activemq/wireformat/openwire/marshal/v6/RemoveInfo

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **RemoveInfoMarshaller** (p. 3202).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.479 src/main/activemq/wireformat/openwire/marshal/v1/RemoveSubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3227).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.480 src/main/activemq/wireformat/openwire/marsh
shal/v2/RemoveSubscriptionInfoMarshaller.h File

Reference

7.480 ⁴⁵⁵⁵src/main/activemq/wireformat/openwire/marsh/v2/RemoveSu

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller**

Marshaling code (p. 1183) for *Open Wire Format* for ***RemoveSubscriptionInfoMarshaller***
(p. 3235).

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.481 src/main/activemq/wireformat/openwire/marshal/v3/RemoveSubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3231).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.482 src/main/activemq/wireformat/openwire/marsh
shal/v4/RemoveSubscriptionInfoMarshaller.h File

Reference

7.482 ⁴⁵⁵⁷src/main/activemq/wireformat/openwire/marsh/v4/RemoveSu

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3247).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.483 src/main/activemq/wireformat/openwire/marshal/v5/RemoveSubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3243).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.484 src/main/activemq/wireformat/openwire/marsh
shal/v6/RemoveSubscriptionInfoMarshaller.h File

Reference

~~7.484~~ src/main/activemq/wireformat/openwire/marsh⁴⁵⁵⁹al/v6/RemoveSubscriptionInfoMarshaller.h File

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **RemoveSubscriptionInfoMarshaller** (p. 3239).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.485 src/main/activemq/wireformat/openwire/marshal/v1/ReplayCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3258).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.486 src/main/activemq/wireformat/openwire/mar-
shal/v2/ReplayCommandMarshaller.h File

Reference

7.486 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁵⁶¹/v2/ReplayCon

File Reference

```
#include <activemq/wireformat/openwire/marshall/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3262).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.487 src/main/activemq/wireformat/openwire/marshal/v3/ReplayCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3266).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.488 src/main/activemq/wireformat/openwire/mar-
shal/v4/ReplayCommandMarshaller.h File

Reference

7.488 ⁴⁵⁶³src/main/activemq/wireformat/openwire/marsh/v4/ReplayCom

File Reference

```
#include <activemq/wireformat/openwire/marshall/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3254).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.489 src/main/activemq/wireformat/openwire/marshal/v5/ReplayCommandMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3274).*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.490 src/main/activemq/wireformat/openwire/mar-
shal/v6/ReplayCommandMarshaller.h File

Reference

~~7.490~~ ⁴⁵⁶⁵ src/main/activemq/wireformat/openwire/marsh/v6/ReplayCom
File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller**

*Marshaling code (p. 1183) for Open Wire Format for **ReplayCommandMarshaller** (p. 3270).*

Namespaces

- namespace **activemq**

*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.491 src/main/activemq/wireformat/openwire/marshal/v1/ResponseM File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3315).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.492 src/main/activemq/wireformat/openwire/marshal/v2/ResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3300).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.493 src/main/activemq/wireformat/openwire/marshal/v3/ResponseM File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3310).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.494 src/main/activemq/wireformat/openwire/marshal/v4/ResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3295).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.495 src/main/activemq/wireformat/openwire/marshal/v5/ResponseM File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3305).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.496 src/main/activemq/wireformat/openwire/marshal/v6/ResponseMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ResponseMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ResponseMarshaller** (p. 3320).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.497 src/main/activemq/wireformat/openwire/marshal/v1/SessionIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3403).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.498 src/main/activemq/wireformat/openwire/marshal/v2/SessionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3383).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.499 src/main/activemq/wireformat/openwire/marshal/v3/SessionIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3399).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.500 src/main/activemq/wireformat/openwire/marshal/v4/SessionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3387).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.501 src/main/activemq/wireformat/openwire/marshal/v5/SessionIdM File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3395).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.502 src/main/activemq/wireformat/openwire/marshal/v6/SessionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionIdMarshaller** (p. 3391).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.503 src/main/activemq/wireformat/openwire/marshal/v1/SessionInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3419).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.504

src/main/activemq/wireformat/openwire/marshal/v2/SessionInfoMarshaller.h File

Reference

7.504 src/main/activemq/wireformat/openwire/marshal/v2/SessionInfo⁴⁵⁷⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3427).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.505 src/main/activemq/wireformat/openwire/marshal/v3/SessionInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3423).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.506

src/main/activemq/wireformat/openwire/marshal/v4/SessionInfoMarshaller.h File

Reference

7.506 src/main/activemq/wireformat/openwire/marshal/v4/SessionInfo⁴⁵⁸¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3431).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.507 src/main/activemq/wireformat/openwire/marshal/v5/SessionInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3415).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.508

src/main/activemq/wireformat/openwire/marshal/v6/SessionInfoMarshaller.h File

Reference

7.508 src/main/activemq/wireformat/openwire/marshal/v6/SessionInfo⁴⁵⁸³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SessionInfoMarshaller** (p. 3411).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.509 src/main/activemq/wireformat/openwire/marshal/v1/ShutdownInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3481).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.510

src/main/activemq/wireformat/openwire/marshal/v2/ShutdownInfoMarshaller.h

File Reference

7.510 src/main/activemq/wireformat/openwire/marshal/v2/ShutdownI⁴⁵⁸⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3477).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.511 src/main/activemq/wireformat/openwire/marshal/v3/ShutdownInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3489).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.512

src/main/activemq/wireformat/openwire/marshal/v4/ShutdownInfoMarshaller.h

File Reference

7.512 src/main/activemq/wireformat/openwire/marshal/v4/ShutdownI⁴⁵⁸⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3493).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.513 src/main/activemq/wireformat/openwire/marshal/v5/ShutdownInfo File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3485).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.514

src/main/activemq/wireformat/openwire/marshal/v6/ShutdownInfoMarshaller.h

File Reference

7.514 src/main/activemq/wireformat/openwire/marshal/v6/ShutdownI⁴⁵⁸⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **ShutdownInfoMarshaller** (p. 3473).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.515 src/main/activemq/wireformat/openwire/marshal/v1/SubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3680).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.516

src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h

File Reference

7.516 ⁴⁵⁹¹src/main/activemq/wireformat/openwire/marshal/v2/SubscriptionInfoMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3696).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.517 src/main/activemq/wireformat/openwire/marshal/v3/SubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3676).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.518

src/main/activemq/wireformat/openwire/marshal/v4/SubscriptionInfoMarshaller.h

File Reference

7.518 src/main/activemq/wireformat/openwire/marshal/v4/SubscriptionInfoMarshaller.h⁴⁵⁹³

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3688).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.519 src/main/activemq/wireformat/openwire/marshal/v5/SubscriptionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3684).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.520

src/main/activemq/wireformat/openwire/marshal/v6/SubscriptionInfoMarshaller.h

File Reference

7.520 src/main/activemq/wireformat/openwire/marshal/v6/SubscriptionInfoMarshaller.h⁴⁵⁹⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **SubscriptionInfoMarshaller** (p. 3692).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.521 src/main/activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3827).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.522

src/main/activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h

File Reference

7.522 src/main/activemq/wireformat/openwire/marshal/v2/Transaction⁴⁵⁹⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3831).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.523 src/main/activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3835).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.524

src/main/activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h

File Reference

7.524 src/main/activemq/wireformat/openwire/marshal/v4/Transaction⁴⁵⁹⁹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3839).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.525 src/main/activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3823).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.526

src/main/activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h

File Reference

7.526 src/main/activemq/wireformat/openwire/marshal/v6/Transaction⁴⁶⁰¹

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionIdMarshaller** (p. 3843).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.527 src/main/activemq/wireformat/openwire/marshal/v1/TransactionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3855).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.528

src/main/activemq/wireformat/openwire/marshal/v2/TransactionInfoMarshaller.h

File Reference

7.528 src/main/activemq/wireformat/openwire/marshal/v2/Transaction⁴⁶⁰³

File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3871).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.529 src/main/activemq/wireformat/openwire/marshal/v3/TransactionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3859).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.530

src/main/activemq/wireformat/openwire/marshal/v4/TransactionInfoMarshaller.h

File Reference

7.530 src/main/activemq/wireformat/openwire/marshal/v4/Transaction⁴⁶⁰⁵

File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3867).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.531 src/main/activemq/wireformat/openwire/marshal/v5/TransactionInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3851).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.532

src/main/activemq/wireformat/openwire/marshal/v6/TransactionInfoMarshaller.h

File Reference

7.532 src/main/activemq/wireformat/openwire/marshal/v6/Transaction⁴⁶⁰⁷

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/BaseCommandMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **TransactionInfoMarshaller** (p. 3863).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.533 src/main/activemq/wireformat/openwire/marshal/v1/WireFormatInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4008).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.534

src/main/activemq/wireformat/openwire/marshal/v2/WireFormatInfoMarshaller.h

File Reference

7.534 src/main/activemq/wireformat/openwire/marshal/v2/WireFormatInfoMarshaller.h 4609

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4000).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.535 src/main/activemq/wireformat/openwire/marshal/v3/WireFormatInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4012).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.536

src/main/activemq/wireformat/openwire/marshal/v4/WireFormatInfoMarshaller.h

File Reference

7.536 src/main/activemq/wireformat/openwire/marshal/v4/WireFormatInfoMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 4004).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.537 src/main/activemq/wireformat/openwire/marshal/v5/WireFormatInfoMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3992).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.538

src/main/activemq/wireformat/openwire/marshal/v6/WireFormatInfoMarshaller.h

File Reference

7.538 src/main/activemq/wireformat/openwire/marshal/v6/WireFormatInfoMarshaller.h

File Reference

```
#include <activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller**
*Marshaling code (p. 1183) for Open Wire Format for **WireFormatInfoMarshaller** (p. 3996).*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.539 src/main/activemq/wireformat/openwire/marshal/v1/XATransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v1/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4048).

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v1**

7.540 src/main/activemq/wireformat/openwire/mar-
shal/v2/XATransactionIdMarshaller.h File

Reference

7.540 ⁴⁶¹⁵src/main/activemq/wireformat/openwire/marshal/v2/XATransac
File Reference

```
#include <activemq/wireformat/openwire/marshal/v2/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4040).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v2**

7.541 src/main/activemq/wireformat/openwire/marshal/v3/XATransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v3/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4052).

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v3**

7.542 src/main/activemq/wireformat/openwire/mar-
shal/v4/XATransactionIdMarshaller.h File

Reference

7.542 ⁴⁶¹⁷src/main/activemq/wireformat/openwire/marsh/v4/XATransac
File Reference

```
#include <activemq/wireformat/openwire/marshal/v4/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4044).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v4**

7.543 src/main/activemq/wireformat/openwire/marshal/v5/XATransactionIdMarshaller.h File Reference

```
#include <activemq/wireformat/openwire/marshal/v5/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4056).

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v5**

7.544 src/main/activemq/wireformat/openwire/marsh
shal/v6/XATransactionIdMarshaller.h File

Reference

7.544 ~~src/main/activemq/wireformat/openwire/marsh~~⁴⁶¹⁹/v6/XATransac

File Reference

```
#include <activemq/wireformat/openwire/marshal/v6/TransactionIdMarshaller.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <activemq/util/Config.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/openwire/Utils/BooleanStream.h>
```

Data Structures

- class **activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller**

Marshaling code (p. 1183) for Open Wire Format for XATransactionIdMarshaller (p. 4036).

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**
- namespace **activemq::wireformat::openwire::marshal::v6**

7.545 src/main/activemq/wireformat/openwire/OpenWireFormat.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/commands/WireFormatInfo.h>
#include <activemq/commands/DataStructure.h>
#include <activemq/wireformat/WireFormat.h>
#include <activemq/wireformat/openwire/utils/BooleanStream.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/Properties.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <memory>
```

Data Structures

- class **activemq::wireformat::openwire::OpenWireFormat**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::marshal**

7.546 src/main/activemq/wireformat/openwire/OpenWireFormatFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/wireformat/WireFormatFactory.h>
#include <activemq/commands/WireFormatInfo.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/Pointer.h>
#include <decaf/util/Properties.h>
```

Data Structures

- class **activemq::wireformat::openwire::OpenWireFormatFactory**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**

7.547 src/main/activemq/wireformat/openwire/OpenWireFormatNegotiator.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <activemq/wireformat/openwire/OpenWireFormat.h>
#include <activemq/wireformat/WireFormatNegotiator.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/CountDownLatch.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::openwire::OpenWireFormatNegotiator**

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**

7.548 src/main/activemq/wireformat/openwire/OpenWireResponseBuilder.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/mock/ResponseBuilder.h>
#include <decaf/util/StlQueue.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::openwire::OpenWireResponseBuilder**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**

7.549 src/main/activemq/wireformat/openwire/utils/BooleanStream.h File Reference

```
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq:wireformat::openwire::utils::BooleanStream**
Manages the writing and reading of boolean data streams to and from a data source such as a `DataInputStream` or `DataOutputStream`.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq:wireformat**
- namespace **activemq:wireformat::openwire**
- namespace **activemq:wireformat::openwire::utils**

7.550 src/main/activemq/wireformat/openwire/Utils/HexTable.h File Reference

```
#include <vector>
#include <string>
#include <activemq/util/Config.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **activemq::wireformat::openwire::Utils::HexTable**

*The **HexTable** (p. 1984) class maps hexadecimal strings to the value of an index into the table, i.e.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::Utils**

7.551 src/main/activemq/wireformat/openwire/Utils/MessagePropertyInterceptor.h File Reference

```
#include <activemq/Util/Config.h>
#include <activemq/commands/Message.h>
#include <activemq/Util/PrimitiveMap.h>
#include <activemq/exceptions/ActiveMQException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
```

Data Structures

- class **activemq::wireformat::openwire::Utils::MessagePropertyInterceptor**
Used the base ActiveMQMessage class to intercept calls to get and set properties in order to capture the calls that use the reserved JMS properties and get and set them in the OpenWire Message properties.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::openwire**
- namespace **activemq::wireformat::openwire::Utils**

7.552 src/main/activemq/wireformat/stomp/StompCommandConstants.h File Reference

```
#include <cms/Destination.h>
#include <activemq/util/Config.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <string>
#include <map>
```

Data Structures

- class **activemq::wireformat::stomp::StompCommandConstants**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::stomp**

7.553 src/main/activemq/wireformat/stomp/StompFrame.h File Reference

```
#include <string>
#include <string.h>
#include <map>
#include <decaf/util/Properties.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/DataInputStream.h>
#include <activemq/util/Config.h>
```

Data Structures

- class **activemq::wireformat::stomp::StompFrame**
A Stomp-level message frame that encloses all messages to and from the broker.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::stomp**

7.554 src/main/activemq/wireformat/stomp/StompHelper.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/util/LongSequenceGenerator.h>
#include <activemq/wireformat/stomp/StompFrame.h>
#include <activemq/commands/Message.h>
#include <activemq/commands/MessageId.h>
#include <activemq/commands/ProducerId.h>
#include <activemq/commands/ConsumerId.h>
#include <activemq/commands/TransactionId.h>
#include <activemq/commands/ActiveMQDestination.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::stomp::StompHelper**
Utility Methods used when marshaling to and from StompFrame's.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::stomp**

7.555 src/main/activemq/wireformat/stomp/StompWireFormat.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/wireformat/WireFormat.h>
#include <activemq/wireformat/stomp/StompFrame.h>
#include <activemq/wireformat/stomp/StompHelper.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::stomp::StompWireFormat**

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::stomp**

7.556 src/main/activemq/wireformat/stomp/StompWireFormatFactory File Reference

```
#include <activemq/util/Config.h>
#include <activemq/wireformat/WireFormatFactory.h>
#include <activemq/wireformat/stomp/StompWireFormat.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::stomp::StompWireFormatFactory**
Factory used to create the Stomp Wire Format instance.

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**
- namespace **activemq::wireformat::stomp**

7.557 src/main/activemq/wireformat/WireFormat.h File Reference

```
#include <activemq/wireformat/WireFormatNegotiator.h>
#include <decaf/io/DataInputStream.h>
#include <decaf/io/DataOutputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/Pointer.h>
#include <activemq/util/Config.h>
#include <activemq/commands/Command.h>
#include <activemq/transport/Transport.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
```

Data Structures

- class **activemq::wireformat::WireFormat**
*Provides a mechanism to marshal **commands** (p. 87) into and out of packets or into and out of streams, Channels and Datagrams.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**

7.558 src/main/activemq/wireformat/WireFormatFactory.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/wireformat/WireFormat.h>
#include <decaf/util/Properties.h>
#include <decaf/lang/Pointer.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
```

Data Structures

- class **activemq::wireformat::WireFormatFactory**

*The **WireFormatFactory** (p. 3980) is the interface that all **WireFormatFactory** (p. 3980) classes must extend.*

Namespaces

- namespace **activemq**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **activemq::wireformat**

7.559 src/main/activemq/wireformat/WireFormatNegotiator.h File Reference

```
#include <activemq/util/Config.h>
#include <activemq/transport/TransportFilter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **activemq::wireformat::WireFormatNegotiator**
*Defines a **WireFormatNegotiator** (p. 4016) which allows a **WireFormat** (p. 3976) to.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**

7.560 src/main/activemq/wireformat/WireFormatRegistry.h File Reference

```
#include <activemq/util/Config.h>
#include <string>
#include <vector>
#include <activemq/wireformat/WireFormatFactory.h>
#include <decaf/util/StlMap.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **activemq::wireformat::WireFormatRegistry**
*Registry of all **WireFormat** (p. 3976) Factories that are available to the client at runtime.*

Namespaces

- namespace **activemq**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **activemq::wireformat**

7.561 src/main/cms/BytesMessage.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <cms/MessageNotReadableException.h>
#include <cms/MessageNotWriteableException.h>
#include <cms/MessageEOFException.h>
#include <cms/MessageFormatException.h>
```

Data Structures

- class **cms::BytesMessage**

*A **BytesMessage** (p. 1056) object is used to send a message containing a stream of unsigned bytes.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.562 src/main/cms/Closeable.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Closeable**
Interface for a class that implements the close method.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.563 src/main/decaf/io/Closeable.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::Closeable**
Interface for a class that implements the close method.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.564 src/main/cms/CMSException.h File Reference

```
#include <string>
#include <vector>
#include <iostream>
#include <exception>
#include <cms/Config.h>
```

Data Structures

- class **cms::CMSException**

CMS API Exception that is the base for all exceptions thrown from CMS classes.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.565 src/main/cms/CMSProperties.h File Reference

```
#include <cms/Config.h>
#include <map>
#include <string>
#include <vector>
```

Data Structures

- class **cms::CMSProperties**
Interface for a Java-like properties object.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.566 src/main/cms/CMSSecurityException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::CMSSecurityException**

This exception must be thrown when a provider rejects a user name/password submitted by a client.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.567 src/main/cms/Connection.h File Reference

```
#include <cms/Config.h>
#include <cms/Startable.h>
#include <cms/Stopable.h>
#include <cms/Closeable.h>
#include <cms/Session.h>
#include <cms/ConnectionMetaData.h>
```

Data Structures

- class **cms::Connection**
The client's connection to its provider.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.568 src/main/cms/ConnectionFactory.h File Reference

```
#include <cms/Config.h>
#include <cms/Connection.h>
#include <cms/CMSException.h>
#include <string>
```

Data Structures

- class **cms::ConnectionFactory**

*Defines the interface for a factory that creates connection objects, the **Connection** (p. 1262) objects returned implement the **CMS Connection** (p. 1262) interface and hide the CMS Provider specific implementation details behind that interface.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.569 src/main/cms/ConnectionMetaData.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::ConnectionMetaData**

*A **ConnectionMetaData** (p. 1385) object provides information describing the **Connection** (p. 1262) object.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.570 src/main/cms/DeliveryMode.h File Reference

```
#include <cms/Config.h>
```

Data Structures

- class **cms::DeliveryMode**

This is an Abstract class whose purpose is to provide a container for the delivery mode enumeration for CMS messages.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.571 src/main/cms/Destination.h File Reference

```
#include <cms/CMSProperties.h>
#include <cms/Config.h>
#include <string>
```

Data Structures

- class **cms::Destination**

*A **Destination** (p. 1723) object encapsulates a provider-specific address.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.572 src/main/cms/ExceptionListener.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::ExceptionListener**

*If a CMS provider detects a serious problem, it notifies the client application through an **ExceptionListener** (p. 1838) that is registered with the **Connection** (p. 1262).*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.573 src/main/cms/IllegalStateException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::IllegalStateException**

This exception is thrown when a method is invoked at an illegal or inappropriate time or if the provider is not in an appropriate state for the requested operation.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.574 src/main/decaf/lang/exceptions/IllegalStateException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::IllegalStateException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.575 src/main/cms/InvalidClientIdException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::InvalidClientIdException**

This exception must be thrown when a client attempts to set a connection's client ID to a value that is rejected by a provider.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.576 src/main/cms/InvalidDestinationException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::InvalidDestinationException**

This exception must be thrown when a destination either is not understood by a provider or is no longer valid.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.577 src/main/cms/InvalidSelectorException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::InvalidSelectorException**

This exception must be thrown when a CMS client attempts to give a provider a message selector with invalid syntax.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.578 src/main/cms/MapMessage.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageNotWriteableException.h>
```

Data Structures

- class **cms::MapMessage**

*A **MapMessage** (p. 2472) object is used to send a set of name-value pairs.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.579 src/main/cms/MessageConsumer.h File Reference

```
#include <cms/Config.h>
#include <cms/MessageListener.h>
#include <cms/Message.h>
#include <cms/Closeable.h>
```

Data Structures

- class **cms::MessageConsumer**

A client uses a `MessageConsumer` (p. 2589) to received messages from a destination.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.580 src/main/cms/MessageEnumeration.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::MessageEnumeration**
Defines an object that enumerates a collection of Messages.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.581 src/main/cms/MessageEOFException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::MessageEOFException**

*This exception must be thrown when an unexpected end of stream has been reached when a **StreamMessage** (p. 3652) or **BytesMessage** (p. 1056) is being read.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.582 src/main/cms/MessageFormatException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::MessageFormatException**

This exception must be thrown when a CMS client attempts to use a data type not supported by a message or attempts to read data in a message as the wrong type.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.583 src/main/cms/MessageListener.h File Reference

```
#include <cms/Config.h>
```

Data Structures

- class **cms::MessageListener**

A `MessageListener` (p. 2692) object is used to receive asynchronously delivered messages.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.584 src/main/cms/MessageNotReadableException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::MessageNotReadableException**

This exception must be thrown when a CMS client attempts to read a write-only message.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.585 src/main/cms/MessageNotWriteableException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::MessageNotWriteableException**

This exception must be thrown when a CMS client attempts to write to a read-only message.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.586 src/main/cms/MessageProducer.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/Destination.h>
#include <cms/Closeable.h>
#include <cms/CMSException.h>
#include <cms/InvalidDestinationException.h>
#include <cms/MessageFormatException.h>
#include <cms/UnsupportedOperationException.h>
#include <cms/DeliveryMode.h>
```

Data Structures

- class **cms::MessageProducer**

*A client uses a **MessageProducer** (p. 2725) object to send messages to a **Destination** (p. 1723).*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.587 src/main/cms/ObjectMessage.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
```

Data Structures

- class **cms::ObjectMessage**

Place holder for interaction with JMS systems that support Java, the C++ client is not responsible for deserializing the contained Object.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.588 src/main/cms/Queue.h File Reference

```
#include <cms/Config.h>
#include <cms/Destination.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Queue**

An interface encapsulating a provider-specific queue name.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.589 src/main/decaf/util/Queue.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/AbstractCollection.h>
#include <decaf/lang/Exception.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::util::Queue< E >**
A kind of collection provides advanced operations than other basic collections, such as insertion, extraction, and inspection.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.590 src/main/cms/QueueBrowser.h File Reference

```
#include <string>
#include <cms/Config.h>
#include <cms/Closeable.h>
#include <cms/Queue.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <cms/MessageEnumeration.h>
```

Data Structures

- class **cms::QueueBrowser**

*This class implements in interface for browsing the messages in a **Queue** (p. 3148) without removing them.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.591 src/main/cms/Session.h File Reference

```
#include <cms/Config.h>
#include <cms/Closeable.h>
#include <cms/Message.h>
#include <cms/TextMessage.h>
#include <cms/BytesMessage.h>
#include <cms/MapMessage.h>
#include <cms/StreamMessage.h>
#include <cms/MessageProducer.h>
#include <cms/MessageConsumer.h>
#include <cms/Topic.h>
#include <cms/Queue.h>
#include <cms/QueueBrowser.h>
#include <cms/TemporaryTopic.h>
#include <cms/TemporaryQueue.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Session**

*A **Session** (p. 3365) object is a single-threaded context for producing and consuming messages.*

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.592 src/main/cms/Startable.h File Reference

```
#include <cms/Config.h>  
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Startable**
Interface for a class that implements the start method.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.593 src/main/cms/Stoppable.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Stoppable**
Interface for a class that implements the stop method.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.594 src/main/cms/StreamMessage.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <cms/MessageNotReadableException.h>
#include <cms/MessageNotWriteableException.h>
#include <cms/MessageFormatException.h>
#include <cms/MessageEOFException.h>
```

Data Structures

- class **cms::StreamMessage**
*Interface for a **StreamMessage** (p. 3652).*

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.595 src/main/cms/TemporaryQueue.h File Reference

```
#include <cms/Config.h>
#include <cms/Destination.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::TemporaryQueue**
*Defines a Temporary **Queue** (p. 3148) based **Destination** (p. 1723).*

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.596 src/main/cms/TemporaryTopic.h File Reference

```
#include <cms/Config.h>
#include <cms/Destination.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::TemporaryTopic**
*Defines a Temporary **Topic** (p. 3817) based **Destination** (p. 1723).*

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.597 src/main/cms/TextMessage.h File Reference

```
#include <cms/Config.h>
#include <cms/Message.h>
#include <cms/CMSException.h>
#include <cms/MessageNotWriteableException.h>
```

Data Structures

- class **cms::TextMessage**
Interface for a text message.

Namespaces

- namespace **cms**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.598 src/main/cms/Topic.h File Reference

```
#include <cms/Config.h>
#include <cms/Destination.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::Topic**

An interface encapsulating a provider-specific topic name.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.599 src/main/cms/UnsupportedOperationException.h File Reference

```
#include <cms/Config.h>
#include <cms/CMSException.h>
```

Data Structures

- class **cms::UnsupportedOperationException**

This exception must be thrown when a CMS client attempts use a CMS method that is not implemented or not supported by the CMS Provider in use.

Namespaces

- namespace **cms**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

7.600 src/main/decaf/lang/exceptions/UnsupportedOperationException File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::UnsupportedOperationException**

Namespaces

- namespace **decaf**
*Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.*
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.601 src/main/decaf/internal/AprPool.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <apr_pools.h>
```

Data Structures

- class **decaf::internal::AprPool**

*Wraps an APR pool object so that classes in **decaf** (p. 143) can create a static member for use in static methods where apr function calls that need a pool are made.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**

7.602 src/main/decaf/internal/DecafRuntime.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Runtime.h>
#include <apr_pools.h>
```

Data Structures

- class **decaf::internal::DecafRuntime**
Handles APR initialization and termination.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**

7.603 src/main/decaf/internal/io/StandardErrorOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/OutputStream.h>
```

Data Structures

- class **decaf::internal::io::StandardErrorOutputStream**
Wrapper Around the Standard error Output facility on the current platform.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::io**

7.604 src/main/decaf/internal/io/StandardInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/InputStream.h>
```

Data Structures

- class **decaf::internal::io::StandardInputStream**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::io**

7.605 src/main/decaf/internal/io/StandardOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/OutputStream.h>
```

Data Structures

- class **decaf::internal::io::StandardOutputStream**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::io**

7.606 src/main/decaf/internal/net/DefaultServerSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ServerSocketFactory.h>
```

Data Structures

- class **decaf::internal::net::DefaultServerSocketFactory**
Default implementation of the Decaf ServerSocketFactory, creates ServerSocket objects with supplied options.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.607 src/main/decaf/internal/net/DefaultSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketFactory.h>
```

Data Structures

- class **decaf::internal::net::DefaultSocketFactory**
SocketFactory implementation that is used to create Sockets.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.608 src/main/decaf/internal/net/Network.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/internal/util/Resource.h>
#include <decaf/internal/util/GenericResource.h>
```

Data Structures

- class **decaf::internal::net::Network**

Internal class used to manage Networking related resources and hide platform dependent calls from the higher level API.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.609 src/main/decaf/internal/net/SocketFileDescriptor.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/FileDescriptor.h>
```

Data Structures

- class **decaf::internal::net::SocketFileDescriptor**
File Descriptor type used internally by Decaf Socket objects.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.610 src/main/decaf/internal/net/ssl/DefaultSSLContext.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLContext.h>
```

Data Structures

- class **decaf::internal::net::ssl::DefaultSSLContext**
Default SSL Context manager for the Decaf library.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**

7.611 src/main/decaf/internal/net/ssl/DefaultSSLServerSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLServerSocketFactory.h>
```

Data Structures

- class **decaf::internal::net::ssl::DefaultSSLServerSocketFactory**
Default implementation of the SSLServerSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**

7.612 src/main/decaf/internal/net/ssl/DefaultSSLSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLSocketFactory.h>
#include <string>
#include <vector>
```

Data Structures

- class **decaf::internal::net::ssl::DefaultSSLSocketFactory**

Default implementation of the SSLSocketFactory, this factory throws an Exception from all its create methods to indicate that SSL is not supported, this factory is used when OpenSSL is not enabled in the builds.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**

7.613 src/main/decaf/internal/net/ssl/openssl/OpenSSLContextSpi.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLContextSpi.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLContextSpi**
Provides an SSLContext that wraps the OpenSSL API.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.614 src/main/decaf/internal/net/ssl/openssl/OpenSSLParameters.h File Reference

```
#include <decaf/util/Config.h>
#include <string>
#include <vector>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLParameters**
Container class for parameters that are Common to OpenSSL socket classes.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.615 src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocket.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLServerSocket.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLServerSocket**
SSLServerSocket based on OpenSSL library code (p. 1183).

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.616 src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLServerSocketFactory.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory**
SSLServerSocketFactory that creates Server Sockets that use OpenSSL.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.617 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocket.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLSocket.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLSocket**

Wraps a a Normal Socket object and extends or overrides functions in that class to make use of the OpenSSL Socket API.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.618 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketException.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLSocketException**
Subclass of the standard SocketException that knows how to produce an error message from the OpenSSL error stack.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.619 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLSocketFactory.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLSocketFactory**
Client Socket Factory that creates SSL based client sockets using the OpenSSL library.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.620 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketInputStream.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/io/InputStream.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream**
An output stream for reading data from an OpenSSL Socket instance.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.621 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketOutputStream File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/OutputStream.h>
```

Data Structures

- class **decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream**
*OutputStream implementation used to write data to an **OpenSSLSocket** (p. 2858) instance.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::ssl**
- namespace **decaf::internal::net::ssl::openssl**

7.622 src/main/decaf/internal/net/tcp/TcpSocket.h File Reference

```
#include <decaf/net/SocketException.h>
#include <decaf/net/SocketImpl.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
#include <decaf/util/Config.h>
#include <decaf/internal/AprPool.h>
#include <apr_network_io.h>
#include <decaf/io/IOException.h>
#include <decaf/net/SocketTimeoutException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::internal::net::tcp::TcpSocket**
Platform-independent implementation of the socket interface.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::tcp**

7.623 src/main/decaf/internal/net/tcp/TcpSocketInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::internal::net::tcp::TcpSocketInputStream**

Input stream for performing reads on a socket.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::tcp**

7.624 src/main/decaf/internal/net/tcp/TcpSocketOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/OutputStream.h>
```

Data Structures

- class **decaf::internal::net::tcp::TcpSocketOutputStream**
Output stream for performing write operations on a socket.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**
- namespace **decaf::internal::net::tcp**

7.625 src/main/decaf/internal/net/URLEncoderDecoder.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/URISyntaxException.h>
#include <string>
```

Data Structures

- class **decaf::internal::net::URLEncoderDecoder**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.626 src/main/decaf/internal/net/URIHelper.h File Reference

```
#include <string>
#include <decaf/util/Config.h>
#include <decaf/net/URISyntaxException.h>
#include <decaf/internal/net/URIType.h>
```

Data Structures

- class **decaf::internal::net::URIHelper**
Helper class used by the URI classes in encoding and decoding of URI's.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.627 src/main/decaf/internal/net/URIType.h File Reference

```
#include <string>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::internal::net::URIType**
Basic type object that holds data that composes a given URI.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::net**

7.628 src/main/decaf/internal/nio/BufferFactory.h File Reference

```
#include <decaf/nio/ByteBuffer.h>
#include <decaf/nio/CharBuffer.h>
#include <decaf/nio/DoubleBuffer.h>
#include <decaf/nio/FloatBuffer.h>
#include <decaf/nio/LongBuffer.h>
#include <decaf/nio/IntBuffer.h>
#include <decaf/nio/ShortBuffer.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::internal::nio::BufferFactory**

*Factory class used by static methods in the **decaf::nio** (p. 163) package to create the various default version of the NIO interfaces.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.629 src/main/decaf/internal/nio/ByteBuffer.h File Reference

```
#include <decaf/nio/ByteBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/nio/CharBuffer.h>
#include <decaf/nio/DoubleBuffer.h>
#include <decaf/nio/FloatBuffer.h>
#include <decaf/nio/ShortBuffer.h>
#include <decaf/nio/IntBuffer.h>
#include <decaf/nio/LongBuffer.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::ByteBuffer**

This class defines six categories of operations upon byte buffers..

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.630 src/main/decaf/internal/nio/CharArrayBuffer.h File Reference

```
#include <decaf/nio/CharBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::CharArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.631 src/main/decaf/internal/nio/DoubleArrayBuffer.h File Reference

```
#include <decaf/nio/DoubleBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::DoubleArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.632 src/main/decaf/internal/nio/FloatArrayBuffer.h File Reference

```
#include <decaf/nio/FloatBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::FloatArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.633 src/main/decaf/internal/nio/IntArrayBuffer.h File Reference

```
#include <decaf/nio/IntBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::IntArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.634 src/main/decaf/internal/nio/LongArrayBuffer.h File Reference

```
#include <decaf/nio/LongBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::LongArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.635 src/main/decaf/internal/nio/ShortArrayBuffer.h File Reference

```
#include <decaf/nio/ShortBuffer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/internal/util/ByteArrayAdapter.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::nio::ShortArrayBuffer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::nio**

7.636 src/main/decaf/internal/security/unix/SecureRandomImpl.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/SecureRandomSpi.h>
```

Data Structures

- class **decaf::internal::security::SecureRandomImpl**
Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::security**

7.637 src/main/decaf/internal/security/windows/SecureRandomImpl.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/SecureRandomSpi.h>
```

Data Structures

- class **decaf::internal::security::SecureRandomImpl**
Secure Random Number Generator for Unix based platforms that attempts to obtain secure bytes with high entropy from known sources.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::security**

7.638 src/main/decaf/internal/util/ByteArrayAdapter.h File Reference

```
#include <decaf/lang/exceptions/InvalidStateException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
```

Data Structures

- class **decaf::internal::util::ByteArrayAdapter**
This class adapts primitive type arrays to a base byte array so that the classes can inter-operate on the same base byte array without copying data.
- union **decaf::internal::util::ByteArrayAdapter::Array**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.639 src/main/decaf/internal/util/concurrent/ConditionImpl.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::internal::util::concurrent::ConditionImpl**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.640 src/main/decaf/internal/util/concurrent/MutexImpl.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::internal::util::concurrent::MutexImpl**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.641 src/main/decaf/internal/util/concurrent/SynchronizableImpl.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **decaf::internal::util::concurrent::SynchronizableImpl**

A convenience class used by some Decaf classes to implement the Synchronizable interface when there is no issues related to multiple inheritance.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.642 src/main/decaf/internal/util/concurrent/Transferer.h File Reference

```
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/util/concurrent/TimeoutException.h>
```

Data Structures

- class **decaf::internal::util::concurrent::Transferer< E >**
*Shared **internal** (p. 144) API for dual stacks and queues.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.643 src/main/decaf/internal/util/concurrent/TransferQueue.h File Reference

```
#include <decaf/internal/util/concurrent/Transferer.h>
#include <decaf/util/concurrent/locks/LockSupport.h>
#include <decaf/util/concurrent/atomic/AtomicReference.h>
#include <decaf/util/concurrent/TimeoutException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/Thread.h>
```

Data Structures

- class **decaf::internal::util::concurrent::TransferQueue< E >**

This extends Scherer-Scott dual queue algorithm, differing, among other ways, by using modes within nodes rather than marked pointers.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.644 src/main/decaf/internal/util/concurrent/TransferStack.h File Reference

```
#include <decaf/internal/util/concurrent/Transferer.h>
#include <decaf/util/concurrent/TimeoutException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
```

Data Structures

- class **decaf::internal::util::concurrent::TransferStack< E >**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::internal::util::concurrent**

7.645 src/main/decaf/internal/util/concurrent/unix/ConditionHandle.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::ConditionHandle**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.646 src/main/decaf/internal/util/concurrent/windows/ConditionHandle.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::ConditionHandle**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.647 src/main/decaf/internal/util/concurrent/unix/MutexHandle.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::MutexHandle**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.648 src/main/decaf/internal/util/concurrent/windows/MutexHandle. File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::MutexHandle**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.649 src/main/decaf/internal/util/GenericResource.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/internal/util/Resource.h>
```

Data Structures

- class **decaf::internal::util::GenericResource**< **T** >
*A Generic **Resource** (p. 3280) wraps some type and will delete it when the **Resource** (p. 3280) itself is deleted.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.650 src/main/decaf/internal/util/HexStringParser.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <string>
```

Data Structures

- class **decaf::internal::util::HexStringParser**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.651 src/main/decaf/internal/util/Resource.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::internal::util::Resource**

Interface for all Managed Resources in Decaf, these objects are added to the Runtime System and are destroyed at shutdown.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.652 src/main/decaf/internal/util/TimerTaskHeap.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/TimerTask.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::internal::util::TimerTaskHeap**

A Binary Heap implemented specifically for the Timer class in Decaf Util.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**

7.653 src/main/decaf/internal/util/zip/crc32.h File Reference

Variables

- local const unsigned long FAR `crc_table` [TBLS][256]

7.653.1 Variable Documentation

7.653.1.1 local const unsigned long FAR `crc_table`[TBLS][256]

7.654 src/main/decaf/internal/util/zip/deflate.h File Reference

```
#include "zutil.h"
```

Data Structures

- struct **ct_data_s**
- struct **tree_desc_s**
- struct **internal_state**

Defines

- #define **GZIP**
- #define **LENGTH_CODES** 29
- #define **LITERALS** 256
- #define **L_CODES** (LITERALS+1+LENGTH_CODES)
- #define **D_CODES** 30
- #define **BL_CODES** 19
- #define **HEAP_SIZE** (2*L_CODES+1)
- #define **MAX_BITS** 15
- #define **INIT_STATE** 42
- #define **EXTRA_STATE** 69
- #define **NAME_STATE** 73
- #define **COMMENT_STATE** 91
- #define **HCRC_STATE** 103
- #define **BUSY_STATE** 113
- #define **FINISH_STATE** 666
- #define **Freq** fc.freq
- #define **Code** fc.code
- #define **Dad** dl.dad
- #define **Len** dl.len
- #define **max_insert_length** max_lazy_match
- #define **put_byte**(s, c) {s->pending_buf[s->pending++] = (c);}
- #define **MIN_LOOKAHEAD** (MAX_MATCH+MIN_MATCH+1)
- #define **MAX_DIST**(s) ((s)->w_size-MIN_LOOKAHEAD)
- #define **WIN_INIT** MAX_MATCH
- #define **d_code**(dist) ((dist) < 256 ? __dist_code[dist] : __dist_code[256+((dist)>>7)])
- #define **_tr_tally_lit**(s, c, flush)
- #define **_tr_tally_dist**(s, distance, length, flush)

Typedefs

- typedef struct **ct_data_s** **ct_data**
- typedef struct static_tree_desc_s **static_tree_desc**
- typedef struct **tree_desc_s** **tree_desc**
- typedef **ush** **Pos**
- typedef **Pos** FAR **Posf**
- typedef unsigned **IPos**
- typedef struct **internal_state** **deflate_state**

Functions

- void ZLIB_INTERNAL _tr_init **OF** ((deflate_state *s))
- int ZLIB_INTERNAL _tr_tally **OF** ((deflate_state *s, unsigned dist, unsigned lc))
- void ZLIB_INTERNAL _tr_flush_block **OF** ((deflate_state *s, charf *buf, ulg stored_len, int last))

Variables

- uch ZLIB_INTERNAL _length_code []
- uch ZLIB_INTERNAL _dist_code []

7.654.1 Define Documentation

7.654.1.1 #define _tr_tally_dist(s, distance, length, flush)

Value:

```
{ uch len = (length); \
  ush dist = (distance); \
  s->d_buf[s->last_lit] = dist; \
  s->l_buf[s->last_lit++] = len; \
  dist--; \
  s->dyn_ltree[_length_code[len]+LITERALS+1].Freq++; \
  s->dyn_dtree[d_code(dist)].Freq++; \
  flush = (s->last_lit == s->lit_bufsize-1); \
}
```

7.654.1.2 #define _tr_tally_lit(s, c, flush)

Value:

```
{ uch cc = (c); \
  s->d_buf[s->last_lit] = 0; \
  s->l_buf[s->last_lit++] = cc; \
  s->dyn_ltree[cc].Freq++; \
  flush = (s->last_lit == s->lit_bufsize-1); \
}
```


- 7.654.1.3 `#define BL_CODES 19`
- 7.654.1.4 `#define BUSY_STATE 113`
- 7.654.1.5 `#define Code fc.code`
- 7.654.1.6 `#define COMMENT_STATE 91`
- 7.654.1.7 `#define d_code(dist) ((dist) < 256 ? _dist_code[dist] :
_dist_code[256+((dist)>>7)])`
- 7.654.1.8 `#define D_CODES 30`
- 7.654.1.9 `#define Dad dl.dad`
- 7.654.1.10 `#define EXTRA_STATE 69`
- 7.654.1.11 `#define FINISH_STATE 666`
- 7.654.1.12 `#define Freq fc.freq`
- 7.654.1.13 `#define GZIP`
- 7.654.1.14 `#define HCRC_STATE 103`
- 7.654.1.15 `#define HEAP_SIZE (2*L_CODES+1)`
- 7.654.1.16 `#define INIT_STATE 42`
- 7.654.1.17 `#define L_CODES (LITERALS+1+LENGTH_CODES)`
- 7.654.1.18 `#define Len dl.len`
- 7.654.1.19 `#define LENGTH_CODES 29`
- 7.654.1.20 `#define LITERALS 256`
- 7.654.1.21 `#define MAX_BITS 15`
- 7.654.1.22 `#define MAX_DIST(s) ((s)->w_size-MIN_LOOKAHEAD)`
- 7.654.1.23 `#define max_insert_length max_lazy_match`
- 7.654.1.24 `#define MIN_LOOKAHEAD (MAX_MATCH+MIN_MATCH+1)`
- 7.654.1.25 `#define NAME_STATE 73`
- 7.654.1.26 `#define put_byte(s, c) {s->pending_buf[s->pending++] = (c);}`
- 7.654.1.27 `#define WIN_INIT MAX_MATCH`

7.654.2 Typedef Documentation

7.654.2.1 `typedef struct ct_data_s ct_data`

Generated on Wed Nov 10 22:25:45 2010 for activemq-omp-3.2.3 by Doxygen

7.654.2.2 `typedef struct internal_state deflate_state`

7.654.2.3 `typedef unsigned IPos`

7.654.2.4 `typedef ush Pos`

7.654.2.5 `typedef struct FAR DeflParams`

7.655 src/main/decaf/internal/util/zip/gzguts.h File Reference

```
#include <stdio.h>
#include "zlib.h"
#include <fcntl.h>
```

Data Structures

- struct **gz_state**

Defines

- #define **ZLIB_INTERNAL**
- #define **local** static
- #define **zstrerror()** "stdio error (consult errno)"
- #define **GZBUFSIZE** 8192
- #define **GZ_NONE** 0
- #define **GZ_READ** 7247
- #define **GZ_WRITE** 31153
- #define **GZ_APPEND** 1
- #define **LOOK** 0
- #define **COPY** 1
- #define **GZIP** 2
- #define **GT_OFF(x)** (sizeof(int) == sizeof(z_off64_t) && (x) > gz_intmax())

Typedefs

- typedef **gz_state FAR * gz_statep**

Functions

- **voidp** malloc **OF** ((**uInt** size))
- void free **OF** ((**voidpf** ptr))
- ZEXTERN **gzFile** ZEXPORT gzopen64 **OF** ((const char *, const char *))
- ZEXTERN z_off64_t ZEXPORT gzseek64 **OF** ((**gzFile**, z_off64_t, int))
- ZEXTERN z_off64_t ZEXPORT gtell64 **OF** ((**gzFile**))
- void ZLIB_INTERNAL gz_error **OF** ((**gz_statep**, int, const char *))
- unsigned ZLIB_INTERNAL gz_intmax **OF** ((void))

7.655.1 Define Documentation

7.655.1.1 `#define COPY 1`

7.655.1.2 `#define GT_OFF(x) (sizeof(int) == sizeof(z_off64_t) && (x) > gz_intmax())`

7.655.1.3 `#define GZ_APPEND 1`

7.655.1.4 `#define GZ_NONE 0`

7.655.1.5 `#define GZ_READ 7247`

7.655.1.6 `#define GZ_WRITE 31153`

7.655.1.7 `#define GZBUFSIZE 8192`

7.655.1.8 `#define GZIP 2`

7.655.1.9 `#define local static`

7.655.1.10 `#define LOOK 0`

7.655.1.11 `#define ZLIB_INTERNAL`

7.655.1.12 `#define zstrerror() "stdio error (consult errno)"`

7.655.2 Typedef Documentation

7.655.2.1 `typedef gz_state FAR* gz_statep`

7.655.3 Function Documentation

7.655.3.1 `unsigned ZLIB_INTERNAL gz_intmax OF ((void))`

7.655.3.2 `void ZLIB_INTERNAL gz_error OF ((gz_statep, int, const char *))`

7.655.3.3 `ZEXTERN z_off64_t ZEXPORT gztell64 OF ((gzFile))`

7.655.3.4 `ZEXTERN z_off64_t ZEXPORT gzseek64 OF ((gzFile, z_off64_t, int))`

7.655.3.5 `ZEXTERN gzFile ZEXPORT gzopen64 OF ((const char *, const char *))`

7.655.3.6 `void free OF ((voidpf ptr))`

7.655.3.7 `voidp malloc OF ((uInt size))`

7.656 src/main/decaf/internal/util/zip/inffast.h File Reference

Functions

- void ZLIB_INTERNAL inflate_fast OF ((z_stream strm, unsigned start))

7.656.1 Function Documentation

- 7.656.1.1 void ZLIB_INTERNAL inflate_fast OF ((z_stream strm, unsigned start))

7.657 src/main/decaf/internal/util/zip/inffixed.h File Reference

7.658 src/main/decaf/internal/util/zip/inflate.h File Reference

Data Structures

- struct `inflate_state`

Defines

- `#define GUNZIP`

Enumerations

- enum `inflate_mode` {
 HEAD, **FLAGS**, **TIME**, **OS**,
 EXLEN, **EXTRA**, **NAME**, **COMMENT**,
 HCRC, **DICTID**, **DICT**, **TYPE**,
 TYPEDO, **STORED**, **COPY_**, **COPY**,
 TABLE, **LENLENS**, **CODELENS**, **LEN_**,
 LEN, **LENEXT**, **DIST**, **DISTEXT**,
 MATCH, **LIT**, **CHECK**, **LENGTH**,
 DONE, **BAD**, **MEM**, **SYNC** }

7.658.1 Define Documentation

7.658.1.1 `#define GUNZIP`

7.658.2 Enumeration Type Documentation

7.658.2.1 enum `inflate_mode`

Enumerator:

HEAD
FLAGS
TIME
OS
EXLEN
EXTRA
NAME
COMMENT
HCRC
DICTID
DICT
TYPE

TYPEDO
STORED
COPY_
COPY
TABLE
LENLENS
CODELENS
LEN_
LEN
LENEXT
DIST
DISTEXT
MATCH
LIT
CHECK
LENGTH
DONE
BAD
MEM
SYNC

7.659 src/main/decaf/internal/util/zip/inftrees.h File Reference

Data Structures

- struct **code**

Defines

- `#define ENOUGH_LENS 852`
- `#define ENOUGH_DISTS 592`
- `#define ENOUGH (ENOUGH_LENS+ENOUGH_DISTS)`

Enumerations

- enum **codetype** { **CODES**, **LENS**, **DISTS** }

Functions

- int ZLIB_INTERNAL inflate_table OF ((**codetype** type, unsigned short FAR *lens, unsigned codes, **code** FAR *FAR *table, unsigned FAR *bits, unsigned short FAR *work))

7.659.1 Define Documentation

7.659.1.1 `#define ENOUGH (ENOUGH_LENS+ENOUGH_DISTS)`

7.659.1.2 `#define ENOUGH_DISTS 592`

7.659.1.3 `#define ENOUGH_LENS 852`

7.659.2 Enumeration Type Documentation

7.659.2.1 enum **codetype**

Enumerator:

CODES

LENS

DISTS

7.659.3 Function Documentation

7.659.3.1 int ZLIB_INTERNAL inflate_table OF ((**codetype** type, unsigned short FAR *lens, unsigned codes, **code** FAR *FAR *table, unsigned FAR *bits, unsigned short FAR *work))


```

21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 21, 22, 22, 22, 22,
22, 22, 22, 22, 22, 22, 22, 22, 22, 22, 22, 23, 23, 23, 23, 23, 23, 23, 23,
23, 23, 23, 23, 23, 23, 23, 23, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24,
24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24, 24,
25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25,
25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 25, 26, 26, 26, 26, 26, 26, 26, 26,
26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26, 26,
26, 26, 26, 26, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27,
27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 27, 28
}

```

7.660.1.3 local const int base__dist[D_CODES]

Initial value:

```

{
    0,      1,      2,      3,      4,      6,      8,      12,     16,     24,
   32,     48,     64,     96,    128,    192,    256,    384,    512,    768,
  1024,  1536,  2048,  3072,  4096,  6144,  8192, 12288, 16384, 24576
}

```

7.660.1.4 local const int base__length[LENGTH_CODES]

Initial value:

```

{
0, 1, 2, 3, 4, 5, 6, 7, 8, 10, 12, 14, 16, 20, 24, 28, 32, 40, 48, 56,
64, 80, 96, 112, 128, 160, 192, 224, 0
}

```

7.660.1.5 local const ct__data static __dtree[D_CODES]

Initial value:

```

{
{{ 0},{ 5}}, {{16},{ 5}}, {{ 8},{ 5}}, {{24},{ 5}}, {{ 4},{ 5}},
{{20},{ 5}}, {{12},{ 5}}, {{28},{ 5}}, {{ 2},{ 5}}, {{18},{ 5}},
{{10},{ 5}}, {{26},{ 5}}, {{ 6},{ 5}}, {{22},{ 5}}, {{14},{ 5}},
{{30},{ 5}}, {{ 1},{ 5}}, {{17},{ 5}}, {{ 9},{ 5}}, {{25},{ 5}},
{{ 5},{ 5}}, {{21},{ 5}}, {{13},{ 5}}, {{29},{ 5}}, {{ 3},{ 5}},
{{19},{ 5}}, {{11},{ 5}}, {{27},{ 5}}, {{ 7},{ 5}}, {{23},{ 5}}
}

```

7.660.1.6 local const ct__data static __ltree[L_CODES+2]

7.661 src/main/decaf/internal/util/zip/zconf.h File Reference

```
#include <decaf/util/Config.h>
```

Defines

- `#define const`
- `#define MAX__MEM__LEVEL 9`
- `#define MAX__WBITS 15`
- `#define OF(args) ()`
- `#define ZEXTERN extern`
- `#define SEEK__SET 0`
- `#define SEEK__CUR 1`
- `#define SEEK__END 2`
- `#define z__off__t long`
- `#define z__off64__t z__off__t`

Typedefs

- `typedef unsigned char Byte`
- `typedef unsigned int uInt`
- `typedef unsigned long uLong`
- `typedef Byte FAR Bytef`
- `typedef char FAR charf`
- `typedef int FAR intf`
- `typedef uInt FAR uIntf`
- `typedef uLong FAR uLongf`
- `typedef Byte const * voidpc`
- `typedef Byte FAR * voidpf`
- `typedef Byte * voidp`

7.661.1 Define Documentation

- 7.661.1.1 `#define const`
- 7.661.1.2 `#define MAX__MEM__LEVEL 9`
- 7.661.1.3 `#define MAX__WBITS 15`
- 7.661.1.4 `#define OF(args) ()`
- 7.661.1.5 `#define SEEK__CUR 1`
- 7.661.1.6 `#define SEEK__END 2`
- 7.661.1.7 `#define SEEK__SET 0`
- 7.661.1.8 `#define z__off64__t z__off__t`
- 7.661.1.9 `#define z__off__t long`
- 7.661.1.10 `#define ZEXTERN extern`

7.661.2 Typedef Documentation

- 7.661.2.1 `typedef unsigned char Byte`
- 7.661.2.2 `typedef Byte FAR Bytef`
- 7.661.2.3 `typedef char FAR charf`
- 7.661.2.4 `typedef int FAR intf`
- 7.661.2.5 `typedef unsigned int uInt`
- 7.661.2.6 `typedef uInt FAR uIntf`
- 7.661.2.7 `typedef unsigned long uLong`
- 7.661.2.8 `typedef uLong FAR uLongf`
- 7.661.2.9 `typedef Byte* voidp`
- 7.661.2.10 `typedef Byte const* voidpc`
- 7.661.2.11 `typedef Byte FAR* voidpf`

7.662 src/main/decaf/internal/util/zip/zlib.h File Reference

```
#include "zconf.h"
```

Data Structures

- struct `z_stream_s`
- struct `gz_header_s`
- struct `internal_state`

Defines

- `#define ZLIB_VERSION "1.2.5"`
- `#define ZLIB_VERNUM 0x1250`
- `#define ZLIB_VER_MAJOR 1`
- `#define ZLIB_VER_MINOR 2`
- `#define ZLIB_VER_REVISION 5`
- `#define ZLIB_VER_SUBREVISION 0`
- `#define Z_NO_FLUSH 0`
- `#define Z_PARTIAL_FLUSH 1`
- `#define Z_SYNC_FLUSH 2`
- `#define Z_FULL_FLUSH 3`
- `#define Z_FINISH 4`
- `#define Z_BLOCK 5`
- `#define Z_TREES 6`
- `#define Z_OK 0`
- `#define Z_STREAM_END 1`
- `#define Z_NEED_DICT 2`
- `#define Z_ERRNO (-1)`
- `#define Z_STREAM_ERROR (-2)`
- `#define Z_DATA_ERROR (-3)`
- `#define Z_MEM_ERROR (-4)`
- `#define Z_BUF_ERROR (-5)`
- `#define Z_VERSION_ERROR (-6)`
- `#define Z_NO_COMPRESSION 0`
- `#define Z_BEST_SPEED 1`
- `#define Z_BEST_COMPRESSION 9`
- `#define Z_DEFAULT_COMPRESSION (-1)`
- `#define Z_FILTERED 1`
- `#define Z_HUFFMAN_ONLY 2`
- `#define Z_RLE 3`
- `#define Z_FIXED 4`
- `#define Z_DEFAULT_STRATEGY 0`
- `#define Z_BINARY 0`
- `#define Z_TEXT 1`
- `#define Z_ASCII Z_TEXT`
- `#define Z_UNKNOWN 2`
- `#define Z_DEFLATED 8`

- `#define Z_NULL 0`
- `#define zlib_version zlibVersion()`
- `#define deflateInit(strm, level) deflateInit_((strm), (level), ZLIB_VERSION, sizeof(z_stream))`
- `#define inflateInit(strm) inflateInit_((strm), ZLIB_VERSION, sizeof(z_stream))`
- `#define deflateInit2(strm, level, method, windowBits, memLevel, strategy)`
- `#define inflateInit2(strm, windowBits) inflateInit2_((strm), (windowBits), ZLIB_VERSION, sizeof(z_stream))`
- `#define inflateBackInit(strm, windowBits, window)`

Typedefs

- `typedef voidpf alloc_func OF ((voidpf opaque, uInt items, uInt size))`
- `typedef struct z_stream_s z_stream`
- `typedef z_stream FAR * z_streamp`
- `typedef struct gz_header_s gz_header`
- `typedef gz_header FAR * gz_headerp`
- `typedef voidp gzFile`

Functions

- `ZEXTERN const char *ZEXPORT zlibVersion OF ((void))`
- `ZEXTERN int ZEXPORT deflate OF ((z_streamp strm, int flush))`
- `ZEXTERN int ZEXPORT deflateEnd OF ((z_streamp strm))`
- `ZEXTERN int ZEXPORT deflateSetDictionary OF ((z_streamp strm, const Bytef *dictionary, uIntdictLength))`
- `ZEXTERN int ZEXPORT deflateCopy OF ((z_streamp dest, z_streamp source))`
- `ZEXTERN int ZEXPORT deflateParams OF ((z_streamp strm, int level, int strategy))`
- `ZEXTERN int ZEXPORT deflateTune OF ((z_streamp strm, int good_length, int max_lazy, int nice_length, int max_chain))`
- `ZEXTERN uLong ZEXPORT deflateBound OF ((z_streamp strm, uLong sourceLen))`
- `ZEXTERN int ZEXPORT deflatePrime OF ((z_streamp strm, int bits, int value))`
- `ZEXTERN int ZEXPORT deflateSetHeader OF ((z_streamp strm, gz_headerp head))`
- `ZEXTERN int ZEXPORT inflateReset2 OF ((z_streamp strm, int windowBits))`
- `ZEXTERN int ZEXPORT inflateBack OF ((z_streamp strm, in_func in, void FAR *in_desc, out_func out, void FAR *out_desc))`
- `ZEXTERN int ZEXPORT compress OF ((Bytef *dest, uLongf *destLen, const Bytef *source, uLong sourceLen))`
- `ZEXTERN int ZEXPORT compress2 OF ((Bytef *dest, uLongf *destLen, const Bytef *source, uLong sourceLen, int level))`
- `ZEXTERN uLong ZEXPORT compressBound OF ((uLong sourceLen))`
- `ZEXTERN gzFile ZEXPORT gzdopen OF ((int fd, const char *mode))`
- `ZEXTERN int ZEXPORT gzbuffer OF ((gzFile file, unsigned size))`
- `ZEXTERN int ZEXPORT gzsetparams OF ((gzFile file, int level, int strategy))`
- `ZEXTERN int ZEXPORT gzread OF ((gzFile file, voidp buf, unsigned len))`
- `ZEXTERN int ZEXPORT gzwrite OF ((gzFile file, voidpc buf, unsigned len))`
- `ZEXTERN int ZEXPORTVA gzprintf OF ((gzFile file, const char *format,...))`
- `ZEXTERN int ZEXPORT gzputs OF ((gzFile file, const char *s))`
- `ZEXTERN char *ZEXPORT gzgets OF ((gzFile file, char *buf, int len))`
- `ZEXTERN int ZEXPORT gzputc OF ((gzFile file, int c))`

- ZEXTERN int ZEXPORT gzgetc **OF** ((**gzFile** file))
- ZEXTERN int ZEXPORT gzungetc **OF** ((int c, **gzFile** file))
- ZEXTERN int ZEXPORT gzflush **OF** ((**gzFile** file, int flush))
- ZEXTERN const char *ZEXPORT gzerror **OF** ((**gzFile** file, int *errnum))
- ZEXTERN **uLong** ZEXPORT Adler32 **OF** ((**uLong** Adler, const **Bytef** *buf, **uInt** len))
- ZEXTERN **uLong** ZEXPORT Crc32 **OF** ((**uLong** Crc, const **Bytef** *buf, **uInt** len))
- ZEXTERN int ZEXPORT deflateInit_ **OF** ((**z_stream** strm, int level, const char *version, int stream_size))
- ZEXTERN int ZEXPORT inflateInit_ **OF** ((**z_stream** strm, const char *version, int stream_size))
- ZEXTERN int ZEXPORT deflateInit2_ **OF** ((**z_stream** strm, intlevel, intmethod, int windowBits, int memLevel, int strategy, const char *version, int stream_size))
- ZEXTERN int ZEXPORT inflateInit2_ **OF** ((**z_stream** strm, intwindowBits, const char *version, int stream_size))
- ZEXTERN int ZEXPORT inflateBackInit_ **OF** ((**z_stream** strm, int windowBits, unsigned char FAR *window, const char *version, int stream_size))
- ZEXTERN **gzFile** ZEXPORT gzopen **OF** ((const char *, const char *))
- ZEXTERN **z_off_t** ZEXPORT gzseek **OF** ((**gzFile**, **z_off_t**, int))
- ZEXTERN **z_off_t** ZEXPORT gztell **OF** ((**gzFile**))
- ZEXTERN **uLong** ZEXPORT Adler32_combine **OF** ((**uLong**, **uLong**, **z_off_t**))
- ZEXTERN const char *ZEXPORT zError **OF** ((int))
- ZEXTERN int ZEXPORT inflateSyncPoint **OF** ((**z_stream**))
- ZEXTERN int ZEXPORT inflateUndermine **OF** ((**z_stream**, int))

7.662.1 Define Documentation

7.662.1.1 `#define deflateInit(strm, level) deflateInit_((strm), (level),
ZLIB_VERSION, sizeof(z_stream))`

7.662.1.2 `#define deflateInit2(strm, level, method, windowBits, memLevel,
strategy)`

Value:

```
deflateInit2_((strm), (level), (method), (windowBits), (memLevel), \
              (strategy), ZLIB_VERSION, sizeof(z_stream))
```

7.662.1.3 `#define inflateBackInit(strm, windowBits, window)`

Value:

```
inflateBackInit_((strm), (windowBits), (window), \
                  ZLIB_VERSION, sizeof(z_stream))
```

7.662.1.4 `#define inflateInit(strm) inflateInit_((strm), ZLIB_VERSION, sizeof(z_stream))`

7.662.1.5 `#define inflateInit2(strm, windowBits) inflateInit2_((strm), (windowBits), ZLIB_VERSION, sizeof(z_stream))`

7.662.1.6 `#define Z_ASCII Z_TEXT`

7.662.1.7 `#define Z_BEST_COMPRESSION 9`

7.662.1.8 `#define Z_BEST_SPEED 1`

7.662.1.9 `#define Z_BINARY 0`

7.662.1.10 `#define Z_BLOCK 5`

7.662.1.11 `#define Z_BUF_ERROR (-5)`

7.662.1.12 `#define Z_DATA_ERROR (-3)`

7.662.1.13 `#define Z_DEFAULT_COMPRESSION (-1)`

7.662.1.14 `#define Z_DEFAULT_STRATEGY 0`

7.662.1.15 `#define Z_DEFLATED 8`

7.662.1.16 `#define Z_ERRNO (-1)`

7.662.1.17 `#define Z_FILTERED 1`

7.662.1.18 `#define Z_FINISH 4`

7.662.1.19 `#define Z_FIXED 4`

7.662.1.20 `#define Z_FULL_FLUSH 3`

7.662.1.21 `#define Z_HUFFMAN_ONLY 2`

7.662.1.22 `#define Z_MEM_ERROR (-4)`

7.662.1.23 `#define Z_NEED_DICT 2`

7.662.1.24 `#define Z_NO_COMPRESSION 0`

7.662.1.25 `#define Z_NO_FLUSH 0`

7.662.1.26 `#define Z_NULL 0`

7.662.1.27 `#define Z_OK 0`

7.662.1.28 `#define Z_PARTIAL_FLUSH 1`

7.662.1.29 `#define Z_RLE 3`

7.662.1.30 `#define Z_STREAM_END 1`

7.662.1.31 `#define Z_STREAM_ERROR (-2)`

7.662.1.32 `#define Z_SYNC_FLUSH 2`

7.662.1.33 `#define Z_TEXT 1`

7.663 src/main/decaf/internal/util/zip/zutil.h File Reference

```
#include "zlib.h"
```

Defines

- `#define ZLIB_INTERNAL`
- `#define ERR_MSG(err) z_errmsg[Z_NEED_DICT-(err)]`
- `#define ERR_RETURN(strm, err) return (strm->msg = (char*)ERR_MSG(err), (err))`
- `#define DEF_WBITS MAX_WBITS`
- `#define DEF_MEM_LEVEL 8`
- `#define STORED_BLOCK 0`
- `#define STATIC_TREES 1`
- `#define DYN_TREES 2`
- `#define MIN_MATCH 3`
- `#define MAX_MATCH 258`
- `#define PRESET_DICT 0x20`
- `#define OS_CODE 0x03`
- `#define F_OPEN(name, mode) fopen((name), (mode))`
- `#define Assert(cond, msg)`
- `#define Trace(x)`
- `#define Tracev(x)`
- `#define Tracevv(x)`
- `#define Tracec(c, x)`
- `#define Tracecv(c, x)`
- `#define ZALLOC(strm, items, size) (*((strm)->zalloc))((strm)->opaque, (items), (size))`
- `#define ZFREE(strm, addr) (*((strm)->zfree))((strm)->opaque, (voidpf)(addr))`
- `#define TRY_FREE(s, p) {if (p) ZFREE(s, p);}`

Typedefs

- `typedef unsigned char uch`
- `typedef uch FAR uchf`
- `typedef unsigned short ush`
- `typedef ush FAR ushf`
- `typedef unsigned long ulg`

Functions

- `ZEXTERN uLong ZEXPORT Adler32_combine64 OF ((uLong, uLong, z_off_t))`
- `void ZLIB_INTERNAL zmemcpy OF ((Bytef *dest, const Bytef *source, uInt len))`
- `int ZLIB_INTERNAL zmemcmp OF ((const Bytef *s1, const Bytef *s2, uInt len))`
- `void ZLIB_INTERNAL zmemzero OF ((Bytef *dest, uInt len))`
- `voidpf ZLIB_INTERNAL zcalloc OF ((voidpf opaque, unsigned items, unsigned size))`
- `void ZLIB_INTERNAL zcfree OF ((voidpf opaque, voidpf ptr))`

Variables

- `const char *const z_errmsg [10]`

7.663.1 Define Documentation

- 7.663.1.1 `#define Assert(cond, msg)`
- 7.663.1.2 `#define DEF_MEM_LEVEL 8`
- 7.663.1.3 `#define DEF_WBITS MAX_WBITS`
- 7.663.1.4 `#define DYN_TREES 2`
- 7.663.1.5 `#define ERR_MSG(err) z_errmsg[Z_NEED_DICT-(err)]`
- 7.663.1.6 `#define ERR_RETURN(strm, err) return (strm->msg = (char*)ERR_MSG(err), (err))`
- 7.663.1.7 `#define F_OPEN(name, mode) fopen((name), (mode))`
- 7.663.1.8 `#define MAX_MATCH 258`
- 7.663.1.9 `#define MIN_MATCH 3`
- 7.663.1.10 `#define OS_CODE 0x03`
- 7.663.1.11 `#define PRESET_DICT 0x20`
- 7.663.1.12 `#define STATIC_TREES 1`
- 7.663.1.13 `#define STORED_BLOCK 0`
- 7.663.1.14 `#define Trace(x)`
- 7.663.1.15 `#define Tracec(c, x)`
- 7.663.1.16 `#define Tracecv(c, x)`
- 7.663.1.17 `#define Tracev(x)`
- 7.663.1.18 `#define Tracevv(x)`
- 7.663.1.19 `#define TRY_FREE(s, p) {if (p) ZFREE(s, p);}`
- 7.663.1.20 `#define ZALLOC(strm, items, size) (*((strm)->zalloc))((strm)->opaque, (items), (size))`
- 7.663.1.21 `#define ZFREE(strm, addr) (*((strm)->zfree))((strm)->opaque, (voidpf)(addr))`
- 7.663.1.22 `#define ZLIB_INTERNAL`

7.663.2 Typedef Documentation

- 7.663.2.1 `typedef unsigned char uch`
- 7.663.2.2 `typedef uch FAR uchf`
- 7.663.2.3 `typedef unsigned long ulg`
- 7.663.2.4 `typedef unsigned short ush`
- 7.663.2.5 `typedef ush FAR ushf`

7.664 src/main/decaf/io/BlockingByteArrayInputStream.h File Reference

```
#include <decaf/io/InputStream.h>
#include <vector>
```

Data Structures

- class **decaf::io::BlockingByteArrayInputStream**
This is a blocking version of a byte buffer stream.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.665 src/main/decaf/io/BufferedInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/FilterInputStream.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::io::BufferedInputStream**

*A wrapper around another input stream that performs a buffered read, where it reads more data than it needs in order to reduce the number of **io** (p. 154) operations on the input stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.666 src/main/decaf/io/BufferedOutputStream.h File Reference

```
#include <decaf/io/FilterOutputStream.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::io::BufferedOutputStream**

Wrapper around another output stream that buffers output before writing to the target output stream.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.667 src/main/decaf/io/ByteArrayInputStream.h File Reference

```
#include <decaf/io/InputStream.h>
#include <decaf/util/concurrent/Mutex.h>
#include <vector>
```

Data Structures

- class **decaf::io::ByteArrayInputStream**

*A **ByteArrayInputStream** (p. 1020) contains an **internal** (p. 144) buffer that contains bytes that may be read from the stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.668 src/main/decaf/io/ByteArrayOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/OutputStream.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <utility>
```

Data Structures

- class **decaf::io::ByteArrayOutputStream**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.669 src/main/decaf/io/DataInput.h File Reference

```
#include <decaf/util/Config.h>
#include <vector>
#include <string>
#include <decaf/io/IOException.h>
#include <decaf/io/EOFException.h>
#include <decaf/io/UTFDataFormatException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::DataInput**

*The **DataInput** (p. 1558) interface provides for reading bytes from a binary stream and reconstructing from them data in any of the C++ primitive types.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.670 src/main/decaf/io/DataInputStream.h File Reference

```
#include <decaf/io/FilterInputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/io/EOFException.h>
#include <decaf/io/UTFDataFormatException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::DataInputStream**

A data input stream lets an application read primitive Java data types from an underlying input stream in a machine-independent way.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.671 src/main/decaf/io/DataOutput.h File Reference

```
#include <decaf/util/Config.h>
#include <vector>
#include <string>
#include <decaf/io/IOException.h>
#include <decaf/io/EOFException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::DataOutput**

*The **DataOutput** (p. 1574) interface provides for converting data from any of the C++ primitive types to a series of bytes and writing these bytes to a binary stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.672 src/main/decaf/io/DataOutputStream.h File Reference

```
#include <decaf/io/FilterOutputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/io/UTFDataFormatException.h>
#include <string>
```

Data Structures

- class **decaf::io::DataOutputStream**

A data output stream lets an application write primitive Java data types to an output stream in a portable way.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.673 src/main/decaf/io/EOFException.h File Reference

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::EOFException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.674 src/main/decaf/io/FileDescriptor.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::io::FileDescriptor**

This class servers as an opaque wrapper around an underlying OS level resource that can be used as a source / sink for byte level data such as sockets and files.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.675 src/main/decaf/io/FilterInputStream.h File Reference

```
#include <decaf/io/InputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::FilterInputStream**

A ***FilterInputStream*** (p. 1894) contains some other input stream, which it uses as its basic source of data, possibly transforming the data along the way or providing additional functionality.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.676 src/main/decaf/io/FilterOutputStream.h File Reference

```
#include <decaf/io/OutputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::FilterOutputStream**

This class is the superclass of all classes that filter output streams.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.677 src/main/decaf/io/Flushable.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::Flushable**

*A **Flushable** (p. 1936) is a destination of data that can be flushed.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.678 src/main/decaf/io/InputStream.h File Reference

```
#include <decaf/io/IOException.h>
#include <decaf/io/Closeable.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::io::InputStream**

A base class that must be implemented by all classes wishing to provide a class that reads in a stream of bytes.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.679 src/main/decaf/io/InputStreamReader.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <decaf/io/Reader.h>
```

Data Structures

- class **decaf::io::InputStreamReader**

*An **InputStreamReader** (p. 2053) is a bridge from byte streams to character streams.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.680 src/main/decaf/io/InterruptedIOException.h File Reference

```
#include <decaf/lang/Exception.h>
```

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::InterruptedIOException**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.681 src/main/decaf/io/IOException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::io::IOException**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.682 src/main/decaf/io/OutputStream.h File Reference

```
#include <decaf/io/Closeable.h>
#include <decaf/io/Flushable.h>
#include <decaf/io/IOException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::OutputStream**

Base interface for any class that wants to represent an output stream of bytes.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.683 src/main/decaf/io/OutputStreamWriter.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/Writer.h>
```

Data Structures

- class **decaf::io::OutputStreamWriter**
A class for turning a character stream into a byte stream.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.684 src/main/decaf/io/PushbackInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/FilterInputStream.h>
```

Data Structures

- class **decaf::io::PushbackInputStream**

*A **PushbackInputStream** (p. 3141) adds functionality to another input stream, namely the ability to "push back" or "unread" one byte.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.685 src/main/decaf/io/Reader.h File Reference

```
#include <string>
#include <decaf/lang/Readable.h>
#include <decaf/io/Closeable.h>
#include <decaf/io/IOException.h>
#include <decaf/io/InputStream.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
```

Data Structures

- class **decaf::io::Reader**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.686 src/main/decaf/io/UnsupportedEncodingException.h File Reference

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::UnsupportedEncodingException**
Thrown when the the Character Encoding is not supported.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.687 src/main/decaf/io/UTFDataFormatException.h File Reference

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::io::UTFDataFormatException**

Thrown from classes that attempt to read or write a UTF-8 encoded string and an encoding error is encountered.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::io**

7.688 src/main/decaf/io/Writer.h File Reference

```
#include <string>
#include <vector>
#include <decaf/io/IOException.h>
#include <decaf/io/Closeable.h>
#include <decaf/io/Flushable.h>
#include <decaf/lang/Appendable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
```

Data Structures

- class **decaf::io::Writer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**

7.689 src/main/decaf/lang/Appendable.h File Reference

```
#include <decaf/lang/Exception.h>
```

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Appendable**

An object to which char sequences and values can be appended.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.690 src/main/decaf/lang/ArrayPointer.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/System.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/util/concurrent/atomic/AtomicRefCounter.h>
#include <decaf/util/Comparator.h>
#include <memory>
#include <typeinfo>
#include <algorithm>
```

Data Structures

- class **decaf::lang::ArrayPointer**< T, REFCOUNTER >
*Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used.*
- struct **decaf::lang::ArrayPointer**< T, REFCOUNTER >::**ArrayData**
- class **decaf::lang::ArrayPointerComparator**< T, R >
*This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the value of the actual pointer to the array being contained in this **ArrayPointer** (p. 730).*
- struct **std::less**< **decaf::lang::ArrayPointer**< T > >
An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **std**

Functions

- template<typename T, typename R, typename U >
 bool **decaf::lang::operator**== (const ArrayPointer< T, R > &left, const U *right)
- template<typename T, typename R, typename U >
 bool **decaf::lang::operator**== (const U *left, const ArrayPointer< T, R > &right)
- template<typename T, typename R, typename U >
 bool **decaf::lang::operator**!= (const ArrayPointer< T, R > &left, const U *right)

- template<typename T , typename R , typename U >
bool **decaf::lang::operator!=** (const U *left, const ArrayPointer< T, R > &right)

7.691 src/main/decaf/lang/Boolean.h File Reference

```
#include <string>
#include <decaf/lang/Comparable.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Boolean**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.692 src/main/decaf/lang/Byte.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NumberFormatException.h>
#include <string>
```

Data Structures

- class **decaf::lang::Byte**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.693 src/main/decaf/lang/Character.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <string>
```

Data Structures

- class **decaf::lang::Character**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.694 src/main/decaf/lang/CharSequence.h File Reference

```
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>  
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::CharSequence**

*A **CharSequence** (p. 1135) is a readable sequence of char values.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.695 src/main/decaf/lang/Comparable.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Comparable**< **T** >

This interface imposes a total ordering on the objects of each class that implements it.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.696 src/main/decaf/lang/Double.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/exceptions/NumberFormatException.h>
#include <string>
```

Data Structures

- class **decaf::lang::Double**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.697 src/main/decaf/lang/Exception.h File Reference

```
#include <decaf/lang/Throwable.h>
#include <decaf/lang/exceptions/ExceptionDefines.h>
#include <decaf/util/Config.h>
#include <stdarg.h>
#include <sstream>
```

Data Structures

- class **decaf::lang::Exception**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.698 src/main/decaf/lang/exceptions/ClassCastException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::ClassCastException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.699 src/main/decaf/lang/exceptions/IllegalArgumentException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::IllegalArgumentException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.700 src/main/decaf/lang/exceptions/IllegalMonitorStateException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::IllegalMonitorStateException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.701 src/main/decaf/lang/exceptions/IllegalThreadStateException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::IllegalThreadStateException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.702 src/main/decaf/lang/exceptions/IndexOutOfBoundsException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::IndexOutOfBoundsException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.703 src/main/decaf/lang/exceptions/InterruptedException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::InterruptedException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.704 src/main/decaf/lang/exceptions/InvalidStateException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::InvalidStateException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.705 src/main/decaf/lang/exceptions/NoSuchElementException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::NoSuchElementException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.706 src/main/decaf/lang/exceptions/NullPointerException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::NullPointerException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.707 src/main/decaf/lang/exceptions/NumberFormatException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::NumberFormatException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.708 src/main/decaf/lang/exceptions/RuntimeException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::lang::exceptions::RuntimeException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::lang::exceptions**

7.709 src/main/decaf/lang/Float.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NumberFormatException.h>
#include <string>
```

Data Structures

- class **decaf::lang::Float**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.710 src/main/decaf/lang/Integer.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <string>
#include <decaf/lang/exceptions/NumberFormatException.h>
```

Data Structures

- class **decaf::lang::Integer**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.711 src/main/decaf/lang/Iterable.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/util/Iterator.h>
```

Data Structures

- class **decaf::lang::Iterable**< **E** >

*Implementing this interface allows an object to be cast to an **Iterable** (p. 2152) type for generic collections API calls.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.712 src/main/decaf/lang/Long.h File Reference

```
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NumberFormatException.h>
#include <string>
```

Data Structures

- class **decaf::lang::Long**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.713 src/main/decaf/lang/Math.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Math**

*The class **Math** (p. 2497) contains methods for performing basic numeric operations such as the elementary exponential, logarithm, square root, and trigonometric functions.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.714 src/main/decaf/lang/Number.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Number**

*The abstract class **Number** (p. 2835) is the superclass of classes **Byte** (p. 960), **Double** (p. 1788), **Float** (p. 1904), **Integer** (p. 2077), **Long** (p. 2420), and **Short** (p. 3440).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.715 src/main/decaf/lang/Pointer.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/ClassCastException.h>
#include <decaf/util/concurrent/atomic/AtomicRefCounter.h>
#include <decaf/util/Comparator.h>
#include <memory>
#include <typeinfo>
#include <algorithm>
```

Data Structures

- struct **decaf::lang::STATIC_CAST_TOKEN**
- struct **decaf::lang::DYNAMIC_CAST_TOKEN**
- class **decaf::lang::Pointer**< T, REFCOUNTER >

*Decaf's implementation of a Smart **Pointer** (p. 2946) that is a template on a Type and is **Thread** (p. 3765) Safe if the default Reference Counter is used.*
- class **decaf::lang::PointerComparator**< T, R >

*This implementation of Comparator is designed to allows objects in a Collection to be sorted or tested for equality based on the value of the Object being Pointed to and not the value of the contained pointer in the **Pointer** (p. 2946) instance.*
- struct **std::less**< **decaf::lang::Pointer**< T > >

An override of the less function object so that the Pointer objects can be stored in STL Maps, etc.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **std**

Functions

- template<typename T, typename R, typename U >
 bool **decaf::lang::operator==** (const Pointer< T, R > &left, const U *right)
- template<typename T, typename R, typename U >
 bool **decaf::lang::operator==** (const U *left, const Pointer< T, R > &right)
- template<typename T, typename R, typename U >
 bool **decaf::lang::operator!=** (const Pointer< T, R > &left, const U *right)
- template<typename T, typename R, typename U >
 bool **decaf::lang::operator!=** (const U *left, const Pointer< T, R > &right)

7.716 src/main/decaf/lang/Readable.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::lang::Readable**
*A **Readable** (p. 3160) is a source of characters.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**
- namespace **decaf::lang**

7.717 src/main/decaf/lang/Runnable.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Runnable**

Interface for a runnable object - defines a task that can be run by a thread.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.718 src/main/decaf/lang/Runtime.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Runtime**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.719 src/main/decaf/lang/Short.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NumberFormatException.h>
#include <string>
```

Data Structures

- class **decaf::lang::Short**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.720 src/main/decaf/lang/String.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/CharSequence.h>
#include <decaf/lang/Comparable.h>
#include <string>
```

Data Structures

- class **decaf::lang::String**

*The **String** (p. 3665) class represents an immutable sequence of chars.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.721 src/main/decaf/lang/System.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Map.h>
#include <decaf/util/Properties.h>
#include <decaf/lang/Exception.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/internal/AprPool.h>
#include <string>
```

Data Structures

- class **decaf::lang::System**

*The **System** (p. 3726) class provides static methods for accessing system level resources and performing some system dependent tasks such as looking up environment values and copying memory and arrays.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.722 src/main/decaf/lang/Thread.h File Reference

```
#include <decaf/lang/exceptions/IllegalThreadStateException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/RuntimeException.h>
#include <decaf/lang/Exception.h>
#include <decaf/lang/Runnable.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Thread**
*A **Thread** (p. 3765) is a concurrent unit of execution.*
- class **decaf::lang::Thread::UncaughtExceptionHandler**
*Interface for handlers invoked when a **Thread** (p. 3765) abruptly terminates due to an uncaught exception.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**
- namespace **decaf::lang**

7.723 src/main/decaf/lang/ThreadGroup.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::ThreadGroup**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**

7.724 src/main/decaf/lang/Throwable.h File Reference

```
#include <string>
#include <vector>
#include <iostream>
#include <exception>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::lang::Throwable**
This class represents an error that has occurred.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**

7.725 src/main/decaf/net/BindException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketException.h>
```

Data Structures

- class **decaf::net::BindException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.726 src/main/decaf/net/ConnectException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketException.h>
```

Data Structures

- class **decaf::net::ConnectException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.727 src/main/decaf/net/HttpRetryException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::HttpRetryException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.728 src/main/decaf/net/Inet4Address.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/InetAddress.h>
```

Data Structures

- class **decaf::net::Inet4Address**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.729 src/main/decaf/net/Inet6Address.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/InetAddress.h>
```

Data Structures

- class **decaf::net::Inet6Address**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.730 src/main/decaf/net/InetAddress.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <decaf/lang/ArrayPointer.h>
```

Data Structures

- class **decaf::net::InetAddress**

Represents an IP address.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.731 src/main/decaf/net/InetSocketAddress.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketAddress.h>
#include <string>
```

Data Structures

- class **decaf::net::InetSocketAddress**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.732 src/main/decaf/net/MalformedURLException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::MalformedURLException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.733 src/main/decaf/net/NoRouteToHostException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketException.h>
```

Data Structures

- class **decaf::net::NoRouteToHostException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.734 src/main/decaf/net/PortUnreachableException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketException.h>
```

Data Structures

- class **decaf::net::PortUnreachableException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.735 src/main/decaf/net/ProtocolException.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::ProtocolException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.736 src/main/decaf/net/ServerSocket.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/InetAddress.h>
#include <decaf/net/SocketImpl.h>
#include <decaf/net/SocketImplFactory.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/net/UnknownHostException.h>
#include <decaf/net/SocketTimeoutException.h>
#include <decaf/io/IOException.h>
#include <string>
```

Data Structures

- class **decaf::net::ServerSocket**
This class implements server sockets.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.737 src/main/decaf/net/ServerSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/InetAddress.h>
```

Data Structures

- class **decaf::net::ServerSocketFactory**
Class used to create Server Sockets, subclasses can be created that create certain types of server sockets according to specific policies.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.738 src/main/decaf/net/Socket.h File Reference

```
#include <decaf/net/InetAddress.h>
#include <decaf/net/SocketImplFactory.h>
#include <decaf/net/SocketException.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
#include <decaf/io/Closeable.h>
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/net/UnknownHostException.h>
#include <decaf/net/SocketTimeoutException.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::Socket**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.739 src/main/decaf/net/SocketAddress.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::net::SocketAddress**
*Base class for protocol specific **Socket** (p. 3503) addresses.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.740 src/main/decaf/net/SocketError.h File Reference

```
#include <string>
```

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::net::SocketError**

Static utility class to simplify handling of error codes for socket operations.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.741 src/main/decaf/net/SocketException.h File Reference

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::SocketException**
Exception for errors when manipulating sockets.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.742 src/main/decaf/net/SocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
#include <decaf/net/UnknownHostException.h>
```

Data Structures

- class **decaf::net::SocketFactory**

*The **SocketFactory** (p. 3524) is used to create **Socket** (p. 3503) objects and can be sub-classed to provide other types of Sockets or Sockets with varying configurations.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.743 src/main/decaf/net/SocketImpl.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
#include <decaf/io/FileDescriptor.h>
#include <decaf/net/SocketException.h>
#include <decaf/net/SocketTimeoutException.h>
#include <decaf/net/SocketOptions.h>
#include <string>
```

Data Structures

- class **decaf::net::SocketImpl**
*Acts as a base class for all physical **Socket** (p. 3503) implementations.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.744 src/main/decaf/net/SocketImplFactory.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::net::SocketImplFactory**
Factory class interface for a Factory that creates ScketImpl objects.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.745 src/main/decaf/net/SocketOptions.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::net::SocketOptions**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.746 src/main/decaf/net/SocketTimeoutException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/InterruptedIOException.h>
```

Data Structures

- class **decaf::net::SocketTimeoutException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.747 src/main/decaf/net/ssl/SSLContext.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ssl/SSLContextSpi.h>
```

Data Structures

- class **decaf::net::ssl::SSLContext**

*Represents on implementation of the Secure **Socket** (p. 3503) Layer for streaming based sockets.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.748 src/main/decaf/net/ssl/SSLContextSpi.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/SecureRandom.h>
```

Data Structures

- class **decaf::net::ssl::SSLContextSpi**
*Defines the interface that should be provided by an **SSLContext** (p. 3545) provider.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.749 src/main/decaf/net/ssl/SSLParameters.h File Reference

```
#include <decaf/util/Config.h>
#include <string>
#include <vector>
```

Data Structures

- class **decaf::net::ssl::SSLParameters**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.750 src/main/decaf/net/ssl/SSLServerSocket.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ServerSocket.h>
```

Data Structures

- class **decaf::net::ssl::SSLServerSocket**
Represents a server socket that is used to accept connections from clients using the Secure Sockets protocol or the Top Level Security protocol.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.751 src/main/decaf/net/ssl/SSLServerSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/ServerSocketFactory.h>
#include <vector>
#include <string>
```

Data Structures

- class **decaf::net::ssl::SSLServerSocketFactory**
Factory class interface that provides methods to create SSL Server Sockets.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.752 src/main/decaf/net/ssl/SSLSocket.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/Socket.h>
#include <decaf/net/ssl/SSLParameters.h>
```

Data Structures

- class **decaf::net::ssl::SSLSocket**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.753 src/main/decaf/net/ssl/SSLSocketFactory.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/net/SocketFactory.h>
#include <vector>
#include <string>
```

Data Structures

- class **decaf::net::ssl::SSLSocketFactory**
*Factory class interface for a **SocketFactory** (p. 3524) that can create **SSLSocket** (p. 3563) objects.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**
- namespace **decaf::net::ssl**

7.754 src/main/decaf/net/UnknownHostException.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::UnknownHostException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.755 src/main/decaf/net/UnknownServiceException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::net::UnknownServiceException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.756 src/main/decaf/net/URI.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/net/URISyntaxException.h>
#include <decaf/net/MalformedURLException.h>
#include <decaf/net/URL.h>
#include <decaf/internal/net/URIType.h>
#include <string>
```

Data Structures

- class **decaf::net::URI**

*This class represents an instance of a **URI** (p. 3921) as defined by RFC 2396.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.757 src/main/decaf/net/URISyntaxException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::net::URISyntaxException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::net**

7.758 src/main/decaf/net/URL.h File Reference

```
#include <decaf/util/Config.h>  
#include <string>
```

Data Structures

- class **decaf::net::URL**

*Class **URL** (p. 3960) represents a Uniform Resource Locator, a pointer to a "resource" on the World Wide Web.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.759 src/main/decaf/net/URLDecoder.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <string>
```

Data Structures

- class **decaf::net::URLDecoder**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.760 src/main/decaf/net/URLEncoder.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <string>
```

Data Structures

- class **decaf::net::URLEncoder**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::net**

7.761 src/main/decaf/nio/Buffer.h File Reference

```
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/nio/InvalidMarkException.h>
```

Data Structures

- class **decaf::nio::Buffer**
A container for data of a specific primitive type.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.762 src/main/decaf/nio/BufferOverflowException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::nio::BufferOverflowException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.763 src/main/decaf/nio/BufferUnderflowException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::nio::BufferUnderflowException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.764 src/main/decaf/nio/ByteBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::ByteBuffer**

This class defines six categories of operations upon byte buffers:.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.765 src/main/decaf/nio/CharBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
#include <decaf/lang/CharSequence.h>
#include <decaf/lang/Appendable.h>
```

Data Structures

- class **decaf::nio::CharBuffer**

This class defines four categories of operations upon character buffers:.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.766 src/main/decaf/nio/DoubleBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::DoubleBuffer**
This class defines four categories of operations upon double buffers:.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.767 src/main/decaf/nio/FloatBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::FloatBuffer**

This class defines four categories of operations upon float buffers:.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.768 src/main/decaf/nio/IntBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::IntBuffer**
This class defines four categories of operations upon int buffers:.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.769 src/main/decaf/nio/InvalidMarkException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
```

Data Structures

- class **decaf::nio::InvalidMarkException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::nio**

7.770 src/main/decaf/nio/LongBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::LongBuffer**

This class defines four categories of operations upon long long buffers:.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.771 src/main/decaf/nio/ReadOnlyBufferException.h File Reference

```
#include <decaf/util/Config.h>
```

```
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
```

Data Structures

- class **decaf::nio::ReadOnlyBufferException**

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.772 src/main/decaf/nio/ShortBuffer.h File Reference

```
#include <decaf/nio/Buffer.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/nio/BufferUnderflowException.h>
#include <decaf/nio/BufferOverflowException.h>
#include <decaf/nio/ReadOnlyBufferException.h>
```

Data Structures

- class **decaf::nio::ShortBuffer**

This class defines four categories of operations upon short buffers:.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::nio**

7.773 src/main/decaf/security/auth/x500/X500Principal.h File Reference

```
#include <string>
#include <vector>
#include <decaf/security/Principal.h>
#include <decaf/util/Map.h>
#include <decaf/io/InputStream.h>
```

Data Structures

- class `decaf::security::auth::x500::X500Principal`

Namespaces

- namespace `decaf`

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace `decaf::security`
- namespace `decaf::security::auth`
- namespace `decaf::security::auth::x500`

7.774 src/main/decaf/security/cert/Certificate.h File Reference

```
#include <vector>
#include <decaf/util/Config.h>
#include <decaf/security/InvalidKeyException.h>
#include <decaf/security/NoSuchAlgorithmException.h>
#include <decaf/security/SignatureException.h>
#include <decaf/security/cert/CertificateEncodingException.h>
#include <decaf/security/cert/CertificateException.h>
```

Data Structures

- class **decaf::security::cert::Certificate**
Base interface for all identity certificates.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.775 src/main/decaf/security/cert/CertificateEncodingException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/cert/CertificateException.h>
```

Data Structures

- class **decaf::security::cert::CertificateEncodingException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.776 src/main/decaf/security/cert/CertificateException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/GeneralSecurityException.h>
```

Data Structures

- class **decaf::security::cert::CertificateException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.777 src/main/decaf/security/cert/CertificateExpiredException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/cert/CertificateException.h>
```

Data Structures

- class **decaf::security::cert::CertificateExpiredException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.778 src/main/decaf/security/cert/CertificateNotYetValidException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/cert/CertificateException.h>
```

Data Structures

- class **decaf::security::cert::CertificateNotYetValidException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agree-
ments.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.779 src/main/decaf/security/cert/CertificateParsingException.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/security/cert/CertificateException.h>
```

Data Structures

- class **decaf::security::cert::CertificateParsingException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.780 src/main/decaf/security/cert/X509Certificate.h File Reference

```
#include <decaf/security/cert/Certificate.h>
#include <decaf/util/Config.h>
#include <decaf/util/Date.h>
```

Data Structures

- class **decaf::security::cert::X509Certificate**
Base interface for all identity certificates.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**
- namespace **decaf::security::cert**

7.781 src/main/decaf/security/GeneralSecurityException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::security::GeneralSecurityException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.782 src/main/decaf/security/InvalidKeyException.h File Reference

```
#include <decaf/security/KeyException.h>
```

Data Structures

- class **decaf::security::InvalidKeyException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.783 src/main/decaf/security/Key.h File Reference

```
#include <vector>
#include <string>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::security::Key**
*The **Key** (p. 2293) interface is the top-level interface for all keys.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.784 src/main/decaf/security/KeyException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/GeneralSecurityException.h>
```

Data Structures

- class **decaf::security::KeyException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.785 src/main/decaf/security/KeyManagementException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/KeyException.h>
```

Data Structures

- class **decaf::security::KeyManagementException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.786 src/main/decaf/security/NoSuchAlgorithmException.h File Reference

```
#include <decaf/security/GeneralSecurityException.h>
```

Data Structures

- class **decaf::security::NoSuchAlgorithmException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.787 src/main/decaf/security/NoSuchProviderException.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/security/GeneralSecurityException.h>
```

Data Structures

- class **decaf::security::NoSuchProviderException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.788 src/main/decaf/security/Principal.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::security::Principal**

Base interface for a principal, which can represent an individual or organization.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::security**

7.789 src/main/decaf/security/PublicKey.h File Reference

```
#include <decaf/security/Key.h>
```

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::security::PublicKey**
A public key.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.790 src/main/decaf/security/SecureRandom.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Random.h>
#include <decaf/security/SecureRandomSpi.h>
#include <memory>
```

Data Structures

- class **decaf::security::SecureRandom**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.791 src/main/decaf/security/SecureRandomSpi.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::security::SecureRandomSpi**

Interface class used by Security Service Providers to implement a source of secure random bytes.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::security**

7.792 src/main/decaf/security/SignatureException.h File Reference

```
#include <decaf/util/Config.h>  
#include <decaf/security/GeneralSecurityException.h>
```

Data Structures

- class **decaf::security::SignatureException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::security**

7.793 src/main/decaf/util/AbstractCollection.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/Collection.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractCollection**< E >

*This class provides a skeletal implementation of the **Collection** (p. 1184) interface, to minimize the effort required to implement this interface.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.794 src/main/decaf/util/AbstractList.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/List.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractList**< **E** >

*This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "random access" data store (such as an array).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.795 src/main/decaf/util/AbstractMap.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/Map.h>
#include <decaf/util/Set.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractMap**< K, V, COMPARATOR >

*This class provides a skeletal implementation of the **Map** (p. 2459) interface, to minimize the effort required to implement this interface.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.796 src/main/decaf/util/AbstractQueue.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/Queue.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractQueue**< **E** >

*This class provides skeletal implementations of some **Queue** (p. 3149) operations.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.797 src/main/decaf/util/AbstractSequentialList.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/AbstractList.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractSequentialList**< E >

*This class provides a skeletal implementation of the **List** (p. 2337) interface to minimize the effort required to implement this interface backed by a "sequential access" data store (such as a linked list).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.798 src/main/decaf/util/AbstractSet.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/Set.h>
#include <memory>
```

Data Structures

- class **decaf::util::AbstractSet**< E >

*This class provides a skeletal implementation of the **Set** (p. 3439) interface to minimize the effort required to implement this interface.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.799 src/main/decaf/util/Collection.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/Iterable.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/concurrent/Synchronizable.h>
```

Data Structures

- class **decaf::util::Collection< E >**
The root interface in the collection hierarchy.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.800 src/main/decaf/util/Comparator.h File Reference

```
#include <decaf/util/Config.h>
#include <algorithm>
#include <functional>
```

Data Structures

- class **decaf::util::Comparator**< **T** >
A comparison function, which imposes a total ordering on some collection of objects.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.801 src/main/decaf/util/comparators/Less.h File Reference

```
#include <decaf/util/Comparator.h>
```

Data Structures

- class **decaf::util::comparators::Less**< **E** >
*Simple **Less** (p. 2328) **Comparator** (p. 1217) that compares to elements to determine if the first is less than the second.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::comparators**

7.802 src/main/decaf/util/concurrent/atomic/AtomicBoolean.h File Reference

```
#include <string>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::atomic::AtomicBoolean**

A boolean value that may be updated atomically.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::atomic**

7.803 src/main/decaf/util/concurrent/atomic/AtomicInteger.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Number.h>
#include <string>
```

Data Structures

- class **decaf::util::concurrent::atomic::AtomicInteger**
An int value that may be updated atomically.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::atomic**

7.804 src/main/decaf/util/concurrent/atomic/AtomicRefCounter.h File Reference

```
#include <decaf/util/concurrent/atomic/AtomicInteger.h>
```

Data Structures

- class **decaf::util::concurrent::atomic::AtomicRefCounter**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::atomic**

7.805 src/main/decaf/util/concurrent/atomic/AtomicReference.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Long.h>
#include <apr_atomic.h>
```

Data Structures

- class **decaf::util::concurrent::atomic::AtomicReference< T >**
An Pointer reference that may be updated atomically.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::atomic**

7.806 src/main/decaf/util/concurrent/BlockingQueue.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/AbstractQueue.h>
#include <decaf/util/concurrent/TimeUnit.h>
#include <decaf/lang/exceptions/InterruptedException.h>
```

Data Structures

- class **decaf::util::concurrent::BlockingQueue**< **E** >

A **decaf::util::Queue** (p. 3149) that additionally supports operations that wait for the queue to become non-empty when retrieving an element, and wait for space to become available in the queue when storing an element.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.807 src/main/decaf/util/concurrent/BrokenBarrierException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::BrokenBarrierException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.808 src/main/decaf/util/concurrent/Callable.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::Callable**< V >
A task that returns a result and may throw an exception.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.809 src/main/decaf/util/concurrent/CancellationException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::CancellationException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.810 src/main/decaf/util/concurrent/Concurrent.h File Reference

```
#include <decaf/util/concurrent/Lock.h>
```

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

Defines

- `#define WAIT_INFINITE 0xFFFFFFFF`
*The synchronized macro defines a mechanism for synchronizing a section of **code** (p. 1183).*
- `#define synchronized(W)`

7.810.1 Define Documentation

7.810.1.1 `#define synchronized(W)`

Value:

```
if(false){}
else
    for( decaf::util::concurrent::Lock lock_W(W);
        lock_W.isLocked(); lock_W.unlock() )
```

7.810.1.2 `#define WAIT_INFINITE 0xFFFFFFFF`

The synchronized macro defines a mechanism for synchronizing a section of **code** (p. 1183). The macro must be passed an object that implements the Synchronizable interface.

The macro works by creating a for loop that will loop exactly once, creating a Lock object that is scoped to the loop. Once the loop completes and exits the Lock object goes out of scope releasing the lock on object W. For added safety the if else is used because not all compilers restrict the lifetime of loop variables to the loop, they will however restrict them to the scope of the else.

The macro would be used as follows.

Synchronizable X;

```
somefunction() { synchronized(X) (p. 4893) { // Do something that needs synchronizing. } }
```

7.811 src/main/decaf/util/concurrent/ConcurrentMap.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Map.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
```

Data Structures

- class **decaf::util::concurrent::ConcurrentMap**< **K**, **V**, **COMPARATOR** >
*Interface for a **Map** (p. 2459) type that provides additional **atomic** (p. 173) **putIfAbsent**, **remove**, and **replace** methods alongside the already available **Map** (p. 2459) interface.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.812 src/main/decaf/util/concurrent/ConcurrentStlMap.h File Reference

```
#include <map>
#include <vector>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/ConcurrentMap.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Map.h>
```

Data Structures

- class **decaf::util::concurrent::ConcurrentStlMap**< K, V, COMPARATOR >
Map (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.813 src/main/decaf/util/concurrent/CountDownLatch.h File Reference

```
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/concurrent/TimeUnit.h>
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::CountDownLatch**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.814 src/main/decaf/util/concurrent/Delayed.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/util/concurrent/TimeUnit.h>
```

Data Structures

- class **decaf::util::concurrent::Delayed**

A mix-in style interface for marking objects that should be acted upon after a given delay.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.815 src/main/decaf/util/concurrent/ExecutionException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::ExecutionException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.816 src/main/decaf/util/concurrent/Executor.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Runnable.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/util/concurrent/RejectedExecutionException.h>
```

Data Structures

- class **decaf::util::concurrent::Executor**
*An object that executes submitted **decaf.lang.Runnable** (p. 3325) tasks.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.817 src/main/decaf/util/concurrent/ExecutorService.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/concurrent/Executor.h>
#include <decaf/util/concurrent/TimeUnit.h>
#include <decaf/lang/exceptions/InterruptedException.h>
```

Data Structures

- class **decaf::util::concurrent::ExecutorService**

*An **Executor** (p. 1869) that provides methods to manage termination and methods that can produce a **Future** (p. 1966) for tracking progress of one or more asynchronous tasks.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.818 src/main/decaf/util/concurrent/Future.h File Reference

Data Structures

- class **decaf::util::concurrent::Future**< **V** >
*A **Future** (p. 1966) represents the result of an asynchronous computation.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.819 src/main/decaf/util/concurrent/Lock.h File Reference

```
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::Lock**

A wrapper class around a given synchronization mechanism that provides automatic release upon destruction.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.820 src/main/decaf/util/concurrent/locks/Lock.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/util/concurrent/locks/Condition.h>
```

Data Structures

- class **decaf::util::concurrent::locks::Lock**

***Lock** (p. 2377) implementations provide more extensive locking operations than can be obtained using synchronized statements.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**

7.821 src/main/decaf/util/concurrent/locks/Condition.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Date.h>
#include <decaf/util/concurrent/TimeUnit.h>
#include <decaf/lang/exceptions/RuntimeException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/IllegalMonitorStateException.h>
```

Data Structures

- class **decaf::util::concurrent::locks::Condition**

***Condition** (p. 1249) factors out the **Mutex** (p. 2782) monitor methods (wait, notify and notifyAll) into distinct objects to give the effect of having multiple wait-sets per object, by combining them with the use of arbitrary **Lock** (p. 2377) implementations.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**

7.822 src/main/decaf/util/concurrent/locks/LockSupport.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::locks::LockSupport**

*Basic thread blocking primitives for creating **locks** (p. 174) and other synchronization classes.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**

7.823 src/main/decaf/util/concurrent/locks/ReadWriteLock.h File Reference

Data Structures

- class **decaf::util::concurrent::locks::ReadWriteLock**

*A **ReadWriteLock** (p. 3172) maintains a pair of associated **locks** (p. 174), one for read-only operations and one for writing.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**

7.824 src/main/decaf/util/concurrent/locks/ReentrantLock.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/concurrent/locks/Lock.h>
#include <decaf/lang/Pointer.h>
```

Data Structures

- class **decaf::util::concurrent::locks::ReentrantLock**
*A reentrant mutual exclusion **Lock** (p. 2377) with extended capabilities.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**
- namespace **decaf::util::concurrent::locks**

7.825 src/main/decaf/util/concurrent/Mutex.h File Reference

```
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/lang/Thread.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::Mutex**

***Mutex** (p. 2782) object that offers recursive support on all platforms as well as providing the ability to use the standard wait / notify pattern used in languages like Java.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.826 src/main/decaf/util/concurrent/PooledThread.h File Reference

```
#include <decaf/lang/Thread.h>
#include <decaf/util/concurrent/PooledThreadListener.h>
#include <decaf/util/logging/LoggerDefines.h>
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::PooledThread**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.827 src/main/decaf/util/concurrent/PooledThreadListener.h File Reference

```
#include <decaf/lang/Exception.h>
```

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::PooledThreadListener**
Abstract Listener Interface for users of `ThreadPool` (p. 3777).

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.828 src/main/decaf/util/concurrent/RejectedExecutionException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::RejectedExecutionException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.829 src/main/decaf/util/concurrent/RejectedExecutionHandler.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Runnable.h>
#include <decaf/util/concurrent/RejectedExecutionException.h>
```

Data Structures

- class **decaf::util::concurrent::RejectedExecutionHandler**
*A handler for tasks that cannot be executed by a **ThreadPoolExecutor** (p.??).*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.830 src/main/decaf/util/concurrent/Semaphore.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/RuntimeException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/util/concurrent/TimeUnit.h>
#include <memory>
```

Data Structures

- class **decaf::util::concurrent::Semaphore**
A counting semaphore.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.831 src/main/decaf/util/concurrent/Synchronizable.h File Reference

```
#include <decaf/lang/exceptions/RuntimeException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/IllegalMonitorStateException.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::Synchronizable**
The interface for all synchronizable objects (that is, objects that can be locked and unlocked).

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.832 src/main/decaf/util/concurrent/SynchronousQueue.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/concurrent/BlockingQueue.h>
#include <vector>
```

Data Structures

- class **decaf::util::concurrent::SynchronousQueue< E >**
*A **blocking queue** (p. 843) in which each insert operation must wait for a corresponding remove operation by another thread, and vice versa.*
- class **decaf::util::concurrent::SynchronousQueue< E >::EmptyIterator**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.833 src/main/decaf/util/concurrent/TaskListener.h File Reference

```
#include <decaf/lang/Runnable.h>
#include <decaf/lang/Exception.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::TaskListener**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.834 src/main/decaf/util/concurrent/ThreadFactory.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::concurrent::ThreadFactory**
*public interface **ThreadFactory** (p. 3774)*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::lang**
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.835 src/main/decaf/util/concurrent/ThreadPool.h File Reference

```
#include <decaf/lang/Runnable.h>
#include <decaf/util/concurrent/PooledThread.h>
#include <decaf/util/concurrent/PooledThreadListener.h>
#include <decaf/util/concurrent/TaskListener.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/StlQueue.h>
#include <decaf/util/logging/LoggerDefines.h>
#include <decaf/util/Config.h>
#include <vector>
```

Data Structures

- class **decaf::util::concurrent::ThreadPool**

Defines a Thread Pool object that implements the functionality of pooling threads to perform user tasks.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.836 src/main/decaf/util/concurrent/TimeoutException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::concurrent::TimeoutException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.837 src/main/decaf/util/concurrent/TimeUnit.h File Reference

```
#include <string>
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/InterruptedException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
```

Data Structures

- class **decaf::util::concurrent::TimeUnit**

*A **TimeUnit** (p. 3807) represents time durations at a given unit of granularity and provides utility methods to convert across units, and to perform timing and delay operations in these units.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**
- namespace **decaf::util**
- namespace **decaf::util::concurrent**

7.838 src/main/decaf/util/Date.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <string>
```

Data Structures

- class **decaf::util::Date**
Wrapper class around a time value in milliseconds.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.839 src/main/decaf/util/Iterator.h File Reference

```
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
```

Data Structures

- class **decaf::util::Iterator**< T >
Defines an object that can be used to iterate over the elements of a collection.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.840 src/main/decaf/util/List.h File Reference

```
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/Config.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/AbstractCollection.h>
#include <decaf/util/ListIterator.h>
```

Data Structures

- class **decaf::util::List**< **E** >
An ordered collection (also known as a sequence).

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.841 src/main/decaf/util/ListIterator.h File Reference

```
#include <decaf/util/Iterator.h>
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::util::ListIterator**< **E** >

An iterator for lists that allows the programmer to traverse the list in either direction, modify the list during iteration, and obtain the iterator's current position in the list.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.842 src/main/decaf/util/logging/ConsoleHandler.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/logging/StreamHandler.h>
#include <decaf/util/logging/SimpleFormatter.h>
#include <decaf/io/IOException.h>
#include <decaf/internal/io/StandardErrorOutputStream.h>
```

Data Structures

- class **decaf::util::logging::ConsoleHandler**
*This **Handler** (p. 1978) publishes log records to `System.err`.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.843 src/main/decaf/util/logging/EventManager.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Exception.h>
#include <decaf/util/concurrent/atomic/AtomicBoolean.h>
#include <string>
```

Data Structures

- class **decaf::util::logging::EventManager**

***ErrorManager** (p. 1828) objects can be attached to *Handlers* to process any error that occur on a *Handler* (p. 1978) during Logging.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.844 src/main/decaf/util/logging/Filter.h File Reference

```
#include <decaf/util/logging/LogRecord.h>
```

Data Structures

- class **decaf::util::logging::Filter**

*A **Filter** (p. 1893) can be used to provide fine grain control over what is logged, beyond the control provided by log levels.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.845 src/main/decaf/util/logging/Formatter.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/logging/Handler.h>
```

Data Structures

- class **decaf::util::logging::Formatter**
*A **Formatter** (p. 1964) provides support for formatting LogRecords.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.846 src/main/decaf/util/logging/Handler.h File Reference

```
#include <decaf/io/Closeable.h>
#include <decaf/lang/Exception.h>
#include <decaf/util/logging/LogRecord.h>
#include <decaf/util/logging/Level.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <string>
```

Data Structures

- class **decaf::util::logging::Handler**

A **Handler** (p. 1978) object takes log messages from a **Logger** (p. 2386) and exports them.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.847 src/main/decaf/util/logging/Level.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::util::logging::Level**

*The **Level** (p. 2332) class defines a set of standard **logging** (p. 175) levels that can be used to control **logging** (p. 175) output.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.848 src/main/decaf/util/logging/Logger.h File Reference

```
#include <decaf/util/logging/LoggerCommon.h>
#include <decaf/util/logging/LogRecord.h>
#include <decaf/util/logging/LogManager.h>
#include <decaf/util/logging/Handler.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <list>
#include <string>
#include <stdarg.h>
```

Data Structures

- class **decaf::util::logging::Logger**

A *Logger* (p. 2386) object is used to log messages for a specific system or application component.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.849 src/main/decaf/util/logging/LoggerCommon.h File Reference

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

Enumerations

- enum **decaf::util::logging::Levels** {
 decaf::util::logging::Off, **decaf::util::logging::Null**, **decaf::util::logging::Markblock**,
 decaf::util::logging::Debug,
 decaf::util::logging::Info, **decaf::util::logging::Warn**, **decaf::util::logging::Error**,
 decaf::util::logging::Fatal,
 decaf::util::logging::Throwing }
Defines an enumeration for logging levels.

7.850 src/main/decaf/util/logging/LoggerDefines.h File Reference

```
#include <decaf/util/logging/SimpleLogger.h>
#include <sstream>
```

Defines

- **#define LOGDECAF_DECLARE(loggerName) static decaf::util::logging::SimpleLogger loggerName;**
- **#define LOGDECAF_INITIALIZE(loggerName, className, loggerFamily) decaf::util::logging::SimpleLogger className::loggerName(loggerFamily);**
- **#define LOGDECAF_DECLARE_LOCAL(loggerName) decaf::util::logging::Logger loggerName;**
- **#define LOGDECAF_DEBUG(logger, message) logger.debug(__FILE__, __LINE__, message);**
- **#define LOGDECAF_DEBUG_1(logger, message, value)**
- **#define LOGDECAF_INFO(logger, message) logger.info(__FILE__, __LINE__, message);**
- **#define LOGDECAF_ERROR(logger, message) logger.error(__FILE__, __LINE__, message);**
- **#define LOGDECAF_WARN(logger, message) logger.warn(__FILE__, __LINE__, message);**
- **#define LOGDECAF_FATAL(logger, message) logger.fatal(__FILE__, __LINE__, message);**

7.850.1 Define Documentation

7.850.1.1 #define LOGDECAF_DEBUG(logger, message) logger.debug(__FILE__, __LINE__, message);

7.850.1.2 #define LOGDECAF_DEBUG_1(logger, message, value)

Value:

```
;
{
    std::ostringstream ostream;
    ostream << message << value;
    logger.debug(__FILE__, __LINE__, ostream.str());
}
```

- 7.850.1.3 `#define LOGDECAF_DECLARE(loggerName) static
decaf::util::logging::SimpleLogger loggerName;`
- 7.850.1.4 `#define LOGDECAF_DECLARE_LOCAL(loggerName) de-
caf::util::logging::Logger loggerName;`
- 7.850.1.5 `#define LOGDECAF_ERROR(logger, message) logger.error(__-
FILE __, __LINE __, message);`
- 7.850.1.6 `#define LOGDECAF_FATAL(logger, message) logger.fatal(__FILE __-
__, __LINE __, message);`
- 7.850.1.7 `#define LOGDECAF_INFO(logger, message) logger.info(__FILE __,
__LINE __, message);`
- 7.850.1.8 `#define LOGDECAF_INITIALIZE(loggerName,
className, loggerFamily) decaf::util::logging::SimpleLogger
className::loggerName(loggerFamily);`
- 7.850.1.9 `#define LOGDECAF_WARN(logger, message) logger.warn(__FILE __-
__, __LINE __, message);`

7.851 src/main/decaf/util/logging/LoggerHierarchy.h File Reference

Data Structures

- class `decaf::util::logging::LoggerHierarchy`

Namespaces

- namespace `decaf`
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace `decaf::util`
- namespace `decaf::util::logging`

7.852 src/main/decaf/util/logging/LogManager.h File Reference

```
#include <map>
#include <list>
#include <string>
#include <vector>
#include <decaf/lang/Pointer.h>
#include <decaf/util/Properties.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Config.h>
#include <decaf/io/IOException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::util::logging::LogManager**

*There is a single global **LogManager** (p. 2406) object that is used to maintain a set of shared state about Loggers and log services.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::lang**
- namespace **decaf::io**
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.853 src/main/decaf/util/logging/LogRecord.h File Reference

```
#include <decaf/lang/Throwable.h>
#include <decaf/util/logging/LoggerCommon.h>
#include <decaf/util/logging/Level.h>
#include <decaf/util/Config.h>
#include <memory>
#include <string>
```

Data Structures

- class **decaf::util::logging::LogRecord**
LogRecord (p. 2413) objects are used to pass *logging* (p. 175) requests between the *logging* (p. 175) framework and individual log Handlers.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.854 src/main/decaf/util/logging/LogWriter.h File Reference

```
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **decaf::util::logging::LogWriter**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.855 src/main/decaf/util/logging/MarkBlockLogger.h File Reference

```
#include <decaf/util/logging/Logger.h>
```

Data Structures

- class **decaf::util::logging::MarkBlockLogger**

Defines a class that can be used to mark the entry and exit from scoped blocks.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.856 src/main/decaf/util/logging/PropertiesChangeListener.h File Reference

```
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::logging::PropertiesChangeListener**

*Defines the interface that classes can use to listen for change events on **Properties** (p. 3126).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.857 src/main/decaf/util/logging/SimpleFormatter.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/logging/Formatter.h>
#include <string>
```

Data Structures

- class **decaf::util::logging::SimpleFormatter**

*Print a brief summary of the **LogRecord** (p. 2413) in a human readable format.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::logging**

7.858 src/main/decaf/util/logging/SimpleLogger.h File Reference

```
#include <string>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::logging::SimpleLogger**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.859 src/main/decaf/util/logging/StreamHandler.h File Reference

```
#include <decaf/util/logging/LoggerCommon.h>
#include <decaf/util/logging/Handler.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/InvalidStateException.h>
#include <decaf/util/concurrent/Concurrent.h>
#include <decaf/util/Config.h>
```

Data Structures

- class **decaf::util::logging::StreamHandler**
*Stream based **logging** (p. 175) **Handler** (p. 1978).*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.860 src/main/decaf/util/logging/XMLFormatter.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/logging/Formatter.h>
#include <decaf/util/logging/LogRecord.h>
```

Data Structures

- class **decaf::util::logging::XMLFormatter**
*Format a **LogRecord** (p. 2413) into a standard XML format.*

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::logging**

7.861 src/main/decaf/util/Map.h File Reference

```
#include <functional>
#include <vector>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **decaf::util::Map**< **K**, **V**, **COMPARATOR** >
***Map** (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.*
- class **decaf::util::Map**< **K**, **V**, **COMPARATOR** >::**Entry**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.862 src/main/decaf/util/PriorityQueue.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/Collection.h>
#include <decaf/util/AbstractQueue.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/Comparator.h>
#include <decaf/util/comparators/Less.h>
#include <decaf/lang/Math.h>
#include <decaf/lang/Pointer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <memory>
```

Data Structures

- class **decaf::util::PriorityQueue< E >**
An unbounded priority queue based on a binary heap algorithm.
- class **decaf::util::PriorityQueue< E >::PriorityQueueIterator**
- class **decaf::util::PriorityQueue< E >::ConstPriorityQueueIterator**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.863 src/main/decaf/util/Properties.h File Reference

```
#include <vector>
#include <string>
#include <decaf/util/Config.h>
#include <decaf/util/StlMap.h>
#include <decaf/io/InputStream.h>
#include <decaf/io/OutputStream.h>
#include <decaf/lang/Pointer.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::util::Properties**
Java-like properties class for mapping string names to string values.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::io**
- namespace **decaf::util**

7.864 src/main/decaf/util/Random.h File Reference

```
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/util/Config.h>
#include <vector>
#include <cmath>
```

Data Structures

- class **decaf::util::Random**

***Random** (p. 3155) Value Generator which is used to generate a stream of pseudorandom numbers.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.865 src/main/decaf/util/Set.h File Reference

```
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/AbstractCollection.h>
```

Data Structures

- class **decaf::util::Set**< **E** >
A collection that contains no duplicate elements.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.866 src/main/decaf/util/StlList.h File Reference

```
#include <list>
#include <algorithm>
#include <memory>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Config.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/ListIterator.h>
#include <decaf/util/List.h>
```

Data Structures

- class **decaf::util::StlList< E >**
List (p. 2337) class that wraps the STL list object to provide a simpler interface and additional methods not provided by the STL type.
- class **decaf::util::StlList< E >::StlListIterator**
- class **decaf::util::StlList< E >::ConstStlListIterator**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.867 src/main/decaf/util/StlMap.h File Reference

```
#include <map>
#include <vector>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Map.h>
```

Data Structures

- class **decaf::util::StlMap< K, V, COMPARATOR >**
Map (p. 2459) template that wraps around a `std::map` to provide a more user-friendly interface and to provide common functions that do not exist in `std::map`.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.868 src/main/decaf/util/StlQueue.h File Reference

```
#include <list>
#include <vector>
#include <decaf/util/Iterator.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::StlQueue< T >**
*The **Queue** (p. 3149) class accepts messages with an **psuh(m)** command where *m* is the message to be queued.*
- class **decaf::util::StlQueue< T >::QueueIterator**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.869 src/main/decaf/util/StlSet.h File Reference

```
#include <set>
#include <vector>
#include <memory>
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/concurrent/Synchronizable.h>
#include <decaf/util/concurrent/Mutex.h>
#include <decaf/util/Iterator.h>
#include <decaf/util/AbstractSet.h>
```

Data Structures

- class **decaf::util::StlSet< E >**
Set (p. 3439) template that wraps around a std::set to provide a more user-friendly interface and to provide common functions that do not exist in std::set.
- class **decaf::util::StlSet< E >::SetIterator**
- class **decaf::util::StlSet< E >::ConstSetIterator**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.870 src/main/decaf/util/StringTokenizer.h File Reference

```
#include <decaf/lang/exceptions/NoSuchElementException.h>
#include <decaf/util/Config.h>
#include <string>
```

Data Structures

- class **decaf::util::StringTokenizer**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**

7.871 src/main/decaf/util/Timer.h File Reference

```
#include <memory>
#include <decaf/util/Config.h>
#include <decaf/util/Date.h>
#include <decaf/lang/Pointer.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
```

Data Structures

- class **decaf::util::Timer**

A facility for threads to schedule tasks for future execution in a background thread.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.872 src/main/decaf/util/TimerTask.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Runnable.h>
#include <decaf/util/concurrent/Mutex.h>
```

Data Structures

- class **decaf::util::TimerTask**

*A Base class for a task object that can be scheduled for one-time or repeated execution by a **Timer** (p. 3790).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::internal**
- namespace **decaf::internal::util**
- namespace **decaf::util**

7.873 src/main/decaf/util/UUID.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/Comparable.h>
#include <decaf/lang/exceptions/UnsupportedOperationException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <apr_uuid.h>
#include <string>
```

Data Structures

- class **decaf::util::UUID**

*A class that represents an immutable universally unique identifier (**UUID** (p. 3969)).*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**

7.874 src/main/decaf/util/zip/Adler32.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/zip/Checksum.h>
```

Data Structures

- class **decaf::util::zip::Adler32**

*Clas that can be used to compute an Adler-32 **Checksum** (p. 1142) for a data stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.875 src/main/decaf/util/zip/CheckedInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/zip/Checksum.h>
#include <decaf/io/FilterInputStream.h>
```

Data Structures

- class **decaf::util::zip::CheckedInputStream**

*An implementation of a `FilterInputStream` that will maintain a **Checksum** (p. 1142) of the bytes read, the **Checksum** (p. 1142) can then be used to verify the integrity of the input stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.876 src/main/decaf/util/zip/CheckedOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/zip/Checksum.h>
#include <decaf/io/FilterOutputStream.h>
```

Data Structures

- class **decaf::util::zip::CheckedOutputStream**

*An implementation of a `FilterOutputStream` that will maintain a **Checksum** (p. 1142) of the bytes written, the **Checksum** (p. 1142) can then be used to verify the integrity of the output stream.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.877 src/main/decaf/util/zip/Checksum.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <vector>
```

Data Structures

- class **decaf::util::zip::Checksum**

*An interface used to represent **Checksum** (p. 1142) values in the Zip package.*

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.878 src/main/decaf/util/zip/CRC32.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/util/zip/Checksum.h>
```

Data Structures

- class **decaf::util::zip::CRC32**

Class that can be used to compute a CRC-32 checksum for a data stream.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.879 src/main/decaf/util/zip/DataFormatException.h File Reference

```
#include <decaf/lang/Exception.h>
```

Data Structures

- class **decaf::util::zip::DataFormatException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::zip**

7.880 src/main/decaf/util/zip/Deflater.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <vector>
```

Data Structures

- class **decaf::util::zip::Deflater**

This class compresses data using the DEFLATE algorithm (see [specification](#)).

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.881 src/main/decaf/util/zip/DeflaterOutputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/FilterOutputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/util/zip/Deflater.h>
#include <vector>
```

Data Structures

- class **decaf::util::zip::DeflaterOutputStream**

Provides a FilterOutputStream instance that compresses the data before writing it to the wrapped OutputStream.

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.882 src/main/decaf/util/zip/Inflater.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/lang/exceptions/NullPointerException.h>
#include <decaf/lang/exceptions/IllegalArgumentException.h>
#include <decaf/lang/exceptions/IllegalStateException.h>
#include <decaf/lang/exceptions/IndexOutOfBoundsException.h>
#include <decaf/util/zip/DataFormatException.h>
#include <vector>
```

Data Structures

- class **decaf::util::zip::Inflater**

This class uncompresses data that was compressed using the DEFLATE algorithm (see specification).

Namespaces

- namespace **decaf**

Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.

- namespace **decaf::util**
- namespace **decaf::util::zip**

7.883 src/main/decaf/util/zip/InflaterInputStream.h File Reference

```
#include <decaf/util/Config.h>
#include <decaf/io/FilterInputStream.h>
#include <decaf/io/IOException.h>
#include <decaf/util/zip/Inflater.h>
#include <vector>
```

Data Structures

- class **decaf::util::zip::InflaterInputStream**
A FilterInputStream that decompresses data read from the wrapped InputStream instance.

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::zip**

7.884 src/main/decaf/util/zip/ZipException.h File Reference

```
#include <decaf/io/IOException.h>
```

Data Structures

- class **decaf::util::zip::ZipException**

Namespaces

- namespace **decaf**
Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements.
- namespace **decaf::util**
- namespace **decaf::util::zip**

Index

- ~AbstractCollection
 - decaf::util::AbstractCollection, 182
- ~AbstractList
 - decaf::util::AbstractList, 192
- ~AbstractMap
 - decaf::util::AbstractMap, 193
- ~AbstractQueue
 - decaf::util::AbstractQueue, 195
- ~AbstractSequentialList
 - decaf::util::AbstractSequentialList, 198
- ~AbstractSet
 - decaf::util::AbstractSet, 199
- ~AbstractTransportFactory
 - activemq::transport::AbstractTransportFactory, 201
- ~ActiveMQAckHandler
 - activemq::core::ActiveMQAckHandler, 203
- ~ActiveMQBlobMessage
 - activemq::commands::ActiveMQBlobMessage, 205
- ~ActiveMQBlobMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller, 214
 - activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller, 222
 - activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller, 210
 - activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller, 218
 - activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller, 226
 - activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller, 230
- ~ActiveMQBytesMessage
 - activemq::commands::ActiveMQBytesMessage, 236
- ~ActiveMQBytesMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller, 254
 - activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller, 270
 - activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller, 250
 - activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller, 258
- activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller, 262
- activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller, 266
- ~ActiveMQCPP
 - activemq::library::ActiveMQCPP, 320
- ~ActiveMQConnection
 - activemq::core::ActiveMQConnection, 278
- ~ActiveMQConnectionFactory
 - activemq::core::ActiveMQConnectionFactory, 294
- ~ActiveMQConnectionMetaData
 - activemq::core::ActiveMQConnectionMetaData, 304
- ~ActiveMQConsumer
 - activemq::core::ActiveMQConsumer, 312
- ~ActiveMQDestination
 - activemq::commands::ActiveMQDestination, 324
- ~ActiveMQDestinationMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller, 338
 - activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller, 340
 - activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller, 342
 - activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller, 344
 - activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller, 346
 - activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller, 348
- ~ActiveMQException
 - activemq::exceptions::ActiveMQException, 358
- ~ActiveMQMapMessage
 - activemq::commands::ActiveMQMapMessage, 363
- ~ActiveMQMapMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller, 379
 - activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller, 391
 - activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller, 375

- activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller, 383
- activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller, 387
- activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller, 395
- ~ActiveMQMessage
 - activemq::commands::ActiveMQMessage, 398
- ~ActiveMQMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller, 406
 - activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller, 418
 - activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller, 402
 - activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller, 410
 - activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller, 414
 - activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller, 422
- ~ActiveMQMessageTemplate
 - activemq::commands::ActiveMQMessageTemplate, 428
- ~ActiveMQObjectMessage
 - activemq::commands::ActiveMQObjectMessage, 444
- ~ActiveMQObjectMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller, 451
 - activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller, 463
 - activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller, 447
 - activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller, 455
 - activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller, 459
 - activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller, 467
- ~ActiveMQProducer
 - activemq::core::ActiveMQProducer, 472
- ~ActiveMQProperties
 - activemq::util::ActiveMQProperties, 479
- ~ActiveMQQueue
 - activemq::commands::ActiveMQQueue, 484
- ~ActiveMQQueueBrowser
 - activemq::core::ActiveMQQueueBrowser, 488
- ~ActiveMQQueueMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller, 496
- activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller, 508
- activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller, 492
- activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller, 500
- activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller, 504
- activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller, 512
- ~ActiveMQSession
 - activemq::core::ActiveMQSession, 519
- ~ActiveMQSessionExecutor
 - activemq::core::ActiveMQSessionExecutor, 534
- ~ActiveMQStreamMessage
 - activemq::commands::ActiveMQStreamMessage, 540
- ~ActiveMQStreamMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller, 557
 - activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller, 569
 - activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller, 553
 - activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller, 561
 - activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller, 565
 - activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller, 573
- ~ActiveMQTempDestination
 - activemq::commands::ActiveMQTempDestination, 577
- ~ActiveMQTempDestinationMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller, 585
 - activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller, 597
 - activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller, 581
 - activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller, 589
 - activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller, 593
 - activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller, 601
- ~ActiveMQTempQueue
 - activemq::commands::ActiveMQTempQueue, 605
- ~ActiveMQTempQueueMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller, 614

activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller,	708
626	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller,	712
610	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller,	720
618	activemq::core::ActiveMQTransactionContext,
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller,	720
622	~Adler32
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller,	723
630	~Appendable
~ActiveMQTempTopic	decaf::lang::Appendable, 726
activemq::commands::ActiveMQTempTopic,	~AprPool
634	decaf::internal::AprPool, 728
~ActiveMQTempTopicMarshaller	~ArrayPointer
activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller,	decaf::lang::ArrayPointer, 733
647	~AtomicBoolean
activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller,	decaf::util::concurrent::atomic::AtomicBoolean,
655	738
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller,	~AtomicInteger
639	decaf::util::concurrent::atomic::AtomicInteger,
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller,	742
643	~AtomicRefCounter
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller,	decaf::util::concurrent::atomic::AtomicRefCounter,
651	747
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller,	~AtomicReference
659	decaf::util::concurrent::atomic::AtomicReference,
~ActiveMQTextMessage	750
activemq::commands::ActiveMQTextMessage,	~BackupTransport
663	activemq::transport::failover::BackupTransport,
~ActiveMQTextMessageMarshaller	752
activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller,	~BackupTransportPool
676	activemq::transport::failover::BackupTransportPool,
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller,	756
688	~BaseCommand
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller,	activemq::commands::BaseCommand, 759
668	~BaseCommandMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller,	activemq::wireformat::openwire::marshal::v1::BaseCommandM
672	780
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller,	activemq::wireformat::openwire::marshal::v2::BaseCommandM
680	801
activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller,	activemq::wireformat::openwire::marshal::v3::BaseCommandM
684	806
~ActiveMQTopic	activemq::wireformat::openwire::marshal::v4::BaseCommandM
activemq::commands::ActiveMQTopic, 692	773
~ActiveMQTopicMarshaller	activemq::wireformat::openwire::marshal::v5::BaseCommandM
activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller,	787
704	activemq::wireformat::openwire::marshal::v6::BaseCommandM
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller,	794
716	~BaseDataStreamMarshaller
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller,	activemq::wireformat::openwire::marshal::BaseDataStreamMa
696	813
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller,	~BaseDataStructure
700	activemq::wireformat::openwire::marshal::BaseDataStructure,
	831

- ~BindException
 - decaf::net::BindException, 837
- ~BlockingByteArrayInputStream
 - decaf::io::BlockingByteArrayInputStream, 840
- ~BlockingQueue
 - decaf::util::concurrent::BlockingQueue, 846
- ~Boolean
 - decaf::lang::Boolean, 851
- ~BooleanExpression
 - activemq::commands::BooleanExpression, 855
- ~BooleanStream
 - activemq::wireformat::openwire::utils::BooleanStream, 858
- ~BrokenBarrierException
 - decaf::util::concurrent::BrokenBarrierException, 861
- ~BrokerError
 - activemq::commands::BrokerError, 864
- ~BrokerException
 - activemq::exceptions::BrokerException, 867
- ~BrokerId
 - activemq::commands::BrokerId, 870
- ~BrokerIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller, 881
 - activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller, 893
 - activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller, 873
 - activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller, 877
 - activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller, 885
 - activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller, 889
- ~BrokerInfo
 - activemq::commands::BrokerInfo, 897
- ~BrokerInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller, 913
 - activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller, 925
 - activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller, 905
 - activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller, 909
 - activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller, 917
 - activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller, 921
- ~Buffer
 - decaf::nio::Buffer, 930
- ~BufferFactory
 - decaf::internal::nio::BufferFactory, 944
- ~BufferOverflowException
 - decaf::nio::BufferOverflowException, 955
- ~BufferUnderflowException
 - decaf::nio::BufferUnderflowException, 958
- ~BufferedInputStream
 - decaf::io::BufferedInputStream, 936
- ~BufferedOutputStream
 - decaf::io::BufferedOutputStream, 941
- ~Byte
 - decaf::lang::Byte, 962
- ~ByteArrayAdapter
 - decaf::internal::util::ByteArrayAdapter, 976
- ~ByteBuffer
 - decaf::internal::nio::ByteBuffer, 1003
- ~ByteArrayInputStream
 - decaf::io::ByteArrayInputStream, 1023
- ~ByteArrayOutputStream
 - decaf::io::ByteArrayOutputStream, 1029
- ~ByteBuffer
 - decaf::nio::ByteBuffer, 1036
- ~BytesMessage
 - cms::BytesMessage, 1059
- ~CMSEncryptionSupport
 - cms::CMSEncryptionSupport, 1161
- ~CMSEncryptionSupport
 - activemq::util::CMSEncryptionSupport, 1163
- ~CMSProperties
 - cms::CMSProperties, 1166
- ~CMSSecurityException
 - cms::CMSSecurityException, 1169
- ~CRC32
 - decaf::util::CRC32, 1525
- ~CachedConsumer
 - activemq::cmsutil::CachedConsumer, 1072
- ~CachedProducer
 - activemq::cmsutil::CachedProducer, 1076
- ~Callable
 - decaf::util::concurrent::Callable, 1082
- ~CancellationException
 - decaf::util::concurrent::CancellationException, 1084
- ~Certificate
 - decaf::security::cert::Certificate, 1087
- ~CertificateEncodingException
 - decaf::security::cert::CertificateEncodingException, 1091
- ~CertificateException
 - decaf::security::cert::CertificateException, 1093

- ~CertificateExpiredException
 - decaf::security::cert::CertificateExpiredException, 1095
- ~CertificateNotYetValidException
 - decaf::security::cert::CertificateNotYetValidException, 1097
- ~CertificateParsingException
 - decaf::security::cert::CertificateParsingException, 1099
- ~CharArrayBuffer
 - decaf::internal::nio::CharArrayBuffer, 1113
- ~CharBuffer
 - decaf::nio::CharBuffer, 1122
- ~CharSequence
 - decaf::lang::CharSequence, 1135
- ~CheckedInputStream
 - decaf::util::zip::CheckedInputStream, 1138
- ~CheckedOutputStream
 - decaf::util::zip::CheckedOutputStream, 1141
- ~Checksum
 - decaf::util::zip::Checksum, 1142
- ~ClassCastException
 - decaf::lang::exceptions::ClassCastException, 1146
- ~CloseTransportsTask
 - activemq::transport::failover::CloseTransportsTask, 1151
- ~Closeable
 - cms::Closeable, 1148
 - decaf::io::Closeable, 1149
- ~CmsAccessor
 - activemq::cmsutil::CmsAccessor, 1154
- ~CmsDestinationAccessor
 - activemq::cmsutil::CmsDestinationAccessor, 1158
- ~CmsTemplate
 - activemq::cmsutil::CmsTemplate, 1173
- ~Collection
 - decaf::util::Collection, 1186
- ~Command
 - activemq::commands::Command, 1195
- ~CommandVisitor
 - activemq::state::CommandVisitor, 1202
- ~CommandVisitorAdapter
 - activemq::state::CommandVisitorAdapter, 1211
- ~Comparable
 - decaf::lang::Comparable, 1214
- ~Comparator
 - decaf::util::Comparator, 1217
- ~CompositeData
 - activemq::util::CompositeData, 1220
- ~CompositeTask
 - activemq::threads::CompositeTask, 1221
 - decaf::security::cert::CertificateExpiredException, 1095
 - activemq::threads::CompositeTaskRunner, 1224
 - activemq::threads::CompositeTaskRunner, 1224
 - activemq::transport::CompositeTransport, 1226
 - activemq::transport::CompositeTransport, 1226
 - decaf::util::concurrent::ConcurrentMap, 1229
 - decaf::util::concurrent::ConcurrentMap, 1229
 - ~ConcurrentStlMap
 - decaf::util::concurrent::ConcurrentStlMap, 1237
 - ~Condition
 - decaf::util::concurrent::locks::Condition, 1251
 - ~ConditionHandle
 - decaf::util::concurrent::ConditionHandle, 1255
 - ~ConnectException
 - decaf::net::ConnectException, 1260
 - ~Connection
 - cms::Connection, 1263
 - ~ConnectionControl
 - activemq::commands::ConnectionControl, 1268
 - ~ConnectionControlMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller, 1281
 - activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller, 1293
 - activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller, 1273
 - activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller, 1277
 - activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller, 1285
 - activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller, 1289
 - ~ConnectionError
 - activemq::commands::ConnectionError, 1297
 - ~ConnectionErrorMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller, 1313
 - activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller, 1301
 - activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller, 1305
 - activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller, 1309
 - activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller, 1317

- activemq::wireformat::openwire::marshal::v6::ConnectionFactoryMarshaller, 1321
- activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller, 1415
- ~ConnectionFactory
 - cms::ConnectionFactory, 1325
- ~ConnectionId
 - activemq::commands::ConnectionId, 1328
- ~ConnectionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller, 1344
 - activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller, 1332
 - activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller, 1336
 - activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller, 1340
 - activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller, 1348
 - activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller, 1352
- ~ConnectionInfo
 - activemq::commands::ConnectionInfo, 1356
- ~ConnectionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller, 1374
 - activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller, 1362
 - activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller, 1366
 - activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller, 1370
 - activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller, 1378
 - activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller, 1382
- ~ConnectionMetaData
 - cms::ConnectionMetaData, 1386
- ~ConnectionState
 - activemq::state::ConnectionState, 1390
- ~ConnectionStateTracker
 - activemq::state::ConnectionStateTracker, 1394
- ~ConsoleHandler
 - decaf::util::logging::ConsoleHandler, 1399
- ~ConsumerControl
 - activemq::commands::ConsumerControl, 1402
- ~ConsumerControlMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller, 1419
 - activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller, 1407
 - activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller, 1411
- activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller, 1423
- activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller, 1427
- ~ConsumerId
 - activemq::commands::ConsumerId, 1431
- ~ConsumerIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller, 1448
 - activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller, 1436
 - activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller, 1440
 - activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller, 1444
 - activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller, 1452
- activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller, 1456
- ~ConsumerInfo
 - activemq::commands::ConsumerInfo, 1461
- ~ConsumerInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller, 1481
 - activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller, 1469
 - activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller, 1473
 - activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller, 1477
 - activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller, 1485
 - activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller, 1489
- ~ConsumerState
 - activemq::state::ConsumerState, 1492
- ~ControlCommand
 - activemq::commands::ControlCommand, 1494
- ~ControlCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller, 1510
 - activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller, 1498
 - activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller, 1502
 - activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller, 1506
 - activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller, 1514
 - activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller, 1518

- ~CountDownLatch
 - decaf::util::concurrent::CountDownLatch, 1521
- ~DataArrayResponse
 - activemq::commands::DataArrayResponse, 1529
- ~DataArrayResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller, 1544
 - activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller, 1532
 - activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller, 1536
 - activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller, 1540
 - activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller, 1548
 - activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller, 1552
- ~DataFormatException
 - decaf::util::zip::DataFormatException, 1556
- ~DataInput
 - decaf::io::DataInput, 1559
- ~DataInputStream
 - decaf::io::DataInputStream, 1567
- ~DataOutput
 - decaf::io::DataOutput, 1575
- ~DataOutputStream
 - decaf::io::DataOutputStream, 1580
- ~DataResponse
 - activemq::commands::DataResponse, 1584
- ~DataResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller, 1607
 - activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller, 1595
 - activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller, 1599
 - activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller, 1603
 - activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller, 1587
 - activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller, 1591
- ~DataStreamMarshaller
 - activemq::wireformat::openwire::marshal::DataStreamMarshaller, 1611
- ~DataStructure
 - activemq::commands::DataStructure, 1660
- ~Date
 - decaf::util::Date, 1666
- ~DecafRuntime
 - decaf::internal::DecafRuntime, 1670
- ~DedicatedTaskRunner
 - activemq::threads::DedicatedTaskRunner, 1671
- ~DefaultPrefetchPolicy
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
- ~DefaultRedeliveryPolicy
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
- ~DefaultSSLContextMarshaller
 - decaf::internal::net::ssl::DefaultSSLContext, 1684
- ~DefaultSSLServerSocketFactory
 - activemq::core::policies::DefaultSSLServerSocketFactory, 1694
- ~DefaultSSLSocketFactory
 - decaf::internal::net::ssl::DefaultSSLSocketFactory, 1698
- ~DefaultServerSocketFactory
 - decaf::internal::net::DefaultServerSocketFactory, 1683
- ~DefaultSocketFactory
 - decaf::internal::net::DefaultSocketFactory, 1688
- ~DefaultTransportListener
 - activemq::transport::DefaultTransportListener, 1704
- ~Deflater
 - decaf::util::zip::Deflater, 1708
- ~DeflaterOutputStream
 - decaf::util::zip::DeflaterOutputStream, 1718
- ~Delayed
 - activemq::core::Delayed, 1720
- ~DeliveryMode
 - activemq::core::DeliveryMode, 1722
- ~Destination
 - activemq::core::Destination, 1724
- ~DestinationInfo
 - activemq::core::DestinationInfo, 1728
- ~DestinationInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller, 1715
 - activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller, 1733
 - activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller, 1737
 - activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller, 1741
 - activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller, 1753
 - activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller, 1749

- ~DestinationResolver
 - activemq::cmsutil::DestinationResolver, 1756
- ~DiscoveryEvent
 - activemq::commands::DiscoveryEvent, 1759
- ~DiscoveryEventMarshaller
 - activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller, 1779
 - activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller, 1767
 - activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller, 1771
 - activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller, 1775
 - activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller, 1783
 - activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller, 1763
- ~Dispatcher
 - activemq::core::Dispatcher, 1787
- ~Double
 - decaf::lang::Double, 1790
- ~DoubleArrayBuffer
 - decaf::internal::nio::DoubleArrayBuffer, 1803
- ~DoubleBuffer
 - decaf::nio::DoubleBuffer, 1811
- ~DynamicDestinationResolver
 - activemq::cmsutil::DynamicDestinationResolver, 1822
- ~EOFException
 - decaf::io::EOFException, 1826
- ~Entry
 - decaf::util::Map::Entry, 1824
- ~ErrorManager
 - decaf::util::logging::ErrorManager, 1829
- ~Exception
 - decaf::lang::Exception, 1833
- ~ExceptionListener
 - cms::ExceptionListener, 1838
- ~ExceptionResponse
 - activemq::commands::ExceptionResponse, 1840
- ~ExceptionResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller, 1863
 - activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller, 1847
 - activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller, 1851
 - activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller, 1859
- activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller, 1855
- activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller, 1843
- ~ExecutionException
 - decaf::util::concurrent::ExecutionException, 1867
- ~Executor
 - decaf::util::concurrent::Executor, 1870
- ~ExecutorService
 - decaf::util::concurrent::ExecutorService, 1872
- ~FailoverTransport
 - activemq::transport::failover::FailoverTransport, 1875
- ~FailoverTransportFactory
 - activemq::transport::failover::FailoverTransportFactory, 1886
- ~FailoverTransportListener
 - activemq::transport::failover::FailoverTransportListener, 1889
- ~FileDescriptor
 - decaf::io::FileDescriptor, 1892
- ~Filter
 - decaf::util::logging::Filter, 1893
- ~FilterInputStream
 - decaf::io::FilterInputStream, 1896
- ~FilterOutputStream
 - decaf::io::FilterOutputStream, 1901
- ~Float
 - decaf::lang::Float, 1906
- ~FloatArrayBuffer
 - decaf::internal::nio::FloatArrayBuffer, 1919
- ~FloatBuffer
 - decaf::nio::FloatBuffer, 1927
- ~FlushCommand
 - activemq::commands::FlushCommand, 1938
- ~FlushCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller, 1957
 - activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller, 1945
 - activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller, 1949
 - activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller, 1953
 - activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller, 1965
 - activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller, 1945
- ~Flushable
 - decaf::util::Flushable, 1936
- ~Formatter

- decaf::util::logging::Formatter, 1964
- ~Future
 - decaf::util::concurrent::Future, 1967
- ~FutureResponse
 - activemq::transport::correlator::FutureResponse, 1969
- ~GeneralSecurityException
 - decaf::security::GeneralSecurityException, 1972
- ~GenericResource
 - decaf::internal::util::GenericResource, 1974
- ~Handler
 - decaf::util::logging::Handler, 1979
- ~HexStringParser
 - decaf::internal::util::HexStringParser, 1982
- ~HexTable
 - activemq::wireformat::openwire::utils::HexTable, 1984
- ~HttpRequestException
 - decaf::net::HttpRequestException, 1987
- ~IOException
 - decaf::io::IOException, 2143
- ~IOTransport
 - activemq::transport::IOTransport, 2147
- ~IdGenerator
 - activemq::util::IdGenerator, 1989
- ~IllegalArgumentException
 - decaf::lang::exceptions::IllegalArgumentException, 1992
- ~IllegalMonitorStateException
 - decaf::lang::exceptions::IllegalMonitorStateException, 1995
- ~IllegalStateException
 - cms::IllegalStateException, 1997
 - decaf::lang::exceptions::IllegalStateException, 1999
- ~IllegalThreadStateException
 - decaf::lang::exceptions::IllegalThreadStateException, 2002
- ~InactivityMonitor
 - activemq::transport::inactivity::InactivityMonitor, 2005
- ~IndexOutOfBoundsException
 - decaf::lang::exceptions::IndexOutOfBoundsException, 2009
- ~Inet4Address
 - decaf::net::Inet4Address, 2012
- ~Inet6Address
 - decaf::net::Inet6Address, 2015
- ~InetAddress
 - decaf::net::InetAddress, 2018
- ~InetSocketAddress
 - decaf::net::InetSocketAddress, 2023
- ~Inflater
 - decaf::util::zip::Inflater, 2029
- ~InflaterInputStream
 - decaf::util::zip::InflaterInputStream, 2038
- ~InputStream
 - decaf::io::InputStream, 2045
- ~InputStreamReader
 - decaf::io::InputStreamReader, 2054
- ~IntArrayBuffer
 - decaf::internal::nio::IntArrayBuffer, 2060
- ~IntBuffer
 - decaf::nio::IntBuffer, 2068
- ~Integer
 - decaf::lang::Integer, 2080
- ~IntegerResponse
 - activemq::commands::IntegerResponse, 2092
- ~IntegerResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller, 2111
 - activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller, 2099
 - activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller, 2103
 - activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller, 2107
 - activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller, 2115
 - activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller, 2095
- ~InternalCommandListener
 - activemq::transport::mock::InternalCommandListener, 2122
- ~InterruptedException
 - decaf::lang::exceptions::InterruptedException, 2125
- ~InterruptedIOException
 - decaf::io::InterruptedIOException, 2128
- ~InvalidClientIdException
 - cms::InvalidClientIdException, 2130
- ~InvalidDestinationException
 - cms::InvalidDestinationException, 2131
- ~InvalidKeyException
 - decaf::security::InvalidKeyException, 2133
- ~InvalidMarkException
 - decaf::nio::InvalidMarkException, 2136
- ~InvalidSelectorException
 - cms::InvalidSelectorException, 2138
- ~InvalidStateException
 - decaf::lang::exceptions::InvalidStateException, 2140
- ~Iterable
 - decaf::lang::Iterable, 2152
- ~Iterator
 - decaf::util::Iterator, 2154

- ~JournalQueueAck
 - activemq::commands::JournalQueueAck, 2157
- ~JournalQueueAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller, 2180
 - activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller, 2164
 - activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller, 2172
 - activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller, 2176
 - activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller, 2168
 - activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller, 2160
- ~JournalTopicAck
 - activemq::commands::JournalTopicAck, 2184
- ~JournalTopicAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller, 2209
 - activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller, 2193
 - activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller, 2197
 - activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller, 2205
 - activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller, 2189
 - activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller, 2201
- ~JournalTrace
 - activemq::commands::JournalTrace, 2213
- ~JournalTraceMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller, 2232
 - activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller, 2216
 - activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller, 2220
 - activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller, 2228
 - activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller, 2236
 - activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller, 2224
- ~JournalTransaction
 - activemq::commands::JournalTransaction, 2240
- ~JournalTransactionMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller, 2263
- activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller, 2247
- activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller, 2251
- activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller, 2259
- activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller, 2255
- activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller, 2243
- ~KeepAliveInfo
 - activemq::commands::KeepAliveInfo, 2267
- ~KeepAliveInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller, 2290
 - activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller, 2274
 - activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller, 2278
 - activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller, 2282
 - activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller, 2286
 - activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller, 2270
- ~Key
 - decaf::security::Key, 2294
- ~KeyException
 - decaf::security::KeyException, 2296
- ~KeyManagementException
 - decaf::security::KeyManagementException, 2299
- ~LastPartialCommand
 - activemq::commands::LastPartialCommand, 2301
- ~LastPartialCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller, 2325
 - activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller, 2313
 - activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller, 2309
 - activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller, 2321
 - activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller, 2317
 - activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller, 2305
- ~Less
 - decaf::util::comparators::Less, 2328
- ~Level
 - decaf::util::logging::Level, 2334
- ~List
 - decaf::util::List, 2338

- ~ListIterator
 - decaf::util::ListIterator, 2345
- ~LocalTransactionId
 - activemq::commands::LocalTransactionId, 2348
- ~LocalTransactionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller, 2372
 - activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller, 2356
 - activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller, 2360
 - activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller, 2368
 - activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller, 2364
 - activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller, 2352
- ~Lock
 - decaf::util::concurrent::Lock, 2375
 - decaf::util::concurrent::locks::Lock, 2378
- ~LockSupport
 - decaf::util::concurrent::locks::LockSupport, 2384
- ~LogManager
 - decaf::util::logging::LogManager, 2408
- ~LogRecord
 - decaf::util::logging::LogRecord, 2414
- ~LogWriter
 - decaf::util::logging::LogWriter, 2418
- ~Logger
 - decaf::util::logging::Logger, 2389
- ~LoggerHierarchy
 - decaf::util::logging::LoggerHierarchy, 2398
- ~LoggingInputStream
 - activemq::io::LoggingInputStream, 2399
- ~LoggingOutputStream
 - activemq::io::LoggingOutputStream, 2401
- ~LoggingTransport
 - activemq::transport::logging::LoggingTransport, 2403
- ~Long
 - decaf::lang::Long, 2423
- ~LongArrayBuffer
 - decaf::internal::nio::LongArrayBuffer, 2438
- ~LongBuffer
 - decaf::nio::LongBuffer, 2446
- ~LongSequenceGenerator
 - activemq::util::LongSequenceGenerator, 2455
- ~MalformedURLException
 - decaf::net::MalformedURLException, 2457
- ~Map
 - decaf::util::Map, 2460
- ~MapMessage
 - cms::MapMessage, 2474
- ~MarkBlockLogger
 - decaf::util::logging::MarkBlockLogger, 2483
- ~MarshalAware
 - activemq::wireformat::openwire::marshal::v1::MarshalAware, 2484
- ~MarshallerFactory
 - activemq::wireformat::openwire::marshal::v1::MarshallerFactory, 2491
 - activemq::wireformat::openwire::marshal::v2::MarshallerFactory, 2492
 - activemq::wireformat::openwire::marshal::v3::MarshallerFactory, 2488
 - activemq::wireformat::openwire::marshal::v4::MarshallerFactory, 2489
 - activemq::wireformat::openwire::marshal::v5::MarshallerFactory, 2490
 - activemq::wireformat::openwire::marshal::v6::MarshallerFactory, 2487
- ~MarshallSupport
 - activemq::util::MarshallSupport, 2494
- ~Math
 - decaf::lang::Math, 2499
- ~MemoryUsage
 - activemq::util::MemoryUsage, 2513
- ~Message
 - activemq::commands::Message, 2520
 - cms::Message, 2538
- ~MessageAck
 - activemq::commands::MessageAck, 2560
- ~MessageAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller, 2582
 - activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller, 2570
 - activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller, 2574
 - activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller, 2578
 - activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller, 2586
 - activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller, 2566
- ~MessageConsumer
 - cms::MessageConsumer, 2590
- ~MessageCreator
 - activemq::cmsutil::MessageCreator, 2593
- ~MessageDispatch
 - activemq::commands::MessageDispatch, 2595
- ~MessageDispatchChannel
 - activemq::core::MessageDispatchChannel, 2600

- ~MessageDispatchMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller, 2623
 - activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller, 2607
 - activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller, 2611
 - activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller, 2619
 - activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller, 2615
 - activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller, 2627
- ~MessageDispatchNotification
 - activemq::commands::MessageDispatchNotification, 2631
- ~MessageDispatchNotificationMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller, 2652
 - activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller, 2640
 - activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller, 2644
 - activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller, 2648
 - activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller, 2656
 - activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller, 2636
- ~MessageEOFException
 - cms::MessageEOFException, 2661
- ~MessageEnumeration
 - cms::MessageEnumeration, 2659
- ~MessageFormatException
 - cms::MessageFormatException, 2662
- ~MessageId
 - activemq::commands::MessageId, 2664
- ~MessageIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller, 2689
 - activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller, 2669
 - activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller, 2681
 - activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller, 2673
 - activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller, 2677
 - activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller, 2685
- ~MessageListener
 - cms::MessageListener, 2692
- ~MessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessageMarshaller, 2714
 - activemq::wireformat::openwire::marshal::v2::MessageMarshaller, 2704
 - activemq::wireformat::openwire::marshal::v3::MessageMarshaller, 2699
 - activemq::wireformat::openwire::marshal::v4::MessageMarshaller, 2709
 - activemq::wireformat::openwire::marshal::v5::MessageMarshaller, 2694
 - activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 2719
- ~MessageNotReadableException
 - cms::MessageNotReadableException, 2723
- ~MessageNotWritableException
 - cms::MessageNotWritableException, 2724
- ~MessageProducer
 - cms::MessageProducer, 2726
- ~MessagePropertyInterceptor
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2733
- ~MessagePull
 - activemq::commands::MessagePull, 2740
- ~MessagePullMarshaller
 - activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller, 2761
 - activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller, 2745
 - activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller, 2753
 - activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller, 2757
 - activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller, 2749
 - activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller, 2765
- ~MockTransport
 - activemq::transport::mock::MockTransport, 2770
- ~MockTransportFactory
 - activemq::transport::mock::MockTransportFactory, 2780
- ~Mutex
 - cms::util::concurrent::Mutex, 2783
- ~MutexHandle
 - cms::util::concurrent::MutexHandle, 2787
- ~Network
 - activemq::net::Network, 2791
- ~NetworkBridgeFilter
 - activemq::commands::NetworkBridgeFilter, 2794
- ~NetworkBridgeFilterMarshaller
 - activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller, 2817

- activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller, 2797
- activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller, 2809
- activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller, 2813
- activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller, 2805
- activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller, 2801
- ~NoRouteToHostException
 - decaf::net::NoRouteToHostException, 2821
- ~NoSuchAlgorithmException
 - decaf::security::NoSuchAlgorithmException, 2824
- ~NoSuchElementException
 - decaf::lang::exceptions::NoSuchElementException, 2827
- ~NoSuchProviderException
 - decaf::security::NoSuchProviderException, 2830
- ~NullPointerException
 - decaf::lang::exceptions::NullPointerException, 2833
- ~Number
 - decaf::lang::Number, 2835
- ~NumberFormatException
 - decaf::lang::exceptions::NumberFormatException, 2840
- ~ObjectMessage
 - cms::ObjectMessage, 2841
- ~OpenSSLContextSpi
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2843
- ~OpenSSLParameters
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2845
- ~OpenSSLServerSocket
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2849
- ~OpenSSLServerSocketFactory
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2855
- ~OpenSSLSocket
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2862
- ~OpenSSLSocketException
 - decaf::internal::net::ssl::openssl::OpenSSLSocketException, 2873
- ~OpenSSLSocketFactory
 - decaf::internal::net::ssl::openssl::OpenSSLSocketFactory, 2877
- ~OpenSSLSocketInputStream
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
- ~OpenSSLServerSocketOutputStream
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocketOutputStream, 2886
- ~OpenWireFormat
 - activemq::wireformat::openwire::OpenWireFormat, 2890
- ~OpenWireFormatFactory
 - activemq::wireformat::openwire::OpenWireFormatFactory, 2899
- ~OpenWireFormatNegotiator
 - activemq::wireformat::openwire::OpenWireFormatNegotiator, 2902
- ~OpenWireResponseBuilder
 - activemq::wireformat::openwire::OpenWireResponseBuilder, 2905
- ~OutputStream
 - decaf::io::OutputStream, 2909
- ~OutputStreamWriter
 - decaf::io::OutputStreamWriter, 2916
- ~PartialCommand
 - activemq::commands::PartialCommand, 2919
- ~PartialCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2943
 - activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2927
 - activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2935
 - activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2939
 - activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2931
 - activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2923
- ~Pointer
 - decaf::lang::Pointer, 2949
- ~PooledSession
 - activemq::cmsutil::PooledSession, 2957
- ~PooledThread
 - decaf::util::concurrent::PooledThread, 2968
- ~PooledThreadListener
 - decaf::util::concurrent::PooledThreadListener, 2971
- ~PortUnreachableException
 - decaf::net::PortUnreachableException, 2974
- ~PrefetchPolicy
 - activemq::core::PrefetchPolicy, 2977
- ~PrimitiveList
 - activemq::util::PrimitiveList, 2982
- ~PrimitiveMap
 - activemq::util::PrimitiveMap, 2984

- activemq::util::PrimitiveMap, 2993
- ~PrimitiveTypesMarshaller
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3003
- ~PrimitiveValueConverter
 - activemq::util::PrimitiveValueConverter, 3010
- ~PrimitiveValueNode
 - activemq::util::PrimitiveValueNode, 3018
- ~Principal
 - decaf::security::Principal, 3026
- ~PriorityQueue
 - decaf::util::PriorityQueue, 3031
- ~ProducerAck
 - activemq::commands::ProducerAck, 3037
- ~ProducerAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller, 3061
 - activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller, 3041
 - activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller, 3049
 - activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller, 3045
 - activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller, 3053
 - activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller, 3057
- ~ProducerCallback
 - activemq::cmsutil::ProducerCallback, 3064
- ~ProducerExecutor
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3065
- ~ProducerId
 - activemq::commands::ProducerId, 3068
- ~ProducerIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller, 3093
 - activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller, 3073
 - activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller, 3081
 - activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller, 3077
 - activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller, 3085
 - activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3089
- ~ProducerInfo
 - activemq::commands::ProducerInfo, 3097
- ~ProducerInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller, 3110
- activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller, 3106
- activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller, 3118
- activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller, 3102
- activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller, 3114
- activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller, 3122
- ~ProducerState
 - activemq::state::ProducerState, 3125
- ~Properties
 - decaf::util::Properties, 3128
- ~PropertiesChangeListener
 - decaf::util::logging::PropertiesChangeListener, 3135
- ~ProtocolException
 - decaf::net::ProtocolException, 3138
- ~PublicKey
 - decaf::security::PublicKey, 3140
- ~PushbackInputStream
 - decaf::io::PushbackInputStream, 3143
- ~Queue
 - cms::Queue, 3148
 - decaf::util::Queue, 3150
- ~QueueBrowser
 - cms::QueueBrowser, 3153
- ~ReadChecker
 - activemq::transport::inactivity::ReadChecker, 3162
- ~ReadOnlyBufferException
 - decaf::nio::ReadOnlyBufferException, 3170
- ~ReadWriteLock
 - decaf::util::concurrent::locks::ReadWriteLock, 3173
- ~Readable
 - decaf::lang::Readable, 3160
- ~Reader
 - decaf::io::Reader, 3164
- ~ReceiveExecutor
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
- ~RedeliveryPolicy
 - activemq::core::RedeliveryPolicy, 3178
- ~ReentrantLock
 - decaf::util::concurrent::locks::ReentrantLock, 3185
- ~RejectedExecutionException
 - decaf::util::concurrent::RejectedExecutionException, 3190
- ~RejectedExecutionHandler
 - decaf::util::concurrent::RejectedExecutionHandler, 3192

- ~RemoveInfo
 - activemq::commands::RemoveInfo, 3195
- ~RemoveInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller, 3211
 - activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller, 3199
 - activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller, 3207
 - activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller, 3219
 - activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller, 3215
 - activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller, 3203
- ~RemoveSubscriptionInfo
 - activemq::commands::RemoveSubscriptionInfo, 3223
- ~RemoveSubscriptionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller, 3228
 - activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller, 3236
 - activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller, 3232
 - activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller, 3248
 - activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller, 3244
 - activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller, 3240
- ~ReplayCommand
 - activemq::commands::ReplayCommand, 3252
- ~ReplayCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller, 3259
 - activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller, 3263
 - activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller, 3267
 - activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller, 3255
 - activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller, 3275
 - activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller, 3271
- ~ResolveProducerExecutor
 - activemq::cmsutil::CmsTemplate::ResolveProducerExecutor, 3278
- ~ResolveReceiveExecutor
 - activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor, 3279
- ~Resource
 - decaf::internal::util::Resource, 3280
- ~ResourceLifecycleManager
 - activemq::cmsutil::ResourceLifecycleManager, 3287
 - decaf::internal::util::ResourceLifecycleManager, 3288
- ~Response
 - activemq::commands::Response, 3286
- ~ResponseBuilder
 - activemq::transport::mock::ResponseBuilder, 3289
- ~ResponseCorrelator
 - activemq::transport::correlator::ResponseCorrelator, 3292
- ~ResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::ResponseMarshaller, 3316
 - activemq::wireformat::openwire::marshal::v2::ResponseMarshaller, 3301
 - activemq::wireformat::openwire::marshal::v3::ResponseMarshaller, 3311
 - activemq::wireformat::openwire::marshal::v4::ResponseMarshaller, 3296
 - activemq::wireformat::openwire::marshal::v5::ResponseMarshaller, 3306
 - activemq::wireformat::openwire::marshal::v6::ResponseMarshaller, 3321
- ~Runnable
 - decaf::lang::Runnable, 3325
- ~Runtime
 - decaf::lang::Runtime, 3326
- ~RuntimeException
 - decaf::lang::exceptions::RuntimeException, 3329
- ~SSLContext
 - decaf::net::ssl::SSLContext, 3545
- ~SSLContextSpi
 - decaf::net::ssl::SSLContextSpi, 3548
- ~SSLParameters
 - decaf::net::ssl::SSLParameters, 3552
- ~SSLServerSocket
 - decaf::net::ssl::SSLServerSocket, 3556
- ~SSLServerSocketFactory
 - decaf::net::ssl::SSLServerSocketFactory, 3561
- ~SSLSocketFactory
 - decaf::net::ssl::SSLSocketFactory, 3572
- ~SecureRandom
 - decaf::security::SecureRandom, 3333
 - decaf::internal::security::SecureRandomImpl, 3337

- ~SecureRandomSpi
 - decaf::security::SecureRandomSpi, 3339
- ~Semaphore
 - decaf::util::concurrent::Semaphore, 3344
- ~SendExecutor
 - activemq::cmsutil::CmsTemplate::SendExecutor, 3350
- ~ServerSocket
 - decaf::net::ServerSocket, 3355
- ~ServerSocketFactory
 - decaf::net::ServerSocketFactory, 3362
- ~Session
 - cms::Session, 3368
- ~SessionCallback
 - activemq::cmsutil::SessionCallback, 3378
- ~SessionId
 - activemq::commands::SessionId, 3380
- ~SessionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller, 3404
 - activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller, 3384
 - activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller, 3400
 - activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller, 3388
 - activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller, 3396
 - activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3392
- ~SessionInfo
 - activemq::commands::SessionInfo, 3408
- ~SessionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller, 3420
 - activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller, 3428
 - activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller, 3424
 - activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller, 3432
 - activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller, 3416
 - activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller, 3412
- ~SessionPool
 - activemq::cmsutil::SessionPool, 3435
- ~SessionState
 - activemq::state::SessionState, 3438
- ~Set
 - decaf::util::Set, 3439
- ~Short
 - decaf::lang::Short, 3442
- ~ShortArrayBuffer
 - decaf::internal::nio::ShortArrayBuffer, 3453
- ~ShortBuffer
 - decaf::nio::ShortBuffer, 3461
- ~ShutdownInfo
 - activemq::commands::ShutdownInfo, 3471
- ~ShutdownInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller, 3482
 - activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller, 3478
 - activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller, 3490
 - activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller, 3494
 - activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller, 3486
 - activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3474
- ~SignatureException
 - decaf::security::SignatureException, 3498
- ~SimpleFormatter
 - decaf::util::logging::SimpleFormatter, 3500
- ~SimpleLogger
 - decaf::util::logging::SimpleLogger, 3501
- ~Socket
 - decaf::net::Socket, 3508
- ~SocketAddress
 - decaf::net::SocketAddress, 3519
- ~SocketException
 - decaf::net::SocketException, 3522
- ~SocketFactory
 - decaf::net::SocketFactory, 3525
- ~SocketFileDescriptor
 - decaf::internal::net::SocketFileDescriptor, 3528
- ~SocketImpl
 - decaf::net::SocketImpl, 3531
- ~SocketImplFactory
 - decaf::net::SocketImplFactory, 3537
- ~SocketOptions
 - decaf::net::SocketOptions, 3539
- ~SocketTimeoutException
 - decaf::net::SocketTimeoutException, 3543
- ~SslTransport
 - activemq::transport::tcp::SslTransport, 3575
- ~SslTransportFactory
 - activemq::transport::tcp::SslTransportFactory, 3576
- ~StandardErrorOutputStream
 - decaf::internal::io::StandardErrorOutputStream, 3580
- ~StandardInputStream

- decaf::internal::io::StandardInputStream, 3582
- ~StandardOutputStream
 - decaf::internal::io::StandardOutputStream, 3584
- ~Startable
 - cms::Startable, 3586
- ~StaticInitializer
 - activemq::core::ActiveMQConstants::StaticInitializer, 3588
- ~StlList
 - decaf::util::StlList, 3594
- ~StlMap
 - decaf::util::StlMap, 3606
- ~StlQueue
 - decaf::util::StlQueue, 3617
- ~StlSet
 - decaf::util::StlSet, 3625
- ~StompFrame
 - activemq::wireformat::stomp::StompFrame, 3634
- ~StompHelper
 - activemq::wireformat::stomp::StompHelper, 3639
- ~StompWireFormat
 - activemq::wireformat::stomp::StompWireFormat, 3644
- ~StompWireFormatFactory
 - activemq::wireformat::stomp::StompWireFormatFactory, 3647
- ~Stoppable
 - cms::Stoppable, 3648
- ~StreamHandler
 - decaf::util::logging::StreamHandler, 3650
- ~StreamMessage
 - cms::StreamMessage, 3655
- ~String
 - decaf::lang::String, 3666
- ~StringTokenizer
 - decaf::util::StringTokenizer, 3669
- ~SubscriptionInfo
 - activemq::commands::SubscriptionInfo, 3672
- ~SubscriptionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller, 3681
 - activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller, 3697
 - activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller, 3677
 - activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller, 3689
 - activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller, 3685
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfo, 3693
- ~Synchronizable
 - decaf::util::concurrent::Synchronizable, 3701
- ~SynchronizableImpl
 - decaf::internal::util::concurrent::SynchronizableImpl, 3712
- ~Synchronization
 - activemq::core::Synchronization, 3715
- ~SynchronousQueue
 - decaf::util::concurrent::SynchronousQueue, 3718
- ~System
 - decaf::lang::System, 3728
- ~Task
 - activemq::threads::Task, 3734
- ~TaskListener
 - decaf::util::concurrent::TaskListener, 3735
- ~TaskRunner
 - activemq::threads::TaskRunner, 3736
- ~TcpSocket
 - decaf::internal::net::tcp::TcpSocket, 3741
- ~TcpSocketInputStream
 - decaf::internal::net::tcp::TcpSocketInputStream, 3748
- ~TcpSocketOutputStream
 - decaf::internal::net::tcp::TcpSocketOutputStream, 3750
- ~TcpTransport
 - activemq::transport::tcp::TcpTransport, 3753
- ~TcpTransportFactory
 - activemq::transport::tcp::TcpTransportFactory, 3757
- ~TemporaryQueue
 - cms::TemporaryQueue, 3759
- ~TemporaryTopic
 - cms::TemporaryTopic, 3761
- ~TextMessage
 - cms::TextMessage, 3763
- ~Thread
 - decaf::lang::Thread, 3769
- ~ThreadFactory
 - decaf::util::concurrent::ThreadFactory, 3774
- ~ThreadPool
 - decaf::lang::ThreadGroup, 3776
- ~ThreadPool
 - decaf::util::concurrent::ThreadPool, 3779
- ~Throwable
 - decaf::lang::Throwable, 3784
- ~TimeUnit
 - decaf::util::concurrent::TimeUnit, 3809

- ~TimeoutException
 - decaf::util::concurrent::TimeoutException, 3788
- ~Timer
 - decaf::util::Timer, 3792
- ~TimerTask
 - decaf::util::TimerTask, 3802
- ~TimerTaskHeap
 - decaf::internal::util::TimerTaskHeap, 3805
- ~Topic
 - cms::Topic, 3817
- ~Tracked
 - activemq::state::Tracked, 3818
- ~TransactionId
 - activemq::commands::TransactionId, 3820
- ~TransactionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller, 3828
 - activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller, 3832
 - activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller, 3836
 - activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller, 3840
 - activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller, 3824
 - activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller, 3844
- ~TransactionInfo
 - activemq::commands::TransactionInfo, 3848
- ~TransactionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller, 3856
 - activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller, 3872
 - activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller, 3860
 - activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller, 3868
 - activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller, 3852
 - activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller, 3864
- ~TransactionState
 - activemq::state::TransactionState, 3876
- ~TransferQueue
 - decaf::internal::util::concurrent::TransferQueue, 3878
- ~TransferStack
 - decaf::internal::util::concurrent::TransferStack, 3881
- ~Transport
 - activemq::transport::Transport, 3884
- ~TransportFactory
 - activemq::transport::TransportFactory, 3889
- ~TransportFilter
 - activemq::transport::TransportFilter, 3893
- ~TransportListener
 - activemq::transport::TransportListener, 3900
- ~TransportRegistry
 - activemq::transport::TransportRegistry, 3903
- ~URI
 - decaf::net::URI, 3924
- ~URIEncoderDecoder
 - decaf::internal::net::URIEncoderDecoder, 3932
- ~URIHelper
 - decaf::internal::net::URIHelper, 3936
- ~URIPool
 - activemq::transport::failover::URIPool, 3942
- ~URISyntaxException
 - decaf::net::URISyntaxException, 3950
- ~URIType
 - decaf::net::URIType, 3954
- ~URL
 - decaf::net::URL, 3961
- ~URLDecoder
 - decaf::net::URLDecoder, 3962
- ~URLEncoder
 - decaf::net::URLEncoder, 3963
- ~UTFDataFormatException
 - decaf::io::UTFDataFormatException, 3968
- ~UUID
 - decaf::util::UUID, 3971
- ~UncaughtExceptionHandler
 - decaf::util::UncaughtExceptionHandler, 3906
- ~UnknownHostException
 - decaf::net::UnknownHostException, 3908
- ~UnknownServiceException
 - decaf::net::UnknownServiceException, 3911
- ~UnsupportedEncodingException
 - decaf::io::UnsupportedEncodingException, 3915
- ~UnsupportedOperationException
 - cms::UnsupportedOperationException, 3919
 - decaf::lang::exceptions::UnsupportedOperationException, 3917
- ~Usage
 - activemq::util::Usage, 3964
- ~WireFormat

- activemq::wireformat::WireFormat, 3977
- ~WireFormatFactory
 - activemq::wireformat::WireFormatFactory, 3980
- ~WireFormatInfo
 - activemq::commands::WireFormatInfo, 3984
- ~WireFormatInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller, 4009
 - activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller, 4001
 - activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller, 4013
 - activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller, 4005
 - activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller, 3993
 - activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller, 3997
- ~WireFormatNegotiator
 - activemq::wireformat::WireFormatNegotiator, 4016
- ~WireFormatRegistry
 - activemq::wireformat::WireFormatRegistry, 4018
- ~WriteChecker
 - activemq::transport::inactivity::WriteChecker, 4020
- ~Writer
 - decaf::io::Writer, 4022
- ~X500Principal
 - decaf::security::auth::x500::X500Principal, 4027
- ~X509Certificate
 - decaf::security::cert::X509Certificate, 4029
- ~XATransactionId
 - activemq::commands::XATransactionId, 4032
- ~XATransactionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller, 4049
 - activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller, 4041
 - activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller, 4053
 - activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller, 4045
 - activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller, 4057
 - activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller, 4037
- ~XMLFormatter
 - decaf::util::logging::XMLFormatter, 4060
- ~ZipException
 - decaf::util::zip::ZipException, 4065
- _FALSE
 - decaf::lang::Boolean, 854
- _TRUE
 - decaf::lang::Boolean, 854
- _array
 - decaf::internal::nio::CharArrayBuffer, 1118
- _ByteBuffer
 - decaf::nio::Buffer, 933
- _deflate
 - deflate.h, 4727
- _length_code
 - trees.h, 4735
- _limit
 - decaf::nio::Buffer, 933
- _mark
 - decaf::nio::Buffer, 933
- _markSet
 - decaf::nio::Buffer, 933
- _position
 - decaf::nio::Buffer, 933
- _tr_tally_dist
 - deflate.h, 4726
- _tr_tally_lit
 - deflate.h, 4726
- ABORT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- abs
 - decaf::lang::Math, 2499, 2500
- AbstractCollection
 - decaf::util::AbstractCollection, 182
- AbstractQueue
 - decaf::util::AbstractQueue, 195
- accept
 - decaf::internal::net::ssl::OpenSSLServerSocket, 2849
 - decaf::internal::net::tcp::TcpSocket, 3741
 - decaf::net::ServerSocket, 3356
 - decaf::net::SocketImpl, 3531
- accepted
 - decaf::net::ServerSocket, 3356
- ACK
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- ACK_AUTO
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- ACK_CLIENT

- activemq::wireformat::stomp::StompCommandConstants, 3631
- ACK_INDIVIDUAL
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- ACK_TYPE_CONSUMED
 - activemq::core::ActiveMQConstants, 308
- ACK_TYPE_DELIVERED
 - activemq::core::ActiveMQConstants, 308
- ACK_TYPE_INDIVIDUAL
 - activemq::core::ActiveMQConstants, 308
- ACK_TYPE_POISON
 - activemq::core::ActiveMQConstants, 308
- ACK_TYPE_REDELIVERED
 - activemq::core::ActiveMQConstants, 308
- acknowledge
 - activemq::commands::ActiveMQMessageTemplate, 428
 - activemq::core::ActiveMQConsumer, 312
 - activemq::core::ActiveMQSession, 519
 - cms::Message, 2538
- acknowledgeMessage
 - activemq::core::ActiveMQAckHandler, 203
- AcknowledgeMode
 - cms::Session, 3368
- AckType
 - activemq::core::ActiveMQConstants, 308
- ackType
 - activemq::commands::MessageAck, 2564
- acquire
 - decaf::util::concurrent::Semaphore, 3344
- acquireUninterruptibly
 - decaf::util::concurrent::Semaphore, 3345
- action
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3066
- activemq, 85
- activemq/exceptions/ExceptionDefines.h
 - AMQ_CATCH_EXCEPTION_CONVERT, 4170
 - AMQ_CATCH_NOTHROW, 4170
 - AMQ_CATCH_RETHROW, 4171
 - AMQ_CATCHALL_NOTHROW, 4171
 - AMQ_CATCHALL_THROW, 4171
- activemq/util/Config.h
 - AMQCPP_API, 4227
- activemq::cmsutil, 86
- activemq::cmsutil::CachedConsumer, 1071
 - ~CachedConsumer, 1072
 - CachedConsumer, 1072
 - close, 1072
 - getMessageListener, 1072
 - getMessageSelector, 1072
 - operator=, 1072
- activemq::cmsutil::CachedProducer, 1075
 - ~CachedProducer, 1076
 - CachedProducer, 1076
 - close, 1076
 - getDeliveryMode, 1076
 - getDisableMessageID, 1077
 - getDisableMessageTimeStamp, 1077
 - getPriority, 1077
 - getTimeToLive, 1077
 - operator=, 1078
 - send, 1078, 1079
 - setDeliveryMode, 1080
 - setDisableMessageID, 1080
 - setDisableMessageTimeStamp, 1080
 - setPriority, 1080
 - setTimeToLive, 1081
- activemq::cmsutil::CmsAccessor, 1153
 - ~CmsAccessor, 1154
 - checkConnectionFactory, 1154
 - CmsAccessor, 1154
 - createConnection, 1154
 - createSession, 1155
 - destroy, 1155
 - getConnectionFactory, 1155
 - getResourceLifecycleManager, 1155
 - getSessionAcknowledgeMode, 1155
 - init, 1156
 - operator=, 1156
 - setConnectionFactory, 1156
 - setSessionAcknowledgeMode, 1156
- activemq::cmsutil::CmsDestinationAccessor, 1157
 - ~CmsDestinationAccessor, 1158
 - checkDestinationResolver, 1158
 - CmsDestinationAccessor, 1158
 - destroy, 1158
 - getDestinationResolver, 1158
 - init, 1158
 - isPubSubDomain, 1158
 - operator=, 1159
 - resolveDestinationName, 1159
 - setDestinationResolver, 1159
 - setPubSubDomain, 1159
- activemq::cmsutil::CmsTemplate, 1170
 - ~CmsTemplate, 1173
 - CmsTemplate, 1173
 - DEFAULT_PRIORITY, 1182
 - DEFAULT_TIME_TO_LIVE, 1182
 - destroy, 1173
 - execute, 1174
 - getDefaultDestination, 1175

- getDefaultDestinationName, 1175
- getDeliveryMode, 1175
- getPriority, 1175
- getReceiveTimeout, 1175
- getTimeToLive, 1176
- init, 1176
- isExplicitQosEnabled, 1176
- isMessageIdEnabled, 1176
- isMessageTimestampEnabled, 1176
- isNoLocal, 1176
- operator=, 1176
- ProducerExecutor, 1182
- receive, 1176, 1177
- RECEIVE_TIMEOUT_INDEFINITE_WAIT, 1182
- RECEIVE_TIMEOUT_NO_WAIT, 1182
- ReceiveExecutor, 1182
- receiveSelected, 1177, 1178
- ResolveProducerExecutor, 1182
- ResolveReceiveExecutor, 1182
- send, 1178, 1179
- SendExecutor, 1182
- setDefaultDestination, 1179
- setDefaultDestinationName, 1179
- setDeliveryMode, 1180
- setDeliveryPersistent, 1180
- setExplicitQosEnabled, 1180
- setMessageIdEnabled, 1180
- setMessageTimestampEnabled, 1181
- setNoLocal, 1181
- setPriority, 1181
- setPubSubDomain, 1181
- setReceiveTimeout, 1181
- setTimeToLive, 1181
- activemq::cmsutil::CmsTemplate::ProducerExecutor, 3065
 - ~ProducerExecutor, 3065
 - action, 3066
 - destination, 3066
 - doInCms, 3065
 - getDestination, 3066
 - operator=, 3066
 - parent, 3066
 - ProducerExecutor, 3065
- activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3174
 - ~ReceiveExecutor, 3175
 - destination, 3176
 - doInCms, 3175
 - getDestination, 3175
 - getMessage, 3175
 - message, 3176
 - noLocal, 3176
 - operator=, 3175
 - parent, 3176
 - ReceiveExecutor, 3175
 - selector, 3176
- activemq::cmsutil::CmsTemplate::ResolveProducerExecutor, 3278
 - ~ResolveProducerExecutor, 3278
 - getDestination, 3278
 - operator=, 3278
 - ResolveProducerExecutor, 3278
- activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor, 3279
 - ~ResolveReceiveExecutor, 3279
 - getDestination, 3279
 - operator=, 3279
 - ResolveReceiveExecutor, 3279
- activemq::cmsutil::CmsTemplate::SendExecutor, 3350
 - ~SendExecutor, 3350
 - doInCms, 3350
 - operator=, 3350
 - SendExecutor, 3350
- activemq::cmsutil::DestinationResolver, 1756
 - ~DestinationResolver, 1756
 - destroy, 1756
 - init, 1756
 - resolveDestinationName, 1757
- activemq::cmsutil::DynamicDestinationResolver, 1821
 - ~DynamicDestinationResolver, 1822
 - destroy, 1822
 - DynamicDestinationResolver, 1822
 - init, 1822
 - operator=, 1822
 - resolveDestinationName, 1822
- activemq::cmsutil::MessageCreator, 2593
 - ~MessageCreator, 2593
 - createMessage, 2593
- activemq::cmsutil::PooledSession, 2955
 - ~PooledSession, 2957
 - close, 2957
 - commit, 2958
 - createBrowser, 2958
 - createBytesMessage, 2959
 - createCachedConsumer, 2959
 - createCachedProducer, 2960
 - createConsumer, 2960, 2961
 - createDurableConsumer, 2961
 - createMapMessage, 2962
 - createMessage, 2962
 - createProducer, 2962
 - createQueue, 2963
 - createStreamMessage, 2963
 - createTemporaryQueue, 2963
 - createTemporaryTopic, 2963

- createTextMessage, 2964
- createTopic, 2964
- getAcknowledgeMode, 2965
- getSession, 2965
- isTransacted, 2965
- operator=, 2965
- PooledSession, 2957
- recover, 2966
- rollback, 2966
- unsubscribe, 2966
- activemq::cmsutil::ProducerCallback, 3064
 - ~ProducerCallback, 3064
 - doInCms, 3064
- activemq::cmsutil::ResourceLifecycleManager, 3282
 - ~ResourceLifecycleManager, 3283
 - addConnection, 3283
 - addDestination, 3283
 - addMessageConsumer, 3283
 - addMessageProducer, 3283
 - addSession, 3283
 - destroy, 3284
 - operator=, 3284
 - releaseAll, 3284
 - ResourceLifecycleManager, 3283
- activemq::cmsutil::SessionCallback, 3378
 - ~SessionCallback, 3378
 - doInCms, 3378
- activemq::cmsutil::SessionPool, 3435
 - ~SessionPool, 3435
 - getResourceLifecycleManager, 3436
 - operator=, 3436
 - returnSession, 3436
 - SessionPool, 3435
 - takeSession, 3436
- activemq::commands, 87
- activemq::commands::ActiveMQBlobMessage, 204
 - ~ActiveMQBlobMessage, 205
 - ActiveMQBlobMessage, 205
 - BINARY_MIME_TYPE, 208
 - clone, 205
 - cloneDataStructure, 205
 - copyDataStructure, 205
 - equals, 206
 - getDataStructureType, 206
 - getMimeType, 206
 - getName, 206
 - getRemoteBlobUrl, 206
 - ID_ACTIVEMQBLOBMESSAGE, 208
 - isDeletedByBroker, 207
 - setDeletedByBroker, 207
 - setMimeType, 207
 - setName, 207
 - setRemoteBlobUrl, 207
 - toString, 207
- activemq::commands::ActiveMQBytesMessage, 233
 - ~ActiveMQBytesMessage, 236
 - ActiveMQBytesMessage, 236
 - clearBody, 236
 - clone, 236
 - cloneDataStructure, 236
 - copyDataStructure, 237
 - equals, 237
 - getBodyBytes, 237
 - getBodyLength, 237
 - getDataStructureType, 238
 - ID_ACTIVEMQBYTESMESSAGE, 248
 - onSend, 238
 - readBoolean, 238
 - readByte, 238
 - readBytes, 239
 - readChar, 240
 - readDouble, 240
 - readFloat, 241
 - readInt, 241
 - readLong, 241
 - readShort, 242
 - readString, 242
 - readUnsignedShort, 242
 - readUTF, 243
 - reset, 243
 - setBodyBytes, 243
 - toString, 244
 - writeBoolean, 244
 - writeByte, 244
 - writeBytes, 245
 - writeChar, 245
 - writeDouble, 246
 - writeFloat, 246
 - writeInt, 246
 - writeLong, 247
 - writeShort, 247
 - writeString, 247
 - writeUnsignedShort, 247
 - writeUTF, 248
- activemq::commands::ActiveMQDestination, 322
 - ~ActiveMQDestination, 324
 - ActiveMQDestination, 324
 - advisory, 331
 - ADVISORY_PREFIX, 331
 - cloneDataStructure, 324
 - COMPOSITE_SEPARATOR, 331
 - CONNECTION_ADVISORY_PREFIX, 331
 - CONSUMER_ADVISORY_PREFIX, 331

- copyDataStructure, 325
- createDestination, 325
- createTemporaryName, 325
- DEFAULT_ORDERED_TARGET, 331
- equals, 325
- exclusive, 331
- getClientId, 326
- getCMSDestination, 326
- getDataStructureType, 326
- getDestinationType, 327
- getOptions, 327
- getOrderedTarget, 327
- getPhysicalName, 327
- ID_ACTIVEMQDESTINATION, 332
- isAdvisory, 327
- isComposite, 328
- isConnectionAdvisory, 328
- isConsumerAdvisory, 328
- isExclusive, 328
- isOrdered, 328
- isProducerAdvisory, 328
- isQueue, 329
- isTemporary, 329
- isTopic, 329
- isWildcard, 329
- options, 332
- ordered, 332
- orderedTarget, 332
- physicalName, 332
- PRODUCER_ADVISORY_PREFIX, 332
- QUEUE_QUALIFIED_PREFIX, 332
- setAdvisory, 329
- setExclusive, 329
- setOrdered, 330
- setOrderedTarget, 330
- setPhysicalName, 330
- TEMP_POSTFIX, 332
- TEMP_PREFIX, 332
- TEMP_QUEUE_QUALIFIED_PREFIX, 332
- TEMP_TOPIC_QUALIFIED_PREFIX, 332
- TOPIC_QUALIFIED_PREFIX, 332
- toString, 330
- activemq::commands::ActiveMQDestination::DestinationFilter, 1726
 - ANY_CHILD, 1726
 - ANY_DESCENDENT, 1726
- activemq::commands::ActiveMQMapMessage, 360
 - ~ActiveMQMapMessage, 363
 - ActiveMQMapMessage, 363
 - beforeMarshal, 363
 - checkMapIsUnmarshalled, 363
 - clearBody, 363
 - clone, 363
 - cloneDataStructure, 363
 - copyDataStructure, 364
 - equals, 364
 - getBoolean, 364
 - getByte, 364
 - getBytes, 365
 - getChar, 365
 - getDataStructureType, 365
 - getDouble, 366
 - getFloat, 366
 - getInt, 366
 - getLong, 367
 - getMap, 367
 - getMapNames, 367
 - getShort, 367
 - getString, 368
 - ID_ACTIVEMQMAPMESSAGE, 372
 - isMarshalAware, 368
 - itemExists, 368
 - setBoolean, 369
 - setByte, 369
 - setBytes, 369
 - setChar, 370
 - setDouble, 370
 - setFloat, 370
 - setInt, 371
 - setLong, 371
 - setShort, 371
 - setString, 372
 - toString, 372
- activemq::commands::ActiveMQMessage, 398
 - ~ActiveMQMessage, 398
 - ActiveMQMessage, 398
 - clone, 398
 - cloneDataStructure, 399
 - copyDataStructure, 399
 - equals, 399
 - getDataStructureType, 399
 - ID_ACTIVEMQMESSAGE, 400
 - toString, 399
- activemq::commands::ActiveMQMessageTemplate, 425
 - ~ActiveMQMessageTemplate, 428
 - ActiveMQMessageTemplate, 428
 - acknowledge, 428
 - clearBody, 428
 - clearProperties, 429
 - equals, 429
 - failIfReadOnlyBody, 429
 - failIfReadOnlyProperties, 429
 - failIfWriteOnlyBody, 429
 - getBooleanProperty, 429

- getByteProperty, 430
- getCMSCorrelationID, 430
- getCMSDeliveryMode, 430
- getCMSDestination, 431
- getCMSExpiration, 431
- getCMSMessageID, 431
- getCMSPriority, 431
- getCMSRedelivered, 432
- getCMSReplyTo, 432
- getCMSTimestamp, 432
- getCMSType, 433
- getDoubleProperty, 433
- getFloatProperty, 433
- getIntProperty, 434
- getLongProperty, 434
- getPropertyNames, 434
- getShortProperty, 435
- getStringProperty, 435
- onSend, 435
- propertyExists, 436
- setBooleanProperty, 436
- setByteProperty, 436
- setCMSCorrelationID, 437
- setCMSDeliveryMode, 437
- setCMSDestination, 437
- setCMSExpiration, 437
- setCMSMessageID, 438
- setCMSPriority, 438
- setCMSRedelivered, 438
- setCMSReplyTo, 439
- setCMSTimestamp, 439
- setCMSType, 439
- setDoubleProperty, 439
- setFloatProperty, 440
- setIntProperty, 440
- setLongProperty, 440
- setShortProperty, 441
- setStringProperty, 441
- activemq::commands::ActiveMQObjectMessage, 443
 - ~ActiveMQObjectMessage, 444
 - ActiveMQObjectMessage, 444
 - clone, 444
 - cloneDataStructure, 444
 - copyDataStructure, 444
 - equals, 444
 - getDataStructureType, 445
 - ID_ACTIVEMQOBJECTMESSAGE, 445
 - toString, 445
- activemq::commands::ActiveMQQueue, 483
 - ~ActiveMQQueue, 484
 - ActiveMQQueue, 484
 - clone, 484
 - cloneDataStructure, 484
 - copy, 484
 - copyDataStructure, 484
 - equals, 484
 - getCMSDestination, 485
 - getCMSProperties, 485
 - getDataStructureType, 485
 - getDestinationType, 485
 - getQueueName, 486
 - ID_ACTIVEMQQUEUE, 486
 - toString, 486
- activemq::commands::ActiveMQStreamMessage, 537
 - ~ActiveMQStreamMessage, 540
 - ActiveMQStreamMessage, 540
 - clearBody, 540
 - clone, 540
 - cloneDataStructure, 540
 - copyDataStructure, 540
 - equals, 541
 - getDataStructureType, 541
 - ID_ACTIVEMQSTREAMMESSAGE, 551
 - onSend, 541
 - readBoolean, 541
 - readByte, 542
 - readBytes, 542, 543
 - readChar, 543
 - readDouble, 544
 - readFloat, 544
 - readInt, 544
 - readLong, 545
 - readShort, 545
 - readString, 546
 - readUnsignedShort, 546
 - reset, 546
 - toString, 547
 - writeBoolean, 547
 - writeByte, 547
 - writeBytes, 548
 - writeChar, 548
 - writeDouble, 549
 - writeFloat, 549
 - writeInt, 549
 - writeLong, 549
 - writeShort, 550
 - writeString, 550
 - writeUnsignedShort, 550
- activemq::commands::ActiveMQTempDestination, 576
 - ~ActiveMQTempDestination, 577
 - ActiveMQTempDestination, 577
 - cloneDataStructure, 577
 - close, 577
 - connection, 579

- copyDataStructure, 577
- equals, 577
- getDataStructureType, 578
- ID_ACTIVEMQTEMPDESTINATION, 579
- setConnection, 578
- toString, 578
- activemq::commands::ActiveMQTempQueue, 604
 - ~ActiveMQTempQueue, 605
 - ActiveMQTempQueue, 605
 - clone, 605
 - cloneDataStructure, 605
 - copy, 605
 - copyDataStructure, 605
 - destroy, 606
 - equals, 606
 - getCMSDestination, 606
 - getCMSProperties, 606
 - getDataStructureType, 607
 - getDestinationType, 607
 - getQueueName, 607
 - ID_ACTIVEMQTEMPQUEUE, 608
 - toString, 607
- activemq::commands::ActiveMQTempTopic, 633
 - ~ActiveMQTempTopic, 634
 - ActiveMQTempTopic, 634
 - clone, 634
 - cloneDataStructure, 634
 - copy, 634
 - copyDataStructure, 634
 - destroy, 635
 - equals, 635
 - getCMSDestination, 635
 - getCMSProperties, 635
 - getDataStructureType, 636
 - getDestinationType, 636
 - getTopicName, 636
 - ID_ACTIVEMQTEMPTOPIC, 637
 - toString, 636
- activemq::commands::ActiveMQTextMessage, 662
 - ~ActiveMQTextMessage, 663
 - ActiveMQTextMessage, 663
 - beforeMarshal, 663
 - clearBody, 663
 - clone, 663
 - cloneDataStructure, 664
 - copyDataStructure, 664
 - equals, 664
 - getDataStructureType, 664
 - getSize, 664
 - getText, 665
 - ID_ACTIVEMQTEXTMESSAGE, 666
 - setText, 665
 - text, 666
 - toString, 666
- activemq::commands::ActiveMQTopic, 691
 - ~ActiveMQTopic, 692
 - ActiveMQTopic, 692
 - clone, 692
 - cloneDataStructure, 692
 - copy, 692
 - copyDataStructure, 692
 - equals, 692
 - getCMSDestination, 693
 - getCMSProperties, 693
 - getDataStructureType, 693
 - getDestinationType, 693
 - getTopicName, 694
 - ID_ACTIVEMQTOPIC, 694
 - toString, 694
- activemq::commands::BaseCommand, 758
 - ~BaseCommand, 759
 - BaseCommand, 759
 - copyDataStructure, 759
 - equals, 759
 - getCommandId, 760
 - isBrokerInfo, 760
 - isConnectionInfo, 761
 - isConsumerInfo, 761
 - isKeepAliveInfo, 761
 - isMessage, 761
 - isMessageAck, 761
 - isMessageDispatch, 761
 - isMessageDispatchNotification, 761
 - isProducerAck, 761
 - isProducerInfo, 762
 - isRemoveInfo, 762
 - isRemoveSubscriptionInfo, 762
 - isResponse, 762
 - isResponseRequired, 762
 - isShutdownInfo, 762
 - isTransactionInfo, 762
 - isWireFormatInfo, 763
 - setCommandId, 763
 - setResponseRequired, 763
 - toString, 763
- activemq::commands::BaseDataStructure, 830
 - ~BaseDataStructure, 831
 - afterMarshal, 831
 - afterUnmarshal, 831
 - beforeMarshal, 831
 - beforeUnmarshal, 831
 - copyDataStructure, 831
 - equals, 832
 - getMarshaledForm, 832

- isMarshalAware, 832
- setMarshaledForm, 832
- toString, 833
- activemq::commands::BooleanExpression, 855
 - ~BooleanExpression, 855
 - BooleanExpression, 855
 - cloneDataStructure, 855
 - copyDataStructure, 855
 - equals, 856
 - toString, 856
- activemq::commands::BrokerError, 863
 - ~BrokerError, 864
 - BrokerError, 864
 - cloneDataStructure, 864
 - copyDataStructure, 864
 - getCause, 864
 - getDataStructureType, 865
 - getExceptionClass, 865
 - getMessage, 865
 - getStackTraceElements, 865
 - setCause, 865
 - setExceptionClass, 866
 - setMessage, 866
 - setStackTraceElements, 866
 - visit, 866
- activemq::commands::BrokerError::StackTraceElement, 3578
 - ClassName, 3578
 - FileName, 3578
 - LineNumber, 3578
 - MethodName, 3578
- activemq::commands::BrokerId, 869
 - ~BrokerId, 870
 - BrokerId, 870
 - cloneDataStructure, 870
 - COMPARATOR, 870
 - compareTo, 870
 - copyDataStructure, 870
 - equals, 870
 - getDataStructureType, 870
 - getValue, 871
 - ID_BROKERID, 871
 - operator<, 871
 - operator=, 871
 - operator==, 871
 - setValue, 871
 - toString, 871
 - value, 871
- activemq::commands::BrokerInfo, 896
 - ~BrokerInfo, 897
 - brokerId, 903
 - BrokerInfo, 897
 - brokerName, 903
 - brokerUploadUrl, 903
 - brokerURL, 903
 - cloneDataStructure, 897
 - connectionId, 903
 - copyDataStructure, 898
 - duplexConnection, 903
 - equals, 898
 - faultTolerantConfiguration, 903
 - getBrokerId, 898, 899
 - getBrokerName, 899
 - getBrokerUploadUrl, 899
 - getBrokerURL, 899
 - getConnectionId, 899
 - getDataStructureType, 899
 - getNetworkProperties, 899, 900
 - getPeerBrokerInfos, 900
 - ID_BROKERINFO, 903
 - isBrokerInfo, 900
 - isDuplexConnection, 900
 - isFaultTolerantConfiguration, 901
 - isMasterBroker, 901
 - isNetworkConnection, 901
 - isSlaveBroker, 901
 - masterBroker, 903
 - networkConnection, 903
 - networkProperties, 903
 - peerBrokerInfos, 903
 - setBrokerId, 901
 - setBrokerName, 901
 - setBrokerUploadUrl, 901
 - setBrokerURL, 901
 - setConnectionId, 901
 - setDuplexConnection, 901
 - setFaultTolerantConfiguration, 901
 - setMasterBroker, 901
 - setNetworkConnection, 901
 - setNetworkProperties, 901
 - setPeerBrokerInfos, 901
 - setSlaveBroker, 901
 - slaveBroker, 903
 - toString, 901
 - visit, 902
- activemq::commands::Command, 1194
 - ~Command, 1195
 - getCommandId, 1195
 - isBrokerInfo, 1195
 - isConnectionInfo, 1195
 - isConsumerInfo, 1195
 - isKeepAliveInfo, 1195
 - isMessage, 1195
 - isMessageAck, 1195
 - isMessageDispatch, 1196
 - isMessageDispatchNotification, 1196
 - isProducerAck, 1196
 - isProducerInfo, 1196

- isRemoveInfo, 1196
- isRemoveSubscriptionInfo, 1196
- isResponse, 1196
- isResponseRequired, 1196
- isShutdownInfo, 1197
- isTransactionInfo, 1197
- isWireFormatInfo, 1197
- setCommandId, 1197
- setResponseRequired, 1197
- toString, 1197
- visit, 1198
- activemq::commands::ConnectionControl, 1267
 - ~ConnectionControl, 1268
 - cloneDataStructure, 1268
 - close, 1271
 - connectedBrokers, 1271
 - ConnectionControl, 1268
 - copyDataStructure, 1268
 - equals, 1268
 - exit, 1271
 - faultTolerant, 1271
 - getConnectedBrokers, 1269
 - getDataStructureType, 1269
 - getReconnectTo, 1269, 1270
 - ID_CONNECTIONCONTROL, 1271
 - isClose, 1270
 - isExit, 1270
 - isFaultTolerant, 1270
 - isRebalanceConnection, 1270
 - isResume, 1270
 - isSuspend, 1270
 - rebalanceConnection, 1271
 - reconnectTo, 1271
 - resume, 1271
 - setClose, 1270
 - setConnectedBrokers, 1270
 - setExit, 1270
 - setFaultTolerant, 1270
 - setRebalanceConnection, 1270
 - setReconnectTo, 1270
 - setResume, 1270
 - setSuspend, 1270
 - suspend, 1271
 - toString, 1270
 - visit, 1271
- activemq::commands::ConnectionError, 1296
 - ~ConnectionError, 1297
 - cloneDataStructure, 1297
 - ConnectionError, 1297
 - connectionId, 1299
 - copyDataStructure, 1297
 - equals, 1297
 - exception, 1299
 - getConnectionId, 1297, 1298
 - getDataStructureType, 1298
 - getException, 1298
 - ID_CONNECTIONERROR, 1299
 - setConnectionId, 1298
 - setException, 1298
 - toString, 1298
 - visit, 1298
- activemq::commands::ConnectionId, 1327
 - ~ConnectionId, 1328
 - cloneDataStructure, 1328
 - COMPARATOR, 1328
 - compareTo, 1328
 - ConnectionId, 1328
 - copyDataStructure, 1328
 - equals, 1328, 1329
 - getDataStructureType, 1329
 - getValue, 1329
 - ID_CONNECTIONID, 1330
 - operator<, 1329
 - operator=, 1329
 - operator==, 1329
 - setValue, 1329
 - toString, 1329
 - value, 1330
- activemq::commands::ConnectionInfo, 1355
 - ~ConnectionInfo, 1356
 - brokerMasterConnector, 1360
 - brokerPath, 1360
 - clientId, 1360
 - clientMaster, 1360
 - cloneDataStructure, 1356
 - connectionId, 1360
 - ConnectionInfo, 1356
 - copyDataStructure, 1356
 - createRemoveCommand, 1357
 - equals, 1357
 - faultTolerant, 1360
 - getBrokerPath, 1357
 - getClientId, 1357
 - getConnectionId, 1357
 - getDataStructureType, 1357
 - getPassword, 1358
 - getUserName, 1358
 - ID_CONNECTIONINFO, 1360
 - isBrokerMasterConnector, 1358
 - isClientMaster, 1358
 - isConnectionInfo, 1358
 - isFaultTolerant, 1358
 - isManageable, 1359
 - manageable, 1360
 - password, 1360
 - setBrokerMasterConnector, 1359
 - setBrokerPath, 1359
 - setClientId, 1359

- setClientMaster, 1359
- setConnectionId, 1359
- setFaultTolerant, 1359
- setManageable, 1359
- setPassword, 1359
- setUserName, 1359
- toString, 1359
- userName, 1360
- visit, 1359
- activemq::commands::ConsumerControl, 1401
 - ~ConsumerControl, 1402
 - cloneDataStructure, 1402
 - close, 1405
 - ConsumerControl, 1402
 - consumerId, 1405
 - copyDataStructure, 1402
 - destination, 1405
 - equals, 1402
 - flush, 1405
 - getConsumerId, 1403
 - getDataStructureType, 1403
 - getDestination, 1403, 1404
 - getPrefetch, 1404
 - ID_CONSUMERCONTROL, 1405
 - isClose, 1404
 - isFlush, 1404
 - isStart, 1404
 - isStop, 1404
 - prefetch, 1405
 - setClose, 1404
 - setConsumerId, 1404
 - setDestination, 1404
 - setFlush, 1404
 - setPrefetch, 1404
 - setStart, 1404
 - setStop, 1404
 - start, 1405
 - stop, 1405
 - toString, 1404
 - visit, 1404
- activemq::commands::ConsumerId, 1430
 - ~ConsumerId, 1431
 - cloneDataStructure, 1431
 - COMPARATOR, 1431
 - compareTo, 1431
 - connectionId, 1433
 - ConsumerId, 1431
 - copyDataStructure, 1431
 - equals, 1431, 1432
 - getConnectionId, 1432
 - getDataStructureType, 1432
 - getParentId, 1432
 - getSessionId, 1433
 - getValue, 1433
 - ID_CONSUMERID, 1433
 - operator<, 1433
 - operator=, 1433
 - operator==, 1433
 - sessionId, 1433
 - setConnectionId, 1433
 - setSessionId, 1433
 - setValue, 1433
 - toString, 1433
 - value, 1434
- activemq::commands::ConsumerInfo, 1459
 - ~ConsumerInfo, 1461
 - additionalPredicate, 1466
 - brokerPath, 1466
 - browser, 1466
 - cloneDataStructure, 1461
 - consumerId, 1466
 - ConsumerInfo, 1461
 - copyDataStructure, 1461
 - createRemoveCommand, 1461
 - destination, 1466
 - dispatchAsync, 1466
 - equals, 1461
 - exclusive, 1466
 - getAdditionalPredicate, 1462
 - getBrokerPath, 1462
 - getConsumerId, 1462
 - getDataStructureType, 1462
 - getDestination, 1462, 1463
 - getMaximumPendingMessageLimit, 1463
 - getNetworkConsumerPath, 1463
 - getPrefetchSize, 1463
 - getPriority, 1463
 - getSelector, 1463
 - getSubscriptionName, 1463
 - ID_CONSUMERINFO, 1466
 - isBrowser, 1463
 - isConsumerInfo, 1463
 - isDispatchAsync, 1463
 - isExclusive, 1464
 - isNetworkSubscription, 1464
 - isNoLocal, 1464
 - isNoRangeAcks, 1464
 - isOptimizedAcknowledge, 1464
 - isRetroactive, 1464
 - maximumPendingMessageLimit, 1466
 - networkConsumerPath, 1466
 - networkSubscription, 1466
 - noLocal, 1466
 - noRangeAcks, 1466
 - optimizedAcknowledge, 1466
 - prefetchSize, 1466
 - priority, 1466
 - retroactive, 1466

- selector, 1466
- setAdditionalPredicate, 1464
- setBrokerPath, 1464
- setBrowser, 1464
- setConsumerId, 1464
- setDestination, 1464
- setDispatchAsync, 1464
- setExclusive, 1464
- setMaximumPendingMessageLimit, 1464
- setNetworkConsumerPath, 1464
- setNetworkSubscription, 1464
- setNoLocal, 1464
- setNoRangeAcks, 1464
- setOptimizedAcknowledge, 1464
- setPrefetchSize, 1464
- setPriority, 1464
- setRetroactive, 1464
- setSelector, 1464
- setSubscriptionName, 1464
- subscriptionName, 1466
- toString, 1464
- visit, 1465
- activemq::commands::ControlCommand, 1493
 - ~ControlCommand, 1494
 - cloneDataStructure, 1494
 - command, 1496
 - ControlCommand, 1494
 - copyDataStructure, 1494
 - equals, 1494
 - getCommand, 1494, 1495
 - getDataStructureType, 1495
 - ID_CONTROLCOMMAND, 1496
 - setCommand, 1495
 - toString, 1495
 - visit, 1495
- activemq::commands::DataArrayResponse, 1528
 - ~DataArrayResponse, 1529
 - cloneDataStructure, 1529
 - copyDataStructure, 1529
 - data, 1530
 - DataArrayResponse, 1529
 - equals, 1529
 - getData, 1529, 1530
 - getDataStructureType, 1530
 - ID_DATAARRAYRESPONSE, 1530
 - setData, 1530
 - toString, 1530
- activemq::commands::DataResponse, 1583
 - ~DataResponse, 1584
 - cloneDataStructure, 1584
 - copyDataStructure, 1584
 - data, 1585
 - DataResponse, 1584
 - equals, 1584
 - getData, 1584, 1585
 - getDataStructureType, 1585
 - ID_DATARESPONSE, 1585
 - setData, 1585
 - toString, 1585
- activemq::commands::DataStructure, 1660
 - ~DataStructure, 1660
 - cloneDataStructure, 1660
 - copyDataStructure, 1661
 - equals, 1661
 - getDataStructureType, 1662
 - toString, 1663
- activemq::commands::DestinationInfo, 1727
 - ~DestinationInfo, 1728
 - brokerPath, 1731
 - cloneDataStructure, 1728
 - connectionId, 1731
 - copyDataStructure, 1728
 - destination, 1731
 - DestinationInfo, 1728
 - equals, 1728
 - getBrokerPath, 1729
 - getConnectionId, 1729
 - getDataStructureType, 1729
 - getDestination, 1729, 1730
 - getOperationType, 1730
 - getTimeout, 1730
 - ID_DESTINATIONINFO, 1731
 - operationType, 1731
 - setBrokerPath, 1730
 - setConnectionId, 1730
 - setDestination, 1730
 - setOperationType, 1730
 - setTimeout, 1730
 - timeout, 1731
 - toString, 1730
 - visit, 1730
- activemq::commands::DiscoveryEvent, 1758
 - ~DiscoveryEvent, 1759
 - brokerName, 1761
 - cloneDataStructure, 1759
 - copyDataStructure, 1759
 - DiscoveryEvent, 1759
 - equals, 1759
 - getBrokerName, 1759, 1760
 - getDataStructureType, 1760
 - getServiceName, 1760
 - ID_DISCOVERYEVENT, 1761
 - serviceName, 1761
 - setBrokerName, 1760
 - setServiceName, 1760
 - toString, 1760
- activemq::commands::ExceptionResponse, 1839

- ~ExceptionResponse, 1840
- cloneDataStructure, 1840
- copyDataStructure, 1840
- equals, 1840
- exception, 1841
- ExceptionResponse, 1840
- getDataStructureType, 1840
- getException, 1841
- ID_EXCEPTIONRESPONSE, 1841
- setException, 1841
- toString, 1841
- activemq::commands::FlushCommand, 1937
 - ~FlushCommand, 1938
 - cloneDataStructure, 1938
 - copyDataStructure, 1938
 - equals, 1938
 - FlushCommand, 1938
 - getDataStructureType, 1938
 - ID_FLUSHCOMMAND, 1939
 - toString, 1939
 - visit, 1939
- activemq::commands::IntegerResponse, 2091
 - ~IntegerResponse, 2092
 - cloneDataStructure, 2092
 - copyDataStructure, 2092
 - equals, 2092
 - getDataStructureType, 2092
 - getResult, 2093
 - ID_INTEGERRESPONSE, 2093
 - IntegerResponse, 2092
 - result, 2093
 - setResult, 2093
 - toString, 2093
- activemq::commands::JournalQueueAck, 2156
 - ~JournalQueueAck, 2157
 - cloneDataStructure, 2157
 - copyDataStructure, 2157
 - destination, 2158
 - equals, 2157
 - getDataStructureType, 2157
 - getDestination, 2157, 2158
 - getMessageAck, 2158
 - ID_JOURNALQUEUEACK, 2158
 - JournalQueueAck, 2157
 - messageAck, 2158
 - setDestination, 2158
 - setMessageAck, 2158
 - toString, 2158
- activemq::commands::JournalTopicAck, 2183
 - ~JournalTopicAck, 2184
 - clientId, 2187
 - cloneDataStructure, 2184
 - copyDataStructure, 2184
 - destination, 2187
 - equals, 2184
 - getClientId, 2184, 2185
 - getDataStructureType, 2185
 - getDestination, 2185, 2186
 - getMessageId, 2186
 - getMessageSequenceId, 2186
 - getSubscriptionName, 2186
 - getTransactionId, 2186
 - ID_JOURNALTOPICACK, 2187
 - JournalTopicAck, 2184
 - messageId, 2187
 - messageSequenceId, 2187
 - setClientId, 2186
 - setDestination, 2186
 - setMessageId, 2186
 - setMessageSequenceId, 2186
 - setSubscriptionName, 2186
 - setTransactionId, 2186
 - subscriptionName, 2187
 - toString, 2186
 - transactionId, 2187
- activemq::commands::JournalTrace, 2212
 - ~JournalTrace, 2213
 - cloneDataStructure, 2213
 - copyDataStructure, 2213
 - equals, 2213
 - getDataStructureType, 2213
 - getMessage, 2213, 2214
 - ID_JOURNALTRACE, 2214
 - JournalTrace, 2213
 - message, 2214
 - setMessage, 2214
 - toString, 2214
- activemq::commands::JournalTransaction, 2239
 - ~JournalTransaction, 2240
 - cloneDataStructure, 2240
 - copyDataStructure, 2240
 - equals, 2240
 - getDataStructureType, 2240
 - getTransactionId, 2240, 2241
 - getType, 2241
 - getWasPrepared, 2241
 - ID_JOURNALTRANSACTION, 2241
 - JournalTransaction, 2240
 - setTransactionId, 2241
 - setType, 2241
 - setWasPrepared, 2241
 - toString, 2241
 - transactionId, 2241
 - type, 2241
 - wasPrepared, 2241
- activemq::commands::KeepAliveInfo, 2266
 - ~KeepAliveInfo, 2267
 - cloneDataStructure, 2267

- copyDataStructure, 2267
- equals, 2267
- getDataStructureType, 2267
- ID_KEEPLIVEINFO, 2268
- isKeepAliveInfo, 2268
- KeepAliveInfo, 2267
- toString, 2268
- visit, 2268
- activemq::commands::LastPartialCommand, 2301
 - ~LastPartialCommand, 2301
 - cloneDataStructure, 2301
 - copyDataStructure, 2302
 - equals, 2302
 - getDataStructureType, 2302
 - ID_LASTPARTIALCOMMAND, 2303
 - LastPartialCommand, 2301
 - toString, 2302
- activemq::commands::LocalTransactionId, 2347
 - ~LocalTransactionId, 2348
 - cloneDataStructure, 2348
 - COMPARATOR, 2348
 - compareTo, 2348
 - connectionId, 2350
 - copyDataStructure, 2348
 - equals, 2348, 2349
 - getConnectionId, 2349
 - getDataStructureType, 2349
 - getValue, 2349
 - ID_LOCALTRANSACTIONID, 2350
 - LocalTransactionId, 2348
 - operator<, 2349
 - operator=, 2349
 - operator==, 2349
 - setConnectionId, 2350
 - setValue, 2350
 - toString, 2350
 - value, 2350
- activemq::commands::Message, 2516
 - ~Message, 2520
 - afterUnmarshal, 2520
 - arrival, 2532
 - beforeMarshal, 2520
 - brokerInTime, 2532
 - brokerOutTime, 2532
 - brokerPath, 2532
 - cloneDataStructure, 2520
 - cluster, 2532
 - compressed, 2532
 - connection, 2532
 - content, 2532
 - copyDataStructure, 2521
 - correlationId, 2532
 - dataStructure, 2532
 - DEFAULT_MESSAGE_SIZE, 2532
 - destination, 2532
 - droppable, 2532
 - equals, 2521
 - expiration, 2532
 - getAckHandler, 2521
 - getArrival, 2522
 - getBrokerInTime, 2522
 - getBrokerOutTime, 2522
 - getBrokerPath, 2522
 - getCluster, 2522
 - getConnection, 2522
 - getContent, 2522, 2523
 - getCorrelationId, 2523
 - getDataStructure, 2523
 - getDataStructureType, 2523
 - getDestination, 2523, 2524
 - getExpiration, 2524
 - getGroupID, 2524
 - getGroupSequence, 2524
 - getMarshaledProperties, 2524
 - getMessageId, 2524
 - getMessageProperties, 2524
 - getOriginalDestination, 2524, 2525
 - getOriginalTransactionId, 2525
 - getPriority, 2525
 - getProducerId, 2525
 - getRedeliveryCounter, 2525
 - getReplyTo, 2525
 - getSize, 2525
 - getTargetConsumerId, 2525, 2526
 - getTimestamp, 2526
 - getTransactionId, 2526
 - getType, 2526
 - getUserID, 2526
 - groupID, 2532
 - groupSequence, 2532
 - ID_MESSAGE, 2532
 - isCompressed, 2526
 - isDroppable, 2526
 - isExpired, 2526
 - isMarshalAware, 2526
 - isMessage, 2527
 - isPersistent, 2527
 - isReadOnlyBody, 2527
 - isReadOnlyProperties, 2527
 - isRecievedByDFBridge, 2527
 - marshalledProperties, 2532
 - Message, 2520
 - messageId, 2532
 - onSend, 2527
 - originalDestination, 2532
 - originalTransactionId, 2532
 - persistent, 2532

- priority, 2532
- producerId, 2532
- recievedByDFBridge, 2532
- redeliveryCounter, 2532
- replyTo, 2532
- setAckHandler, 2527
- setArrival, 2528
- setBrokerInTime, 2528
- setBrokerOutTime, 2528
- setBrokerPath, 2528
- setCluster, 2528
- setCompressed, 2528
- setConnection, 2528
- setContent, 2528
- setCorrelationId, 2529
- setDataStructure, 2529
- setDestination, 2529
- setDroppable, 2529
- setExpiration, 2529
- setGroupID, 2529
- setGroupSequence, 2529
- setMarshaledProperties, 2529
- setMessageId, 2529
- setOriginalDestination, 2529
- setOriginalTransactionId, 2529
- setPersistent, 2529
- setPriority, 2529
- setProducerId, 2529
- setReadOnlyBody, 2529
- setReadOnlyProperties, 2529
- setRecievedByDFBridge, 2530
- setRedeliveryCounter, 2530
- setReplyTo, 2530
- setTargetConsumerId, 2530
- setTimestamp, 2530
- setTransactionId, 2530
- setType, 2530
- setUserID, 2530
- targetConsumerId, 2532
- timestamp, 2532
- toString, 2530
- transactionId, 2532
- type, 2532
- userId, 2532
- visit, 2530
- activemq::commands::MessageAck, 2559
 - ~MessageAck, 2560
 - ackType, 2564
 - cloneDataStructure, 2560
 - consumerId, 2564
 - copyDataStructure, 2560
 - destination, 2564
 - equals, 2560
 - firstMessageId, 2564
 - getAckType, 2561
 - getConsumerId, 2561
 - getDataStructureType, 2561
 - getDestination, 2561, 2562
 - getFirstMessageId, 2562
 - getLastMessageId, 2562
 - getMessageCount, 2562
 - getTransactionId, 2562
 - ID_MESSAGEACK, 2564
 - isMessageAck, 2562
 - lastMessageId, 2564
 - MessageAck, 2560
 - messageCount, 2564
 - setAckType, 2562
 - setConsumerId, 2563
 - setDestination, 2563
 - setFirstMessageId, 2563
 - setLastMessageId, 2563
 - setMessageCount, 2563
 - setTransactionId, 2563
 - toString, 2563
 - transactionId, 2564
 - visit, 2563
- activemq::commands::MessageDispatch, 2594
 - ~MessageDispatch, 2595
 - cloneDataStructure, 2595
 - consumerId, 2598
 - copyDataStructure, 2595
 - destination, 2598
 - equals, 2595
 - getConsumerId, 2595, 2596
 - getDataStructureType, 2596
 - getDestination, 2596
 - getMessage, 2596
 - getRedeliveryCounter, 2596
 - ID_MESSAGEDISPATCH, 2598
 - isMessageDispatch, 2596
 - message, 2598
 - MessageDispatch, 2595
 - redeliveryCounter, 2598
 - setConsumerId, 2596
 - setDestination, 2597
 - setMessage, 2597
 - setRedeliveryCounter, 2597
 - toString, 2597
 - visit, 2597
- activemq::commands::MessageDispatchNotification, 2630
 - ~MessageDispatchNotification, 2631
 - cloneDataStructure, 2631
 - consumerId, 2634
 - copyDataStructure, 2631
 - deliverySequenceId, 2634
 - destination, 2634

- equals, 2631
- getConsumerId, 2631, 2632
- getDataStructureType, 2632
- getDeliverySequenceId, 2632
- getDestination, 2632
- getMessageId, 2632
- ID_MESSAGEDISPATCHNOTIFICATION, 2634
- isMessageDispatchNotification, 2632
- MessageDispatchNotification, 2631
- messageId, 2634
- setConsumerId, 2632
- setDeliverySequenceId, 2633
- setDestination, 2633
- setMessageId, 2633
- toString, 2633
- visit, 2633
- activemq::commands::MessageId, 2663
 - ~MessageId, 2664
 - brokerSequenceId, 2667
 - cloneDataStructure, 2664
 - COMPARATOR, 2664
 - compareTo, 2664
 - copyDataStructure, 2665
 - equals, 2665
 - getBrokerSequenceId, 2665
 - getDataStructureType, 2665
 - getProducerId, 2665, 2666
 - getProducerSequenceId, 2666
 - ID_MESSAGEID, 2667
 - MessageId, 2664
 - operator<, 2666
 - operator=, 2666
 - operator==, 2666
 - producerId, 2667
 - producerSequenceId, 2667
 - setBrokerSequenceId, 2666
 - setProducerId, 2666
 - setProducerSequenceId, 2666
 - setTextView, 2666
 - setValue, 2666
 - toString, 2666
- activemq::commands::MessagePull, 2739
 - ~MessagePull, 2740
 - cloneDataStructure, 2740
 - consumerId, 2743
 - copyDataStructure, 2740
 - correlationId, 2743
 - destination, 2743
 - equals, 2740
 - getConsumerId, 2740, 2741
 - getCorrelationId, 2741
 - getDataStructureType, 2741
 - getDestination, 2741, 2742
 - getMessageId, 2742
 - getTimeout, 2742
 - ID_MESSAGEPULL, 2743
 - messageId, 2743
 - MessagePull, 2740
 - setConsumerId, 2742
 - setCorrelationId, 2742
 - setDestination, 2742
 - setMessageId, 2742
 - setTimeout, 2742
 - timeout, 2743
 - toString, 2742
 - visit, 2742
- activemq::commands::NetworkBridgeFilter, 2793
 - ~NetworkBridgeFilter, 2794
 - cloneDataStructure, 2794
 - copyDataStructure, 2794
 - equals, 2794
 - getDataStructureType, 2794
 - getNetworkBrokerId, 2794, 2795
 - getNetworkTTL, 2795
 - ID_NETWORKBRIDGEFILTER, 2795
 - NetworkBridgeFilter, 2794
 - networkBrokerId, 2795
 - networkTTL, 2795
 - setNetworkBrokerId, 2795
 - setNetworkTTL, 2795
 - toString, 2795
- activemq::commands::PartialCommand, 2918
 - ~PartialCommand, 2919
 - cloneDataStructure, 2919
 - commandId, 2921
 - copyDataStructure, 2919
 - data, 2921
 - equals, 2919
 - getCommandId, 2919
 - getData, 2920
 - getDataStructureType, 2920
 - ID_PARTIALCOMMAND, 2921
 - PartialCommand, 2919
 - setCommandId, 2920
 - setData, 2920
 - toString, 2920
- activemq::commands::ProducerAck, 3036
 - ~ProducerAck, 3037
 - cloneDataStructure, 3037
 - copyDataStructure, 3037
 - equals, 3037
 - getDataStructureType, 3037
 - getProducerId, 3037, 3038
 - getSize, 3038
 - ID_PRODUCERACK, 3039
 - isProducerAck, 3038

- ProducerAck, 3037
- producerId, 3039
- setProducerId, 3038
- setSize, 3038
- size, 3039
- toString, 3038
- visit, 3038
- activemq::commands::ProducerId, 3067
 - ~ProducerId, 3068
 - cloneDataStructure, 3068
 - COMPARATOR, 3068
 - compareTo, 3068
 - connectionId, 3070
 - copyDataStructure, 3068
 - equals, 3069
 - getConnectionId, 3069
 - getDataStructureType, 3069
 - getParentId, 3069
 - getSessionId, 3070
 - getValue, 3070
 - ID_PRODUCERID, 3070
 - operator<, 3070
 - operator=, 3070
 - operator==, 3070
 - ProducerId, 3068
 - sessionId, 3070
 - setConnectionId, 3070
 - setProducerSessionKey, 3070
 - setSessionId, 3070
 - setValue, 3070
 - toString, 3070
 - value, 3071
- activemq::commands::ProducerInfo, 3096
 - ~ProducerInfo, 3097
 - brokerPath, 3100
 - cloneDataStructure, 3097
 - copyDataStructure, 3097
 - createRemoveCommand, 3097
 - destination, 3100
 - dispatchAsync, 3100
 - equals, 3097
 - getBrokerPath, 3098
 - getDataStructureType, 3098
 - getDestination, 3098
 - getProducerId, 3098
 - getWindowSize, 3098
 - ID_PRODUCERINFO, 3100
 - isDispatchAsync, 3098
 - isProducerInfo, 3098
 - producerId, 3100
 - ProducerInfo, 3097
 - setBrokerPath, 3098
 - setDestination, 3099
 - setDispatchAsync, 3099
 - setProducerId, 3099
 - setWindowSize, 3099
 - toString, 3099
 - visit, 3099
 - windowSize, 3100
- activemq::commands::RemoveInfo, 3194
 - ~RemoveInfo, 3195
 - cloneDataStructure, 3195
 - copyDataStructure, 3195
 - equals, 3195
 - getDataStructureType, 3195
 - getLastDeliveredSequenceId, 3195
 - getObjectId, 3196
 - ID_REMOVEINFO, 3197
 - isRemoveInfo, 3196
 - lastDeliveredSequenceId, 3197
 - objectId, 3197
 - RemoveInfo, 3195
 - setLastDeliveredSequenceId, 3196
 - setObjectId, 3196
 - toString, 3196
 - visit, 3196
- activemq::commands::RemoveSubscriptionInfo, 3222
 - ~RemoveSubscriptionInfo, 3223
 - clientId, 3226
 - cloneDataStructure, 3223
 - connectionId, 3226
 - copyDataStructure, 3223
 - equals, 3223
 - getClientId, 3223, 3224
 - getConnectionId, 3224
 - getDataStructureType, 3224
 - getSubscriptionName, 3224
 - ID_REMOVESUBSCRIPTIONINFO, 3226
 - isRemoveSubscriptionInfo, 3224
 - RemoveSubscriptionInfo, 3223
 - setClientId, 3224
 - setConnectionId, 3225
 - setSubscriptionName, 3225
 - subscriptionName, 3226
 - toString, 3225
 - visit, 3225
- activemq::commands::ReplayCommand, 3251
 - ~ReplayCommand, 3252
 - cloneDataStructure, 3252
 - copyDataStructure, 3252
 - equals, 3252
 - firstNakNumber, 3253
 - getDataStructureType, 3252
 - getFirstNakNumber, 3253
 - getLastNakNumber, 3253
 - ID_REPLAYCOMMAND, 3253

- lastNakNumber, 3253
- ReplayCommand, 3252
- setFirstNakNumber, 3253
- setLastNakNumber, 3253
- toString, 3253
- visit, 3253
- activemq::commands::Response, 3285
 - ~Response, 3286
 - cloneDataStructure, 3286
 - copyDataStructure, 3286
 - correlationId, 3288
 - equals, 3286
 - getCorrelationId, 3286
 - getDataStructureType, 3287
 - ID_RESPONSE, 3288
 - isResponse, 3287
 - Response, 3286
 - setCorrelationId, 3287
 - toString, 3287
 - visit, 3287
- activemq::commands::SessionId, 3379
 - ~SessionId, 3380
 - cloneDataStructure, 3380
 - COMPARATOR, 3380
 - compareTo, 3380
 - connectionId, 3382
 - copyDataStructure, 3380
 - equals, 3381
 - getConnectionId, 3381
 - getDataStructureType, 3381
 - getParentId, 3381
 - getValue, 3382
 - ID_SESSIONID, 3382
 - operator<, 3382
 - operator=, 3382
 - operator==, 3382
 - SessionId, 3380
 - setConnectionId, 3382
 - setValue, 3382
 - toString, 3382
 - value, 3382
- activemq::commands::SessionInfo, 3407
 - ~SessionInfo, 3408
 - cloneDataStructure, 3408
 - copyDataStructure, 3408
 - createRemoveCommand, 3408
 - equals, 3408
 - getAckMode, 3408
 - getDataStructureType, 3409
 - getSessionId, 3409
 - ID_SESSIONINFO, 3410
 - sessionId, 3410
 - SessionInfo, 3408
 - setAckMode, 3409
 - setSessionId, 3409
 - toString, 3409
 - visit, 3409
- activemq::commands::ShutdownInfo, 3470
 - ~ShutdownInfo, 3471
 - cloneDataStructure, 3471
 - copyDataStructure, 3471
 - equals, 3471
 - getDataStructureType, 3471
 - ID_SHUTDOWNINFO, 3472
 - isShutdownInfo, 3472
 - ShutdownInfo, 3471
 - toString, 3472
 - visit, 3472
- activemq::commands::SubscriptionInfo, 3671
 - ~SubscriptionInfo, 3672
 - clientId, 3675
 - cloneDataStructure, 3672
 - copyDataStructure, 3672
 - destination, 3675
 - equals, 3672
 - getClientId, 3672, 3673
 - getDataStructureType, 3673
 - getDestination, 3673, 3674
 - getSelector, 3674
 - getSubscriptionName, 3674
 - getSubscribedDestination, 3674
 - ID_SUBSCRIPTIONINFO, 3675
 - selector, 3675
 - setClientId, 3674
 - setDestination, 3674
 - setSelector, 3674
 - setSubscriptionName, 3674
 - setSubscribedDestination, 3674
 - subscriptionName, 3675
 - subscribedDestination, 3675
 - SubscriptionInfo, 3672
 - toString, 3674
- activemq::commands::TransactionId, 3819
 - ~TransactionId, 3820
 - cloneDataStructure, 3820
 - COMPARATOR, 3819
 - compareTo, 3820
 - copyDataStructure, 3820
 - equals, 3820
 - getDataStructureType, 3821
 - ID_TRANSACTIONID, 3822
 - operator<, 3821
 - operator=, 3821
 - operator==, 3821
 - toString, 3821
 - TransactionId, 3820
- activemq::commands::TransactionInfo, 3847
 - ~TransactionInfo, 3848

- cloneDataStructure, 3848
- connectionId, 3850
- copyDataStructure, 3848
- equals, 3848
- getConnectionId, 3848, 3849
- getDataStructureType, 3849
- getTransactionId, 3849
- getType, 3849
- ID_TRANSACTIONINFO, 3850
- isTransactionInfo, 3849
- setConnectionId, 3849
- setTransactionId, 3849
- setType, 3849
- toString, 3849
- transactionId, 3850
- TransactionInfo, 3848
- type, 3850
- visit, 3850
- activemq::commands::WireFormatInfo, 3982
 - ~WireFormatInfo, 3984
 - afterUnmarshal, 3984
 - beforeMarshal, 3985
 - cloneDataStructure, 3985
 - copyDataStructure, 3985
 - equals, 3985
 - getCacheSize, 3985
 - getDataStructureType, 3986
 - getMagic, 3986
 - getMarshaledProperties, 3986
 - getMaxInactivityDuration, 3986
 - getMaxInactivityDurationInitialDelay, 3986
 - getProperties, 3987
 - getVersion, 3987
 - ID_WIREFORMATINFO, 3991
 - isCacheEnabled, 3987
 - isMarshalAware, 3987
 - isSizePrefixDisabled, 3988
 - isStackTraceEnabled, 3988
 - isTcpNoDelayEnabled, 3988
 - isTightEncodingEnabled, 3988
 - isValid, 3988
 - isWireFormatInfo, 3988
 - setCacheEnabled, 3989
 - setCacheSize, 3989
 - setMagic, 3989
 - setMarshaledProperties, 3989
 - setMaxInactivityDuration, 3989
 - setMaxInactivityDurationInitialDelay, 3989
 - setProperties, 3990
 - setSizePrefixDisabled, 3990
 - setStackTraceEnabled, 3990
 - setTcpNoDelayEnabled, 3990
 - setTightEncodingEnabled, 3990
 - setVersion, 3990
 - toString, 3991
 - visit, 3991
 - WireFormatInfo, 3984
- activemq::commands::XATransactionId, 4031
 - ~XATransactionId, 4032
 - branchQualifier, 4035
 - cloneDataStructure, 4032
 - COMPARATOR, 4032
 - compareTo, 4032
 - copyDataStructure, 4032
 - equals, 4033
 - formatId, 4035
 - getBranchQualifier, 4033
 - getDataStructureType, 4033
 - getFormatId, 4033
 - getGlobalTransactionId, 4034
 - globalTransactionId, 4035
 - ID_XATRANSACTIONID, 4035
 - operator<, 4034
 - operator=, 4034
 - operator==, 4034
 - setBranchQualifier, 4034
 - setFormatId, 4034
 - setGlobalTransactionId, 4034
 - toString, 4034
 - XATransactionId, 4032
- activemq::core, 89
- activemq::core::ActiveMQAckHandler, 203
 - ~ActiveMQAckHandler, 203
 - acknowledgeMessage, 203
- activemq::core::ActiveMQConnection, 273
 - ~ActiveMQConnection, 278
 - ActiveMQConnection, 278
 - addDispatcher, 278
 - addProducer, 278
 - addTransportListener, 278
 - close, 279
 - createSession, 279
 - destroyDestination, 279, 280
 - fire, 280
 - getBrokerURL, 280
 - getClientID, 280
 - getCloseTimeout, 281
 - getConnectionId, 281
 - getConnectionInfo, 281
 - getExceptionListener, 281
 - getMetaData, 281
 - getNextLocalTransactionId, 282
 - getNextSessionId, 282
 - getNextTempDestinationId, 282
 - getPassword, 282
 - getPrefetchPolicy, 283
 - getProducerWindowSize, 283
 - getRedeliveryPolicy, 283

- getSendTimeout, 283
- getTransport, 283
- getUsername, 284
- isAlwaysSyncSend, 284
- isClosed, 284
- isDispatchAsync, 284
- isStarted, 284
- isTransportFailed, 284
- isUseAsyncSend, 285
- isUseCompression, 285
- onCommand, 285
- oneway, 285
- onException, 285
- removeDispatcher, 286
- removeProducer, 286
- removeSession, 286
- removeTransportListener, 286
- sendPullRequest, 286
- setAlwaysSyncSend, 287
- setBrokerURL, 287
- setClientID, 287
- setCloseTimeout, 288
- setDefaultClientId, 288
- setDispatchAsync, 288
- setExceptionHandler, 288
- setPassword, 288
- setPrefetchPolicy, 288
- setProducerWindowSize, 289
- setRedeliveryPolicy, 289
- setSendTimeout, 289
- setTransportInterruptionProcessingComplete, 289
- setUseAsyncSend, 289
- setUseCompression, 290
- setUsername, 290
- start, 290
- stop, 290
- syncRequest, 290
- transportInterrupted, 291
- transportResumed, 291
- activemq::core::ActiveMQConnectionFactory, 292
 - ~ActiveMQConnectionFactory, 294
 - ActiveMQConnectionFactory, 294
 - createConnection, 295, 296
 - DEFAULT_URI, 302
 - getBrokerURL, 296
 - getClientId, 296
 - getCloseTimeout, 297
 - getExceptionHandler, 297
 - getPassword, 297
 - getPrefetchPolicy, 297
 - getProducerWindowSize, 297
 - getRedeliveryPolicy, 298
 - getSendTimeout, 298
 - getUsername, 298
 - isAlwaysSyncSend, 298
 - isDispatchAsync, 298
 - isUseAsyncSend, 299
 - isUseCompression, 299
 - setAlwaysSyncSend, 299
 - setBrokerURL, 299
 - setClientId, 299
 - setCloseTimeout, 299
 - setDispatchAsync, 300
 - setExceptionHandler, 300
 - setPassword, 300
 - setPrefetchPolicy, 300
 - setProducerWindowSize, 300
 - setRedeliveryPolicy, 301
 - setSendTimeout, 301
 - setUseAsyncSend, 301
 - setUseCompression, 301
 - setUsername, 301
- activemq::core::ActiveMQConnectionMetaData, 303
 - ~ActiveMQConnectionMetaData, 304
 - ActiveMQConnectionMetaData, 304
 - getCMSMajorVersion, 304
 - getCMSMinorVersion, 304
 - getCMSProviderName, 304
 - getCMSVersion, 305
 - getCMSXPathPropertyNames, 305
 - getProviderMajorVersion, 305
 - getProviderMinorVersion, 305
 - getProviderVersion, 306
- activemq::core::ActiveMQConstants, 307
 - ACK_TYPE_CONSUMED, 308
 - ACK_TYPE_DELIVERED, 308
 - ACK_TYPE_INDIVIDUAL, 308
 - ACK_TYPE_POISON, 308
 - ACK_TYPE_REDELIVERED, 308
 - AckType, 308
 - CONNECTION_ALWAYS_SYNC_SEND, 309
 - CONNECTION_CLOSE_TIMEOUT, 309
 - CONNECTION_DISPATCH_ASYNC, 309
 - CONNECTION_PRODUCER_WINDOW_SIZE, 309
 - CONNECTION_SEND_TIMEOUT, 309
 - CONNECTION_USE_ASYNC_SEND, 309
 - CONNECTION_USE_COMPRESSION, 309
 - CONSUMER_DISPATCH_ASYNC, 308
 - CONSUMER_EXCLUSIVE, 308
 - CONSUMER_NOLOCAL, 308
 - CONSUMER_PREFETCH_SIZE, 308
 - CONSUMER_PRIORITY, 308

- CONSUMER_RETROACTIVE, 308
- CONSUMER_SELECTOR, 308
- CUNSUMER_-
 - MAXPENDINGMSGLIMIT, 308
- DESTINATION_ADD_OPERATION, 308
- DESTINATION_REMOVE_OPERATION, 308
- DestinationActions, 308
- DestinationOption, 308
- NUM_OPTIONS, 308
- NUM_PARAMS, 309
- PARAM_CLIENTID, 309
- PARAM_PASSWORD, 309
- PARAM_USERNAME, 309
- toDestinationOption, 309
- toString, 309
- toURIOption, 309
- TRANSACTION_STATE_BEGIN, 309
- TRANSACTION_STATE_-
 - COMMITONEPHASE, 309
- TRANSACTION_STATE_-
 - COMMITTWOPHASE, 309
- TRANSACTION_STATE_END, 309
- TRANSACTION_STATE_FORGET, 309
- TRANSACTION_STATE_PREPARE, 309
- TRANSACTION_STATE_RECOVER, 309
- TRANSACTION_STATE_ROLLBACK, 309
- TransactionState, 308
- URIParam, 309
- activemq::core::ActiveMQConstants::StaticInitializer, 3588
 - ~StaticInitializer, 3588
 - destOptionMap, 3588
 - destOptions, 3588
 - StaticInitializer, 3588
 - uriParams, 3588
 - uriParamsMap, 3588
- activemq::core::ActiveMQConsumer, 310
 - ~ActiveMQConsumer, 312
 - acknowledge, 312
 - ActiveMQConsumer, 312
 - afterMessageIsConsumed, 313
 - beforeMessageIsConsumed, 313
 - clearMessagesInProgress, 313
 - close, 313
 - commit, 313
 - deliverAcks, 314
 - dequeue, 314
 - dispatch, 314
 - doClose, 314
 - getConsumerId, 314
 - getConsumerInfo, 315
 - getLastDeliveredSequenceId, 315
 - getMessageAvailableCount, 315
 - getMessageListener, 315
 - getMessageSelector, 315
 - getRedeliveryPolicy, 316
 - inProgressClearRequired, 316
 - isClosed, 316
 - isSynchronizationRegistered, 316
 - iterate, 316
 - receive, 316, 317
 - receiveNoWait, 317
 - rollback, 317
 - setLastDeliveredSequenceId, 318
 - setMessageListener, 318
 - setRedeliveryPolicy, 318
 - setSynchronizationRegistered, 318
 - start, 318
 - stop, 318
- activemq::core::ActiveMQProducer, 470
 - ~ActiveMQProducer, 472
 - ActiveMQProducer, 471
 - close, 472
 - getDeliveryMode, 472
 - getDisableMessageID, 472
 - getDisableMessageTimeStamp, 472
 - getPriority, 473
 - getProducerId, 473
 - getProducerInfo, 473
 - getSendTimeout, 473
 - getTimeToLive, 473
 - isClosed, 474
 - onProducerAck, 474
 - send, 474, 475
 - setDeliveryMode, 476
 - setDisableMessageID, 476
 - setDisableMessageTimeStamp, 476
 - setPriority, 476
 - setSendTimeout, 477
 - setTimeToLive, 477
- activemq::core::ActiveMQQueueBrowser, 487
 - ~ActiveMQQueueBrowser, 488
 - ActiveMQQueueBrowser, 488
 - Browser, 490
 - close, 488
 - getEnumeration, 488
 - getMessageSelector, 488
 - getQueue, 489
 - hasMoreMessages, 489
 - nextMessage, 489
- activemq::core::ActiveMQSession, 515
 - ~ActiveMQSession, 519
 - acknowledge, 519

- ActiveMQSession, 519
- ActiveMQSessionExecutor, 532
- addConsumer, 519
- addProducer, 519
- clearMessagesInProgress, 519
- close, 520
- commit, 520
- createBrowser, 520
- createBytesMessage, 521
- createConsumer, 521, 522
- createDurableConsumer, 522
- createMapMessage, 523
- createMessage, 523
- createProducer, 523
- createQueue, 524
- createStreamMessage, 524
- createTemporaryQueue, 524
- createTemporaryTopic, 525
- createTextMessage, 525
- createTopic, 525
- deliverAcks, 526
- dispatch, 526
- doStartTransaction, 526
- fire, 526
- getAcknowledgeMode, 526
- getConnection, 527
- getExceptionListener, 527
- getLastDeliveredSequenceId, 527
- getNextConsumerId, 527
- getNextProducerId, 527
- getSessionId, 527
- getSessionInfo, 528
- getTransactionContext, 528
- isAutoAcknowledge, 528
- isClientAcknowledge, 528
- isDupsOkAcknowledge, 528
- isIndividualAcknowledge, 528
- isStarted, 528
- isTransacted, 529
- oneway, 529
- recover, 529
- redispatch, 529
- removeConsumer, 530
- removeProducer, 530
- rollback, 530
- send, 530
- setLastDeliveredSequenceId, 531
- start, 531
- stop, 531
- syncRequest, 531
- unsubscribe, 531
- wakeup, 532
- activemq::core::ActiveMQSessionExecutor, 533
 - ~ActiveMQSessionExecutor, 534
- ActiveMQSessionExecutor, 534
 - clear, 534
 - clearMessagesInProgress, 534
 - close, 534
 - execute, 534
 - executeFirst, 534
 - getUnconsumedMessages, 535
 - hasUnconsumedMessages, 535
 - isEmpty, 535
 - isRunning, 535
 - iterate, 535
 - start, 535
 - stop, 535
 - wakeup, 536
- activemq::core::ActiveMQTransactionContext, 719
 - ~ActiveMQTransactionContext, 720
 - ActiveMQTransactionContext, 720
 - addSynchronization, 720
 - begin, 720
 - commit, 720
 - getTransactionId, 720
 - isInTransaction, 721
 - removeSynchronization, 721
 - rollback, 721
- activemq::core::DispatchData, 1786
 - DispatchData, 1786
 - getConsumerId, 1786
 - getMessage, 1786
- activemq::core::Dispatcher, 1787
 - ~Dispatcher, 1787
 - dispatch, 1787
- activemq::core::MessageDispatchChannel, 2599
 - ~MessageDispatchChannel, 2600
 - clear, 2600
 - close, 2600
 - dequeue, 2600
 - dequeueNoWait, 2601
 - enqueue, 2601
 - enqueueFirst, 2601
 - isClosed, 2601
 - isEmpty, 2601
 - isRunning, 2602
 - lock, 2602
 - MessageDispatchChannel, 2600
 - notify, 2602
 - notifyAll, 2602
 - peek, 2603
 - removeAll, 2603
 - size, 2603
 - start, 2603
 - stop, 2603
 - tryLock, 2603
 - unlock, 2604

- wait, 2604, 2605
- activemq::core::policies, 91
- activemq::core::policies::DefaultPrefetchPolicy, 1673
 - ~DefaultPrefetchPolicy, 1674
 - clone, 1674
 - DEFAULT_DURABLE_TOPIC_PREFETCH, 1676
 - DEFAULT_QUEUE_BROWSER_PREFETCH, 1676
 - DEFAULT_QUEUE_PREFETCH, 1676
 - DEFAULT_TOPIC_PREFETCH, 1676
 - DefaultPrefetchPolicy, 1674
 - getDurableTopicPrefetch, 1674
 - getMaxPrefetchLimit, 1674
 - getQueueBrowserPrefetch, 1674
 - getQueuePrefetch, 1675
 - getTopicPrefetch, 1675
 - MAX_PREFETCH_SIZE, 1676
 - setDurableTopicPrefetch, 1675
 - setQueueBrowserPrefetch, 1675
 - setQueuePrefetch, 1675
 - setTopicPrefetch, 1676
- activemq::core::policies::DefaultRedeliveryPolicy, 1677
 - ~DefaultRedeliveryPolicy, 1678
 - clone, 1678
 - DefaultRedeliveryPolicy, 1678
 - getBackOffMultiplier, 1678
 - getCollisionAvoidancePercent, 1678
 - getInitialRedeliveryDelay, 1678
 - getMaximumRedeliveries, 1678
 - getRedeliveryDelay, 1679
 - isUseCollisionAvoidance, 1679
 - isUseExponentialBackOff, 1679
 - setBackOffMultiplier, 1679
 - setCollisionAvoidancePercent, 1680
 - setInitialRedeliveryDelay, 1680
 - setMaximumRedeliveries, 1680
 - setUseCollisionAvoidance, 1680
 - setUseExponentialBackOff, 1680
- activemq::core::PrefetchPolicy, 2976
 - ~PrefetchPolicy, 2977
 - clone, 2977
 - configure, 2977
 - getDurableTopicPrefetch, 2977
 - getMaxPrefetchLimit, 2978
 - getQueueBrowserPrefetch, 2978
 - getQueuePrefetch, 2978
 - getTopicPrefetch, 2978
 - PrefetchPolicy, 2977
 - setDurableTopicPrefetch, 2978
 - setQueueBrowserPrefetch, 2979
 - setQueuePrefetch, 2979
 - setTopicPrefetch, 2979
- activemq::core::RedeliveryPolicy, 3177
 - ~RedeliveryPolicy, 3178
 - clone, 3178
 - configure, 3178
 - getBackOffMultiplier, 3178
 - getCollisionAvoidancePercent, 3179
 - getInitialRedeliveryDelay, 3179
 - getMaximumRedeliveries, 3179
 - getRedeliveryDelay, 3179
 - isUseCollisionAvoidance, 3180
 - isUseExponentialBackOff, 3180
 - NO_MAXIMUM_REDELIVERIES, 3181
 - RedeliveryPolicy, 3178
 - setBackOffMultiplier, 3180
 - setCollisionAvoidancePercent, 3180
 - setInitialRedeliveryDelay, 3180
 - setMaximumRedeliveries, 3180
 - setUseCollisionAvoidance, 3181
 - setUseExponentialBackOff, 3181
- activemq::core::Synchronization, 3715
 - ~Synchronization, 3715
 - afterCommit, 3715
 - afterRollback, 3715
 - beforeEnd, 3715
- activemq::exceptions, 92
- activemq::exceptions::ActiveMQException, 357
 - ~ActiveMQException, 358
 - ActiveMQException, 357, 358
 - clone, 358
 - convertToCMSException, 358
- activemq::exceptions::BrokerException, 867
 - ~BrokerException, 867
 - BrokerException, 867
 - clone, 867
- activemq::io, 93
- activemq::io::LoggingInputStream, 2399
 - ~LoggingInputStream, 2399
 - doReadArrayBounded, 2399
 - doReadByte, 2399
 - LoggingInputStream, 2399
- activemq::io::LoggingOutputStream, 2401
 - ~LoggingOutputStream, 2401
 - doWriteArrayBounded, 2401
 - doWriteByte, 2401
 - LoggingOutputStream, 2401
- activemq::library, 94
- activemq::library::ActiveMQCPP, 320
 - ~ActiveMQCPP, 320
 - ActiveMQCPP, 320
 - initializeLibrary, 320, 321
 - operator=, 321
 - shutdownLibrary, 321
- activemq::state, 95

- activemq::state::CommandVisitor, 1200
 - ~CommandVisitor, 1202
 - processBeginTransaction, 1202
 - processBrokerError, 1202
 - processBrokerInfo, 1202
 - processCommitTransactionOnePhase, 1202
 - processCommitTransactionTwoPhase, 1202
 - processConnectionControl, 1202
 - processConnectionError, 1203
 - processConnectionInfo, 1203
 - processConsumerControl, 1203
 - processConsumerInfo, 1203
 - processControlCommand, 1203
 - processDestinationInfo, 1203
 - processEndTransaction, 1203
 - processFlushCommand, 1203
 - processForgetTransaction, 1204
 - processKeepAliveInfo, 1204
 - processMessage, 1204
 - processMessageAck, 1204
 - processMessageDispatch, 1204
 - processMessageDispatchNotification, 1204
 - processMessagePull, 1204
 - processPrepareTransaction, 1204
 - processProducerAck, 1204
 - processProducerInfo, 1205
 - processRecoverTransactions, 1205
 - processRemoveConnection, 1205
 - processRemoveConsumer, 1205
 - processRemoveDestination, 1205
 - processRemoveInfo, 1205
 - processRemoveProducer, 1205
 - processRemoveSession, 1205
 - processRemoveSubscriptionInfo, 1206
 - processReplayCommand, 1206
 - processResponse, 1206
 - processRollbackTransaction, 1206
 - processSessionInfo, 1206
 - processShutdownInfo, 1206
 - processTransactionInfo, 1206
 - processWireFormat, 1206
- activemq::state::CommandVisitorAdapter, 1208
 - ~CommandVisitorAdapter, 1211
 - processBeginTransaction, 1211
 - processBrokerError, 1211
 - processBrokerInfo, 1211
 - processCommitTransactionOnePhase, 1211
 - processCommitTransactionTwoPhase, 1211
 - processConnectionControl, 1211
 - processConnectionError, 1211
 - processConnectionInfo, 1211
 - processConsumerControl, 1211
 - processConsumerInfo, 1211
 - processControlCommand, 1211
 - processDestinationInfo, 1211
 - processEndTransaction, 1211
 - processFlushCommand, 1211
 - processForgetTransaction, 1211
 - processKeepAliveInfo, 1211
 - processMessage, 1211
 - processMessageAck, 1211
 - processMessageDispatch, 1211
 - processMessageDispatchNotification, 1211
 - processMessagePull, 1211
 - processPrepareTransaction, 1211
 - processProducerAck, 1211
 - processProducerInfo, 1211
 - processRecoverTransactions, 1211
 - processRemoveConnection, 1211
 - processRemoveConsumer, 1211
 - processRemoveDestination, 1211
 - processRemoveInfo, 1211
 - processRemoveProducer, 1212
 - processRemoveSession, 1212
 - processRemoveSubscriptionInfo, 1212
 - processReplayCommand, 1212
 - processResponse, 1212
 - processRollbackTransaction, 1212
 - processSessionInfo, 1212
 - processShutdownInfo, 1212
 - processTransactionInfo, 1212
 - processWireFormat, 1213
- activemq::state::ConnectionState, 1389
 - ~ConnectionState, 1390
 - addSession, 1390
 - addTempDestination, 1390
 - addTransactionState, 1390
 - checkShutdown, 1390
 - ConnectionState, 1390
 - getInfo, 1390
 - getRecoveringPullConsumers, 1390
 - getSessionState, 1390
 - getSessionStates, 1390
 - getTempDestinations, 1390
 - getTransactionState, 1390
 - getTransactionStates, 1390
 - isConnectionInterruptProcessingComplete, 1391
 - removeSession, 1391
 - removeTempDestination, 1391
 - removeTransactionState, 1391
 - reset, 1391
 - setConnectionInterruptProcessingComplete, 1391
 - shutdown, 1391
 - toString, 1391

- activemq::state::ConnectionStateTracker, 1392
 - ~ConnectionStateTracker, 1394
 - connectionInterruptProcessingComplete, 1394
 - ConnectionStateTracker, 1394
 - getMaxCacheSize, 1394
 - isRestoreConsumers, 1394
 - isRestoreProducers, 1394
 - isRestoreSessions, 1394
 - isRestoreTransaction, 1394
 - isTrackMessages, 1394
 - isTrackTransactionProducers, 1394
 - isTrackTransactions, 1394
 - processBeginTransaction, 1394
 - processCommitTransactionOnePhase, 1394
 - processCommitTransactionTwoPhase, 1394
 - processConnectionInfo, 1395
 - processConsumerInfo, 1395
 - processDestinationInfo, 1395
 - processEndTransaction, 1395
 - processMessage, 1395
 - processMessageAck, 1395
 - processPrepareTransaction, 1395
 - processProducerInfo, 1396
 - processRemoveConnection, 1396
 - processRemoveConsumer, 1396
 - processRemoveDestination, 1396
 - processRemoveProducer, 1396
 - processRemoveSession, 1396
 - processRollbackTransaction, 1396
 - processSessionInfo, 1397
 - RemoveTransactionAction, 1398
 - restore, 1397
 - setMaxCacheSize, 1398
 - setRestoreConsumers, 1398
 - setRestoreProducers, 1398
 - setRestoreSessions, 1398
 - setRestoreTransaction, 1398
 - setTrackMessages, 1398
 - setTrackTransactionProducers, 1398
 - setTrackTransactions, 1398
 - track, 1398
 - trackBack, 1398
 - transportInterrupted, 1398
- activemq::state::ConsumerState, 1492
 - ~ConsumerState, 1492
 - ConsumerState, 1492
 - getInfo, 1492
 - toString, 1492
- activemq::state::ProducerState, 3125
 - ~ProducerState, 3125
 - getInfo, 3125
 - getTransactionState, 3125
 - ProducerState, 3125
 - setTransactionState, 3125
 - toString, 3125
- activemq::state::SessionState, 3437
 - ~SessionState, 3438
 - addConsumer, 3438
 - addProducer, 3438
 - checkShutdown, 3438
 - getConsumerState, 3438
 - getConsumerStates, 3438
 - getInfo, 3438
 - getProducerState, 3438
 - getProducerStates, 3438
 - removeConsumer, 3438
 - removeProducer, 3438
 - SessionState, 3438
 - shutdown, 3438
 - toString, 3438
- activemq::state::Tracked, 3818
 - ~Tracked, 3818
 - isWaitingForResponse, 3818
 - onResponse, 3818
 - Tracked, 3818
- activemq::state::TransactionState, 3875
 - ~TransactionState, 3876
 - addCommand, 3876
 - addProducerState, 3876
 - checkShutdown, 3876
 - getCommands, 3876
 - getId, 3876
 - getPreparedResult, 3876
 - getProducerStates, 3876
 - isPrepared, 3876
 - setPrepared, 3876
 - setPreparedResult, 3876
 - shutdown, 3876
 - toString, 3876
 - TransactionState, 3876
- activemq::threads, 96
- activemq::threads::CompositeTask, 1221
 - ~CompositeTask, 1221
 - isPending, 1221
- activemq::threads::CompositeTaskRunner, 1223
 - ~CompositeTaskRunner, 1224
 - addTask, 1224
 - CompositeTaskRunner, 1224
 - iterate, 1224
 - removeTask, 1224
 - run, 1224
 - shutdown, 1224
 - wakeup, 1225
- activemq::threads::DedicatedTaskRunner, 1671
 - ~DedicatedTaskRunner, 1671
 - DedicatedTaskRunner, 1671

- run, 1671
- shutdown, 1671, 1672
- wakeup, 1672
- activemq::threads::Task, 3734
 - ~Task, 3734
- iterate, 3734
- activemq::threads::TaskRunner, 3736
 - ~TaskRunner, 3736
- shutdown, 3736
- wakeup, 3736
- activemq::transport, 97
- activemq::transport::AbstractTransportFactory, 201
 - ~AbstractTransportFactory, 201
 - createWireFormat, 201
- activemq::transport::CompositeTransport, 1226
 - ~CompositeTransport, 1226
- addURI, 1226
- removeURI, 1226
- activemq::transport::correlator, 98
- activemq::transport::correlator::FutureResponse, 1969
 - ~FutureResponse, 1969
 - FutureResponse, 1969
 - getResponse, 1969, 1970
 - setResponse, 1970
- activemq::transport::correlator::ResponseCorrelator, 3291
 - ~ResponseCorrelator, 3292
 - close, 3292
 - onCommand, 3292
 - oneway, 3292
 - onTransportException, 3293
 - request, 3293
 - ResponseCorrelator, 3292
 - start, 3294
- activemq::transport::DefaultTransportListener, 1704
 - ~DefaultTransportListener, 1704
 - onCommand, 1704
 - onException, 1704
 - transportInterrupted, 1705
 - transportResumed, 1705
- activemq::transport::failover, 99
- activemq::transport::failover::BackupTransport, 752
 - ~BackupTransport, 752
 - BackupTransport, 752
 - getTransport, 752
 - getUri, 753
 - isClosed, 753
 - onException, 753
 - setClosed, 753
 - setTransport, 753
 - setUri, 753
- activemq::transport::failover::BackupTransportPool, 755
 - ~BackupTransportPool, 756
 - BackupTransport, 757
 - BackupTransportPool, 756
 - getBackup, 756
 - getBackupPoolSize, 756
 - isEnabled, 756
 - isPending, 756
 - iterate, 757
 - setBackupPoolSize, 757
 - setEnabled, 757
- activemq::transport::failover::CloseTransportsTask, 1151
 - ~CloseTransportsTask, 1151
 - add, 1151
 - CloseTransportsTask, 1151
 - isPending, 1151
 - iterate, 1151
- activemq::transport::failover::FailoverTransport, 1873
 - ~FailoverTransport, 1875
 - add, 1875
 - addURI, 1876
 - close, 1876
 - FailoverTransport, 1875
 - FailoverTransportListener, 1884
 - getBackOffMultiplier, 1876
 - getBackupPoolSize, 1877
 - getInitialReconnectDelay, 1877
 - getMaxCacheSize, 1877
 - getMaxReconnectAttempts, 1877
 - getMaxReconnectDelay, 1877
 - getReconnectDelay, 1877
 - getRemoteAddress, 1877
 - getStartupMaxReconnectAttempts, 1877
 - getTimeout, 1877
 - getTransportListener, 1877
 - handleTransportFailure, 1877
 - isBackup, 1878
 - isClosed, 1878
 - isConnected, 1878
 - isFaultTolerant, 1878
 - isInitialized, 1878
 - isPending, 1879
 - isRandomize, 1879
 - isTrackMessages, 1879
 - isTrackTransactionProducers, 1879
 - isUseExponentialBackOff, 1879
 - iterate, 1879
 - narrow, 1879
 - oneway, 1880
 - reconnect, 1880

- removeURI, 1880
- request, 1881
- restoreTransport, 1882
- setBackOffMultiplier, 1882
- setBackup, 1882
- setBackupPoolSize, 1882
- setConnectionInterruptProcessingComplete, 1882
- setInitialized, 1882
- setInitialReconnectDelay, 1882
- setMaxCacheSize, 1883
- setMaxReconnectAttempts, 1883
- setMaxReconnectDelay, 1883
- setRandomize, 1883
- setReconnectDelay, 1883
- setStartupMaxReconnectAttempts, 1883
- setTimeout, 1883
- setTrackMessages, 1883
- setTrackTransactionProducers, 1883
- setTransportListener, 1883
- setUseExponentialBackOff, 1883
- setWireFormat, 1884
- start, 1884
- stop, 1884
- activemq::transport::failover::FailoverTransportFactory, 1885
 - ~FailoverTransportFactory, 1886
 - create, 1886
 - createComposite, 1886
 - doCreateComposite, 1886
- activemq::transport::failover::FailoverTransportListener, 1888
 - ~FailoverTransportListener, 1889
 - FailoverTransportListener, 1889
 - onCommand, 1889
 - onException, 1889
 - transportInterrupted, 1889
 - transportResumed, 1889
- activemq::transport::failover::URIPool, 3942
 - ~URIPool, 3942
 - addURI, 3943
 - addURIs, 3943
 - getURI, 3943
 - isRandomize, 3943
 - removeURI, 3943
 - setRandomize, 3944
 - URIPool, 3942
- activemq::transport::inactivity, 100
- activemq::transport::inactivity::InactivityMonitor, 2004
 - ~InactivityMonitor, 2005
 - AsyncSignalReadErrorTask, 2007
 - AsyncWriteTask, 2007
 - close, 2005
 - getInitialDelayTime, 2005
 - getReadCheckTime, 2005
 - getWriteCheckTime, 2005
 - InactivityMonitor, 2005
 - isKeepAliveResponseRequired, 2005
 - onCommand, 2005
 - oneway, 2006
 - onException, 2006
 - ReadChecker, 2007
 - setInitialDelayTime, 2006
 - setKeepAliveResponseRequired, 2007
 - setReadCheckTime, 2007
 - setWriteCheckTime, 2007
 - WriteChecker, 2007
- activemq::transport::inactivity::ReadChecker, 3162
 - ~ReadChecker, 3162
 - ReadChecker, 3162
 - run, 3162
- activemq::transport::inactivity::WriteChecker, 4020
 - ~WriteChecker, 4020
 - run, 4020
 - WriteChecker, 4020
- activemq::transport::IOTransport, 2145
 - ~IOTransport, 2147
 - close, 2147
 - getRemoteAddress, 2147
 - getTransportListener, 2147
 - IOTransport, 2146
 - isClosed, 2147
 - isConnected, 2148
 - isFaultTolerant, 2148
 - narrow, 2148
 - oneway, 2148
 - reconnect, 2148
 - request, 2149
 - run, 2149
 - setInputStream, 2150
 - setOutputStream, 2150
 - setTransportListener, 2150
 - setWireFormat, 2150
 - start, 2150
 - stop, 2151
- activemq::transport::logging, 101
- activemq::transport::logging::LoggingTransport, 2403
 - ~LoggingTransport, 2403
 - LoggingTransport, 2403
 - onCommand, 2404
 - oneway, 2404
 - request, 2404
- activemq::transport::mock, 102

- activemq::transport::mock::InternalCommandListener, start, 2777
 - 2122
 - ~InternalCommandListener, 2122
 - InternalCommandListener, 2122
 - onCommand, 2122
 - run, 2123
 - setResponseBuilder, 2123
 - setTransport, 2123
- activemq::transport::mock::MockTransport, 2768
 - ~MockTransport, 2770
 - close, 2770
 - fireCommand, 2770
 - fireException, 2771
 - getInstance, 2771
 - getNumReceivedMessageBeforeFail, 2771
 - getNumReceivedMessages, 2771
 - getNumSentKeepAlives, 2771
 - getNumSentKeepAlivesBeforeFail, 2771
 - getNumSentMessageBeforeFail, 2771
 - getNumSentMessages, 2771
 - getRemoteAddress, 2771
 - getTransportListener, 2772
 - getWireFormat, 2772
 - isClosed, 2772
 - isConnected, 2772
 - isFailOnClose, 2772
 - isFailOnKeepAliveSends, 2773
 - isFailOnReceiveMessage, 2773
 - isFailOnSendMessage, 2773
 - isFailOnStart, 2773
 - isFailOnStop, 2773
 - isFaultTolerant, 2773
 - MockTransport, 2770
 - narrow, 2773
 - oneway, 2773
 - reconnect, 2774
 - request, 2774
 - setFailOnClose, 2775
 - setFailOnKeepAliveSends, 2776
 - setFailOnReceiveMessage, 2776
 - setFailOnSendMessage, 2776
 - setFailOnStart, 2776
 - setFailOnStop, 2776
 - setNumReceivedMessageBeforeFail, 2776
 - setNumReceivedMessages, 2776
 - setNumSentKeepAlives, 2776
 - setNumSentKeepAlivesBeforeFail, 2776
 - setNumSentMessageBeforeFail, 2776
 - setNumSentMessages, 2776
 - setOutgoingListener, 2776
 - setResponseBuilder, 2776
 - setTransportListener, 2777
 - setWireFormat, 2777
- activemq::transport::mock::MockTransportFactory, 2779
 - ~MockTransportFactory, 2780
 - create, 2780
 - createComposite, 2780
 - doCreateComposite, 2780
- activemq::transport::mock::ResponseBuilder, 3289
 - ~ResponseBuilder, 3289
 - buildIncomingCommands, 3289
 - buildResponse, 3290
- activemq::transport::tcp, 103
- activemq::transport::tcp::SslTransport, 3574
 - ~SslTransport, 3575
 - configureSocket, 3575
 - createSocket, 3575
 - SslTransport, 3574
- activemq::transport::tcp::SslTransportFactory, 3576
 - ~SslTransportFactory, 3576
 - doCreateComposite, 3576
- activemq::transport::tcp::TcpTransport, 3752
 - ~TcpTransport, 3753
 - close, 3753
 - configureSocket, 3753
 - connect, 3753
 - createSocket, 3754
 - isClosed, 3754
 - isConnected, 3754
 - isFaultTolerant, 3754
 - TcpTransport, 3753
- activemq::transport::tcp::TcpTransportFactory, 3756
 - ~TcpTransportFactory, 3757
 - create, 3757
 - createComposite, 3757
 - doCreateComposite, 3757
- activemq::transport::Transport, 3883
 - ~Transport, 3884
 - getRemoteAddress, 3884
 - getTransportListener, 3884
 - isClosed, 3884
 - isConnected, 3885
 - isFaultTolerant, 3885
 - narrow, 3885
 - oneway, 3886
 - reconnect, 3886
 - request, 3886, 3887
 - setTransportListener, 3887
 - setWireFormat, 3888
 - start, 3888
 - stop, 3888

- activemq::transport::TransportFactory, 3889
 - ~TransportFactory, 3889
 - create, 3889
 - createComposite, 3890
- activemq::transport::TransportFilter, 3891
 - ~TransportFilter, 3893
 - close, 3893
 - fire, 3893
 - getRemoteAddress, 3894
 - getTransportListener, 3894
 - isClosed, 3894
 - isConnected, 3894
 - isFaultTolerant, 3894
 - listener, 3898
 - narrow, 3895
 - next, 3898
 - onCommand, 3895
 - oneway, 3895
 - onException, 3896
 - reconnect, 3896
 - request, 3896, 3897
 - setTransportListener, 3897
 - setWireFormat, 3897
 - start, 3897
 - stop, 3898
 - TransportFilter, 3893
 - transportInterrupted, 3898
 - transportResumed, 3898
- activemq::transport::TransportListener, 3900
 - ~TransportListener, 3900
 - onCommand, 3900
 - onException, 3901
 - transportInterrupted, 3901
 - transportResumed, 3901
- activemq::transport::TransportRegistry, 3902
 - ~TransportRegistry, 3903
 - findFactory, 3903
 - getInstance, 3903
 - getTransportNames, 3903
 - registerFactory, 3903
 - unregisterFactory, 3904
- activemq::util, 104
- activemq::util::ActiveMQProperties, 478
 - ~ActiveMQProperties, 479
 - ActiveMQProperties, 479
 - clear, 479
 - clone, 479
 - copy, 479
 - getProperties, 479, 480
 - getProperty, 480
 - hasProperty, 480
 - isEmpty, 480
 - remove, 481
 - setProperty, 481
- setProperty, 481
 - toArray, 481
 - toString, 481
- activemq::util::CMSExceptionSupport, 1163
 - ~CMSExceptionSupport, 1163
 - create, 1163
 - createMessageEOFException, 1163
 - createMessageFormatException, 1163
- activemq::util::CompositeData, 1219
 - ~CompositeData, 1220
 - CompositeData, 1220
 - getComponents, 1220
 - getFragment, 1220
 - getHost, 1220
 - getParameters, 1220
 - getPath, 1220
 - getScheme, 1220
 - setComponents, 1220
 - setFragment, 1220
 - setHost, 1220
 - setParameters, 1220
 - setPath, 1220
 - setScheme, 1220
 - toURI, 1220
- activemq::util::IdGenerator, 1989
 - ~IdGenerator, 1989
 - compare, 1989
 - generateId, 1990
 - getHostname, 1990
 - getSeedFromId, 1990
 - getSequenceFromId, 1990
 - IdGenerator, 1989
- activemq::util::LongSequenceGenerator, 2455
 - ~LongSequenceGenerator, 2455
 - getLastSequenceId, 2455
 - getNextSequenceId, 2455
 - LongSequenceGenerator, 2455
- activemq::util::MarshallingSupport, 2493
 - ~MarshallingSupport, 2494
 - asciiToModifiedUtf8, 2494
 - MarshallingSupport, 2494
 - modifiedUtf8ToAscii, 2494
 - readString16, 2494
 - readString32, 2495
 - writeString, 2495
 - writeString16, 2496
 - writeString32, 2496
- activemq::util::MemoryUsage, 2512
 - ~MemoryUsage, 2513
 - decreaseUsage, 2513
 - enqueueUsage, 2513
 - getLimit, 2513
 - getUsage, 2513
 - increaseUsage, 2514

- isFull, 2514
- MemoryUsage, 2513
- setLimit, 2514
- setUsage, 2514
- waitForSpace, 2514
- activemq::util::PrimitiveList, 2980
 - ~PrimitiveList, 2982
 - getBool, 2983
 - getByte, 2983
 - getByteArray, 2983
 - getChar, 2984
 - getDouble, 2984
 - getFloat, 2985
 - getInt, 2985
 - getLong, 2985
 - getShort, 2986
 - getString, 2986
 - PrimitiveList, 2982
 - setBool, 2986
 - setByte, 2987
 - setByteArray, 2987
 - setChar, 2987
 - setDouble, 2988
 - setFloat, 2988
 - setInt, 2988
 - setLong, 2989
 - setShort, 2989
 - setString, 2989
 - toString, 2990
- activemq::util::PrimitiveMap, 2991
 - ~PrimitiveMap, 2993
 - getBool, 2994
 - getByte, 2994
 - getByteArray, 2994
 - getChar, 2995
 - getDouble, 2995
 - getFloat, 2995
 - getInt, 2996
 - getLong, 2996
 - getShort, 2997
 - getString, 2997
 - PrimitiveMap, 2993
 - setBool, 2997
 - setByte, 2998
 - setByteArray, 2998
 - setChar, 2998
 - setDouble, 2998
 - setFloat, 2999
 - setInt, 2999
 - setLong, 2999
 - setShort, 2999
 - setString, 2999
 - toString, 3000
- activemq::util::PrimitiveValueConverter, 3010
 - ~PrimitiveValueConverter, 3010
 - convert, 3010
 - PrimitiveValueConverter, 3010
- activemq::util::PrimitiveValueNode, 3012
 - ~PrimitiveValueNode, 3018
 - BIG_STRING_TYPE, 3016
 - BOOLEAN_TYPE, 3015
 - BYTE_ARRAY_TYPE, 3016
 - BYTE_TYPE, 3016
 - CHAR_TYPE, 3016
 - clear, 3018
 - DOUBLE_TYPE, 3016
 - FLOAT_TYPE, 3016
 - getBool, 3018
 - getByte, 3019
 - getByteArray, 3019
 - getChar, 3019
 - getDouble, 3019
 - getFloat, 3020
 - getInt, 3020
 - getList, 3020
 - getLong, 3020
 - getMap, 3021
 - getShort, 3021
 - getString, 3021
 - getType, 3021
 - getValue, 3022
 - INTEGER_TYPE, 3016
 - LIST_TYPE, 3016
 - LONG_TYPE, 3016
 - MAP_TYPE, 3016
 - NULL_TYPE, 3015
 - operator=, 3022
 - operator==, 3022
 - PrimitiveType, 3015
 - PrimitiveValueNode, 3016–3018
 - setBool, 3022
 - setByte, 3022
 - setByteArray, 3022
 - setChar, 3023
 - setDouble, 3023
 - setFloat, 3023
 - setInt, 3023
 - setList, 3023
 - setLong, 3024
 - setMap, 3024
 - setShort, 3024
 - setString, 3024
 - setValue, 3024
 - SHORT_TYPE, 3016
 - STRING_TYPE, 3016
 - toString, 3024
- activemq::util::PrimitiveValueNode::PrimitiveValue, 3008

- boolValue, 3009
- byteArrayValue, 3009
- byteValue, 3009
- charValue, 3009
- doubleValue, 3009
- floatValue, 3009
- intValue, 3009
- listValue, 3009
- longValue, 3009
- mapValue, 3009
- shortValue, 3009
- stringValue, 3009
- activemq::util::URISupport, 3945
 - createQueryString, 3945
 - parseComposite, 3945
 - parseQuery, 3946
 - parseURL, 3946
- activemq::util::Usage, 3964
 - ~Usage, 3964
 - decreaseUsage, 3964
 - enqueueUsage, 3964
 - increaseUsage, 3965
 - isFull, 3965
 - waitForSpace, 3965
- activemq::wireformat, 105
- activemq::wireformat::MarshalAware, 2484
 - ~MarshalAware, 2484
 - afterMarshal, 2484
 - afterUnmarshal, 2485
 - beforeMarshal, 2485
 - beforeUnmarshal, 2485
 - getMarshaledForm, 2485
 - isMarshalAware, 2485
 - setMarshaledForm, 2486
- activemq::wireformat::openwire, 106
- activemq::wireformat::openwire::marshal, 107
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 807
 - ~BaseDataStreamMarshaller, 813
 - looseMarshal, 813
 - looseMarshalBrokerError, 814
 - looseMarshalCachedObject, 814
 - looseMarshalLong, 814
 - looseMarshalNestedObject, 815
 - looseMarshalObjectArray, 815
 - looseMarshalString, 815
 - looseUnmarshal, 816
 - looseUnmarshalBrokerError, 816
 - looseUnmarshalByteArray, 816
 - looseUnmarshalCachedObject, 817
 - looseUnmarshalConstByteArray, 817
 - looseUnmarshalLong, 818
 - looseUnmarshalNestedObject, 818
 - looseUnmarshalString, 818
- readAsciiString, 819
- tightMarshal1, 819
- tightMarshal2, 819
- tightMarshalBrokerError1, 820
- tightMarshalBrokerError2, 820
- tightMarshalCachedObject1, 820
- tightMarshalCachedObject2, 821
- tightMarshalLong1, 821
- tightMarshalLong2, 822
- tightMarshalNestedObject1, 822
- tightMarshalNestedObject2, 822
- tightMarshalObjectArray1, 823
- tightMarshalObjectArray2, 823
- tightMarshalString1, 824
- tightMarshalString2, 824
- tightUnmarshal, 824
- tightUnmarshalBrokerError, 825
- tightUnmarshalByteArray, 825
- tightUnmarshalCachedObject, 826
- tightUnmarshalConstByteArray, 826
- tightUnmarshalLong, 826
- tightUnmarshalNestedObject, 827
- tightUnmarshalString, 827
- toHexFromBytes, 828
- toString, 828
- activemq::wireformat::openwire::marshal::DataStreamMarshaller, 1610
 - ~DataStreamMarshaller, 1611
 - createObject, 1611
 - getDataStructureType, 1617
 - looseMarshal, 1623
 - looseUnmarshal, 1631
 - tightMarshal1, 1638
 - tightMarshal2, 1645
 - tightUnmarshal, 1652
- activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3001
 - ~PrimitiveTypesMarshaller, 3003
 - marshal, 3003
 - marshalList, 3003
 - marshalMap, 3004
 - marshalPrimitive, 3004
 - marshalPrimitiveList, 3004
 - marshalPrimitiveMap, 3004
 - PrimitiveTypesMarshaller, 3003
 - unmarshal, 3005
 - unmarshalList, 3005
 - unmarshalMap, 3006
 - unmarshalPrimitive, 3006
 - unmarshalPrimitiveList, 3006
 - unmarshalPrimitiveMap, 3007
- activemq::wireformat::openwire::marshal::v1, 108

- activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller, 213
 - ~ActiveMQBlobMessageMarshaller, 214
 - ActiveMQBlobMessageMarshaller, 214
 - createObject, 214
 - getDataStructureType, 214
 - looseMarshal, 214
 - looseUnmarshal, 214
 - tightMarshal1, 215
 - tightMarshal2, 215
 - tightUnmarshal, 216
- activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller, 253
 - ~ActiveMQBytesMessageMarshaller, 254
 - ActiveMQBytesMessageMarshaller, 254
 - createObject, 254
 - getDataStructureType, 254
 - looseMarshal, 254
 - looseUnmarshal, 254
 - tightMarshal1, 255
 - tightMarshal2, 255
 - tightUnmarshal, 256
- activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller, 337
 - ~ActiveMQDestinationMarshaller, 338
 - ActiveMQDestinationMarshaller, 338
 - looseMarshal, 338
 - looseUnmarshal, 338
 - tightMarshal1, 339
 - tightMarshal2, 339
 - tightUnmarshal, 340
- activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller, 378
 - ~ActiveMQMapMessageMarshaller, 379
 - ActiveMQMapMessageMarshaller, 379
 - createObject, 379
 - getDataStructureType, 379
 - looseMarshal, 379
 - looseUnmarshal, 379
 - tightMarshal1, 380
 - tightMarshal2, 380
 - tightUnmarshal, 381
- activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller, 405
 - ~ActiveMQMessageMarshaller, 406
 - ActiveMQMessageMarshaller, 406
 - createObject, 406
 - getDataStructureType, 406
 - looseMarshal, 406
 - looseUnmarshal, 406
 - tightMarshal1, 407
 - tightMarshal2, 407
 - tightUnmarshal, 408
- activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMessageMarshaller, 450
 - ~ActiveMQObjectMessageMarshaller, 451
 - ActiveMQObjectMessageMarshaller, 451
 - createObject, 451
 - getDataStructureType, 451
 - looseMarshal, 451
 - looseUnmarshal, 451
 - tightMarshal1, 452
 - tightMarshal2, 452
 - tightUnmarshal, 453
- activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller, 495
 - ~ActiveMQQueueMarshaller, 496
 - ActiveMQQueueMarshaller, 496
 - createObject, 496
 - getDataStructureType, 496
 - looseMarshal, 496
 - looseUnmarshal, 496
 - tightMarshal1, 497
 - tightMarshal2, 497
 - tightUnmarshal, 498
- activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMessageMarshaller, 556
 - ~ActiveMQStreamMessageMarshaller, 557
 - ActiveMQStreamMessageMarshaller, 557
 - createObject, 557
 - getDataStructureType, 557
 - looseMarshal, 557
 - looseUnmarshal, 557
 - tightMarshal1, 558
 - tightMarshal2, 558
 - tightUnmarshal, 559
- activemq::wireformat::openwire::marshal::v1::ActiveMQTempDestinationMarshaller, 584
 - ~ActiveMQTempDestinationMarshaller, 585
 - ActiveMQTempDestinationMarshaller, 585
 - looseMarshal, 585
 - looseUnmarshal, 585
 - tightMarshal1, 586
 - tightMarshal2, 586
 - tightUnmarshal, 587
- activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller, 613
 - ~ActiveMQTempQueueMarshaller, 614
 - ActiveMQTempQueueMarshaller, 614
 - createObject, 614
 - getDataStructureType, 614
 - looseMarshal, 614
 - looseUnmarshal, 614
 - tightMarshal1, 615
 - tightMarshal2, 615
 - tightUnmarshal, 616

- activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller, 646
 - ~ActiveMQTempTopicMarshaller, 647
 - ActiveMQTempTopicMarshaller, 647
 - createObject, 647
 - getDataStructureType, 647
 - looseMarshal, 647
 - looseUnmarshal, 647
 - tightMarshal1, 648
 - tightMarshal2, 648
 - tightUnmarshal, 649
- activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller, 675
 - ~ActiveMQTextMessageMarshaller, 676
 - ActiveMQTextMessageMarshaller, 676
 - createObject, 676
 - getDataStructureType, 676
 - looseMarshal, 676
 - looseUnmarshal, 676
 - tightMarshal1, 677
 - tightMarshal2, 677
 - tightUnmarshal, 678
- activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller, 703
 - ~ActiveMQTopicMarshaller, 704
 - ActiveMQTopicMarshaller, 704
 - createObject, 704
 - getDataStructureType, 704
 - looseMarshal, 704
 - looseUnmarshal, 704
 - tightMarshal1, 705
 - tightMarshal2, 705
 - tightUnmarshal, 706
- activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller, 779
 - ~BaseCommandMarshaller, 780
 - BaseCommandMarshaller, 780
 - looseMarshal, 780
 - looseUnmarshal, 781
 - tightMarshal1, 782
 - tightMarshal2, 783
 - tightUnmarshal, 784
- activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller, 880
 - ~BrokerIdMarshaller, 881
 - BrokerIdMarshaller, 881
 - createObject, 881
 - getDataStructureType, 881
 - looseMarshal, 881
 - looseUnmarshal, 881
 - tightMarshal1, 882
 - tightMarshal2, 882
 - tightUnmarshal, 883
- activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller, 912
 - ~BrokerInfoMarshaller, 913
 - BrokerInfoMarshaller, 913
 - createObject, 913
 - getDataStructureType, 913
 - looseMarshal, 913
 - looseUnmarshal, 913
 - tightMarshal1, 914
 - tightMarshal2, 914
 - tightUnmarshal, 915
- activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller, 1280
 - ~ConnectionControlMarshaller, 1281
 - ConnectionControlMarshaller, 1281
 - createObject, 1281
 - getDataStructureType, 1281
 - looseMarshal, 1281
 - looseUnmarshal, 1281
 - tightMarshal1, 1282
 - tightMarshal2, 1282
 - tightUnmarshal, 1283
- activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller, 1312
 - ~ConnectionErrorMarshaller, 1313
 - ConnectionErrorMarshaller, 1313
 - createObject, 1313
 - getDataStructureType, 1313
 - looseMarshal, 1313
 - looseUnmarshal, 1313
 - tightMarshal1, 1314
 - tightMarshal2, 1314
 - tightUnmarshal, 1315
- activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller, 1343
 - ~ConnectionIdMarshaller, 1344
 - ConnectionIdMarshaller, 1344
 - createObject, 1344
 - getDataStructureType, 1344
 - looseMarshal, 1344
 - looseUnmarshal, 1344
 - tightMarshal1, 1345
 - tightMarshal2, 1345
 - tightUnmarshal, 1346
- activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller, 1373
 - ~ConnectionInfoMarshaller, 1374
 - ConnectionInfoMarshaller, 1374
 - createObject, 1374
 - getDataStructureType, 1374
 - looseMarshal, 1374
 - looseUnmarshal, 1374
 - tightMarshal1, 1375
 - tightMarshal2, 1375

- tightUnmarshal, 1376
- activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller, 1418
 - ~ConsumerControlMarshaller, 1419
 - ConsumerControlMarshaller, 1419
 - createObject, 1419
 - getDataStructureType, 1419
 - looseMarshal, 1419
 - looseUnmarshal, 1419
 - tightMarshal1, 1420
 - tightMarshal2, 1420
 - tightUnmarshal, 1421
- activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller, 1447
 - ~ConsumerIdMarshaller, 1448
 - ConsumerIdMarshaller, 1448
 - createObject, 1448
 - getDataStructureType, 1448
 - looseMarshal, 1448
 - looseUnmarshal, 1448
 - tightMarshal1, 1449
 - tightMarshal2, 1449
 - tightUnmarshal, 1450
- activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller, 1480
 - ~ConsumerInfoMarshaller, 1481
 - ConsumerInfoMarshaller, 1481
 - createObject, 1481
 - getDataStructureType, 1481
 - looseMarshal, 1481
 - looseUnmarshal, 1481
 - tightMarshal1, 1482
 - tightMarshal2, 1482
 - tightUnmarshal, 1483
- activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller, 1509
 - ~ControlCommandMarshaller, 1510
 - ControlCommandMarshaller, 1510
 - createObject, 1510
 - getDataStructureType, 1510
 - looseMarshal, 1510
 - looseUnmarshal, 1510
 - tightMarshal1, 1511
 - tightMarshal2, 1511
 - tightUnmarshal, 1512
- activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller, 1543
 - ~DataArrayResponseMarshaller, 1544
 - createObject, 1544
 - DataArrayResponseMarshaller, 1544
 - getDataStructureType, 1544
 - looseMarshal, 1544
 - looseUnmarshal, 1545
 - tightMarshal1, 1545
- tightMarshal2, 1545
- activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller, 1606
 - ~DataResponseMarshaller, 1607
 - createObject, 1607
 - DataResponseMarshaller, 1607
 - getDataStructureType, 1607
 - looseMarshal, 1607
 - looseUnmarshal, 1608
 - tightMarshal1, 1608
 - tightMarshal2, 1608
- activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller, 1744
 - ~DestinationInfoMarshaller, 1745
 - createObject, 1745
 - DestinationInfoMarshaller, 1745
 - getDataStructureType, 1745
 - looseMarshal, 1745
 - looseUnmarshal, 1745
 - tightMarshal1, 1746
 - tightMarshal2, 1746
- activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller, 1778
 - ~DiscoveryEventMarshaller, 1779
 - createObject, 1779
 - DiscoveryEventMarshaller, 1779
 - getDataStructureType, 1779
 - looseMarshal, 1779
 - looseUnmarshal, 1779
 - tightMarshal1, 1780
 - tightMarshal2, 1780
- activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller, 1862
 - ~ExceptionResponseMarshaller, 1863
 - createObject, 1863
 - ExceptionResponseMarshaller, 1863
 - getDataStructureType, 1863
 - looseMarshal, 1863
 - looseUnmarshal, 1864
 - tightMarshal1, 1864
 - tightMarshal2, 1864
- activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller, 1956
 - ~FlushCommandMarshaller, 1957
 - createObject, 1957
 - FlushCommandMarshaller, 1957
 - getDataStructureType, 1957
 - looseMarshal, 1957
 - looseUnmarshal, 1957

- tightMarshal1, 1958
- tightMarshal2, 1958
- tightUnmarshal, 1959
- activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller, 2110
- ~IntegerResponseMarshaller, 2111
- createObject, 2111
- getDataStructureType, 2111
- IntegerResponseMarshaller, 2111
- looseMarshal, 2111
- looseUnmarshal, 2112
- tightMarshal1, 2112
- tightMarshal2, 2112
- tightUnmarshal, 2113
- activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller, 2179
- ~JournalQueueAckMarshaller, 2180
- createObject, 2180
- getDataStructureType, 2180
- JournalQueueAckMarshaller, 2180
- looseMarshal, 2180
- looseUnmarshal, 2180
- tightMarshal1, 2181
- tightMarshal2, 2181
- tightUnmarshal, 2182
- activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller, 2208
- ~JournalTopicAckMarshaller, 2209
- createObject, 2209
- getDataStructureType, 2209
- JournalTopicAckMarshaller, 2209
- looseMarshal, 2209
- looseUnmarshal, 2209
- tightMarshal1, 2210
- tightMarshal2, 2210
- tightUnmarshal, 2211
- activemq::wireformat::openwire::marshal::v1::JournalTraceMarshaller, 2231
- ~JournalTraceMarshaller, 2232
- createObject, 2232
- getDataStructureType, 2232
- JournalTraceMarshaller, 2232
- looseMarshal, 2232
- looseUnmarshal, 2232
- tightMarshal1, 2233
- tightMarshal2, 2233
- tightUnmarshal, 2234
- activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller, 2262
- ~JournalTransactionMarshaller, 2263
- createObject, 2263
- getDataStructureType, 2263
- JournalTransactionMarshaller, 2263
- looseMarshal, 2263
- looseUnmarshal, 2263
- tightMarshal1, 2264
- tightMarshal2, 2264
- tightUnmarshal, 2265
- activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller, 2289
- ~KeepAliveInfoMarshaller, 2290
- createObject, 2290
- getDataStructureType, 2290
- KeepAliveInfoMarshaller, 2290
- looseMarshal, 2290
- looseUnmarshal, 2290
- tightMarshal1, 2291
- tightMarshal2, 2291
- activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller, 2324
- ~LastPartialCommandMarshaller, 2325
- createObject, 2325
- getDataStructureType, 2325
- LastPartialCommandMarshaller, 2325
- looseMarshal, 2325
- looseUnmarshal, 2326
- tightMarshal1, 2326
- tightMarshal2, 2326
- activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller, 2371
- ~LocalTransactionIdMarshaller, 2372
- createObject, 2372
- getDataStructureType, 2372
- LocalTransactionIdMarshaller, 2372
- looseMarshal, 2372
- looseUnmarshal, 2372
- tightMarshal1, 2373
- tightMarshal2, 2373
- activemq::wireformat::openwire::marshal::v1::MarshallerFactory, 2491
- ~MarshallerFactory, 2491
- configure, 2491
- activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller, 2581
- ~MessageAckMarshaller, 2582
- createObject, 2582
- getDataStructureType, 2582
- looseMarshal, 2582
- looseUnmarshal, 2582
- tightMarshal1, 2583
- tightMarshal2, 2583
- tightUnmarshal, 2584
- activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller, 2622

- ~MessageDispatchMarshaller, 2623
 - createObject, 2623
 - getDataStructureType, 2623
 - looseMarshal, 2623
 - looseUnmarshal, 2623
 - MessageDispatchMarshaller, 2623
 - tightMarshal1, 2624
 - tightMarshal2, 2624
 - tightUnmarshal, 2625
- activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller, 2651
 - ~MessageDispatchNotificationMarshaller, 2652
 - createObject, 2652
 - getDataStructureType, 2652
 - looseMarshal, 2652
 - looseUnmarshal, 2652
 - MessageDispatchNotificationMarshaller, 2652
 - tightMarshal1, 2653
 - tightMarshal2, 2653
 - tightUnmarshal, 2654
- activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller, 2688
 - ~MessageIdMarshaller, 2689
 - createObject, 2689
 - getDataStructureType, 2689
 - looseMarshal, 2689
 - looseUnmarshal, 2689
 - MessageIdMarshaller, 2689
 - tightMarshal1, 2690
 - tightMarshal2, 2690
 - tightUnmarshal, 2691
- activemq::wireformat::openwire::marshal::v1::MessageMarshaller, 2713
 - ~MessageMarshaller, 2714
 - looseMarshal, 2714
 - looseUnmarshal, 2714
 - MessageMarshaller, 2714
 - tightMarshal1, 2715
 - tightMarshal2, 2715
 - tightUnmarshal, 2716
- activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller, 2760
 - ~MessagePullMarshaller, 2761
 - createObject, 2761
 - getDataStructureType, 2761
 - looseMarshal, 2761
 - looseUnmarshal, 2761
 - MessagePullMarshaller, 2761
 - tightMarshal1, 2762
 - tightMarshal2, 2762
 - tightUnmarshal, 2763
- activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller, 2816
 - ~NetworkBridgeFilterMarshaller, 2817
 - createObject, 2817
 - getDataStructureType, 2817
 - looseMarshal, 2817
 - looseUnmarshal, 2817
 - NetworkBridgeFilterMarshaller, 2817
 - tightMarshal1, 2818
 - tightMarshal2, 2818
 - tightUnmarshal, 2819
- activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2942
 - ~PartialCommandMarshaller, 2943
 - createObject, 2943
 - getDataStructureType, 2943
 - looseMarshal, 2943
 - looseUnmarshal, 2944
 - PartialCommandMarshaller, 2943
 - tightMarshal1, 2944
 - tightMarshal2, 2944
 - tightUnmarshal, 2945
- activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller, 3060
 - ~ProducerAckMarshaller, 3061
 - createObject, 3061
 - getDataStructureType, 3061
 - looseMarshal, 3061
 - looseUnmarshal, 3061
 - ProducerAckMarshaller, 3061
 - tightMarshal1, 3062
 - tightMarshal2, 3062
 - tightUnmarshal, 3063
- activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller, 3092
 - ~ProducerIdMarshaller, 3093
 - createObject, 3093
 - getDataStructureType, 3093
 - looseMarshal, 3093
 - looseUnmarshal, 3093
 - ProducerIdMarshaller, 3093
 - tightMarshal1, 3094
 - tightMarshal2, 3094
 - tightUnmarshal, 3095
- activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller, 3109
 - ~ProducerInfoMarshaller, 3110
 - createObject, 3110
 - getDataStructureType, 3110
 - looseMarshal, 3110
 - looseUnmarshal, 3110
 - ProducerInfoMarshaller, 3110
 - tightMarshal1, 3111
 - tightMarshal2, 3111

- tightUnmarshal, 3112
- activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller, 3406
 - 3210
 - ~RemoveInfoMarshaller, 3211
 - createObject, 3211
 - getDataStructureType, 3211
 - looseMarshal, 3211
 - looseUnmarshal, 3211
 - RemoveInfoMarshaller, 3211
 - tightMarshal1, 3212
 - tightMarshal2, 3212
 - tightUnmarshal, 3213
- activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller, 3227
 - ~RemoveSubscriptionInfoMarshaller, 3228
 - createObject, 3228
 - getDataStructureType, 3228
 - looseMarshal, 3228
 - looseUnmarshal, 3228
 - RemoveSubscriptionInfoMarshaller, 3228
 - tightMarshal1, 3229
 - tightMarshal2, 3229
 - tightUnmarshal, 3230
- activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller, 3258
 - ~ReplayCommandMarshaller, 3259
 - createObject, 3259
 - getDataStructureType, 3259
 - looseMarshal, 3259
 - looseUnmarshal, 3259
 - ReplayCommandMarshaller, 3259
 - tightMarshal1, 3260
 - tightMarshal2, 3260
 - tightUnmarshal, 3261
- activemq::wireformat::openwire::marshal::v1::ResponseMarshaller, 3315
 - ~ResponseMarshaller, 3316
 - createObject, 3316
 - getDataStructureType, 3316
 - looseMarshal, 3316
 - looseUnmarshal, 3317
 - ResponseMarshaller, 3316
 - tightMarshal1, 3317
 - tightMarshal2, 3318
 - tightUnmarshal, 3318
- activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller, 3403
 - ~SessionIdMarshaller, 3404
 - createObject, 3404
 - getDataStructureType, 3404
 - looseMarshal, 3404
 - looseUnmarshal, 3404
 - SessionIdMarshaller, 3404
 - tightMarshal1, 3405
- tightMarshal2, 3405
- activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller, 3419
 - ~SessionInfoMarshaller, 3420
 - createObject, 3420
 - getDataStructureType, 3420
 - looseMarshal, 3420
 - looseUnmarshal, 3420
 - SessionInfoMarshaller, 3420
 - tightMarshal1, 3421
 - tightMarshal2, 3421
- activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller, 3481
 - ~ShutdownInfoMarshaller, 3482
 - createObject, 3482
 - getDataStructureType, 3482
 - looseMarshal, 3482
 - looseUnmarshal, 3482
 - ShutdownInfoMarshaller, 3482
 - tightMarshal1, 3483
 - tightMarshal2, 3483
- activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller, 3680
 - ~SubscriptionInfoMarshaller, 3681
 - createObject, 3681
 - getDataStructureType, 3681
 - looseMarshal, 3681
 - looseUnmarshal, 3681
 - SubscriptionInfoMarshaller, 3681
 - tightMarshal1, 3682
 - tightMarshal2, 3682
- activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller, 3827
 - ~TransactionIdMarshaller, 3828
 - looseMarshal, 3828
 - looseUnmarshal, 3828
 - tightMarshal1, 3829
 - tightMarshal2, 3829
 - tightUnmarshal, 3830
 - TransactionIdMarshaller, 3828
- activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller, 3855
 - ~TransactionInfoMarshaller, 3856
 - createObject, 3856
 - getDataStructureType, 3856
 - looseMarshal, 3856
 - looseUnmarshal, 3856
 - tightMarshal1, 3857
 - tightMarshal2, 3857
 - tightUnmarshal, 3858

- TransactionInfoMarshaller, 3856
- activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller, 4008
 - ~WireFormatInfoMarshaller, 4009
 - createObject, 4009
 - getDataStructureType, 4009
 - looseMarshal, 4009
 - looseUnmarshal, 4009
 - tightMarshal1, 4010
 - tightMarshal2, 4010
 - tightUnmarshal, 4011
 - WireFormatInfoMarshaller, 4009
- activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller, 4048
 - ~XATransactionIdMarshaller, 4049
 - createObject, 4049
 - getDataStructureType, 4049
 - looseMarshal, 4049
 - looseUnmarshal, 4049
 - tightMarshal1, 4050
 - tightMarshal2, 4050
 - tightUnmarshal, 4051
 - XATransactionIdMarshaller, 4049
- activemq::wireformat::openwire::marshal::v2, 113
- activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller, 221
 - ~ActiveMQBlobMessageMarshaller, 222
 - ActiveMQBlobMessageMarshaller, 222
 - createObject, 222
 - getDataStructureType, 222
 - looseMarshal, 222
 - looseUnmarshal, 222
 - tightMarshal1, 223
 - tightMarshal2, 223
 - tightUnmarshal, 224
- activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller, 269
 - ~ActiveMQBytesMessageMarshaller, 270
 - ActiveMQBytesMessageMarshaller, 270
 - createObject, 270
 - getDataStructureType, 270
 - looseMarshal, 270
 - looseUnmarshal, 270
 - tightMarshal1, 271
 - tightMarshal2, 271
 - tightUnmarshal, 272
- activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller, 349
 - ~ActiveMQDestinationMarshaller, 350
 - ActiveMQDestinationMarshaller, 350
 - looseMarshal, 350
 - looseUnmarshal, 350
 - tightMarshal1, 351
- tightMarshal2, 351
- activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller, 390
 - ~ActiveMQMapMessageMarshaller, 391
 - ActiveMQMapMessageMarshaller, 391
 - createObject, 391
 - getDataStructureType, 391
 - looseMarshal, 391
 - looseUnmarshal, 391
 - tightMarshal1, 392
 - tightMarshal2, 392
- activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller, 417
 - ~ActiveMQMessageMarshaller, 418
 - ActiveMQMessageMarshaller, 418
 - createObject, 418
 - getDataStructureType, 418
 - looseMarshal, 418
 - looseUnmarshal, 418
 - tightMarshal1, 419
 - tightMarshal2, 419
 - tightUnmarshal, 420
- activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMessageMarshaller, 463
 - ~ActiveMQObjectMessageMarshaller, 463
 - ActiveMQObjectMessageMarshaller, 463
 - createObject, 463
 - getDataStructureType, 463
 - looseMarshal, 463
 - looseUnmarshal, 463
 - tightMarshal1, 464
 - tightMarshal2, 464
 - tightUnmarshal, 465
- activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMessageMarshaller, 508
 - ~ActiveMQQueueMessageMarshaller, 508
 - ActiveMQQueueMessageMarshaller, 508
 - createObject, 508
 - getDataStructureType, 508
 - looseMarshal, 508
 - looseUnmarshal, 508
 - tightMarshal1, 509
 - tightMarshal2, 509
 - tightUnmarshal, 510
- activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMessageMarshaller, 569
 - ~ActiveMQStreamMessageMarshaller, 569
 - ActiveMQStreamMessageMarshaller, 569
 - createObject, 569
 - getDataStructureType, 569
 - looseMarshal, 569
 - looseUnmarshal, 569

- tightMarshal1, 570
- tightMarshal2, 570
- tightUnmarshal, 571
- activemq::wireformat::openwire::marshal::v2::ActiveMQTempDestinationMarshaller, 596
 - ~ActiveMQTempDestinationMarshaller, 597
 - ActiveMQTempDestinationMarshaller, 597
 - looseMarshal, 597
 - looseUnmarshal, 597
 - tightMarshal1, 598
 - tightMarshal2, 598
 - tightUnmarshal, 599
- activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller, 625
 - ~ActiveMQTempQueueMarshaller, 626
 - ActiveMQTempQueueMarshaller, 626
 - createObject, 626
 - getDataStructureType, 626
 - looseMarshal, 626
 - looseUnmarshal, 626
 - tightMarshal1, 627
 - tightMarshal2, 627
 - tightUnmarshal, 628
- activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller, 654
 - ~ActiveMQTempTopicMarshaller, 655
 - ActiveMQTempTopicMarshaller, 655
 - createObject, 655
 - getDataStructureType, 655
 - looseMarshal, 655
 - looseUnmarshal, 655
 - tightMarshal1, 656
 - tightMarshal2, 656
 - tightUnmarshal, 657
- activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller, 687
 - ~ActiveMQTextMessageMarshaller, 688
 - ActiveMQTextMessageMarshaller, 688
 - createObject, 688
 - getDataStructureType, 688
 - looseMarshal, 688
 - looseUnmarshal, 688
 - tightMarshal1, 689
 - tightMarshal2, 689
 - tightUnmarshal, 690
- activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller, 715
 - ~ActiveMQTopicMarshaller, 716
 - ActiveMQTopicMarshaller, 716
 - createObject, 716
 - getDataStructureType, 716
 - looseMarshal, 716
 - looseUnmarshal, 716
- tightMarshal1, 717
- tightMarshal2, 717
- tightUnmarshal, 718
- activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller, 800
 - ~BaseCommandMarshaller, 801
 - BaseCommandMarshaller, 801
 - looseMarshal, 801
 - looseUnmarshal, 802
 - tightMarshal1, 803
 - tightMarshal2, 804
 - tightUnmarshal, 805
- activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller, 892
 - ~BrokerIdMarshaller, 893
 - BrokerIdMarshaller, 893
 - createObject, 893
 - getDataStructureType, 893
 - looseMarshal, 893
 - looseUnmarshal, 893
 - tightMarshal1, 894
 - tightMarshal2, 894
 - tightUnmarshal, 895
- activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller, 924
 - ~BrokerInfoMarshaller, 925
 - BrokerInfoMarshaller, 925
 - createObject, 925
 - getDataStructureType, 925
 - looseMarshal, 925
 - looseUnmarshal, 925
 - tightMarshal1, 926
 - tightMarshal2, 926
 - tightUnmarshal, 927
- activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller, 1292
 - ~ConnectionControlMarshaller, 1293
 - ConnectionControlMarshaller, 1293
 - createObject, 1293
 - getDataStructureType, 1293
 - looseMarshal, 1293
 - looseUnmarshal, 1293
 - tightMarshal1, 1294
 - tightMarshal2, 1294
 - tightUnmarshal, 1295
- activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller, 1300
 - ~ConnectionErrorMarshaller, 1301
 - ConnectionErrorMarshaller, 1301
 - createObject, 1301
 - getDataStructureType, 1301
 - looseMarshal, 1301
 - looseUnmarshal, 1301
 - tightMarshal1, 1302

- tightMarshal2, 1302
- tightUnmarshal, 1303
- activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller, 1331
 - ~ConnectionIdMarshaller, 1332
 - ConnectionIdMarshaller, 1332
 - createObject, 1332
 - getDataStructureType, 1332
 - looseMarshal, 1332
 - looseUnmarshal, 1332
 - tightMarshal1, 1333
 - tightMarshal2, 1333
 - tightUnmarshal, 1334
- activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller, 1361
 - ~ConnectionInfoMarshaller, 1362
 - ConnectionInfoMarshaller, 1362
 - createObject, 1362
 - getDataStructureType, 1362
 - looseMarshal, 1362
 - looseUnmarshal, 1362
 - tightMarshal1, 1363
 - tightMarshal2, 1363
 - tightUnmarshal, 1364
- activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller, 1406
 - ~ConsumerControlMarshaller, 1407
 - ConsumerControlMarshaller, 1407
 - createObject, 1407
 - getDataStructureType, 1407
 - looseMarshal, 1407
 - looseUnmarshal, 1407
 - tightMarshal1, 1408
 - tightMarshal2, 1408
 - tightUnmarshal, 1409
- activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller, 1435
 - ~ConsumerIdMarshaller, 1436
 - ConsumerIdMarshaller, 1436
 - createObject, 1436
 - getDataStructureType, 1436
 - looseMarshal, 1436
 - looseUnmarshal, 1436
 - tightMarshal1, 1437
 - tightMarshal2, 1437
 - tightUnmarshal, 1438
- activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller, 1468
 - ~ConsumerInfoMarshaller, 1469
 - ConsumerInfoMarshaller, 1469
 - createObject, 1469
 - getDataStructureType, 1469
 - looseMarshal, 1469
 - looseUnmarshal, 1469
- tightMarshal1, 1470
- tightMarshal2, 1470
- tightUnmarshal, 1471
- activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller, 1497
 - ~ControlCommandMarshaller, 1498
 - ControlCommandMarshaller, 1498
 - createObject, 1498
 - getDataStructureType, 1498
 - looseMarshal, 1498
 - looseUnmarshal, 1498
 - tightMarshal1, 1499
 - tightMarshal2, 1499
- activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller, 1531
 - ~DataArrayResponseMarshaller, 1532
 - createObject, 1532
 - DataArrayResponseMarshaller, 1532
 - getDataStructureType, 1532
 - looseMarshal, 1532
 - looseUnmarshal, 1533
 - tightMarshal1, 1533
 - tightMarshal2, 1533
- activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller, 1594
 - ~DataResponseMarshaller, 1595
 - createObject, 1595
 - DataResponseMarshaller, 1595
 - getDataStructureType, 1595
 - looseMarshal, 1595
 - looseUnmarshal, 1596
 - tightMarshal1, 1596
 - tightMarshal2, 1596
- activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller, 1732
 - ~DestinationInfoMarshaller, 1733
 - createObject, 1733
 - DestinationInfoMarshaller, 1733
 - getDataStructureType, 1733
 - looseMarshal, 1733
 - looseUnmarshal, 1733
 - tightMarshal1, 1734
 - tightMarshal2, 1734
- activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller, 1766
 - ~DiscoveryEventMarshaller, 1767
 - createObject, 1767
 - DiscoveryEventMarshaller, 1767
 - getDataStructureType, 1767
 - looseMarshal, 1767

- looseUnmarshal, 1767
- tightMarshal1, 1768
- tightMarshal2, 1768
- tightUnmarshal, 1769
- activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller, 1846
 - ~ExceptionResponseMarshaller, 1847
 - createObject, 1847
 - ExceptionResponseMarshaller, 1847
 - getDataStructureType, 1847
 - looseMarshal, 1847
 - looseUnmarshal, 1848
 - tightMarshal1, 1848
 - tightMarshal2, 1848
 - tightUnmarshal, 1849
- activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller, 1944
 - ~FlushCommandMarshaller, 1945
 - createObject, 1945
 - FlushCommandMarshaller, 1945
 - getDataStructureType, 1945
 - looseMarshal, 1945
 - looseUnmarshal, 1945
 - tightMarshal1, 1946
 - tightMarshal2, 1946
 - tightUnmarshal, 1947
- activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller, 2098
 - ~IntegerResponseMarshaller, 2099
 - createObject, 2099
 - getDataStructureType, 2099
 - IntegerResponseMarshaller, 2099
 - looseMarshal, 2099
 - looseUnmarshal, 2100
 - tightMarshal1, 2100
 - tightMarshal2, 2100
 - tightUnmarshal, 2101
- activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller, 2163
 - ~JournalQueueAckMarshaller, 2164
 - createObject, 2164
 - getDataStructureType, 2164
 - JournalQueueAckMarshaller, 2164
 - looseMarshal, 2164
 - looseUnmarshal, 2164
 - tightMarshal1, 2165
 - tightMarshal2, 2165
 - tightUnmarshal, 2166
- activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller, 2192
 - ~JournalTopicAckMarshaller, 2193
 - createObject, 2193
 - getDataStructureType, 2193
 - JournalTopicAckMarshaller, 2193
- looseMarshal, 2193
- looseUnmarshal, 2193
- tightMarshal1, 2194
- tightMarshal2, 2194
- activemq::wireformat::openwire::marshal::v2::JournalTraceMarshaller, 2215
 - ~JournalTraceMarshaller, 2216
 - createObject, 2216
 - getDataStructureType, 2216
 - JournalTraceMarshaller, 2216
 - looseMarshal, 2216
 - looseUnmarshal, 2216
 - tightMarshal1, 2217
 - tightMarshal2, 2217
- activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller, 2246
 - ~JournalTransactionMarshaller, 2247
 - createObject, 2247
 - getDataStructureType, 2247
 - JournalTransactionMarshaller, 2247
 - looseMarshal, 2247
 - looseUnmarshal, 2247
 - tightMarshal1, 2248
 - tightMarshal2, 2248
- activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller, 2273
 - ~KeepAliveInfoMarshaller, 2274
 - createObject, 2274
 - getDataStructureType, 2274
 - KeepAliveInfoMarshaller, 2274
 - looseMarshal, 2274
 - looseUnmarshal, 2274
 - tightMarshal1, 2275
 - tightMarshal2, 2275
- activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller, 2312
 - ~LastPartialCommandMarshaller, 2313
 - createObject, 2313
 - getDataStructureType, 2313
 - LastPartialCommandMarshaller, 2313
 - looseMarshal, 2313
 - looseUnmarshal, 2314
 - tightMarshal1, 2314
 - tightMarshal2, 2314
- activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller, 2355
 - ~LocalTransactionIdMarshaller, 2356
 - createObject, 2356
 - getDataStructureType, 2356

- LocalTransactionIdMarshaller, 2356
- looseMarshal, 2356
- looseUnmarshal, 2356
- tightMarshal1, 2357
- tightMarshal2, 2357
- tightUnmarshal, 2358
- activemq::wireformat::openwire::marshal::v2::MarshallerFactory, 2492
 - ~MarshallerFactory, 2492
 - configure, 2492
- activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller, 2569
 - ~MessageAckMarshaller, 2570
 - createObject, 2570
 - getDataStructureType, 2570
 - looseMarshal, 2570
 - looseUnmarshal, 2570
 - MessageAckMarshaller, 2570
 - tightMarshal1, 2571
 - tightMarshal2, 2571
 - tightUnmarshal, 2572
- activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller, 2606
 - ~MessageDispatchMarshaller, 2607
 - createObject, 2607
 - getDataStructureType, 2607
 - looseMarshal, 2607
 - looseUnmarshal, 2607
 - MessageDispatchMarshaller, 2607
 - tightMarshal1, 2608
 - tightMarshal2, 2608
 - tightUnmarshal, 2609
- activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller, 2639
 - ~MessageDispatchNotificationMarshaller, 2640
 - createObject, 2640
 - getDataStructureType, 2640
 - looseMarshal, 2640
 - looseUnmarshal, 2640
 - MessageDispatchNotificationMarshaller, 2640
 - tightMarshal1, 2641
 - tightMarshal2, 2641
 - tightUnmarshal, 2642
- activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller, 2668
 - ~MessageIdMarshaller, 2669
 - createObject, 2669
 - getDataStructureType, 2669
 - looseMarshal, 2669
 - looseUnmarshal, 2669
 - MessageIdMarshaller, 2669
 - tightMarshal1, 2670
- tightMarshal2, 2670
- tightUnmarshal, 2671
- activemq::wireformat::openwire::marshal::v2::MessageMarshallerFactory, 2703
 - ~MessageMarshaller, 2704
 - looseMarshal, 2704
 - looseUnmarshal, 2704
 - MessageMarshaller, 2704
 - tightMarshal1, 2705
 - tightMarshal2, 2705
 - tightUnmarshal, 2706
- activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller, 2744
 - ~MessagePullMarshaller, 2745
 - createObject, 2745
 - getDataStructureType, 2745
 - looseMarshal, 2745
 - looseUnmarshal, 2745
 - MessagePullMarshaller, 2745
 - tightMarshal1, 2746
 - tightMarshal2, 2746
 - tightUnmarshal, 2747
- activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaller, 2796
 - ~NetworkBridgeFilterMarshaller, 2797
 - createObject, 2797
 - getDataStructureType, 2797
 - looseMarshal, 2797
 - looseUnmarshal, 2797
 - NetworkBridgeFilterMarshaller, 2797
 - tightMarshal1, 2798
 - tightMarshal2, 2798
 - tightUnmarshal, 2799
- activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2926
 - ~PartialCommandMarshaller, 2927
 - createObject, 2927
 - getDataStructureType, 2927
 - looseMarshal, 2927
 - looseUnmarshal, 2928
 - PartialCommandMarshaller, 2927
 - tightMarshal1, 2928
 - tightMarshal2, 2928
 - tightUnmarshal, 2929
- activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller, 3041
 - ~ProducerAckMarshaller, 3041
 - createObject, 3041
 - getDataStructureType, 3041
 - looseMarshal, 3041
 - looseUnmarshal, 3041
 - ProducerAckMarshaller, 3041
 - tightMarshal1, 3042
 - tightMarshal2, 3042

- tightUnmarshal, 3043
- activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller, 3072
 - ~ProducerIdMarshaller, 3073
 - createObject, 3073
 - getDataStructureType, 3073
 - looseMarshal, 3073
 - looseUnmarshal, 3073
 - ProducerIdMarshaller, 3073
 - tightMarshal1, 3074
 - tightMarshal2, 3074
 - tightUnmarshal, 3075
- activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller, 3105
 - ~ProducerInfoMarshaller, 3106
 - createObject, 3106
 - getDataStructureType, 3106
 - looseMarshal, 3106
 - looseUnmarshal, 3106
 - ProducerInfoMarshaller, 3106
 - tightMarshal1, 3107
 - tightMarshal2, 3107
 - tightUnmarshal, 3108
- activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller, 3198
 - ~RemoveInfoMarshaller, 3199
 - createObject, 3199
 - getDataStructureType, 3199
 - looseMarshal, 3199
 - looseUnmarshal, 3199
 - RemoveInfoMarshaller, 3199
 - tightMarshal1, 3200
 - tightMarshal2, 3200
 - tightUnmarshal, 3201
- activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller, 3235
 - ~RemoveSubscriptionInfoMarshaller, 3236
 - createObject, 3236
 - getDataStructureType, 3236
 - looseMarshal, 3236
 - looseUnmarshal, 3236
 - RemoveSubscriptionInfoMarshaller, 3236
 - tightMarshal1, 3237
 - tightMarshal2, 3237
 - tightUnmarshal, 3238
- activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller, 3262
 - ~ReplayCommandMarshaller, 3263
 - createObject, 3263
 - getDataStructureType, 3263
 - looseMarshal, 3263
 - looseUnmarshal, 3263
 - ReplayCommandMarshaller, 3263
 - tightMarshal1, 3264
- tightMarshal2, 3264
- tightUnmarshal, 3265
- activemq::wireformat::openwire::marshal::v2::ResponseMarshaller, 3300
 - ~ResponseMarshaller, 3301
 - createObject, 3301
 - getDataStructureType, 3301
 - looseMarshal, 3301
 - looseUnmarshal, 3302
 - ResponseMarshaller, 3301
 - tightMarshal1, 3302
 - tightMarshal2, 3303
- activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller, 3383
 - ~SessionIdMarshaller, 3384
 - createObject, 3384
 - getDataStructureType, 3384
 - looseMarshal, 3384
 - looseUnmarshal, 3384
 - SessionIdMarshaller, 3384
 - tightMarshal1, 3385
 - tightMarshal2, 3385
- activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller, 3427
 - ~SessionInfoMarshaller, 3428
 - createObject, 3428
 - getDataStructureType, 3428
 - looseMarshal, 3428
 - looseUnmarshal, 3428
 - SessionInfoMarshaller, 3428
 - tightMarshal1, 3429
 - tightMarshal2, 3429
- activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller, 3477
 - ~ShutdownInfoMarshaller, 3478
 - createObject, 3478
 - getDataStructureType, 3478
 - looseMarshal, 3478
 - looseUnmarshal, 3478
 - ShutdownInfoMarshaller, 3478
 - tightMarshal1, 3479
 - tightMarshal2, 3479
- activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller, 3696
 - ~SubscriptionInfoMarshaller, 3697
 - createObject, 3697
 - getDataStructureType, 3697
 - looseMarshal, 3697
 - looseUnmarshal, 3697
 - SubscriptionInfoMarshaller, 3697

- tightMarshal1, 3698
 - tightMarshal2, 3698
 - tightUnmarshal, 3699
- activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller, 212
 - 3831
 - ~TransactionIdMarshaller, 3832
 - looseMarshal, 3832
 - looseUnmarshal, 3832
 - tightMarshal1, 3833
 - tightMarshal2, 3833
 - tightUnmarshal, 3834
 - TransactionIdMarshaller, 3832
- activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller, 251
 - 3871
 - ~TransactionInfoMarshaller, 3872
 - createObject, 3872
 - getDataStructureType, 3872
 - looseMarshal, 3872
 - looseUnmarshal, 3872
 - tightMarshal1, 3873
 - tightMarshal2, 3873
 - tightUnmarshal, 3874
 - TransactionInfoMarshaller, 3872
- activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller, 336
 - 4000
 - ~WireFormatInfoMarshaller, 4001
 - createObject, 4001
 - getDataStructureType, 4001
 - looseMarshal, 4001
 - looseUnmarshal, 4001
 - tightMarshal1, 4002
 - tightMarshal2, 4002
 - tightUnmarshal, 4003
 - WireFormatInfoMarshaller, 4001
- activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller, 401
 - 4040
 - ~XATransactionIdMarshaller, 4041
 - createObject, 4041
 - getDataStructureType, 4041
 - looseMarshal, 4041
 - looseUnmarshal, 4041
 - tightMarshal1, 4042
 - tightMarshal2, 4042
 - tightUnmarshal, 4043
 - XATransactionIdMarshaller, 4041
- activemq::wireformat::openwire::marshal::v3, 118
- activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller, 209
 - ~ActiveMQBlobMessageMarshaller, 210
 - ActiveMQBlobMessageMarshaller, 210
 - createObject, 210
 - getDataStructureType, 210
 - looseMarshal, 210
 - looseUnmarshal, 210
 - tightMarshal1, 211
 - tightMarshal2, 211
- activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller, 249
 - ~ActiveMQBytesMessageMarshaller, 250
 - ActiveMQBytesMessageMarshaller, 250
 - createObject, 250
 - getDataStructureType, 250
 - looseMarshal, 250
 - looseUnmarshal, 250
 - tightMarshal1, 251
 - tightMarshal2, 251
 - tightUnmarshal, 252
- activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller, 333
 - ~ActiveMQDestinationMarshaller, 334
 - ActiveMQDestinationMarshaller, 334
 - looseMarshal, 334
 - looseUnmarshal, 334
 - tightMarshal1, 335
 - tightMarshal2, 335
- activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller, 374
 - ~ActiveMQMapMessageMarshaller, 375
 - ActiveMQMapMessageMarshaller, 375
 - createObject, 375
 - getDataStructureType, 375
 - looseMarshal, 375
 - looseUnmarshal, 375
 - tightMarshal1, 376
 - tightMarshal2, 376
- activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller, 401
 - ~ActiveMQMessageMarshaller, 402
 - ActiveMQMessageMarshaller, 402
 - createObject, 402
 - getDataStructureType, 402
 - looseMarshal, 402
 - looseUnmarshal, 402
 - tightMarshal1, 403
 - tightMarshal2, 403
 - tightUnmarshal, 404
- activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller, 447
 - ~ActiveMQObjectMessageMarshaller, 447
 - ActiveMQObjectMessageMarshaller, 447
 - createObject, 447
 - getDataStructureType, 447
 - looseMarshal, 447
 - looseUnmarshal, 447

- tightMarshal1, 448
- tightMarshal2, 448
- tightUnmarshal, 449
- activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller, 491
 - ~ActiveMQQueueMarshaller, 492
 - ActiveMQQueueMarshaller, 492
 - createObject, 492
 - getDataStructureType, 492
 - looseMarshal, 492
 - looseUnmarshal, 492
 - tightMarshal1, 493
 - tightMarshal2, 493
 - tightUnmarshal, 494
- activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMessageMarshaller, 552
 - ~ActiveMQStreamMessageMarshaller, 553
 - ActiveMQStreamMessageMarshaller, 553
 - createObject, 553
 - getDataStructureType, 553
 - looseMarshal, 553
 - looseUnmarshal, 553
 - tightMarshal1, 554
 - tightMarshal2, 554
 - tightUnmarshal, 555
- activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller, 580
 - ~ActiveMQTempDestinationMarshaller, 581
 - ActiveMQTempDestinationMarshaller, 581
 - looseMarshal, 581
 - looseUnmarshal, 581
 - tightMarshal1, 582
 - tightMarshal2, 582
 - tightUnmarshal, 583
- activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller, 609
 - ~ActiveMQTempQueueMarshaller, 610
 - ActiveMQTempQueueMarshaller, 610
 - createObject, 610
 - getDataStructureType, 610
 - looseMarshal, 610
 - looseUnmarshal, 610
 - tightMarshal1, 611
 - tightMarshal2, 611
 - tightUnmarshal, 612
- activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller, 638
 - ~ActiveMQTempTopicMarshaller, 639
 - ActiveMQTempTopicMarshaller, 639
 - createObject, 639
 - getDataStructureType, 639
 - looseMarshal, 639
 - looseUnmarshal, 639
- tightMarshal1, 640
- tightMarshal2, 640
- tightUnmarshal, 641
- activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller, 667
 - ~ActiveMQTextMessageMarshaller, 668
 - ActiveMQTextMessageMarshaller, 668
 - createObject, 668
 - getDataStructureType, 668
 - looseMarshal, 668
 - looseUnmarshal, 668
 - tightMarshal1, 669
 - tightMarshal2, 669
 - tightUnmarshal, 670
- activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller, 695
 - ~ActiveMQTopicMarshaller, 696
 - ActiveMQTopicMarshaller, 696
 - createObject, 696
 - getDataStructureType, 696
 - looseMarshal, 696
 - looseUnmarshal, 696
 - tightMarshal1, 697
 - tightMarshal2, 697
 - tightUnmarshal, 698
- activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller, 765
 - ~BaseCommandMarshaller, 766
 - BaseCommandMarshaller, 766
 - looseMarshal, 766
 - looseUnmarshal, 767
 - tightMarshal1, 768
 - tightMarshal2, 769
 - tightUnmarshal, 770
- activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller, 872
 - ~BrokerIdMarshaller, 873
 - BrokerIdMarshaller, 873
 - createObject, 873
 - getDataStructureType, 873
 - looseMarshal, 873
 - looseUnmarshal, 873
 - tightMarshal1, 874
 - tightMarshal2, 874
 - tightUnmarshal, 875
- activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller, 904
 - ~BrokerInfoMarshaller, 905
 - BrokerInfoMarshaller, 905
 - createObject, 905
 - getDataStructureType, 905
 - looseMarshal, 905
 - looseUnmarshal, 905
 - tightMarshal1, 906

- tightMarshal2, 906
- tightUnmarshal, 907
- activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller, 1272
 - ~ConnectionControlMarshaller, 1273
 - ConnectionControlMarshaller, 1273
 - createObject, 1273
 - getDataStructureType, 1273
 - looseMarshal, 1273
 - looseUnmarshal, 1273
 - tightMarshal1, 1274
 - tightMarshal2, 1274
 - tightUnmarshal, 1275
- activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller, 1304
 - ~ConnectionErrorMarshaller, 1305
 - ConnectionErrorMarshaller, 1305
 - createObject, 1305
 - getDataStructureType, 1305
 - looseMarshal, 1305
 - looseUnmarshal, 1305
 - tightMarshal1, 1306
 - tightMarshal2, 1306
 - tightUnmarshal, 1307
- activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller, 1335
 - ~ConnectionIdMarshaller, 1336
 - ConnectionIdMarshaller, 1336
 - createObject, 1336
 - getDataStructureType, 1336
 - looseMarshal, 1336
 - looseUnmarshal, 1336
 - tightMarshal1, 1337
 - tightMarshal2, 1337
 - tightUnmarshal, 1338
- activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller, 1365
 - ~ConnectionInfoMarshaller, 1366
 - ConnectionInfoMarshaller, 1366
 - createObject, 1366
 - getDataStructureType, 1366
 - looseMarshal, 1366
 - looseUnmarshal, 1366
 - tightMarshal1, 1367
 - tightMarshal2, 1367
 - tightUnmarshal, 1368
- activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller, 1410
 - ~ConsumerControlMarshaller, 1411
 - ConsumerControlMarshaller, 1411
 - createObject, 1411
 - getDataStructureType, 1411
 - looseMarshal, 1411
 - looseUnmarshal, 1411
- tightMarshal1, 1412
- tightMarshal2, 1412
- tightUnmarshal, 1413
- activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller, 1439
 - ~ConsumerIdMarshaller, 1440
 - ConsumerIdMarshaller, 1440
 - createObject, 1440
 - getDataStructureType, 1440
 - looseMarshal, 1440
 - looseUnmarshal, 1440
 - tightMarshal1, 1441
 - tightMarshal2, 1441
- activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller, 1472
 - ~ConsumerInfoMarshaller, 1473
 - ConsumerInfoMarshaller, 1473
 - createObject, 1473
 - getDataStructureType, 1473
 - looseMarshal, 1473
 - looseUnmarshal, 1473
 - tightMarshal1, 1474
 - tightMarshal2, 1474
- activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller, 1501
 - ~ControlCommandMarshaller, 1502
 - ControlCommandMarshaller, 1502
 - createObject, 1502
 - getDataStructureType, 1502
 - looseMarshal, 1502
 - looseUnmarshal, 1502
 - tightMarshal1, 1503
 - tightMarshal2, 1503
- activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller, 1535
 - ~DataArrayResponseMarshaller, 1536
 - createObject, 1536
 - DataArrayResponseMarshaller, 1536
 - getDataStructureType, 1536
 - looseMarshal, 1536
 - looseUnmarshal, 1537
 - tightMarshal1, 1537
 - tightMarshal2, 1537
- activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller, 1598
 - ~DataResponseMarshaller, 1599
 - createObject, 1599
 - DataResponseMarshaller, 1599
 - getDataStructureType, 1599
 - looseMarshal, 1599

- looseUnmarshal, 1600
- tightMarshal1, 1600
- tightMarshal2, 1600
- tightUnmarshal, 1601
- activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller, 1736
 - ~DestinationInfoMarshaller, 1737
 - createObject, 1737
 - DestinationInfoMarshaller, 1737
 - getDataStructureType, 1737
 - looseMarshal, 1737
 - looseUnmarshal, 1737
 - tightMarshal1, 1738
 - tightMarshal2, 1738
 - tightUnmarshal, 1739
- activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller, 1770
 - ~DiscoveryEventMarshaller, 1771
 - createObject, 1771
 - DiscoveryEventMarshaller, 1771
 - getDataStructureType, 1771
 - looseMarshal, 1771
 - looseUnmarshal, 1771
 - tightMarshal1, 1772
 - tightMarshal2, 1772
 - tightUnmarshal, 1773
- activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller, 1850
 - ~ExceptionResponseMarshaller, 1851
 - createObject, 1851
 - ExceptionResponseMarshaller, 1851
 - getDataStructureType, 1851
 - looseMarshal, 1851
 - looseUnmarshal, 1852
 - tightMarshal1, 1852
 - tightMarshal2, 1852
 - tightUnmarshal, 1853
- activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller, 1948
 - ~FlushCommandMarshaller, 1949
 - createObject, 1949
 - FlushCommandMarshaller, 1949
 - getDataStructureType, 1949
 - looseMarshal, 1949
 - looseUnmarshal, 1949
 - tightMarshal1, 1950
 - tightMarshal2, 1950
 - tightUnmarshal, 1951
- activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller, 2102
 - ~IntegerResponseMarshaller, 2103
 - createObject, 2103
 - getDataStructureType, 2103
 - IntegerResponseMarshaller, 2103
- looseMarshal, 2103
- looseUnmarshal, 2104
- tightMarshal1, 2104
- tightMarshal2, 2104
- activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller, 2171
 - ~JournalQueueAckMarshaller, 2172
 - createObject, 2172
 - getDataStructureType, 2172
 - JournalQueueAckMarshaller, 2172
 - looseMarshal, 2172
 - looseUnmarshal, 2172
 - tightMarshal1, 2173
 - tightMarshal2, 2173
- activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller, 2196
 - ~JournalTopicAckMarshaller, 2197
 - createObject, 2197
 - getDataStructureType, 2197
 - JournalTopicAckMarshaller, 2197
 - looseMarshal, 2197
 - looseUnmarshal, 2197
 - tightMarshal1, 2198
 - tightMarshal2, 2198
- activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller, 2219
 - ~JournalTraceMarshaller, 2220
 - createObject, 2220
 - getDataStructureType, 2220
 - JournalTraceMarshaller, 2220
 - looseMarshal, 2220
 - looseUnmarshal, 2220
 - tightMarshal1, 2221
 - tightMarshal2, 2221
- activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller, 2250
 - ~JournalTransactionMarshaller, 2251
 - createObject, 2251
 - getDataStructureType, 2251
 - JournalTransactionMarshaller, 2251
 - looseMarshal, 2251
 - looseUnmarshal, 2251
 - tightMarshal1, 2252
 - tightMarshal2, 2252
- activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller, 2277
 - ~KeepAliveInfoMarshaller, 2278
 - createObject, 2278
 - getDataStructureType, 2278

- KeepAliveInfoMarshaller, 2278
- looseMarshal, 2278
- looseUnmarshal, 2278
- tightMarshal1, 2279
- tightMarshal2, 2279
- tightUnmarshal, 2280
- activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller, 2308
 - ~LastPartialCommandMarshaller, 2309
 - createObject, 2309
 - getDataStructureType, 2309
 - LastPartialCommandMarshaller, 2309
 - looseMarshal, 2309
 - looseUnmarshal, 2310
 - tightMarshal1, 2310
 - tightMarshal2, 2310
 - tightUnmarshal, 2311
- activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller, 2359
 - ~LocalTransactionIdMarshaller, 2360
 - createObject, 2360
 - getDataStructureType, 2360
 - LocalTransactionIdMarshaller, 2360
 - looseMarshal, 2360
 - looseUnmarshal, 2360
 - tightMarshal1, 2361
 - tightMarshal2, 2361
 - tightUnmarshal, 2362
- activemq::wireformat::openwire::marshal::v3::MarshallerFactory, 2488
 - ~MarshallerFactory, 2488
 - configure, 2488
- activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller, 2573
 - ~MessageAckMarshaller, 2574
 - createObject, 2574
 - getDataStructureType, 2574
 - looseMarshal, 2574
 - looseUnmarshal, 2574
 - MessageAckMarshaller, 2574
 - tightMarshal1, 2575
 - tightMarshal2, 2575
 - tightUnmarshal, 2576
- activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller, 2610
 - ~MessageDispatchMarshaller, 2611
 - createObject, 2611
 - getDataStructureType, 2611
 - looseMarshal, 2611
 - looseUnmarshal, 2611
 - MessageDispatchMarshaller, 2611
 - tightMarshal1, 2612
 - tightMarshal2, 2612
 - tightUnmarshal, 2613
- activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller, 2643
 - ~MessageDispatchNotificationMarshaller, 2644
 - createObject, 2644
 - getDataStructureType, 2644
 - looseMarshal, 2644
 - looseUnmarshal, 2644
 - MessageDispatchNotificationMarshaller, 2644
 - tightMarshal1, 2645
 - tightMarshal2, 2645
 - tightUnmarshal, 2646
- activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller, 2680
 - ~MessageIdMarshaller, 2681
 - createObject, 2681
 - getDataStructureType, 2681
 - looseMarshal, 2681
 - looseUnmarshal, 2681
 - MessageIdMarshaller, 2681
 - tightMarshal1, 2682
 - tightMarshal2, 2682
 - tightUnmarshal, 2683
- activemq::wireformat::openwire::marshal::v3::MessageMarshaller, 2698
 - ~MessageMarshaller, 2699
 - looseMarshal, 2699
 - looseUnmarshal, 2699
 - MessageMarshaller, 2699
 - tightMarshal1, 2700
 - tightMarshal2, 2700
 - tightUnmarshal, 2701
- activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller, 2752
 - ~MessagePullMarshaller, 2753
 - createObject, 2753
 - getDataStructureType, 2753
 - looseMarshal, 2753
 - looseUnmarshal, 2753
 - MessagePullMarshaller, 2753
 - tightMarshal1, 2754
 - tightMarshal2, 2754
- activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshaller, 2808
 - ~NetworkBridgeFilterMarshaller, 2809
 - createObject, 2809
 - getDataStructureType, 2809
 - looseMarshal, 2809
 - looseUnmarshal, 2809
 - NetworkBridgeFilterMarshaller, 2809
 - tightMarshal1, 2810
 - tightMarshal2, 2810

- tightUnmarshal, 2811
- activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2934
 - ~PartialCommandMarshaller, 2935
 - createObject, 2935
 - getDataStructureType, 2935
 - looseMarshal, 2935
 - looseUnmarshal, 2936
 - PartialCommandMarshaller, 2935
 - tightMarshal1, 2936
 - tightMarshal2, 2936
 - tightUnmarshal, 2937
- activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller, 3048
 - ~ProducerAckMarshaller, 3049
 - createObject, 3049
 - getDataStructureType, 3049
 - looseMarshal, 3049
 - looseUnmarshal, 3049
 - ProducerAckMarshaller, 3049
 - tightMarshal1, 3050
 - tightMarshal2, 3050
 - tightUnmarshal, 3051
- activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller, 3080
 - ~ProducerIdMarshaller, 3081
 - createObject, 3081
 - getDataStructureType, 3081
 - looseMarshal, 3081
 - looseUnmarshal, 3081
 - ProducerIdMarshaller, 3081
 - tightMarshal1, 3082
 - tightMarshal2, 3082
 - tightUnmarshal, 3083
- activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller, 3117
 - ~ProducerInfoMarshaller, 3118
 - createObject, 3118
 - getDataStructureType, 3118
 - looseMarshal, 3118
 - looseUnmarshal, 3118
 - ProducerInfoMarshaller, 3118
 - tightMarshal1, 3119
 - tightMarshal2, 3119
 - tightUnmarshal, 3120
- activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller, 3206
 - ~RemoveInfoMarshaller, 3207
 - createObject, 3207
 - getDataStructureType, 3207
 - looseMarshal, 3207
 - looseUnmarshal, 3207
 - RemoveInfoMarshaller, 3207
 - tightMarshal1, 3208
- tightMarshal2, 3208
- tightUnmarshal, 3209
- activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller, 3231
 - ~RemoveSubscriptionInfoMarshaller, 3232
 - createObject, 3232
 - getDataStructureType, 3232
 - looseMarshal, 3232
 - looseUnmarshal, 3232
 - RemoveSubscriptionInfoMarshaller, 3232
 - tightMarshal1, 3233
 - tightMarshal2, 3233
- activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller, 3266
 - ~ReplayCommandMarshaller, 3267
 - createObject, 3267
 - getDataStructureType, 3267
 - looseMarshal, 3267
 - looseUnmarshal, 3267
 - ReplayCommandMarshaller, 3267
 - tightMarshal1, 3268
 - tightMarshal2, 3268
- activemq::wireformat::openwire::marshal::v3::ResponseMarshaller, 3310
 - ~ResponseMarshaller, 3311
 - createObject, 3311
 - getDataStructureType, 3311
 - looseMarshal, 3311
 - looseUnmarshal, 3312
 - ResponseMarshaller, 3311
 - tightMarshal1, 3312
 - tightMarshal2, 3313
- activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller, 3399
 - ~SessionIdMarshaller, 3400
 - createObject, 3400
 - getDataStructureType, 3400
 - looseMarshal, 3400
 - looseUnmarshal, 3400
 - SessionIdMarshaller, 3400
 - tightMarshal1, 3401
 - tightMarshal2, 3401
- activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller, 3423
 - ~SessionInfoMarshaller, 3424
 - createObject, 3424
 - getDataStructureType, 3424
 - looseMarshal, 3424
 - looseUnmarshal, 3424
 - SessionInfoMarshaller, 3424

- tightMarshal1, 3425
- tightMarshal2, 3425
- tightUnmarshal, 3426
- activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller, 3489
 - ~ShutdownInfoMarshaller, 3490
 - createObject, 3490
 - getDataStructureType, 3490
 - looseMarshal, 3490
 - looseUnmarshal, 3490
 - ShutdownInfoMarshaller, 3490
 - tightMarshal1, 3491
 - tightMarshal2, 3491
 - tightUnmarshal, 3492
- activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller, 3676
 - ~SubscriptionInfoMarshaller, 3677
 - createObject, 3677
 - getDataStructureType, 3677
 - looseMarshal, 3677
 - looseUnmarshal, 3677
 - SubscriptionInfoMarshaller, 3677
 - tightMarshal1, 3678
 - tightMarshal2, 3678
 - tightUnmarshal, 3679
- activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller, 3835
 - ~TransactionIdMarshaller, 3836
 - looseMarshal, 3836
 - looseUnmarshal, 3836
 - tightMarshal1, 3837
 - tightMarshal2, 3837
 - tightUnmarshal, 3838
 - TransactionIdMarshaller, 3836
- activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller, 3859
 - ~TransactionInfoMarshaller, 3860
 - createObject, 3860
 - getDataStructureType, 3860
 - looseMarshal, 3860
 - looseUnmarshal, 3860
 - tightMarshal1, 3861
 - tightMarshal2, 3861
 - tightUnmarshal, 3862
 - TransactionInfoMarshaller, 3860
- activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller, 4012
 - ~WireFormatInfoMarshaller, 4013
 - createObject, 4013
 - getDataStructureType, 4013
 - looseMarshal, 4013
 - looseUnmarshal, 4013
 - tightMarshal1, 4014
 - tightMarshal2, 4014
- tightUnmarshal, 4015
- WireFormatInfoMarshaller, 4013
- activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller, 4052
 - ~XATransactionIdMarshaller, 4053
 - createObject, 4053
 - getDataStructureType, 4053
 - looseMarshal, 4053
 - looseUnmarshal, 4053
 - tightMarshal1, 4054
 - tightMarshal2, 4054
 - tightUnmarshal, 4055
 - XATransactionIdMarshaller, 4053
- activemq::wireformat::openwire::marshal::v4, 4053
 - activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller, 217
 - ~ActiveMQBlobMessageMarshaller, 218
 - ActiveMQBlobMessageMarshaller, 218
 - createObject, 218
 - getDataStructureType, 218
 - looseMarshal, 218
 - looseUnmarshal, 218
 - tightMarshal1, 219
 - tightMarshal2, 219
 - activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller, 257
 - ~ActiveMQBytesMessageMarshaller, 258
 - ActiveMQBytesMessageMarshaller, 258
 - createObject, 258
 - getDataStructureType, 258
 - looseMarshal, 258
 - looseUnmarshal, 258
 - tightMarshal1, 259
 - tightMarshal2, 259
 - tightUnmarshal, 260
 - activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller, 341
 - ~ActiveMQDestinationMarshaller, 342
 - ActiveMQDestinationMarshaller, 342
 - looseMarshal, 342
 - looseUnmarshal, 342
 - tightMarshal1, 343
 - tightMarshal2, 343
 - activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller, 382
 - ~ActiveMQMapMessageMarshaller, 383
 - ActiveMQMapMessageMarshaller, 383
 - createObject, 383
 - getDataStructureType, 383
 - looseMarshal, 383
 - looseUnmarshal, 383

- tightMarshal1, 384
- tightMarshal2, 384
- tightUnmarshal, 385
- activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller, 409
 - ~ActiveMQMessageMarshaller, 410
 - ActiveMQMessageMarshaller, 410
 - createObject, 410
 - getDataStructureType, 410
 - looseMarshal, 410
 - looseUnmarshal, 410
 - tightMarshal1, 411
 - tightMarshal2, 411
 - tightUnmarshal, 412
- activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller, 454
 - ~ActiveMQObjectMessageMarshaller, 455
 - ActiveMQObjectMessageMarshaller, 455
 - createObject, 455
 - getDataStructureType, 455
 - looseMarshal, 455
 - looseUnmarshal, 455
 - tightMarshal1, 456
 - tightMarshal2, 456
 - tightUnmarshal, 457
- activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMessageMarshaller, 499
 - ~ActiveMQQueueMarshaller, 500
 - ActiveMQQueueMarshaller, 500
 - createObject, 500
 - getDataStructureType, 500
 - looseMarshal, 500
 - looseUnmarshal, 500
 - tightMarshal1, 501
 - tightMarshal2, 501
 - tightUnmarshal, 502
- activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMessageMarshaller, 560
 - ~ActiveMQStreamMessageMarshaller, 561
 - ActiveMQStreamMessageMarshaller, 561
 - createObject, 561
 - getDataStructureType, 561
 - looseMarshal, 561
 - looseUnmarshal, 561
 - tightMarshal1, 562
 - tightMarshal2, 562
 - tightUnmarshal, 563
- activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller, 588
 - ~ActiveMQTempDestinationMarshaller, 589
 - ActiveMQTempDestinationMarshaller, 589
 - looseMarshal, 589
 - looseUnmarshal, 589
- tightMarshal1, 590
- tightMarshal2, 590
- tightUnmarshal, 591
- activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller, 617
 - ~ActiveMQTempQueueMarshaller, 618
 - ActiveMQTempQueueMarshaller, 618
 - createObject, 618
 - getDataStructureType, 618
 - looseMarshal, 618
 - looseUnmarshal, 618
 - tightMarshal1, 619
 - tightMarshal2, 619
 - tightUnmarshal, 620
- activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller, 642
 - ~ActiveMQTempTopicMarshaller, 643
 - ActiveMQTempTopicMarshaller, 643
 - createObject, 643
 - getDataStructureType, 643
 - looseMarshal, 643
 - looseUnmarshal, 643
 - tightMarshal1, 644
 - tightMarshal2, 644
 - tightUnmarshal, 645
- activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller, 671
 - ~ActiveMQTextMessageMarshaller, 672
 - ActiveMQTextMessageMarshaller, 672
 - createObject, 672
 - getDataStructureType, 672
 - looseMarshal, 672
 - looseUnmarshal, 672
 - tightMarshal1, 673
 - tightMarshal2, 673
 - tightUnmarshal, 674
- activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller, 699
 - ~ActiveMQTopicMarshaller, 700
 - ActiveMQTopicMarshaller, 700
 - createObject, 700
 - getDataStructureType, 700
 - looseMarshal, 700
 - looseUnmarshal, 700
 - tightMarshal1, 701
 - tightMarshal2, 701
 - tightUnmarshal, 702
- activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller, 772
 - ~BaseCommandMarshaller, 773
 - BaseCommandMarshaller, 773
 - looseMarshal, 773
 - looseUnmarshal, 774
 - tightMarshal1, 775

- tightMarshal2, 776
- tightUnmarshal, 777
- activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller, 876
 - ~BrokerIdMarshaller, 877
 - BrokerIdMarshaller, 877
 - createObject, 877
 - getDataStructureType, 877
 - looseMarshal, 877
 - looseUnmarshal, 877
 - tightMarshal1, 878
 - tightMarshal2, 878
 - tightUnmarshal, 879
- activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller, 908
 - ~BrokerInfoMarshaller, 909
 - BrokerInfoMarshaller, 909
 - createObject, 909
 - getDataStructureType, 909
 - looseMarshal, 909
 - looseUnmarshal, 909
 - tightMarshal1, 910
 - tightMarshal2, 910
 - tightUnmarshal, 911
- activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller, 1276
 - ~ConnectionControlMarshaller, 1277
 - ConnectionControlMarshaller, 1277
 - createObject, 1277
 - getDataStructureType, 1277
 - looseMarshal, 1277
 - looseUnmarshal, 1277
 - tightMarshal1, 1278
 - tightMarshal2, 1278
 - tightUnmarshal, 1279
- activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller, 1308
 - ~ConnectionErrorMarshaller, 1309
 - ConnectionErrorMarshaller, 1309
 - createObject, 1309
 - getDataStructureType, 1309
 - looseMarshal, 1309
 - looseUnmarshal, 1309
 - tightMarshal1, 1310
 - tightMarshal2, 1310
 - tightUnmarshal, 1311
- activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller, 1339
 - ~ConnectionIdMarshaller, 1340
 - ConnectionIdMarshaller, 1340
 - createObject, 1340
 - getDataStructureType, 1340
 - looseMarshal, 1340
 - looseUnmarshal, 1340
- tightMarshal1, 1341
- tightMarshal2, 1341
- activemq::wireformat::openwire::marshal::v4::Marshal, 1342
- activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller, 1369
 - ~ConnectionInfoMarshaller, 1370
 - ConnectionInfoMarshaller, 1370
 - createObject, 1370
 - getDataStructureType, 1370
 - looseMarshal, 1370
 - looseUnmarshal, 1370
 - tightMarshal1, 1371
 - tightMarshal2, 1371
- activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller, 1414
 - ~ConsumerControlMarshaller, 1415
 - ConsumerControlMarshaller, 1415
 - createObject, 1415
 - getDataStructureType, 1415
 - looseMarshal, 1415
 - looseUnmarshal, 1415
 - tightMarshal1, 1416
 - tightMarshal2, 1416
- activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller, 1443
 - ~ConsumerIdMarshaller, 1444
 - ConsumerIdMarshaller, 1444
 - createObject, 1444
 - getDataStructureType, 1444
 - looseMarshal, 1444
 - looseUnmarshal, 1444
 - tightMarshal1, 1445
 - tightMarshal2, 1445
- activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller, 1476
 - ~ConsumerInfoMarshaller, 1477
 - ConsumerInfoMarshaller, 1477
 - createObject, 1477
 - getDataStructureType, 1477
 - looseMarshal, 1477
 - looseUnmarshal, 1477
 - tightMarshal1, 1478
 - tightMarshal2, 1478
- activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller, 1505
 - ~ControlCommandMarshaller, 1506
 - ControlCommandMarshaller, 1506
 - createObject, 1506
 - getDataStructureType, 1506
 - looseMarshal, 1506

- looseUnmarshal, 1506
- tightMarshal1, 1507
- tightMarshal2, 1507
- tightUnmarshal, 1508
- activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller, 1539
 - ~DataArrayResponseMarshaller, 1540
 - createObject, 1540
 - DataArrayResponseMarshaller, 1540
 - getDataStructureType, 1540
 - looseMarshal, 1540
 - looseUnmarshal, 1541
 - tightMarshal1, 1541
 - tightMarshal2, 1541
 - tightUnmarshal, 1542
- activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller, 1602
 - ~DataResponseMarshaller, 1603
 - createObject, 1603
 - DataResponseMarshaller, 1603
 - getDataStructureType, 1603
 - looseMarshal, 1603
 - looseUnmarshal, 1604
 - tightMarshal1, 1604
 - tightMarshal2, 1604
 - tightUnmarshal, 1605
- activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller, 1740
 - ~DestinationInfoMarshaller, 1741
 - createObject, 1741
 - DestinationInfoMarshaller, 1741
 - getDataStructureType, 1741
 - looseMarshal, 1741
 - looseUnmarshal, 1741
 - tightMarshal1, 1742
 - tightMarshal2, 1742
 - tightUnmarshal, 1743
- activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller, 1774
 - ~DiscoveryEventMarshaller, 1775
 - createObject, 1775
 - DiscoveryEventMarshaller, 1775
 - getDataStructureType, 1775
 - looseMarshal, 1775
 - looseUnmarshal, 1775
 - tightMarshal1, 1776
 - tightMarshal2, 1776
 - tightUnmarshal, 1777
- activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller, 1858
 - ~ExceptionResponseMarshaller, 1859
 - createObject, 1859
 - ExceptionResponseMarshaller, 1859
 - getDataStructureType, 1859
- looseMarshal, 1859
- looseUnmarshal, 1860
- tightMarshal1, 1860
- tightMarshal2, 1860
- activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller, 1952
 - ~FlushCommandMarshaller, 1953
 - createObject, 1953
 - FlushCommandMarshaller, 1953
 - getDataStructureType, 1953
 - looseMarshal, 1953
 - looseUnmarshal, 1953
 - tightMarshal1, 1954
 - tightMarshal2, 1954
- activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller, 2106
 - ~IntegerResponseMarshaller, 2107
 - createObject, 2107
 - getDataStructureType, 2107
 - IntegerResponseMarshaller, 2107
 - looseMarshal, 2107
 - looseUnmarshal, 2108
 - tightMarshal1, 2108
 - tightMarshal2, 2108
- activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller, 2175
 - ~JournalQueueAckMarshaller, 2176
 - createObject, 2176
 - getDataStructureType, 2176
 - JournalQueueAckMarshaller, 2176
 - looseMarshal, 2176
 - looseUnmarshal, 2176
 - tightMarshal1, 2177
 - tightMarshal2, 2177
- activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller, 2204
 - ~JournalTopicAckMarshaller, 2205
 - createObject, 2205
 - getDataStructureType, 2205
 - JournalTopicAckMarshaller, 2205
 - looseMarshal, 2205
 - looseUnmarshal, 2205
 - tightMarshal1, 2206
 - tightMarshal2, 2206
- activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller, 2227
 - ~JournalTraceMarshaller, 2228
 - createObject, 2228
 - getDataStructureType, 2228

- JournalTraceMarshaller, 2228
- looseMarshal, 2228
- looseUnmarshal, 2228
- tightMarshal1, 2229
- tightMarshal2, 2229
- tightUnmarshal, 2230
- activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller, 2258
 - ~JournalTransactionMarshaller, 2259
 - createObject, 2259
 - getDataStructureType, 2259
 - JournalTransactionMarshaller, 2259
 - looseMarshal, 2259
 - looseUnmarshal, 2259
 - tightMarshal1, 2260
 - tightMarshal2, 2260
 - tightUnmarshal, 2261
- activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller, 2281
 - ~KeepAliveInfoMarshaller, 2282
 - createObject, 2282
 - getDataStructureType, 2282
 - KeepAliveInfoMarshaller, 2282
 - looseMarshal, 2282
 - looseUnmarshal, 2282
 - tightMarshal1, 2283
 - tightMarshal2, 2283
 - tightUnmarshal, 2284
- activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller, 2320
 - ~LastPartialCommandMarshaller, 2321
 - createObject, 2321
 - getDataStructureType, 2321
 - LastPartialCommandMarshaller, 2321
 - looseMarshal, 2321
 - looseUnmarshal, 2322
 - tightMarshal1, 2322
 - tightMarshal2, 2322
 - tightUnmarshal, 2323
- activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller, 2367
 - ~LocalTransactionIdMarshaller, 2368
 - createObject, 2368
 - getDataStructureType, 2368
 - LocalTransactionIdMarshaller, 2368
 - looseMarshal, 2368
 - looseUnmarshal, 2368
 - tightMarshal1, 2369
 - tightMarshal2, 2369
 - tightUnmarshal, 2370
- activemq::wireformat::openwire::marshal::v4::MarshallerFactory, 2489
 - ~MarshallerFactory, 2489
 - configure, 2489
- activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller, 2577
 - ~MessageAckMarshaller, 2578
 - createObject, 2578
 - getDataStructureType, 2578
 - looseMarshal, 2578
 - looseUnmarshal, 2578
 - MessageAckMarshaller, 2578
 - tightMarshal1, 2579
 - tightMarshal2, 2579
 - tightUnmarshal, 2580
- activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller, 2618
 - ~MessageDispatchMarshaller, 2619
 - createObject, 2619
 - getDataStructureType, 2619
 - looseMarshal, 2619
 - looseUnmarshal, 2619
 - MessageDispatchMarshaller, 2619
 - tightMarshal1, 2620
 - tightMarshal2, 2620
 - tightUnmarshal, 2621
- activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller, 2647
 - ~MessageDispatchNotificationMarshaller, 2648
 - createObject, 2648
 - getDataStructureType, 2648
 - looseMarshal, 2648
 - looseUnmarshal, 2648
 - MessageDispatchNotificationMarshaller, 2648
 - tightMarshal1, 2649
 - tightMarshal2, 2649
 - tightUnmarshal, 2650
- activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller, 2672
 - ~MessageIdMarshaller, 2673
 - createObject, 2673
 - getDataStructureType, 2673
 - looseMarshal, 2673
 - looseUnmarshal, 2673
 - MessageIdMarshaller, 2673
 - tightMarshal1, 2674
 - tightMarshal2, 2674
 - tightUnmarshal, 2675
- activemq::wireformat::openwire::marshal::v4::MessageMarshaller, 2708
 - ~MessageMarshaller, 2709
 - looseMarshal, 2709
 - looseUnmarshal, 2709
 - MessageMarshaller, 2709
 - tightMarshal1, 2710
 - tightMarshal2, 2710

- tightUnmarshal, 2711
- activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller, 2756
 - ~MessagePullMarshaller, 2757
 - createObject, 2757
 - getDataStructureType, 2757
 - looseMarshal, 2757
 - looseUnmarshal, 2757
 - MessagePullMarshaller, 2757
 - tightMarshal1, 2758
 - tightMarshal2, 2758
 - tightUnmarshal, 2759
- activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshaller, 2812
 - ~NetworkBridgeFilterMarshaller, 2813
 - createObject, 2813
 - getDataStructureType, 2813
 - looseMarshal, 2813
 - looseUnmarshal, 2813
 - NetworkBridgeFilterMarshaller, 2813
 - tightMarshal1, 2814
 - tightMarshal2, 2814
 - tightUnmarshal, 2815
- activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2938
 - ~PartialCommandMarshaller, 2939
 - createObject, 2939
 - getDataStructureType, 2939
 - looseMarshal, 2939
 - looseUnmarshal, 2940
 - PartialCommandMarshaller, 2939
 - tightMarshal1, 2940
 - tightMarshal2, 2940
 - tightUnmarshal, 2941
- activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller, 3044
 - ~ProducerAckMarshaller, 3045
 - createObject, 3045
 - getDataStructureType, 3045
 - looseMarshal, 3045
 - looseUnmarshal, 3045
 - ProducerAckMarshaller, 3045
 - tightMarshal1, 3046
 - tightMarshal2, 3046
 - tightUnmarshal, 3047
- activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller, 3076
 - ~ProducerIdMarshaller, 3077
 - createObject, 3077
 - getDataStructureType, 3077
 - looseMarshal, 3077
 - looseUnmarshal, 3077
 - ProducerIdMarshaller, 3077
 - tightMarshal1, 3078
- tightMarshal2, 3078
- activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller, 3101
 - ~ProducerInfoMarshaller, 3102
 - createObject, 3102
 - getDataStructureType, 3102
 - looseMarshal, 3102
 - looseUnmarshal, 3102
 - ProducerInfoMarshaller, 3102
 - tightMarshal1, 3103
 - tightMarshal2, 3103
- activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller, 3218
 - ~RemoveInfoMarshaller, 3219
 - createObject, 3219
 - getDataStructureType, 3219
 - looseMarshal, 3219
 - looseUnmarshal, 3219
 - RemoveInfoMarshaller, 3219
 - tightMarshal1, 3220
 - tightMarshal2, 3220
- activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller, 3247
 - ~RemoveSubscriptionInfoMarshaller, 3248
 - createObject, 3248
 - getDataStructureType, 3248
 - looseMarshal, 3248
 - looseUnmarshal, 3248
 - RemoveSubscriptionInfoMarshaller, 3248
 - tightMarshal1, 3249
 - tightMarshal2, 3249
- activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller, 3254
 - ~ReplayCommandMarshaller, 3255
 - createObject, 3255
 - getDataStructureType, 3255
 - looseMarshal, 3255
 - looseUnmarshal, 3255
 - ReplayCommandMarshaller, 3255
 - tightMarshal1, 3256
 - tightMarshal2, 3256
- activemq::wireformat::openwire::marshal::v4::ResponseMarshaller, 3295
 - ~ResponseMarshaller, 3296
 - createObject, 3296
 - getDataStructureType, 3296
 - looseMarshal, 3296
 - looseUnmarshal, 3297
 - ResponseMarshaller, 3296

- tightMarshal1, 3297
- tightMarshal2, 3298
- tightUnmarshal, 3298
- activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller, 3387
 - ~SessionIdMarshaller, 3388
 - createObject, 3388
 - getDataStructureType, 3388
 - looseMarshal, 3388
 - looseUnmarshal, 3388
 - SessionIdMarshaller, 3388
 - tightMarshal1, 3389
 - tightMarshal2, 3389
 - tightUnmarshal, 3390
- activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller, 3431
 - ~SessionInfoMarshaller, 3432
 - createObject, 3432
 - getDataStructureType, 3432
 - looseMarshal, 3432
 - looseUnmarshal, 3432
 - SessionInfoMarshaller, 3432
 - tightMarshal1, 3433
 - tightMarshal2, 3433
 - tightUnmarshal, 3434
- activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller, 3493
 - ~ShutdownInfoMarshaller, 3494
 - createObject, 3494
 - getDataStructureType, 3494
 - looseMarshal, 3494
 - looseUnmarshal, 3494
 - ShutdownInfoMarshaller, 3494
 - tightMarshal1, 3495
 - tightMarshal2, 3495
 - tightUnmarshal, 3496
- activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller, 3688
 - ~SubscriptionInfoMarshaller, 3689
 - createObject, 3689
 - getDataStructureType, 3689
 - looseMarshal, 3689
 - looseUnmarshal, 3689
 - SubscriptionInfoMarshaller, 3689
 - tightMarshal1, 3690
 - tightMarshal2, 3690
 - tightUnmarshal, 3691
- activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller, 3839
 - ~TransactionIdMarshaller, 3840
 - looseMarshal, 3840
 - looseUnmarshal, 3840
 - tightMarshal1, 3841
 - tightMarshal2, 3841
- tightUnmarshal, 3842
- TransactionIdMarshaller, 3840
- activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller, 3867
 - ~TransactionInfoMarshaller, 3868
 - createObject, 3868
 - getDataStructureType, 3868
 - looseMarshal, 3868
 - looseUnmarshal, 3868
 - tightMarshal1, 3869
 - tightMarshal2, 3869
 - tightUnmarshal, 3870
 - TransactionInfoMarshaller, 3868
- activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller, 4004
 - ~WireFormatInfoMarshaller, 4005
 - createObject, 4005
 - getDataStructureType, 4005
 - looseMarshal, 4005
 - looseUnmarshal, 4005
 - tightMarshal1, 4006
 - tightMarshal2, 4006
 - tightUnmarshal, 4007
 - WireFormatInfoMarshaller, 4005
- activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller, 4044
 - ~XATransactionIdMarshaller, 4045
 - createObject, 4045
 - getDataStructureType, 4045
 - looseMarshal, 4045
 - looseUnmarshal, 4045
 - tightMarshal1, 4046
 - tightMarshal2, 4046
 - tightUnmarshal, 4047
 - XATransactionIdMarshaller, 4045
- activemq::wireformat::openwire::marshal::v5, 1128
 - Marshaller, 225
 - ~ActiveMQBlobMessageMarshaller, 226
 - ActiveMQBlobMessageMarshaller, 226
 - createObject, 226
 - getDataStructureType, 226
 - looseMarshal, 226
 - looseUnmarshal, 226
 - tightMarshal1, 227
 - tightMarshal2, 227
- activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller, 261
 - ~ActiveMQBytesMessageMarshaller, 262
 - ActiveMQBytesMessageMarshaller, 262
 - createObject, 262
 - getDataStructureType, 262

- looseMarshal, 262
- looseUnmarshal, 262
- tightMarshal1, 263
- tightMarshal2, 263
- tightUnmarshal, 264
- activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller, 345
 - ~ActiveMQDestinationMarshaller, 346
 - ActiveMQDestinationMarshaller, 346
 - looseMarshal, 346
 - looseUnmarshal, 346
 - tightMarshal1, 347
 - tightMarshal2, 347
 - tightUnmarshal, 348
- activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller, 386
 - ~ActiveMQMapMessageMarshaller, 387
 - ActiveMQMapMessageMarshaller, 387
 - createObject, 387
 - getDataStructureType, 387
 - looseMarshal, 387
 - looseUnmarshal, 387
 - tightMarshal1, 388
 - tightMarshal2, 388
 - tightUnmarshal, 389
- activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller, 413
 - ~ActiveMQMessageMarshaller, 414
 - ActiveMQMessageMarshaller, 414
 - createObject, 414
 - getDataStructureType, 414
 - looseMarshal, 414
 - looseUnmarshal, 414
 - tightMarshal1, 415
 - tightMarshal2, 415
 - tightUnmarshal, 416
- activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller, 458
 - ~ActiveMQObjectMessageMarshaller, 459
 - ActiveMQObjectMessageMarshaller, 459
 - createObject, 459
 - getDataStructureType, 459
 - looseMarshal, 459
 - looseUnmarshal, 459
 - tightMarshal1, 460
 - tightMarshal2, 460
 - tightUnmarshal, 461
- activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller, 503
 - ~ActiveMQQueueMarshaller, 504
 - ActiveMQQueueMarshaller, 504
 - createObject, 504
 - getDataStructureType, 504
 - looseMarshal, 504
 - looseUnmarshal, 504
 - tightMarshal1, 505
 - tightMarshal2, 505
 - tightUnmarshal, 506
- activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller, 564
 - ~ActiveMQStreamMessageMarshaller, 565
 - ActiveMQStreamMessageMarshaller, 565
 - createObject, 565
 - getDataStructureType, 565
 - looseMarshal, 565
 - looseUnmarshal, 565
 - tightMarshal1, 566
 - tightMarshal2, 566
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller, 592
 - ~ActiveMQTempDestinationMarshaller, 593
 - ActiveMQTempDestinationMarshaller, 593
 - looseMarshal, 593
 - looseUnmarshal, 593
 - tightMarshal1, 594
 - tightMarshal2, 594
 - tightUnmarshal, 595
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller, 621
 - ~ActiveMQTempQueueMarshaller, 622
 - ActiveMQTempQueueMarshaller, 622
 - createObject, 622
 - getDataStructureType, 622
 - looseMarshal, 622
 - looseUnmarshal, 622
 - tightMarshal1, 623
 - tightMarshal2, 623
 - tightUnmarshal, 624
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller, 650
 - ~ActiveMQTempTopicMarshaller, 651
 - ActiveMQTempTopicMarshaller, 651
 - createObject, 651
 - getDataStructureType, 651
 - looseMarshal, 651
 - looseUnmarshal, 651
 - tightMarshal1, 652
 - tightMarshal2, 652
 - tightUnmarshal, 653
- activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller, 679
 - ~ActiveMQTextMessageMarshaller, 680
 - ActiveMQTextMessageMarshaller, 680
 - createObject, 680
 - getDataStructureType, 680
 - looseMarshal, 680

- looseUnmarshal, 680
 - tightMarshal1, 681
 - tightMarshal2, 681
 - tightUnmarshal, 682
- activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller, 707
 - ~ActiveMQTopicMarshaller, 708
 - ActiveMQTopicMarshaller, 708
 - createObject, 708
 - getDataStructureType, 708
 - looseMarshal, 708
 - looseUnmarshal, 708
 - tightMarshal1, 709
 - tightMarshal2, 709
 - tightUnmarshal, 710
- activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller, 786
 - ~BaseCommandMarshaller, 787
 - BaseCommandMarshaller, 787
 - looseMarshal, 787
 - looseUnmarshal, 788
 - tightMarshal1, 789
 - tightMarshal2, 790
 - tightUnmarshal, 791
- activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller, 884
 - ~BrokerIdMarshaller, 885
 - BrokerIdMarshaller, 885
 - createObject, 885
 - getDataStructureType, 885
 - looseMarshal, 885
 - looseUnmarshal, 885
 - tightMarshal1, 886
 - tightMarshal2, 886
 - tightUnmarshal, 887
- activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller, 916
 - ~BrokerInfoMarshaller, 917
 - BrokerInfoMarshaller, 917
 - createObject, 917
 - getDataStructureType, 917
 - looseMarshal, 917
 - looseUnmarshal, 917
 - tightMarshal1, 918
 - tightMarshal2, 918
 - tightUnmarshal, 919
- activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller, 1284
 - ~ConnectionControlMarshaller, 1285
 - ConnectionControlMarshaller, 1285
 - createObject, 1285
 - getDataStructureType, 1285
 - looseMarshal, 1285
 - looseUnmarshal, 1285
- tightMarshal1, 1286
 - tightMarshal2, 1286
 - tightUnmarshal, 1287
- activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller, 1316
 - ~ConnectionErrorMarshaller, 1317
 - ConnectionErrorMarshaller, 1317
 - createObject, 1317
 - getDataStructureType, 1317
 - looseMarshal, 1317
 - looseUnmarshal, 1317
 - tightMarshal1, 1318
 - tightMarshal2, 1318
 - tightUnmarshal, 1319
- activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller, 1347
 - ~ConnectionIdMarshaller, 1348
 - ConnectionIdMarshaller, 1348
 - createObject, 1348
 - getDataStructureType, 1348
 - looseMarshal, 1348
 - looseUnmarshal, 1348
 - tightMarshal1, 1349
 - tightMarshal2, 1349
- activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller, 1377
 - ~ConnectionInfoMarshaller, 1378
 - ConnectionInfoMarshaller, 1378
 - createObject, 1378
 - getDataStructureType, 1378
 - looseMarshal, 1378
 - looseUnmarshal, 1378
 - tightMarshal1, 1379
 - tightMarshal2, 1379
- activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller, 1422
 - ~ConsumerControlMarshaller, 1423
 - ConsumerControlMarshaller, 1423
 - createObject, 1423
 - getDataStructureType, 1423
 - looseMarshal, 1423
 - looseUnmarshal, 1423
 - tightMarshal1, 1424
 - tightMarshal2, 1424
- activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller, 1451
 - ~ConsumerIdMarshaller, 1452
 - ConsumerIdMarshaller, 1452
 - createObject, 1452
 - getDataStructureType, 1452
 - looseMarshal, 1452

- looseUnmarshal, 1452
- tightMarshal1, 1453
- tightMarshal2, 1453
- tightUnmarshal, 1454
- activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller, 1484
 - ~ConsumerInfoMarshaller, 1485
 - ConsumerInfoMarshaller, 1485
 - createObject, 1485
 - getDataSetType, 1485
 - looseMarshal, 1485
 - looseUnmarshal, 1485
 - tightMarshal1, 1486
 - tightMarshal2, 1486
 - tightUnmarshal, 1487
- activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller, 1513
 - ~ControlCommandMarshaller, 1514
 - ControlCommandMarshaller, 1514
 - createObject, 1514
 - getDataSetType, 1514
 - looseMarshal, 1514
 - looseUnmarshal, 1514
 - tightMarshal1, 1515
 - tightMarshal2, 1515
 - tightUnmarshal, 1516
- activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller, 1547
 - ~DataArrayResponseMarshaller, 1548
 - createObject, 1548
 - DataArrayResponseMarshaller, 1548
 - getDataSetType, 1548
 - looseMarshal, 1548
 - looseUnmarshal, 1549
 - tightMarshal1, 1549
 - tightMarshal2, 1549
 - tightUnmarshal, 1550
- activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller, 1586
 - ~DataResponseMarshaller, 1587
 - createObject, 1587
 - DataResponseMarshaller, 1587
 - getDataSetType, 1587
 - looseMarshal, 1587
 - looseUnmarshal, 1588
 - tightMarshal1, 1588
 - tightMarshal2, 1588
 - tightUnmarshal, 1589
- activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller, 1752
 - ~DestinationInfoMarshaller, 1753
 - createObject, 1753
 - DestinationInfoMarshaller, 1753
 - getDataSetType, 1753
- looseMarshal, 1753
- looseUnmarshal, 1753
- tightMarshal1, 1754
- tightMarshal2, 1754
- tightUnmarshal, 1755
- activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller, 1782
 - ~DiscoveryEventMarshaller, 1783
 - createObject, 1783
 - DiscoveryEventMarshaller, 1783
 - getDataSetType, 1783
 - looseMarshal, 1783
 - looseUnmarshal, 1783
 - tightMarshal1, 1784
 - tightMarshal2, 1784
- activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller, 1854
 - ~ExceptionResponseMarshaller, 1855
 - createObject, 1855
 - ExceptionResponseMarshaller, 1855
 - getDataSetType, 1855
 - looseMarshal, 1855
 - looseUnmarshal, 1856
 - tightMarshal1, 1856
 - tightMarshal2, 1856
- activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller, 1960
 - ~FlushCommandMarshaller, 1961
 - createObject, 1961
 - FlushCommandMarshaller, 1961
 - getDataSetType, 1961
 - looseMarshal, 1961
 - looseUnmarshal, 1961
 - tightMarshal1, 1962
 - tightMarshal2, 1962
- activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller, 2114
 - ~IntegerResponseMarshaller, 2115
 - createObject, 2115
 - getDataSetType, 2115
 - IntegerResponseMarshaller, 2115
 - looseMarshal, 2115
 - looseUnmarshal, 2116
 - tightMarshal1, 2116
 - tightMarshal2, 2116
- activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller, 2167
 - ~JournalQueueAckMarshaller, 2168
 - createObject, 2168
 - getDataSetType, 2168

- JournalQueueAckMarshaller, 2168
- looseMarshal, 2168
- looseUnmarshal, 2168
- tightMarshal1, 2169
- tightMarshal2, 2169
- tightUnmarshal, 2170
- activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller, 2188
 - ~JournalTopicAckMarshaller, 2189
 - createObject, 2189
 - getDataStructureType, 2189
 - JournalTopicAckMarshaller, 2189
 - looseMarshal, 2189
 - looseUnmarshal, 2189
 - tightMarshal1, 2190
 - tightMarshal2, 2190
 - tightUnmarshal, 2191
- activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller, 2235
 - ~JournalTraceMarshaller, 2236
 - createObject, 2236
 - getDataStructureType, 2236
 - JournalTraceMarshaller, 2236
 - looseMarshal, 2236
 - looseUnmarshal, 2236
 - tightMarshal1, 2237
 - tightMarshal2, 2237
 - tightUnmarshal, 2238
- activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller, 2254
 - ~JournalTransactionMarshaller, 2255
 - createObject, 2255
 - getDataStructureType, 2255
 - JournalTransactionMarshaller, 2255
 - looseMarshal, 2255
 - looseUnmarshal, 2255
 - tightMarshal1, 2256
 - tightMarshal2, 2256
 - tightUnmarshal, 2257
- activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller, 2285
 - ~KeepAliveInfoMarshaller, 2286
 - createObject, 2286
 - getDataStructureType, 2286
 - KeepAliveInfoMarshaller, 2286
 - looseMarshal, 2286
 - looseUnmarshal, 2286
 - tightMarshal1, 2287
 - tightMarshal2, 2287
 - tightUnmarshal, 2288
- activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller, 2316
 - ~LastPartialCommandMarshaller, 2317
 - createObject, 2317
 - getDataStructureType, 2317
 - LastPartialCommandMarshaller, 2317
 - looseMarshal, 2317
 - looseUnmarshal, 2318
 - tightMarshal1, 2318
 - tightMarshal2, 2318
- activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller, 2363
 - ~LocalTransactionIdMarshaller, 2364
 - createObject, 2364
 - getDataStructureType, 2364
 - LocalTransactionIdMarshaller, 2364
 - looseMarshal, 2364
 - looseUnmarshal, 2364
 - tightMarshal1, 2365
 - tightMarshal2, 2365
- activemq::wireformat::openwire::marshal::v5::MarshallerFactory, 2490
 - ~MarshallerFactory, 2490
 - configure, 2490
- activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller, 2585
 - ~MessageAckMarshaller, 2586
 - createObject, 2586
 - getDataStructureType, 2586
 - looseMarshal, 2586
 - MessageAckMarshaller, 2586
 - tightMarshal1, 2587
 - tightMarshal2, 2587
 - tightUnmarshal, 2588
- activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller, 2614
 - ~MessageDispatchMarshaller, 2615
 - createObject, 2615
 - getDataStructureType, 2615
 - looseMarshal, 2615
 - MessageDispatchMarshaller, 2615
 - tightMarshal1, 2616
 - tightMarshal2, 2616
 - tightUnmarshal, 2617
- activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller, 2655
 - ~MessageDispatchNotificationMarshaller, 2656
 - createObject, 2656
 - getDataStructureType, 2656
 - looseMarshal, 2656
 - MessageDispatchNotificationMarshaller, 2656

- tightMarshal1, 2657
- tightMarshal2, 2657
- tightUnmarshal, 2658
- activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller, 2676
 - ~MessageIdMarshaller, 2677
 - createObject, 2677
 - getDataStructureType, 2677
 - looseMarshal, 2677
 - looseUnmarshal, 2677
 - MessageIdMarshaller, 2677
 - tightMarshal1, 2678
 - tightMarshal2, 2678
 - tightUnmarshal, 2679
- activemq::wireformat::openwire::marshal::v5::MessageMarshaller, 2693
 - ~MessageMarshaller, 2694
 - looseMarshal, 2694
 - looseUnmarshal, 2694
 - MessageMarshaller, 2694
 - tightMarshal1, 2695
 - tightMarshal2, 2695
 - tightUnmarshal, 2696
- activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller, 2748
 - ~MessagePullMarshaller, 2749
 - createObject, 2749
 - getDataStructureType, 2749
 - looseMarshal, 2749
 - looseUnmarshal, 2749
 - MessagePullMarshaller, 2749
 - tightMarshal1, 2750
 - tightMarshal2, 2750
 - tightUnmarshal, 2751
- activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller, 2804
 - ~NetworkBridgeFilterMarshaller, 2805
 - createObject, 2805
 - getDataStructureType, 2805
 - looseMarshal, 2805
 - looseUnmarshal, 2805
 - NetworkBridgeFilterMarshaller, 2805
 - tightMarshal1, 2806
 - tightMarshal2, 2806
 - tightUnmarshal, 2807
- activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2930
 - ~PartialCommandMarshaller, 2931
 - createObject, 2931
 - getDataStructureType, 2931
 - looseMarshal, 2931
 - looseUnmarshal, 2932
 - PartialCommandMarshaller, 2931
 - tightMarshal1, 2932
- tightMarshal2, 2932
- tightUnmarshal, 2933
- activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller, 3052
 - ~ProducerAckMarshaller, 3053
 - createObject, 3053
 - getDataStructureType, 3053
 - looseMarshal, 3053
 - looseUnmarshal, 3053
 - ProducerAckMarshaller, 3053
 - tightMarshal1, 3054
 - tightMarshal2, 3054
 - tightUnmarshal, 3055
- activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller, 3084
 - ~ProducerIdMarshaller, 3085
 - createObject, 3085
 - getDataStructureType, 3085
 - looseMarshal, 3085
 - looseUnmarshal, 3085
 - ProducerIdMarshaller, 3085
 - tightMarshal1, 3086
 - tightMarshal2, 3086
- activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller, 3113
 - ~ProducerInfoMarshaller, 3114
 - createObject, 3114
 - getDataStructureType, 3114
 - looseMarshal, 3114
 - looseUnmarshal, 3114
 - ProducerInfoMarshaller, 3114
 - tightMarshal1, 3115
 - tightMarshal2, 3115
- activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller, 3214
 - ~RemoveInfoMarshaller, 3215
 - createObject, 3215
 - getDataStructureType, 3215
 - looseMarshal, 3215
 - looseUnmarshal, 3215
 - RemoveInfoMarshaller, 3215
 - tightMarshal1, 3216
 - tightMarshal2, 3216
- activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller, 3243
 - ~RemoveSubscriptionInfoMarshaller, 3244
 - createObject, 3244
 - getDataStructureType, 3244
 - looseMarshal, 3244
 - looseUnmarshal, 3244
 - RemoveSubscriptionInfoMarshaller, 3244

- tightMarshal1, 3245
- tightMarshal2, 3245
- tightUnmarshal, 3246
- activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshal1, 3274
- ~ReplayCommandMarshaller, 3275
- createObject, 3275
- getDataStructureType, 3275
- looseMarshal, 3275
- looseUnmarshal, 3275
- ReplayCommandMarshaller, 3275
- tightMarshal1, 3276
- tightMarshal2, 3276
- tightUnmarshal, 3277
- activemq::wireformat::openwire::marshal::v5::ResponseCommandMarshal, 3305
- ~ResponseMarshaller, 3306
- createObject, 3306
- getDataStructureType, 3306
- looseMarshal, 3306
- looseUnmarshal, 3307
- ResponseMarshaller, 3306
- tightMarshal1, 3307
- tightMarshal2, 3308
- tightUnmarshal, 3308
- activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller, 3395
- ~SessionIdMarshaller, 3396
- createObject, 3396
- getDataStructureType, 3396
- looseMarshal, 3396
- looseUnmarshal, 3396
- SessionIdMarshaller, 3396
- tightMarshal1, 3397
- tightMarshal2, 3397
- tightUnmarshal, 3398
- activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller, 3415
- ~SessionInfoMarshaller, 3416
- createObject, 3416
- getDataStructureType, 3416
- looseMarshal, 3416
- looseUnmarshal, 3416
- SessionInfoMarshaller, 3416
- tightMarshal1, 3417
- tightMarshal2, 3417
- tightUnmarshal, 3418
- activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller, 3485
- ~ShutdownInfoMarshaller, 3486
- createObject, 3486
- getDataStructureType, 3486
- looseMarshal, 3486
- looseUnmarshal, 3486
- ShutdownInfoMarshaller, 3486
- tightMarshal1, 3487
- tightMarshal2, 3487
- tightUnmarshal, 3488
- activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller, 3684
- ~SubscriptionInfoMarshaller, 3685
- createObject, 3685
- getDataStructureType, 3685
- looseMarshal, 3685
- looseUnmarshal, 3685
- SubscriptionInfoMarshaller, 3685
- tightMarshal1, 3686
- tightMarshal2, 3686
- tightUnmarshal, 3687
- activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller, 3823
- ~TransactionIdMarshaller, 3824
- looseMarshal, 3824
- looseUnmarshal, 3824
- tightMarshal1, 3825
- tightMarshal2, 3825
- tightUnmarshal, 3826
- TransactionIdMarshaller, 3824
- activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller, 3851
- ~TransactionInfoMarshaller, 3852
- createObject, 3852
- getDataStructureType, 3852
- looseMarshal, 3852
- looseUnmarshal, 3852
- tightMarshal1, 3853
- tightMarshal2, 3853
- tightUnmarshal, 3854
- TransactionInfoMarshaller, 3852
- activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller, 3992
- ~WireFormatInfoMarshaller, 3993
- createObject, 3993
- getDataStructureType, 3993
- looseMarshal, 3993
- looseUnmarshal, 3993
- tightMarshal1, 3994
- tightMarshal2, 3994
- tightUnmarshal, 3995
- WireFormatInfoMarshaller, 3993
- activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller, 4056
- ~XATransactionIdMarshaller, 4057
- createObject, 4057
- getDataStructureType, 4057
- looseMarshal, 4057
- looseUnmarshal, 4057
- tightMarshal1, 4058

- tightMarshal2, 4058
- tightUnmarshal, 4059
- XATransactionIdMarshaller, 4057
- activemq::wireformat::openwire::marshal::v6, 133
- activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller, 229
 - ~ActiveMQBlobMessageMarshaller, 230
 - ActiveMQBlobMessageMarshaller, 230
 - createObject, 230
 - getDataStructureType, 230
 - looseMarshal, 230
 - looseUnmarshal, 230
 - tightMarshal1, 231
 - tightMarshal2, 231
 - tightUnmarshal, 232
- activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller, 265
 - ~ActiveMQBytesMessageMarshaller, 266
 - ActiveMQBytesMessageMarshaller, 266
 - createObject, 266
 - getDataStructureType, 266
 - looseMarshal, 266
 - looseUnmarshal, 266
 - tightMarshal1, 267
 - tightMarshal2, 267
 - tightUnmarshal, 268
- activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller, 353
 - ~ActiveMQDestinationMarshaller, 354
 - ActiveMQDestinationMarshaller, 354
 - looseMarshal, 354
 - looseUnmarshal, 354
 - tightMarshal1, 355
 - tightMarshal2, 355
 - tightUnmarshal, 356
- activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller, 394
 - ~ActiveMQMapMessageMarshaller, 395
 - ActiveMQMapMessageMarshaller, 395
 - createObject, 395
 - getDataStructureType, 395
 - looseMarshal, 395
 - looseUnmarshal, 395
 - tightMarshal1, 396
 - tightMarshal2, 396
 - tightUnmarshal, 397
- activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller, 421
 - ~ActiveMQMessageMarshaller, 422
 - ActiveMQMessageMarshaller, 422
 - createObject, 422
 - getDataStructureType, 422
 - looseMarshal, 422
 - looseUnmarshal, 422
 - tightMarshal1, 423
 - tightMarshal2, 423
 - tightUnmarshal, 424
- activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller, 467
 - ~ActiveMQObjectMessageMarshaller, 467
 - ActiveMQObjectMessageMarshaller, 467
 - createObject, 467
 - getDataStructureType, 467
 - looseMarshal, 467
 - looseUnmarshal, 467
 - tightMarshal1, 468
 - tightMarshal2, 468
 - tightUnmarshal, 469
- activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller, 512
 - ~ActiveMQQueueMessageMarshaller, 512
 - ActiveMQQueueMessageMarshaller, 512
 - createObject, 512
 - getDataStructureType, 512
 - looseMarshal, 512
 - looseUnmarshal, 512
 - tightMarshal1, 513
 - tightMarshal2, 513
 - tightUnmarshal, 514
- activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller, 573
 - ~ActiveMQStreamMessageMarshaller, 573
 - ActiveMQStreamMessageMarshaller, 573
 - createObject, 573
 - getDataStructureType, 573
 - looseMarshal, 573
 - looseUnmarshal, 573
 - tightMarshal1, 574
 - tightMarshal2, 574
 - tightUnmarshal, 575
- activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller, 600
 - ~ActiveMQTempDestinationMarshaller, 601
 - ActiveMQTempDestinationMarshaller, 601
 - looseMarshal, 601
 - looseUnmarshal, 601
 - tightMarshal1, 602
 - tightMarshal2, 602
 - tightUnmarshal, 603
- activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller, 629
 - ~ActiveMQTempQueueMarshaller, 630
 - ActiveMQTempQueueMarshaller, 630
 - createObject, 630
 - getDataStructureType, 630
 - looseMarshal, 630

- looseUnmarshal, 630
- tightMarshal1, 631
- tightMarshal2, 631
- tightUnmarshal, 632
- activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller, 658
 - ~ActiveMQTempTopicMarshaller, 659
 - ActiveMQTempTopicMarshaller, 659
 - createObject, 659
 - getDataStructureType, 659
 - looseMarshal, 659
 - looseUnmarshal, 659
 - tightMarshal1, 660
 - tightMarshal2, 660
 - tightUnmarshal, 661
- activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller, 683
 - ~ActiveMQTextMessageMarshaller, 684
 - ActiveMQTextMessageMarshaller, 684
 - createObject, 684
 - getDataStructureType, 684
 - looseMarshal, 684
 - looseUnmarshal, 684
 - tightMarshal1, 685
 - tightMarshal2, 685
 - tightUnmarshal, 686
- activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller, 711
 - ~ActiveMQTopicMarshaller, 712
 - ActiveMQTopicMarshaller, 712
 - createObject, 712
 - getDataStructureType, 712
 - looseMarshal, 712
 - looseUnmarshal, 712
 - tightMarshal1, 713
 - tightMarshal2, 713
 - tightUnmarshal, 714
- activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller, 793
 - ~BaseCommandMarshaller, 794
 - BaseCommandMarshaller, 794
 - looseMarshal, 794
 - looseUnmarshal, 795
 - tightMarshal1, 796
 - tightMarshal2, 797
 - tightUnmarshal, 798
- activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller, 888
 - ~BrokerIdMarshaller, 889
 - BrokerIdMarshaller, 889
 - createObject, 889
 - getDataStructureType, 889
 - looseMarshal, 889
 - looseUnmarshal, 889
- tightMarshal1, 890
- tightMarshal2, 890
- tightUnmarshal, 891
- activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller, 920
 - ~BrokerInfoMarshaller, 921
 - BrokerInfoMarshaller, 921
 - createObject, 921
 - getDataStructureType, 921
 - looseMarshal, 921
 - looseUnmarshal, 921
 - tightMarshal1, 922
 - tightMarshal2, 922
 - tightUnmarshal, 923
- activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller, 1288
 - ~ConnectionControlMarshaller, 1289
 - ConnectionControlMarshaller, 1289
 - createObject, 1289
 - getDataStructureType, 1289
 - looseMarshal, 1289
 - looseUnmarshal, 1289
 - tightMarshal1, 1290
 - tightMarshal2, 1290
 - tightUnmarshal, 1291
- activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller, 1320
 - ~ConnectionErrorMarshaller, 1321
 - ConnectionErrorMarshaller, 1321
 - createObject, 1321
 - getDataStructureType, 1321
 - looseMarshal, 1321
 - looseUnmarshal, 1321
 - tightMarshal1, 1322
 - tightMarshal2, 1322
 - tightUnmarshal, 1323
- activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller, 1351
 - ~ConnectionIdMarshaller, 1352
 - ConnectionIdMarshaller, 1352
 - createObject, 1352
 - getDataStructureType, 1352
 - looseMarshal, 1352
 - looseUnmarshal, 1352
 - tightMarshal1, 1353
 - tightMarshal2, 1353
 - tightUnmarshal, 1354
- activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller, 1381
 - ~ConnectionInfoMarshaller, 1382
 - ConnectionInfoMarshaller, 1382
 - createObject, 1382
 - getDataStructureType, 1382
 - looseMarshal, 1382

- looseUnmarshal, 1382
- tightMarshal1, 1383
- tightMarshal2, 1383
- tightUnmarshal, 1384
- activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller, 1426
 - ~ConsumerControlMarshaller, 1427
 - ConsumerControlMarshaller, 1427
 - createObject, 1427
 - getDataStructureType, 1427
 - looseMarshal, 1427
 - looseUnmarshal, 1427
 - tightMarshal1, 1428
 - tightMarshal2, 1428
 - tightUnmarshal, 1429
- activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller, 1455
 - ~ConsumerIdMarshaller, 1456
 - ConsumerIdMarshaller, 1456
 - createObject, 1456
 - getDataStructureType, 1456
 - looseMarshal, 1456
 - looseUnmarshal, 1456
 - tightMarshal1, 1457
 - tightMarshal2, 1457
 - tightUnmarshal, 1458
- activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller, 1488
 - ~ConsumerInfoMarshaller, 1489
 - ConsumerInfoMarshaller, 1489
 - createObject, 1489
 - getDataStructureType, 1489
 - looseMarshal, 1489
 - looseUnmarshal, 1489
 - tightMarshal1, 1490
 - tightMarshal2, 1490
 - tightUnmarshal, 1491
- activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller, 1517
 - ~ControlCommandMarshaller, 1518
 - ControlCommandMarshaller, 1518
 - createObject, 1518
 - getDataStructureType, 1518
 - looseMarshal, 1518
 - looseUnmarshal, 1518
 - tightMarshal1, 1519
 - tightMarshal2, 1519
 - tightUnmarshal, 1520
- activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller, 1551
 - ~DataArrayResponseMarshaller, 1552
 - createObject, 1552
 - DataArrayResponseMarshaller, 1552
 - getDataStructureType, 1552
- looseMarshal, 1552
- looseUnmarshal, 1553
- tightMarshal1, 1553
- tightMarshal2, 1553
- activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller, 1590
 - ~DataResponseMarshaller, 1591
 - createObject, 1591
 - DataResponseMarshaller, 1591
 - getDataStructureType, 1591
 - looseMarshal, 1591
 - looseUnmarshal, 1592
 - tightMarshal1, 1592
 - tightMarshal2, 1592
 - tightUnmarshal, 1593
- activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller, 1748
 - ~DestinationInfoMarshaller, 1749
 - createObject, 1749
 - DestinationInfoMarshaller, 1749
 - getDataStructureType, 1749
 - looseMarshal, 1749
 - looseUnmarshal, 1749
 - tightMarshal1, 1750
 - tightMarshal2, 1750
 - tightUnmarshal, 1751
- activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller, 1762
 - ~DiscoveryEventMarshaller, 1763
 - createObject, 1763
 - DiscoveryEventMarshaller, 1763
 - getDataStructureType, 1763
 - looseMarshal, 1763
 - looseUnmarshal, 1763
 - tightMarshal1, 1764
 - tightMarshal2, 1764
 - tightUnmarshal, 1765
- activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller, 1842
 - ~ExceptionResponseMarshaller, 1843
 - createObject, 1843
 - ExceptionResponseMarshaller, 1843
 - getDataStructureType, 1843
 - looseMarshal, 1843
 - looseUnmarshal, 1844
 - tightMarshal1, 1844
 - tightMarshal2, 1844
 - tightUnmarshal, 1845
- activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller, 1940
 - ~FlushCommandMarshaller, 1941
 - createObject, 1941
 - FlushCommandMarshaller, 1941

- getDataStructureType, 1941
 - looseMarshal, 1941
 - looseUnmarshal, 1941
 - tightMarshal1, 1942
 - tightMarshal2, 1942
 - tightUnmarshal, 1943
- activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller, 2094
 - ~IntegerResponseMarshaller, 2095
 - createObject, 2095
 - getDataStructureType, 2095
 - IntegerResponseMarshaller, 2095
 - looseMarshal, 2095
 - looseUnmarshal, 2096
 - tightMarshal1, 2096
 - tightMarshal2, 2096
 - tightUnmarshal, 2097
- activemq::wireformat::openwire::marshal::v6::JournalQueueAckMarshaller, 2159
 - ~JournalQueueAckMarshaller, 2160
 - createObject, 2160
 - getDataStructureType, 2160
 - JournalQueueAckMarshaller, 2160
 - looseMarshal, 2160
 - looseUnmarshal, 2160
 - tightMarshal1, 2161
 - tightMarshal2, 2161
 - tightUnmarshal, 2162
- activemq::wireformat::openwire::marshal::v6::JournalTopicAckMarshaller, 2200
 - ~JournalTopicAckMarshaller, 2201
 - createObject, 2201
 - getDataStructureType, 2201
 - JournalTopicAckMarshaller, 2201
 - looseMarshal, 2201
 - looseUnmarshal, 2201
 - tightMarshal1, 2202
 - tightMarshal2, 2202
 - tightUnmarshal, 2203
- activemq::wireformat::openwire::marshal::v6::JournalTraceMarshaller, 2223
 - ~JournalTraceMarshaller, 2224
 - createObject, 2224
 - getDataStructureType, 2224
 - JournalTraceMarshaller, 2224
 - looseMarshal, 2224
 - looseUnmarshal, 2224
 - tightMarshal1, 2225
 - tightMarshal2, 2225
 - tightUnmarshal, 2226
- activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller, 2242
 - ~JournalTransactionMarshaller, 2243
 - createObject, 2243
 - getDataStructureType, 2243
 - JournalTransactionMarshaller, 2243
 - looseMarshal, 2243
 - looseUnmarshal, 2243
 - tightMarshal1, 2244
 - tightMarshal2, 2244
 - tightUnmarshal, 2245
- activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller, 2269
 - ~KeepAliveInfoMarshaller, 2270
 - createObject, 2270
 - getDataStructureType, 2270
 - KeepAliveInfoMarshaller, 2270
 - looseMarshal, 2270
 - looseUnmarshal, 2270
 - tightMarshal1, 2271
 - tightMarshal2, 2271
- activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller, 2304
 - ~LastPartialCommandMarshaller, 2305
 - createObject, 2305
 - getDataStructureType, 2305
 - LastPartialCommandMarshaller, 2305
 - looseMarshal, 2305
 - looseUnmarshal, 2306
 - tightMarshal1, 2306
 - tightMarshal2, 2306
- activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller, 2351
 - ~LocalTransactionIdMarshaller, 2352
 - createObject, 2352
 - getDataStructureType, 2352
 - LocalTransactionIdMarshaller, 2352
 - looseMarshal, 2352
 - looseUnmarshal, 2352
 - tightMarshal1, 2353
 - tightMarshal2, 2353
- activemq::wireformat::openwire::marshal::v6::MarshallerFactory, 2487
 - ~MarshallerFactory, 2487
 - configure, 2487
- activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller, 2565
 - ~MessageAckMarshaller, 2566
 - createObject, 2566
 - getDataStructureType, 2566
 - looseMarshal, 2566
 - looseUnmarshal, 2566
 - MessageAckMarshaller, 2566
 - tightMarshal1, 2567
 - tightMarshal2, 2567

- tightUnmarshal, 2568
- activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller, 2626
 - ~MessageDispatchMarshaller, 2627
 - createObject, 2627
 - getDataStructureType, 2627
 - looseMarshal, 2627
 - looseUnmarshal, 2627
 - MessageDispatchMarshaller, 2627
 - tightMarshal1, 2628
 - tightMarshal2, 2628
 - tightUnmarshal, 2629
- activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller, 2635
 - ~MessageDispatchNotificationMarshaller, 2636
 - createObject, 2636
 - getDataStructureType, 2636
 - looseMarshal, 2636
 - looseUnmarshal, 2636
 - MessageDispatchNotificationMarshaller, 2636
 - tightMarshal1, 2637
 - tightMarshal2, 2637
 - tightUnmarshal, 2638
- activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller, 2684
 - ~MessageIdMarshaller, 2685
 - createObject, 2685
 - getDataStructureType, 2685
 - looseMarshal, 2685
 - looseUnmarshal, 2685
 - MessageIdMarshaller, 2685
 - tightMarshal1, 2686
 - tightMarshal2, 2686
 - tightUnmarshal, 2687
- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 2718
 - ~MessageMarshaller, 2719
 - looseMarshal, 2719
 - looseUnmarshal, 2719
 - MessageMarshaller, 2719
 - tightMarshal1, 2720
 - tightMarshal2, 2720
 - tightUnmarshal, 2721
- activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller, 2764
 - ~MessagePullMarshaller, 2765
 - createObject, 2765
 - getDataStructureType, 2765
 - looseMarshal, 2765
 - looseUnmarshal, 2765
 - MessagePullMarshaller, 2765
 - tightMarshal1, 2766
- tightMarshal2, 2766
- activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller, 2800
 - ~NetworkBridgeFilterMarshaller, 2801
 - createObject, 2801
 - getDataStructureType, 2801
 - looseMarshal, 2801
 - looseUnmarshal, 2801
 - NetworkBridgeFilterMarshaller, 2801
 - tightMarshal1, 2802
 - tightMarshal2, 2802
- activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2922
 - ~PartialCommandMarshaller, 2923
 - createObject, 2923
 - getDataStructureType, 2923
 - looseMarshal, 2923
 - looseUnmarshal, 2924
 - PartialCommandMarshaller, 2923
 - tightMarshal1, 2924
 - tightMarshal2, 2924
 - tightUnmarshal, 2925
- activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller, 3057
 - ~ProducerAckMarshaller, 3057
 - createObject, 3057
 - getDataStructureType, 3057
 - looseMarshal, 3057
 - looseUnmarshal, 3057
 - ProducerAckMarshaller, 3057
 - tightMarshal1, 3058
 - tightMarshal2, 3058
 - tightUnmarshal, 3059
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3089
 - ~ProducerIdMarshaller, 3089
 - createObject, 3089
 - getDataStructureType, 3089
 - looseMarshal, 3089
 - looseUnmarshal, 3089
 - ProducerIdMarshaller, 3089
 - tightMarshal1, 3090
 - tightMarshal2, 3090
- activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller, 3121
 - ~ProducerInfoMarshaller, 3122
 - createObject, 3122
 - getDataStructureType, 3122
 - looseMarshal, 3122
 - looseUnmarshal, 3122
 - ProducerInfoMarshaller, 3122

- tightMarshal1, 3123
- tightMarshal2, 3123
- tightUnmarshal, 3124
- activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller, 3394
 - 3202
 - ~RemoveInfoMarshaller, 3203
 - createObject, 3203
 - getDataStructureType, 3203
 - looseMarshal, 3203
 - looseUnmarshal, 3203
 - RemoveInfoMarshaller, 3203
 - tightMarshal1, 3204
 - tightMarshal2, 3204
 - tightUnmarshal, 3205
- activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller, 3239
 - ~RemoveSubscriptionInfoMarshaller, 3240
 - createObject, 3240
 - getDataStructureType, 3240
 - looseMarshal, 3240
 - looseUnmarshal, 3240
 - RemoveSubscriptionInfoMarshaller, 3240
 - tightMarshal1, 3241
 - tightMarshal2, 3241
 - tightUnmarshal, 3242
- activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller, 3270
 - ~ReplayCommandMarshaller, 3271
 - createObject, 3271
 - getDataStructureType, 3271
 - looseMarshal, 3271
 - looseUnmarshal, 3271
 - ReplayCommandMarshaller, 3271
 - tightMarshal1, 3272
 - tightMarshal2, 3272
 - tightUnmarshal, 3273
- activemq::wireformat::openwire::marshal::v6::ResponseMarshaller, 3320
 - ~ResponseMarshaller, 3321
 - createObject, 3321
 - getDataStructureType, 3321
 - looseMarshal, 3321
 - looseUnmarshal, 3322
 - ResponseMarshaller, 3321
 - tightMarshal1, 3322
 - tightMarshal2, 3323
 - tightUnmarshal, 3323
- activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3391
 - ~SessionIdMarshaller, 3392
 - createObject, 3392
 - getDataStructureType, 3392
 - looseMarshal, 3392
 - looseUnmarshal, 3392
- SessionIdMarshaller, 3392
- tightMarshal1, 3393
- tightMarshal2, 3393
- activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller, 3411
 - ~SessionInfoMarshaller, 3412
 - createObject, 3412
 - getDataStructureType, 3412
 - looseMarshal, 3412
 - looseUnmarshal, 3412
 - SessionInfoMarshaller, 3412
 - tightMarshal1, 3413
 - tightMarshal2, 3413
- activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3473
 - ~ShutdownInfoMarshaller, 3474
 - createObject, 3474
 - getDataStructureType, 3474
 - looseMarshal, 3474
 - looseUnmarshal, 3474
 - ShutdownInfoMarshaller, 3474
 - tightMarshal1, 3475
 - tightMarshal2, 3475
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller, 3692
 - ~SubscriptionInfoMarshaller, 3693
 - createObject, 3693
 - getDataStructureType, 3693
 - looseMarshal, 3693
 - looseUnmarshal, 3693
 - SubscriptionInfoMarshaller, 3693
 - tightMarshal1, 3694
 - tightMarshal2, 3694
- activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller, 3843
 - ~TransactionIdMarshaller, 3844
 - looseMarshal, 3844
 - looseUnmarshal, 3844
 - tightMarshal1, 3845
 - tightMarshal2, 3845
 - tightUnmarshal, 3846
 - TransactionIdMarshaller, 3844
- activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller, 3863
 - ~TransactionInfoMarshaller, 3864
 - createObject, 3864
 - getDataStructureType, 3864
 - looseMarshal, 3864
 - looseUnmarshal, 3864
 - tightMarshal1, 3865

- tightMarshal2, 3865
- tightUnmarshal, 3866
- TransactionInfoMarshaller, 3864
- activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller, 3996
 - ~WireFormatInfoMarshaller, 3997
 - createObject, 3997
 - getDataStructureType, 3997
 - looseMarshal, 3997
 - looseUnmarshal, 3997
 - tightMarshal1, 3998
 - tightMarshal2, 3998
 - tightUnmarshal, 3999
 - WireFormatInfoMarshaller, 3997
- activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller, 4036
 - ~XATransactionIdMarshaller, 4037
 - createObject, 4037
 - getDataStructureType, 4037
 - looseMarshal, 4037
 - looseUnmarshal, 4037
 - tightMarshal1, 4038
 - tightMarshal2, 4038
 - tightUnmarshal, 4039
 - XATransactionIdMarshaller, 4037
- activemq::wireformat::openwire::OpenWireFormat, 2887
 - ~OpenWireFormat, 2890
 - addMarshaller, 2890
 - createNegotiator, 2890
 - DEFAULT_VERSION, 2898
 - destroyMarshalers, 2890
 - doUnmarshal, 2890
 - getCacheSize, 2891
 - getMaxInactivityDuration, 2891
 - getMaxInactivityDurationInitialDelay, 2891
 - getPreferredWireFormatInfo, 2891
 - getVersion, 2892
 - hasNegotiator, 2892
 - inReceive, 2892
 - isCacheEnabled, 2892
 - isSizePrefixDisabled, 2892
 - isStackTraceEnabled, 2893
 - isTcpNoDelayEnabled, 2893
 - isTightEncodingEnabled, 2893
 - looseMarshalNestedObject, 2893
 - looseUnmarshalNestedObject, 2894
 - marshal, 2894
 - NULL_TYPE, 2898
 - OpenWireFormat, 2890
 - renegotiateWireFormat, 2894
 - setCacheEnabled, 2895
 - setCacheSize, 2895
 - setMaxInactivityDuration, 2895
 - setMaxInactivityDurationInitialDelay, 2895
 - setPreferredWireFormatInfo, 2895
 - setSizePrefixDisabled, 2896
 - setStackTraceEnabled, 2896
 - setTcpNoDelayEnabled, 2896
 - setTightEncodingEnabled, 2896
 - setVersion, 2896
 - tightMarshalNestedObject1, 2897
 - tightMarshalNestedObject2, 2897
 - tightUnmarshalNestedObject, 2897
 - unmarshal, 2898
- activemq::wireformat::openwire::OpenWireFormatFactory, 2899
 - ~OpenWireFormatFactory, 2899
 - createWireFormat, 2899
 - OpenWireFormatFactory, 2899
- activemq::wireformat::openwire::OpenWireFormatNegotiator, 2901
 - ~OpenWireFormatNegotiator, 2902
 - close, 2902
 - onCommand, 2902
 - oneway, 2902
 - onTransportException, 2903
 - OpenWireFormatNegotiator, 2901
 - request, 2903
 - start, 2904
- activemq::wireformat::openwire::OpenWireResponseBuilder, 2905
 - ~OpenWireResponseBuilder, 2905
 - buildIncomingCommands, 2905
 - buildResponse, 2905
 - OpenWireResponseBuilder, 2905
- activemq::wireformat::openwire::utils, 138
- activemq::wireformat::openwire::utils::BooleanStream, 857
 - ~BooleanStream, 858
 - BooleanStream, 858
 - clear, 858
 - marshal, 858
 - marshalledSize, 858
 - readBoolean, 858
 - unmarshal, 858
 - writeBoolean, 859
- activemq::wireformat::openwire::utils::HexTable, 1984
 - ~HexTable, 1984
 - HexTable, 1984
 - operator[], 1984
 - size, 1985
- activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2732
 - ~MessagePropertyInterceptor, 2733

- getBooleanProperty, 2734
- getByteProperty, 2734
- getDoubleProperty, 2734
- getFloatProperty, 2734
- getIntProperty, 2735
- getLongProperty, 2735
- getShortProperty, 2735
- getStringProperty, 2735
- MessagePropertyInterceptor, 2733
- setBooleanProperty, 2736
- setByteProperty, 2736
- setDoubleProperty, 2736
- setFloatProperty, 2736
- setIntProperty, 2737
- setLongProperty, 2737
- setShortProperty, 2737
- setStringProperty, 2737
- activemq::wireformat::stomp, 139
- activemq::wireformat::stomp::StompCommandConstants, 3629
 - ABORT, 3631
 - ACK, 3631
 - ACK_AUTO, 3631
 - ACK_CLIENT, 3631
 - ACK_INDIVIDUAL, 3631
 - BEGIN, 3631
 - BYTES, 3631
 - COMMIT, 3631
 - CONNECT, 3631
 - CONNECTED, 3631
 - DISCONNECT, 3631
 - ERROR_CMD, 3631
 - HEADER_ACK, 3631
 - HEADER_CLIENT_ID, 3631
 - HEADER_CONSUMERPRIORITY, 3631
 - HEADER_CONTENTLENGTH, 3631
 - HEADER_CORRELATIONID, 3631
 - HEADER_DESTINATION, 3631
 - HEADER_DISPATCH_ASYNC, 3631
 - HEADER_EXCLUSIVE, 3631
 - HEADER_EXPIRES, 3631
 - HEADER_ID, 3631
 - HEADER_JMSPRIORITY, 3631
 - HEADER_LOGIN, 3631
 - HEADER_MAXPENDINGMSGLIMIT, 3631
 - HEADER_MESSAGE, 3631
 - HEADER_MESSAGEID, 3631
 - HEADER_NOLOCAL, 3631
 - HEADER_OLDSUBSCRIPTIONNAME, 3631
 - HEADER_PASSWORD, 3631
 - HEADER_PERSISTENT, 3631
 - HEADER_PREFETCHSIZE, 3631
 - HEADER_RECEIPT_REQUIRED, 3631
 - HEADER_RECEIPTID, 3631
 - HEADER_REDELIVERED, 3631
 - HEADER_REDELIVERYCOUNT, 3631
 - HEADER_REPLYTO, 3631
 - HEADER_REQUESTID, 3631
 - HEADER_RESPONSEID, 3631
 - HEADER_RETROACTIVE, 3631
 - HEADER_SELECTOR, 3631
 - HEADER_SESSIONID, 3631
 - HEADER_SUBSCRIPTION, 3631
 - HEADER_SUBSCRIPTIONNAME, 3631
 - HEADER_TIMESTAMP, 3631
 - HEADER_TRANSACTIONID, 3631
 - HEADER_TRANSFORMATION, 3631
 - HEADER_TRANSFORMATION_ERROR, 3631
 - HEADER_TYPE, 3631
 - MESSAGE, 3631
 - QUEUE_PREFIX, 3631
 - RECEIPT, 3631
 - SEND, 3631
 - SUBSCRIBE, 3631
 - TEMPQUEUE_PREFIX, 3631
 - TEMPTOPIC_PREFIX, 3631
 - TEXT, 3631
 - TOPIC_PREFIX, 3631
 - UNSUBSCRIBE, 3631
- activemq::wireformat::stomp::StompFrame, 3633
 - ~StompFrame, 3634
 - clone, 3634
 - copy, 3634
 - fromStream, 3634
 - getBody, 3635
 - getBodyLength, 3635
 - getCommand, 3635
 - getProperties, 3635
 - getProperty, 3636
 - hasProperty, 3636
 - removeProperty, 3636
 - setBody, 3636
 - setCommand, 3636
 - setProperty, 3637
 - StompFrame, 3634
 - toStream, 3637
- activemq::wireformat::stomp::StompHelper, 3638
 - ~StompHelper, 3639
 - convertConsumerId, 3639
 - convertDestination, 3639, 3640
 - convertMessageId, 3640
 - convertProducerId, 3640, 3641
 - convertProperties, 3641

- convertTransactionId, 3641, 3642
- StompHelper, 3639
- activemq::wireformat::stomp::StompWireFormat, 3643
 - ~StompWireFormat, 3644
 - createNegotiator, 3644
 - getVersion, 3644
 - hasNegotiator, 3644
 - inReceive, 3644
 - marshal, 3645
 - setVersion, 3645
 - StompWireFormat, 3644
 - unmarshal, 3645
- activemq::wireformat::stomp::StompWireFormatFactory, 3647
 - ~StompWireFormatFactory, 3647
 - createWireFormat, 3647
 - StompWireFormatFactory, 3647
- activemq::wireformat::WireFormat, 3976
 - ~WireFormat, 3977
 - createNegotiator, 3977
 - getVersion, 3977
 - hasNegotiator, 3977
 - inReceive, 3978
 - marshal, 3978
 - setVersion, 3978
 - unmarshal, 3978
- activemq::wireformat::WireFormatFactory, 3980
 - ~WireFormatFactory, 3980
 - createWireFormat, 3980
- activemq::wireformat::WireFormatNegotiator, 4016
 - ~WireFormatNegotiator, 4016
 - WireFormatNegotiator, 4016
- activemq::wireformat::WireFormatRegistry, 4017
 - ~WireFormatRegistry, 4018
 - findFactory, 4018
 - getInstance, 4018
 - getWireFormatNames, 4018
 - registerFactory, 4018
 - unregisterFactory, 4019
- ActiveMQBlobMessage
 - activemq::commands::ActiveMQBlobMessage, 205
- ActiveMQBlobMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMessageMarshaller, 214
 - activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMessageMarshaller, 222
 - activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMessageMarshaller, 210
- activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMessageMarshaller, 218
- activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller, 226
- activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMessageMarshaller, 230
- ActiveMQBytesMessage
 - activemq::commands::ActiveMQBytesMessage, 236
- ActiveMQBytesMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMessageMarshaller, 254
 - activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMessageMarshaller, 270
 - activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMessageMarshaller, 250
 - activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMessageMarshaller, 258
 - activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMessageMarshaller, 262
 - activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller, 266
- ActiveMQConnection
 - activemq::core::ActiveMQConnection, 278
- ActiveMQConnectionFactory
 - activemq::core::ActiveMQConnectionFactory, 294
- ActiveMQConnectionMetaData
 - activemq::core::ActiveMQConnectionMetaData, 304
- ActiveMQConsumer
 - activemq::core::ActiveMQConsumer, 312
- ActiveMQCPP
 - activemq::library::ActiveMQCPP, 320
- ActiveMQDestination
 - activemq::commands::ActiveMQDestination, 324
- ActiveMQDestinationMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller, 338
 - activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller, 350
 - activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller, 334
 - activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller, 342
 - activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller, 346
 - activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller, 354
- ActiveMQException
 - activemq::exceptions::ActiveMQException, 357
- ActiveMQMapMessage

activemq::commands::ActiveMQMapMessage, ActiveMQQueue
 363
 activemq::commands::ActiveMQQueue,
 484
 ActiveMQMapMessageMarshaller
 379
 activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller,
 379
 activemq::core::ActiveMQQueueBrowser,
 388
 activemq::wireformat::openwire::marshal::v2::ActiveMQMapMessageMarshaller,
 391
 ActiveMQQueueMarshaller
 375
 activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller,
 496
 activemq::wireformat::openwire::marshal::v1::ActiveMQQueue
 383
 activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller,
 508
 activemq::wireformat::openwire::marshal::v2::ActiveMQQueue
 387
 activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller,
 492
 activemq::wireformat::openwire::marshal::v3::ActiveMQQueue
 395
 activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller,
 500
 activemq::wireformat::openwire::marshal::v4::ActiveMQQueue
 ActiveMQMessage
 activemq::commands::ActiveMQMessage,
 504
 activemq::wireformat::openwire::marshal::v5::ActiveMQQueue
 398
 activemq::wireformat::openwire::marshal::v6::ActiveMQQueue
 ActiveMQMessageMarshaller
 512
 activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller,
 406
 ActiveMQSession
 418
 activemq::core::ActiveMQSession, 519
 activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller,
 ActiveMQSessionExecutor
 402
 activemq::core::ActiveMQSession, 532
 activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller,
 activemq::core::ActiveMQSessionExecutor,
 534
 activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller,
 ActiveMQStreamMessage
 410
 activemq::commands::ActiveMQStreamMessage,
 540
 activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller,
 414
 ActiveMQStreamMessageMarshaller
 422
 activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller,
 557
 activemq::wireformat::openwire::marshal::v1::ActiveMQStream
 ActiveMQMessageTemplate
 activemq::commands::ActiveMQMessageTemplate,
 569
 428
 activemq::wireformat::openwire::marshal::v2::ActiveMQStream
 ActiveMQObjectMessage
 553
 activemq::commands::ActiveMQObjectMessage,
 561
 444
 activemq::wireformat::openwire::marshal::v3::ActiveMQStream
 ActiveMQObjectMessageMarshaller
 451
 activemq::wireformat::openwire::marshal::v4::ActiveMQStream
 463
 activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller,
 573
 447
 activemq::wireformat::openwire::marshal::v6::ActiveMQStream
 ActiveMQTempDestination
 455
 activemq::commands::ActiveMQTempDestination,
 577
 459
 activemq::wireformat::openwire::marshal::v1::ActiveMQTemp
 467
 activemq::wireformat::openwire::marshal::v2::ActiveMQTemp
 ActiveMQProducer
 activemq::core::ActiveMQProducer, 471
 581
 ActiveMQProperties
 activemq::util::ActiveMQProperties, 479
 589

- activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller, 593
- activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller, 601
- ActiveMQTempQueue
 - activemq::commands::ActiveMQTempQueue, 605
- ActiveMQTempQueueMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller, 614
 - activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller, 626
 - activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller, 610
 - activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller, 618
 - activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller, 622
 - activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller, 630
- ActiveMQTempTopic
 - activemq::commands::ActiveMQTempTopic, 634
- ActiveMQTempTopicMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempTopicMarshaller, 647
 - activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller, 655
 - activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller, 639
 - activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller, 643
 - activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller, 651
 - activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller, 659
- ActiveMQTextMessage
 - activemq::commands::ActiveMQTextMessage, 663
- ActiveMQTextMessageMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller, 676
 - activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller, 688
 - activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller, 668
 - activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller, 672
 - activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller, 680
 - activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller, 684
- ActiveMQTopic
 - activemq::commands::ActiveMQTopic, 692
- ActiveMQTopicMarshaller
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller, 716
 - activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller, 696
 - activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller, 700
 - activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller, 712
 - activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller, 720
 - activemq::transport::failover::CloseTransportsTask, 1875
 - activemq::transport::failover::FailoverTransport, 1875
- decaf::util::AbstractCollection, 182
- decaf::util::AbstractQueue, 195
- decaf::util::Collection, 1186
- decaf::util::ListIterator, 2345
- decaf::util::PriorityQueue, 3031
- decaf::util::StlList, 3594
- decaf::util::StlSet, 3625
- decaf::util::AbstractCollection, 182
- decaf::util::AbstractQueue, 195
- decaf::util::List, 2338
- decaf::util::StlList, 3594
- decaf::util::concurrent::atomic::AtomicInteger, 742
- addAsResource
- decaf::internal::net::Network, 2791
- addConsumer
- activemq::state::TransactionState, 3876
- activemq::cmsutil::ResourceLifecycleManager, 3876
- activemq::state::SessionState, 3438
- activemq::cmsutil::ResourceLifecycleManager, 3876
- addDispatcher
- activemq::core::ActiveMQConnection, 278
- addHandler

- decaf::util::logging::Logger, 2389
- additionalPredicate
 - activemq::commands::ConsumerInfo, 1466
- addLogger
 - decaf::util::logging::LogManager, 2409
- addMarshaller
 - activemq::wireformat::openwire::OpenWireFormatz_stream_s, 4062
 - 2890
- addMessageConsumer
 - activemq::cmsutil::ResourceLifecycleManageradvisory
 - 3283
- addMessageProducer
 - activemq::cmsutil::ResourceLifecycleManagerADVISORY_PREFIX
 - 3283
- addNetworkResource
 - decaf::internal::net::Network, 2791
- addProducer
 - activemq::core::ActiveMQConnection, 278
 - activemq::core::ActiveMQSession, 519
 - activemq::state::SessionState, 3438
- addProducerState
 - activemq::state::TransactionState, 3876
- addPropertyChangeListener
 - decaf::util::logging::LogManager, 2409
- addResource
 - decaf::internal::util::ResourceLifecycleManagerafterRollback
 - 3281
- address
 - decaf::net::SocketImpl, 3536
- addressBytes
 - decaf::net::InetAddress, 2022
- addSession
 - activemq::cmsutil::ResourceLifecycleManager,
 - 3283
 - activemq::state::ConnectionState, 1390
- addSynchronization
 - activemq::core::ActiveMQTransactionContextallocate
 - 720
- addTask
 - activemq::threads::CompositeTaskRunner,
 - 1224
- addTempDestination
 - activemq::state::ConnectionState, 1390
- addTransactionState
 - activemq::state::ConnectionState, 1390
- addTransportListener
 - activemq::core::ActiveMQConnection, 278
- addURI
 - activemq::transport::CompositeTransport,
 - 1226
 - activemq::transport::failover::FailoverTransport,
 - 1876
 - activemq::transport::failover::URIPool,
 - 3943
- addURIs
 - activemq::transport::failover::URIPool,
 - 3943
- adjustMinimum
 - decaf::internal::util::TimerTaskHeap, 3805
- adler
 - Adler32
 - decaf::util::zip::Adler32, 723
- activemq::commands::ActiveMQDestination, 331
- ADVISORY_PREFIX
 - activemq::commands::ActiveMQDestination,
 - 331
- after
 - decaf::util::Date, 1666
- afterCommit
 - activemq::core::Synchronization, 3715
- afterMarshal
 - activemq::commands::BaseDataStructure,
 - 831
 - activemq::wireformat::MarshalAware, 2484
- afterMessageIsConsumed
 - activemq::core::ActiveMQConsumer, 313
- afterRollback
 - activemq::core::Synchronization, 3715
- afterUnmarshal
 - activemq::commands::BaseDataStructure,
 - 831
 - activemq::commands::Message, 2520
 - activemq::commands::WireFormatInfo,
 - 3984
 - activemq::wireformat::MarshalAware, 2485
- ALL
 - decaf::util::logging::Level, 2335
- allocate
 - decaf::nio::ByteBuffer, 1036
 - decaf::nio::CharBuffer, 1122
 - decaf::nio::DoubleBuffer, 1811
 - decaf::nio::FloatBuffer, 1927
 - decaf::nio::IntBuffer, 2068
 - decaf::nio::LongBuffer, 2446
 - decaf::nio::ShortBuffer, 3461
- AMQ_CATCH_ALL_THROW_CMSEXCEPTION
 - CMSEExceptionSupport.h, 4224
- AMQ_CATCH_EXCEPTION_CONVERT
 - activemq/exceptions/ExceptionDefines.h,
 - 4170
- AMQ_CATCH_NOTHROW
 - activemq/exceptions/ExceptionDefines.h,
 - 4170
- AMQ_CATCH_RETHROW

- activemq/exceptions/ExceptionDefines.h, 4171
- AMQ_CATCHALL_NOTHROW
 - activemq/exceptions/ExceptionDefines.h, 4171
- AMQ_CATCHALL_THROW
 - activemq/exceptions/ExceptionDefines.h, 4171
- AMQCPP_API
 - activemq/util/Config.h, 4227
- ANY_CHILD
 - activemq::commands::ActiveMQDestination::DestinationFilter, 1726
- ANY_DESCENDENT
 - activemq::commands::ActiveMQDestination::DestinationFilter, 1726
- anyBytes
 - decaf::net::InetAddress, 2022
- append
 - decaf::io::Writer, 4022, 4023
 - decaf::lang::Appendable, 726
 - decaf::nio::CharBuffer, 1123
- AprPool
 - decaf::internal::AprPool, 728
- array
 - decaf::internal::nio::ByteBuffer, 1003
 - decaf::internal::nio::CharArrayBuffer, 1113
 - decaf::internal::nio::DoubleArrayBuffer, 1803
 - decaf::internal::nio::FloatArrayBuffer, 1919
 - decaf::internal::nio::IntArrayBuffer, 2060
 - decaf::internal::nio::LongArrayBuffer, 2438
 - decaf::internal::nio::ShortArrayBuffer, 3453
 - decaf::nio::ByteBuffer, 1037
 - decaf::nio::CharBuffer, 1124
 - decaf::nio::DoubleBuffer, 1812
 - decaf::nio::FloatBuffer, 1927
 - decaf::nio::IntBuffer, 2068
 - decaf::nio::LongBuffer, 2447
 - decaf::nio::ShortBuffer, 3461
- arraycopy
 - decaf::lang::System, 3728, 3729
- arrayOffset
 - decaf::internal::nio::ByteBuffer, 1004
 - decaf::internal::nio::CharArrayBuffer, 1113
 - decaf::internal::nio::DoubleArrayBuffer, 1804
 - decaf::internal::nio::FloatArrayBuffer, 1920
 - decaf::internal::nio::IntArrayBuffer, 2061
 - decaf::internal::nio::LongArrayBuffer, 2439
 - decaf::internal::nio::ShortArrayBuffer, 3454
 - decaf::nio::ByteBuffer, 1037
- decaf::nio::CharBuffer, 1124
- decaf::nio::DoubleBuffer, 1812
- decaf::nio::FloatBuffer, 1928
- decaf::nio::IntBuffer, 2069
- decaf::nio::LongBuffer, 2447
- decaf::nio::ShortBuffer, 3462
- ArrayPointer
 - decaf::lang::ArrayPointer, 732, 733
- arrival
 - activemq::commands::Message, 2532
- asCharBuffer
 - decaf::internal::nio::ByteBuffer, 1004
 - decaf::nio::ByteBuffer, 1037
- asciiToModifiedUtf8
 - activemq/util::MarshallingSupport, 2494
- asDoubleBuffer
 - decaf::internal::nio::ByteBuffer, 1004
 - decaf::nio::ByteBuffer, 1038
- asFloatBuffer
 - decaf::internal::nio::ByteBuffer, 1005
 - decaf::nio::ByteBuffer, 1038
- asIntBuffer
 - decaf::internal::nio::ByteBuffer, 1005
 - decaf::nio::ByteBuffer, 1038
- asLongBuffer
 - decaf::internal::nio::ByteBuffer, 1005
 - decaf::nio::ByteBuffer, 1039
- asReadOnlyBuffer
 - decaf::internal::nio::ByteBuffer, 1006
 - decaf::internal::nio::CharArrayBuffer, 1114
 - decaf::internal::nio::DoubleArrayBuffer, 1804
 - decaf::internal::nio::FloatArrayBuffer, 1920
 - decaf::internal::nio::IntArrayBuffer, 2061
 - decaf::internal::nio::LongArrayBuffer, 2439
 - decaf::internal::nio::ShortArrayBuffer, 3454
 - decaf::nio::ByteBuffer, 1039
 - decaf::nio::CharBuffer, 1125
 - decaf::nio::DoubleBuffer, 1812
 - decaf::nio::FloatBuffer, 1928
 - decaf::nio::IntBuffer, 2069
 - decaf::nio::LongBuffer, 2447
 - decaf::nio::ShortBuffer, 3462
- Assert
 - zutil.h, 4745
- asShortBuffer
 - decaf::internal::nio::ByteBuffer, 1006
 - decaf::nio::ByteBuffer, 1039
- AsyncSignalReadErrorTask
 - activemq::transport::inactivity::InactivityMonitor, 2007
- AsyncWriteTask

- activemq::transport::inactivity::InactivityMonitor, 2007
- atEOF
 - decaf::util::zip::InflaterInputStream, 2041
- AtomicBoolean
 - decaf::util::concurrent::atomic::AtomicBoolean, 738
- AtomicInteger
 - decaf::util::concurrent::atomic::AtomicInteger, 742
- AtomicRefCounter
 - decaf::util::concurrent::atomic::AtomicRefCounter, 747
- AtomicReference
 - decaf::util::concurrent::atomic::AtomicReference, 750
- AUTO_ACKNOWLEDGE
 - cms::Session, 3368
- avail_in
 - z_stream_s, 4062
- avail_out
 - z_stream_s, 4062
- available
 - decaf::internal::io::StandardInputStream, 3582
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2862
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
 - decaf::internal::net::tcp::TcpSocket, 3741
 - decaf::internal::net::tcp::TcpSocketInputStream, 3748
 - decaf::io::BlockingByteArrayInputStream, 840
 - decaf::io::BufferedInputStream, 936
 - decaf::io::ByteArrayInputStream, 1023
 - decaf::io::FilterInputStream, 1896
 - decaf::io::InputStream, 2045
 - decaf::io::PushbackInputStream, 3143
 - decaf::net::SocketImpl, 3531
 - decaf::util::zip::InflaterInputStream, 2038
- availablePermits
 - decaf::util::concurrent::Semaphore, 3345
- availableProcessors
 - decaf::lang::System, 3729
- await
 - decaf::util::concurrent::CountDownLatch, 1522, 1523
 - decaf::util::concurrent::locks::Condition, 1251
- awaitNanos
 - decaf::util::concurrent::locks::Condition, 1252
- awaitTermination
 - decaf::util::concurrent::locks::Condition, 1253
 - decaf::util::concurrent::locks::Condition, 1254
- awaitUninterruptibly
 - decaf::util::concurrent::locks::Condition, 1253
 - decaf::util::concurrent::locks::Condition, 1254
- back
 - decaf::util::StlQueue, 3617
- inflate_state, 2025
- BackupTransport
 - activemq::transport::failover::BackupTransport, 752
 - activemq::transport::failover::BackupTransportPool, 757
- BackupTransportPool
 - activemq::transport::failover::BackupTransportPool, 756
- BAD
 - inflate.h, 4733
- base_dist
 - trees.h, 4736
- base_length
 - trees.h, 4736
- BaseCommand
 - activemq::commands::BaseCommand, 759
- BaseCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller, 780
 - activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller, 801
 - activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller, 766
 - activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaller, 773
 - activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller, 787
 - activemq::wireformat::openwire::marshal::v6::BaseCommandMarshaller, 794
- before
 - decaf::util::Date, 1666
- beforeEnd
 - activemq::core::Synchronization, 3715
- beforeMarshal
 - activemq::commands::ActiveMQMapMessage, 363
 - activemq::commands::ActiveMQTextMessage, 663
 - activemq::commands::BaseDataStructure, 831
 - activemq::commands::Message, 2520

- activemq::commands::WireFormatInfo, 3985
- activemq::wireformat::MarshalAware, 2485
- beforeMessageIsConsumed
- activemq::core::ActiveMQConsumer, 313
- beforeUnmarshal
- activemq::commands::BaseDataStructure, 831
- activemq::wireformat::MarshalAware, 2485
- BEGIN
- activemq::wireformat::stomp::StompCommandConstants, 3631
- begin
- activemq::core::ActiveMQTransactionContext, 720
- BEST_COMPRESSION
- decaf::util::zip::Deflater, 1714
- BEST_SPEED
- decaf::util::zip::Deflater, 1714
- bi_buf
- internal_state, 2120
- bi_valid
- internal_state, 2120
- BIG_STRING_TYPE
- activemq::util::PrimitiveValueNode, 3016
- BINARY_MIME_TYPE
- activemq::commands::ActiveMQBlobMessage, 208
- bind
- decaf::internal::net::tcp::TcpSocket, 3741
- decaf::net::ServerSocket, 3356
- decaf::net::Socket, 3508
- decaf::net::SocketImpl, 3531
- BindException
- decaf::net::BindException, 836, 837
- bitCount
- decaf::lang::Integer, 2080
- decaf::lang::Long, 2423
- bits
- code, 1183
- inflate_state, 2025
- BL_CODES
- deflate.h, 4726
- bl_count
- internal_state, 2120
- bl_desc
- internal_state, 2120
- bl_tree
- internal_state, 2120
- block_start
- internal_state, 2120
- BLOCKED
- decaf::lang::Thread, 3768
- BlockingByteArrayInputStream
- decaf::io::BlockingByteArrayInputStream, 840
- Boolean
- decaf::lang::Boolean, 851
- BOOLEAN_TYPE
- activemq::util::PrimitiveValueNode, 3015
- BooleanExpression
- activemq::commands::BooleanExpression, 855
- BooleanStream
- activemq::wireformat::openwire::utils::BooleanStream, 858
- booleanValue
- decaf::lang::Boolean, 851
- boolValue
- activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
- branchQualifier
- activemq::commands::XATransactionId, 4035
- BrokenBarrierException
- decaf::util::concurrent::BrokenBarrierException, 860, 861
- BrokerError
- activemq::commands::BrokerError, 864
- BrokerException
- activemq::exceptions::BrokerException, 867
- BrokerId
- activemq::commands::BrokerId, 870
- brokerId
- activemq::commands::BrokerInfo, 903
- BrokerIdMarshaller
- activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller, 881
- activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller, 893
- activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller, 873
- activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller, 877
- activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller, 885
- activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller, 889
- BrokerInfo
- activemq::commands::BrokerInfo, 897
- BrokerInfoMarshaller
- activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller, 913
- activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller, 925
- activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller, 905

- activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller, 909
- activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshallerUnderflowException, 957, 958
- activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller, 917
- activemq::transport::mock::ResponseBuilder, 3289
- activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller, 921
- activemq::wireformat::openwire::OpenWireResponseBuilder, 2905
- brokerInTime
 - activemq::commands::Message, 2532
- brokerMasterConnector
 - activemq::commands::ConnectionInfo, 1360
- brokerName
 - activemq::commands::BrokerInfo, 903
 - activemq::commands::DiscoveryEvent, 1761
- brokerOutTime
 - activemq::commands::Message, 2532
- brokerPath
 - activemq::commands::ConnectionInfo, 1360
 - activemq::commands::ConsumerInfo, 1466
 - activemq::commands::DestinationInfo, 1731
 - activemq::commands::Message, 2532
 - activemq::commands::ProducerInfo, 3100
- brokerSequenceId
 - activemq::commands::MessageId, 2667
- brokerUploadUrl
 - activemq::commands::BrokerInfo, 903
- brokerURL
 - activemq::commands::BrokerInfo, 903
- Browser
 - activemq::core::ActiveMQQueueBrowser, 490
- browser
 - activemq::commands::ConsumerInfo, 1466
- buf
 - decaf::util::zip::DeflaterOutputStream, 1719
- buff
 - decaf::util::zip::InflaterInputStream, 2041
- Buffer
 - decaf::nio::Buffer, 930
- buffer
 - decaf::io::DataOutputStream, 1582
- BufferedInputStream
 - decaf::io::BufferedInputStream, 936
- BufferedOutputStream
 - decaf::io::BufferedOutputStream, 940
- BufferOverflowException
 - decaf::nio::BufferOverflowException, 954, 955
- BufferUnderflowException
- buildMessage
 - decaf::lang::Exception, 1834
- buildResponse
 - activemq::transport::mock::ResponseBuilder, 3290
 - activemq::wireformat::openwire::OpenWireResponseBuilder, 2905
- BUSY_STATE
 - deflate.h, 4727
- Byte
 - decaf::lang::Byte, 961
 - zconf.h, 4738
- BYTE_ARRAY_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- BYTE_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- ByteArrayAdapter
 - decaf::internal::util::ByteArrayAdapter, 973–976
- ByteArrayBuffer
 - decaf::internal::nio::ByteArrayBuffer, 1002, 1003
- ByteArrayInputStream
 - decaf::io::ByteArrayInputStream, 1022, 1023
- ByteArrayOutputStream
 - decaf::io::ByteArrayOutputStream, 1028
- byteArrayValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
- ByteBuffer
 - decaf::nio::ByteBuffer, 1036
- Bytef
 - zconf.h, 4738
- BYTES
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- bytesToInt
 - decaf::net::InetAddress, 2018
- byteValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
 - decaf::lang::Byte, 962
 - decaf::lang::Character, 1102
 - decaf::lang::Double, 1790
 - decaf::lang::Float, 1906
 - decaf::lang::Integer, 2080

- decaf::lang::Long, 2423
- decaf::lang::Number, 2835
- decaf::lang::Short, 3442
- CachedConsumer
 - activemq::cmsutil::CachedConsumer, 1072
- CachedProducer
 - activemq::cmsutil::CachedProducer, 1076
- call
 - decaf::util::concurrent::Callable, 1082
- cancel
 - decaf::util::concurrent::Future, 1967
 - decaf::util::Timer, 3792
 - decaf::util::TimerTask, 3802
- CancellationException
 - decaf::util::concurrent::CancellationException, 1083, 1084
- capacity
 - decaf::nio::Buffer, 930
- cause
 - decaf::lang::Exception, 1837
- ceil
 - decaf::lang::Math, 2500
- CertificateEncodingException
 - decaf::security::cert::CertificateEncodingException, 1090, 1091
- CertificateException
 - decaf::security::cert::CertificateException, 1092, 1093
- CertificateExpiredException
 - decaf::security::cert::CertificateExpiredException, 1094, 1095
- CertificateNotYetValidException
 - decaf::security::cert::CertificateNotYetValidException, 1096, 1097
- CertificateParsingException
 - decaf::security::cert::CertificateParsingException, 1098, 1099
- CHAR_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- Character
 - decaf::lang::Character, 1102
- CharArrayBuffer
 - decaf::internal::nio::CharArrayBuffer, 1111, 1112
- charAt
 - decaf::lang::CharSequence, 1135
 - decaf::lang::String, 3666
 - decaf::nio::CharBuffer, 1125
- CharBuffer
 - decaf::nio::CharBuffer, 1122
- charf
 - zconf.h, 4738
- charValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
- CHECK
 - inflate.h, 4733
- check
 - inflate_state, 2025
- checkClosed
 - decaf::io::InputStreamReader, 2054
 - decaf::io::OutputStreamWriter, 2916
 - decaf::net::ServerSocket, 3357
 - decaf::net::Socket, 3509
- checkConnectionFactory
 - activemq::cmsutil::CmsAccessor, 1154
- checkDestinationResolver
 - activemq::cmsutil::CmsDestinationAccessor, 1158
- CheckedInputStream
 - decaf::util::zip::CheckedInputStream, 1138
- CheckedOutputStream
 - decaf::util::zip::CheckedOutputStream, 1140
- checkMapIsUnmarshalled
 - activemq::commands::ActiveMQMapMessage, 363
- checkResult
 - decaf::internal::net::tcp::TcpSocket, 3741
- checkShutdown
 - activemq::state::ConnectionState, 1390
 - activemq::state::SessionState, 3438
 - activemq::state::TransactionState, 3876
- checkValidity
 - decaf::security::cert::X509Certificate, 4029
- ClassCastException
 - decaf::lang::exceptions::ClassCastException, 1145, 1146
- ClassName
 - activemq::commands::BrokerError::StackTraceElement, 3578
- cleanup
 - decaf::internal::AprPool, 728
- clear
 - activemq::core::ActiveMQSessionExecutor, 534
 - activemq::core::MessageDispatchChannel, 2600
 - activemq::util::ActiveMQProperties, 479
 - activemq::util::PrimitiveValueNode, 3018
 - activemq::wireformat::openwire::utils::BooleanStream, 858
 - cms::CMSProperties, 1166
 - decaf::internal::util::ByteArrayAdapter, 976
 - decaf::nio::Buffer, 930
 - decaf::util::AbstractCollection, 183

- decaf::util::AbstractQueue, 196
- decaf::util::Collection, 1187
- decaf::util::concurrent::ConcurrentStlMap, 1237
- decaf::util::concurrent::SynchronousQueue, 3718
- decaf::util::Map, 2460
- decaf::util::PriorityQueue, 3031
- decaf::util::Properties, 3128
- decaf::util::StlList, 3596
- decaf::util::StlMap, 3606
- decaf::util::StlQueue, 3617
- decaf::util::StlSet, 3626
- clearBody
 - activemq::commands::ActiveMQBytesMessage, 236
 - activemq::commands::ActiveMQMapMessage, 363
 - activemq::commands::ActiveMQMessageTemplate, 428
 - activemq::commands::ActiveMQStreamMessage, 540
 - activemq::commands::ActiveMQTextMessage, 663
 - cms::Message, 2538
- clearMessagesInProgress
 - activemq::core::ActiveMQConsumer, 313
 - activemq::core::ActiveMQSession, 519
 - activemq::core::ActiveMQSessionExecutor, 534
- clearProperties
 - activemq::commands::ActiveMQMessageTemplate, 429
 - cms::Message, 2539
- clearProperty
 - decaf::lang::System, 3729
- CLIENT_ACKNOWLEDGE
 - cms::Session, 3368
- clientId
 - activemq::commands::ConnectionInfo, 1360
 - activemq::commands::JournalTopicAck, 2187
 - activemq::commands::RemoveSubscriptionInfo, 3226
 - activemq::commands::SubscriptionInfo, 3675
- clientMaster
 - activemq::commands::ConnectionInfo, 1360
- clockSequence
 - decaf::util::UUID, 3971
- clone
 - activemq::commands::ActiveMQBlobMessage, 205
 - activemq::commands::ActiveMQBytesMessage, 236
 - activemq::commands::ActiveMQMapMessage, 363
 - activemq::commands::ActiveMQMessage, 398
 - activemq::commands::ActiveMQObjectMessage, 444
 - activemq::commands::ActiveMQQueue, 484
 - activemq::commands::ActiveMQStreamMessage, 540
 - activemq::commands::ActiveMQTempQueue, 605
 - activemq::commands::ActiveMQTempTopic, 634
 - activemq::commands::ActiveMQTextMessage, 663
 - activemq::commands::ActiveMQTopic, 692
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
 - activemq::core::PrefetchPolicy, 2977
 - activemq::core::RedeliveryPolicy, 3178
 - activemq::exceptions::ActiveMQException, 358
 - activemq::exceptions::BrokerException, 867
 - activemq::util::ActiveMQProperties, 479
 - activemq::wireformat::stomp::StompFrame, 3634
 - cms::BytesMessage, 1059
 - cms::CMSProperties, 1166
 - cms::Destination, 1724
 - cms::Message, 2539
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2845
 - decaf::internal::net::ssl::openssl::OpenSSLSocketException, 2873
 - decaf::io::EOFException, 1827
 - decaf::io::InterruptedIOException, 2129
 - decaf::io::IOException, 2144
 - decaf::io::UnsupportedEncodingException, 3915
 - decaf::io::UTFDataFormatException, 3968
 - decaf::lang::ArrayPointer, 733
 - decaf::lang::Exception, 1834
 - decaf::lang::exceptions::ClassCastException, 1147
 - decaf::lang::exceptions::IllegalArgument Exception, 1993

- decaf::lang::exceptions::IllegalMonitorStateException, 1996
- decaf::lang::exceptions::IllegalStateException, 2000
- decaf::lang::exceptions::IllegalThreadStateException, 2003
- decaf::lang::exceptions::IndexOutOfBoundsException, 2010
- decaf::lang::exceptions::InterruptedException, 2126
- decaf::lang::exceptions::InvalidStateException, 2141
- decaf::lang::exceptions::NoSuchElementException, 2828
- decaf::lang::exceptions::NullPointerException, 2834
- decaf::lang::exceptions::NumberFormatException, 2840
- decaf::lang::exceptions::RuntimeException, 3330
- decaf::lang::exceptions::UnsupportedOperationException, 3918
- decaf::lang::Throwable, 3784
- decaf::net::BindException, 838
- decaf::net::ConnectException, 1261
- decaf::net::HttpRetryException, 1988
- decaf::net::MalformedURLException, 2458
- decaf::net::NoRouteToHostException, 2822
- decaf::net::PortUnreachableException, 2975
- decaf::net::ProtocolException, 3139
- decaf::net::SocketException, 3522
- decaf::net::SocketTimeoutException, 3544
- decaf::net::UnknownHostException, 3909
- decaf::net::UnknownServiceException, 3912
- decaf::net::URISyntaxException, 3950
- decaf::nio::BufferOverflowException, 956
- decaf::nio::BufferUnderflowException, 959
- decaf::nio::InvalidMarkException, 2137
- decaf::nio::ReadOnlyBufferException, 3171
- decaf::security::cert::CertificateEncodingException, 1091
- decaf::security::cert::CertificateException, 1093
- decaf::security::cert::CertificateExpiredException, 1095
- decaf::security::cert::CertificateNotYetValidException, 1097
- decaf::security::cert::CertificateParsingException, 1099
- decaf::security::GeneralSecurityException, 1973
- decaf::security::InvalidKeyException, 2134
- decaf::security::KeyException, 2297
- decaf::security::KeyManagementException, 2300
- decaf::security::NoSuchAlgorithmException, 2825
- decaf::security::NoSuchProviderException, 2831
- decaf::security::SignatureException, 3499
- decaf::util::concurrent::BrokenBarrierException, 862
- decaf::util::concurrent::CancellationException, 1085
- decaf::util::concurrent::ExecutionException, 1868
- decaf::util::concurrent::RejectedExecutionException, 3191
- decaf::util::concurrent::TimeoutException, 3789
- decaf::util::Properties, 3128
- decaf::util::zip::DataFormatException, 4057
- decaf::util::zip::ZipException, 4066
- cloneDataStructure
 - activemq::commands::ActiveMQBlobMessage, 205
 - activemq::commands::ActiveMQBytesMessage, 236
 - activemq::commands::ActiveMQDestination, 324
 - activemq::commands::ActiveMQMapMessage, 363
 - activemq::commands::ActiveMQMessage, 399
 - activemq::commands::ActiveMQObjectMessage, 444
 - activemq::commands::ActiveMQQueue, 484
 - activemq::commands::ActiveMQStreamMessage, 540
 - activemq::commands::ActiveMQTempDestination, 577
 - activemq::commands::ActiveMQTempQueue, 605
 - activemq::commands::ActiveMQTempTopic, 634
 - activemq::commands::ActiveMQTextMessage, 664
 - activemq::commands::ActiveMQTopic, 692
 - activemq::commands::BooleanExpression, 855
 - activemq::commands::BrokerError, 864
 - activemq::commands::BrokerId, 870
 - activemq::commands::BrokerInfo, 897

- activemq::commands::ConnectionControl, 1268
- activemq::commands::ConnectionError, 1297
- activemq::commands::ConnectionId, 1328
- activemq::commands::ConnectionInfo, 1356
- activemq::commands::ConsumerControl, 1402
- activemq::commands::ConsumerId, 1431
- activemq::commands::ConsumerInfo, 1461
- activemq::commands::ControlCommand, 1494
- activemq::commands::DataArrayResponse, 1529
- activemq::commands::DataResponse, 1584
- activemq::commands::DataStructure, 1660
- activemq::commands::DestinationInfo, 1728
- activemq::commands::DiscoveryEvent, 1759
- activemq::commands::ExceptionResponse, 1840
- activemq::commands::FlushCommand, 1938
- activemq::commands::IntegerResponse, 2092
- activemq::commands::JournalQueueAck, 2157
- activemq::commands::JournalTopicAck, 2184
- activemq::commands::JournalTrace, 2213
- activemq::commands::JournalTransaction, 2240
- activemq::commands::KeepAliveInfo, 2267
- activemq::commands::LastPartialCommand, 2301
- activemq::commands::LocalTransactionId, 2348
- activemq::commands::Message, 2520
- activemq::commands::MessageAck, 2560
- activemq::commands::MessageDispatch, 2595
- activemq::commands::MessageDispatchNotification, 2631
- activemq::commands::MessageId, 2664
- activemq::commands::MessagePull, 2740
- activemq::commands::NetworkBridgeFilter, 2794
- activemq::commands::PartialCommand, 2919
- activemq::commands::ProducerAck, 3037
- activemq::commands::ProducerId, 3068
- activemq::commands::ProducerInfo, 3097
- activemq::commands::RemoveInfo, 3195
- activemq::commands::RemoveSubscriptionInfo, 3223
- activemq::commands::ReplayCommand, 3252
- activemq::commands::Response, 3286
- activemq::commands::SessionId, 3380
- activemq::commands::SessionInfo, 3408
- activemq::commands::ShutdownInfo, 3471
- activemq::commands::SubscriptionInfo, 3672
- activemq::commands::TransactionId, 3820
- activemq::commands::TransactionInfo, 3848
- activemq::commands::WireFormatInfo, 3985
- activemq::commands::XATransactionId, 4032
- close
 - activemq::cmsutil::CachedConsumer, 1072
 - activemq::cmsutil::CachedProducer, 1076
 - activemq::cmsutil::PooledSession, 2957
 - activemq::commands::ActiveMQTempDestination, 577
 - activemq::commands::ConnectionControl, 1271
 - activemq::commands::ConsumerControl, 1405
 - activemq::core::ActiveMQConnection, 279
 - activemq::core::ActiveMQConsumer, 313
 - activemq::core::ActiveMQProducer, 472
 - activemq::core::ActiveMQQueueBrowser, 488
 - activemq::core::ActiveMQSession, 520
 - activemq::core::ActiveMQSessionExecutor, 534
 - activemq::core::MessageDispatchChannel, 2600
 - activemq::transport::correlator::ResponseCorrelator, 3292
 - activemq::transport::failover::FailoverTransport, 1876
 - activemq::transport::inactivity::InactivityMonitor, 2005
 - activemq::transport::IOTransport, 2147
 - activemq::transport::mock::MockTransport, 2770
 - activemq::transport::tcp::TcpTransport, 3753
 - activemq::transport::TransportFilter, 3893
 - activemq::wireformat::openwire::OpenWireFormatNegotiator, 2902
- cms::Closeable, 1148
- cms::Connection, 1263

- cms::Session, 3368
- decaf::internal::io::StandardErrorOutputStream, 3580
- decaf::internal::io::StandardOutputStream, 3584
- decaf::internal::net::ssl::openssl::OpenSSLSocket, 2863
- decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
- decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream, 2886
- decaf::internal::net::tcp::TcpSocket, 3742
- decaf::internal::net::tcp::TcpSocketInputStream, 3748
- decaf::internal::net::tcp::TcpSocketOutputStream, 3751
- decaf::io::BlockingByteArrayInputStream, 841
- decaf::io::BufferedInputStream, 937
- decaf::io::Closeable, 1149
- decaf::io::FilterInputStream, 1896
- decaf::io::FilterOutputStream, 1901
- decaf::io::InputStream, 2045
- decaf::io::InputStreamReader, 2054
- decaf::io::OutputStream, 2909
- decaf::io::OutputStreamWriter, 2916
- decaf::net::ServerSocket, 3357
- decaf::net::Socket, 3509
- decaf::net::SocketImpl, 3532
- decaf::util::logging::ConsoleHandler, 1399
- decaf::util::logging::StreamHandler, 3650
- decaf::util::zip::DeflaterOutputStream, 1718
- decaf::util::zip::InflaterInputStream, 2039
- CLOSE_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- closed
 - decaf::io::FilterInputStream, 1899
 - decaf::io::FilterOutputStream, 1903
- CloseTransportsTask
 - activemq::transport::failover::CloseTransportsTask, 1151
- cluster
 - activemq::commands::Message, 2532
- cms, 140
- cms/Config.h
 - CMS_API, 4228
- cms::BytesMessage, 1056
 - ~BytesMessage, 1059
 - clone, 1059
 - getBodyBytes, 1059
 - getBodyLength, 1060
 - readBoolean, 1060
 - readByte, 1060
 - readBytes, 1061
 - readChar, 1062
 - readDouble, 1062
 - readFloat, 1062
 - readInt, 1063
 - readLong, 1063
 - readShort, 1063
 - readString, 1064
 - readUnsignedShort, 1064
 - readUTF, 1065
 - reset, 1065
 - setBodyBytes, 1065
 - writeBoolean, 1065
 - writeByte, 1066
 - writeBytes, 1066
 - writeChar, 1067
 - writeDouble, 1067
 - writeFloat, 1067
 - writeInt, 1068
 - writeLong, 1068
 - writeShort, 1068
 - writeString, 1069
 - writeUnsignedShort, 1069
 - writeUTF, 1069
- cms::Closeable, 1148
 - ~Closeable, 1148
 - close, 1148
- cms::CMSException, 1160
 - ~CMSException, 1161
 - CMSException, 1161
 - getCause, 1161
 - getMessage, 1161
 - getStackTrace, 1161
 - getStackTraceString, 1162
 - printStackTrace, 1162
 - setMark, 1162
 - what, 1162
- cms::CMSProperties, 1165
 - ~CMSProperties, 1166
 - clear, 1166
 - clone, 1166
 - copy, 1166
 - getProperty, 1166
 - hasProperty, 1167
 - isEmpty, 1167
 - remove, 1167
 - setProperty, 1167
 - toArray, 1168
 - toString, 1168
- cms::CMSSecurityException, 1169
 - ~CMSSecurityException, 1169
 - CMSSecurityException, 1169
- cms::Connection, 1262
 - ~Connection, 1263

- close, 1263
- createSession, 1263, 1264
- getClientID, 1264
- getExceptionListener, 1264
- getMetaData, 1264
- setClientID, 1265
- setExceptionListener, 1265
- cms::ConnectionFactory, 1324
 - ~ConnectionFactory, 1325
 - createCMSConnectionFactory, 1325
 - createConnection, 1325, 1326
- cms::ConnectionMetaData, 1385
 - ~ConnectionMetaData, 1386
 - getCMSMajorVersion, 1386
 - getCMSMinorVersion, 1386
 - getCMSProviderName, 1386
 - getCMSVersion, 1386
 - getCMSXPropertyNames, 1387
 - getProviderMajorVersion, 1387
 - getProviderMinorVersion, 1387
 - getProviderVersion, 1388
- cms::DeliveryMode, 1721
 - ~DeliveryMode, 1722
 - DELIVERY_MODE, 1721
 - NON_PERSISTENT, 1721
 - PERSISTENT, 1721
- cms::Destination, 1723
 - ~Destination, 1724
 - clone, 1724
 - copy, 1724
 - DestinationType, 1723
 - getCMSProperties, 1724
 - getDestinationType, 1724
 - QUEUE, 1723
 - TEMPORARY_QUEUE, 1723
 - TEMPORARY_TOPIC, 1723
 - TOPIC, 1723
- cms::ExceptionListener, 1838
 - ~ExceptionListener, 1838
 - onException, 1838
- cms::IllegalStateException, 1997
 - ~IllegalStateException, 1997
 - IllegalStateException, 1997
- cms::InvalidClientIdException, 2130
 - ~InvalidClientIdException, 2130
 - InvalidClientIdException, 2130
- cms::InvalidDestinationException, 2131
 - ~InvalidDestinationException, 2131
 - InvalidDestinationException, 2131
- cms::InvalidSelectorException, 2138
 - ~InvalidSelectorException, 2138
 - InvalidSelectorException, 2138
- cms::MapMessage, 2472
 - ~MapMessage, 2474
 - getBoolean, 2474
 - getByte, 2474
 - getBytes, 2475
 - getChar, 2475
 - getDouble, 2475
 - getFloat, 2476
 - getInt, 2476
 - getLong, 2476
 - getMapNames, 2477
 - getShort, 2477
 - getString, 2477
 - itemExists, 2478
 - setBoolean, 2478
 - setByte, 2478
 - setBytes, 2479
 - setChar, 2479
 - setDouble, 2479
 - setFloat, 2480
 - setInt, 2480
 - setLong, 2480
 - setShort, 2481
 - setString, 2481
- cms::Message, 2534
 - ~Message, 2538
 - acknowledge, 2538
 - clearBody, 2538
 - clearProperties, 2539
 - clone, 2539
 - getBooleanProperty, 2540
 - getByteProperty, 2540
 - getCMSCorrelationID, 2540
 - getCMSDeliveryMode, 2541
 - getCMSDestination, 2541
 - getCMSExpiration, 2542
 - getCMSMessageID, 2542
 - getCMSPriority, 2543
 - getCMSRedelivered, 2543
 - getCMSReplyTo, 2544
 - getCMSTimestamp, 2544
 - getCMSType, 2545
 - getDoubleProperty, 2545
 - getFloatProperty, 2546
 - getIntProperty, 2546
 - getLongProperty, 2547
 - getPropertyNames, 2547
 - getShortProperty, 2548
 - getStringProperty, 2548
 - propertyExists, 2549
 - setBooleanProperty, 2549
 - setByteProperty, 2550
 - setCMSCorrelationID, 2550
 - setCMSDeliveryMode, 2551
 - setCMSDestination, 2551
 - setCMSExpiration, 2552

- setCMSMessageID, 2552
- setCMSPriority, 2552
- setCMSRedelivered, 2553
- setCMSReplyTo, 2553
- setCMSTimestamp, 2554
- setCMSType, 2554
- setDoubleProperty, 2555
- setFloatProperty, 2555
- setIntProperty, 2556
- setLongProperty, 2556
- setShortProperty, 2557
- setStringProperty, 2557
- cms::MessageConsumer, 2589
 - ~MessageConsumer, 2590
 - getMessageListener, 2590
 - getMessageSelector, 2590
 - receive, 2590, 2591
 - receiveNoWait, 2591
 - setMessageListener, 2591
- cms::MessageEnumeration, 2659
 - ~MessageEnumeration, 2659
 - hasMoreMessages, 2659
 - nextMessage, 2659
- cms::MessageEOFException, 2661
 - ~MessageEOFException, 2661
 - MessageEOFException, 2661
- cms::MessageFormatException, 2662
 - ~MessageFormatException, 2662
 - MessageFormatException, 2662
- cms::MessageListener, 2692
 - ~MessageListener, 2692
 - onMessage, 2692
- cms::MessageNotReadableException, 2723
 - ~MessageNotReadableException, 2723
 - MessageNotReadableException, 2723
- cms::MessageNotWriteableException, 2724
 - ~MessageNotWriteableException, 2724
 - MessageNotWriteableException, 2724
- cms::MessageProducer, 2725
 - ~MessageProducer, 2726
 - getDeliveryMode, 2726
 - getDisableMessageID, 2727
 - getDisableMessageTimeStamp, 2727
 - getPriority, 2727
 - getTimeToLive, 2727
 - send, 2728, 2729
 - setDeliveryMode, 2730
 - setDisableMessageID, 2730
 - setDisableMessageTimeStamp, 2730
 - setPriority, 2731
 - setTimeToLive, 2731
- cms::ObjectMessage, 2841
 - ~ObjectMessage, 2841
- cms::Queue, 3148
 - ~Queue, 3148
 - getQueueName, 3148
- cms::QueueBrowser, 3153
 - ~QueueBrowser, 3153
 - getEnumeration, 3153
 - getMessageSelector, 3154
 - getQueue, 3154
- cms::Session, 3365
 - ~Session, 3368
 - AcknowledgeMode, 3368
 - AUTO_ACKNOWLEDGE, 3368
 - CLIENT_ACKNOWLEDGE, 3368
 - close, 3368
 - commit, 3369
 - createBrowser, 3369
 - createBytesMessage, 3370
 - createConsumer, 3370, 3371
 - createDurableConsumer, 3371
 - createMapMessage, 3372
 - createMessage, 3372
 - createProducer, 3372
 - createQueue, 3373
 - createStreamMessage, 3373
 - createTemporaryQueue, 3373
 - createTemporaryTopic, 3374
 - createTextMessage, 3374
 - createTopic, 3374
 - DUPS_OK_ACKNOWLEDGE, 3368
 - getAcknowledgeMode, 3375
 - INDIVIDUAL_ACKNOWLEDGE, 3368
 - isTransacted, 3375
 - recover, 3375
 - rollback, 3376
 - SESSION_TRANSACTED, 3368
 - unsubscribe, 3376
- cms::Startable, 3586
 - ~Startable, 3586
 - start, 3586
- cms::Stoppable, 3648
 - ~Stoppable, 3648
 - stop, 3648
- cms::StreamMessage, 3652
 - ~StreamMessage, 3655
 - readBoolean, 3655
 - readByte, 3655
 - readBytes, 3655, 3656
 - readChar, 3657
 - readDouble, 3657
 - readFloat, 3657
 - readInt, 3658
 - readLong, 3658
 - readShort, 3659
 - readString, 3659
 - readUnsignedShort, 3659

- writeBoolean, 3660
- writeByte, 3660
- writeBytes, 3661
- writeChar, 3661
- writeDouble, 3662
- writeFloat, 3662
- writeInt, 3662
- writeLong, 3663
- writeShort, 3663
- writeString, 3663
- writeUnsignedShort, 3664
- cms::TemporaryQueue, 3759
 - ~TemporaryQueue, 3759
 - destroy, 3759
 - getQueueName, 3759
- cms::TemporaryTopic, 3761
 - ~TemporaryTopic, 3761
 - destroy, 3761
 - getTopicName, 3761
- cms::TextMessage, 3763
 - ~TextMessage, 3763
 - getText, 3763
 - setText, 3764
- cms::Topic, 3817
 - ~Topic, 3817
 - getTopicName, 3817
- cms::UnsupportedOperationException, 3919
 - ~UnsupportedOperationException, 3919
 - UnsupportedOperationException, 3919
- CMS_API
 - cms/Config.h, 4228
- CmsAccessor
 - activemq::cmsutil::CmsAccessor, 1154
- CmsDestinationAccessor
 - activemq::cmsutil::CmsDestinationAccessor, 1158
- CMSException
 - cms::CMSException, 1161
- CMSExceptionSupport.h
 - AMQ_CATCH_ALL_THROW_-CMSEXCEPTION, 4224
- CMSSecurityException
 - cms::CMSSecurityException, 1169
- CmsTemplate
 - activemq::cmsutil::CmsTemplate, 1173
- Code
 - deflate.h, 4727
- code, 1183
 - bits, 1183
 - ct_data_s, 1527
 - op, 1183
 - val, 1183
- CODELENS
 - inflate.h, 4733
- CODES
 - inftrees.h, 4734
- codes
 - inflate_state, 2025
- codetype
 - inftrees.h, 4734
- comm_max
 - gz_header_s, 1975
- command
 - activemq::commands::ControlCommand, 1496
- commandId
 - activemq::commands::PartialCommand, 2921
- COMMENT
 - inflate.h, 4732
- comment
 - gz_header_s, 1975
- COMMENT_STATE
 - deflate.h, 4727
- COMMIT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- commit
 - activemq::cmsutil::PooledSession, 2958
 - activemq::core::ActiveMQConsumer, 313
 - activemq::core::ActiveMQSession, 520
 - activemq::core::ActiveMQTransactionContext, 720
 - cms::Session, 3369
- compact
 - decaf::internal::nio::ByteBuffer, 1007
 - decaf::internal::nio::CharArrayBuffer, 1114
 - decaf::internal::nio::DoubleArrayBuffer, 1804
 - decaf::internal::nio::FloatArrayBuffer, 1920
 - decaf::internal::nio::IntArrayBuffer, 2061
 - decaf::internal::nio::LongArrayBuffer, 2439
 - decaf::internal::nio::ShortArrayBuffer, 3454
 - decaf::nio::ByteBuffer, 1040
 - decaf::nio::CharBuffer, 1125
 - decaf::nio::DoubleBuffer, 1813
 - decaf::nio::FloatBuffer, 1929
 - decaf::nio::IntBuffer, 2070
 - decaf::nio::LongBuffer, 2448
 - decaf::nio::ShortBuffer, 3463
- COMPARATOR
 - activemq::commands::BrokerId, 870
 - activemq::commands::ConnectionId, 1328
 - activemq::commands::ConsumerId, 1431
 - activemq::commands::LocalTransactionId, 2348
 - activemq::commands::MessageId, 2664

- activemq::commands::ProducerId, 3068
- activemq::commands::SessionId, 3380
- activemq::commands::TransactionId, 3819
- activemq::commands::XATransactionId, 4032
- comparator
 - decaf::util::PriorityQueue, 3031
- compare
 - activemq::util::IdGenerator, 1989
 - decaf::lang::ArrayPointerComparator, 737
 - decaf::lang::Double, 1790
 - decaf::lang::Float, 1906
 - decaf::lang::PointerComparator, 2954
 - decaf::util::Comparator, 1217
 - decaf::util::comparators::Less, 2328
- compareAndSet
 - decaf::util::concurrent::atomic::AtomicBoolean, 739
 - decaf::util::concurrent::atomic::AtomicInteger, 743
 - decaf::util::concurrent::atomic::AtomicReference, 750
- compareTo
 - activemq::commands::BrokerId, 870
 - activemq::commands::ConnectionId, 1328
 - activemq::commands::ConsumerId, 1431
 - activemq::commands::LocalTransactionId, 2348
 - activemq::commands::MessageId, 2664
 - activemq::commands::ProducerId, 3068
 - activemq::commands::SessionId, 3380
 - activemq::commands::TransactionId, 3820
 - activemq::commands::XATransactionId, 4032
 - decaf::lang::Boolean, 851
 - decaf::lang::Byte, 962
 - decaf::lang::Character, 1102
 - decaf::lang::Comparable, 1214
 - decaf::lang::Double, 1791
 - decaf::lang::Float, 1907
 - decaf::lang::Integer, 2080
 - decaf::lang::Long, 2423
 - decaf::lang::Short, 3442
 - decaf::net::URI, 3925
 - decaf::nio::ByteBuffer, 1040
 - decaf::nio::CharBuffer, 1126
 - decaf::nio::DoubleBuffer, 1813
 - decaf::nio::FloatBuffer, 1929
 - decaf::nio::IntBuffer, 2070
 - decaf::nio::LongBuffer, 2448
 - decaf::nio::ShortBuffer, 3463
 - decaf::util::concurrent::TimeUnit, 3809
 - decaf::util::Date, 1667
 - decaf::util::logging::Level, 2334
 - decaf::util::UUID, 3971
- COMPOSITE_SEPARATOR
 - activemq::commands::ActiveMQDestination, 331
- CompositeData
 - activemq::util::CompositeData, 1220
- CompositeTaskRunner
 - activemq::threads::CompositeTaskRunner, 1224
- compressed
 - activemq::commands::Message, 2532
- Concurrent.h
 - synchronized, 4893
 - WAIT_INFINITE, 4893
- ConcurrentStlMap
 - decaf::util::concurrent::ConcurrentStlMap, 1237
- condition
 - decaf::util::concurrent::ConditionHandle, 1255
- ConditionHandle
 - decaf::util::concurrent::ConditionHandle, 1255
- CONFIG
 - decaf::util::logging::Level, 2335
- config
 - decaf::util::logging::Logger, 2389
- configure
 - activemq::core::PrefetchPolicy, 2977
 - activemq::core::RedeliveryPolicy, 3178
 - activemq::wireformat::openwire::marshal::v1::MarshallerFactory, 2491
 - activemq::wireformat::openwire::marshal::v2::MarshallerFactory, 2492
 - activemq::wireformat::openwire::marshal::v3::MarshallerFactory, 2488
 - activemq::wireformat::openwire::marshal::v4::MarshallerFactory, 2489
 - activemq::wireformat::openwire::marshal::v5::MarshallerFactory, 2490
 - activemq::wireformat::openwire::marshal::v6::MarshallerFactory, 2487
- configureSocket
 - activemq::transport::tcp::SslTransport, 3575
 - activemq::transport::tcp::TcpTransport, 3753
- CONNECT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- connect
 - activemq::transport::tcp::TcpTransport, 3753

- decaf::internal::net::ssl::openssl::OpenSSLSocket, 2863
- decaf::internal::net::tcp::TcpSocket, 3742
- decaf::net::Socket, 3509
- decaf::net::SocketImpl, 3532
- CONNECTED
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- connectedBrokers
 - activemq::commands::ConnectionControl, 1271
- ConnectException
 - decaf::net::ConnectException, 1259, 1260
- connection
 - activemq::commands::ActiveMQTempDestination, 579
 - activemq::commands::Message, 2532
- CONNECTION_ADVISORY_PREFIX
 - activemq::commands::ActiveMQDestination, 331
- CONNECTION_ALWAYS_SYNC_SEND
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_CLOSE_TIMEOUT
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_DISPATCH_ASYNC
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_PRODUCER_WINDOW_SIZE
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_SEND_TIMEOUT
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_USE_ASYNC_SEND
 - activemq::core::ActiveMQConstants, 309
- CONNECTION_USE_COMPRESSION
 - activemq::core::ActiveMQConstants, 309
- ConnectionControl
 - activemq::commands::ConnectionControl, 1268
- ConnectionControlMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller, 1281
 - activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller, 1293
 - activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller, 1273
 - activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller, 1277
 - activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller, 1285
 - activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller, 1289
- ConnectionError
 - activemq::commands::ConnectionError, 1297
- ConnectionErrorMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller, 1313
 - activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller, 1301
 - activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller, 1305
 - activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller, 1309
 - activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller, 1317
 - activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller, 1321
- ConnectionId
 - activemq::commands::ConnectionId, 1328
- ConnectionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller, 1344
 - activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller, 1332
 - activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller, 1336
 - activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller, 1340
 - activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller, 1348
 - activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller, 1352
- ConnectionInfo
 - activemq::commands::BrokerInfo, 903
 - activemq::commands::ConnectionError, 1299
 - activemq::commands::ConnectionInfo, 1360
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::DestinationInfo, 1731
 - activemq::commands::LocalTransactionId, 2350
 - activemq::commands::ProducerId, 3070
 - activemq::commands::RemoveSubscriptionInfo, 3226
 - activemq::commands::SessionId, 3382
 - activemq::commands::TransactionInfo, 3850
- ConnectionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller, 1374
 - activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller, 1362
 - activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller, 1366

- activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller, ConsumerId, 1431
1370 consumerId
- activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller, ConsumerControl,
1378 1405
- activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller, ConsumerInfo, 1466
1382 activemq::commands::MessageAck, 2564
- connectionInterruptProcessingComplete
activemq::state::ConnectionStateTracker,
1394 2598
- ConnectionState
activemq::state::ConnectionState, 1390
- ConnectionStateTracker
activemq::state::ConnectionStateTracker,
1394 2634
- ConsoleHandler
decaf::util::logging::ConsoleHandler, 1399
- const
zconf.h, 4738
- ConstReferenceType
decaf::lang::ArrayPointer, 732
- CONSUMER_ADVISORY_PREFIX
activemq::commands::ActiveMQDestination,
331 2743
- CONSUMER_DISPATCHASYNC
activemq::core::ActiveMQConstants, 308
- CONSUMER_EXCLUSIVE
activemq::core::ActiveMQConstants, 308
- CONSUMER_NOLOCAL
activemq::core::ActiveMQConstants, 308
- CONSUMER_PREFETCHSIZE
activemq::core::ActiveMQConstants, 308
- CONSUMER_PRIORITY
activemq::core::ActiveMQConstants, 308
- CONSUMER_RETROACTIVE
activemq::core::ActiveMQConstants, 308
- CONSUMER_SELECTOR
activemq::core::ActiveMQConstants, 308
- ConsumerControl
activemq::commands::ConsumerControl,
1402
- ConsumerControlMarshaller
activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller,
1419 decaf::util::AbstractCollection, 184
- activemq::wireformat::openwire::marshal::v2::ConsumerControlMarshaller, 188
1407 decaf::util::concurrent::SynchronousQueue,
3718
- activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller,
1411 decaf::util::StlList, 3596
- activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller, 3626,
1415 containsAll
- activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller, 184
1423 decaf::util::Collection, 1189
- activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller, SynchronousQueue,
1427 3719
- ConsumerId
containsKey
- ConsumerInfo
activemq::commands::ConsumerInfo, 1461
- ConsumerInfoMarshaller
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller,
1481
- activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller,
1469
- activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller,
1473
- activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller,
1477
- activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller,
1485
- activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller,
1489
- ConsumerState
activemq::state::ConsumerState, 1492
- ConsumerStateMarshaller
decaf::util::AbstractCollection, 184
- decaf::util::concurrent::SynchronousQueue,
3718
- decaf::util::StlList, 3596
- decaf::util::Collection, 1189
- decaf::util::SynchronousQueue,
3719
- containsKey

- decaf::util::concurrent::ConcurrentStlMap, 1238
- decaf::util::Map, 2461
- decaf::util::StlMap, 3606
- containsValue
 - decaf::util::concurrent::ConcurrentStlMap, 1238
 - decaf::util::Map, 2462
 - decaf::util::StlMap, 3607
- content
 - activemq::commands::Message, 2532
- ControlCommand
 - activemq::commands::ControlCommand, 1494
- ControlCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller, 1510
 - activemq::wireformat::openwire::marshal::v2::ControlCommandMarshaller, 1498
 - activemq::wireformat::openwire::marshal::v3::ControlCommandMarshaller, 1502
 - activemq::wireformat::openwire::marshal::v4::ControlCommandMarshaller, 1506
 - activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller, 1514
 - activemq::wireformat::openwire::marshal::v6::ControlCommandMarshaller, 1518
- convert
 - activemq::util::PrimitiveValueConverter, 3010
 - decaf::util::concurrent::TimeUnit, 3810
- convertConsumerId
 - activemq::wireformat::stomp::StompHelper, 3639
- convertDestination
 - activemq::wireformat::stomp::StompHelper, 3639, 3640
- convertMessageId
 - activemq::wireformat::stomp::StompHelper, 3640
- convertProducerId
 - activemq::wireformat::stomp::StompHelper, 3640, 3641
- convertProperties
 - activemq::wireformat::stomp::StompHelper, 3641
- convertToCMSException
 - activemq::exceptions::ActiveMQException, 358
- convertTransactionId
 - activemq::wireformat::stomp::StompHelper, 3641, 3642
- COPY
 - gzguts.h, 4729
 - inflate.h, 4733
- copy
 - activemq::commands::ActiveMQQueue, 484
 - activemq::commands::ActiveMQTempQueue, 605
 - activemq::commands::ActiveMQTempTopic, 634
 - activemq::commands::ActiveMQTopic, 692
 - activemq::util::ActiveMQProperties, 479
 - activemq::wireformat::stomp::StompFrame, 3634
 - cms::CMSProperties, 1166
 - cms::Destination, 1724
 - decaf::util::AbstractCollection, 185
 - decaf::util::concurrent::ConcurrentStlMap, 1238, 1239
 - decaf::util::Map, 2463
 - decaf::util::Properties, 3128
 - decaf::util::StlList, 3396
 - decaf::util::StlMap, 3607
 - decaf::util::StlSet, 3627
- COPY
 - ControlCommandMarshaller, inflate.h, 4733
 - copyDataStructure
 - activemq::commands::ActiveMQBlobMessage, 205
 - activemq::commands::ActiveMQBytesMessage, 237
 - activemq::commands::ActiveMQDestination, 325
 - activemq::commands::ActiveMQMapMessage, 364
 - activemq::commands::ActiveMQMessage, 399
 - activemq::commands::ActiveMQObjectMessage, 444
 - activemq::commands::ActiveMQQueue, 484
 - activemq::commands::ActiveMQStreamMessage, 540
 - activemq::commands::ActiveMQTempDestination, 577
 - activemq::commands::ActiveMQTempQueue, 605
 - activemq::commands::ActiveMQTempTopic, 634
 - activemq::commands::ActiveMQTextMessage, 664
 - activemq::commands::ActiveMQTopic, 692
 - activemq::commands::BaseCommand, 759
 - activemq::commands::BaseDataStructure, 831

- activemq::commands::BooleanExpression, 855
- activemq::commands::BrokerError, 864
- activemq::commands::BrokerId, 870
- activemq::commands::BrokerInfo, 898
- activemq::commands::ConnectionControl, 1268
- activemq::commands::ConnectionError, 1297
- activemq::commands::ConnectionId, 1328
- activemq::commands::ConnectionInfo, 1356
- activemq::commands::ConsumerControl, 1402
- activemq::commands::ConsumerId, 1431
- activemq::commands::ConsumerInfo, 1461
- activemq::commands::ControlCommand, 1494
- activemq::commands::DataArrayResponse, 1529
- activemq::commands::DataResponse, 1584
- activemq::commands::DataStructure, 1661
- activemq::commands::DestinationInfo, 1728
- activemq::commands::DiscoveryEvent, 1759
- activemq::commands::ExceptionResponse, 1840
- activemq::commands::FlushCommand, 1938
- activemq::commands::IntegerResponse, 2092
- activemq::commands::JournalQueueAck, 2157
- activemq::commands::JournalTopicAck, 2184
- activemq::commands::JournalTrace, 2213
- activemq::commands::JournalTransaction, 2240
- activemq::commands::KeepAliveInfo, 2267
- activemq::commands::LastPartialCommand, 2302
- activemq::commands::LocalTransactionId, 2348
- activemq::commands::Message, 2521
- activemq::commands::MessageAck, 2560
- activemq::commands::MessageDispatch, 2595
- activemq::commands::MessageDispatchNotification, 2631
- activemq::commands::MessageId, 2665
- activemq::commands::MessagePull, 2740
- activemq::commands::NetworkBridgeFilter, 2794
- activemq::commands::PartialCommand, 2919
- activemq::commands::ProducerAck, 3037
- activemq::commands::ProducerId, 3068
- activemq::commands::ProducerInfo, 3097
- activemq::commands::RemoveInfo, 3195
- activemq::commands::RemoveSubscriptionInfo, 3223
- activemq::commands::ReplayCommand, 3252
- activemq::commands::Response, 3286
- activemq::commands::SessionId, 3380
- activemq::commands::SessionInfo, 3408
- activemq::commands::ShutdownInfo, 3471
- activemq::commands::SubscriptionInfo, 3672
- activemq::commands::TransactionId, 3820
- activemq::commands::TransactionInfo, 3848
- activemq::commands::WireFormatInfo, 3985
- activemq::commands::XATransactionId, 4032
- correlationId
 - activemq::commands::Message, 2532
 - activemq::commands::MessagePull, 2743
 - activemq::commands::Response, 3288
- countDown
 - decaf::util::concurrent::CountDownLatch, 1523
- CountDownLatch
 - decaf::util::concurrent::CountDownLatch, 1521
- CounterType
 - decaf::lang::ArrayPointer, 732
 - decaf::lang::Pointer, 2948
- countTokens
 - decaf::util::StringTokenizer, 3669
- CRC32
 - decaf::util::zip::CRC32, 1525
- crc32.h
 - crc_table, 4724
- crc_table
 - crc32.h, 4724
- create
 - activemq::transport::failover::FailoverTransportFactory, 1886
 - activemq::transport::mock::MockTransportFactory, 2780
 - activemq::transport::tcp::TcpTransportFactory, 3757
 - activemq::transport::TransportFactory, 3889

- activemq::util::CMSExceptionSupport, 1163
- decaf::internal::net::tcp::TcpSocket, 3742
- decaf::internal::util::concurrent::ConditionImpl, 1257
- decaf::internal::util::concurrent::MutexImpl, 2788
- decaf::net::SocketImpl, 3532
- decaf::net::URI, 3925
- createBrowser
 - activemq::cmsutil::PooledSession, 2958
 - activemq::core::ActiveMQSession, 520
 - cms::Session, 3369
- createByteBuffer
 - decaf::internal::nio::BufferFactory, 944, 945
- createBytesMessage
 - activemq::cmsutil::PooledSession, 2959
 - activemq::core::ActiveMQSession, 521
 - cms::Session, 3370
- createCachedConsumer
 - activemq::cmsutil::PooledSession, 2959
- createCachedProducer
 - activemq::cmsutil::PooledSession, 2960
- createCharBuffer
 - decaf::internal::nio::BufferFactory, 945, 946
- createCMSConnectionFactory
 - cms::ConnectionFactory, 1325
- createComposite
 - activemq::transport::failover::FailoverTransportFactory, 1886
 - activemq::transport::mock::MockTransportFactory, 2780
 - activemq::transport::tcp::TcpTransportFactory, 3757
 - activemq::transport::TransportFactory, 3890
- createConnection
 - activemq::cmsutil::CmsAccessor, 1154
 - activemq::core::ActiveMQConnectionFactory, 295, 296
 - cms::ConnectionFactory, 1325, 1326
- createConsumer
 - activemq::cmsutil::PooledSession, 2960, 2961
 - activemq::core::ActiveMQSession, 521, 522
 - cms::Session, 3370, 3371
- createDestination
 - activemq::commands::ActiveMQDestination, 325
- createDoubleBuffer
 - decaf::internal::nio::BufferFactory, 946, 947
- createDurableConsumer
 - activemq::cmsutil::PooledSession, 2961
 - activemq::core::ActiveMQSession, 522
- cms::Session, 3371
- createFloatBuffer
 - decaf::internal::nio::BufferFactory, 948
- createIntBuffer
 - decaf::internal::nio::BufferFactory, 949, 950
- createLongBuffer
 - decaf::internal::nio::BufferFactory, 950, 951
- createMapMessage
 - activemq::cmsutil::PooledSession, 2962
 - activemq::core::ActiveMQSession, 523
 - cms::Session, 3372
- createMessage
 - activemq::cmsutil::MessageCreator, 2593
 - activemq::cmsutil::PooledSession, 2962
 - activemq::core::ActiveMQSession, 523
 - cms::Session, 3372
- createMessageEOFException
 - activemq::util::CMSExceptionSupport, 1163
- createMessageFormatException
 - activemq::util::CMSExceptionSupport, 1163
- createNegotiator
 - activemq::wireformat::openwire::OpenWireFormat, 2890
 - activemq::wireformat::stomp::StompWireFormat, 3644
 - activemq::wireformat::WireFormat, 3977
- createObject
 - activemq::wireformat::openwire::marshal::DataStreamMarshal, 1611
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBlobM, 214
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBytesL, 254
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMapM, 379
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMessa, 406
 - activemq::wireformat::openwire::marshal::v1::ActiveMQObject, 451
 - activemq::wireformat::openwire::marshal::v1::ActiveMQQueue, 496
 - activemq::wireformat::openwire::marshal::v1::ActiveMQStream, 557
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempO, 614
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTempT, 647
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTextM, 676
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTopicM, 704

activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller	2689	activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller
881		
activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller	2761	activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller
913		
activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller	2817	activemq::wireformat::openwire::marshal::v1::NetworkBridgeFormat
1281		
activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller	2943	activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller
1313		
activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller	3061	activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller
1344		
activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller	3093	activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller
1374		
activemq::wireformat::openwire::marshal::v1::ConsumerGroupViewMarshaller	3110	activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller
1419		
activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller	3211	activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller
1448		
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller	3228	activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionMarshaller
1481		
activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller	3259	activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller
1510		
activemq::wireformat::openwire::marshal::v1::DataActiveResponseMarshaller	3316	activemq::wireformat::openwire::marshal::v1::ResponseMarshaller
1544		
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller	3404	activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller
1607		
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller	3420	activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller
1745		
activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller	3482	activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller
1779		
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller	3681	activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller
1863		
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller	3856	activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller
1957		
activemq::wireformat::openwire::marshal::v1::IntegrationResponseMarshaller	4009	activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller
2111		
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	4049	activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller
2180		
activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller	222	activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMarshaller
2209		
activemq::wireformat::openwire::marshal::v1::JournalValueMarshaller	270	activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMarshaller
2232		
activemq::wireformat::openwire::marshal::v1::JournalValueViewMarshaller	391	activemq::wireformat::openwire::marshal::v2::ActiveMQMapMarshaller
2263		
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller	418	activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller
2290		
activemq::wireformat::openwire::marshal::v1::LastReceivedCommandMarshaller	463	activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMarshaller
2325		
activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller	508	activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller
2372		
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller	569	activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMarshaller
2582		
activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller	626	activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller
2623		
activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller	655	activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller
2652		

activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller	688	activemq::wireformat::openwire::marshal::v2::MessageDispatcher	2607
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMessageMarshaller	716	activemq::wireformat::openwire::marshal::v2::MessageDispatcher	2640
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller	893	activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2669
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller	925	activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller	2745
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller	1293	activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilter	2797
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller	1301	activemq::wireformat::openwire::marshal::v2::PartialCommand	2927
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller	1332	activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller	3041
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller	1362	activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller	3073
activemq::wireformat::openwire::marshal::v2::ConsumerGroupMarshaller	1407	activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller	3106
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller	1436	activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller	3199
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller	1469	activemq::wireformat::openwire::marshal::v2::RemoveSubscription	3236
activemq::wireformat::openwire::marshal::v2::ContactCommandMarshaller	1498	activemq::wireformat::openwire::marshal::v2::ReplayCommand	3263
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	1532	activemq::wireformat::openwire::marshal::v2::ResponseMarshaller	3301
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	1595	activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller	3384
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller	1733	activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller	3428
activemq::wireformat::openwire::marshal::v2::DiscardResponseMarshaller	1767	activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller	3478
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	1847	activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	3697
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller	1945	activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller	3872
activemq::wireformat::openwire::marshal::v2::IntegrationResponseMarshaller	2099	activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller	4001
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	2164	activemq::wireformat::openwire::marshal::v2::XATransactionInfoMarshaller	4041
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	2193	activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMarshaller	210
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	2216	activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMarshaller	250
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	2247	activemq::wireformat::openwire::marshal::v3::ActiveMQMapMarshaller	375
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller	2274	activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller	402
activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller	2313	activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMarshaller	447
activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller	2356	activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller	492
activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller	2570	activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMarshaller	553

activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	2360	activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller	2360
610		activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller	2574
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	2574	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2611
639		activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2611
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	2611	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2644
668		activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	2681
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMessageMarshaller	2644	activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	2681
696		activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller	2753
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	2681	activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller	2753
873		activemq::wireformat::openwire::marshal::v3::NetworkBridgeFactory	2809
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	2753	activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller	2935
905		activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller	2935
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	2809	activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller	3049
1273		activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller	3049
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	2935	activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller	3081
1305		activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller	3081
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	3049	activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller	3118
1336		activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller	3118
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	3081	activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller	3207
1366		activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller	3207
activemq::wireformat::openwire::marshal::v3::ConsumerGroupWithMarshaller	3118	activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionMarshaller	3232
1411		activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionMarshaller	3232
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	3118	activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	3267
1440		activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	3267
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	3207	activemq::wireformat::openwire::marshal::v3::ResponseMarshaller	3311
1473		activemq::wireformat::openwire::marshal::v3::ResponseMarshaller	3311
activemq::wireformat::openwire::marshal::v3::ContactCommandMarshaller	3232	activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller	3400
1502		activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller	3400
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller	3267	activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller	3424
1536		activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller	3424
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller	3311	activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller	3490
1599		activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller	3490
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	3400	activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller	3677
1737		activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller	3677
activemq::wireformat::openwire::marshal::v3::DiscardResponseMarshaller	3424	activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller	3860
1771		activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller	3860
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	3490	activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	4013
1851		activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	4013
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	3677	activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	4053
1949		activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	4053
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller	3860	activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMarshaller	218
2103		activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMarshaller	218
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	4013	activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMarshaller	258
2172		activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMarshaller	258
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	4053	activemq::wireformat::openwire::marshal::v4::ActiveMQMapMarshaller	383
2197		activemq::wireformat::openwire::marshal::v4::ActiveMQMapMarshaller	383
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	218	activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	410
2220		activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	410
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	258	activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMarshaller	455
2251		activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMarshaller	455
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller	383		
2278			
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	410		
2309			

activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller	500	activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller	2282
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMessageMarshaller	561	activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller	2321
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueFormatMarshaller	618	activemq::wireformat::openwire::marshal::v4::LocalTransactionMarshaller	2368
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueTopicMarshaller	643	activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller	2578
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMessageMarshaller	672	activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller	2619
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMessageMarshaller	700	activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller	2648
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	877	activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller	2673
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	909	activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller	2757
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	1277	activemq::wireformat::openwire::marshal::v4::NetworkBridgeFormatMarshaller	2813
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller	1309	activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller	2939
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller	1340	activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller	3045
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	1370	activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller	3077
activemq::wireformat::openwire::marshal::v4::ConsumerGroupMarshaller	1415	activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller	3102
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	1444	activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller	3219
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	1477	activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionMarshaller	3248
activemq::wireformat::openwire::marshal::v4::ContactCommandMarshaller	1506	activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller	3255
activemq::wireformat::openwire::marshal::v4::DataActiveResponseMarshaller	1540	activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	3296
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller	1603	activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	3388
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller	1741	activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	3432
activemq::wireformat::openwire::marshal::v4::DiscardResponseMarshaller	1775	activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	3494
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller	1859	activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	3689
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller	1953	activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	3868
activemq::wireformat::openwire::marshal::v4::IntegratedResponseMarshaller	2107	activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller	4005
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller	2176	activemq::wireformat::openwire::marshal::v4::XATransactionInfoMarshaller	4045
activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller	2205	activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMarshaller	226
activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller	2228	activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMarshaller	262
activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller	2259	activemq::wireformat::openwire::marshal::v5::ActiveMQMapMarshaller	387

activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	2236	activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller
414		
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	2255	activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller
459		
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	2286	activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller
504		
activemq::wireformat::openwire::marshal::v5::ActiveMQSequenceMessageMarshaller	2317	activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller
565		
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	2364	activemq::wireformat::openwire::marshal::v5::LocalTransactionMarshaller
622		
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	2586	activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller
651		
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	2615	activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
680		
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	2656	activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller
708		
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	2677	activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller
885		
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller	2749	activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller
917		
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller	2805	activemq::wireformat::openwire::marshal::v5::NetworkBridgeMarshaller
1285		
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller	2931	activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller
1317		
activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller	3053	activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller
1348		
activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller	3085	activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller
1378		
activemq::wireformat::openwire::marshal::v5::ConsumerGroupMarshaller	3114	activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller
1423		
activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller	3215	activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller
1452		
activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller	3244	activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionMarshaller
1485		
activemq::wireformat::openwire::marshal::v5::ContainerCommandMarshaller	3275	activemq::wireformat::openwire::marshal::v5::ReplayCommandMarshaller
1514		
activemq::wireformat::openwire::marshal::v5::DataActiveResponseMarshaller	3306	activemq::wireformat::openwire::marshal::v5::ResponseMarshaller
1548		
activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller	3396	activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller
1587		
activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller	3416	activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller
1753		
activemq::wireformat::openwire::marshal::v5::DiscoveryInfoMarshaller	3486	activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller
1783		
activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller	3685	activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller
1855		
activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller	3852	activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller
1961		
activemq::wireformat::openwire::marshal::v5::IntegrationResponseMarshaller	3993	activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller
2115		
activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller	4057	activemq::wireformat::openwire::marshal::v5::XATransactionInfoMarshaller
2168		
activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller	230	activemq::wireformat::openwire::marshal::v6::ActiveMQBlobMarshaller
2189		

activemq::wireformat::openwire::marshal::v6::ActiveMQByteMessageMarshaller	266	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2160	activemq::wireformat::openwire::marshal::v6::JournalQueueAck	
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller	395	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2201	activemq::wireformat::openwire::marshal::v6::JournalTopicAck	
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	422	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2224	activemq::wireformat::openwire::marshal::v6::JournalTraceMa	
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller	467	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2243	activemq::wireformat::openwire::marshal::v6::JournalTransact	
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	512	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2270	activemq::wireformat::openwire::marshal::v6::KeepAliveInfoM	
activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceMessageMarshaller	573	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2305	activemq::wireformat::openwire::marshal::v6::LastPartialComm	
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	630	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2352	activemq::wireformat::openwire::marshal::v6::LocalTransaction	
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	659	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2566	activemq::wireformat::openwire::marshal::v6::MessageAckMar	
activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller	684	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2627	activemq::wireformat::openwire::marshal::v6::MessageDispatc	
activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller	712	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2636	activemq::wireformat::openwire::marshal::v6::MessageDispatc	
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller	889	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2685	activemq::wireformat::openwire::marshal::v6::MessageIdMarsh	
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller	921	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2765	activemq::wireformat::openwire::marshal::v6::MessagePullMar	
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller	1289	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2801	activemq::wireformat::openwire::marshal::v6::NetworkBridgeF	
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller	1321	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	2923	activemq::wireformat::openwire::marshal::v6::PartialCommand	
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller	1352	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3057	activemq::wireformat::openwire::marshal::v6::ProducerAckMar	
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller	1382	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3089	activemq::wireformat::openwire::marshal::v6::ProducerIdMars	
activemq::wireformat::openwire::marshal::v6::ConsumerGroupMarshaller	1427	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3122	activemq::wireformat::openwire::marshal::v6::ProducerInfoMa	
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller	1456	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3203	activemq::wireformat::openwire::marshal::v6::RemoveInfoMars	
activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller	1489	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3240	activemq::wireformat::openwire::marshal::v6::RemoveSubscrip	
activemq::wireformat::openwire::marshal::v6::ContainerProviderMarshaller	1518	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3271	activemq::wireformat::openwire::marshal::v6::ReplayCommand	
activemq::wireformat::openwire::marshal::v6::DataActiveResponseMarshaller	1552	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3321	activemq::wireformat::openwire::marshal::v6::ResponseMarsha	
activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller	1591	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3392	activemq::wireformat::openwire::marshal::v6::SessionIdMarsha	
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller	1749	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3412	activemq::wireformat::openwire::marshal::v6::SessionInfoMars	
activemq::wireformat::openwire::marshal::v6::DiscoveryEventMarshaller	1763	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3474	activemq::wireformat::openwire::marshal::v6::ShutdownInfoMa	
activemq::wireformat::openwire::marshal::v6::ExceptionResponseMarshaller	1843	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3693	activemq::wireformat::openwire::marshal::v6::SubscriptionInfo	
activemq::wireformat::openwire::marshal::v6::FlushCommandMarshaller	1941	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3864	activemq::wireformat::openwire::marshal::v6::TransactionInfo	
activemq::wireformat::openwire::marshal::v6::IntegrationResponseMarshaller	2095	activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMessageMarshaller	3997	activemq::wireformat::openwire::marshal::v6::WireFormatInfo	

- activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller, 4037
- createProducer
 - activemq::cmsutil::PooledSession, 2962
 - activemq::core::ActiveMQSession, 523
 - cms::Session, 3372
- createQueryString
 - activemq::util::URISupport, 3945
- createQueue
 - activemq::cmsutil::PooledSession, 2963
 - activemq::core::ActiveMQSession, 524
 - cms::Session, 3373
- createRemoveCommand
 - activemq::commands::ConnectionInfo, 1357
 - activemq::commands::ConsumerInfo, 1461
 - activemq::commands::ProducerInfo, 3097
 - activemq::commands::SessionInfo, 3408
- createServerSocket
 - decaf::internal::net::DefaultServerSocketFactory, 1683, 1684
 - decaf::internal::net::ssl::DefaultSSLServerSocketFactory, 1694, 1695
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2855, 2856
 - decaf::net::ServerSocketFactory, 3362, 3363
- createSession
 - activemq::cmsutil::CmsAccessor, 1155
 - activemq::core::ActiveMQConnection, 279
 - cms::Connection, 1263, 1264
- createShortBuffer
 - decaf::internal::nio::BufferFactory, 951, 952
- createSocket
 - activemq::transport::tcp::SslTransport, 3575
 - activemq::transport::tcp::TcpTransport, 3754
 - decaf::internal::net::DefaultSocketFactory, 1688–1690
 - decaf::internal::net::ssl::DefaultSSLSocketFactory, 1699–1702
 - decaf::internal::net::ssl::openssl::OpenSSLSocketFactory, 2877–2880
 - decaf::net::SocketFactory, 3525–3527
 - decaf::net::ssl::SSLSocketFactory, 3572
- createSocketImpl
 - decaf::net::SocketImplFactory, 3537
- createStreamMessage
 - activemq::cmsutil::PooledSession, 2963
 - activemq::core::ActiveMQSession, 524
 - cms::Session, 3373
- createTemporaryName
 - activemq::commands::ActiveMQDestination, Dad 325
- activemq::cmsutil::PooledSession, 2963
- activemq::core::ActiveMQSession, 524
- cms::Session, 3373
- createTemporaryTopic
 - activemq::cmsutil::PooledSession, 2963
 - activemq::core::ActiveMQSession, 525
 - cms::Session, 3374
- createTextMessage
 - activemq::cmsutil::PooledSession, 2964
 - activemq::core::ActiveMQSession, 525
 - cms::Session, 3374
- createTopic
 - activemq::cmsutil::PooledSession, 2964
 - activemq::core::ActiveMQSession, 525
 - cms::Session, 3374
- createWireFormat
 - activemq::transport::AbstractTransportFactory, 201
 - activemq::wireformat::openwire::OpenWireFormatFactory, 2899
 - activemq::wireformat::stomp::StompWireFormatFactory, 3647
 - activemq::wireformat::WireFormatFactory, 3980
- criticalSection
 - decaf::util::concurrent::ConditionHandle, 1255
- ct_data
 - deflate.h, 4727
- ct_data_s, 1527
- code, 1527
- dad, 1527
- dl, 1527
- fc, 1527
- freq, 1527
- len, 1527
- CUNSUMER_MAXPENDINGMSGLIMIT
- activemq::core::ActiveMQConstants, 308
- currentThread
 - decaf::lang::Thread, 3769
- currentTimeMillis
 - decaf::lang::System, 3730
- d_buf
 - internal_state, 2120
- d_code
 - deflate.h, 4727
- D_CODES
 - deflate.h, 4727
- d_desc
 - internal_state, 2120
- deflate.h, 4727

- dad
 - ct_data_s, 1527
- data
 - activemq::commands::DataArrayResponse, 1530
 - activemq::commands::DataResponse, 1585
 - activemq::commands::PartialCommand, 2921
- data_type
 - z_stream_s, 4062
- DataArrayResponse
 - activemq::commands::DataArrayResponse, 1529
- DataArrayResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller, 1544
 - activemq::wireformat::openwire::marshal::v2::DataArrayResponseMarshaller, 1532
 - activemq::wireformat::openwire::marshal::v3::DataArrayResponseMarshaller, 1536
 - activemq::wireformat::openwire::marshal::v4::DataArrayResponseMarshaller, 1540
 - activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller, 1548
 - activemq::wireformat::openwire::marshal::v6::DataArrayResponseMarshaller, 1552
- DataFormatException
 - decaf::util::zip::DataFormatException, 1555, 1556
- DataInputStream
 - decaf::io::DataInputStream, 1567
- DataOutputStream
 - decaf::io::DataOutputStream, 1580
- DataResponse
 - activemq::commands::DataResponse, 1584
- DataResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller, 1607
 - activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller, 1595
 - activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller, 1599
 - activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller, 1603
 - activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller, 1587
 - activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller, 1591
- dataStructure
 - activemq::commands::Message, 2532
- Date
 - decaf::util::Date, 1666
- DAYS
 - decaf::util::concurrent::TimeUnit, 3815
- DEBUG
 - decaf::util::logging::Level, 2335
- Debug
 - decaf::util::logging, 176
- debug
 - decaf::util::logging::Logger, 2390
 - decaf::util::logging::SimpleLogger, 3502
- decaf, 143
- decaf/lang/exceptions/ExceptionDefines.h
 - DECAF_CATCH_EXCEPTION_-CONVERT, 4173
 - DECAF_CATCH_NOTHROW, 4173
 - DECAF_CATCH_RETHROW, 4174
 - DECAF_CATCHALL_NOTHROW, 4174
 - DECAF_CATCHALL_THROW, 4174
- decaf/util/Config.h
 - DECAF_USE_POOL, 4228
 - DECAF_UNUSED, 4229
- decaf::internal::AprPool, 728
 - AprPool, 728
- decaf::internal::DecafRuntime, 1670
 - ~DecafRuntime, 1670
 - DecafRuntime, 1670
 - getGlobalPool, 1670
- decaf::internal::io, 145
- decaf::internal::io::StandardErrorOutputStream, 3579
 - ~StandardErrorOutputStream, 3580
 - close, 3580
 - doWriteArrayBounded, 3580
 - doWriteByte, 3580
 - flush, 3580
 - StandardErrorOutputStream, 3580
- decaf::internal::io::StandardInputStream, 3582
 - ~StandardInputStream, 3582
 - doReadByte, 3582
 - StandardInputStream, 3582
- decaf::internal::io::StandardOutputStream, 3584
 - ~StandardOutputStream, 3584
 - doWriteArrayBounded, 3585
 - doWriteByte, 3585
 - flush, 3585
 - StandardOutputStream, 3584
- decaf::internal::net, 146
- decaf::internal::net::DefaultServerSocketFactory, 1682

- ~DefaultServerSocketFactory, 1683
- createServerSocket, 1683, 1684
- DefaultServerSocketFactory, 1683
- decaf::internal::net::DefaultSocketFactory, 1686
 - ~DefaultSocketFactory, 1688
 - createSocket, 1688–1690
 - DefaultSocketFactory, 1688
- decaf::internal::net::Network, 2790
 - ~Network, 2791
 - addAsResource, 2791
 - addNetworkResource, 2791
 - getNetworkRuntime, 2791
 - getRuntimeLock, 2791
 - initializeNetworking, 2791
 - Network, 2791
 - shutdownNetworking, 2791
- decaf::internal::net::SocketFileDescriptor, 3528
 - ~SocketFileDescriptor, 3528
 - getValue, 3528
 - SocketFileDescriptor, 3528
- decaf::internal::net::ssl, 147
- decaf::internal::net::ssl::DefaultSSLContext, 1691
 - ~DefaultSSLContext, 1691
 - DefaultSSLContext, 1691
 - getContext, 1691
- decaf::internal::net::ssl::DefaultSSLServerSocketFactory, 1692
 - ~DefaultSSLServerSocketFactory, 1694
 - createServerSocket, 1694, 1695
 - DefaultSSLServerSocketFactory, 1694
 - getDefaultCipherSuites, 1695
 - getSupportedCipherSuites, 1696
- decaf::internal::net::ssl::DefaultSSLSocketFactory, 1697
 - ~DefaultSSLSocketFactory, 1699
 - createSocket, 1699–1702
 - DefaultSSLSocketFactory, 1699
 - getDefaultCipherSuites, 1702
 - getSupportedCipherSuites, 1702
- decaf::internal::net::ssl::openssl, 148
- decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2842
 - ~OpenSSLContextSpi, 2843
 - OpenSSLContextSpi, 2843
 - OpenSSLContextSpi, 2844
 - OpenSSLContextSpi, 2844
 - providerGetServerSocketFactory, 2843
 - providerGetSocketFactory, 2843
 - providerInit, 2844
- decaf::internal::net::ssl::openssl::OpenSSLParameters, 2845
 - ~OpenSSLParameters, 2845
 - clone, 2845
 - setEnabledCipherSuites, 2845
 - setEnabledProtocols, 2846
 - getNeedClientAuth, 2846
 - getSupportedCipherSuites, 2846
 - getSupportedProtocols, 2846
 - getUseClientMode, 2846
 - getWantClientAuth, 2846
 - setEnabledCipherSuites, 2846
 - setEnabledProtocols, 2846
 - setNeedClientAuth, 2846
 - setUseClientMode, 2846
 - setWantClientAuth, 2846
- decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2847
 - ~OpenSSLServerSocket, 2849
 - accept, 2849
 - setEnabledCipherSuites, 2849
 - setEnabledProtocols, 2849
 - getNeedClientAuth, 2850
 - getSupportedCipherSuites, 2850
 - getSupportedProtocols, 2850
 - getWantClientAuth, 2850
 - OpenSSLServerSocket, 2849
 - setEnabledCipherSuites, 2851
 - setEnabledProtocols, 2851
 - setNeedClientAuth, 2851
 - setWantClientAuth, 2852
- decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2853
 - ~OpenSSLServerSocketFactory, 2855
 - createServerSocket, 2855, 2856
 - getDefaultCipherSuites, 2856
 - getSupportedCipherSuites, 2857
 - OpenSSLServerSocketFactory, 2855
- decaf::internal::net::ssl::openssl::OpenSSLSocket, 2858
 - ~OpenSSLSocket, 2862
 - available, 2862
 - close, 2863
 - connect, 2863
 - setEnabledCipherSuites, 2863
 - setEnabledProtocols, 2864
 - getInputStream, 2864
 - getNeedClientAuth, 2864
 - getOutputStream, 2864
 - getSupportedCipherSuites, 2865
 - getSupportedProtocols, 2865
 - getUseClientMode, 2865
 - getWantClientAuth, 2866
 - OpenSSLSocket, 2862
 - read, 2866
 - sendUrgentData, 2866
 - setEnabledCipherSuites, 2867
 - setEnabledProtocols, 2867

- setNeedClientAuth, 2867
 - setOOBInline, 2868
 - setUseClientMode, 2868
 - setWantClientAuth, 2868
 - shutdownInput, 2869
 - shutdownOutput, 2869
 - startHandshake, 2869
 - write, 2869
- decaf::internal::net::ssl::openssl::OpenSSLSocketException, 3747
 - 2871
 - ~OpenSSLSocketException, 2873
 - clone, 2873
 - getErrorString, 2874
 - OpenSSLSocketException, 2872, 2873
- decaf::internal::net::ssl::openssl::OpenSSLSocketFactory, 2875
 - ~OpenSSLSocketFactory, 2877
 - createSocket, 2877–2880
 - getDefaultCipherSuites, 2880
 - getSupportedCipherSuites, 2880
 - OpenSSLSocketFactory, 2877
- decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2882
 - ~OpenSSLSocketInputStream, 2883
 - available, 2883
 - close, 2883
 - doReadArrayBounded, 2883
 - doReadByte, 2883
 - OpenSSLSocketInputStream, 2883
 - skip, 2884
- decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream, 2885
 - ~OpenSSLSocketOutputStream, 2886
 - close, 2886
 - doWriteArrayBounded, 2886
 - doWriteByte, 2886
 - OpenSSLSocketOutputStream, 2886
- decaf::internal::net::tcp, 149
- decaf::internal::net::tcp::TcpSocket, 3738
 - ~TcpSocket, 3741
 - accept, 3741
 - available, 3741
 - bind, 3741
 - checkResult, 3741
 - close, 3742
 - connect, 3742
 - create, 3742
 - getInputStream, 3742
 - getLocalAddress, 3743
 - getOption, 3743
 - getOutputStream, 3743
 - getSocketHandle, 3744
 - isClosed, 3744
 - isConnected, 3744
 - listen, 3744
 - read, 3744
 - setOption, 3745
 - shutdownInput, 3745
 - shutdownOutput, 3745
 - TcpSocket, 3741
 - write, 3746
- decaf::internal::net::tcp::TcpSocketInputStream, 3748
 - ~TcpSocketInputStream, 3748
 - available, 3748
 - close, 3748
 - doReadArrayBounded, 3748
 - doReadByte, 3749
 - skip, 3749
 - TcpSocketInputStream, 3748
- decaf::internal::net::tcp::TcpSocketOutputStream, 3750
 - ~TcpSocketOutputStream, 3750
 - close, 3751
 - doWriteArrayBounded, 3751
 - doWriteByte, 3751
 - TcpSocketOutputStream, 3750
- decaf::internal::net::URIEncoderDecoder, 3932
 - ~URIEncoderDecoder, 3932
 - decode, 3932
 - encodeOthers, 3933
 - quoteIllegal, 3933
 - URIEncoderDecoder, 3932
 - validate, 3933
- decaf::internal::net::URIHelper, 3935
 - ~URIHelper, 3936
 - isValidDomainName, 3937
 - isValidHexChar, 3937
 - isValidHost, 3937
 - isValidIP4Word, 3937
 - isValidIP6Address, 3938
 - isValidIPv4Address, 3938
 - parseAuthority, 3938
 - parseURI, 3939
 - URIHelper, 3936
 - validateAuthority, 3939
 - validateFragment, 3939
 - validatePath, 3939
 - validateQuery, 3940
 - validateScheme, 3940
 - validateSsp, 3940
 - validateUserinfo, 3941
- decaf::internal::net::URIType, 3952
 - ~URIType, 3954
 - getAuthority, 3954
 - getFragment, 3954
 - getHost, 3954

- getPath, 3954
- getPort, 3954
- getQuery, 3955
- getScheme, 3955
- getSchemeSpecificPart, 3955
- getSource, 3955
- getUserInfo, 3955
- isAbsolute, 3955
- isOpaque, 3956
- isServerAuthority, 3956
- isValid, 3956
- setAbsolute, 3956
- setAuthority, 3956
- setFragment, 3956
- setHost, 3957
- setOpaque, 3957
- setPath, 3957
- setPort, 3957
- setQuery, 3957
- setScheme, 3957
- setSchemeSpecificPart, 3958
- setServerAuthority, 3958
- setSource, 3958
- setUserInfo, 3958
- setValid, 3958
- URIType, 3954
- decaf::internal::nio, 150
- decaf::internal::nio::BufferFactory, 942
 - ~BufferFactory, 944
 - createByteBuffer, 944, 945
 - createCharBuffer, 945, 946
 - createDoubleBuffer, 946, 947
 - createFloatBuffer, 948
 - createIntBuffer, 949, 950
 - createLongBuffer, 950, 951
 - createShortBuffer, 951, 952
- decaf::internal::nio::ByteBuffer, 991
 - ~ByteBuffer, 1003
 - array, 1003
 - arrayOffset, 1004
 - asCharBuffer, 1004
 - asDoubleBuffer, 1004
 - asFloatBuffer, 1005
 - asIntBuffer, 1005
 - asLongBuffer, 1005
 - asReadOnlyBuffer, 1006
 - asShortBuffer, 1006
 - ByteBuffer, 1002, 1003
 - compact, 1007
 - duplicate, 1007
 - get, 1007, 1008
 - getChar, 1008
 - getDouble, 1009
 - getFloat, 1009, 1010
 - getInt, 1010
 - getLong, 1011
 - getShort, 1011, 1012
 - hasArray, 1012
 - isReadOnly, 1012
 - put, 1013
 - putChar, 1013, 1014
 - putDouble, 1014, 1015
 - putFloat, 1015, 1016
 - putInt, 1016
 - putLong, 1017
 - putShort, 1018
 - setReadOnly, 1019
 - slice, 1019
- decaf::internal::nio::CharArrayBuffer, 1108
 - ~CharArrayBuffer, 1113
 - _array, 1118
 - array, 1113
 - arrayOffset, 1113
 - asReadOnlyBuffer, 1114
 - CharArrayBuffer, 1111, 1112
 - compact, 1114
 - duplicate, 1114
 - get, 1115
 - hasArray, 1115
 - isReadOnly, 1116
 - length, 1118
 - offset, 1118
 - put, 1116
 - readOnly, 1118
 - setReadOnly, 1117
 - slice, 1117
 - subSequence, 1117
- decaf::internal::nio::DoubleArrayBuffer, 1799
 - ~DoubleArrayBuffer, 1803
 - array, 1803
 - arrayOffset, 1804
 - asReadOnlyBuffer, 1804
 - compact, 1804
 - DoubleArrayBuffer, 1802, 1803
 - duplicate, 1805
 - get, 1805, 1806
 - hasArray, 1806
 - isReadOnly, 1806
 - put, 1806, 1807
 - setReadOnly, 1807
 - slice, 1807
- decaf::internal::nio::FloatArrayBuffer, 1915
 - ~FloatArrayBuffer, 1919
 - array, 1919
 - arrayOffset, 1920
 - asReadOnlyBuffer, 1920
 - compact, 1920
 - duplicate, 1921

- FloatArrayBuffer, 1918, 1919
- get, 1921, 1922
- hasArray, 1922
- isReadOnly, 1922
- put, 1922, 1923
- setReadOnly, 1923
- slice, 1923
- decaf::internal::nio::IntArrayBuffer, 2056
 - ~IntArrayBuffer, 2060
 - array, 2060
 - arrayOffset, 2061
 - asReadOnlyBuffer, 2061
 - compact, 2061
 - duplicate, 2062
 - get, 2062, 2063
 - hasArray, 2063
 - IntArrayBuffer, 2059, 2060
 - isReadOnly, 2063
 - put, 2063, 2064
 - setReadOnly, 2064
 - slice, 2064
- decaf::internal::nio::LongArrayBuffer, 2434
 - ~LongArrayBuffer, 2438
 - array, 2438
 - arrayOffset, 2439
 - asReadOnlyBuffer, 2439
 - compact, 2439
 - duplicate, 2440
 - get, 2440, 2441
 - hasArray, 2441
 - isReadOnly, 2441
 - LongArrayBuffer, 2437, 2438
 - put, 2441, 2442
 - setReadOnly, 2442
 - slice, 2442
- decaf::internal::nio::ShortArrayBuffer, 3449
 - ~ShortArrayBuffer, 3453
 - array, 3453
 - arrayOffset, 3454
 - asReadOnlyBuffer, 3454
 - compact, 3454
 - duplicate, 3455
 - get, 3455, 3456
 - hasArray, 3456
 - isReadOnly, 3456
 - put, 3456, 3457
 - setReadOnly, 3457
 - ShortArrayBuffer, 3452, 3453
 - slice, 3457
- decaf::internal::security, 151
- decaf::internal::security::SecureRandomImpl, 3336
 - ~SecureRandomImpl, 3337
 - providerGenerateSeed, 3337
 - providerNextBytes, 3337, 3338
 - providerSetSeed, 3338
 - SecureRandomImpl, 3337
- decaf::internal::util, 152
- decaf::internal::util::ByteArrayAdapter, 969
 - ~ByteArrayAdapter, 976
 - ByteArrayAdapter, 973–976
 - clear, 976
 - get, 976
 - getByteArray, 976
 - getCapacity, 977
 - getChar, 977
 - getCharArray, 977
 - getCharCapacity, 977
 - getDouble, 978
 - getDoubleArray, 978
 - getDoubleAt, 978
 - getDoubleCapacity, 978
 - getFloat, 979
 - getFloatArray, 979
 - getFloatAt, 979
 - getFloatCapacity, 980
 - getInt, 980
 - getIntArray, 980
 - getIntAt, 980
 - getIntCapacity, 981
 - getLong, 981
 - getLongArray, 981
 - getLongAt, 981
 - getLongCapacity, 982
 - getShort, 982
 - getShortArray, 982
 - getShortAt, 983
 - getShortCapacity, 983
 - operator[], 983
 - put, 984
 - putChar, 984
 - putDouble, 984
 - putDoubleAt, 985
 - putFloat, 985
 - putFloatAt, 986
 - putInt, 986
 - putIntAt, 986
 - putLong, 987
 - putLongAt, 987
 - putShort, 988
 - putShortAt, 988
 - read, 988
 - resize, 989
 - write, 989
- decaf::internal::util::concurrent, 153
- decaf::internal::util::concurrent::ConditionImpl, 1257
 - create, 1257

- destroy, 1257
- notify, 1257
- notifyAll, 1258
- wait, 1258
- decaf::internal::util::concurrent::MutexImpl, 2788
 - create, 2788
 - destroy, 2788
 - lock, 2788
 - trylock, 2789
 - unlock, 2789
- decaf::internal::util::concurrent::SynchronizableImpl, 3711
 - ~SynchronizableImpl, 3712
 - lock, 3712
 - notify, 3712
 - notifyAll, 3712
 - SynchronizableImpl, 3712
 - tryLock, 3713
 - unlock, 3713
 - wait, 3713, 3714
- decaf::internal::util::concurrent::Transferer, 3877
- decaf::internal::util::concurrent::TransferQueue, 3878
 - ~TransferQueue, 3878
 - transfer, 3879
 - TransferQueue, 3878
- decaf::internal::util::concurrent::TransferStack, 3881
 - ~TransferStack, 3881
 - transfer, 3881, 3882
 - TransferStack, 3881
- decaf::internal::util::GenericResource, 1974
 - ~GenericResource, 1974
 - GenericResource, 1974
 - getManaged, 1974
 - setManaged, 1974
- decaf::internal::util::HexStringParser, 1982
 - ~HexStringParser, 1982
 - HexStringParser, 1982
 - parse, 1982
 - parseDouble, 1982
 - parseFloat, 1983
- decaf::internal::util::Resource, 3280
 - ~Resource, 3280
- decaf::internal::util::ResourceLifecycleManager, 3281
 - ~ResourceLifecycleManager, 3281
 - addResource, 3281
 - destroyResources, 3281
 - ResourceLifecycleManager, 3281
- decaf::internal::util::TimerTaskHeap, 3804
 - ~TimerTaskHeap, 3805
 - adjustMinimum, 3805
 - decaf::util::TimerTask, 3803
 - deleteIfCancelled, 3805
 - find, 3805
 - insert, 3805
 - isEmpty, 3805
 - peek, 3805
 - remove, 3806
 - reset, 3806
 - size, 3806
 - TimerTaskHeap, 3805
- decaf::io, 154
 - decaf::io::BlockingByteArrayInputStream, 839
 - ~BlockingByteArrayInputStream, 840
 - available, 840
 - BlockingByteArrayInputStream, 840
 - close, 841
 - doReadArrayBounded, 841
 - doReadByte, 841
 - setByteArray, 841
 - skip, 841
 - decaf::io::BufferedInputStream, 934
 - ~BufferedInputStream, 936
 - available, 936
 - BufferedInputStream, 936
 - close, 937
 - doReadArrayBounded, 937
 - doReadByte, 937
 - mark, 937
 - markSupported, 937
 - reset, 938
 - skip, 938
 - decaf::io::BufferedOutputStream, 940
 - ~BufferedOutputStream, 941
 - BufferedOutputStream, 940
 - doWriteArray, 941
 - doWriteArrayBounded, 941
 - doWriteByte, 941
 - flush, 941
 - decaf::io::ByteArrayInputStream, 1020
 - ~ByteArrayInputStream, 1023
 - available, 1023
 - ByteArrayInputStream, 1022, 1023
 - doReadArrayBounded, 1024
 - doReadByte, 1024
 - mark, 1024
 - markSupported, 1024
 - reset, 1025
 - setByteArray, 1025, 1026
 - skip, 1026
 - decaf::io::ByteArrayOutputStream, 1028
 - ~ByteArrayOutputStream, 1029
 - ByteArrayOutputStream, 1028
 - doWriteArrayBounded, 1029

- doWriteByte, 1029
- reset, 1029
- size, 1029
- toByteArray, 1029
- toString, 1030
- writeTo, 1030
- decaf::io::Closeable, 1149
 - ~Closeable, 1149
 - close, 1149
- decaf::io::DataInput, 1558
 - ~DataInput, 1559
 - readBoolean, 1559
 - readByte, 1560
 - readChar, 1560
 - readDouble, 1560
 - readFloat, 1560
 - readFully, 1561
 - readInt, 1562
 - readLine, 1562
 - readLong, 1563
 - readShort, 1563
 - readString, 1563
 - readUnsignedByte, 1564
 - readUnsignedShort, 1564
 - readUTF, 1564
 - skipBytes, 1565
- decaf::io::DataInputStream, 1566
 - ~DataInputStream, 1567
 - DataInputStream, 1567
 - readBoolean, 1568
 - readByte, 1568
 - readChar, 1568
 - readDouble, 1568
 - readFloat, 1569
 - readFully, 1569, 1570
 - readInt, 1570
 - readLine, 1570
 - readLong, 1571
 - readShort, 1571
 - readString, 1572
 - readUnsignedByte, 1572
 - readUnsignedShort, 1572
 - readUTF, 1572
 - skipBytes, 1573
- decaf::io::DataOutput, 1574
 - ~DataOutput, 1575
 - writeBoolean, 1575
 - writeByte, 1575
 - writeBytes, 1575
 - writeChar, 1576
 - writeChars, 1576
 - writeDouble, 1576
 - writeFloat, 1577
 - writeInt, 1577
 - writeLong, 1577
 - writeShort, 1577
 - writeUnsignedShort, 1578
 - writeUTF, 1578
- decaf::io::DataOutputStream, 1579
 - ~DataOutputStream, 1580
 - buffer, 1582
 - DataOutputStream, 1580
 - doWriteArrayBounded, 1580
 - doWriteByte, 1580
 - size, 1581
 - writeBoolean, 1581
 - writeByte, 1582
 - writeBytes, 1582
 - writeChar, 1582
 - writeChars, 1582
 - writeDouble, 1582
 - writeFloat, 1582
 - writeInt, 1582
 - writeLong, 1582
 - writeShort, 1582
 - writeUnsignedShort, 1582
 - writeUTF, 1582
 - written, 1582
- decaf::io::EOFException, 1825
 - ~EOFException, 1826
 - clone, 1827
 - EOFException, 1825, 1826
- decaf::io::FileDescriptor, 1891
 - ~FileDescriptor, 1892
 - descriptor, 1892
 - err, 1892
 - FileDescriptor, 1892
 - in, 1892
 - out, 1892
 - readonly, 1892
 - sync, 1892
 - valid, 1892
- decaf::io::FilterInputStream, 1894
 - ~FilterInputStream, 1896
 - available, 1896
 - close, 1896
 - closed, 1899
 - doReadArray, 1897
 - doReadArrayBounded, 1897
 - doReadByte, 1897
 - FilterInputStream, 1896
 - inputStream, 1899
 - isClosed, 1897
 - mark, 1897
 - markSupported, 1898
 - own, 1899
 - reset, 1898
 - skip, 1899

- decaf::io::FilterOutputStream, 1900
 - ~FilterOutputStream, 1901
 - close, 1901
 - closed, 1903
 - doWriteArray, 1901
 - doWriteArrayBounded, 1902
 - doWriteByte, 1902
 - FilterOutputStream, 1901
 - flush, 1902
 - isClosed, 1902
 - outputStream, 1903
 - own, 1903
 - toString, 1902
- decaf::io::Flushable, 1936
 - ~Flushable, 1936
 - flush, 1936
- decaf::io::InputStream, 2043
 - ~InputStream, 2045
 - available, 2045
 - close, 2045
 - doReadArray, 2045
 - doReadArrayBounded, 2045
 - doReadByte, 2046
 - InputStream, 2045
 - lock, 2046
 - mark, 2046
 - markSupported, 2046
 - notify, 2047
 - notifyAll, 2047
 - read, 2047–2049
 - reset, 2049
 - skip, 2050
 - toString, 2050
 - tryLock, 2051
 - unlock, 2051
 - wait, 2051, 2052
- decaf::io::InputStreamReader, 2053
 - ~InputStreamReader, 2054
 - checkClosed, 2054
 - close, 2054
 - doReadArrayBounded, 2054
 - InputStreamReader, 2054
 - ready, 2054
- decaf::io::InterruptedIOException, 2127
 - ~InterruptedIOException, 2128
 - clone, 2129
 - InterruptedIOException, 2127, 2128
- decaf::io::IOException, 2142
 - ~IOException, 2143
 - clone, 2144
 - IOException, 2142, 2143
- decaf::io::OutputStream, 2907
 - ~OutputStream, 2909
 - close, 2909
 - doWriteArray, 2909
 - doWriteArrayBounded, 2909
 - doWriteByte, 2909
 - flush, 2910
 - lock, 2910
 - notify, 2910
 - notifyAll, 2910
 - OutputStream, 2909
 - toString, 2911
 - tryLock, 2911
 - unlock, 2911
 - wait, 2911, 2912
 - write, 2913, 2914
- decaf::io::OutputStreamWriter, 2915
 - ~OutputStreamWriter, 2916
 - checkClosed, 2916
 - close, 2916
 - doWriteArrayBounded, 2916
 - flush, 2916
 - OutputStreamWriter, 2915
- decaf::io::PushbackInputStream, 3141
 - ~PushbackInputStream, 3143
 - available, 3143
 - doReadArrayBounded, 3144
 - doReadByte, 3144
 - mark, 3144
 - markSupported, 3144
 - PushbackInputStream, 3143
 - reset, 3144
 - skip, 3145
 - unread, 3146
- decaf::io::Reader, 3163
 - ~Reader, 3164
 - doReadArray, 3164
 - doReadArrayBounded, 3164
 - doReadChar, 3164
 - doReadCharBuffer, 3165
 - doReadVector, 3165
 - mark, 3165
 - markSupported, 3165
 - read, 3165–3167
 - Reader, 3164
 - ready, 3167
 - reset, 3168
 - skip, 3168
- decaf::io::UnsupportedEncodingException, 3913
 - ~UnsupportedEncodingException, 3915
 - clone, 3915
 - UnsupportedEncodingException, 3913, 3914
- decaf::io::UTFDataFormatException, 3966
 - ~UTFDataFormatException, 3968
 - clone, 3968

- UTFDataFormatException, 3966, 3967
- decaf::io::Writer, 4021
 - ~Writer, 4022
 - append, 4022, 4023
 - doAppendChar, 4023
 - doAppendCharSequence, 4024
 - doAppendCharSequenceStartEnd, 4024
 - doWriteArray, 4024
 - doWriteArrayBounded, 4024
 - doWriteChar, 4024
 - doWriteString, 4024
 - doWriteStringBounded, 4024
 - doWriteVector, 4024
 - write, 4024–4026
 - Writer, 4022
- decaf::lang, 156
 - operator==, 158
- decaf::lang::Appendable, 725
 - ~Appendable, 726
 - append, 726
- decaf::lang::ArrayPointer, 730
 - ~ArrayPointer, 733
 - ArrayPointer, 732, 733
 - clone, 733
 - ConstReferenceType, 732
 - CounterType, 732
 - get, 733
 - length, 733
 - operator=, 734
 - operator==, 734, 736
 - operator[], 735
 - PointerType, 732
 - ReferenceType, 732
 - release, 735
 - reset, 735
 - swap, 736
- decaf::lang::ArrayPointerComparator, 737
 - compare, 737
 - operator(), 737
- decaf::lang::Boolean, 850
 - ~Boolean, 851
 - _FALSE, 854
 - _TRUE, 854
 - Boolean, 851
 - booleanValue, 851
 - compareTo, 851
 - equals, 852
 - operator<, 852
 - operator==, 853
 - parseBoolean, 853
 - toString, 853, 854
 - valueOf, 854
- decaf::lang::Byte, 960
 - ~Byte, 962
- Byte, 961
 - byteValue, 962
 - compareTo, 962
 - decode, 963
 - doubleValue, 963
 - equals, 963
 - floatValue, 963
 - intValue, 964
 - longValue, 964
 - MAX_VALUE, 968
 - MIN_VALUE, 968
 - operator<, 964
 - operator==, 965
 - parseByte, 965
 - shortValue, 966
 - SIZE, 968
 - toString, 966
 - valueOf, 966, 967
- decaf::lang::Character, 1100
 - byteValue, 1102
 - Character, 1102
 - compareTo, 1102
 - digit, 1102
 - doubleValue, 1103
 - equals, 1103
 - floatValue, 1103
 - intValue, 1103
 - isDigit, 1104
 - isISOControl, 1104
 - isLetter, 1104
 - isLetterOrDigit, 1104
 - isLowerCase, 1104
 - isUpperCase, 1104
 - isWhitespace, 1104
 - longValue, 1104
 - MAX_RADIX, 1106
 - MAX_VALUE, 1106
 - MIN_RADIX, 1106
 - MIN_VALUE, 1107
 - operator<, 1105
 - operator==, 1105
 - shortValue, 1106
 - SIZE, 1107
 - toString, 1106
 - valueOf, 1106
- decaf::lang::CharSequence, 1135
 - ~CharSequence, 1135
 - charAt, 1135
 - length, 1136
 - subSequence, 1136
 - toString, 1136
- decaf::lang::Comparable, 1214
 - ~Comparable, 1214
 - compareTo, 1214

- equals, 1215
- operator<, 1215
- operator==, 1215
- decaf::lang::Double, 1788
 - ~Double, 1790
 - byteValue, 1790
 - compare, 1790
 - compareTo, 1791
 - Double, 1790
 - doubleToLongBits, 1791
 - doubleToRawLongBits, 1792
 - doubleValue, 1792
 - equals, 1792, 1793
 - floatValue, 1793
 - intValue, 1793
 - isInfinite, 1793
 - isNaN, 1794
 - longBitsToDouble, 1794
 - longValue, 1794
 - MAX_VALUE, 1798
 - MIN_VALUE, 1798
 - NaN, 1798
 - NEGATIVE_INFINITY, 1798
 - operator<, 1794, 1795
 - operator==, 1795
 - parseDouble, 1795
 - POSITIVE_INFINITY, 1798
 - shortValue, 1796
 - SIZE, 1798
 - toHexString, 1796
 - toString, 1797
 - valueOf, 1797
- decaf::lang::DYNAMIC_CAST_TOKEN, 1820
- decaf::lang::Exception, 1831
 - ~Exception, 1833
 - buildMessage, 1834
 - cause, 1837
 - clone, 1834
 - Exception, 1832, 1833
 - getCause, 1835
 - getMessage, 1835
 - getStackTrace, 1835
 - getStackTraceString, 1835
 - initCause, 1836
 - message, 1837
 - operator=, 1836
 - printStackTrace, 1836
 - setMark, 1836
 - setMessage, 1836
 - setStackTrace, 1837
 - stackTrace, 1837
 - what, 1837
- decaf::lang::exceptions, 159
 - decaf::lang::exceptions::ClassCastException, 1145
 - ~ClassCastException, 1146
 - ClassCastException, 1145, 1146
 - clone, 1147
 - decaf::lang::exceptions::IllegalArgumentException, 1991
 - ~IllegalArgumentException, 1992
 - clone, 1993
 - IllegalArgumentException, 1991, 1992
 - decaf::lang::exceptions::IllegalMonitorStateException, 1994
 - ~IllegalMonitorStateException, 1995
 - clone, 1996
 - IllegalMonitorStateException, 1994, 1995
 - decaf::lang::exceptions::IllegalStateException, 1998
 - ~IllegalStateException, 1999
 - clone, 2000
 - IllegalStateException, 1998, 1999
 - decaf::lang::exceptions::IllegalThreadStateException, 2001
 - ~IllegalThreadStateException, 2002
 - clone, 2003
 - IllegalThreadStateException, 2001, 2002
 - decaf::lang::exceptions::IndexOutOfBoundsException, 2008
 - ~IndexOutOfBoundsException, 2009
 - clone, 2010
 - IndexOutOfBoundsException, 2008, 2009
 - decaf::lang::exceptions::InterruptedException, 2124
 - ~InterruptedException, 2125
 - clone, 2126
 - InterruptedException, 2124, 2125
 - decaf::lang::exceptions::InvalidStateException, 2139
 - ~InvalidStateException, 2140
 - clone, 2141
 - InvalidStateException, 2139, 2140
 - decaf::lang::exceptions::NoSuchElementException, 2826
 - ~NoSuchElementException, 2827
 - clone, 2828
 - NoSuchElementException, 2826, 2827
 - decaf::lang::exceptions::NullPointerException, 2832
 - ~NullPointerException, 2833
 - clone, 2834
 - NullPointerException, 2832, 2833
 - decaf::lang::exceptions::NumberFormatException, 2838
 - ~NumberFormatException, 2840
 - clone, 2840

- NumberFormatException, 2838, 2839
- decaf::lang::exceptions::RuntimeException, 3328
 - ~RuntimeException, 3329
 - clone, 3330
 - RuntimeException, 3328, 3329
- decaf::lang::exceptions::UnsupportedOperationException, 3916
 - ~UnsupportedOperationException, 3917
 - clone, 3918
 - UnsupportedOperationException, 3916, 3917
- decaf::lang::Float, 1904
 - ~Float, 1906
 - byteValue, 1906
 - compare, 1906
 - compareTo, 1907
 - doubleValue, 1907
 - equals, 1907, 1908
 - Float, 1906
 - floatToIntBits, 1908
 - floatToRawIntBits, 1908
 - floatValue, 1909
 - intBitsToFloat, 1909
 - intValue, 1909
 - isInfinite, 1909, 1910
 - isNaN, 1910
 - longValue, 1910
 - MAX_VALUE, 1914
 - MIN_VALUE, 1914
 - NaN, 1914
 - NEGATIVE_INFINITY, 1914
 - operator<, 1910, 1911
 - operator==, 1911
 - parseFloat, 1911
 - POSITIVE_INFINITY, 1914
 - shortValue, 1912
 - SIZE, 1914
 - toHexString, 1912
 - toString, 1912, 1913
 - valueOf, 1913
- decaf::lang::Integer, 2077
 - ~Integer, 2080
 - bitCount, 2080
 - byteValue, 2080
 - compareTo, 2080
 - decode, 2081
 - doubleValue, 2081
 - equals, 2081, 2082
 - floatValue, 2082
 - highestOneBit, 2082
 - Integer, 2079
 - intValue, 2082
 - longValue, 2082
 - lowestOneBit, 2083
 - MAX_VALUE, 2090
 - MIN_VALUE, 2090
 - numberOfLeadingZeros, 2083
 - numberOfTrailingZeros, 2083
 - operator<, 2084
 - operator==, 2084
 - parseInt, 2085
 - reverse, 2086
 - reverseBytes, 2086
 - rotateLeft, 2086
 - rotateRight, 2086
 - shortValue, 2087
 - signum, 2087
 - SIZE, 2090
 - toBinaryString, 2087
 - toHexString, 2088
 - toOctalString, 2088
 - toString, 2088, 2089
 - valueOf, 2089, 2090
- decaf::lang::Iterable, 2152
 - ~Iterable, 2152
 - iterator, 2152
- decaf::lang::Long, 2420
 - ~Long, 2423
 - bitCount, 2423
 - byteValue, 2423
 - compareTo, 2423
 - decode, 2424
 - doubleValue, 2424
 - equals, 2424, 2425
 - floatValue, 2425
 - highestOneBit, 2425
 - intValue, 2425
 - Long, 2422
 - longValue, 2425
 - lowestOneBit, 2426
 - MAX_VALUE, 2433
 - MIN_VALUE, 2433
 - numberOfLeadingZeros, 2426
 - numberOfTrailingZeros, 2426
 - operator<, 2427
 - operator==, 2427
 - parseLong, 2428
 - reverse, 2428
 - reverseBytes, 2429
 - rotateLeft, 2429
 - rotateRight, 2429
 - shortValue, 2430
 - signum, 2430
 - SIZE, 2433
 - toBinaryString, 2430
 - toHexString, 2430
 - toOctalString, 2431

- toString, 2431
- valueOf, 2432
- decaf::lang::Math, 2497
 - ~Math, 2499
 - abs, 2499, 2500
 - ceil, 2500
 - E, 2511
 - floor, 2501
 - Math, 2499
 - max, 2501, 2502
 - min, 2503, 2504
 - PI, 2511
 - pow, 2505
 - random, 2505
 - round, 2506
 - signum, 2506, 2507
 - sqrt, 2508
 - toDegrees, 2511
 - toRadians, 2511
- decaf::lang::Number, 2835
 - ~Number, 2835
 - byteValue, 2835
 - doubleValue, 2836
 - floatValue, 2836
 - intValue, 2836
 - longValue, 2836
 - shortValue, 2837
- decaf::lang::Pointer, 2946
 - ~Pointer, 2949
 - CounterType, 2948
 - dynamicCast, 2950
 - get, 2950
 - operator*, 2950
 - operator->, 2951
 - operator=, 2951
 - operator==, 2951, 2953
 - Pointer, 2948, 2949
 - PointerType, 2948
 - ReferenceType, 2948
 - release, 2951
 - reset, 2952
 - staticCast, 2952
 - swap, 2952
- decaf::lang::PointerComparator, 2954
 - compare, 2954
 - operator(), 2954
- decaf::lang::Readable, 3160
 - ~Readable, 3160
 - read, 3160
- decaf::lang::Runnable, 3325
 - ~Runnable, 3325
 - run, 3325
- decaf::lang::Runtime, 3326
 - ~Runtime, 3326
- decaf::lang::System, 3733
- decaf::lang::Thread, 3773
- decaf::util::logging::LogManager, 2412
- getRuntime, 3326
- initializeRuntime, 3326
- shutdownRuntime, 3327
- decaf::lang::Short, 3440
 - ~Short, 3442
 - byteValue, 3442
 - compareTo, 3442
 - decode, 3443
 - doubleValue, 3443
 - equals, 3443
 - floatValue, 3443
 - intValue, 3444
 - longValue, 3444
 - MAX_VALUE, 3448
 - MIN_VALUE, 3448
 - operator<, 3444
 - operator==, 3445
 - parseShort, 3445
 - reverseBytes, 3446
 - Short, 3441
 - shortValue, 3446
 - SIZE, 3448
 - toString, 3446
 - valueOf, 3447
- decaf::lang::STATIC_CAST_TOKEN, 3587
- decaf::lang::String, 3665
 - ~String, 3666
 - charAt, 3666
 - isEmpty, 3666
 - length, 3667
 - String, 3666
 - subSequence, 3667
 - toString, 3667
- decaf::lang::System, 3726
 - ~System, 3728
 - arraycopy, 3728, 3729
 - availableProcessors, 3729
 - clearProperty, 3729
 - currentTimeMillis, 3730
 - decaf::lang::Runtime, 3733
 - getenv, 3730
 - getProperties, 3731
 - getProperty, 3731
 - nanoTime, 3732
 - setenv, 3732
 - setProperty, 3732
 - System, 3728
 - unsetenv, 3732
- decaf::lang::Thread, 3765
 - ~Thread, 3769
 - BLOCKED, 3768

- currentThread, 3769
- decaf::lang::Runtime, 3773
- decaf::util::concurrent::locks::LockSupport, 3773
- getId, 3769
- getName, 3769
- getPriority, 3769
- getState, 3769
- getUncaughtExceptionHandler, 3770
- isAlive, 3770
- join, 3770, 3771
- MAX_PRIORITY, 3773
- MIN_PRIORITY, 3773
- NEW, 3768
- NORM_PRIORITY, 3773
- run, 3771
- RUNNABLE, 3768
- setName, 3771
- setPriority, 3771
- setUncaughtExceptionHandler, 3771
- sleep, 3772
- SLEEPING, 3768
- start, 3772
- State, 3768
- TERMINATED, 3768
- Thread, 3768
- TIMED_WAITING, 3768
- toString, 3773
- WAITING, 3768
- yield, 3773
- decaf::lang::Thread::UncaughtExceptionHandler, 3906
 - ~UncaughtExceptionHandler, 3906
 - uncaughtException, 3906
- decaf::lang::ThreadGroup, 3776
 - ~ThreadGroup, 3776
 - ThreadGroup, 3776
- decaf::lang::Throwable, 3783
 - ~Throwable, 3784
 - clone, 3784
 - getCause, 3785
 - getMessage, 3785
 - getStackTrace, 3785
 - getStackTraceString, 3785
 - initCause, 3786
 - printStackTrace, 3786
 - setMark, 3786
 - Throwable, 3784
- decaf::net, 160
- decaf::net::BindException, 836
 - ~BindException, 837
 - BindException, 836, 837
 - clone, 838
- decaf::net::ConnectException, 1259
 - ~ConnectException, 1260
 - clone, 1261
 - ConnectException, 1259, 1260
- decaf::net::HttpRetryException, 1986
 - ~HttpRetryException, 1987
 - clone, 1988
 - HttpRetryException, 1986, 1987
- decaf::net::Inet4Address, 2011
 - ~Inet4Address, 2012
 - Inet4Address, 2012
 - InetAddress, 2014
 - isAnyLocalAddress, 2012
 - isLinkLocalAddress, 2012
 - isLoopbackAddress, 2012
 - isMCGlobal, 2012
 - isMCLinkLocal, 2013
 - isMCNodeLocal, 2013
 - isMCOrgLocal, 2013
 - isMCSiteLocal, 2013
 - isMulticastAddress, 2013
 - isSiteLocalAddress, 2014
- decaf::net::Inet6Address, 2015
 - ~Inet6Address, 2015
 - Inet6Address, 2015
 - InetAddress, 2015
- decaf::net::InetAddress, 2016
 - ~InetAddress, 2018
 - addressBytes, 2022
 - anyBytes, 2022
 - bytesToInt, 2018
 - getAddress, 2018
 - getAnyAddress, 2018
 - getByAddress, 2019
 - getHostAddress, 2019
 - getHostName, 2019
 - getLocalHost, 2020
 - getLoopbackAddress, 2020
 - hostname, 2022
 - InetAddress, 2018
 - isAnyLocalAddress, 2020
 - isLinkLocalAddress, 2020
 - isLoopbackAddress, 2020
 - isMCGlobal, 2020
 - isMCLinkLocal, 2021
 - isMCNodeLocal, 2021
 - isMCOrgLocal, 2021
 - isMCSiteLocal, 2021
 - isMulticastAddress, 2021
 - isSiteLocalAddress, 2022
 - loopbackBytes, 2022
 - reached, 2022
 - toString, 2022
- decaf::net::InetSocketAddress, 2023
 - ~InetSocketAddress, 2023

- InetAddress, 2023
- decaf::net::MalformedURLException, 2456
 - ~MalformedURLException, 2457
 - clone, 2458
 - MalformedURLException, 2456, 2457
- decaf::net::NoRouteToHostException, 2820
 - ~NoRouteToHostException, 2821
 - clone, 2822
 - NoRouteToHostException, 2820, 2821
- decaf::net::PortUnreachableException, 2973
 - ~PortUnreachableException, 2974
 - clone, 2975
 - PortUnreachableException, 2973, 2974
- decaf::net::ProtocolException, 3137
 - ~ProtocolException, 3138
 - clone, 3139
 - ProtocolException, 3137, 3138
- decaf::net::ServerSocket, 3352
 - ~ServerSocket, 3355
 - accept, 3356
 - bind, 3356
 - checkClosed, 3357
 - close, 3357
 - ensureCreated, 3357
 - getDefaultBacklog, 3357
 - getLocalPort, 3357
 - getReceiveBufferSize, 3357
 - getReuseAddress, 3357
 - getSoTimeout, 3358
 - implAccept, 3358
 - isBound, 3358
 - isClosed, 3358
 - ServerSocket, 3354, 3355
 - setReceiveBufferSize, 3358
 - setReuseAddress, 3359
 - setSocketImplFactory, 3359
 - setSoTimeout, 3359
 - setupSocketImpl, 3360
 - toString, 3360
- decaf::net::ServerSocketFactory, 3361
 - ~ServerSocketFactory, 3362
 - createServerSocket, 3362, 3363
 - getDefault, 3363
 - ServerSocketFactory, 3362
- decaf::net::Socket, 3503
 - ~Socket, 3508
 - accepted, 3508
 - bind, 3508
 - checkClosed, 3509
 - close, 3509
 - connect, 3509
 - ensureCreated, 3510
 - getInetAddress, 3510
 - getInputStream, 3510
 - getKeepAlive, 3510
 - getLocalAddress, 3510
 - getLocalPort, 3511
 - getOOBInline, 3511
 - getOutputStream, 3511
 - getPort, 3511
 - getReceiveBufferSize, 3511
 - getReuseAddress, 3512
 - getSendBufferSize, 3512
 - getSoLinger, 3512
 - getSoTimeout, 3512
 - getTcpNoDelay, 3513
 - getTrafficClass, 3513
 - impl, 3518
 - initSocketImpl, 3513
 - isBound, 3513
 - isClosed, 3513
 - isConnected, 3514
 - isInputShutdown, 3514
 - isOutputShutdown, 3514
 - sendUrgentData, 3514
 - ServerSocket, 3518
 - setKeepAlive, 3514
 - setOOBInline, 3514
 - setReceiveBufferSize, 3515
 - setReuseAddress, 3515
 - setSendBufferSize, 3515
 - setSocketImplFactory, 3516
 - setSoLinger, 3516
 - setSoTimeout, 3516
 - setTcpNoDelay, 3517
 - setTrafficClass, 3517
 - shutdownInput, 3517
 - shutdownOutput, 3517
 - Socket, 3506–3508
 - toString, 3518
- decaf::net::SocketAddress, 3519
 - ~SocketAddress, 3519
- decaf::net::SocketError, 3520
 - getErrorCode, 3520
 - getErrorString, 3520
- decaf::net::SocketException, 3521
 - ~SocketException, 3522
 - clone, 3522
 - SocketException, 3521, 3522
- decaf::net::SocketFactory, 3524
 - ~SocketFactory, 3525
 - createSocket, 3525–3527
 - getDefault, 3527
 - SocketFactory, 3525
- decaf::net::SocketImpl, 3529
 - ~SocketImpl, 3531
 - accept, 3531
 - address, 3536

- available, 3531
- bind, 3531
- close, 3532
- connect, 3532
- create, 3532
- fd, 3536
- getFileDescriptor, 3532
- getInetAddress, 3533
- getInputStream, 3533
- getLocalAddress, 3533
- getLocalPort, 3533
- getOption, 3533
- getOutputStream, 3534
- getPort, 3534
- listen, 3534
- localPort, 3536
- port, 3536
- sendUrgentData, 3535
- setOption, 3535
- shutdownInput, 3535
- shutdownOutput, 3535
- SocketImpl, 3531
- supportsUrgentData, 3536
- toString, 3536
- decaf::net::SocketImplFactory, 3537
 - ~SocketImplFactory, 3537
 - createSocketImpl, 3537
- decaf::net::SocketOptions, 3538
 - ~SocketOptions, 3539
 - SOCKET_OPTION_BINDADDR, 3539
 - SOCKET_OPTION_BROADCAST, 3539
 - SOCKET_OPTION_IP_-
MULTICAST_IF, 3539
 - SOCKET_OPTION_IP_-
MULTICAST_IF2, 3539
 - SOCKET_OPTION_IP_-
MULTICAST_LOOP, 3540
 - SOCKET_OPTION_IP_TOS, 3540
 - SOCKET_OPTION_KEEPAIVE, 3540
 - SOCKET_OPTION_LINGER, 3540
 - SOCKET_OPTION_OOINLINE, 3540
 - SOCKET_OPTION_RCVBUF, 3540
 - SOCKET_OPTION_REUSEADDR, 3541
 - SOCKET_OPTION_SNDBUF, 3541
 - SOCKET_OPTION_TCP_NODELAY, 3541
 - SOCKET_OPTION_TIMEOUT, 3541
- decaf::net::SocketTimeoutException, 3542
 - ~SocketTimeoutException, 3543
 - clone, 3544
 - SocketTimeoutException, 3542, 3543
- decaf::net::ssl, 162
 - decaf::net::ssl::SSLContext, 3545
 - ~SSLContext, 3545
 - getDefault, 3545
 - getDefaultSSLParameters, 3546
 - getServerSocketFactory, 3546
 - getSocketFactory, 3546
 - getSupportedSSLParameters, 3546
 - setDefault, 3547
 - SSLContext, 3545
 - decaf::net::ssl::SSLContextSpi, 3548
 - ~SSLContextSpi, 3548
 - providerGetDefaultSSLParameters, 3548
 - providerGetServerSocketFactory, 3549
 - providerGetSocketFactory, 3549
 - providerGetSupportedSSLParameters, 3549
 - providerInit, 3550
 - decaf::net::ssl::SSLParameters, 3551
 - ~SSLParameters, 3552
 - getCipherSuites, 3552
 - getNeedClientAuth, 3552
 - getProtocols, 3552
 - getWantClientAuth, 3552
 - setCipherSuites, 3552
 - setNeedClientAuth, 3553
 - setProtocols, 3553
 - setWantClientAuth, 3553
 - SSLParameters, 3551, 3552
 - decaf::net::ssl::SSLServerSocket, 3554
 - ~SSLServerSocket, 3556
 - getEnabledCipherSuites, 3556
 - getEnabledProtocols, 3557
 - getNeedClientAuth, 3557
 - getSupportedCipherSuites, 3557
 - getSupportedProtocols, 3557
 - getWantClientAuth, 3557
 - setEnabledCipherSuites, 3558
 - setEnabledProtocols, 3558
 - setNeedClientAuth, 3558
 - setWantClientAuth, 3558
 - SSLServerSocket, 3555, 3556
 - decaf::net::ssl::SSLServerSocketFactory, 3560
 - ~SSLServerSocketFactory, 3561
 - getDefault, 3561
 - getDefaultCipherSuites, 3561
 - getSupportedCipherSuites, 3561
 - SSLServerSocketFactory, 3561
 - decaf::net::ssl::SSLSocket, 3563
 - ~SSLSocket, 3566
 - getEnabledCipherSuites, 3566
 - getEnabledProtocols, 3566
 - getNeedClientAuth, 3566
 - getSSLParameters, 3567
 - getSupportedCipherSuites, 3567

- getSupportedProtocols, 3567
- getUseClientMode, 3567
- getWantClientAuth, 3568
- setEnabledCipherSuites, 3568
- setEnabledProtocols, 3568
- setNeedClientAuth, 3569
- setSSLParameters, 3569
- setUseClientMode, 3569
- setWantClientAuth, 3570
- SSLSocket, 3564, 3565
- startHandshake, 3570
- decaf::net::ssl::SSLSocketFactory, 3571
 - ~SSLSocketFactory, 3572
 - createSocket, 3572
 - getDefault, 3572
 - getDefaultCipherSuites, 3572
 - getSupportedCipherSuites, 3573
 - SSLSocketFactory, 3572
- decaf::net::UnknownHostException, 3907
 - ~UnknownHostException, 3908
 - clone, 3909
 - UnknownHostException, 3907, 3908
- decaf::net::UnknownServiceException, 3910
 - ~UnknownServiceException, 3911
 - clone, 3912
 - UnknownServiceException, 3910, 3911
- decaf::net::URI, 3921
 - ~URI, 3924
 - compareTo, 3925
 - create, 3925
 - equals, 3925
 - getAuthority, 3925
 - getFragment, 3925
 - getHost, 3925
 - getPath, 3926
 - getPort, 3926
 - getQuery, 3926
 - getRawAuthority, 3926
 - getRawFragment, 3926
 - getRawPath, 3926
 - getRawQuery, 3927
 - getRawSchemeSpecificPart, 3927
 - getRawUserInfo, 3927
 - getScheme, 3927
 - getSchemeSpecificPart, 3927
 - getUserInfo, 3927
 - isAbsolute, 3928
 - isOpaque, 3928
 - normalize, 3928
 - operator<, 3928
 - operator==, 3929
 - parseServerAuthority, 3929
 - relativize, 3929
 - resolve, 3930
 - toString, 3931
 - toURL, 3931
 - URI, 3923, 3924
- decaf::net::URISyntaxException, 3948
 - ~URISyntaxException, 3950
 - clone, 3950
 - getIndex, 3950
 - getInput, 3951
 - getReason, 3951
 - URISyntaxException, 3948–3950
- decaf::net::URL, 3960
 - ~URL, 3961
 - URL, 3961
- decaf::net::URLDecoder, 3962
 - ~URLDecoder, 3962
 - decode, 3962
- decaf::net::URLEncoder, 3963
 - ~URLEncoder, 3963
 - encode, 3963
- decaf::nio, 163
- decaf::nio::Buffer, 928
 - ~Buffer, 930
 - _capacity, 933
 - _limit, 933
 - _mark, 933
 - _markSet, 933
 - _position, 933
 - Buffer, 930
 - capacity, 930
 - clear, 930
 - flip, 931
 - hasRemaining, 931
 - isReadOnly, 931
 - limit, 931, 932
 - mark, 932
 - position, 932
 - remaining, 932
 - reset, 933
 - rewind, 933
- decaf::nio::BufferOverflowException, 954
 - ~BufferOverflowException, 955
 - BufferOverflowException, 954, 955
 - clone, 956
- decaf::nio::BufferUnderflowException, 957
 - ~BufferUnderflowException, 958
 - BufferUnderflowException, 957, 958
 - clone, 959
- decaf::nio::ByteBuffer, 1031
 - ~ByteBuffer, 1036
 - allocate, 1036
 - array, 1037
 - arrayOffset, 1037
 - asCharBuffer, 1037
 - asDoubleBuffer, 1038

- asFloatBuffer, 1038
- asIntBuffer, 1038
- asLongBuffer, 1039
- asReadOnlyBuffer, 1039
- asShortBuffer, 1039
- ByteBuffer, 1036
- compact, 1040
- compareTo, 1040
- duplicate, 1040
- equals, 1040
- get, 1040–1042
- getChar, 1042
- getDouble, 1042, 1043
- getFloat, 1043
- getInt, 1044
- getLong, 1044, 1045
- getShort, 1045
- hasArray, 1046
- isReadOnly, 1046
- operator<, 1046
- operator==, 1046
- put, 1046–1048
- putChar, 1049
- putDouble, 1049, 1050
- putFloat, 1050, 1051
- putInt, 1051
- putLong, 1052
- putShort, 1053
- slice, 1053
- toString, 1054
- wrap, 1054
- decaf::nio::CharBuffer, 1119
 - ~CharBuffer, 1122
 - allocate, 1122
 - append, 1123
 - array, 1124
 - arrayOffset, 1124
 - asReadOnlyBuffer, 1125
 - charAt, 1125
 - CharBuffer, 1122
 - compact, 1125
 - compareTo, 1126
 - duplicate, 1126
 - equals, 1126
 - get, 1126, 1127
 - hasArray, 1128
 - length, 1128
 - operator<, 1128
 - operator==, 1128
 - put, 1128–1131
 - read, 1131
 - slice, 1132
 - subSequence, 1132
 - toString, 1133
 - wrap, 1133
- decaf::nio::DoubleBuffer, 1809
 - ~DoubleBuffer, 1811
 - allocate, 1811
 - array, 1812
 - arrayOffset, 1812
 - asReadOnlyBuffer, 1812
 - compact, 1813
 - compareTo, 1813
 - DoubleBuffer, 1811
 - duplicate, 1813
 - equals, 1814
 - get, 1814, 1815
 - hasArray, 1815
 - operator<, 1815
 - operator==, 1816
 - put, 1816, 1817
 - slice, 1818
 - toString, 1818
 - wrap, 1818, 1819
- decaf::nio::FloatBuffer, 1925
 - ~FloatBuffer, 1927
 - allocate, 1927
 - array, 1927
 - arrayOffset, 1928
 - asReadOnlyBuffer, 1928
 - compact, 1929
 - compareTo, 1929
 - duplicate, 1929
 - equals, 1929
 - FloatBuffer, 1927
 - get, 1929–1931
 - hasArray, 1931
 - operator<, 1931
 - operator==, 1931
 - put, 1931–1933
 - slice, 1933
 - toString, 1934
 - wrap, 1934
- decaf::nio::IntBuffer, 2066
 - ~IntBuffer, 2068
 - allocate, 2068
 - array, 2068
 - arrayOffset, 2069
 - asReadOnlyBuffer, 2069
 - compact, 2070
 - compareTo, 2070
 - duplicate, 2070
 - equals, 2070
 - get, 2070–2072
 - hasArray, 2072
 - IntBuffer, 2068
 - operator<, 2072
 - operator==, 2072

- put, 2072–2074
- slice, 2075
- toString, 2075
- wrap, 2075
- decaf::nio::InvalidMarkException, 2135
 - ~InvalidMarkException, 2136
 - clone, 2137
 - InvalidMarkException, 2135, 2136
- decaf::nio::LongBuffer, 2444
 - ~LongBuffer, 2446
 - allocate, 2446
 - array, 2447
 - arrayOffset, 2447
 - asReadOnlyBuffer, 2447
 - compact, 2448
 - compareTo, 2448
 - duplicate, 2448
 - equals, 2448
 - get, 2448–2450
 - hasArray, 2450
 - LongBuffer, 2446
 - operator<, 2450
 - operator==, 2450
 - put, 2450–2452
 - slice, 2453
 - toString, 2453
 - wrap, 2453
- decaf::nio::ReadOnlyBufferException, 3169
 - ~ReadOnlyBufferException, 3170
 - clone, 3171
 - ReadOnlyBufferException, 3169, 3170
- decaf::nio::ShortBuffer, 3459
 - ~ShortBuffer, 3461
 - allocate, 3461
 - array, 3461
 - arrayOffset, 3462
 - asReadOnlyBuffer, 3462
 - compact, 3463
 - compareTo, 3463
 - duplicate, 3463
 - equals, 3463
 - get, 3463–3465
 - hasArray, 3465
 - operator<, 3465
 - operator==, 3465
 - put, 3465–3467
 - ShortBuffer, 3461
 - slice, 3467
 - toString, 3468
 - wrap, 3468
- decaf::security, 164
- decaf::security::auth, 165
- decaf::security::auth::x500, 166
- decaf::security::auth::x500::X500Principal, 4027
 - ~X500Principal, 4027
 - getEncoded, 4027
 - getName, 4027
 - hashCode, 4027
- decaf::security::cert, 167
- decaf::security::cert::Certificate, 1086
 - ~Certificate, 1087
 - equals, 1087
 - getEncoded, 1087
 - getPublicKey, 1087
 - getType, 1087
 - toString, 1088
 - verify, 1088
- decaf::security::cert::CertificateEncodingException, 1090
 - ~CertificateEncodingException, 1091
 - CertificateEncodingException, 1090, 1091
 - clone, 1091
- decaf::security::cert::CertificateException, 1092
 - ~CertificateException, 1093
 - CertificateException, 1092, 1093
 - clone, 1093
- decaf::security::cert::CertificateExpiredException, 1094
 - ~CertificateExpiredException, 1095
 - CertificateExpiredException, 1094, 1095
 - clone, 1095
- decaf::security::cert::CertificateNotYetValidException, 1096
 - ~CertificateNotYetValidException, 1097
 - CertificateNotYetValidException, 1096, 1097
 - clone, 1097
- decaf::security::cert::CertificateParsingException, 1098
 - ~CertificateParsingException, 1099
 - CertificateParsingException, 1098, 1099
 - clone, 1099
- decaf::security::cert::X509Certificate, 4028
 - ~X509Certificate, 4029
 - checkValidity, 4029
 - getBasicConstraints, 4029
 - getIssuerUniqueID, 4029
 - getIssuerX500Principal, 4029
 - getKeyUsage, 4029
 - getNotAfter, 4029
 - getNotBefore, 4029
 - getSigAlgName, 4029
 - getSigAlgOID, 4029
 - getSigAlgParams, 4029
 - getSignature, 4029
 - getSubjectUniqueID, 4029
 - getSubjectX500Principal, 4029
 - getTBSCertificate, 4029

- getVersion, 4029
- decaf::security::GeneralSecurityException, 1971
 - ~GeneralSecurityException, 1972
 - clone, 1973
 - GeneralSecurityException, 1971, 1972
- decaf::security::InvalidKeyException, 2132
 - ~InvalidKeyException, 2133
 - clone, 2134
 - InvalidKeyException, 2132, 2133
- decaf::security::Key, 2293
 - ~Key, 2294
 - getAlgorithm, 2294
 - getEncoded, 2294
 - getFormat, 2294
- decaf::security::KeyException, 2295
 - ~KeyException, 2296
 - clone, 2297
 - KeyException, 2295, 2296
- decaf::security::KeyManagementException, 2298
 - ~KeyManagementException, 2299
 - clone, 2300
 - KeyManagementException, 2298, 2299
- decaf::security::NoSuchAlgorithmException, 2823
 - ~NoSuchAlgorithmException, 2824
 - clone, 2825
 - NoSuchAlgorithmException, 2823, 2824
- decaf::security::NoSuchProviderException, 2829
 - ~NoSuchProviderException, 2830
 - clone, 2831
 - NoSuchProviderException, 2829, 2830
- decaf::security::Principal, 3026
 - ~Principal, 3026
 - equals, 3026
 - getName, 3026
- decaf::security::PublicKey, 3140
 - ~PublicKey, 3140
- decaf::security::SecureRandom, 3331
 - ~SecureRandom, 3333
 - next, 3333
 - nextBytes, 3333, 3334
 - SecureRandom, 3332, 3333
 - setSeed, 3334, 3335
- decaf::security::SecureRandomSpi, 3339
 - ~SecureRandomSpi, 3339
 - providerGenerateSeed, 3339
 - providerNextBytes, 3340
 - providerSetSeed, 3340
 - SecureRandomSpi, 3339
- decaf::security::SignatureException, 3497
 - ~SignatureException, 3498
 - clone, 3499
 - SignatureException, 3497, 3498
- decaf::util, 168
- decaf::util::AbstractCollection, 179
 - ~AbstractCollection, 182
 - AbstractCollection, 182
 - add, 182
 - addAll, 182
 - clear, 183
 - contains, 184
 - containsAll, 184
 - copy, 185
 - equals, 185
 - isEmpty, 185
 - lock, 186
 - mutex, 191
 - notify, 186
 - notifyAll, 186
 - operator=, 187
 - remove, 187
 - removeAll, 188
 - retainAll, 188
 - toArray, 189
 - tryLock, 189
 - unlock, 190
 - wait, 190, 191
- decaf::util::AbstractList, 192
 - ~AbstractList, 192
- decaf::util::AbstractMap, 193
 - ~AbstractMap, 193
- decaf::util::AbstractQueue, 194
 - ~AbstractQueue, 195
 - AbstractQueue, 195
 - add, 195
 - addAll, 195
 - clear, 196
 - element, 196
 - remove, 196
- decaf::util::AbstractSequentialList, 198
 - ~AbstractSequentialList, 198
- decaf::util::AbstractSet, 199
 - ~AbstractSet, 199
 - removeAll, 199
- decaf::util::Collection, 1184
 - ~Collection, 1186
 - add, 1186
 - addAll, 1186
 - clear, 1187
 - contains, 1188
 - containsAll, 1189
 - equals, 1189
 - isEmpty, 1189
 - remove, 1190
 - removeAll, 1191
 - retainAll, 1191
 - size, 1191

- toArray, 1192
- decaf::util::Comparator, 1217
 - ~Comparator, 1217
 - compare, 1217
 - operator(), 1218
- decaf::util::comparators, 170
- decaf::util::comparators::Less, 2328
 - ~Less, 2328
 - compare, 2328
 - Less, 2328
 - operator(), 2329
- decaf::util::concurrent, 171
- decaf::util::concurrent::atomic, 173
- decaf::util::concurrent::atomic::AtomicBoolean, 738
 - ~AtomicBoolean, 738
 - AtomicBoolean, 738
 - compareAndSet, 739
 - get, 739
 - getAndSet, 739
 - set, 739
 - toString, 739
- decaf::util::concurrent::atomic::AtomicInteger, 741
 - ~AtomicInteger, 742
 - addAndGet, 742
 - AtomicInteger, 742
 - compareAndSet, 743
 - decrementAndGet, 743
 - doubleValue, 743
 - floatValue, 743
 - get, 743
 - getAndAdd, 744
 - getAndDecrement, 744
 - getAndIncrement, 744
 - getAndSet, 744
 - incrementAndGet, 744
 - intValue, 745
 - longValue, 745
 - set, 745
 - toString, 745
- decaf::util::concurrent::atomic::AtomicRefCounter, 746
 - ~AtomicRefCounter, 747
 - AtomicRefCounter, 747
 - release, 747
 - swap, 748
- decaf::util::concurrent::atomic::AtomicReference, 749
 - ~AtomicReference, 750
 - AtomicReference, 750
 - compareAndSet, 750
 - get, 750
 - getAndSet, 750
 - set, 750
 - toString, 751
- decaf::util::concurrent::BlockingQueue, 843
 - ~BlockingQueue, 846
 - drainTo, 846
 - offer, 847
 - poll, 847
 - put, 848
 - remainingCapacity, 848
 - take, 848
- decaf::util::concurrent::BrokenBarrierException, 860
 - ~BrokenBarrierException, 861
 - BrokenBarrierException, 860, 861
 - clone, 862
- decaf::util::concurrent::Callable, 1082
 - ~Callable, 1082
 - call, 1082
- decaf::util::concurrent::CancellationException, 1083
 - ~CancellationException, 1084
 - CancellationException, 1083, 1084
 - clone, 1085
- decaf::util::concurrent::ConcurrentMap, 1228
 - ~ConcurrentMap, 1229
 - putIfAbsent, 1229
 - remove, 1229
 - replace, 1230, 1231
- decaf::util::concurrent::ConcurrentStlMap, 1233
 - ~ConcurrentStlMap, 1237
 - clear, 1237
 - ConcurrentStlMap, 1237
 - containsKey, 1238
 - containsValue, 1238
 - copy, 1238, 1239
 - equals, 1239
 - get, 1239, 1240
 - isEmpty, 1240
 - keySet, 1240
 - lock, 1241
 - notify, 1241
 - notifyAll, 1241
 - put, 1242
 - putAll, 1242
 - putIfAbsent, 1243
 - remove, 1243, 1244
 - replace, 1244, 1245
 - size, 1245
 - tryLock, 1246
 - unlock, 1246
 - values, 1246
 - wait, 1246, 1247
- decaf::util::concurrent::ConditionHandle, 1255
 - ~ConditionHandle, 1255

- condition, 1255
- ConditionHandle, 1255
- criticalSection, 1255
- generation, 1255
- mutex, 1255
- numWaiting, 1255
- numWake, 1255
- semaphore, 1255
- decaf::util::concurrent::CountDownLatch, 1521
 - ~CountDownLatch, 1521
 - await, 1522, 1523
 - countDown, 1523
 - CountDownLatch, 1521
 - getCount, 1523
- decaf::util::concurrent::Delayed, 1720
 - ~Delayed, 1720
 - getDelay, 1720
- decaf::util::concurrent::ExecutionException, 1866
 - ~ExecutionException, 1867
 - clone, 1868
 - ExecutionException, 1866, 1867
- decaf::util::concurrent::Executor, 1869
 - ~Executor, 1870
 - execute, 1870
- decaf::util::concurrent::ExecutorService, 1871
 - ~ExecutorService, 1872
 - awaitTermination, 1872
- decaf::util::concurrent::Future, 1966
 - ~Future, 1967
 - cancel, 1967
 - get, 1967
 - isCancelled, 1968
 - isDone, 1968
- decaf::util::concurrent::Lock, 2375
 - ~Lock, 2375
 - isLocked, 2376
 - Lock, 2375
 - lock, 2376
 - unlock, 2376
- decaf::util::concurrent::locks, 174
- decaf::util::concurrent::locks::Condition, 1249
 - ~Condition, 1251
 - await, 1251
 - awaitNanos, 1252
 - awaitUninterruptibly, 1253
 - awaitUntil, 1254
 - signal, 1254
 - signalAll, 1254
- decaf::util::concurrent::locks::Lock, 2377
 - ~Lock, 2378
 - lock, 2378
 - lockInterruptibly, 2379
 - newCondition, 2379
 - tryLock, 2380, 2381
 - unlock, 2381
- decaf::util::concurrent::locks::LockSupport, 2383
 - ~LockSupport, 2384
- decaf::lang::Thread, 3773
 - park, 2384
 - parkNanos, 2384
 - parkUntil, 2385
 - unpark, 2385
- decaf::util::concurrent::locks::ReadWriteLock, 3172
 - ~ReadWriteLock, 3173
 - readLock, 3173
 - writeLock, 3173
- decaf::util::concurrent::locks::ReentrantLock, 3182
 - ~ReentrantLock, 3183
 - getHoldCount, 3183
 - isFair, 3184
 - isHeldByCurrentThread, 3184
 - isLocked, 3184
 - lock, 3184
 - lockInterruptibly, 3185
 - newCondition, 3185
 - ReentrantLock, 3183
 - toString, 3186
 - tryLock, 3186, 3187
 - unlock, 3188
- decaf::util::concurrent::Mutex, 2782
 - ~Mutex, 2783
 - lock, 2783
 - Mutex, 2783
 - notify, 2783
 - notifyAll, 2783
 - tryLock, 2784
 - unlock, 2784
 - wait, 2785, 2786
- decaf::util::concurrent::MutexHandle, 2787
 - ~MutexHandle, 2787
 - lock_count, 2787
 - lock_owner, 2787
 - mutex, 2787
 - MutexHandle, 2787
- decaf::util::concurrent::PooledThread, 2968
 - ~PooledThread, 2968
 - getPooledThreadListener, 2969
 - isBusy, 2969
 - PooledThread, 2968
 - run, 2969
 - setPooledThreadListener, 2969
 - stop, 2969
- decaf::util::concurrent::PooledThreadListener, 2971

- ~PooledThreadListener, 2971
- onTaskCompleted, 2971
- onTaskException, 2972
- onTaskStarted, 2972
- decaf::util::concurrent::RejectedExecutionException, 3189
 - ~RejectedExecutionException, 3190
 - clone, 3191
 - RejectedExecutionException, 3189, 3190
- decaf::util::concurrent::RejectedExecutionHandler, 3192
 - ~RejectedExecutionHandler, 3192
 - rejectedExecution, 3192
- decaf::util::concurrent::Semaphore, 3341
 - ~Semaphore, 3344
 - acquire, 3344
 - acquireUninterruptibly, 3345
 - availablePermits, 3345
 - drainPermits, 3346
 - isFair, 3346
 - release, 3346
 - Semaphore, 3343
 - toString, 3347
 - tryAcquire, 3347–3349
- decaf::util::concurrent::Synchronizable, 3700
 - ~Synchronizable, 3701
 - lock, 3701
 - notify, 3702
 - notifyAll, 3703
 - tryLock, 3704
 - unlock, 3705
 - wait, 3706, 3708, 3709
- decaf::util::concurrent::SynchronousQueue, 3716
 - ~SynchronousQueue, 3718
 - clear, 3718
 - contains, 3718
 - containsAll, 3719
 - drainTo, 3719, 3720
 - equals, 3720
 - isEmpty, 3720
 - iterator, 3721
 - offer, 3721
 - peek, 3722
 - poll, 3722
 - put, 3723
 - remainingCapacity, 3723
 - remove, 3723
 - removeAll, 3724
 - retainAll, 3724
 - size, 3724
 - SynchronousQueue, 3718
 - take, 3724
 - toArray, 3724
- decaf::util::concurrent::TaskListener, 3735
 - ~TaskListener, 3735
 - onTaskComplete, 3735
 - onTaskException, 3735
- decaf::util::concurrent::ThreadFactory, 3774
 - ~ThreadFactory, 3774
 - newThread, 3774
- decaf::util::concurrent::ThreadPool, 3777
 - ~ThreadPool, 3779
 - DEFAULT_MAX_BLOCK_SIZE, 3782
 - DEFAULT_MAX_POOL_SIZE, 3782
 - deQueueTask, 3779
 - getBacklog, 3779
 - getBlockSize, 3779
 - getFreeThreadCount, 3779
 - getInstance, 3780
 - getMaxThreads, 3780
 - getPoolSize, 3780
 - onTaskCompleted, 3780
 - onTaskException, 3780
 - onTaskStarted, 3781
 - queueTask, 3781
 - reserve, 3781
 - setBlockSize, 3781
 - setMaxThreads, 3781
 - Task, 3779
 - ThreadPool, 3779
- decaf::util::concurrent::TimeoutException, 3787
 - ~TimeoutException, 3788
 - clone, 3789
 - TimeoutException, 3787, 3788
- decaf::util::concurrent::TimeUnit, 3807
 - ~TimeUnit, 3809
 - compareTo, 3809
 - convert, 3810
 - DAYS, 3815
 - equals, 3810
 - HOURS, 3815
 - MICROSECONDS, 3815
 - MILLISECONDS, 3815
 - MINUTES, 3815
 - NANOSECONDS, 3815
 - operator<, 3810
 - operator==, 3810
 - SECONDS, 3815
 - sleep, 3811
 - timedJoin, 3811
 - timedWait, 3811
 - TimeUnit, 3809
 - toDays, 3812
 - toHours, 3812
 - toMicros, 3813
 - toMillis, 3813
 - toMinutes, 3813

- toNanos, 3814
- toSeconds, 3814
- toString, 3814
- valueOf, 3815
- values, 3816
- decaf::util::Date, 1665
 - ~Date, 1666
 - after, 1666
 - before, 1666
 - compareTo, 1667
 - Date, 1666
 - equals, 1667
 - getTime, 1667
 - operator<, 1667
 - operator=, 1667
 - operator==, 1668
 - setTime, 1668
 - toString, 1668
- decaf::util::Iterator, 2154
 - ~Iterator, 2154
 - hasNext, 2154
 - next, 2154
 - remove, 2155
- decaf::util::List, 2337
 - ~List, 2338
 - add, 2338
 - addAll, 2338
 - get, 2339
 - indexOf, 2339
 - lastIndexOf, 2340
 - List, 2338
 - listIterator, 2340, 2341
 - remove, 2342
 - set, 2342
- decaf::util::ListIterator, 2344
 - ~ListIterator, 2345
 - add, 2345
 - hasPrevious, 2345
 - nextIndex, 2345
 - previous, 2345
 - previousIndex, 2346
 - set, 2346
- decaf::util::logging, 175
 - Debug, 176
 - Error, 176
 - Fatal, 176
 - Info, 176
 - Levels, 176
 - Markblock, 176
 - Null, 176
 - Off, 176
 - Throwing, 176
 - Warn, 176
- decaf::util::logging::ConsoleHandler, 1399
 - ~ConsoleHandler, 1399
 - close, 1399
 - ConsoleHandler, 1399
 - publish, 1400
- decaf::util::logging::ErrorManager, 1828
 - ~ErrorManager, 1829
 - CLOSE_FAILURE, 1829
 - error, 1829
 - ErrorManager, 1829
 - FLUSH_FAILURE, 1829
 - FORMAT_FAILURE, 1829
 - GENERIC_FAILURE, 1829
 - OPEN_FAILURE, 1829
 - WRITE_FAILURE, 1829
- decaf::util::logging::Filter, 1893
 - ~Filter, 1893
 - isLoggable, 1893
- decaf::util::logging::Formatter, 1964
 - ~Formatter, 1964
 - format, 1964
 - formatMessage, 1965
 - getHead, 1965
 - getTail, 1965
- decaf::util::logging::Handler, 1978
 - ~Handler, 1979
 - flush, 1979
 - getErrorManager, 1979
 - getFilter, 1979
 - getFormatter, 1979
 - getLevel, 1979
 - Handler, 1979
 - isLoggable, 1980
 - publish, 1980
 - reportError, 1980
 - setErrorManager, 1980
 - setFilter, 1980
 - setFormatter, 1981
 - setLevel, 1981
- decaf::util::logging::Level, 2332
 - ~Level, 2334
 - ALL, 2335
 - compareTo, 2334
 - CONFIG, 2335
 - DEBUG, 2335
 - equals, 2334
 - FINE, 2335
 - FINER, 2335
 - FINEST, 2335
 - getName, 2334
 - INFO, 2336
 - INHERIT, 2336
 - intValue, 2334
 - Level, 2333
 - OFF, 2336

- operator<, 2334
- operator==, 2334
- parse, 2334
- SEVERE, 2336
- toString, 2335
- WARNING, 2336
- decaf::util::logging::Logger, 2386
 - ~Logger, 2389
 - addHandler, 2389
 - config, 2389
 - debug, 2390
 - entering, 2390
 - exiting, 2390
 - fine, 2390
 - finer, 2391
 - finest, 2391
 - getAnonymousLogger, 2391
 - getFilter, 2392
 - getHandlers, 2392
 - getLevel, 2392
 - getLogger, 2392
 - getName, 2392
 - getParent, 2393
 - getUseParentHandlers, 2393
 - info, 2393
 - isLoggable, 2393
 - log, 2394
 - Logger, 2389
 - removeHandler, 2395
 - setFilter, 2395
 - setLevel, 2395
 - setParent, 2395
 - setUseParentHandlers, 2395
 - severe, 2396
 - throwing, 2396
 - warning, 2396
- decaf::util::logging::LoggerHierarchy, 2398
 - ~LoggerHierarchy, 2398
 - LoggerHierarchy, 2398
- decaf::util::logging::LogManager, 2406
 - ~LogManager, 2408
 - addLogger, 2409
 - addPropertyChangeListener, 2409
 - decaf::lang::Runtime, 2412
 - getLogger, 2409
 - getLoggerNames, 2409
 - getLogManager, 2409
 - getProperties, 2410
 - getProperty, 2410
 - LogManager, 2408
 - operator=, 2410
 - readConfiguration, 2410, 2411
 - removePropertyChangeListener, 2411
 - reset, 2411
 - setProperties, 2411
- decaf::util::logging::LogRecord, 2413
 - ~LogRecord, 2414
 - getLevel, 2414
 - getLoggerName, 2414
 - getMessage, 2414
 - getSourceFile, 2415
 - getSourceFunction, 2415
 - getSourceLine, 2415
 - getThrown, 2415
 - getTimestamp, 2415
 - getTreadId, 2415
 - LogRecord, 2414
 - setLevel, 2416
 - setLoggerName, 2416
 - setMessage, 2416
 - setSourceFile, 2416
 - setSourceFunction, 2416
 - setSourceLine, 2416
 - setThrown, 2417
 - setTimestamp, 2417
 - setTreadId, 2417
- decaf::util::logging::LogWriter, 2418
 - ~LogWriter, 2418
 - destroy, 2418
 - getInstance, 2418
 - log, 2418, 2419
 - LogWriter, 2418
 - returnInstance, 2419
- decaf::util::logging::MarkBlockLogger, 2483
 - ~MarkBlockLogger, 2483
 - MarkBlockLogger, 2483
- decaf::util::logging::PropertiesChangeListener, 3135
 - ~PropertiesChangeListener, 3135
 - onPropertiesReset, 3135
 - onPropertyChanged, 3135
- decaf::util::logging::SimpleFormatter, 3500
 - ~SimpleFormatter, 3500
 - format, 3500
 - SimpleFormatter, 3500
- decaf::util::logging::SimpleLogger, 3501
 - ~SimpleLogger, 3501
 - debug, 3502
 - error, 3502
 - fatal, 3502
 - info, 3502
 - log, 3502
 - mark, 3502
 - SimpleLogger, 3501
 - warn, 3502
- decaf::util::logging::StreamHandler, 3649
 - ~StreamHandler, 3650
 - close, 3650

- flush, 3650
- isLoggable, 3651
- publish, 3651
- setOutputStream, 3651
- StreamHandler, 3650
- decaf::util::logging::XMLFormatter, 4060
 - ~XMLFormatter, 4060
- format, 4060
- getHead, 4061
- getTail, 4061
- XMLFormatter, 4060
- decaf::util::Map, 2459
 - ~Map, 2460
 - clear, 2460
 - containsKey, 2461
 - containsValue, 2462
 - copy, 2463
 - equals, 2463
 - get, 2463, 2464
 - isEmpty, 2465
 - keySet, 2466
 - Map, 2460
 - put, 2467
 - putAll, 2467
 - remove, 2468
 - size, 2469
 - values, 2470
- decaf::util::Map::Entry, 1824
 - ~Entry, 1824
 - Entry, 1824
 - getKey, 1824
 - getValue, 1824
 - setValue, 1824
- decaf::util::PriorityQueue, 3028
 - ~PriorityQueue, 3031
 - add, 3031
 - clear, 3031
 - comparator, 3031
 - iterator, 3032
 - offer, 3032
 - operator=, 3032, 3033
 - peek, 3033
 - poll, 3033
 - PriorityQueue, 3030, 3031
 - PriorityQueueIterator, 3035
 - remove, 3033, 3034
 - size, 3034
- decaf::util::Properties, 3126
 - ~Properties, 3128
 - clear, 3128
 - clone, 3128
 - copy, 3128
 - defaults, 3134
 - equals, 3128
 - getProperty, 3128, 3129
 - hasProperty, 3129
 - isEmpty, 3129
 - load, 3129, 3131
 - operator=, 3131
 - Properties, 3128
 - propertyNames, 3132
 - remove, 3132
 - setProperty, 3132
 - size, 3132
 - store, 3132, 3133
 - toArray, 3134
 - toString, 3134
- decaf::util::Queue, 3149
 - ~Queue, 3150
 - element, 3150
 - offer, 3150
 - peek, 3150
 - poll, 3151
 - remove, 3151
- decaf::util::Random, 3155
 - next, 3156
 - nextBoolean, 3157
 - nextBytes, 3157
 - nextDouble, 3157
 - nextFloat, 3158
 - nextGaussian, 3158
 - nextInt, 3158
 - nextLong, 3159
 - Random, 3156
 - setSeed, 3159
- decaf::util::Set, 3439
 - ~Set, 3439
- decaf::util::StlList, 3589
 - ~StlList, 3594
 - add, 3594
 - addAll, 3595
 - clear, 3596
 - contains, 3596
 - copy, 3596
 - equals, 3596
 - get, 3597
 - indexOf, 3597
 - isEmpty, 3597
 - iterator, 3598
 - lastIndexOf, 3598
 - listIterator, 3598, 3599
 - remove, 3599, 3600
 - set, 3600
 - size, 3601
 - StlList, 3593, 3594
- decaf::util::StlMap, 3602
 - ~StlMap, 3606
 - clear, 3606

- containsKey, 3606
- containsValue, 3607
- copy, 3607
- equals, 3607, 3608
- get, 3608
- isEmpty, 3609
- keySet, 3609
- lock, 3609
- notify, 3609
- notifyAll, 3610
- put, 3610
- putAll, 3610, 3611
- remove, 3611
- size, 3611
- StlMap, 3605, 3606
- tryLock, 3612
- unlock, 3612
- values, 3612
- wait, 3612, 3613
- decaf::util::StlQueue, 3615
 - ~StlQueue, 3617
 - back, 3617
 - clear, 3617
 - empty, 3617
 - enqueueFront, 3618
 - front, 3618
 - getSafeValue, 3618
 - iterator, 3618
 - lock, 3618
 - notify, 3619
 - notifyAll, 3619
 - pop, 3619
 - push, 3619
 - reverse, 3620
 - size, 3620
 - StlQueue, 3617
 - toArray, 3620
 - tryLock, 3620
 - unlock, 3620
 - wait, 3621, 3622
- decaf::util::StlSet, 3623
 - ~StlSet, 3625
 - add, 3625
 - clear, 3626
 - contains, 3626
 - copy, 3627
 - equals, 3627
 - isEmpty, 3627
 - iterator, 3627
 - remove, 3628
 - size, 3628
 - StlSet, 3625
- decaf::util::StringTokenizer, 3668
 - ~StringTokenizer, 3669
 - countTokens, 3669
 - hasMoreTokens, 3669
 - nextToken, 3669
 - reset, 3670
 - StringTokenizer, 3668
 - toArray, 3670
- decaf::util::Timer, 3790
 - ~Timer, 3792
 - cancel, 3792
 - purge, 3792
 - schedule, 3792–3796
 - scheduleAtFixedRate, 3797–3799
 - Timer, 3792
- decaf::util::TimerTask, 3801
 - ~TimerTask, 3802
 - cancel, 3802
 - decaf::internal::util::TimerTaskHeap, 3803
 - getWhen, 3802
 - isScheduled, 3802
 - scheduledExecutionTime, 3802
 - setScheduledTime, 3802
 - Timer, 3803
 - TimerImpl, 3803
 - TimerTask, 3802
- decaf::util::UUID, 3969
 - ~UUID, 3971
 - clockSequence, 3971
 - compareTo, 3971
 - equals, 3971
 - fromString, 3971
 - getLeastSignificantBits, 3972
 - getMostSignificantBits, 3972
 - nameUUIDFromBytes, 3972
 - node, 3972
 - operator<, 3973
 - operator==, 3973
 - randomUUID, 3973
 - timestamp, 3973
 - toString, 3974
 - UUID, 3970
 - variant, 3974
 - version, 3974
- decaf::util::zip, 177
- decaf::util::zip::Adler32, 722
 - ~Adler32, 723
 - Adler32, 723
 - getValue, 723
 - reset, 723
 - update, 723, 724
- decaf::util::zip::CheckedInputStream, 1137
 - ~CheckedInputStream, 1138
 - CheckedInputStream, 1138
 - doReadArrayBounded, 1138
 - doReadByte, 1138

- getChecksum, 1138
 - skip, 1138
- decaf::util::zip::CheckedOutputStream, 1140
 - ~CheckedOutputStream, 1141
 - CheckedOutputStream, 1140
 - doWriteArrayBounded, 1141
 - doWriteByte, 1141
 - getChecksum, 1141
- decaf::util::zip::Checksum, 1142
 - ~Checksum, 1142
 - getValue, 1142
 - reset, 1143
 - update, 1143, 1144
- decaf::util::zip::CRC32, 1524
 - ~CRC32, 1525
 - CRC32, 1525
 - getValue, 1525
 - reset, 1525
 - update, 1525, 1526
- decaf::util::zip::DataFormatException, 1555
 - ~DataFormatException, 1556
 - clone, 1557
 - DataFormatException, 1555, 1556
- decaf::util::zip::Deflater, 1706
 - ~Deflater, 1708
 - BEST_COMPRESSION, 1714
 - BEST_SPEED, 1714
 - DEFAULT_COMPRESSION, 1714
 - DEFAULT_STRATEGY, 1714
 - deflate, 1709
 - DEFLATED, 1714
 - Deflater, 1708
 - end, 1710
 - FILTERED, 1715
 - finish, 1710
 - finished, 1710
 - getAdler, 1710
 - getBytesRead, 1710
 - getBytesWritten, 1711
 - HUFFMAN_ONLY, 1715
 - needsInput, 1711
 - NO_COMPRESSION, 1715
 - reset, 1711
 - setDictionary, 1711, 1712
 - setInput, 1712, 1713
 - setLevel, 1713
 - setStrategy, 1714
- decaf::util::zip::DeflaterOutputStream, 1716
 - ~DeflaterOutputStream, 1718
 - buf, 1719
 - close, 1718
 - DEFAULT_BUFFER_SIZE, 1719
 - deflate, 1718
 - deflater, 1719
 - DeflaterOutputStream, 1717, 1718
 - doWriteArrayBounded, 1718
 - doWriteByte, 1719
 - finish, 1719
 - isDone, 1719
 - ownDeflater, 1719
- decaf::util::zip::Inflater, 2027
 - ~Inflater, 2029
 - end, 2029
 - finish, 2029
 - finished, 2029
 - getAdler, 2029
 - getBytesRead, 2029
 - getBytesWritten, 2030
 - getRemaining, 2030
 - inflate, 2030, 2031
 - Inflater, 2029
 - needsDictionary, 2031
 - needsInput, 2032
 - reset, 2032
 - setDictionary, 2032, 2033
 - setInput, 2033, 2034
- decaf::util::zip::InflaterInputStream, 2035
 - ~InflaterInputStream, 2038
 - atEOF, 2041
 - available, 2038
 - buff, 2041
 - close, 2039
 - DEFAULT_BUFFER_SIZE, 2041
 - doReadArrayBounded, 2039
 - doReadByte, 2039
 - fill, 2039
 - inflater, 2041
 - InflaterInputStream, 2037, 2038
 - length, 2041
 - mark, 2039
 - markSupported, 2040
 - ownInflater, 2041
 - reset, 2040
 - skip, 2040
- decaf::util::zip::ZipException, 4064
 - ~ZipException, 4065
 - clone, 4066
 - ZipException, 4064, 4065
- DECAF_API
 - decaf/util/Config.h, 4229
- DECAF_CATCH_EXCEPTION_CONVERT
 - decaf/lang/exceptions/ExceptionDe-
fines.h, 4173
- DECAF_CATCH_NOTHROW
 - decaf/lang/exceptions/ExceptionDe-
fines.h, 4173
- DECAF_CATCH_RETHROW

- decaf/lang/exceptions/ExceptionDefines.h, 4174
- DECAF_CATCHALL_NOTHROW
 - decaf/lang/exceptions/ExceptionDefines.h, 4174
- DECAF_CATCHALL_THROW
 - decaf/lang/exceptions/ExceptionDefines.h, 4174
- DECAF_UNUSED
 - decaf/util/Config.h, 4229
- DecafRuntime
 - decaf::internal::DecafRuntime, 1670
- decode
 - decaf::internal::net::URLEncoderDecoder, 3932
 - decaf::lang::Byte, 963
 - decaf::lang::Integer, 2081
 - decaf::lang::Long, 2424
 - decaf::lang::Short, 3443
 - decaf::net::URLDecoder, 3962
- decreaseUsage
 - activemq::util::MemoryUsage, 2513
 - activemq::util::Usage, 3964
- decrementAndGet
 - decaf::util::concurrent::atomic::AtomicInteger, 743
- DedicatedTaskRunner
 - activemq::threads::DedicatedTaskRunner, 1671
- DEF_MEM_LEVEL
 - zutil.h, 4745
- DEF_WBITS
 - zutil.h, 4745
- DEFAULT_BUFFER_SIZE
 - decaf::util::zip::DeflaterOutputStream, 1719
 - decaf::util::zip::InflaterInputStream, 2041
- DEFAULT_COMPRESSION
 - decaf::util::zip::Deflater, 1714
- DEFAULT_DURABLE_TOPIC_PREFETCH
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
- DEFAULT_MAX_BLOCK_SIZE
 - decaf::util::concurrent::ThreadPool, 3782
- DEFAULT_MAX_POOL_SIZE
 - decaf::util::concurrent::ThreadPool, 3782
- DEFAULT_MESSAGE_SIZE
 - activemq::commands::Message, 2532
- DEFAULT_ORDERED_TARGET
 - activemq::commands::ActiveMQDestination, 331
- DEFAULT_PRIORITY
 - activemq::cmsutil::CmsTemplate, 1182
- DEFAULT_QUEUE_BROWSER_PREFETCH
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
- DEFAULT_QUEUE_PREFETCH
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
- DEFAULT_STRATEGY
 - decaf::util::zip::Deflater, 1714
- DEFAULT_TIME_TO_LIVE
 - activemq::cmsutil::CmsTemplate, 1182
- DEFAULT_TOPIC_PREFETCH
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
- DEFAULT_URI
 - activemq::core::ActiveMQConnectionFactory, 302
- DEFAULT_VERSION
 - activemq::wireformat::openwire::OpenWireFormat, 2898
- DefaultPrefetchPolicy
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
- DefaultRedeliveryPolicy
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
- defaults
 - decaf::util::Properties, 3134
- DefaultServerSocketFactory
 - decaf::internal::net::DefaultServerSocketFactory, 1683
- DefaultSocketFactory
 - decaf::internal::net::DefaultSocketFactory, 1688
- DefaultSSLContext
 - decaf::internal::net::ssl::DefaultSSLContext, 1691
- DefaultSSLServerSocketFactory
 - decaf::internal::net::ssl::DefaultSSLServerSocketFactory, 1694
- DefaultSSLSocketFactory
 - decaf::internal::net::ssl::DefaultSSLSocketFactory, 1699
- deflate
 - decaf::util::zip::Deflater, 1709
 - decaf::util::zip::DeflaterOutputStream, 1718
- deflate.h
 - _dist_code, 4727
 - _length_code, 4727
 - _tr_tally_dist, 4726
 - _tr_tally_lit, 4726
 - BL_CODES, 4726
 - BUSY_STATE, 4727

- Code, 4727
- COMMENT_STATE, 4727
- ct_data, 4727
- d_code, 4727
- D_CODES, 4727
- Dad, 4727
- deflate_state, 4727
- EXTRA_STATE, 4727
- FINISH_STATE, 4727
- Freq, 4727
- GZIP, 4727
- HCRC_STATE, 4727
- HEAP_SIZE, 4727
- INIT_STATE, 4727
- IPos, 4727
- L_CODES, 4727
- Len, 4727
- LENGTH_CODES, 4727
- LITERALS, 4727
- MAX_BITS, 4727
- MAX_DIST, 4727
- max_insert_length, 4727
- MIN_LOOKAHEAD, 4727
- NAME_STATE, 4727
- OF, 4727
- Pos, 4727
- Posf, 4727
- put_byte, 4727
- static_tree_desc, 4727
- tree_desc, 4727
- WIN_INIT, 4727
- deflate_state
 - deflate.h, 4727
- DEFLATED
 - decaf::util::zip::Deflater, 1714
- deflateInit
 - zlib.h, 4741
- deflateInit2
 - zlib.h, 4741
- Deflater
 - decaf::util::zip::Deflater, 1708
- deflater
 - decaf::util::zip::DeflaterOutputStream, 1719
- DeflaterOutputStream
 - decaf::util::zip::DeflaterOutputStream, 1717, 1718
- deleteIfCancelled
 - decaf::internal::util::TimerTaskHeap, 3805
- deliverAcks
 - activemq::core::ActiveMQConsumer, 314
 - activemq::core::ActiveMQSession, 526
- DELIVERY_MODE
 - cms::DeliveryMode, 1721
- deliverySequenceId
 - activemq::commands::MessageDispatchNotification, 2634
- depth
 - internal_state, 2120
- dequeue
 - activemq::core::ActiveMQConsumer, 314
 - activemq::core::MessageDispatchChannel, 2600
- dequeueNoWait
 - activemq::core::MessageDispatchChannel, 2601
- deQueueTask
 - decaf::util::concurrent::ThreadPool, 3779
- descriptor
 - decaf::io::FileDescriptor, 1892
- destination
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3066
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3176
 - activemq::commands::ConsumerControl, 1405
 - activemq::commands::ConsumerInfo, 1466
 - activemq::commands::DestinationInfo, 1731
 - activemq::commands::JournalQueueAck, 2158
 - activemq::commands::JournalTopicAck, 2187
 - activemq::commands::Message, 2532
 - activemq::commands::MessageAck, 2564
 - activemq::commands::MessageDispatch, 2598
 - activemq::commands::MessageDispatchNotification, 2634
 - activemq::commands::MessagePull, 2743
 - activemq::commands::ProducerInfo, 3100
 - activemq::commands::SubscriptionInfo, 3675
- DESTINATION_ADD_OPERATION
 - activemq::core::ActiveMQConstants, 308
- DESTINATION_REMOVE_OPERATION
 - activemq::core::ActiveMQConstants, 308
- DestinationActions
 - activemq::core::ActiveMQConstants, 308
- DestinationInfo
 - activemq::commands::DestinationInfo, 1728
- DestinationInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::DestinationInfo, 1745
 - activemq::wireformat::openwire::marshal::v2::DestinationInfo, 1733

- activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller, 1102
- 1737
- direct
- activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller, 1741
- DISCONNECT
- activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller; stomp::StompCommandConstants, 1753
- 3631
- activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller, 1749
- activemq::commands::DiscoveryEvent, 1759
- DiscoveryEventMarshaller
- DestinationOption
- activemq::core::ActiveMQConstants, 308
- DestinationType
- cms::Destination, 1723
- destOptionMap
- activemq::core::ActiveMQConstants::StaticInitializer, 1767
- 3588
- destOptions
- activemq::core::ActiveMQConstants::StaticInitializer, 1775
- 3588
- destroy
- activemq::cmsutil::CmsAccessor, 1155
- activemq::cmsutil::CmsDestinationAccessor, 1158
- activemq::cmsutil::CmsTemplate, 1173
- activemq::cmsutil::DestinationResolver, 1756
- activemq::cmsutil::DynamicDestinationResolver, 1822
- activemq::cmsutil::ResourceLifecycleManager, 3284
- activemq::commands::ActiveMQTempQueue, DispatchData, 606
- activemq::commands::ActiveMQTempTopic, DIST, 635
- cms::TemporaryQueue, 3759
- cms::TemporaryTopic, 3761
- decaf::internal::util::concurrent::ConditionImpl, 1257
- decaf::internal::util::concurrent::MutexImpl, 2788
- decaf::util::logging::LogWriter, 2418
- destroyDestination
- activemq::core::ActiveMQConnection, 279, 280
- destroyMarshalers
- activemq::wireformat::openwire::OpenWireFormat, 2890
- destroyResources
- decaf::internal::util::ResourceLifecycleManager, 3281
- DICT
- inflate.h, 4732
- DICTID
- inflate.h, 4732
- digit
- activemq::core::ActiveMQConsumer, 314
- activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller, 1779
- activemq::wireformat::openwire::marshal::v2::DiscoveryEventMarshaller, 1771
- activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller, 1775
- activemq::wireformat::openwire::marshal::v4::DiscoveryEventMarshaller, 1783
- activemq::wireformat::openwire::marshal::v5::DiscoveryEventMarshaller, 1763
- dispatch
- activemq::core::ActiveMQConsumer, 314
- activemq::core::ActiveMQSession, 526
- activemq::core::Dispatcher, 1787
- dispatchAsync
- activemq::commands::ConsumerInfo, 1466
- activemq::commands::ProducerInfo, 3100
- DispatchData
- activemq::core::DispatchData, 1786
- inflate.h, 4733
- distbits
- inflate_state, 2025
- distcode
- inflate_state, 2025
- DISTEXT
- inflate.h, 4733
- DISTS
- infrees.h, 4734
- dl
- ct_data_s, 1527
- dmax
- inflate_state, 2025
- doAppendChar
- decaf::io::Writer, 4023
- doAppendCharSequence
- decaf::io::Writer, 4024
- doAppendCharSequenceStartEnd
- decaf::io::Writer, 4024
- doClose
- activemq::core::ActiveMQConsumer, 314
- doCreateComposite

- activemq::transport::failover::FailoverTransportFactory, 1886
- activemq::transport::mock::MockTransportFactory, 2780
- activemq::transport::tcp::SslTransportFactory, 3576
- activemq::transport::tcp::TcpTransportFactory, 3757
- doInCms
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3065
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
 - activemq::cmsutil::CmsTemplate::SendExecutor, 3350
 - activemq::cmsutil::ProducerCallback, 3064
 - activemq::cmsutil::SessionCallback, 3378
- DONE
 - inflate.h, 4733
- done
 - gz_header_s, 1975
- doReadArray
 - decaf::io::FilterInputStream, 1897
 - decaf::io::InputStream, 2045
 - decaf::io::Reader, 3164
- doReadArrayBounded
 - activemq::io::LoggingInputStream, 2399
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
 - decaf::internal::net::tcp::TcpSocketInputStream, 3748
 - decaf::io::BlockingByteArrayInputStream, 841
 - decaf::io::BufferedInputStream, 937
 - decaf::io::ByteArrayInputStream, 1024
 - decaf::io::FilterInputStream, 1897
 - decaf::io::InputStream, 2045
 - decaf::io::InputStreamReader, 2054
 - decaf::io::PushbackInputStream, 3144
 - decaf::io::Reader, 3164
 - decaf::util::zip::CheckedInputStream, 1138
 - decaf::util::zip::InflaterInputStream, 2039
- doReadByte
 - activemq::io::LoggingInputStream, 2399
 - decaf::internal::io::StandardInputStream, 3582
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
 - decaf::internal::net::tcp::TcpSocketInputStream, 3749
 - decaf::io::BlockingByteArrayInputStream, 841
 - decaf::io::BufferedInputStream, 937
 - decaf::io::ByteArrayInputStream, 1024
- decaf::io::FilterInputStream, 1897
- decaf::io::InputStream, 2046
- decaf::io::PushbackInputStream, 3144
- decaf::util::zip::CheckedInputStream, 1138
- decaf::util::zip::InflaterInputStream, 2039
- doReadChar
- doReadCharBuffer
- decaf::io::Reader, 3164
- doReadCharVector
- decaf::io::Reader, 3165
- doStartTransaction
 - activemq::core::ActiveMQSession, 526
- Double
 - decaf::lang::Double, 1790
- DOUBLE_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- DoubleArrayBuffer
 - decaf::internal::nio::DoubleArrayBuffer, 1802, 1803
- DoubleBuffer
 - decaf::nio::DoubleBuffer, 1811
- doubleToLongBits
 - decaf::lang::Double, 1791
- doubleToRawLongBits
 - decaf::lang::Double, 1792
- doubleValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
 - decaf::lang::Byte, 963
 - decaf::lang::Character, 1103
 - decaf::lang::Double, 1792
 - decaf::lang::Float, 1907
 - decaf::lang::Integer, 2081
 - decaf::lang::Long, 2424
 - decaf::lang::Number, 2836
 - decaf::lang::Short, 3443
 - decaf::util::concurrent::atomic::AtomicInteger, 743
- doUnmarshal
 - activemq::wireformat::openwire::OpenWireFormat, 2890
- doWriteArray
 - decaf::io::BufferedOutputStream, 941
 - decaf::io::FilterOutputStream, 1901
 - decaf::io::OutputStream, 2909
 - decaf::io::Writer, 4024
- doWriteArrayBounded
 - activemq::io::LoggingOutputStream, 2401
 - decaf::internal::io::StandardErrorOutputStream, 3580
 - decaf::internal::io::StandardOutputStream, 3585

- decaf::internal::net::ssl::openssl::OpenSSLSocketOutputSteam, 2886
- decaf::internal::net::tcp::TcpSocketOutputStream, 3751
- decaf::io::BufferedOutputStream, 941
- decaf::io::ByteArrayOutputStream, 1029
- decaf::io::DataOutputStream, 1580
- decaf::io::FilterOutputStream, 1902
- decaf::io::OutputStream, 2909
- decaf::io::OutputStreamWriter, 2916
- decaf::io::Writer, 4024
- decaf::util::zip::CheckedOutputStream, 1141
- decaf::util::zip::DeflaterOutputStream, 1718
- doWriteByte
 - activemq::io::LoggingOutputStream, 2401
- decaf::internal::io::StandardErrorOutputStream, 3580
- decaf::internal::io::StandardOutputStream, 3585
- decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream, 2886
- decaf::internal::net::tcp::TcpSocketOutputStream, 3751
- decaf::io::BufferedOutputStream, 941
- decaf::io::ByteArrayOutputStream, 1029
- decaf::io::DataOutputStream, 1580
- decaf::io::FilterOutputStream, 1902
- decaf::io::OutputStream, 2909
- decaf::util::zip::CheckedOutputStream, 1141
- decaf::util::zip::DeflaterOutputStream, 1719
- doWriteChar
 - decaf::io::Writer, 4024
- doWriteString
 - decaf::io::Writer, 4024
- doWriteStringBounded
 - decaf::io::Writer, 4024
- doWriteVector
 - decaf::io::Writer, 4024
- drainPermits
 - decaf::util::concurrent::Semaphore, 3346
- drainTo
 - decaf::util::concurrent::BlockingQueue, 846
 - decaf::util::concurrent::SynchronousQueue, 3719, 3720
- droppable
 - activemq::commands::Message, 2532
- dummy
 - internal_state, 2120
- duplexConnection
 - activemq::commands::BrokerInfo, 903
- decaf::internal::nio::ByteBuffer, 1007
- decaf::internal::nio::CharArrayBuffer, 1114
- decaf::internal::nio::DoubleArrayBuffer, 1805
- decaf::internal::nio::FloatArrayBuffer, 1921
- decaf::internal::nio::IntArrayBuffer, 2062
- decaf::internal::nio::LongArrayBuffer, 2440
- decaf::internal::nio::ShortArrayBuffer, 3455
- decaf::nio::ByteBuffer, 1040
- decaf::nio::CharBuffer, 1126
- decaf::nio::DoubleBuffer, 1813
- decaf::nio::FloatBuffer, 1929
- decaf::nio::IntBuffer, 2070
- decaf::nio::LongBuffer, 2448
- decaf::nio::ShortBuffer, 3463
- DUPS_OK_ACKNOWLEDGE
 - cms::Session, 3368
- dyn_dtree
 - internal_state, 2120
- dyn_output
 - internal_state, 2120
- dyn_tree
 - tree_desc_s, 3905
- DYN_TREES
 - zutil.h, 4745
- dynamicCast
 - decaf::lang::Pointer, 2950
- DynamicDestinationResolver
 - activemq::cmsutil::DynamicDestinationResolver, 1822
- E
 - decaf::lang::Math, 2511
- element
 - decaf::util::AbstractQueue, 196
 - decaf::util::Queue, 3150
- empty
 - decaf::util::StlQueue, 3617
- encode
 - decaf::net::URLEncoder, 3963
- encodeOthers
 - decaf::internal::net::URLEncoderDecoder, 3933
- end
 - decaf::util::zip::Deflater, 1710
 - decaf::util::zip::Inflater, 2029
- ENOUGH
 - inftrees.h, 4734
- ENOUGH_DISTS
 - inftrees.h, 4734
- ENOUGH_LENS
 - inftrees.h, 4734

- enqueue
 - activemq::core::MessageDispatchChannel, 2601
- enqueueFirst
 - activemq::core::MessageDispatchChannel, 2601
- enqueueFront
 - decaf::util::StlQueue, 3618
- enqueueUsage
 - activemq::util::MemoryUsage, 2513
 - activemq::util::Usage, 3964
- ensureCreated
 - decaf::net::ServerSocket, 3357
 - decaf::net::Socket, 3510
- entering
 - decaf::util::logging::Logger, 2390
- Entry
 - decaf::util::Map::Entry, 1824
- eof
 - gz_state, 1977
- EOFException
 - decaf::io::EOFException, 1825, 1826
- equals
 - activemq::commands::ActiveMQBlobMessage, 206
 - activemq::commands::ActiveMQBytesMessage, 237
 - activemq::commands::ActiveMQDestination, 325
 - activemq::commands::ActiveMQMapMessage, 364
 - activemq::commands::ActiveMQMessage, 399
 - activemq::commands::ActiveMQMessageTemplate, 429
 - activemq::commands::ActiveMQObjectMessage, 444
 - activemq::commands::ActiveMQQueue, 484
 - activemq::commands::ActiveMQStreamMessage, 541
 - activemq::commands::ActiveMQTempDestination, 577
 - activemq::commands::ActiveMQTempQueue, 606
 - activemq::commands::ActiveMQTempTopic, 635
 - activemq::commands::ActiveMQTextMessage, 664
 - activemq::commands::ActiveMQTopic, 692
 - activemq::commands::BaseCommand, 759
 - activemq::commands::BaseDataStructure, 832
 - activemq::commands::BooleanExpression, 856
 - activemq::commands::BrokerId, 870
 - activemq::commands::BrokerInfo, 898
 - activemq::commands::ConnectionControl, 1268
 - activemq::commands::ConnectionError, 1297
 - activemq::commands::ConnectionId, 1328, 1329
 - activemq::commands::ConnectionInfo, 1357
 - activemq::commands::ConsumerControl, 1402
 - activemq::commands::ConsumerId, 1431, 1432
 - activemq::commands::ConsumerInfo, 1461
 - activemq::commands::ControlCommand, 1494
 - activemq::commands::DataArrayResponse, 1529
 - activemq::commands::DataResponse, 1584
 - activemq::commands::DataStructure, 1661
 - activemq::commands::DestinationInfo, 1728
 - activemq::commands::DiscoveryEvent, 1759
 - activemq::commands::ExceptionResponse, 1840
 - activemq::commands::FlushCommand, 1938
 - activemq::commands::IntegerResponse, 2092
 - activemq::commands::JournalQueueAck, 2157
 - activemq::commands::JournalTopicAck, 2184
 - activemq::commands::JournalTrace, 2213
 - activemq::commands::JournalTransaction, 2240
 - activemq::commands::KeepAliveInfo, 2267
 - activemq::commands::LastPartialCommand, 2302
 - activemq::commands::LocalTransactionId, 2348, 2349
 - activemq::commands::Message, 2521
 - activemq::commands::MessageAck, 2560
 - activemq::commands::MessageDispatch, 2595
 - activemq::commands::MessageDispatchNotification, 2631
 - activemq::commands::MessageId, 2665
 - activemq::commands::MessagePull, 2740

- activemq::commands::NetworkBridgeFilter, 2794
- activemq::commands::PartialCommand, 2919
- activemq::commands::ProducerAck, 3037
- activemq::commands::ProducerId, 3069
- activemq::commands::ProducerInfo, 3097
- activemq::commands::RemoveInfo, 3195
- activemq::commands::RemoveSubscriptionInfo, 3223
- activemq::commands::ReplayCommand, 3252
- activemq::commands::Response, 3286
- activemq::commands::SessionId, 3381
- activemq::commands::SessionInfo, 3408
- activemq::commands::ShutdownInfo, 3471
- activemq::commands::SubscriptionInfo, 3672
- activemq::commands::TransactionId, 3820
- activemq::commands::TransactionInfo, 3848
- activemq::commands::WireFormatInfo, 3985
- activemq::commands::XATransactionId, 4033
- decaf::lang::Boolean, 852
- decaf::lang::Byte, 963
- decaf::lang::Character, 1103
- decaf::lang::Comparable, 1215
- decaf::lang::Double, 1792, 1793
- decaf::lang::Float, 1907, 1908
- decaf::lang::Integer, 2081, 2082
- decaf::lang::Long, 2424, 2425
- decaf::lang::Short, 3443
- decaf::net::URI, 3925
- decaf::nio::ByteBuffer, 1040
- decaf::nio::CharBuffer, 1126
- decaf::nio::DoubleBuffer, 1814
- decaf::nio::FloatBuffer, 1929
- decaf::nio::IntBuffer, 2070
- decaf::nio::LongBuffer, 2448
- decaf::nio::ShortBuffer, 3463
- decaf::security::cert::Certificate, 1087
- decaf::security::Principal, 3026
- decaf::util::AbstractCollection, 185
- decaf::util::Collection, 1189
- decaf::util::concurrent::ConcurrentStlMap, 1239
- decaf::util::concurrent::SynchronousQueue, 3720
- decaf::util::concurrent::TimeUnit, 3810
- decaf::util::Date, 1667
- decaf::util::logging::Level, 2334
- decaf::util::Map, 2463
- decaf::util::Properties, 3128
- decaf::util::StlList, 3596
- decaf::util::StlMap, 3607, 3608
- decaf::util::StlSet, 3627
- decaf::util::UUID, 3971
- err
 - decaf::io::FileDescriptor, 1892
 - gz_state, 1977
- ERR_MSG
 - zutil.h, 4745
- ERR_RETURN
 - zutil.h, 4745
- Error
 - decaf::util::logging, 176
- error
 - decaf::util::logging::ErrorManager, 1829
 - decaf::util::logging::SimpleLogger, 3502
- ERROR_CMD
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- ErrorManager
 - decaf::util::logging::ErrorManager, 1829
- Exception
 - decaf::lang::Exception, 1832, 1833
- exception
 - activemq::commands::ConnectionError, 1299
 - activemq::commands::ExceptionResponse, 1841
- ExceptionResponse
 - activemq::commands::ExceptionResponse, 1840
- ExceptionResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::ExceptionResponse, 1863
 - activemq::wireformat::openwire::marshal::v2::ExceptionResponse, 1847
 - activemq::wireformat::openwire::marshal::v3::ExceptionResponse, 1851
 - activemq::wireformat::openwire::marshal::v4::ExceptionResponse, 1859
 - activemq::wireformat::openwire::marshal::v5::ExceptionResponse, 1855
 - activemq::wireformat::openwire::marshal::v6::ExceptionResponse, 1843
- exclusive
 - activemq::commands::ActiveMQDestination, 331
 - activemq::commands::ConsumerInfo, 1466
- execute
 - activemq::cmsutil::CmsTemplate, 1174
 - activemq::core::ActiveMQSessionExecutor, 534
 - decaf::util::concurrent::Executor, 1870

- executeFirst
 - activemq::core::ActiveMQSessionExecutor, 534
- ExecutionException
 - decaf::util::concurrent::ExecutionException, 1866, 1867
- exit
 - activemq::commands::ConnectionControl, 1271
- exiting
 - decaf::util::logging::Logger, 2390
- EXLEN
 - inflate.h, 4732
- expiration
 - activemq::commands::Message, 2532
- EXTRA
 - inflate.h, 4732
- extra
 - gz_header_s, 1975
 - inflate_state, 2025
- extra_len
 - gz_header_s, 1975
- extra_max
 - gz_header_s, 1975
- EXTRA_STATE
 - deflate.h, 4727
- F_OPEN
 - zutil.h, 4745
- failIfReadOnlyBody
 - activemq::commands::ActiveMQMessageTemplate, 429
- failIfReadOnlyProperties
 - activemq::commands::ActiveMQMessageTemplate, 429
- failIfWriteOnlyBody
 - activemq::commands::ActiveMQMessageTemplate, 429
- FailoverTransport
 - activemq::transport::failover::FailoverTransport, 1875
- FailoverTransportListener
 - activemq::transport::failover::FailoverTransport, 1884
 - activemq::transport::failover::FailoverTransportListener, 1889
- Fatal
 - decaf::util::logging, 176
- fatal
 - decaf::util::logging::SimpleLogger, 3502
- faultTolerant
 - activemq::commands::ConnectionControl, 1271
- activemq::commands::ConnectionInfo, 1360
- faultTolerantConfiguration
 - activemq::commands::BrokerInfo, 903
- fc
 - ct_data_s, 1527
- fd
 - decaf::net::SocketImpl, 3536
 - gz_state, 1977
- FileDescriptor
 - decaf::io::FileDescriptor, 1892
- FileName
 - activemq::commands::BrokerError::StackTraceElement, 3578
- fill
 - decaf::util::zip::InflaterInputStream, 2039
- FILTERED
 - decaf::util::zip::Deflater, 1715
- FilterInputStream
 - decaf::io::FilterInputStream, 1896
- FilterOutputStream
 - decaf::io::FilterOutputStream, 1901
- find
 - decaf::internal::util::TimerTaskHeap, 3805
- findFactory
 - activemq::transport::TransportRegistry, 3903
 - activemq::wireformat::WireFormatRegistry, 4018
- FINE
 - decaf::util::logging::Level, 2335
 - decaf::util::logging::Logger, 2390
- FINER
 - decaf::util::logging::Level, 2335
- finer
 - decaf::util::logging::Logger, 2391
- FINEST
 - decaf::util::logging::Level, 2335
- finest
 - decaf::util::logging::Logger, 2391
- finish
 - decaf::util::zip::Deflater, 1710
 - decaf::util::zip::DeflaterOutputStream, 1719
 - decaf::util::zip::Inflater, 2029
- FINISH_STATE
 - deflate.h, 4727
- finished
 - decaf::util::zip::Deflater, 1710
 - decaf::util::zip::Inflater, 2029
- fire
 - activemq::core::ActiveMQConnection, 280
 - activemq::core::ActiveMQSession, 526

- activemq::transport::TransportFilter, 3893
- fireCommand
 - activemq::transport::mock::MockTransport, 2770
- fireException
 - activemq::transport::mock::MockTransport, 2771
- firstMessageId
 - activemq::commands::MessageAck, 2564
- firstNakNumber
 - activemq::commands::ReplayCommand, 3253
- FLAGS
 - inflate.h, 4732
- flags
 - inflate_state, 2025
- flip
 - decaf::nio::Buffer, 931
- Float
 - decaf::lang::Float, 1906
- FLOAT_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- FloatArrayBuffer
 - decaf::internal::nio::FloatArrayBuffer, 1918, 1919
- FloatBuffer
 - decaf::nio::FloatBuffer, 1927
- floatToIntBits
 - decaf::lang::Float, 1908
- floatToRawIntBits
 - decaf::lang::Float, 1908
- floatValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
 - decaf::lang::Byte, 963
 - decaf::lang::Character, 1103
 - decaf::lang::Double, 1793
 - decaf::lang::Float, 1909
 - decaf::lang::Integer, 2082
 - decaf::lang::Long, 2425
 - decaf::lang::Number, 2836
 - decaf::lang::Short, 3443
 - decaf::util::concurrent::atomic::AtomicInteger, 743
- floor
 - decaf::lang::Math, 2501
- flush
 - activemq::commands::ConsumerControl, 1405
 - decaf::internal::io::StandardErrorOutputStream, 3580
 - decaf::internal::io::StandardOutputStream, 3585
 - decaf::io::BufferedOutputStream, 941
 - decaf::io::FilterOutputStream, 1902
 - decaf::io::Flushable, 1936
 - decaf::io::OutputStream, 2910
 - decaf::io::OutputStreamWriter, 2916
 - decaf::util::logging::Handler, 1979
 - decaf::util::logging::StreamHandler, 3650
- FLUSH_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- FlushCommand
 - activemq::commands::FlushCommand, 1938
- FlushCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::FlushCommand, 1957
 - activemq::wireformat::openwire::marshal::v2::FlushCommand, 1945
 - activemq::wireformat::openwire::marshal::v3::FlushCommand, 1949
 - activemq::wireformat::openwire::marshal::v4::FlushCommand, 1953
 - activemq::wireformat::openwire::marshal::v5::FlushCommand, 1961
 - activemq::wireformat::openwire::marshal::v6::FlushCommand, 1941
- format
 - decaf::util::logging::Formatter, 1964
 - decaf::util::logging::SimpleFormatter, 3500
 - decaf::util::logging::XMLFormatter, 4060
- FORMAT_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- formatId
 - activemq::commands::XATransactionId, 4035
- formatMessage
 - decaf::util::logging::Formatter, 1965
- Freq
 - deflate.h, 4727
- freq
 - ct_data_s, 1527
- fromStream
 - activemq::wireformat::stomp::StompFrame, 3634
- fromString
 - decaf::util::UUID, 3971
- front
 - decaf::util::StlQueue, 3618
- FutureResponse
 - activemq::transport::correlator::FutureResponse, 1969
- GeneralSecurityException
 - decaf::security::GeneralSecurityException, 1971, 1972
- generateId

- activemq::util::IdGenerator, 1990
- generation
 - decaf::util::concurrent::ConditionHandle, 1255
- GENERIC_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- GenericResource
 - decaf::internal::util::GenericResource, 1974
- get
 - decaf::internal::nio::ByteBuffer, 1007, 1008
 - decaf::internal::nio::CharArrayBuffer, 1115
 - decaf::internal::nio::DoubleArrayBuffer, 1805, 1806
 - decaf::internal::nio::FloatArrayBuffer, 1921, 1922
 - decaf::internal::nio::IntArrayBuffer, 2062, 2063
 - decaf::internal::nio::LongArrayBuffer, 2440, 2441
 - decaf::internal::nio::ShortArrayBuffer, 3455, 3456
 - decaf::internal::util::ByteArrayAdapter, 976
 - decaf::lang::ArrayPointer, 733
 - decaf::lang::Pointer, 2950
 - decaf::nio::ByteBuffer, 1040–1042
 - decaf::nio::CharBuffer, 1126, 1127
 - decaf::nio::DoubleBuffer, 1814, 1815
 - decaf::nio::FloatBuffer, 1929–1931
 - decaf::nio::IntBuffer, 2070–2072
 - decaf::nio::LongBuffer, 2448–2450
 - decaf::nio::ShortBuffer, 3463–3465
 - decaf::util::concurrent::atomic::AtomicBoolean, 739
 - decaf::util::concurrent::atomic::AtomicInteger, 743
 - decaf::util::concurrent::atomic::AtomicReference, 750
 - decaf::util::concurrent::ConcurrentStlMap, 1239, 1240
 - decaf::util::concurrent::Future, 1967
 - decaf::util::List, 2339
 - decaf::util::Map, 2463, 2464
 - decaf::util::StlList, 3597
 - decaf::util::StlMap, 3608
- getAckHandler
 - activemq::commands::Message, 2521
- getAckMode
 - activemq::commands::SessionInfo, 3408
- getAcknowledgeMode
 - activemq::cmsutil::PooledSession, 2965
 - activemq::core::ActiveMQSession, 526
 - cms::Session, 3375
- getAckType
 - activemq::commands::MessageAck, 2561
- getAdditionalPredicate
 - activemq::commands::ConsumerInfo, 1462
- getAddress
 - decaf::net::InetAddress, 2018
- getAdler
 - decaf::util::zip::Deflater, 1710
 - decaf::util::zip::Inflater, 2029
- getAlgorithm
 - decaf::security::Key, 2294
- getAndAdd
 - decaf::util::concurrent::atomic::AtomicInteger, 744
- getAndDecrement
 - decaf::util::concurrent::atomic::AtomicInteger, 744
- getAndIncrement
 - decaf::util::concurrent::atomic::AtomicInteger, 744
- getAndSet
 - decaf::util::concurrent::atomic::AtomicBoolean, 739
 - decaf::util::concurrent::atomic::AtomicInteger, 744
 - decaf::util::concurrent::atomic::AtomicReference, 750
- getAnonymousLogger
 - decaf::util::logging::Logger, 2391
- getAnyAddress
 - decaf::net::InetAddress, 2018
- getAprPool
 - decaf::internal::AprPool, 728
- getArrival
 - activemq::commands::Message, 2522
- getAuthority
 - decaf::internal::net::URIType, 3954
- getBacklog
 - decaf::util::concurrent::ThreadPool, 3779
- getBackOffMultiplier
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
 - activemq::core::RedeliveryPolicy, 3178
 - activemq::transport::failover::FailoverTransport, 1876
- getBackup
 - activemq::transport::failover::BackupTransportPool, 756
- getBackupPoolSize
 - activemq::transport::failover::BackupTransportPool, 756
 - activemq::transport::failover::FailoverTransport, 1877

- getBasicConstraints
 - decaf::security::cert::X509Certificate, 4029
- getBlockSize
 - decaf::util::concurrent::ThreadPool, 3779
- getBody
 - activemq::wireformat::stomp::StompFrame, 3635
- getBodyBytes
 - activemq::commands::ActiveMQBytesMessage, 237
 - cms::BytesMessage, 1059
- getBodyLength
 - activemq::commands::ActiveMQBytesMessage, 237
 - activemq::wireformat::stomp::StompFrame, 3635
 - cms::BytesMessage, 1060
- getBool
 - activemq::util::PrimitiveList, 2983
 - activemq::util::PrimitiveMap, 2994
 - activemq::util::PrimitiveValueNode, 3018
- getBoolean
 - activemq::commands::ActiveMQMapMessage, 364
 - cms::MapMessage, 2474
- getBooleanProperty
 - activemq::commands::ActiveMQMessageTemplate, 429
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2734
 - cms::Message, 2540
- getBranchQualifier
 - activemq::commands::XATransactionId, 4033
- getBrokerId
 - activemq::commands::BrokerInfo, 898, 899
- getBrokerInTime
 - activemq::commands::Message, 2522
- getBrokerName
 - activemq::commands::BrokerInfo, 899
 - activemq::commands::DiscoveryEvent, 1759, 1760
- getBrokerOutTime
 - activemq::commands::Message, 2522
- getBrokerPath
 - activemq::commands::ConnectionInfo, 1357
 - activemq::commands::ConsumerInfo, 1462
 - activemq::commands::DestinationInfo, 1729
 - activemq::commands::Message, 2522
 - activemq::commands::ProducerInfo, 3098
- getBrokerSequenceId
 - activemq::commands::MessageId, 2665
- getBrokerUploadUrl
 - activemq::commands::BrokerInfo, 899
- getBrokerURL
 - activemq::commands::BrokerInfo, 899
 - activemq::core::ActiveMQConnection, 280
 - activemq::core::ActiveMQConnectionFactory, 296
- getByAddress
 - decaf::net::InetAddress, 2019
- getByte
 - activemq::commands::ActiveMQMapMessage, 364
 - activemq::util::PrimitiveList, 2983
 - activemq::util::PrimitiveMap, 2994
 - activemq::util::PrimitiveValueNode, 3019
 - cms::MapMessage, 2474
- getByteArray
 - activemq::util::PrimitiveList, 2983
 - activemq::util::PrimitiveMap, 2994
 - activemq::util::PrimitiveValueNode, 3019
 - decaf::internal::util::ByteArrayAdapter, 976
- getByteProperty
 - activemq::commands::ActiveMQMessageTemplate, 430
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2734
 - cms::Message, 2540
- getBytePropertyInterceptor
 - activemq::commands::ActiveMQMapMessage, 365
 - cms::MapMessage, 2475
- getBytesRead
 - decaf::util::zip::Deflater, 1710
 - decaf::util::zip::Inflater, 2029
- getBytesWritten
 - decaf::util::zip::Deflater, 1711
 - decaf::util::zip::Inflater, 2030
- getCacheSize
 - activemq::commands::WireFormatInfo, 3985
 - activemq::wireformat::openwire::OpenWireFormat, 2891
- getCapacity
 - decaf::internal::util::ByteArrayAdapter, 977
- getCause
 - activemq::commands::BrokerError, 864
 - cms::CMSException, 1161
 - decaf::lang::Exception, 1835
 - decaf::lang::Throwable, 3785
- getChar
 - activemq::commands::ActiveMQMapMessage, 365

- activemq::util::PrimitiveList, 2984
- activemq::util::PrimitiveMap, 2995
- activemq::util::PrimitiveValueNode, 3019
- cms::MapMessage, 2475
- decaf::internal::nio::ByteBuffer, 1008
- decaf::internal::util::ByteArrayAdapter, 977
- decaf::nio::ByteBuffer, 1042
- getCharArray
 - decaf::internal::util::ByteArrayAdapter, 977
- getCharCapacity
 - decaf::internal::util::ByteArrayAdapter, 977
- getChecksum
 - decaf::util::zip::CheckedInputStream, 1138
 - decaf::util::zip::CheckedOutputStream, 1141
- getCipherSuites
 - decaf::net::ssl::SSLParameters, 3552
- getClientID
 - activemq::core::ActiveMQConnection, 280
 - cms::Connection, 1264
- getClientId
 - activemq::commands::ActiveMQDestination, 326
 - activemq::commands::ConnectionInfo, 1357
 - activemq::commands::JournalTopicAck, 2184, 2185
 - activemq::commands::RemoveSubscriptionInfo, 3223, 3224
 - activemq::commands::SubscriptionInfo, 3672, 3673
 - activemq::core::ActiveMQConnectionFactory, 296
- getCloseTimeout
 - activemq::core::ActiveMQConnection, 281
 - activemq::core::ActiveMQConnectionFactory, 297
- getCluster
 - activemq::commands::Message, 2522
- getCMSCorrelationID
 - activemq::commands::ActiveMQMessageTemplate, 430
 - cms::Message, 2540
- getCMSDeliveryMode
 - activemq::commands::ActiveMQMessageTemplate, 430
 - cms::Message, 2541
- getCMSDestination
 - activemq::commands::ActiveMQDestination, 326
- activemq::commands::ActiveMQMessageTemplate, 431
- activemq::commands::ActiveMQQueue, 485
- activemq::commands::ActiveMQTempQueue, 606
- activemq::commands::ActiveMQTempTopic, 635
- activemq::commands::ActiveMQTopic, 693
- cms::Message, 2541
- getCMSExpiration
 - activemq::commands::ActiveMQMessageTemplate, 431
 - cms::Message, 2542
- getCMSMajorVersion
 - activemq::core::ActiveMQConnectionMetaData, 304
 - cms::ConnectionMetaData, 1386
- getCMSMessageID
 - activemq::commands::ActiveMQMessageTemplate, 431
 - cms::Message, 2542
- getCMSMinorVersion
 - activemq::core::ActiveMQConnectionMetaData, 304
 - cms::ConnectionMetaData, 1386
- getCMSPriority
 - activemq::commands::ActiveMQMessageTemplate, 431
 - cms::Message, 2543
- getCMSProperties
 - activemq::commands::ActiveMQQueue, 485
 - activemq::commands::ActiveMQTempQueue, 606
 - activemq::commands::ActiveMQTempTopic, 635
 - activemq::commands::ActiveMQTopic, 693
 - cms::Destination, 1724
- getCMSProviderName
 - activemq::core::ActiveMQConnectionMetaData, 304
 - cms::ConnectionMetaData, 1386
- getCMSRedelivered
 - activemq::commands::ActiveMQMessageTemplate, 432
 - cms::Message, 2543
- getCMSReplyTo
 - activemq::commands::ActiveMQMessageTemplate, 432
 - cms::Message, 2544
- getCMSTimestamp
 - activemq::commands::ActiveMQMessageTemplate, 432

- cms::Message, 2544
- getCMSType
 - activemq::commands::ActiveMQMessageTemplate, 433
 - cms::Message, 2545
- getCMSVersion
 - activemq::core::ActiveMQConnectionMetaData, 305
 - cms::ConnectionMetaData, 1386
- getCMSXPropertyNames
 - activemq::core::ActiveMQConnectionMetaData, 305
 - cms::ConnectionMetaData, 1387
- getCollisionAvoidancePercent
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
 - activemq::core::RedeliveryPolicy, 3179
- getCommand
 - activemq::commands::ControlCommand, 1494, 1495
 - activemq::wireformat::stomp::StompFrame, 3635
- getCommandId
 - activemq::commands::BaseCommand, 760
 - activemq::commands::Command, 1195
 - activemq::commands::PartialCommand, 2919
- getCommands
 - activemq::state::TransactionState, 3876
- getComponents
 - activemq::util::CompositeData, 1220
- getConnectedBrokers
 - activemq::commands::ConnectionControl, 1269
- getConnection
 - activemq::commands::Message, 2522
 - activemq::core::ActiveMQSession, 527
- getConnectionFactory
 - activemq::cmsutil::CmsAccessor, 1155
- getConnectionId
 - activemq::commands::BrokerInfo, 899
 - activemq::commands::ConnectionError, 1297, 1298
 - activemq::commands::ConnectionInfo, 1357
 - activemq::commands::ConsumerId, 1432
 - activemq::commands::DestinationInfo, 1729
 - activemq::commands::LocalTransactionId, 2349
 - activemq::commands::ProducerId, 3069
 - activemq::commands::RemoveSubscriptionInfo, 3224
 - activemq::commands::SessionId, 3381
 - activemq::commands::TransactionInfo, 3848, 3849
- activemq::core::ActiveMQConnection, 281
- getConnectionInfo
 - activemq::core::ActiveMQConnection, 281
- getConsumerId
 - activemq::commands::ConsumerControl, 1403
 - activemq::commands::ConsumerInfo, 1462
 - activemq::commands::MessageAck, 2561
 - activemq::commands::MessageDispatch, 2595, 2596
 - activemq::commands::MessageDispatchNotification, 2631, 2632
 - activemq::commands::MessagePull, 2740, 2741
 - activemq::core::ActiveMQConsumer, 314
 - activemq::core::DispatchData, 1786
- getConsumerInfo
 - activemq::core::ActiveMQConsumer, 315
- getConsumerState
 - activemq::state::SessionState, 3438
- getConsumerStates
 - activemq::state::SessionState, 3438
- getContent
 - activemq::commands::Message, 2522, 2523
- getContext
 - decaf::internal::net::ssl::DefaultSSLContext, 1691
- getCorrelationId
 - activemq::commands::Message, 2523
 - activemq::commands::MessagePull, 2741
 - activemq::commands::Response, 3286
- getCount
 - decaf::util::concurrent::CountDownLatch, 1523
- getData
 - activemq::commands::DataArrayResponse, 1529, 1530
 - activemq::commands::DataResponse, 1584, 1585
 - activemq::commands::PartialCommand, 2920
- getDataStructure
 - activemq::commands::Message, 2523
- getDataStructureType
 - activemq::commands::ActiveMQBlobMessage, 206
 - activemq::commands::ActiveMQBytesMessage, 238
 - activemq::commands::ActiveMQDestination, 326
 - activemq::commands::ActiveMQMapMessage, 365

- activemq::commands::ActiveMQMessage, 399
- activemq::commands::ActiveMQObjectMessage, 445
- activemq::commands::ActiveMQQueue, 485
- activemq::commands::ActiveMQStreamMessage, 541
- activemq::commands::ActiveMQTempDestination, 578
- activemq::commands::ActiveMQTempQueue, 607
- activemq::commands::ActiveMQTempTopic, 636
- activemq::commands::ActiveMQTextMessage, 664
- activemq::commands::ActiveMQTopic, 693
- activemq::commands::BrokerError, 865
- activemq::commands::BrokerId, 870
- activemq::commands::BrokerInfo, 899
- activemq::commands::ConnectionControl, 1269
- activemq::commands::ConnectionError, 1298
- activemq::commands::ConnectionId, 1329
- activemq::commands::ConnectionInfo, 1357
- activemq::commands::ConsumerControl, 1403
- activemq::commands::ConsumerId, 1432
- activemq::commands::ConsumerInfo, 1462
- activemq::commands::ControlCommand, 1495
- activemq::commands::DataArrayResponse, 1530
- activemq::commands::DataResponse, 1585
- activemq::commands::DataStructure, 1662
- activemq::commands::DestinationInfo, 1729
- activemq::commands::DiscoveryEvent, 1760
- activemq::commands::ExceptionResponse, 1840
- activemq::commands::FlushCommand, 1938
- activemq::commands::IntegerResponse, 2092
- activemq::commands::JournalQueueAck, 2157
- activemq::commands::JournalTopicAck, 2185
- activemq::commands::JournalTrace, 2213
- activemq::commands::JournalTransaction, 2240
- activemq::commands::KeepAliveInfo, 2267
- activemq::commands::LastPartialCommand, 2302
- activemq::commands::LocalTransactionId, 2349
- activemq::commands::Message, 2523
- activemq::commands::MessageAck, 2561
- activemq::commands::MessageDispatch, 2596
- activemq::commands::MessageDispatchNotification, 2632
- activemq::commands::MessageId, 2665
- activemq::commands::MessagePull, 2741
- activemq::commands::NetworkBridgeFilter, 2794
- activemq::commands::PartialCommand, 2920
- activemq::commands::ProducerAck, 3037
- activemq::commands::ProducerId, 3069
- activemq::commands::ProducerInfo, 3098
- activemq::commands::RemoveInfo, 3195
- activemq::commands::RemoveSubscriptionInfo, 3224
- activemq::commands::ReplayCommand, 3252
- activemq::commands::Response, 3287
- activemq::commands::SessionId, 3381
- activemq::commands::SessionInfo, 3409
- activemq::commands::ShutdownInfo, 3471
- activemq::commands::SubscriptionInfo, 3673
- activemq::commands::TransactionId, 3821
- activemq::commands::TransactionInfo, 3849
- activemq::commands::WireFormatInfo, 3986
- activemq::commands::XATransactionId, 4033
- activemq::wireformat::openwire::marshal::DataStreamMarshal, 1617
- activemq::wireformat::openwire::marshal::v1::ActiveMQBlobM, 214
- activemq::wireformat::openwire::marshal::v1::ActiveMQBytesI, 254
- activemq::wireformat::openwire::marshal::v1::ActiveMQMapM, 379
- activemq::wireformat::openwire::marshal::v1::ActiveMQMessa, 406
- activemq::wireformat::openwire::marshal::v1::ActiveMQObject, 451
- activemq::wireformat::openwire::marshal::v1::ActiveMQQueue, 496
- activemq::wireformat::openwire::marshal::v1::ActiveMQStream

activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller	2372	activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller	2372
614		activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller	2582
activemq::wireformat::openwire::marshal::v1::ActiveMQTempQueueMarshaller	2582	activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller	2623
647		activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller	2623
activemq::wireformat::openwire::marshal::v1::ActiveMQTextMessageMarshaller	2623	activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller	2652
676		activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller	2689
activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMessageMarshaller	2652	activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller	2761
704		activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller	2761
activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller	2689	activemq::wireformat::openwire::marshal::v1::NetworkBridgeFormatMarshaller	2817
881		activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller	2943
activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller	2761	activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller	3061
913		activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller	3093
activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller	2817	activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller	3093
1281		activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller	3110
activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller	2943	activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	3211
1313		activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	3211
activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller	3061	activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionMarshaller	3228
1344		activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionMarshaller	3228
activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller	3093	activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller	3259
1374		activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller	3259
activemq::wireformat::openwire::marshal::v1::ConsumerGroupWithMarshaller	3110	activemq::wireformat::openwire::marshal::v1::ResponseMarshaller	3316
1419		activemq::wireformat::openwire::marshal::v1::ResponseMarshaller	3316
activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller	3211	activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller	3404
1448		activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller	3404
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller	3228	activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller	3420
1481		activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller	3420
activemq::wireformat::openwire::marshal::v1::ContactCommandMarshaller	3259	activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller	3482
1510		activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller	3482
activemq::wireformat::openwire::marshal::v1::DataActiveResponseMarshaller	3316	activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller	3681
1544		activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller	3681
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller	3404	activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller	3856
1607		activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller	3856
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller	3420	activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller	4009
1745		activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller	4009
activemq::wireformat::openwire::marshal::v1::DiscardResponseMarshaller	3482	activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller	4049
1779		activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller	4049
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller	3681	activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMarshaller	222
1863		activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMarshaller	222
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller	3856	activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMarshaller	270
1957		activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMarshaller	270
activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller	4009	activemq::wireformat::openwire::marshal::v2::ActiveMQMapMarshaller	391
2111		activemq::wireformat::openwire::marshal::v2::ActiveMQMapMarshaller	391
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	4049	activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller	418
2180		activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller	418
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	4049	activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMarshaller	463
2209		activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMarshaller	463
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	4049		
2232			
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	4049		
2263			
activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller	418		
2290			
activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller	463		
2325			

activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller	2274	activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller	2274
508		activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller	2313
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMessageMarshaller	2313	activemq::wireformat::openwire::marshal::v2::LocalTransactionMarshaller	2356
569		activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller	2570
activemq::wireformat::openwire::marshal::v2::ActiveMQTempQueueMarshaller	2356	activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller	2607
626		activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller	2640
activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller	2570	activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2669
655		activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller	2745
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller	2607	activemq::wireformat::openwire::marshal::v2::NetworkBridgeFactory	2797
688		activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller	2927
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller	2640	activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller	3041
716		activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller	3073
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller	2669	activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller	3106
893		activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller	3199
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller	2745	activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionMarshaller	3236
925		activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller	3263
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller	2797	activemq::wireformat::openwire::marshal::v2::ResponseMarshaller	3301
1293		activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller	3384
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller	2927	activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller	3428
1301		activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller	3478
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller	3041	activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	3697
1332		activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller	3872
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller	3073	activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller	4001
1362		activemq::wireformat::openwire::marshal::v2::XATransactionInfoMarshaller	4041
activemq::wireformat::openwire::marshal::v2::ConsumerGroupWithMarshaller	3106	activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMarshaller	210
1407		activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMarshaller	250
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller	3199	activemq::wireformat::openwire::marshal::v3::ActiveMQMapMarshaller	375
1436			
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller	3236		
1469			
activemq::wireformat::openwire::marshal::v2::ContainerCommandMarshaller	3263		
1498			
activemq::wireformat::openwire::marshal::v2::DataActiveResponseMarshaller	3301		
1532			
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	3384		
1595			
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller	3428		
1733			
activemq::wireformat::openwire::marshal::v2::DiscardResponseMarshaller	3478		
1767			
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	3697		
1847			
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller	3872		
1945			
activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller	4001		
2099			
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	4041		
2164			
activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller	210		
2193			
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller	250		
2216			
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller	375		
2247			

activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller	2220	activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller	2220
402		activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller	2251
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller	2278	activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller	2278
447		492	
activemq::wireformat::openwire::marshal::v3::ActiveMQSequenceMessageMarshaller	2309	activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	2360
553		610	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	2574	activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller	2611
639		668	
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	2644	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2681
668		696	
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller	2753	activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	2753
696		873	
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	2809	activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller	2935
873		905	
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	3049	activemq::wireformat::openwire::marshal::v3::NetworkBridgeFormatMarshaller	3081
905		1273	
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	3118	activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller	3207
1273		1305	
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	3232	activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller	3267
1305		1336	
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	3311	activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller	3400
1336		1366	
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	3424	activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller	3490
1366		1411	
activemq::wireformat::openwire::marshal::v3::ConsumerGroupMarshaller	3577	activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller	3677
1411		1440	
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	3860	activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionMarshaller	4013
1440		1473	
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	4053	activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	218
1473		1502	
activemq::wireformat::openwire::marshal::v3::ContainerMarshaller		1536	
1502		1599	
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller		1737	
1536		1771	
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller		1851	
1599		1949	
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller		2103	
1737		2172	
activemq::wireformat::openwire::marshal::v3::DiscoveryInfoMarshaller		2197	
1771			
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller			
1851			
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller			
1949			
activemq::wireformat::openwire::marshal::v3::IntegrationResponseMarshaller			
2103			
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller			
2172			
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller			
2197			

activemq::wireformat::openwire::marshal::v4::ActiveMQByteMessageMarshaller	2176	activemq::wireformat::openwire::marshal::v4::JournalQueueAck
258		
activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller	2205	activemq::wireformat::openwire::marshal::v4::JournalTopicAck
383		
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	2228	activemq::wireformat::openwire::marshal::v4::JournalTraceMa
410		
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller	2259	activemq::wireformat::openwire::marshal::v4::JournalTransact
455		
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMessageMarshaller	2282	activemq::wireformat::openwire::marshal::v4::KeepAliveInfoM
500		
activemq::wireformat::openwire::marshal::v4::ActiveMQSequenceMessageMarshaller	2321	activemq::wireformat::openwire::marshal::v4::LastPartialComm
561		
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	2368	activemq::wireformat::openwire::marshal::v4::LocalTransaction
618		
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller	2578	activemq::wireformat::openwire::marshal::v4::MessageAckMar
643		
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	2619	activemq::wireformat::openwire::marshal::v4::MessageDispatc
672		
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller	2648	activemq::wireformat::openwire::marshal::v4::MessageDispatc
700		
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2673	activemq::wireformat::openwire::marshal::v4::MessageIdMarsh
877		
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	2757	activemq::wireformat::openwire::marshal::v4::MessagePullMar
909		
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	2813	activemq::wireformat::openwire::marshal::v4::NetworkBridgeF
1277		
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller	2939	activemq::wireformat::openwire::marshal::v4::PartialCommand
1309		
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller	3045	activemq::wireformat::openwire::marshal::v4::ProducerAckMar
1340		
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	3077	activemq::wireformat::openwire::marshal::v4::ProducerIdMars
1370		
activemq::wireformat::openwire::marshal::v4::ConsumerGroupMarshaller	3102	activemq::wireformat::openwire::marshal::v4::ProducerInfoMa
1415		
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	3219	activemq::wireformat::openwire::marshal::v4::RemoveInfoMars
1444		
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	3248	activemq::wireformat::openwire::marshal::v4::RemoveSubscrip
1477		
activemq::wireformat::openwire::marshal::v4::ContentCommandMarshaller	3255	activemq::wireformat::openwire::marshal::v4::ReplayCommand
1506		
activemq::wireformat::openwire::marshal::v4::DataActiveResponseMarshaller	3296	activemq::wireformat::openwire::marshal::v4::ResponseMarsha
1540		
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller	3388	activemq::wireformat::openwire::marshal::v4::SessionIdMarsha
1603		
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller	3432	activemq::wireformat::openwire::marshal::v4::SessionInfoMars
1741		
activemq::wireformat::openwire::marshal::v4::DiscardEventMarshaller	3494	activemq::wireformat::openwire::marshal::v4::ShutdownInfoMa
1775		
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller	3689	activemq::wireformat::openwire::marshal::v4::SubscriptionInfo
1859		
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller	3868	activemq::wireformat::openwire::marshal::v4::TransactionInfo
1953		
activemq::wireformat::openwire::marshal::v4::IntegrationResponseMarshaller	4005	activemq::wireformat::openwire::marshal::v4::WireFormatInfo
2107		

activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller; openwire::marshal::v5::FlushCommandMarshaller; 4045
 activemq::wireformat::openwire::marshal::v5::ActiveMQBlobWireFormatMarshaller; openwire::marshal::v5::IntegerResponseMarshaller; 226
 activemq::wireformat::openwire::marshal::v5::ActiveMQByteWireFormatMarshaller; openwire::marshal::v5::JournalQueueAckMarshaller; 262
 activemq::wireformat::openwire::marshal::v5::ActiveMQMapWireFormatMarshaller; openwire::marshal::v5::JournalTopicAckMarshaller; 387
 activemq::wireformat::openwire::marshal::v5::ActiveMQMessageWireFormatMarshaller; openwire::marshal::v5::JournalTraceMarshaller; 414
 activemq::wireformat::openwire::marshal::v5::ActiveMQObjectWireFormatMarshaller; openwire::marshal::v5::JournalTransactionMarshaller; 459
 activemq::wireformat::openwire::marshal::v5::ActiveMQQueueWireFormatMarshaller; openwire::marshal::v5::KeepAliveInfoMarshaller; 504
 activemq::wireformat::openwire::marshal::v5::ActiveMQStackWireFormatMarshaller; openwire::marshal::v5::LastPartialCommandMarshaller; 565
 activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueWireFormatMarshaller; openwire::marshal::v5::LocalTransactionMarshaller; 622
 activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller; openwire::marshal::v5::MessageAckMarshaller; 651
 activemq::wireformat::openwire::marshal::v5::ActiveMQTextWireFormatMarshaller; openwire::marshal::v5::MessageDispatchMarshaller; 680
 activemq::wireformat::openwire::marshal::v5::ActiveMQTopicWireFormatMarshaller; openwire::marshal::v5::MessageDispatchMarshaller; 708
 activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller; openwire::marshal::v5::MessageIdMarshaller; 885
 activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller; openwire::marshal::v5::MessagePullMarshaller; 917
 activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller; openwire::marshal::v5::NetworkBridgeMarshaller; 1285
 activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller; openwire::marshal::v5::PartialCommandMarshaller; 1317
 activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller; openwire::marshal::v5::ProducerAckMarshaller; 1348
 activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller; openwire::marshal::v5::ProducerIdMarshaller; 1378
 activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller; openwire::marshal::v5::ProducerInfoMarshaller; 1423
 activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller; openwire::marshal::v5::RemoveInfoMarshaller; 1452
 activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller; openwire::marshal::v5::RemoveSubscriptionMarshaller; 1485
 activemq::wireformat::openwire::marshal::v5::ContainerCommandMarshaller; openwire::marshal::v5::ReplayCommandMarshaller; 1514
 activemq::wireformat::openwire::marshal::v5::DataActiveResponseMarshaller; openwire::marshal::v5::ResponseMarshaller; 1548
 activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller; openwire::marshal::v5::SessionIdMarshaller; 1587
 activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller; openwire::marshal::v5::SessionInfoMarshaller; 1753
 activemq::wireformat::openwire::marshal::v5::DiscardQueueMarshaller; openwire::marshal::v5::ShutdownInfoMarshaller; 1783
 activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller; openwire::marshal::v5::SubscriptionInfoMarshaller; 1855

activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller	1763
3852	
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller	1843
3993	
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller	1941
4057	
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobWireFormatMarshaller	2095
230	
activemq::wireformat::openwire::marshal::v6::ActiveMQByteWireFormatMarshaller	2160
266	
activemq::wireformat::openwire::marshal::v6::ActiveMQMapWireFormatMarshaller	2201
395	
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	2224
422	
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectWireFormatMarshaller	2243
467	
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueWireFormatMarshaller	2270
512	
activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceWireFormatMarshaller	2305
573	
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	2352
630	
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	2566
659	
activemq::wireformat::openwire::marshal::v6::ActiveMQTextWireFormatMarshaller	2627
684	
activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller	2636
712	
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller	2685
889	
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller	2765
921	
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller	2801
1289	
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller	2923
1321	
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller	3057
1352	
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller	3089
1382	
activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller	3122
1427	
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller	3203
1456	
activemq::wireformat::openwire::marshal::v6::ConsumerInfoMarshaller	3240
1489	
activemq::wireformat::openwire::marshal::v6::ContentCommandMarshaller	3271
1518	
activemq::wireformat::openwire::marshal::v6::DataActiveResponseMarshaller	3321
1552	
activemq::wireformat::openwire::marshal::v6::DataResponseMarshaller	3392
1591	
activemq::wireformat::openwire::marshal::v6::DestinationInfoMarshaller	3412
1749	

- activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3279
- activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller::CmsTemplate::ResolveReceiveExecutor, 3474
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller, 1403, 1404
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller::ConsumerControl, 3693
- activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller, 1463
- activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller::ConsumerInfo, 1462, 3864
- activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller, 1729, 1730
- activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller::DestinationInfo, 3997
- activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller, 2157, 2158
- activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::JournalQueueAck, 4037
- activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller::JournalTopicAck, 2185, 2186
- getDefault
 - decaf::net::ServerSocketFactory, 3363
 - decaf::net::SocketFactory, 3527
 - decaf::net::ssl::SSLContext, 3545
 - decaf::net::ssl::SSLServerSocketFactory, 3561
 - decaf::net::ssl::SSLSocketFactory, 3572
- getDefaultBacklog
 - decaf::net::ServerSocket, 3357
- getDefaultCipherSuites
 - decaf::internal::net::ssl::DefaultSSLServerSocketFactory, 1695
 - decaf::internal::net::ssl::DefaultSSLSocketFactory, 1702
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2856
 - decaf::internal::net::ssl::openssl::OpenSSLSocketFactory, 2880
 - decaf::net::ssl::SSLServerSocketFactory, 3561
 - decaf::net::ssl::SSLSocketFactory, 3572
- getDefaultDestination
 - activemq::cmsutil::CmsTemplate, 1175
- getDefaultDestinationName
 - activemq::cmsutil::CmsTemplate, 1175
- getDefaultSSLParameters
 - decaf::net::ssl::SSLContext, 3546
- getDelay
 - decaf::util::concurrent::Delayed, 1720
- getDeliveryMode
 - activemq::cmsutil::CachedProducer, 1076
 - activemq::cmsutil::CmsTemplate, 1175
 - activemq::core::ActiveMQProducer, 472
 - cms::MessageProducer, 2726
- getDeliverySequenceId
 - activemq::commands::MessageDispatchNotification, 2632
- getDestination
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3066
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
 - activemq::cmsutil::CmsTemplate::ResolveProducer, 3278
- activemq::commands::JournalTopicAck, 2185, 2186
- activemq::commands::Message, 2523, 2524
- activemq::commands::MessageAck, 2561, 2562
- activemq::commands::MessageDispatch, 2596
- activemq::commands::MessageDispatchNotification, 2632
- activemq::commands::MessagePull, 2741, 2742
- activemq::commands::ProducerInfo, 3098
- activemq::commands::SubscriptionInfo, 3673, 3674
- activemq::core::ActiveMQDestination, 327
- activemq::core::ActiveMQQueue, 485
- activemq::core::ActiveMQTempQueue, 607
- activemq::core::ActiveMQTempTopic, 636
- activemq::core::ActiveMQTopic, 693
- cms::Destination, 1724
- getDisableMessageID
 - activemq::cmsutil::CachedProducer, 1077
 - activemq::core::ActiveMQProducer, 472
 - cms::MessageProducer, 2727
- getDisableMessageTimeStamp
 - activemq::cmsutil::CachedProducer, 1077
 - activemq::core::ActiveMQProducer, 472
- cms::MessageProducer, 2727
- getDouble
 - activemq::commands::ActiveMQMapMessage, 3066
 - activemq::util::PrimitiveList, 2984
 - activemq::util::PrimitiveMap, 2995
 - activemq::util::PrimitiveValueNode, 3019
 - cms::Message, 2475
 - decaf::internal::nio::ByteArrayBuffer, 1009

- decaf::internal::util::ByteArrayAdapter, 978
- decaf::nio::ByteBuffer, 1042, 1043
- getDoubleArray
 - decaf::internal::util::ByteArrayAdapter, 978
- getDoubleAt
 - decaf::internal::util::ByteArrayAdapter, 978
- getDoubleCapacity
 - decaf::internal::util::ByteArrayAdapter, 978
- getDoubleProperty
 - activemq::commands::ActiveMQMessageTemplate, 433
 - activemq::wireformat::openwire::utils::MessageProperty, 2734
 - cms::Message, 2545
- getDurableTopicPrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
 - activemq::core::PrefetchPolicy, 2977
- getEnabledCipherSuites
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2845
 - decaf::internal::net::ssl::openssl::OpenSSLServiceSocket, 2849
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2863
 - decaf::net::ssl::SSLServerSocket, 3556
 - decaf::net::ssl::SSLSocket, 3566
- getEnabledProtocols
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2849
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2864
 - decaf::net::ssl::SSLServerSocket, 3557
 - decaf::net::ssl::SSLSocket, 3566
- getEncoded
 - decaf::security::auth::x500::X500Principal, 4027
 - decaf::security::cert::Certificate, 1087
 - decaf::security::Key, 2294
- getEnumeration
 - activemq::core::ActiveMQQueueBrowser, 488
 - cms::QueueBrowser, 3153
- getenv
 - decaf::lang::System, 3730
- getErrorCode
 - decaf::net::SocketError, 3520
- getErrorManager
 - decaf::util::logging::Handler, 1979
- getErrorString
 - decaf::internal::net::ssl::openssl::OpenSSLSocketException, 2874
 - decaf::net::SocketError, 3520
- getException
 - activemq::commands::ConnectionError, 1298
 - activemq::commands::ExceptionResponse, 1841
- getExceptionClass
 - activemq::commands::BrokerError, 865
- getExceptionListener
 - activemq::core::ActiveMQConnection, 281
 - activemq::core::ActiveMQConnectionFactory, 287
 - activemq::core::ActiveMQSession, 527
 - cms::Connection, 1264
- getExpiration
 - activemq::commands::Message, 2524
- getFileDescriptor
 - decaf::net::SocketImpl, 3532
- getFilter
 - decaf::util::logging::Handler, 1979
 - decaf::util::logging::Logger, 2392
- getFirstMessageId
 - activemq::commands::MessageAck, 2562
- getFirstNakNumber
 - activemq::commands::ReplayCommand, 3253
- getFloat
 - activemq::commands::ActiveMQMapMessage, 366
 - activemq::util::PrimitiveList, 2985
 - activemq::util::PrimitiveMap, 2995
 - activemq::util::PrimitiveValueNode, 3020
 - cms::MapMessage, 2476
- getFloatArray
 - decaf::internal::nio::ByteBuffer, 1009, 1010
 - decaf::internal::util::ByteArrayAdapter, 979
 - decaf::nio::ByteBuffer, 1043
- getFloatAt
 - decaf::internal::util::ByteArrayAdapter, 979
- getFloatCapacity
 - decaf::internal::util::ByteArrayAdapter, 980
- getFloatProperty
 - activemq::commands::ActiveMQMessageTemplate, 433

- activemq::wireformat::openwire::utils::MessageProducerState, 1492
- 2734
- cms::Message, 2546
- getFormat
 - decaf::security::Key, 2294
- getFormatId
 - activemq::commands::XATransactionId, 4033
- getFormatter
 - decaf::util::logging::Handler, 1979
- getFragment
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3954
 - decaf::net::URI, 3925
- getFreeThreadCount
 - decaf::util::concurrent::ThreadPool, 3779
- getGlobalPool
 - decaf::internal::AprPool, 728
 - decaf::internal::DecafRuntime, 1670
- getGlobalTransactionId
 - activemq::commands::XATransactionId, 4034
- getGroupID
 - activemq::commands::Message, 2524
- getGroupSequence
 - activemq::commands::Message, 2524
- getHandlers
 - decaf::util::logging::Logger, 2392
- getHead
 - decaf::util::logging::Formatter, 1965
 - decaf::util::logging::XMLFormatter, 4061
- getHoldCount
 - decaf::util::concurrent::locks::ReentrantLock, 3183
- getHost
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3954
 - decaf::net::URI, 3925
- getHostAddress
 - decaf::net::InetAddress, 2019
- getHostName
 - decaf::net::InetAddress, 2019
- getHostname
 - activemq::util::IdGenerator, 1990
- getId
 - activemq::state::TransactionState, 3876
 - decaf::lang::Thread, 3769
- getIndex
 - decaf::net::URISyntaxException, 3950
- getInetAddress
 - decaf::net::Socket, 3510
 - decaf::net::SocketImpl, 3533
- getInfo
 - activemq::state::ConnectionState, 1390
- getInitialDelayTime
 - activemq::transport::inactivity::InactivityMonitor, 2005
- getInitialReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1877
- getInitialRedeliveryDelay
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
 - activemq::core::RedeliveryPolicy, 3179
- getInput
 - decaf::net::URISyntaxException, 3951
- getInputStream
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2864
 - decaf::internal::net::tcp::TcpSocket, 3742
 - decaf::net::Socket, 3510
 - decaf::net::SocketImpl, 3533
- getInstance
 - activemq::transport::mock::MockTransport, 2771
 - activemq::transport::TransportRegistry, 3903
 - activemq::wireformat::WireFormatRegistry, 4018
 - decaf::util::concurrent::ThreadPool, 3780
 - decaf::util::logging::LogWriter, 2418
- getInt
 - activemq::commands::ActiveMQMapMessage, 366
 - activemq::util::PrimitiveList, 2985
 - activemq::util::PrimitiveMap, 2996
 - activemq::util::PrimitiveValueNode, 3020
 - cms::MapMessage, 2476
 - decaf::internal::nio::ByteBuffer, 1010
 - decaf::internal::util::ByteArrayAdapter, 980
 - decaf::nio::ByteBuffer, 1044
- getIntArray
 - decaf::internal::util::ByteArrayAdapter, 980
- getIntAt
 - decaf::internal::util::ByteArrayAdapter, 980
- getIntCapacity
 - decaf::internal::util::ByteArrayAdapter, 981
- getIntProperty
 - activemq::commands::ActiveMQMessageTemplate, 434

- activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2735
- cms::Message, 2546
- getIssuerUniqueID
 - decaf::security::cert::X509Certificate, 4029
- getIssuerX500Principal
 - decaf::security::cert::X509Certificate, 4029
- getKeepAlive
 - decaf::net::Socket, 3510
- getKey
 - decaf::util::Map::Entry, 1824
- getKeyUsage
 - decaf::security::cert::X509Certificate, 4029
- getLastDeliveredSequenceId
 - activemq::commands::RemoveInfo, 3195
 - activemq::core::ActiveMQConsumer, 315
 - activemq::core::ActiveMQSession, 527
- getLastMessageId
 - activemq::commands::MessageAck, 2562
- getLastNakNumber
 - activemq::commands::ReplayCommand, 3253
- getLastSequenceId
 - activemq::util::LongSequenceGenerator, 2455
- getLeastSignificantBits
 - decaf::util::UUID, 3972
- getLevel
 - decaf::util::logging::Handler, 1979
 - decaf::util::logging::Logger, 2392
 - decaf::util::logging::LogRecord, 2414
- getLimit
 - activemq::util::MemoryUsage, 2513
- getList
 - activemq::util::PrimitiveValueNode, 3020
- getLocalAddress
 - decaf::internal::net::tcp::TcpSocket, 3743
 - decaf::net::Socket, 3510
 - decaf::net::SocketImpl, 3533
- getLocalHost
 - decaf::net::InetAddress, 2020
- getLocalPort
 - decaf::net::ServerSocket, 3357
 - decaf::net::Socket, 3511
 - decaf::net::SocketImpl, 3533
- getLogger
 - decaf::util::logging::Logger, 2392
 - decaf::util::logging::LogManager, 2409
- getLoggerName
 - decaf::util::logging::LogRecord, 2414
- getLoggerNames
 - decaf::util::logging::LogManager, 2409
- getLogManager
 - decaf::util::logging::LogManager, 2409
- getLong
 - activemq::commands::ActiveMQMapMessage, 367
 - activemq::util::PrimitiveList, 2985
 - activemq::util::PrimitiveMap, 2996
 - activemq::util::PrimitiveValueNode, 3020
 - cms::MapMessage, 2476
 - decaf::internal::nio::ByteBuffer, 1011
 - decaf::internal::util::ByteArrayAdapter, 981
 - decaf::nio::ByteBuffer, 1044, 1045
- getLongArray
 - decaf::internal::util::ByteArrayAdapter, 981
- getLongAt
 - decaf::internal::util::ByteArrayAdapter, 981
- getLongCapacity
 - decaf::internal::util::ByteArrayAdapter, 982
- getLongProperty
 - activemq::commands::ActiveMQMessageTemplate, 434
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2735
 - cms::Message, 2547
- getLoopbackAddress
 - decaf::net::InetAddress, 2020
- getMagic
 - activemq::commands::WireFormatInfo, 3986
- getManaged
 - decaf::internal::util::GenericResource, 1974
- getMap
 - activemq::commands::ActiveMQMapMessage, 367
 - activemq::util::PrimitiveValueNode, 3021
- getMapNames
 - activemq::commands::ActiveMQMapMessage, 367
 - cms::MapMessage, 2477
- getMarshaledForm
 - activemq::commands::BaseDataStructure, 832
 - activemq::wireformat::MarshalAware, 2485
- getMarshaledProperties
 - activemq::commands::Message, 2524
 - activemq::commands::WireFormatInfo, 3986
- getMaxCacheSize
 - activemq::state::ConnectionStateTracker, 1394
 - activemq::transport::failover::FailoverTransport, 1877

- getMaximumPendingMessageLimit
 - activemq::commands::ConsumerInfo, 1463
- getMaximumRedeliveries
 - activemq::core::policies::DefaultRedeliveryPolicy, 1678
 - activemq::core::RedeliveryPolicy, 3179
- getMaxInactivityDuration
 - activemq::commands::WireFormatInfo, 3986
 - activemq::wireformat::openwire::OpenWireFormat, 2891
- getMaxInactivityDurationInitialDelay
 - activemq::commands::WireFormatInfo, 3986
- getMaxInactivityDurationInitialDelay
 - activemq::wireformat::openwire::OpenWireFormat, 2891
- getMaxPrefetchLimit
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
 - activemq::core::PrefetchPolicy, 2978
- getMaxReconnectAttempts
 - activemq::transport::failover::FailoverTransport, 1877
- getMaxReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1877
- getMaxThreads
 - decaf::util::concurrent::ThreadPool, 3780
- getMessage
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
 - activemq::commands::BrokerError, 865
 - activemq::commands::JournalTrace, 2213, 2214
 - activemq::commands::MessageDispatch, 2596
 - activemq::core::DispatchData, 1786
 - cms::CMSException, 1161
 - decaf::lang::Exception, 1835
 - decaf::lang::Throwable, 3785
 - decaf::util::logging::LogRecord, 2414
- getMessageAck
 - activemq::commands::JournalQueueAck, 2158
- getMessageAvailableCount
 - activemq::core::ActiveMQConsumer, 315
- getMessageCount
 - activemq::commands::MessageAck, 2562
- getMessageId
 - activemq::commands::JournalTopicAck, 2186
 - activemq::commands::Message, 2524
- activemq::commands::MessageDispatchNotification, 2632
- activemq::commands::MessagePull, 2742
- getMessageListener
 - activemq::cmsutil::CachedConsumer, 1072
 - activemq::core::ActiveMQConsumer, 315
 - cms::MessageConsumer, 2590
- getMessageProperties
 - activemq::commands::Message, 2524
- getMessageSelector
 - activemq::cmsutil::CachedConsumer, 1072
 - activemq::core::ActiveMQConsumer, 315
 - activemq::core::ActiveMQQueueBrowser, 488
 - cms::MessageConsumer, 2590
 - cms::QueueBrowser, 3154
- getMessageSequenceId
 - activemq::commands::JournalTopicAck, 2186
- getMetaData
 - activemq::core::ActiveMQConnection, 281
 - cms::Connection, 1264
- getMimeType
 - activemq::commands::ActiveMQBlobMessage, 206
- getMostSignificantBits
 - decaf::util::UUID, 3972
- getName
 - activemq::commands::ActiveMQBlobMessage, 206
 - decaf::lang::Thread, 3769
 - decaf::security::auth::x500::X500Principal, 4027
 - decaf::security::Principal, 3026
 - decaf::util::logging::Level, 2334
 - decaf::util::logging::Logger, 2392
- getNeedClientAuth
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2850
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2864
 - decaf::net::ssl::SSLParameters, 3552
 - decaf::net::ssl::SSLServerSocket, 3557
 - decaf::net::ssl::SSLSocket, 3566
- getNetworkBrokerId
 - activemq::commands::NetworkBridgeFilter, 2794, 2795
- getNetworkConsumerPath
 - activemq::commands::ConsumerInfo, 1463
- getNetworkProperties
 - activemq::commands::BrokerInfo, 899, 900
- getNetworkRuntime

- decaf::internal::net::Network, 2791
- getNetworkTTL
 - activemq::commands::NetworkBridgeFilter, 2795
- getNextConsumerId
 - activemq::core::ActiveMQSession, 527
- getNextLocalTransactionId
 - activemq::core::ActiveMQConnection, 282
- getNextProducerId
 - activemq::core::ActiveMQSession, 527
- getNextSequenceId
 - activemq::util::LongSequenceGenerator, 2455
- getNextSessionId
 - activemq::core::ActiveMQConnection, 282
- getNextTempDestinationId
 - activemq::core::ActiveMQConnection, 282
- getNotAfter
 - decaf::security::cert::X509Certificate, 4029
- getNotBefore
 - decaf::security::cert::X509Certificate, 4029
- getNumReceivedMessageBeforeFail
 - activemq::transport::mock::MockTransport, 2771
- getNumReceivedMessages
 - activemq::transport::mock::MockTransport, 2771
- getNumSentKeepAlives
 - activemq::transport::mock::MockTransport, 2771
- getNumSentKeepAlivesBeforeFail
 - activemq::transport::mock::MockTransport, 2771
- getNumSentMessageBeforeFail
 - activemq::transport::mock::MockTransport, 2771
- getNumSentMessages
 - activemq::transport::mock::MockTransport, 2771
- getObjectId
 - activemq::commands::RemoveInfo, 3196
- getOOBInline
 - decaf::net::Socket, 3511
- getOperationType
 - activemq::commands::DestinationInfo, 1730
- getOption
 - decaf::internal::net::tcp::TcpSocket, 3743
 - decaf::net::SocketImpl, 3533
- getOptions
 - activemq::commands::ActiveMQDestination, 327
- getOrderedTarget
 - activemq::commands::ActiveMQDestination, 327
- getOriginalDestination
 - activemq::commands::Message, 2524, 2525
- getOriginalTransactionId
 - activemq::commands::Message, 2525
- getOutputStream
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2864
 - decaf::internal::net::tcp::TcpSocket, 3743
 - decaf::net::Socket, 3511
 - decaf::net::SocketImpl, 3534
- getParameters
 - activemq::util::CompositeData, 1220
- getParent
 - decaf::util::logging::Logger, 2393
- getParentId
 - activemq::commands::ConsumerId, 1432
 - activemq::commands::ProducerId, 3069
 - activemq::commands::SessionId, 3381
- getPassword
 - activemq::commands::ConnectionInfo, 1358
 - activemq::core::ActiveMQConnection, 282
 - activemq::core::ActiveMQConnectionFactory, 297
- getPath
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3954
 - decaf::net::URI, 3926
- getPeerBrokerInfos
 - activemq::commands::BrokerInfo, 900
- getPhysicalName
 - activemq::commands::ActiveMQDestination, 327
- getPooledThreadListener
 - decaf::util::concurrent::PooledThread, 2969
- getPoolSize
 - decaf::util::concurrent::ThreadPool, 3780
- getPort
 - decaf::internal::net::URIType, 3954
 - decaf::net::Socket, 3511
 - decaf::net::SocketImpl, 3534
 - decaf::net::URI, 3926
- getPreferredWireFormatInfo
 - activemq::wireformat::openwire::OpenWireFormat, 2891
- getPrefetch
 - activemq::commands::ConsumerControl, 1404
- getPrefetchPolicy
 - activemq::core::ActiveMQConnection, 283
 - activemq::core::ActiveMQConnectionFactory, 297

- getPrefetchSize
 - activemq::commands::ConsumerInfo, 1463
- getPreparedResult
 - activemq::state::TransactionState, 3876
- getPriority
 - activemq::cmsutil::CachedProducer, 1077
 - activemq::cmsutil::CmsTemplate, 1175
 - activemq::commands::ConsumerInfo, 1463
 - activemq::commands::Message, 2525
 - activemq::core::ActiveMQProducer, 473
 - cms::MessageProducer, 2727
 - decaf::lang::Thread, 3769
- getProducerId
 - activemq::commands::Message, 2525
 - activemq::commands::MessageId, 2665, 2666
 - activemq::commands::ProducerAck, 3037, 3038
 - activemq::commands::ProducerInfo, 3098
 - activemq::core::ActiveMQProducer, 473
- getProducerInfo
 - activemq::core::ActiveMQProducer, 473
- getProducerSequenceId
 - activemq::commands::MessageId, 2666
- getProducerState
 - activemq::state::SessionState, 3438
- getProducerStates
 - activemq::state::SessionState, 3438
 - activemq::state::TransactionState, 3876
- getProducerWindowSize
 - activemq::core::ActiveMQConnection, 283
 - activemq::core::ActiveMQConnectionFactory, 297
- getProperties
 - activemq::commands::WireFormatInfo, 3987
 - activemq::util::ActiveMQProperties, 479, 480
 - activemq::wireformat::stomp::StompFrame, 3635
 - decaf::lang::System, 3731
 - decaf::util::logging::LogManager, 2410
- getProperty
 - activemq::util::ActiveMQProperties, 480
 - activemq::wireformat::stomp::StompFrame, 3636
 - cms::CMSProperties, 1166
 - decaf::lang::System, 3731
 - decaf::util::logging::LogManager, 2410
 - decaf::util::Properties, 3128, 3129
- getPropertyNames
 - activemq::commands::ActiveMQMessageTemplate, 434
 - cms::Message, 2547
- getProtocols
 - decaf::net::ssl::SSLParameters, 3552
- getProviderMajorVersion
 - activemq::core::ActiveMQConnectionMetaData, 305
 - cms::ConnectionMetaData, 1387
- getProviderMinorVersion
 - activemq::core::ActiveMQConnectionMetaData, 305
 - cms::ConnectionMetaData, 1387
- getProviderVersion
 - activemq::core::ActiveMQConnectionMetaData, 306
 - cms::ConnectionMetaData, 1388
- getPublicKey
 - decaf::security::cert::Certificate, 1087
- getQuery
 - decaf::internal::net::URIType, 3955
 - decaf::net::URI, 3926
- getQueue
 - activemq::core::ActiveMQQueueBrowser, 489
 - cms::QueueBrowser, 3154
- getQueueBrowserPrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1674
 - activemq::core::PrefetchPolicy, 2978
- getQueueName
 - activemq::commands::ActiveMQQueue, 486
 - activemq::commands::ActiveMQTempQueue, 607
 - cms::Queue, 3148
 - cms::TemporaryQueue, 3759
- getQueuePrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1675
 - activemq::core::PrefetchPolicy, 2978
- getRawAuthority
 - decaf::net::URI, 3926
- getRawFragment
 - decaf::net::URI, 3926
- getRawPath
 - decaf::net::URI, 3926
- getRawQuery
 - decaf::net::URI, 3927
- getRawSchemeSpecificPart
 - decaf::net::URI, 3927
- getRawUserInfo
 - decaf::net::URI, 3927
- getReadCheckTime
 - activemq::transport::inactivity::InactivityMonitor, 2005
- getReason

- decaf::net::URISyntaxException, 3951
- getReceiveBufferSize
 - decaf::net::ServerSocket, 3357
 - decaf::net::Socket, 3511
- getReceiveTimeout
 - activemq::cmsutil::CmsTemplate, 1175
- getReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1877
- getReconnectTo
 - activemq::commands::ConnectionControl, 1269, 1270
- getRecoveringPullConsumers
 - activemq::state::ConnectionState, 1390
- getRedeliveryCounter
 - activemq::commands::Message, 2525
 - activemq::commands::MessageDispatch, 2596
- getRedeliveryDelay
 - activemq::core::policies::DefaultRedeliveryPolicy, 1679
 - activemq::core::RedeliveryPolicy, 3179
- getRedeliveryPolicy
 - activemq::core::ActiveMQConnection, 283
 - activemq::core::ActiveMQConnectionFactory, 298
 - activemq::core::ActiveMQConsumer, 316
- getRemaining
 - decaf::util::zip::Inflater, 2030
- getRemoteAddress
 - activemq::transport::failover::FailoverTransport, 1877
 - activemq::transport::IOTransport, 2147
 - activemq::transport::mock::MockTransport, 2771
 - activemq::transport::Transport, 3884
 - activemq::transport::TransportFilter, 3894
- getRemoteBlobUrl
 - activemq::commands::ActiveMQBlobMessage, 206
- getReplyTo
 - activemq::commands::Message, 2525
- getResourceLifecycleManager
 - activemq::cmsutil::CmsAccessor, 1155
 - activemq::cmsutil::SessionPool, 3436
- getResponse
 - activemq::transport::correlator::FutureResponse, 1969, 1970
- getResult
 - activemq::commands::IntegerResponse, 2093
- getReuseAddress
 - decaf::net::ServerSocket, 3357
 - decaf::net::Socket, 3512
- getRuntime
 - decaf::lang::Runtime, 3326
- getRuntimeLock
 - decaf::internal::net::Network, 2791
- getSafeValue
 - decaf::util::StlQueue, 3618
- getScheme
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3955
 - decaf::net::URI, 3927
- getSchemeSpecificPart
 - decaf::internal::net::URIType, 3955
 - decaf::net::URI, 3927
- getSeedFromId
 - activemq::util::IdGenerator, 1990
- getSelector
 - activemq::commands::ConsumerInfo, 1463
 - activemq::commands::SubscriptionInfo, 3674
- getSendBufferSize
 - decaf::net::Socket, 3512
- getSendTimeout
 - activemq::core::ActiveMQConnection, 283
 - activemq::core::ActiveMQConnectionFactory, 298
 - activemq::core::ActiveMQProducer, 473
- getSequenceFromId
 - activemq::util::IdGenerator, 1990
- getServerSocketFactory
 - decaf::net::ssl::SSLContext, 3546
- getServiceName
 - activemq::commands::DiscoveryEvent, 1760
- getSession
 - activemq::cmsutil::PooledSession, 2965
- getSessionAcknowledgeMode
 - activemq::cmsutil::CmsAccessor, 1155
- getSessionId
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionInfo, 3409
 - activemq::core::ActiveMQSession, 527
- getSessionInfo
 - activemq::core::ActiveMQSession, 528
- getSessionState
 - activemq::state::ConnectionState, 1390
- getSessionStates
 - activemq::state::ConnectionState, 1390
- getShort
 - activemq::commands::ActiveMQMapMessage, 367
 - activemq::util::PrimitiveList, 2986
 - activemq::util::PrimitiveMap, 2997
 - activemq::util::PrimitiveValueNode, 3021

- cms::MapMessage, 2477
- decaf::internal::nio::ByteBuffer, 1011, 1012
- decaf::internal::util::ByteArrayAdapter, 982
- decaf::nio::ByteBuffer, 1045
- getShortArray
 - decaf::internal::util::ByteArrayAdapter, 982
- getShortAt
 - decaf::internal::util::ByteArrayAdapter, 983
- getShortCapacity
 - decaf::internal::util::ByteArrayAdapter, 983
- getShortProperty
 - activemq::commands::ActiveMQMessageTemplate, 435
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2735
 - cms::Message, 2548
- getSigAlgName
 - decaf::security::cert::X509Certificate, 4029
- getSigAlgOID
 - decaf::security::cert::X509Certificate, 4029
- getSigAlgParams
 - decaf::security::cert::X509Certificate, 4029
- getSignature
 - decaf::security::cert::X509Certificate, 4029
- getSize
 - activemq::commands::ActiveMQTextMessage, 664
 - activemq::commands::Message, 2525
 - activemq::commands::ProducerAck, 3038
- getSocketFactory
 - decaf::net::ssl::SSLContext, 3546
- getSocketHandle
 - decaf::internal::net::tcp::TcpSocket, 3744
- getSoLinger
 - decaf::net::Socket, 3512
- getSoTimeout
 - decaf::net::ServerSocket, 3358
 - decaf::net::Socket, 3512
- getSource
 - decaf::internal::net::URIType, 3955
- getSourceFile
 - decaf::util::logging::LogRecord, 2415
- getSourceFunction
 - decaf::util::logging::LogRecord, 2415
- getSourceLine
 - decaf::util::logging::LogRecord, 2415
- getSSLParameters
 - decaf::net::ssl::SSLSocket, 3567
- getStackTrace
 - cms::CMSEException, 1161
 - decaf::lang::Exception, 1835
 - decaf::lang::Throwable, 3785
- getStackTraceElements
 - activemq::commands::BrokerError, 865
- getStackTraceString
 - cms::CMSEException, 1162
 - decaf::lang::Exception, 1835
 - decaf::lang::Throwable, 3785
- getStartupMaxReconnectAttempts
 - activemq::transport::failover::FailoverTransport, 1877
- getState
 - decaf::lang::Thread, 3769
- getString
 - activemq::commands::ActiveMQMapMessage, 368
 - activemq::util::PrimitiveList, 2986
 - activemq::util::PrimitiveMap, 2997
 - activemq::util::PrimitiveValueNode, 3021
 - cms::MapMessage, 2477
- getStringProperty
 - activemq::commands::ActiveMQMessageTemplate, 435
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2735
 - cms::Message, 2548
- getSubscriptionName
 - activemq::commands::RemoveSubscriptionInfo, 3224
 - activemq::commands::SubscriptionInfo, 3674
- getSubjectUniqueID
 - decaf::security::cert::X509Certificate, 4029
- getSubjectX500Principal
 - decaf::security::cert::X509Certificate, 4029
- getSubscribedDestination
 - activemq::commands::SubscriptionInfo, 3674
- getSubscriptionName
 - activemq::commands::ConsumerInfo, 1463
- getSubscriptionName
 - activemq::commands::JournalTopicAck, 2186
- getSupportedCipherSuites
 - decaf::internal::net::ssl::DefaultSSLServerSocketFactory, 1696
 - decaf::internal::net::ssl::DefaultSSLSocketFactory, 1702
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2850

- decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2727
- 2857
- decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2865
- decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2880
- decaf::net::ssl::SSLServerSocket, 3557
- decaf::net::ssl::SSLServerSocketFactory, 3561
- decaf::net::ssl::SSLServerSocket, 3567
- decaf::net::ssl::SSLServerSocketFactory, 3573
- getSupportedProtocols
- decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
- decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2850
- decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2865
- decaf::net::ssl::SSLServerSocket, 3557
- decaf::net::ssl::SSLServerSocket, 3567
- getSupportedSSLParameters
- decaf::net::ssl::SSLContext, 3546
- getTail
- decaf::util::logging::Formatter, 1965
- decaf::util::logging::XMLFormatter, 4061
- getTargetConsumerId
- activemq::commands::Message, 2525, 2526
- getTBCertificate
- decaf::security::cert::X509Certificate, 4029
- getTcpNoDelay
- decaf::net::Socket, 3513
- getTempDestinations
- activemq::state::ConnectionState, 1390
- getText
- activemq::commands::ActiveMQTextMessage, 665
- cms::TextMessage, 3763
- getThrown
- decaf::util::logging::LogRecord, 2415
- getTime
- decaf::util::Date, 1667
- getTimeout
- activemq::commands::DestinationInfo, 1730
- activemq::commands::MessagePull, 2742
- activemq::transport::failover::FailoverTransport, 1877
- getTimeStamp
- activemq::commands::Message, 2526
- decaf::util::logging::LogRecord, 2415
- getTimeToLive
- activemq::cmsutil::CachedProducer, 1077
- activemq::cmsutil::CmsTemplate, 1176
- activemq::core::ActiveMQProducer, 473
- activemq::core::MessageProducer, 2727
- getTopicName
- activemq::commands::ActiveMQTempTopic, 636
- activemq::commands::ActiveMQTopic, 694
- cms::TemporaryTopic, 3761
- cms::Topic, 3817
- getTopicPrefetch
- activemq::core::policies::DefaultPrefetchPolicy, 1675
- activemq::core::PrefetchPolicy, 2978
- getTrafficClass
- decaf::net::Socket, 3513
- getTransactionContext
- activemq::core::ActiveMQSession, 528
- getTransactionId
- activemq::commands::JournalTopicAck, 2186
- activemq::commands::JournalTransaction, 2240, 2241
- activemq::commands::Message, 2526
- activemq::commands::MessageAck, 2562
- activemq::commands::TransactionInfo, 3849
- activemq::core::ActiveMQTransactionContext, 720
- getTransactionState
- activemq::state::ConnectionState, 1390
- activemq::state::ProducerState, 3125
- getTransactionStates
- activemq::state::ConnectionState, 1390
- getTransport
- activemq::core::ActiveMQConnection, 283
- activemq::transport::failover::BackupTransport, 752
- getTransportListener
- activemq::transport::failover::FailoverTransport, 1877
- activemq::transport::IOTransport, 2147
- activemq::transport::mock::MockTransport, 2772
- activemq::transport::Transport, 3884
- activemq::transport::TransportFilter, 3894
- getTransportNames
- activemq::transport::TransportRegistry, 3903
- getTreadId
- decaf::util::logging::LogRecord, 2415
- getType
- activemq::commands::JournalTransaction, 2241
- activemq::commands::Message, 2526
- activemq::commands::TransactionInfo, 3849

- activemq::util::PrimitiveValueNode, 3021
- decaf::security::cert::Certificate, 1087
- getUncaughtExceptionHandler
 - decaf::lang::Thread, 3770
- getUnconsumedMessages
 - activemq::core::ActiveMQSessionExecutor, 535
- getURI
 - activemq::transport::failover::URIPool, 3943
- getUri
 - activemq::transport::failover::BackupTransport, 753
- getUsage
 - activemq::util::MemoryUsage, 2513
- getClientMode
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2865
 - decaf::net::ssl::SSLSocket, 3567
- getParentHandlers
 - decaf::util::logging::Logger, 2393
- getUserID
 - activemq::commands::Message, 2526
- getUserInfo
 - decaf::internal::net::URIType, 3955
 - decaf::net::URI, 3927
- getUserName
 - activemq::commands::ConnectionInfo, 1358
- getUsername
 - activemq::core::ActiveMQConnection, 284
 - activemq::core::ActiveMQConnectionFactory, 298
- getValue
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1329
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::LocalTransactionId, 2349
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionId, 3382
 - activemq::util::PrimitiveValueNode, 3022
 - decaf::internal::net::SocketFileDescriptor, 3528
 - decaf::util::Map::Entry, 1824
 - decaf::util::zip::Adler32, 723
 - decaf::util::zip::Checksum, 1142
 - decaf::util::zip::CRC32, 1525
- getVersion
 - activemq::commands::WireFormatInfo, 3987
- activemq::wireformat::openwire::OpenWireFormat, 2892
- activemq::wireformat::stomp::StompWireFormat, 3644
- activemq::wireformat::WireFormat, 3977
- decaf::security::cert::X509Certificate, 4029
- getWantClientAuth
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2850
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2866
 - decaf::net::ssl::SSLParameters, 3552
 - decaf::net::ssl::SSLServerSocket, 3557
 - decaf::net::ssl::SSLSocket, 3568
- getWasPrepared
 - activemq::commands::JournalTransaction, 2241
- getWhen
 - decaf::util::TimerTask, 3802
- getWindowSize
 - activemq::commands::ProducerInfo, 3098
- getWireFormat
 - activemq::transport::mock::MockTransport, 2772
- getWireFormatNames
 - activemq::wireformat::WireFormatRegistry, 4018
- getWriteCheckTime
 - activemq::transport::inactivity::InactivityMonitor, 2005
- globalTransactionId
 - activemq::commands::XATransactionId, 4035
- good_match
 - internal_state, 2120
- groupID
 - activemq::commands::Message, 2532
- groupSequence
 - activemq::commands::Message, 2532
- GT_OFF
 - gzguts.h, 4729
- GUNZIP
 - inflate.h, 4732
- GZ_APPEND
 - gzguts.h, 4729
- gz_header
 - zlib.h, 4742
- gz_header_s, 1975
 - comm_max, 1975
 - comment, 1975
 - done, 1975
 - extra, 1975

- extra_len, 1975
- extra_max, 1975
- hcrc, 1975
- name, 1975
- name_max, 1975
- os, 1975
- text, 1975
- time, 1975
- xflags, 1975
- gz_headerp
 - zlib.h, 4742
- GZ_NONE
 - gzguts.h, 4729
- GZ_READ
 - gzguts.h, 4729
- gz_state, 1976
 - direct, 1977
 - eof, 1977
 - err, 1977
 - fd, 1977
 - have, 1977
 - how, 1977
 - in, 1977
 - level, 1977
 - mode, 1977
 - msg, 1977
 - next, 1977
 - out, 1977
 - path, 1977
 - pos, 1977
 - raw, 1977
 - seek, 1977
 - size, 1977
 - skip, 1977
 - start, 1977
 - strategy, 1977
 - strm, 1977
 - want, 1977
- gz_statep
 - gzguts.h, 4729
- GZ_WRITE
 - gzguts.h, 4729
- GZBUFSIZE
 - gzguts.h, 4729
- gzFile
 - zlib.h, 4742
- gzguts.h
 - COPY, 4729
 - GT_OFF, 4729
 - GZ_APPEND, 4729
 - GZ_NONE, 4729
 - GZ_READ, 4729
 - gz_statep, 4729
 - GZ_WRITE, 4729
 - GZBUFSIZE, 4729
 - GZIP, 4729
 - local, 4729
 - LOOK, 4729
 - OF, 4729
 - ZLIB_INTERNAL, 4729
 - zstrerror, 4729
- gzhead
 - internal_state, 2120
- gzindex
 - internal_state, 2120
- GZIP
 - deflate.h, 4727
 - gzguts.h, 4729
- Handler
 - decaf::util::logging::Handler, 1979
- handleTransportFailure
 - activemq::transport::failover::FailoverTransport, 1877
- hasArray
 - decaf::internal::nio::ByteBuffer, 1012
 - decaf::internal::nio::CharArrayBuffer, 1115
 - decaf::internal::nio::DoubleArrayBuffer, 1806
 - decaf::internal::nio::FloatArrayBuffer, 1922
 - decaf::internal::nio::IntArrayBuffer, 2063
 - decaf::internal::nio::LongArrayBuffer, 2441
 - decaf::internal::nio::ShortArrayBuffer, 3456
 - decaf::nio::ByteBuffer, 1046
 - decaf::nio::CharBuffer, 1128
 - decaf::nio::DoubleBuffer, 1815
 - decaf::nio::FloatBuffer, 1931
 - decaf::nio::IntBuffer, 2072
 - decaf::nio::LongBuffer, 2450
 - decaf::nio::ShortBuffer, 3465
- hash_bits
 - internal_state, 2120
- hash_mask
 - internal_state, 2120
- hash_shift
 - internal_state, 2120
- hash_size
 - internal_state, 2120
- hashCode
 - decaf::security::auth::x500::X500Principal, 4027
- hasMoreMessages
 - activemq::core::ActiveMQQueueBrowser, 489
 - cms::MessageEnumeration, 2659
- hasMoreTokens
 - decaf::util::StringTokenizer, 3669

- hasNegotiator
 - activemq::wireformat::openwire::OpenWireFormat, 2892
 - activemq::wireformat::stomp::StompWireFormat, 3644
 - activemq::wireformat::WireFormat, 3977
- hasNext
 - decaf::util::Iterator, 2154
- hasPrevious
 - decaf::util::ListIterator, 2345
- hasProperty
 - activemq::util::ActiveMQProperties, 480
 - activemq::wireformat::stomp::StompFrame, 3636
 - cms::CMSProperties, 1167
 - decaf::util::Properties, 3129
- hasRemaining
 - decaf::nio::Buffer, 931
- hasUnconsumedMessages
 - activemq::core::ActiveMQSessionExecutor, 535
- have
 - gz_state, 1977
 - inflate_state, 2025
- havedict
 - inflate_state, 2025
- HCRC
 - inflate.h, 4732
- hcrc
 - gz_header_s, 1975
- HCRC_STATE
 - deflate.h, 4727
- HEAD
 - inflate.h, 4732
- head
 - inflate_state, 2025
 - internal_state, 2120
- HEADER_ACK
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_CLIENT_ID
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_CONSUMERPRIORITY
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_CONTENTLENGTH
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_CORRELATIONID
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_DESTINATION
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_DISPATCH_ASYNC
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_EXCLUSIVE
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_EXPIRES
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_ID
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_JMSPRIORITY
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_LOGIN
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_MAXPENDINGMSGLIMIT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_MESSAGE
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_MESSAGEID
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_NOLOCAL
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_OLDSUBSCRIPTIONNAME
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_PASSWORD
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_PERSISTENT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_PREFETCHSIZE
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_RECEIPT_REQUIRED
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_RECEIPTID
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_REDELIVERED
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- HEADER_REDELIVERYCOUNT
 - activemq::wireformat::stomp::StompCommandConstants, 3631

activemq::wireformat::stomp::StompCommandConstants,	3631	highestOneBit	2120
HEADER_REPLYTO		highestOneBit	
activemq::wireformat::stomp::StompCommandConstants,	3631	Integer, 2082	
HEADER_REQUESTID		decaf::lang::Long, 2425	
activemq::wireformat::stomp::StompCommandConstants,	3631	hold	
HEADER_RESPONSEID		internal_state, 2025	
activemq::wireformat::stomp::StompCommandConstants,	3631	hostname	
HEADER_RETROACTIVE		decaf::net::InetAddress, 2022	
activemq::wireformat::stomp::StompCommandConstants,	3631	HTTP constants,	
HEADER_SELECTOR		decaf::util::concurrent::TimeUnit, 3815	
activemq::wireformat::stomp::StompCommandConstants,	3631	how	
HEADER_SESSIONID		HTTP constants,	
activemq::wireformat::stomp::StompCommandConstants,	3631	http_retry_exception, 1977	
HEADER_SUBSCRIPTION		HttpRetryException	
activemq::wireformat::stomp::StompCommandConstants,	3631	decaf::net::HttpRetryException, 1986,	
HEADER_SUBSCRIPTIONNAME		HTTP constants,	
activemq::wireformat::stomp::StompCommandConstants,	3631	HUFFMAN_ONLY	
HEADER_TIMESTAMP		decaf::util::zip::Deflater, 1715	
activemq::wireformat::stomp::StompCommandConstants,	3631	ID_ACTIVEMQBLOBMESSAGE	
HEADER_TRANSACTIONID		activemq::commands::ActiveMQBlobMessage,	
activemq::wireformat::stomp::StompCommandConstants,	3631	ID_ACTIVEMQBYTESMESSAGE	
HEADER_TRANSFORMATION		activemq::commands::ActiveMQBytesMessage,	
activemq::wireformat::stomp::StompCommandConstants,	3631	ID_ACTIVEMQDESTINATION	
HEADER_TRANSFORMATION_ERROR		activemq::commands::ActiveMQDestination,	
activemq::wireformat::stomp::StompCommandConstants,	3631	ID_ACTIVEMQMAPMESSAGE	
HEADER_TYPE		activemq::commands::ActiveMQMapMessage,	
activemq::wireformat::stomp::StompCommandConstants,	3631	ID_ACTIVEMQMESSAGE	
heap		activemq::commands::ActiveMQMessage,	
internal_state, 2120		ID_ACTIVEMQOBJECTMESSAGE	
heap_len		activemq::commands::ActiveMQObjectMessage,	
internal_state, 2120		ID_ACTIVEMQQUEUE	
heap_max		activemq::commands::ActiveMQQueue,	
internal_state, 2120		ID_ACTIVEMQSTREAMMESSAGE	
HEAP_SIZE		activemq::commands::ActiveMQStreamMessage,	
deflate.h, 4727		ID_ACTIVEMQTEMPDESTINATION	
HexStringParser		activemq::commands::ActiveMQTempDestination,	
decaf::internal::util::HexStringParser, 1982		ID_ACTIVEMQTEMPQUEUE	
HexTable		activemq::commands::ActiveMQTempQueue,	
activemq::wireformat::openwire::utils::HexTable,		ID_ACTIVEMQTEMPTOPIC	
1984		activemq::commands::ActiveMQTempTopic,	
		ID_ACTIVEMQTEXTMESSAGE	

- activemq::commands::ActiveMQTextMessage, 666
- ID_ ACTIVEMQTOPIC
 - activemq::commands::ActiveMQTopic, 694
- ID_ BROKERID
 - activemq::commands::BrokerId, 871
- ID_ BROKERINFO
 - activemq::commands::BrokerInfo, 903
- ID_ CONNECTIONCONTROL
 - activemq::commands::ConnectionControl, 1271
- ID_ CONNECTIONERROR
 - activemq::commands::ConnectionError, 1299
- ID_ CONNECTIONID
 - activemq::commands::ConnectionId, 1330
- ID_ CONNECTIONINFO
 - activemq::commands::ConnectionInfo, 1360
- ID_ CONSUMERCONTROL
 - activemq::commands::ConsumerControl, 1405
- ID_ CONSUMERID
 - activemq::commands::ConsumerId, 1433
- ID_ CONSUMERINFO
 - activemq::commands::ConsumerInfo, 1466
- ID_ CONTROLCOMMAND
 - activemq::commands::ControlCommand, 1496
- ID_ DATAARRAYRESPONSE
 - activemq::commands::DataArrayResponse, 1530
- ID_ DATARESPONSE
 - activemq::commands::DataResponse, 1585
- ID_ DESTINATIONINFO
 - activemq::commands::DestinationInfo, 1731
- ID_ DISCOVERYEVENT
 - activemq::commands::DiscoveryEvent, 1761
- ID_ EXCEPTIONRESPONSE
 - activemq::commands::ExceptionResponse, 1841
- ID_ FLUSHCOMMAND
 - activemq::commands::FlushCommand, 1939
- ID_ INTEGERRESPONSE
 - activemq::commands::IntegerResponse, 2093
- ID_ JOURNALQUEUEACK
 - activemq::commands::JournalQueueAck, 2158
- ID_ JOURNALTOPICACK
 - activemq::commands::JournalTopicAck, 2187
- ID_ JOURNALTRACE
 - activemq::commands::JournalTrace, 2214
- ID_ JOURNALTRANSACTION
 - activemq::commands::JournalTransaction, 2241
- ID_ KEEPALIVEINFO
 - activemq::commands::KeepAliveInfo, 2268
- ID_ LASTPARTIALCOMMAND
 - activemq::commands::LastPartialCommand, 2303
- ID_ LOCALTRANSACTIONID
 - activemq::commands::LocalTransactionId, 2350
- ID_ MESSAGE
 - activemq::commands::Message, 2532
- ID_ MESSAGEACK
 - activemq::commands::MessageAck, 2564
- ID_ MESSAGEDISPATCH
 - activemq::commands::MessageDispatch, 2598
- ID_ MESSAGEDISPATCHNOTIFICATION
 - activemq::commands::MessageDispatchNotification, 2634
- ID_ MESSAGEID
 - activemq::commands::MessageId, 2667
- ID_ MESSAGEPULL
 - activemq::commands::MessagePull, 2743
- ID_ NETWORKBRIDGEFILTER
 - activemq::commands::NetworkBridgeFilter, 2795
- ID_ PARTIALCOMMAND
 - activemq::commands::PartialCommand, 2921
- ID_ PRODUCERACK
 - activemq::commands::ProducerAck, 3039
- ID_ PRODUCERID
 - activemq::commands::ProducerId, 3070
- ID_ PRODUCERINFO
 - activemq::commands::ProducerInfo, 3100
- ID_ REMOVEINFO
 - activemq::commands::RemoveInfo, 3197
- ID_ REMOVESUBSCRIPTIONINFO
 - activemq::commands::RemoveSubscriptionInfo, 3226
- ID_ REPLAYCOMMAND
 - activemq::commands::ReplayCommand, 3253
- ID_ RESPONSE
 - activemq::commands::Response, 3288
- ID_ SESSIONID
 - activemq::commands::SessionId, 3382
- ID_ SESSIONINFO

- activemq::commands::SessionInfo, 3410
- ID_SHUTDOWNINFO
 - activemq::commands::ShutdownInfo, 3472
- ID_SUBSCRIPTIONINFO
 - activemq::commands::SubscriptionInfo, 3675
- ID_TRANSACTIONID
 - activemq::commands::TransactionId, 3822
- ID_TRANSACTIONINFO
 - activemq::commands::TransactionInfo, 3850
- ID_WIREFORMATINFO
 - activemq::commands::WireFormatInfo, 3991
- ID_XATransactionID
 - activemq::commands::XATransactionId, 4035
- IdGenerator
 - activemq::util::IdGenerator, 1989
- IllegalArgumentException
 - decaf::lang::exceptions::IllegalArgumentException, 1991, 1992
- IllegalMonitorStateException
 - decaf::lang::exceptions::IllegalMonitorStateException, 1994, 1995
- IllegalStateException
 - cms::IllegalStateException, 1997
 - decaf::lang::exceptions::IllegalStateException, 1998, 1999
- IllegalThreadStateException
 - decaf::lang::exceptions::IllegalThreadStateException, 2001, 2002
- impl
 - decaf::net::Socket, 3518
- implAccept
 - decaf::net::ServerSocket, 3358
- in
 - decaf::io::FileDescriptor, 1892
 - gz_state, 1977
- InactivityMonitor
 - activemq::transport::inactivity::InactivityMonitor, 2005
- increaseUsage
 - activemq::util::MemoryUsage, 2514
 - activemq::util::Usage, 3965
- incrementAndGet
 - decaf::util::concurrent::atomic::AtomicInteger, 744
- indexOf
 - decaf::util::List, 2339
 - decaf::util::StlList, 3597
- IndexOutOfBounds Exception
 - decaf::lang::exceptions::IndexOutOfBounds Exception, 2008, 2009
- INDIVIDUAL_ACKNOWLEDGE
 - cms::Session, 3368
- Inet4Address
 - decaf::net::Inet4Address, 2012
- Inet6Address
 - decaf::net::Inet6Address, 2015
- InetAddress
 - decaf::net::Inet4Address, 2014
 - decaf::net::Inet6Address, 2015
 - decaf::net::InetAddress, 2018
- InetSocketAddress
 - decaf::net::InetSocketAddress, 2023
- inffast.h
 - OF, 4730
- inflate
 - decaf::util::zip::Inflater, 2030, 2031
- inflate.h
 - BAD, 4733
 - CHECK, 4733
 - CODELENS, 4733
 - COMMENT, 4732
 - COPY, 4733
 - COPY_, 4733
 - DICT, 4732
 - DICTID, 4732
 - DIST, 4733
 - DISTEXT, 4733
 - DONE, 4733
 - EXLEN, 4732
 - EXTRA, 4732
 - FLAGS, 4732
 - GUNZIP, 4732
 - HCRC, 4732
 - HEAD, 4732
 - inflate_mode, 4732
 - LEN, 4733
 - LEN_, 4733
 - LENEXT, 4733
 - LENGTH, 4733
 - LENLENS, 4733
 - LIT, 4733
 - MATCH, 4733
 - MEM, 4733
 - NAME, 4732
 - OS, 4732
 - STORED, 4733
 - SYNC, 4733
 - TABLE, 4733
 - TIME, 4732
 - TYPE, 4732
 - TYPEDO, 4732
- inflate_mode
- inflate.h, 4732
- inflate_state, 2024

- back, 2025
- bits, 2025
- check, 2025
- codes, 2025
- distbits, 2025
- distcode, 2025
- dmax, 2025
- extra, 2025
- flags, 2025
- have, 2025
- havedict, 2025
- head, 2025
- hold, 2025
- last, 2025
- lenbits, 2025
- lencode, 2025
- length, 2025
- lens, 2025
- mode, 2025
- ncode, 2025
- ndist, 2025
- next, 2025
- nlen, 2025
- offset, 2025
- sane, 2025
- total, 2025
- was, 2025
- wbits, 2025
- whave, 2025
- window, 2025
- wnext, 2025
- work, 2025
- wrap, 2025
- wsiz, 2025
- inflateBackInit
 - zlib.h, 4741
- inflateInit
 - zlib.h, 4741
- inflateInit2
 - zlib.h, 4742
- Inflater
 - decaf::util::zip::Inflater, 2029
- inflater
 - decaf::util::zip::InflaterInputStream, 2041
- InflaterInputStream
 - decaf::util::zip::InflaterInputStream, 2037, 2038
- INFO
 - decaf::util::logging::Level, 2336
- Info
 - decaf::util::logging, 176
- info
 - decaf::util::logging::Logger, 2393
 - decaf::util::logging::SimpleLogger, 3502
- inftrees.h
 - CODES, 4734
 - codetype, 4734
 - DISTS, 4734
 - ENOUGH, 4734
 - ENOUGH_DISTS, 4734
 - ENOUGH_LENS, 4734
 - LENS, 4734
 - OF, 4734
- INHERIT
 - decaf::util::logging::Level, 2336
- init
 - activemq::cmsutil::CmsAccessor, 1156
 - activemq::cmsutil::CmsDestinationAccessor, 1158
 - activemq::cmsutil::CmsTemplate, 1176
 - activemq::cmsutil::DestinationResolver, 1756
 - activemq::cmsutil::DynamicDestinationResolver, 1822
- INIT_STATE
 - deflate.h, 4727
- initCause
 - decaf::lang::Exception, 1836
 - decaf::lang::Throwable, 3786
- initializeLibrary
 - activemq::library::ActiveMQCPP, 320, 321
- initializeNetworking
 - decaf::internal::net::Network, 2791
- initializeRuntime
 - decaf::lang::Runtime, 3326
- initSocketImpl
 - decaf::net::Socket, 3513
- inProgressClearRequired
 - activemq::core::ActiveMQConsumer, 316
- InputStream
 - decaf::io::InputStream, 2045
- inputStream
 - decaf::io::FilterInputStream, 1899
- InputStreamReader
 - decaf::io::InputStreamReader, 2054
- inReceive
 - activemq::wireformat::openwire::OpenWireFormat, 2892
 - activemq::wireformat::stomp::StompWireFormat, 3644
 - activemq::wireformat::WireFormat, 3978
- ins_h
 - internal_state, 2120
- insert
 - decaf::internal::util::TimerTaskHeap, 3805
- IntArrayBuffer
 - decaf::internal::nio::IntArrayBuffer, 2059, 2060

- intBitsToFloat
 - decaf::lang::Float, 1909
- IntBuffer
 - decaf::nio::IntBuffer, 2068
- Integer
 - decaf::lang::Integer, 2079
- INTEGER_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- IntegerResponse
 - activemq::commands::IntegerResponse, 2092
- IntegerResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller, 2111
 - activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller, 2099
 - activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller, 2103
 - activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller, 2107
 - activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller, 2115
 - activemq::wireformat::openwire::marshal::v6::IntegerResponseMarshaller, 2095
- internal_state, 2118
 - bi_buf, 2120
 - bi_valid, 2120
 - bl_count, 2120
 - bl_desc, 2120
 - bl_tree, 2120
 - block_start, 2120
 - d_buf, 2120
 - d_desc, 2120
 - depth, 2120
 - dummy, 2120
 - dyn_dtree, 2120
 - dyn_ltree, 2120
 - good_match, 2120
 - gzhead, 2120
 - gzindex, 2120
 - hash_bits, 2120
 - hash_mask, 2120
 - hash_shift, 2120
 - hash_size, 2120
 - head, 2120
 - heap, 2120
 - heap_len, 2120
 - heap_max, 2120
 - high_water, 2120
 - ins_h, 2120
 - l_buf, 2120
 - l_desc, 2120
 - last_eob_len, 2120
 - last_flush, 2120
 - last_lit, 2120
 - level, 2120
 - lit_bufsize, 2120
 - lookahead, 2120
 - match_available, 2120
 - match_length, 2120
 - match_start, 2120
 - matches, 2120
 - max_chain_length, 2120
 - max_lazy_match, 2120
 - method, 2120
 - nice_match, 2120
 - opt_len, 2120
 - pending, 2120
 - pending_buf, 2120
 - pending_buf_size, 2120
 - pending_out, 2120
 - prev, 2120
 - prev_length, 2120
 - prev_match, 2120
 - static_len, 2120
 - status, 2120
 - strategy, 2120
 - strm, 2120
 - strstart, 2120
 - w_bits, 2120
 - w_mask, 2120
 - w_size, 2120
 - window, 2120
 - window_size, 2120
 - wrap, 2120
- InternalCommandListener
 - activemq::transport::mock::InternalCommandListener, 2122
- InterruptedException
 - decaf::lang::exceptions::InterruptedException, 2124, 2125
- InterruptedIOException
 - decaf::io::InterruptedIOException, 2127, 2128
- intf
 - zconf.h, 4738
- intValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
 - decaf::lang::Byte, 964
 - decaf::lang::Character, 1103
 - decaf::lang::Double, 1793
 - decaf::lang::Float, 1909
 - decaf::lang::Integer, 2082
 - decaf::lang::Long, 2425
 - decaf::lang::Number, 2836
 - decaf::lang::Short, 3444

- decaf::util::concurrent::atomic::AtomicIntegerBrowser
 - 745
- decaf::util::logging::Level, 2334
- InvalidClientIdException
 - cms::InvalidClientIdException, 2130
- InvalidDestinationException
 - cms::InvalidDestinationException, 2131
- InvalidKeyException
 - decaf::security::InvalidKeyException, 2132, 2133
- InvalidMarkException
 - decaf::nio::InvalidMarkException, 2135, 2136
- InvalidSelectorException
 - cms::InvalidSelectorException, 2138
- InvalidStateException
 - decaf::lang::exceptions::InvalidStateException, 2139, 2140
- IOException
 - decaf::io::IOException, 2142, 2143
- IOTransport
 - activemq::transport::IOTransport, 2146
- IPos
 - deflate.h, 4727
- isAbsolute
 - decaf::internal::net::URIType, 3955
 - decaf::net::URI, 3928
- isAdvisory
 - activemq::commands::ActiveMQDestination, 327
- isAlive
 - decaf::lang::Thread, 3770
- isAlwaysSyncSend
 - activemq::core::ActiveMQConnection, 284
 - activemq::core::ActiveMQConnectionFactory, 298
- isAnyLocalAddress
 - decaf::net::Inet4Address, 2012
 - decaf::net::InetAddress, 2020
- isAutoAcknowledge
 - activemq::core::ActiveMQSession, 528
- isBackup
 - activemq::transport::failover::FailoverTransport, 1878
- isBound
 - decaf::net::ServerSocket, 3358
 - decaf::net::Socket, 3513
- isBrokerInfo
 - activemq::commands::BaseCommand, 760
 - activemq::commands::BrokerInfo, 900
 - activemq::commands::Command, 1195
- isBrokerMasterConnector
 - activemq::commands::ConnectionInfo, 1358
- activemq::commands::ConsumerInfo, 1463
- isBusy
 - decaf::util::concurrent::PooledThread, 2969
- isCacheEnabled
 - activemq::commands::WireFormatInfo, 3987
 - activemq::wireformat::openwire::OpenWireFormat, 2892
- isCancelled
 - decaf::util::concurrent::Future, 1968
- isClientAcknowledge
 - activemq::core::ActiveMQSession, 528
- isClientMaster
 - activemq::commands::ConnectionInfo, 1358
- isClose
 - activemq::commands::ConnectionControl, 1270
 - activemq::commands::ConsumerControl, 1404
- isClosed
 - activemq::core::ActiveMQConnection, 284
 - activemq::core::ActiveMQConsumer, 316
 - activemq::core::ActiveMQProducer, 474
 - activemq::core::MessageDispatchChannel, 2601
 - activemq::transport::failover::BackupTransport, 753
 - activemq::transport::failover::FailoverTransport, 1878
 - activemq::transport::IOTransport, 2147
 - activemq::transport::mock::MockTransport, 2772
 - activemq::transport::tcp::TcpTransport, 3754
 - activemq::transport::Transport, 3884
 - activemq::transport::TransportFilter, 3894
 - decaf::internal::net::tcp::TcpSocket, 3744
 - decaf::io::FilterInputStream, 1897
 - decaf::io::FilterOutputStream, 1902
 - decaf::net::ServerSocket, 3358
 - decaf::net::Socket, 3513
- isComposite
 - activemq::commands::ActiveMQDestination, 328
- isCompressed
 - activemq::commands::Message, 2526
- isConnected
 - activemq::transport::failover::FailoverTransport, 1878
 - activemq::transport::IOTransport, 2148
 - activemq::transport::mock::MockTransport, 2772

- activemq::transport::tcp::TcpTransport, 3754
- activemq::transport::Transport, 3885
- activemq::transport::TransportFilter, 3894
- decaf::internal::net::tcp::TcpSocket, 3744
- decaf::net::Socket, 3514
- isConnectionAdvisory
 - activemq::commands::ActiveMQDestination, 328
- isConnectionInfo
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1195
 - activemq::commands::ConnectionInfo, 1358
- isConnectionInterruptProcessingComplete
 - activemq::state::ConnectionState, 1391
- isConsumerAdvisory
 - activemq::commands::ActiveMQDestination, 328
- isConsumerInfo
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1195
 - activemq::commands::ConsumerInfo, 1463
- isDeletedByBroker
 - activemq::commands::ActiveMQBlobMessage, 207
- isDigit
 - decaf::lang::Character, 1104
- isDispatchAsync
 - activemq::commands::ConsumerInfo, 1463
 - activemq::commands::ProducerInfo, 3098
 - activemq::core::ActiveMQConnection, 284
 - activemq::core::ActiveMQConnectionFactory, 298
- isDone
 - decaf::util::concurrent::Future, 1968
 - decaf::util::zip::DeflaterOutputStream, 1719
- isDroppable
 - activemq::commands::Message, 2526
- isDuplexConnection
 - activemq::commands::BrokerInfo, 900
- isDupsOkAcknowledge
 - activemq::core::ActiveMQSession, 528
- isEmpty
 - activemq::core::ActiveMQSessionExecutor, 535
 - activemq::core::MessageDispatchChannel, 2601
 - activemq::util::ActiveMQProperties, 480
 - cms::CMSProperties, 1167
 - decaf::internal::util::TimerTaskHeap, 3805
 - decaf::lang::String, 3666
 - decaf::util::AbstractCollection, 185
 - decaf::util::Collection, 1189
 - decaf::util::concurrent::ConcurrentStlMap, 1240
 - decaf::util::concurrent::SynchronousQueue, 3720
 - decaf::util::Map, 2465
 - decaf::util::Properties, 3129
 - decaf::util::StlList, 3597
 - decaf::util::StlMap, 3609
 - decaf::util::StlSet, 3627
- isEnabled
 - activemq::transport::failover::BackupTransportPool, 756
- isExclusive
 - activemq::commands::ActiveMQDestination, 328
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::ConnectionControl, 1270
- isExpired
 - activemq::commands::Message, 2526
- isExplicitQosEnabled
 - activemq::cmsutil::CmsTemplate, 1176
- isFailOnClose
 - activemq::transport::mock::MockTransport, 2772
- isFailOnKeepAliveSends
 - activemq::transport::mock::MockTransport, 2773
- isFailOnReceiveMessage
 - activemq::transport::mock::MockTransport, 2773
- isFailOnSendMessage
 - activemq::transport::mock::MockTransport, 2773
- isFailOnStart
 - activemq::transport::mock::MockTransport, 2773
- isFailOnStop
 - activemq::transport::mock::MockTransport, 2773
- isFair
 - decaf::util::concurrent::locks::ReentrantLock, 3184
 - decaf::util::concurrent::Semaphore, 3346
- isFaultTolerant
 - activemq::commands::ConnectionControl, 1270
 - activemq::commands::ConnectionInfo, 1358
 - activemq::transport::failover::FailoverTransport, 1878
 - activemq::transport::IOTransport, 2148

- activemq::transport::mock::MockTransport, 2773
- activemq::transport::tcp::TcpTransport, 3754
- activemq::transport::Transport, 3885
- activemq::transport::TransportFilter, 3894
- isFaultTolerantConfiguration
 - activemq::commands::BrokerInfo, 901
- isFlush
 - activemq::commands::ConsumerControl, 1404
- isFull
 - activemq::util::MemoryUsage, 2514
 - activemq::util::Usage, 3965
- isHeldByCurrentThread
 - decaf::util::concurrent::locks::ReentrantLock, 3184
- isIndividualAcknowledge
 - activemq::core::ActiveMQSession, 528
- isInfinite
 - decaf::lang::Double, 1793
 - decaf::lang::Float, 1909, 1910
- isInitialized
 - activemq::transport::failover::FailoverTransport, 1878
- isInputShutdown
 - decaf::net::Socket, 3514
- isInTransaction
 - activemq::core::ActiveMQTransactionContext, 721
- isISOCtrl
 - decaf::lang::Character, 1104
- isKeepAliveInfo
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1195
 - activemq::commands::KeepAliveInfo, 2268
- isKeepAliveResponseRequired
 - activemq::transport::inactivity::InactivityMonitor, 2005
- isLetter
 - decaf::lang::Character, 1104
- isLetterOrDigit
 - decaf::lang::Character, 1104
- isLinkLocalAddress
 - decaf::net::Inet4Address, 2012
 - decaf::net::InetAddress, 2020
- isLocked
 - decaf::util::concurrent::Lock, 2376
 - decaf::util::concurrent::locks::ReentrantLock, 3184
- isLoggable
 - decaf::util::logging::Filter, 1893
 - decaf::util::logging::Handler, 1980
 - decaf::util::logging::Logger, 2393
- decaf::util::logging::StreamHandler, 3651
- isLoopbackAddress
 - decaf::net::Inet4Address, 2012
 - decaf::net::InetAddress, 2020
- isLowerCase
 - decaf::lang::Character, 1104
- isManageable
 - activemq::commands::ConnectionInfo, 1359
- isMarshalAware
 - activemq::commands::ActiveMQMapMessage, 368
 - activemq::commands::BaseDataStructure, 832
 - activemq::commands::Message, 2526
 - activemq::commands::WireFormatInfo, 3987
 - activemq::wireformat::MarshalAware, 2485
- isMasterBroker
 - activemq::commands::BrokerInfo, 901
- isMCGlobal
 - decaf::net::Inet4Address, 2012
 - decaf::net::InetAddress, 2020
- isMCLinkLocal
 - decaf::net::Inet4Address, 2013
 - decaf::net::InetAddress, 2021
- isMCNodeLocal
 - decaf::net::Inet4Address, 2013
 - decaf::net::InetAddress, 2021
- isMCOrgLocal
 - decaf::net::Inet4Address, 2013
 - decaf::net::InetAddress, 2021
- isMCSiteLocal
 - decaf::net::Inet4Address, 2013
 - decaf::net::InetAddress, 2021
- isMessage
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1195
 - activemq::commands::Message, 2527
- isMessageAck
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1195
 - activemq::commands::MessageAck, 2562
- isMessageDispatch
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1196
 - activemq::commands::MessageDispatch, 2596
- isMessageDispatchNotification
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1196
 - activemq::commands::MessageDispatchNotification, 2632
- isMessageIdEnabled

- activemq::cmsutil::CmsTemplate, 1176
- isMessageTimestampEnabled
 - activemq::cmsutil::CmsTemplate, 1176
- isMulticastAddress
 - decaf::net::Inet4Address, 2013
 - decaf::net::InetAddress, 2021
- isNaN
 - decaf::lang::Double, 1794
 - decaf::lang::Float, 1910
- isNetworkConnection
 - activemq::commands::BrokerInfo, 901
- isNetworkSubscription
 - activemq::commands::ConsumerInfo, 1464
- isNoLocal
 - activemq::cmsutil::CmsTemplate, 1176
 - activemq::commands::ConsumerInfo, 1464
- isNoRangeAcks
 - activemq::commands::ConsumerInfo, 1464
- isOpaque
 - decaf::internal::net::URIType, 3956
 - decaf::net::URI, 3928
- isOptimizedAcknowledge
 - activemq::commands::ConsumerInfo, 1464
- isOrdered
 - activemq::commands::ActiveMQDestination, 328
- isOutputShutdown
 - decaf::net::Socket, 3514
- isPending
 - activemq::threads::CompositeTask, 1221
 - activemq::transport::failover::BackupTransportPool, 756
 - activemq::transport::failover::CloseTransportsTask, 1151
 - activemq::transport::failover::FailoverTransport, 1879
- isPersistent
 - activemq::commands::Message, 2527
- isPrepared
 - activemq::state::TransactionState, 3876
- isProducerAck
 - activemq::commands::BaseCommand, 761
 - activemq::commands::Command, 1196
 - activemq::commands::ProducerAck, 3038
- isProducerAdvisory
 - activemq::commands::ActiveMQDestination, 328
- isProducerInfo
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1196
 - activemq::commands::ProducerInfo, 3098
- isPubSubDomain
 - activemq::cmsutil::CmsDestinationAccessor, 1158
- isQueue
 - activemq::commands::ActiveMQDestination, 329
- isRandomize
 - activemq::transport::failover::FailoverTransport, 1879
 - activemq::transport::failover::URIPool, 3943
- isReadOnly
 - decaf::internal::nio::ByteBuffer, 1012
 - decaf::internal::nio::CharArrayBuffer, 1116
 - decaf::internal::nio::DoubleArrayBuffer, 1806
 - decaf::internal::nio::FloatArrayBuffer, 1922
 - decaf::internal::nio::IntArrayBuffer, 2063
 - decaf::internal::nio::LongArrayBuffer, 2441
 - decaf::internal::nio::ShortArrayBuffer, 3456
 - decaf::nio::Buffer, 931
 - decaf::nio::ByteBuffer, 1046
- isReadOnlyBody
 - activemq::commands::Message, 2527
- isReadOnlyProperties
 - activemq::commands::Message, 2527
- isRebalanceConnection
 - activemq::commands::ConnectionControl, 1270
- isRecievedByDFBridge
 - activemq::commands::Message, 2527
- isRemoveInfo
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1196
 - activemq::commands::RemoveInfo, 3196
- isRemoveSubscriptionInfo
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1196
 - activemq::commands::RemoveSubscriptionInfo, 3224
- isResponse
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1196
 - activemq::commands::Response, 3287
- isResponseRequired
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1196
- isRestoreConsumers
 - activemq::state::ConnectionStateTracker, 1394
- isRestoreProducers
 - activemq::state::ConnectionStateTracker, 1394
- isRestoreSessions
 - activemq::state::ConnectionStateTracker, 1394

- isRestoreTransaction
 - activemq::state::ConnectionStateTracker, 1394
- isResume
 - activemq::commands::ConnectionControl, 1270
- isRetroactive
 - activemq::commands::ConsumerInfo, 1464
- isRunning
 - activemq::core::ActiveMQSessionExecutor, 535
 - activemq::core::MessageDispatchChannel, 2602
- isScheduled
 - decaf::util::TimerTask, 3802
- isServerAuthority
 - decaf::internal::net::URIType, 3956
- isShutdownInfo
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1197
 - activemq::commands::ShutdownInfo, 3472
- isSiteLocalAddress
 - decaf::net::Inet4Address, 2014
 - decaf::net::InetAddress, 2022
- isSizePrefixDisabled
 - activemq::commands::WireFormatInfo, 3988
 - activemq::wireformat::openwire::OpenWireFormat, 2892
- isSlaveBroker
 - activemq::commands::BrokerInfo, 901
- isStackTraceEnabled
 - activemq::commands::WireFormatInfo, 3988
 - activemq::wireformat::openwire::OpenWireFormat, 2893
- isStart
 - activemq::commands::ConsumerControl, 1404
- isStarted
 - activemq::core::ActiveMQConnection, 284
 - activemq::core::ActiveMQSession, 528
- isStop
 - activemq::commands::ConsumerControl, 1404
- isSuspend
 - activemq::commands::ConnectionControl, 1270
- isSynchronizationRegistered
 - activemq::core::ActiveMQConsumer, 316
- isTcpNoDelayEnabled
 - activemq::commands::WireFormatInfo, 3988
- activemq::wireformat::openwire::OpenWireFormat, 2893
- isTemporary
 - activemq::commands::ActiveMQDestination, 329
- isTightEncodingEnabled
 - activemq::commands::WireFormatInfo, 3988
 - activemq::wireformat::openwire::OpenWireFormat, 2893
- isTopic
 - activemq::commands::ActiveMQDestination, 329
- isTrackMessages
 - activemq::state::ConnectionStateTracker, 1394
 - activemq::transport::failover::FailoverTransport, 1879
- isTrackTransactionProducers
 - activemq::state::ConnectionStateTracker, 1394
 - activemq::transport::failover::FailoverTransport, 1879
- isTrackTransactions
 - activemq::state::ConnectionStateTracker, 1394
- isTransacted
 - activemq::cmsutil::PooledSession, 2965
 - activemq::core::ActiveMQSession, 529
 - cms::Session, 3375
- isTransactionInfo
 - activemq::commands::BaseCommand, 762
 - activemq::commands::Command, 1197
 - activemq::commands::TransactionInfo, 3849
- isTransportFailed
 - activemq::core::ActiveMQConnection, 284
- isUpperCase
 - decaf::lang::Character, 1104
- isUseAsyncSend
 - activemq::core::ActiveMQConnection, 285
 - activemq::core::ActiveMQConnectionFactory, 299
- isUseCollisionAvoidance
 - activemq::core::policies::DefaultRedeliveryPolicy, 1679
 - activemq::core::RedeliveryPolicy, 3180
- isUseCompression
 - activemq::core::ActiveMQConnection, 285
 - activemq::core::ActiveMQConnectionFactory, 299
- isUseExponentialBackOff
 - activemq::core::policies::DefaultRedeliveryPolicy, 1679

- activemq::core::RedeliveryPolicy, 3180
- activemq::transport::failover::FailoverTransport, 1879
- isValid
 - activemq::commands::WireFormatInfo, 3988
 - decaf::internal::net::URIType, 3956
- isValidDomainName
 - decaf::internal::net::URIHelper, 3937
- isValidHexChar
 - decaf::internal::net::URIHelper, 3937
- isValidHost
 - decaf::internal::net::URIHelper, 3937
- isValidIP4Word
 - decaf::internal::net::URIHelper, 3937
- isValidIP6Address
 - decaf::internal::net::URIHelper, 3938
- isValidIPv4Address
 - decaf::internal::net::URIHelper, 3938
- isWaitingForResponse
 - activemq::state::Tracked, 3818
- isWhitespace
 - decaf::lang::Character, 1104
- isWildcard
 - activemq::commands::ActiveMQDestination, 329
- isWireFormatInfo
 - activemq::commands::BaseCommand, 763
 - activemq::commands::Command, 1197
 - activemq::commands::WireFormatInfo, 3988
- itemExists
 - activemq::commands::ActiveMQMapMessage, 368
 - cms::MapMessage, 2478
- iterate
 - activemq::core::ActiveMQConsumer, 316
 - activemq::core::ActiveMQSessionExecutor, 535
 - activemq::threads::CompositeTaskRunner, 1224
 - activemq::threads::Task, 3734
 - activemq::transport::failover::BackupTransportPool, 757
 - activemq::transport::failover::CloseTransportsTask, 1151
 - activemq::transport::failover::FailoverTransport, 1879
- iterator
 - decaf::lang::Iterable, 2152
 - decaf::util::concurrent::SynchronousQueue, 3721
 - decaf::util::PriorityQueue, 3032
 - decaf::util::StlList, 3598
- join
 - decaf::lang::Thread, 3770, 3771
- JournalQueueAck
 - activemq::commands::JournalQueueAck, 2157
- JournalQueueAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalQueueAck, 2180
 - activemq::wireformat::openwire::marshal::v2::JournalQueueAck, 2164
 - activemq::wireformat::openwire::marshal::v3::JournalQueueAck, 2172
 - activemq::wireformat::openwire::marshal::v4::JournalQueueAck, 2176
 - activemq::wireformat::openwire::marshal::v5::JournalQueueAck, 2168
 - activemq::wireformat::openwire::marshal::v6::JournalQueueAck, 2160
- JournalTopicAck
 - activemq::commands::JournalTopicAck, 2184
- JournalTopicAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTopicAck, 2209
 - activemq::wireformat::openwire::marshal::v2::JournalTopicAck, 2193
 - activemq::wireformat::openwire::marshal::v3::JournalTopicAck, 2197
 - activemq::wireformat::openwire::marshal::v4::JournalTopicAck, 2205
 - activemq::wireformat::openwire::marshal::v5::JournalTopicAck, 2189
 - activemq::wireformat::openwire::marshal::v6::JournalTopicAck, 2201
- JournalTrace
 - activemq::commands::JournalTrace, 2213
- JournalTraceMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTraceMa, 2216
 - activemq::wireformat::openwire::marshal::v2::JournalTraceMa, 2220
 - activemq::wireformat::openwire::marshal::v3::JournalTraceMa, 2228
 - activemq::wireformat::openwire::marshal::v4::JournalTraceMa, 2236
 - activemq::wireformat::openwire::marshal::v5::JournalTraceMa, 2224
 - activemq::wireformat::openwire::marshal::v6::JournalTraceMa, 2224
- JournalTransaction

- activemq::commands::JournalTransaction, 2240
- JournalTransactionMarshaller
 - activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller, 2263
 - activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller, 2247
 - activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller, 2251
 - activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller, 2259
 - activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller, 2255
 - activemq::wireformat::openwire::marshal::v6::JournalTransactionMarshaller, 2243
- KeepAliveInfo
 - activemq::commands::KeepAliveInfo, 2267
- KeepAliveInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller, 2290
 - activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller, 2274
 - activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller, 2278
 - activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller, 2282
 - activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller, 2286
 - activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller, 2270
- KeyException
 - decaf::security::KeyException, 2295, 2296
- KeyManagementException
 - decaf::security::KeyManagementException, 2298, 2299
- keySet
 - decaf::util::concurrent::ConcurrentStlMap, 1240
 - decaf::util::Map, 2466
 - decaf::util::StlMap, 3609
- l_buf
 - internal_state, 2120
- L_CODES
 - deflate.h, 4727
- l_desc
 - internal_state, 2120
- last
 - inflate_state, 2025
- last_eob_len
 - internal_state, 2120
- last_flush
 - internal_state, 2120
- last_lit
 - internal_state, 2120
- lastDeliveredSequenceId
 - activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller, 3197
- lastIndexOf
 - decaf::util::StlList, 3598
- lastPartialCommand
 - activemq::commands::MessageAck, 2564
- LastPartialCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller, 2325
 - activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller, 2313
 - activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller, 2309
 - activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller, 2311
 - activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller, 2317
 - activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller, 2305
- LEN
 - deflate.h, 4727
- len
 - ct_data_s, 1527
- LEN_
 - inflate.h, 4733
- lenbits
 - inflate_state, 2025
- lencode
 - inflate_state, 2025
- LENEXT
 - inflate.h, 4733
- LENGTH
 - inflate.h, 4733
- length
 - decaf::internal::nio::CharArrayBuffer, 1118
 - decaf::lang::ArrayPointer, 733
 - decaf::lang::CharSequence, 1136
 - decaf::lang::String, 3667
 - decaf::nio::CharBuffer, 1128
 - decaf::util::zip::InflaterInputStream, 2041
 - inflate_state, 2025
- LENGTH_CODES
 - deflate.h, 4727

- LENLENS
 - inflate.h, 4733
- LENS
 - inftrees.h, 4734
- lens
 - inflate_state, 2025
- Less
 - decaf::util::comparators::Less, 2328
- Level
 - decaf::util::logging::Level, 2333
- level
 - gz_state, 1977
 - internal_state, 2120
- Levels
 - decaf::util::logging, 176
- limit
 - decaf::nio::Buffer, 931, 932
- LineNumber
 - activemq::commands::BrokerError::StackTraceElement, 3578
- List
 - decaf::util::List, 2338
- LIST_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- listen
 - decaf::internal::net::tcp::TcpSocket, 3744
 - decaf::net::SocketImpl, 3534
- listener
 - activemq::transport::TransportFilter, 3898
- listIterator
 - decaf::util::List, 2340, 2341
 - decaf::util::StlList, 3598, 3599
- listValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
- LIT
 - inflate.h, 4733
- lit_bufsize
 - internal_state, 2120
- LITERALS
 - deflate.h, 4727
- load
 - decaf::util::Properties, 3129, 3131
- local
 - gzguts.h, 4729
- localPort
 - decaf::net::SocketImpl, 3536
- LocalTransactionId
 - activemq::commands::LocalTransactionId, 2348
- LocalTransactionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller, 2372
- activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller, 2356
- activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller, 2360
- activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaller, 2368
- activemq::wireformat::openwire::marshal::v5::LocalTransactionIdMarshaller, 2364
- activemq::wireformat::openwire::marshal::v6::LocalTransactionIdMarshaller, 2352
- Lock
 - decaf::util::concurrent::Lock, 2375
- lock
 - activemq::core::MessageDispatchChannel, 2602
 - decaf::internal::util::concurrent::MutexImpl, 2788
 - decaf::internal::util::concurrent::SynchronizableImpl, 3712
 - decaf::io::InputStream, 2046
 - decaf::io::OutputStream, 2910
 - decaf::util::AbstractCollection, 186
 - decaf::util::concurrent::ConcurrentStlMap, 1241
 - decaf::util::concurrent::Lock, 2376
 - decaf::util::concurrent::locks::Lock, 2378
 - decaf::util::concurrent::locks::ReentrantLock, 3184
 - decaf::util::concurrent::Mutex, 2783
 - decaf::util::concurrent::Synchronizable, 3701
 - decaf::util::StlMap, 3609
 - decaf::util::StlQueue, 3618
- lock_count
 - decaf::util::concurrent::MutexHandle, 2787
- lock_owner
 - decaf::util::concurrent::MutexHandle, 2787
- lockInterruptibly
 - decaf::util::concurrent::locks::Lock, 2379
 - decaf::util::concurrent::locks::ReentrantLock, 3185
- log
 - decaf::util::logging::Logger, 2394
 - decaf::util::logging::LogWriter, 2418, 2419
 - decaf::util::logging::SimpleLogger, 3502
- LOGDECAF_DEBUG
 - LoggerDefines.h, 4933
- LOGDECAF_DEBUG_1
 - LoggerDefines.h, 4933
- LOGDECAF_DECLARE
 - LoggerDefines.h, 4933
- LOGDECAF_DECLARE_LOCAL
 - LoggerDefines.h, 4933
- LOGDECAF_ERROR
 - LoggerDefines.h, 4933

- LoggerDefines.h, 4934
- LOGDECAF_FATAL
 - LoggerDefines.h, 4934
- LOGDECAF_INFO
 - LoggerDefines.h, 4934
- LOGDECAF_INITIALIZE
 - LoggerDefines.h, 4934
- LOGDECAF_WARN
 - LoggerDefines.h, 4934
- Logger
 - decaf::util::logging::Logger, 2389
- LoggerDefines.h
 - LOGDECAF_DEBUG, 4933
 - LOGDECAF_DEBUG_1, 4933
 - LOGDECAF_DECLARE, 4933
 - LOGDECAF_DECLARE_LOCAL, 4934
 - LOGDECAF_ERROR, 4934
 - LOGDECAF_FATAL, 4934
 - LOGDECAF_INFO, 4934
 - LOGDECAF_INITIALIZE, 4934
 - LOGDECAF_WARN, 4934
- LoggerHierarchy
 - decaf::util::logging::LoggerHierarchy, 2398
- LoggingInputStream
 - activemq::io::LoggingInputStream, 2399
- LoggingOutputStream
 - activemq::io::LoggingOutputStream, 2401
- LoggingTransport
 - activemq::transport::logging::LoggingTransport, 2403
- LogManager
 - decaf::util::logging::LogManager, 2408
- LogRecord
 - decaf::util::logging::LogRecord, 2414
- LogWriter
 - decaf::util::logging::LogWriter, 2418
- Long
 - decaf::lang::Long, 2422
- LONG_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- LongArrayBuffer
 - decaf::internal::nio::LongArrayBuffer, 2437, 2438
- longBitsToDouble
 - decaf::lang::Double, 1794
- LongBuffer
 - decaf::nio::LongBuffer, 2446
- LongSequenceGenerator
 - activemq::util::LongSequenceGenerator, 2455
- longValue
 - activemq::util::PrimitiveValueNode::PrimitiveValue, 3009
 - decaf::lang::Byte, 964
 - decaf::lang::Character, 1104
 - decaf::lang::Double, 1794
 - decaf::lang::Float, 1910
 - decaf::lang::Integer, 2082
 - decaf::lang::Long, 2425
 - decaf::lang::Number, 2836
 - decaf::lang::Short, 3444
 - decaf::util::concurrent::atomic::AtomicInteger, 745
- LOOK
 - gzguts.h, 4729
- lookahead
 - internal_state, 2120
- loopbackBytes
 - decaf::net::InetAddress, 2022
- looseMarshal
 - activemq::wireformat::openwire::marshal::BaseDataStreamMarshal, 813
 - activemq::wireformat::openwire::marshal::DataStreamMarshal, 1623
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMarshal, 214
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMarshal, 254
 - activemq::wireformat::openwire::marshal::v1::ActiveMQDestination, 338
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMapMarshal, 379
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMessage, 406
 - activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMarshal, 451
 - activemq::wireformat::openwire::marshal::v1::ActiveMQQueue, 496
 - activemq::wireformat::openwire::marshal::v1::ActiveMQStream, 557
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplate, 585
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplate, 614
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplate, 647
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTextMarshal, 676
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTopic, 704
 - activemq::wireformat::openwire::marshal::v1::BaseCommandMarshal, 780
 - activemq::wireformat::openwire::marshal::v1::BrokerIdMarshal, 881
 - activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshal, 913
 - activemq::wireformat::openwire::marshal::v1::ConnectionControl, 1281

activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller	2817
activemq::wireformat::openwire::marshal::v1::NetworkBridgeFactory	1313
activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller	2943
activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller	1344
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller	1374
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller	3061
activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller	1419
activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller	3093
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	1448
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	3110
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	1481
activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller	3211
activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionMarshaller	1510
activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionMarshaller	3228
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller	1544
activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller	3259
activemq::wireformat::openwire::marshal::v1::ResponseMarshaller	1607
activemq::wireformat::openwire::marshal::v1::ResponseMarshaller	3316
activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller	1745
activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller	3404
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller	1779
activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller	3420
activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller	1863
activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller	3482
activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller	1957
activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaller	3681
activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller	2111
activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller	3828
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller	2180
activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller	3856
activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller	2209
activemq::wireformat::openwire::marshal::v1::WireFormatInfoMarshaller	4009
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller	2232
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller	4049
activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMarshaller	2263
activemq::wireformat::openwire::marshal::v2::ActiveMQBlobMarshaller	222
activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMarshaller	2290
activemq::wireformat::openwire::marshal::v2::ActiveMQBytesMarshaller	270
activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller	2325
activemq::wireformat::openwire::marshal::v2::ActiveMQDestinationMarshaller	350
activemq::wireformat::openwire::marshal::v2::ActiveMQMapMarshaller	2372
activemq::wireformat::openwire::marshal::v2::ActiveMQMapMarshaller	391
activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller	2582
activemq::wireformat::openwire::marshal::v2::ActiveMQMessageMarshaller	418
activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMarshaller	2623
activemq::wireformat::openwire::marshal::v2::ActiveMQObjectMarshaller	463
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller	2652
activemq::wireformat::openwire::marshal::v2::ActiveMQQueueMarshaller	508
activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMarshaller	2689
activemq::wireformat::openwire::marshal::v2::ActiveMQStreamMarshaller	569
activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller	2714
activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller	597
activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller	2761
activemq::wireformat::openwire::marshal::v2::ActiveMQTempMarshaller	626

activemq::wireformat::openwire::marshal::v2::ActiveMQTempTopicMarshaller	2356	activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller	2356
655		activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller	2570
activemq::wireformat::openwire::marshal::v2::ActiveMQTextMessageMarshaller	2570	activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller	2607
688		activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2640
activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller	2607	activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2669
716		activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	2704
activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller	2640	activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller	2745
801		activemq::wireformat::openwire::marshal::v2::NetworkBridgeFactory	2797
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller	2669	activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller	2927
893		activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller	2927
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller	2704	activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller	3041
925		activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller	3073
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller	2745	activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller	3106
1293		activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller	3199
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller	2797	activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionMarshaller	3236
1301		activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller	3263
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller	2927	activemq::wireformat::openwire::marshal::v2::ResponseMarshaller	3301
1332		activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller	3384
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller	3041	activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller	3428
1362		activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller	3478
activemq::wireformat::openwire::marshal::v2::ConsumerGroupMarshaller	3073	activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	3697
1407		activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller	3832
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller	3106	activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller	3872
1436		activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller	4001
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller	3199	activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller	4041
1469		activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller	4041
activemq::wireformat::openwire::marshal::v2::ContactGroupAndIdMarshaller	3236	activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMarshaller	210
1498		activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMarshaller	250
activemq::wireformat::openwire::marshal::v2::DataAndResponseMarshaller	3263	activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller	334
1532		activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller	334
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	3301		
1595			
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller	3384		
1733			
activemq::wireformat::openwire::marshal::v2::DiscardInfoMarshaller	3428		
1767			
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	3478		
1847			
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller	3697		
1945			
activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaller	3832		
2099			
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	3872		
2164			
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	4001		
2193			
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	4041		
2216			
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	210		
2247			
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller	250		
2274			
activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller	334		
2313			

activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller	2103
375	
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller	2172
402	
activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller	2197
447	
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMessageMarshaller	2220
492	
activemq::wireformat::openwire::marshal::v3::ActiveMQSequenceMessageMarshaller	2251
553	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller	2278
581	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	2309
610	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller	2360
639	
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	2574
668	
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller	2611
696	
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller	2644
766	
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	2681
873	
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	2699
905	
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	2753
1273	
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	2809
1305	
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	2935
1336	
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	3049
1366	
activemq::wireformat::openwire::marshal::v3::ConsumerGroupMarshaller	3081
1411	
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	3118
1440	
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	3207
1473	
activemq::wireformat::openwire::marshal::v3::ContentCommandMarshaller	3232
1502	
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller	3267
1536	
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller	3311
1599	
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	3400
1737	
activemq::wireformat::openwire::marshal::v3::DiscardEventMarshaller	3424
1771	
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	3490
1851	
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	3677
1949	

activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	1506
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	3836
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	3860
activemq::wireformat::openwire::marshal::v3::WireFormatWireMarshaller	1540
activemq::wireformat::openwire::marshal::v3::WireFormatWireMarshaller	4013
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	1603
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	4053
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobWireMessageMarshaller	1741
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobWireMessageMarshaller	218
activemq::wireformat::openwire::marshal::v4::ActiveMQByteWireMessageMarshaller	1775
activemq::wireformat::openwire::marshal::v4::ActiveMQByteWireMessageMarshaller	258
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	1859
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	342
activemq::wireformat::openwire::marshal::v4::ActiveMQMapWireMessageMarshaller	1953
activemq::wireformat::openwire::marshal::v4::ActiveMQMapWireMessageMarshaller	383
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	2107
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	410
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectWireMessageMarshaller	2176
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectWireMessageMarshaller	455
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	2205
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	500
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	561
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	589
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	618
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	643
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	672
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMarshaller	700
activemq::wireformat::openwire::marshal::v4::BaseCommandWireMarshaller	2619
activemq::wireformat::openwire::marshal::v4::BaseCommandWireMarshaller	773
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2648
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	877
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	909
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1277
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1309
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1340
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1370
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1415
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1444
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1477
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1506
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1540
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1603
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1741
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1775
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1859
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	1953
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2107
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2176
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2205
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2228
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2259
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2282
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2321
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2368
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2578
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2619
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2648
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2673
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2709
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2757
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2813
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2939
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	3045
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	3077
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	3102
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	3219

activemq::wireformat::openwire::marshal::v4::RemoteSubscriptionInfoMarshaller	1285
activemq::wireformat::openwire::marshal::v4::ReplyCommandMarshaller	1317
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	1348
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	1378
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	1423
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	1452
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	1485
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	1514
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	1548
activemq::wireformat::openwire::marshal::v4::WireFormatMarshaller	1587
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller	1753
activemq::wireformat::openwire::marshal::v5::ActiveMQBlockWireFormatMarshaller	1783
activemq::wireformat::openwire::marshal::v5::ActiveMQByteMessageMarshaller	1855
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	1961
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	2115
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	2168
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	2189
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	2236
activemq::wireformat::openwire::marshal::v5::ActiveMQStackingMessageMarshaller	2255
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	2286
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	2317
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	2364
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	2586
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	2615
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller	2656
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	2677
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller	2694

activemq::wireformat::openwire::marshal::v5::MessagePublishInfoFormat	2749	activemq::wireformat::openwire::marshal::v6::ActiveMQTemp	630
activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshal	2805	activemq::wireformat::openwire::marshal::v6::ActiveMQTemp	659
activemq::wireformat::openwire::marshal::v5::PartialCommandFormat	2931	activemq::wireformat::openwire::marshal::v6::ActiveMQTextM	684
activemq::wireformat::openwire::marshal::v5::ProducerAckWireFormat	3053	activemq::wireformat::openwire::marshal::v6::ActiveMQTopicC	712
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshal	3085	activemq::wireformat::openwire::marshal::v6::BaseCommandM	794
activemq::wireformat::openwire::marshal::v5::ProducerInfoWireFormat	3114	activemq::wireformat::openwire::marshal::v6::BrokerIdMarshal	889
activemq::wireformat::openwire::marshal::v5::RemoteInfoWireFormat	3215	activemq::wireformat::openwire::marshal::v6::BrokerInfoMarsh	921
activemq::wireformat::openwire::marshal::v5::RemoteSubscriptionInfoMarshal	3244	activemq::wireformat::openwire::marshal::v6::ConnectionCont	1289
activemq::wireformat::openwire::marshal::v5::ReplaceCommandFormat	3275	activemq::wireformat::openwire::marshal::v6::ConnectionError	1321
activemq::wireformat::openwire::marshal::v5::ResponseMarshal	3306	activemq::wireformat::openwire::marshal::v6::ConnectionIdMa	1352
activemq::wireformat::openwire::marshal::v5::SessionIdMarshal	3396	activemq::wireformat::openwire::marshal::v6::ConnectionInfoM	1382
activemq::wireformat::openwire::marshal::v5::SessionInfoMarshal	3416	activemq::wireformat::openwire::marshal::v6::ConsumerContro	1427
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshal	3486	activemq::wireformat::openwire::marshal::v6::ConsumerIdMar	1456
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshal	3685	activemq::wireformat::openwire::marshal::v6::ConsumerInfoMa	1489
activemq::wireformat::openwire::marshal::v5::TransactionIdMarshal	3824	activemq::wireformat::openwire::marshal::v6::ControlComman	1518
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshal	3852	activemq::wireformat::openwire::marshal::v6::DataArrayRespo	1552
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshal	3993	activemq::wireformat::openwire::marshal::v6::DataResponseM	1591
activemq::wireformat::openwire::marshal::v5::XATransactionInfoMarshal	4057	activemq::wireformat::openwire::marshal::v6::DestinationInfoM	1749
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobWireFormat	230	activemq::wireformat::openwire::marshal::v6::DiscoveryEventM	1763
activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshal	266	activemq::wireformat::openwire::marshal::v6::ExceptionRespor	1843
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationFormat	354	activemq::wireformat::openwire::marshal::v6::FlushCommandI	1941
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshal	395	activemq::wireformat::openwire::marshal::v6::IntegerResponse	2095
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueWireFormat	422	activemq::wireformat::openwire::marshal::v6::JournalQueueAc	2160
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectWireMessageMarshal	467	activemq::wireformat::openwire::marshal::v6::JournalTopicAck	2201
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueWireFormat	512	activemq::wireformat::openwire::marshal::v6::JournalTraceMa	2224
activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceMessageMarshal	573	activemq::wireformat::openwire::marshal::v6::JournalTransact	2243
activemq::wireformat::openwire::marshal::v6::ActiveMQTempInfoFormat	601	activemq::wireformat::openwire::marshal::v6::KeepAliveInfoM	2270

- activemq::wireformat::openwire::marshal::v6::LastPartialCommandMarshaller, 814
- 2305
- activemq::wireformat::openwire::marshal::v6::LooseMarshallingIdMarshaller, 814
- 2352
- activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller, 814
- 2566
- looseMarshalNestedObject
- activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller, 815
- 2627
- activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller, 2893
- 2636
- activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller, 2685
- 2685
- looseMarshalObjectArray
- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 815
- 2719
- looseMarshalString
- activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller, 815
- 2765
- activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshaller, 810
- 2801
- looseCmmarsh
- activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 810
- 2923
- activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller, 1631
- 3057
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 214
- 3089
- activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMarshaller, 294
- 3122
- activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMarshaller, 338
- 3203
- activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller, 379
- 3240
- activemq::wireformat::openwire::marshal::v1::ActiveMQMapMarshaller, 406
- 3271
- activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMarshaller, 451
- 3321
- activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller, 496
- 3392
- activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMarshaller, 557
- 3412
- activemq::wireformat::openwire::marshal::v1::ActiveMQTempMarshaller, 585
- 3474
- activemq::wireformat::openwire::marshal::v1::ActiveMQTempMarshaller, 614
- 3693
- activemq::wireformat::openwire::marshal::v1::ActiveMQTempMarshaller, 647
- 3844
- activemq::wireformat::openwire::marshal::v1::ActiveMQTextMarshaller, 676
- 3864
- activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller, 704
- 3997
- activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller, 781
- 4037
- looseMarshalBrokerError, 881
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 814
- looseMarshalCachedObject, 913

activemq::wireformat::openwire::marshal::v1::ConnectionControlMarshaller; openwire::marshal::v1::MessagePullMarshaller 2761
 1281
 activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller; openwire::marshal::v1::NetworkBridgeFailureMarshaller 2817
 1313
 activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller; openwire::marshal::v1::PartialCommandMarshaller 2944
 1344
 activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller; openwire::marshal::v1::ProducerAckMarshaller 3061
 1374
 activemq::wireformat::openwire::marshal::v1::ConsumerGroupViewMarshaller; openwire::marshal::v1::ProducerIdMarshaller 3093
 1419
 activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller; openwire::marshal::v1::ProducerInfoMarshaller 3110
 1448
 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller; openwire::marshal::v1::RemoveInfoMarshaller 3211
 1481
 activemq::wireformat::openwire::marshal::v1::ContentCommandMarshaller; openwire::marshal::v1::RemoveSubscriptionMarshaller 3228
 1510
 activemq::wireformat::openwire::marshal::v1::DataActiveResponseMarshaller; openwire::marshal::v1::ReplayCommandMarshaller 3259
 1545
 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller; openwire::marshal::v1::ResponseMarshaller 3317
 1608
 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller; openwire::marshal::v1::SessionIdMarshaller 3404
 1745
 activemq::wireformat::openwire::marshal::v1::DisconnectViewMarshaller; openwire::marshal::v1::SessionInfoMarshaller 3420
 1779
 activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller; openwire::marshal::v1::ShutdownInfoMarshaller 3482
 1864
 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller; openwire::marshal::v1::SubscriptionInfoMarshaller 3681
 1957
 activemq::wireformat::openwire::marshal::v1::IntegrationResponseMarshaller; openwire::marshal::v1::TransactionIdMarshaller 3828
 2112
 activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller; openwire::marshal::v1::TransactionInfoMarshaller 3856
 2180
 activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller; openwire::marshal::v1::WireFormatInfoMarshaller 4009
 2209
 activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller; openwire::marshal::v1::XATransactionInfoMarshaller 4049
 2232
 activemq::wireformat::openwire::marshal::v1::JournalTransactionViewMarshaller; openwire::marshal::v2::ActiveMQBlobMarshaller 222
 2263
 activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaller; openwire::marshal::v2::ActiveMQBytesMarshaller 270
 2290
 activemq::wireformat::openwire::marshal::v1::LastPartialCommandMarshaller; openwire::marshal::v2::ActiveMQDestinationMarshaller 350
 2326
 activemq::wireformat::openwire::marshal::v1::LocalTransactionIdMarshaller; openwire::marshal::v2::ActiveMQMapMarshaller 391
 2372
 activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller; openwire::marshal::v2::ActiveMQMessageMarshaller 418
 2582
 activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller; openwire::marshal::v2::ActiveMQObjectMarshaller 463
 2623
 activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller; openwire::marshal::v2::ActiveMQQueueMarshaller 508
 2652
 activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller; openwire::marshal::v2::ActiveMQStreamMarshaller 569
 2689
 activemq::wireformat::openwire::marshal::v1::MessageMarshaller; openwire::marshal::v2::ActiveMQTempMessageMarshaller 597
 2714

activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller; openwire::marshal::v3::FlushCommand	1949
334	
activemq::wireformat::openwire::marshal::v3::ActiveMQMapMessageMarshaller; openwire::marshal::v3::IntegerResponse	2104
375	
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller; openwire::marshal::v3::JournalQueueAck	2172
402	
activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller; openwire::marshal::v3::JournalTopicAck	2197
447	
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller; openwire::marshal::v3::JournalTraceMa	2220
492	
activemq::wireformat::openwire::marshal::v3::ActiveMQSequenceMessageMarshaller; openwire::marshal::v3::JournalTransact	2251
553	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDestinationMarshaller; openwire::marshal::v3::KeepAliveInfoM	2278
581	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller; openwire::marshal::v3::LastPartialComm	2310
610	
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller; openwire::marshal::v3::LocalTransaction	2360
639	
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller; openwire::marshal::v3::MessageAckMar	2574
668	
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller; openwire::marshal::v3::MessageDispatch	2611
696	
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller; openwire::marshal::v3::MessageDispatch	2644
767	
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller; openwire::marshal::v3::MessageIdMarsh	2681
873	
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller; openwire::marshal::v3::MessageMarsh	2699
905	
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller; openwire::marshal::v3::MessagePullMar	2753
1273	
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller; openwire::marshal::v3::NetworkBridgeF	2809
1305	
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller; openwire::marshal::v3::PartialCommand	2936
1336	
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller; openwire::marshal::v3::ProducerAckMar	3049
1366	
activemq::wireformat::openwire::marshal::v3::ConsumerControlMarshaller; openwire::marshal::v3::ProducerIdMars	3081
1411	
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller; openwire::marshal::v3::ProducerInfoMa	3118
1440	
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller; openwire::marshal::v3::RemoveInfoMars	3207
1473	
activemq::wireformat::openwire::marshal::v3::ContentCommandMarshaller; openwire::marshal::v3::RemoveSubscrip	3232
1502	
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller; openwire::marshal::v3::ReplayCommand	3267
1537	
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller; openwire::marshal::v3::ResponseMarsha	3312
1600	
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller; openwire::marshal::v3::SessionIdMarsha	3400
1737	
activemq::wireformat::openwire::marshal::v3::DiscardRequestMarshaller; openwire::marshal::v3::SessionInfoMars	3424
1771	
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller; openwire::marshal::v3::ShutdownInfoM	3490
1852	

activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller	1477
3677	
activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	1506
3836	
activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller	1541
3860	
activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	1604
4013	
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	1741
4053	
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobWireFormatMarshaller	1775
218	
activemq::wireformat::openwire::marshal::v4::ActiveMQByteWireFormatMarshaller	1860
258	
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	1953
342	
activemq::wireformat::openwire::marshal::v4::ActiveMQMapWireFormatMarshaller	2108
383	
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	2176
410	
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectWireFormatMarshaller	2205
455	
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireFormatMarshaller	2228
500	
activemq::wireformat::openwire::marshal::v4::ActiveMQSequenceWireFormatMarshaller	2259
561	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller	2282
589	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	2322
618	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller	2368
643	
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	2578
672	
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller	2619
700	
activemq::wireformat::openwire::marshal::v4::BaseCommandWireFormatMarshaller	2648
774	
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2673
877	
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	2709
909	
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	2757
1277	
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaller	2813
1309	
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller	2940
1340	
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	3045
1370	
activemq::wireformat::openwire::marshal::v4::ConsumerControlMarshaller	3077
1415	
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	3102
1444	
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	

activemq::wireformat::openwire::marshal::v4::RemoteInfoMarshaller	917
activemq::wireformat::openwire::marshal::v4::RemoteInfoMarshaller	3219
activemq::wireformat::openwire::marshal::v4::RemoteSubscriptionInfoMarshaller	1285
activemq::wireformat::openwire::marshal::v4::RemoteSubscriptionInfoMarshaller	3248
activemq::wireformat::openwire::marshal::v4::ReplyCommandMarshaller	1317
activemq::wireformat::openwire::marshal::v4::ReplyCommandMarshaller	3255
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	1348
activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	3297
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	1378
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	3388
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	1423
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	3432
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	1452
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	3494
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	1485
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	3689
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	1514
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	3840
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	1549
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	3868
activemq::wireformat::openwire::marshal::v4::WireFormatMarshaller	1588
activemq::wireformat::openwire::marshal::v4::WireFormatMarshaller	4005
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller	1753
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller	4045
activemq::wireformat::openwire::marshal::v5::ActiveMQBlockWireFormatMarshaller	1783
activemq::wireformat::openwire::marshal::v5::ActiveMQBlockWireFormatMarshaller	226
activemq::wireformat::openwire::marshal::v5::ActiveMQByteMessageMarshaller	1856
activemq::wireformat::openwire::marshal::v5::ActiveMQByteMessageMarshaller	262
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	1961
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	346
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	2116
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	387
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	2168
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	414
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	2189
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	459
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	2236
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller	504
activemq::wireformat::openwire::marshal::v5::ActiveMQStackedMessageMarshaller	2255
activemq::wireformat::openwire::marshal::v5::ActiveMQStackedMessageMarshaller	565
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	2286
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	593
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	2318
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	622
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	2364
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	651
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	2586
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	680
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	2615
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	708
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller	2656
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller	788
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	2677
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	885

activemq::wireformat::openwire::marshal::v5::MessageMarshaller	601	activemq::wireformat::openwire::marshal::v6::ActiveMQTemp
2694		
activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller	630	activemq::wireformat::openwire::marshal::v6::ActiveMQTemp
2749		
activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshaller	659	activemq::wireformat::openwire::marshal::v6::ActiveMQTemp
2805		
activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller	684	activemq::wireformat::openwire::marshal::v6::ActiveMQTextM
2932		
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	712	activemq::wireformat::openwire::marshal::v6::ActiveMQTopicC
3053		
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	795	activemq::wireformat::openwire::marshal::v6::BaseCommandM
3085		
activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller	889	activemq::wireformat::openwire::marshal::v6::BrokerIdMarsh
3114		
activemq::wireformat::openwire::marshal::v5::RemoteInfoMarshaller	921	activemq::wireformat::openwire::marshal::v6::BrokerInfoMarsh
3215		
activemq::wireformat::openwire::marshal::v5::RemoteSubscriptionInfoMarshaller	1289	activemq::wireformat::openwire::marshal::v6::ConnectionCont
3244		
activemq::wireformat::openwire::marshal::v5::ReplyCommandMarshaller	1321	activemq::wireformat::openwire::marshal::v6::ConnectionError
3275		
activemq::wireformat::openwire::marshal::v5::ResponseMarshaller	1352	activemq::wireformat::openwire::marshal::v6::ConnectionIdMa
3307		
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller	1382	activemq::wireformat::openwire::marshal::v6::ConnectionInfoM
3396		
activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller	1427	activemq::wireformat::openwire::marshal::v6::ConsumerContro
3416		
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller	1456	activemq::wireformat::openwire::marshal::v6::ConsumerIdMar
3486		
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller	1489	activemq::wireformat::openwire::marshal::v6::ConsumerInfoMa
3685		
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller	1518	activemq::wireformat::openwire::marshal::v6::ControlComman
3824		
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller	1553	activemq::wireformat::openwire::marshal::v6::DataArrayRespo
3852		
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller	1592	activemq::wireformat::openwire::marshal::v6::DataResponseM
3993		
activemq::wireformat::openwire::marshal::v5::XATransactionMarshaller	1749	activemq::wireformat::openwire::marshal::v6::DestinationInfoM
4057		
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobWireFormatMarshaller	1763	activemq::wireformat::openwire::marshal::v6::DiscoveryEventM
230		
activemq::wireformat::openwire::marshal::v6::ActiveMQByteWireFormatMarshaller	1844	activemq::wireformat::openwire::marshal::v6::ExceptionRespo
266		
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller	1941	activemq::wireformat::openwire::marshal::v6::FlushCommandI
354		
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller	2096	activemq::wireformat::openwire::marshal::v6::IntegerResponse
395		
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	2160	activemq::wireformat::openwire::marshal::v6::JournalQueueAc
422		
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectWireMessageMarshaller	2201	activemq::wireformat::openwire::marshal::v6::JournalTopicAck
467		
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller	2224	activemq::wireformat::openwire::marshal::v6::JournalTraceMa
512		
activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceMessageMarshaller	2243	activemq::wireformat::openwire::marshal::v6::JournalTransact
573		

- activemq::wireformat::openwire::marshal::v6::KeepAliveInfoMarshaller, 2270
- activemq::wireformat::openwire::marshal::v6::LastActiveCommandMarshaller, 2306
- activemq::wireformat::openwire::marshal::v6::LostTimedOutLocalMsgObject, 2352
- activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller, 2566
- activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller, 2627
- activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller, 2636
- activemq::wireformat::openwire::marshal::v6::MessageIDMarshaller, 2685
- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 2719
- activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller, 2765
- activemq::wireformat::openwire::marshal::v6::NewURLBridgeStreamMarshaller, 2801
- activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2924
- activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller, 3057
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3089
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3122
- activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller, 3203
- activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller, 3240
- activemq::wireformat::openwire::marshal::v6::ReplyCommandMarshaller, 3271
- activemq::wireformat::openwire::marshal::v6::ResponseMarshaller, 3322
- activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3392
- activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller, 3412
- activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3474
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller, 3693
- activemq::wireformat::openwire::marshal::v6::TransportIdMarshaller, 3844
- activemq::wireformat::openwire::marshal::v6::TransportInfoMarshaller, 3864
- activemq::wireformat::openwire::marshal::v6::MarkBlockInfoMarshaller, 3997
- activemq::wireformat::openwire::marshal::v6::MarkBlockLoggerMarshaller, 4037
- looseUnmarshalBrokerError, 2483
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 2483

- decaf::io::BufferedInputStream, 937
- decaf::io::ByteArrayInputStream, 1024
- decaf::io::FilterInputStream, 1898
- decaf::io::InputStream, 2046
- decaf::io::PushbackInputStream, 3144
- decaf::io::Reader, 3165
- decaf::util::zip::InflaterInputStream, 2040
- marshal
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3003
 - activemq::wireformat::openwire::OpenWireFormat, 2894
 - activemq::wireformat::openwire::utils::BooleanStream, 858
 - activemq::wireformat::stomp::StompWireFormat, 3645
 - activemq::wireformat::WireFormat, 3978
- marshalledProperties
 - activemq::commands::Message, 2532
- marshalledSize
 - activemq::wireformat::openwire::utils::BooleanStream, 858
- MarshallingSupport
 - activemq::util::MarshallingSupport, 2494
- marshalList
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3003
- marshalMap
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3004
- marshalPrimitive
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3004
- marshalPrimitiveList
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3004
- marshalPrimitiveMap
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3004
- masterBroker
 - activemq::commands::BrokerInfo, 903
- MATCH
 - inflate.h, 4733
- match_available
 - internal_state, 2120
- match_length
 - internal_state, 2120
- match_start
 - internal_state, 2120
- matches
 - internal_state, 2120
- Math
 - decaf::lang::Math, 2499
- max
 - decaf::lang::Math, 2501, 2502
- MAX_BITS
 - deflate.h, 4727
- max_chain_length
 - internal_state, 2120
- max_code
 - tree_desc_s, 3905
- MAX_DIST
 - deflate.h, 4727
- max_insert_length
 - deflate.h, 4727
- max_lazy_match
 - internal_state, 2120
- MAX_MATCH
 - zutil.h, 4745
- MAX_MEM_LEVEL
 - zconf.h, 4738
- MAX_PREFETCH_SIZE
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
- MAX_PRIORITY
 - decaf::lang::Thread, 3773
- MAX_RADIX
 - decaf::lang::Character, 1106
- MAX_VALUE
 - decaf::lang::Character, 1106
 - decaf::lang::Double, 1798
 - decaf::lang::Integer, 2090
 - decaf::lang::Long, 2433
 - decaf::lang::Short, 3448
- MAX_WBITS
 - zconf.h, 4738
- maxValuePerDispatchMessageLimit
 - activemq::commands::ConsumerInfo, 1466
- MEM
 - inflate.h, 4733
- MemoryUsage
 - activemq::util::MemoryUsage, 2513
- MESSAGE
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- Message
 - activemq::commands::Message, 2520
- message
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3176
 - activemq::commands::JournalTrace, 2214
 - activemq::commands::MessageDispatch, 2598
 - decaf::lang::Exception, 1837
- MessageAck
 - activemq::commands::MessageAck, 2560

- | | |
|--|---|
| messageAck | cms::MessageEOFException, 2661 |
| activemq::commands::JournalQueueAck, 2158 | MessageFormatException |
| | cms::MessageFormatException, 2662 |
| MessageAckMarshaller | MessageId |
| activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller, 2582 | activemq::commands::MessageId, 2664 |
| | messageId |
| activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller, 2570 | activemq::commands::JournalTopicAck, 2187 |
| activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller, 2574 | activemq::commands::Message, 2532 |
| activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller, 2578 | activemq::commands::MessageDispatchNotification, 2631 |
| activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller, 2586 | activemq::commands::MessagePull, 2743 |
| activemq::wireformat::openwire::marshal::v6::MessageAckMarshaller, 2566 | activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller, 2669 |
| messageCount | activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller, 2669 |
| activemq::commands::MessageAck, 2564 | activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller, 2681 |
| MessageDispatch | |
| activemq::commands::MessageDispatch, 2595 | activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller, 2673 |
| MessageDispatchChannel | activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller, 2677 |
| activemq::core::MessageDispatchChannel, 2600 | activemq::wireformat::openwire::marshal::v6::MessageIdMarshaller, 2685 |
| MessageDispatchMarshaller | MessageDispatchMarshaller, 2623 |
| activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller, 2607 | activemq::wireformat::openwire::marshal::v1::MessageMarshaller, 2704 |
| activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller, 2611 | activemq::wireformat::openwire::marshal::v2::MessageMarshaller, 2699 |
| activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller, 2619 | activemq::wireformat::openwire::marshal::v3::MessageMarshaller, 2709 |
| activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller, 2615 | activemq::wireformat::openwire::marshal::v4::MessageMarshaller, 2709 |
| activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller, 2627 | activemq::wireformat::openwire::marshal::v5::MessageMarshaller, 2699 |
| activemq::wireformat::openwire::marshal::v6::MessageDispatchMarshaller, 2627 | activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 2719 |
| MessageDispatchNotification | |
| activemq::commands::MessageDispatchNotification, 2631 | MessageNotReadableException |
| | cms::MessageNotReadableException, 2723 |
| MessageDispatchNotificationMarshaller | MessageNotWriteableException |
| activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller, 2652 | MessageDispatchNotificationMarshaller, 2724 |
| activemq::wireformat::openwire::marshal::v2::MessageDispatchNotificationMarshaller, 2640 | MessagePropertyInterceptor |
| activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller, 2644 | activemq::wireformat::openwire::marshal::v1::MessagePropertyInterceptor, 2733 |
| activemq::wireformat::openwire::marshal::v4::MessageDispatchNotificationMarshaller, 2648 | activemq::commands::MessagePull, 2740 |
| activemq::wireformat::openwire::marshal::v5::MessageDispatchNotificationMarshaller, 2656 | activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller, 2750 |
| activemq::wireformat::openwire::marshal::v6::MessageDispatchNotificationMarshaller, 2636 | activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller, 2750 |
| MessageEOFException | activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller, 2753 |

- activemq::wireformat::openwire::marshal::v4::MessagePublicMarshaller
 - 2757
 - decaf::util::Marshaller, 1255
- activemq::wireformat::openwire::marshal::v5::MessagePublicMarshaller
 - 2749
 - decaf::util::Marshaller, 1255
 - MutexHandle, 2787
- activemq::wireformat::openwire::marshal::v6::MessagePublicMarshaller
 - 2765
 - decaf::util::Marshaller, 1255
 - MutexHandle, 2787
- messageSequenceId
 - activemq::commands::JournalTopicAck, 2187
- method
 - internal_state, 2120
- MethodName
 - activemq::commands::BrokerError::StackTraceElement, 3578
- MICROSECONDS
 - decaf::util::concurrent::TimeUnit, 3815
- MILLISECONDS
 - decaf::util::concurrent::TimeUnit, 3815
- min
 - decaf::lang::Math, 2503, 2504
- MIN_LOOKAHEAD
 - deflate.h, 4727
- MIN_MATCH
 - zutil.h, 4745
- MIN_PRIORITY
 - decaf::lang::Thread, 3773
- MIN_RADIX
 - decaf::lang::Character, 1106
- MIN_VALUE
 - decaf::lang::Byte, 968
 - decaf::lang::Character, 1107
 - decaf::lang::Double, 1798
 - decaf::lang::Float, 1914
 - decaf::lang::Integer, 2090
 - decaf::lang::Long, 2433
 - decaf::lang::Short, 3448
- MINUTES
 - decaf::util::concurrent::TimeUnit, 3815
- MockTransport
 - activemq::transport::mock::MockTransport, 2770
- mode
 - gz_state, 1977
 - inflate_state, 2025
- modifiedUtf8ToAscii
 - activemq::util::MarshallingSupport, 2494
- msg
 - gz_state, 1977
 - z_stream_s, 4062
- Mutex
 - decaf::util::concurrent::Mutex, 2783
- mutex
 - decaf::util::AbstractCollection, 191
- NAME
 - inflate.h, 4732
- name
 - gz_header_s, 1975
- name_max
 - gz_header_s, 1975
- NAME_STATE
 - deflate.h, 4727
- nameUUIDFromBytes
 - decaf::util::UUID, 3972
- NaN
 - decaf::lang::Double, 1798
 - decaf::lang::Float, 1914
- NANOSECONDS
 - decaf::util::concurrent::TimeUnit, 3815
- nanoTime
 - decaf::lang::System, 3732
- narrow
 - activemq::transport::failover::FailoverTransport, 1879
 - activemq::transport::IOTransport, 2148
 - activemq::transport::mock::MockTransport, 2773
 - activemq::transport::Transport, 3885
 - activemq::transport::TransportFilter, 3895
- ncode
 - inflate_state, 2025
- ndist
 - inflate_state, 2025
- needsDictionary
 - decaf::util::zip::Inflater, 2031
- needsInput
 - decaf::util::zip::Deflater, 1711
 - decaf::util::zip::Inflater, 2032
- NEGATIVE_INFINITY
 - decaf::lang::Double, 1798
 - decaf::lang::Float, 1914
- Network
 - decaf::internal::net::Network, 2791
- NetworkBridgeFilter
 - activemq::commands::NetworkBridgeFilter, 2794
- NetworkBridgeFilterMarshaller
 - activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilter, 2817
 - activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilter, 2797

- activemq::wireformat::openwire::marshal::v3::NetworkBridgeFilterMarshal, 2845
- 2809
- nextInt
- activemq::wireformat::openwire::marshal::v4::NetworkBridgeFilterMarshal, 2813
- nextLong
- activemq::wireformat::openwire::marshal::v5::NetworkBridgeFilterMarshal, 2805
- nextMessage
- activemq::wireformat::openwire::marshal::v6::NetworkBridgeFilterMarshal, 2801
- 489
- networkBrokerId
- activemq::commands::NetworkBridgeFilter, 2795
- networkConnection
- activemq::commands::BrokerInfo, 903
- networkConsumerPath
- activemq::commands::ConsumerInfo, 1466
- networkProperties
- activemq::commands::BrokerInfo, 903
- networkSubscription
- activemq::commands::ConsumerInfo, 1466
- networkTTL
- activemq::commands::NetworkBridgeFilter, 2795
- NEW
- decaf::lang::Thread, 3768
- newCondition
- decaf::util::concurrent::locks::Lock, 2379
- decaf::util::concurrent::locks::ReentrantLock, 3185
- newThread
- decaf::util::concurrent::ThreadFactory, 3774
- next
- activemq::transport::TransportFilter, 3898
- decaf::security::SecureRandom, 3333
- decaf::util::Iterator, 2154
- decaf::util::Random, 3156
- gz_state, 1977
- inflate_state, 2025
- next_in
- z_stream_s, 4062
- next_out
- z_stream_s, 4062
- nextBoolean
- decaf::util::Random, 3157
- nextBytes
- decaf::security::SecureRandom, 3333, 3334
- decaf::util::Random, 3157
- nextDouble
- decaf::util::Random, 3157
- nextFloat
- decaf::util::Random, 3158
- nextGaussian
- decaf::util::Random, 3158
- nextIndex
- cms::MessageEnumeration, 2659
- nextToken
- decaf::util::StringTokenizer, 3669
- nice_match
- internal_state, 2120
- nlen
- inflate_state, 2025
- NO_COMPRESSION
- decaf::util::zip::Deflater, 1715
- NO_MAXIMUM_REDELIVERIES
- activemq::core::RedeliveryPolicy, 3181
- node
- decaf::util::UUID, 3972
- noLocal
- activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3176
- activemq::commands::ConsumerInfo, 1466
- NON_PERSISTENT
- cms::DeliveryMode, 1721
- noRangeAcks
- activemq::commands::ConsumerInfo, 1466
- NORM_PRIORITY
- decaf::lang::Thread, 3773
- normalize
- decaf::net::URI, 3928
- NoRouteToHostException
- decaf::net::NoRouteToHostException, 2820, 2821
- NoSuchAlgorithmException
- decaf::security::NoSuchAlgorithmException, 2823, 2824
- NoSuchElementException
- decaf::lang::exceptions::NoSuchElementException, 2826, 2827
- NoSuchProviderException
- decaf::security::NoSuchProviderException, 2829, 2830
- notify
- activemq::core::MessageDispatchChannel, 2602
- decaf::internal::util::concurrent::ConditionImpl, 1257
- decaf::internal::util::concurrent::SynchronizableImpl, 3712
- decaf::io::InputStream, 2047
- decaf::io::OutputStream, 2910

- decaf::util::AbstractCollection, 186
- decaf::util::concurrent::ConcurrentStlMap, 1241
- decaf::util::concurrent::Mutex, 2783
- decaf::util::concurrent::Synchronizable, 3702
- decaf::util::StlMap, 3609
- decaf::util::StlQueue, 3619
- notifyAll
 - activemq::core::MessageDispatchChannel, 2602
 - decaf::internal::util::concurrent::ConditionImpl, 1258
 - decaf::internal::util::concurrent::SynchronizableImpl, 3712
 - decaf::io::InputStream, 2047
 - decaf::io::OutputStream, 2910
 - decaf::util::AbstractCollection, 186
 - decaf::util::concurrent::ConcurrentStlMap, 1241
 - decaf::util::concurrent::Mutex, 2783
 - decaf::util::concurrent::Synchronizable, 3703
 - decaf::util::StlMap, 3610
 - decaf::util::StlQueue, 3619
- Null
 - decaf::util::logging, 176
- NULL_TYPE
 - activemq::util::PrimitiveValueNode, 3015
 - activemq::wireformat::openwire::OpenWireFormat, 2898
- NullPointerException
 - decaf::lang::exceptions::NullPointerException, 2832, 2833
- NUM_OPTIONS
 - activemq::core::ActiveMQConstants, 308
- NUM_PARAMS
 - activemq::core::ActiveMQConstants, 309
- NumberFormatException
 - decaf::lang::exceptions::NumberFormatException, 2838, 2839
- numberOfLeadingZeros
 - decaf::lang::Integer, 2083
 - decaf::lang::Long, 2426
- numberOfTrailingZeros
 - decaf::lang::Integer, 2083
 - decaf::lang::Long, 2426
- numWaiting
 - decaf::util::concurrent::ConditionHandle, 1255
- numWake
 - decaf::util::concurrent::ConditionHandle, 1255
- objectId
 - activemq::commands::RemoveInfo, 3197
- OF
 - deflate.h, 4727
 - gzguts.h, 4729
 - inffast.h, 4730
 - infrees.h, 4734
 - zconf.h, 4738
 - zlib.h, 4742
 - zutil.h, 4745
- OFF
 - decaf::util::logging::Level, 2336
- Off
 - decaf::util::logging, 176
- offer
 - decaf::util::concurrent::BlockingQueue, 847
 - decaf::util::concurrent::SynchronousQueue, 3721
 - decaf::util::PriorityQueue, 3032
 - decaf::util::Queue, 3150
- offset
 - decaf::internal::nio::CharArrayBuffer, 1118
 - inflate_state, 2025
- onCommand
 - activemq::core::ActiveMQConnection, 285
 - activemq::transport::correlator::ResponseCorrelator, 3292
 - activemq::transport::DefaultTransportListener, 1704
 - activemq::transport::failover::FailoverTransportListener, 1889
 - activemq::transport::inactivity::InactivityMonitor, 2005
 - activemq::transport::logging::LoggingTransport, 2404
 - activemq::transport::mock::InternalCommandListener, 2122
 - activemq::transport::TransportFilter, 3895
 - activemq::transport::TransportListener, 3900
 - activemq::wireformat::openwire::OpenWireFormatNegotiator, 2902
- oneway
 - activemq::core::ActiveMQConnection, 285
 - activemq::core::ActiveMQSession, 529
 - activemq::transport::correlator::ResponseCorrelator, 3292
 - activemq::transport::failover::FailoverTransport, 1880
 - activemq::transport::inactivity::InactivityMonitor, 2006
 - activemq::transport::IOTransport, 2148
 - activemq::transport::logging::LoggingTransport, 2404

- activemq::transport::mock::MockTransport, 2773
- activemq::transport::Transport, 3886
- activemq::transport::TransportFilter, 3895
- activemq::wireformat::openwire::OpenWireFormatNegotiator, 2902
- onException
 - activemq::core::ActiveMQConnection, 285
 - activemq::transport::DefaultTransportListener, 1704
 - activemq::transport::failover::BackupTransport, 753
 - activemq::transport::failover::FailoverTransportListener, 1889
 - activemq::transport::inactivity::InactivityMonitor, 2006
 - activemq::transport::TransportFilter, 3896
 - activemq::transport::TransportListener, 3901
 - cms::ExceptionListener, 1838
- onMessage
 - cms::MessageListener, 2692
- onProducerAck
 - activemq::core::ActiveMQProducer, 474
- onPropertiesReset
 - decaf::util::logging::PropertiesChangeListener, 3135
- onPropertyChanged
 - decaf::util::logging::PropertiesChangeListener, 3135
- onResponse
 - activemq::state::Tracked, 3818
- onSend
 - activemq::commands::ActiveMQBytesMessage, 238
 - activemq::commands::ActiveMQMessageTemplate, 435
 - activemq::commands::ActiveMQStreamMessage, 541
 - activemq::commands::Message, 2527
- onTaskComplete
 - decaf::util::concurrent::TaskListener, 3735
- onTaskCompleted
 - decaf::util::concurrent::PooledThreadListener, 2971
 - decaf::util::concurrent::ThreadPool, 3780
- onTaskException
 - decaf::util::concurrent::PooledThreadListener, 2972
 - decaf::util::concurrent::TaskListener, 3735
 - decaf::util::concurrent::ThreadPool, 3780
- onTaskStarted
 - decaf::util::concurrent::PooledThreadListener, 2972
- decaf::util::concurrent::ThreadPool, 3781
- onTransportException
 - activemq::transport::correlator::ResponseCorrelator, 3293
 - activemq::wireformat::openwire::OpenWireFormatNegotiator, 2903
- op
 - code, 1183
- opaque
 - z_stream_s, 4062
- OPEN_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- OpenSSLContextSpi
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2843
- OpenSSLServerSocket
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2849
- OpenSSLServerSocketFactory
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocketFactory, 2855
- OpenSSLSocket
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2844
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2862
- OpenSSLSocketException
 - decaf::internal::net::ssl::openssl::OpenSSLSocketException, 2872, 2873
- OpenSSLSocketFactory
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2844
 - decaf::internal::net::ssl::openssl::OpenSSLSocketFactory, 2877
- OpenSSLSocketInputStream
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2883
- OpenSSLSocketOutputStream
 - decaf::internal::net::ssl::openssl::OpenSSLSocketOutputStream, 2886
- OpenWireFormat
 - activemq::wireformat::openwire::OpenWireFormat, 2890
- OpenWireFormatFactory
 - activemq::wireformat::openwire::OpenWireFormatFactory, 2899
- OpenWireFormatNegotiator
 - activemq::wireformat::openwire::OpenWireFormatNegotiator, 2901
- OpenWireResponseBuilder
 - activemq::wireformat::openwire::OpenWireResponseBuilder, 2905
- operationType

- activemq::commands::DestinationInfo, 1731
- operator<
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1329
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::LocalTransactionId, 2349
 - activemq::commands::MessageId, 2666
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionId, 3382
 - activemq::commands::TransactionId, 3821
 - activemq::commands::XATransactionId, 4034
 - decaf::lang::Boolean, 852
 - decaf::lang::Byte, 964
 - decaf::lang::Character, 1105
 - decaf::lang::Comparable, 1215
 - decaf::lang::Double, 1794, 1795
 - decaf::lang::Float, 1910, 1911
 - decaf::lang::Integer, 2084
 - decaf::lang::Long, 2427
 - decaf::lang::Short, 3444
 - decaf::net::URI, 3928
 - decaf::nio::ByteBuffer, 1046
 - decaf::nio::CharBuffer, 1128
 - decaf::nio::DoubleBuffer, 1815
 - decaf::nio::FloatBuffer, 1931
 - decaf::nio::IntBuffer, 2072
 - decaf::nio::LongBuffer, 2450
 - decaf::nio::ShortBuffer, 3465
 - decaf::util::concurrent::TimeUnit, 3810
 - decaf::util::Date, 1667
 - decaf::util::logging::Level, 2334
 - decaf::util::UUID, 3973
- operator*
 - decaf::lang::Pointer, 2950
- operator()
 - decaf::lang::ArrayPointerComparator, 737
 - decaf::lang::PointerComparator, 2954
 - decaf::util::Comparator, 1218
 - decaf::util::comparators::Less, 2329
 - std::less< decaf::lang::ArrayPointer< T > >, 2330
 - std::less< decaf::lang::Pointer< T > >, 2331
- operator->
 - decaf::lang::Pointer, 2951
- operator=
 - activemq::cmsutil::CachedConsumer, 1072
 - activemq::cmsutil::CachedProducer, 1078
 - activemq::cmsutil::CmsAccessor, 1156
 - activemq::cmsutil::CmsDestinationAccessor, 1159
 - activemq::cmsutil::CmsTemplate, 1176
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3066
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
 - activemq::cmsutil::CmsTemplate::ResolveProducerExecutor, 3278
 - activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor, 3279
 - activemq::cmsutil::CmsTemplate::SendExecutor, 3350
 - activemq::cmsutil::DynamicDestinationResolver, 1822
 - activemq::cmsutil::PooledSession, 2965
 - activemq::cmsutil::ResourceLifecycleManager, 3284
 - activemq::cmsutil::SessionPool, 3436
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1329
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::LocalTransactionId, 2349
 - activemq::commands::MessageId, 2666
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionId, 3382
 - activemq::commands::TransactionId, 3821
 - activemq::commands::XATransactionId, 4034
 - activemq::library::ActiveMQCPP, 321
 - activemq::util::PrimitiveValueNode, 3022
 - decaf::lang::ArrayPointer, 734
 - decaf::lang::Exception, 1836
 - decaf::lang::Pointer, 2951
 - decaf::util::AbstractCollection, 187
 - decaf::util::Date, 1667
 - decaf::util::logging::LogManager, 2410
 - decaf::util::PriorityQueue, 3032, 3033
 - decaf::util::Properties, 3131
- operator==
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1329
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::LocalTransactionId, 2349
 - activemq::commands::MessageId, 2666
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionId, 3382
 - activemq::commands::TransactionId, 3821
 - activemq::commands::XATransactionId, 4034
 - activemq::util::PrimitiveValueNode, 3022
 - decaf::lang, 158
 - decaf::lang::ArrayPointer, 734, 736
 - decaf::lang::Boolean, 853

- decaf::lang::Byte, 965
- decaf::lang::Character, 1105
- decaf::lang::Comparable, 1215
- decaf::lang::Double, 1795
- decaf::lang::Float, 1911
- decaf::lang::Integer, 2084
- decaf::lang::Long, 2427
- decaf::lang::Pointer, 2951, 2953
- decaf::lang::Short, 3445
- decaf::net::URI, 3929
- decaf::nio::ByteBuffer, 1046
- decaf::nio::CharBuffer, 1128
- decaf::nio::DoubleBuffer, 1816
- decaf::nio::FloatBuffer, 1931
- decaf::nio::IntBuffer, 2072
- decaf::nio::LongBuffer, 2450
- decaf::nio::ShortBuffer, 3465
- decaf::util::concurrent::TimeUnit, 3810
- decaf::util::Date, 1668
- decaf::util::logging::Level, 2334
- decaf::util::UUID, 3973
- operator[]
 - activemq::wireformat::openwire::utils::HexTable, 1984
 - decaf::internal::util::ByteArrayAdapter, 983
 - decaf::lang::ArrayPointer, 735
- opt_len
 - internal_state, 2120
- optimizedAcknowledge
 - activemq::commands::ConsumerInfo, 1466
- options
 - activemq::commands::ActiveMQDestination, 332
- ordered
 - activemq::commands::ActiveMQDestination, 332
- orderedTarget
 - activemq::commands::ActiveMQDestination, 332
- originalDestination
 - activemq::commands::Message, 2532
- originalTransactionId
 - activemq::commands::Message, 2532
- OS
 - inflate.h, 4732
- os
 - gz_header_s, 1975
- OS_CODE
 - zutil.h, 4745
- out
 - decaf::io::FileDescriptor, 1892
 - gz_state, 1977
- OutputStream
 - decaf::io::OutputStream, 2909
- outputStream
 - decaf::io::FilterOutputStream, 1903
- OutputStreamWriter
 - decaf::io::OutputStreamWriter, 2915
- own
 - decaf::io::FilterInputStream, 1899
 - decaf::io::FilterOutputStream, 1903
- ownDeflater
 - decaf::util::zip::DeflaterOutputStream, 1719
- ownInflater
 - decaf::util::zip::InflaterInputStream, 2041
- PARAM_CLIENTID
 - activemq::core::ActiveMQConstants, 309
- PARAM_PASSWORD
 - activemq::core::ActiveMQConstants, 309
- PARAM_USERNAME
 - activemq::core::ActiveMQConstants, 309
- parent
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3066
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3176
- park
 - decaf::util::concurrent::locks::LockSupport, 2384
- parkNanos
 - decaf::util::concurrent::locks::LockSupport, 2384
- parkUntil
 - decaf::util::concurrent::locks::LockSupport, 2385
- parse
 - decaf::internal::util::HexStringParser, 1982
 - decaf::util::logging::Level, 2334
- parseAuthority
 - decaf::internal::net::URIHelper, 3938
- parseBoolean
 - decaf::lang::Boolean, 853
- parseByte
 - decaf::lang::Byte, 965
- parseComposite
 - activemq::util::URISupport, 3945
- parseDouble
 - decaf::internal::util::HexStringParser, 1982
 - decaf::lang::Double, 1795
- parseFloat
 - decaf::internal::util::HexStringParser, 1983
 - decaf::lang::Float, 1911
- parseInt
 - decaf::lang::Integer, 2085
- parseLong

- decaf::lang::Long, 2428
- parseQuery
 - activemq::util::URISupport, 3946
- parseServerAuthority
 - decaf::net::URI, 3929
- parseShort
 - decaf::lang::Short, 3445
- parseURI
 - decaf::internal::net::URIHelper, 3939
- parseURL
 - activemq::util::URISupport, 3946
- PartialCommand
 - activemq::commands::PartialCommand, 2919
- PartialCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2943
 - activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2927
 - activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2935
 - activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2939
 - activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2931
 - activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2923
- password
 - activemq::commands::ConnectionInfo, 1360
- path
 - gz_state, 1977
- peek
 - activemq::core::MessageDispatchChannel, 2603
 - decaf::internal::util::TimerTaskHeap, 3805
 - decaf::util::concurrent::SynchronousQueue, 3722
 - decaf::util::PriorityQueue, 3033
 - decaf::util::Queue, 3150
- peerBrokerInfos
 - activemq::commands::BrokerInfo, 903
- pending
 - internal_state, 2120
- pending_buf
 - internal_state, 2120
- pending_buf_size
 - internal_state, 2120
- pending_out
 - internal_state, 2120
- PERSISTENT
 - cms::DeliveryMode, 1721
- persistent
 - activemq::commands::Message, 2532
- physicalName
 - activemq::commands::ActiveMQDestination, 332
- PI
 - decaf::lang::Math, 2511
- Pointer
 - decaf::lang::Pointer, 2948, 2949
- PointerType
 - decaf::lang::ArrayPointer, 732
 - decaf::lang::Pointer, 2948
- poll
 - decaf::util::concurrent::BlockingQueue, 847
 - decaf::util::concurrent::SynchronousQueue, 3722
 - decaf::util::PriorityQueue, 3033
- PartialCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2943
 - activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2927
 - activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2935
 - activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2939
 - activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2931
 - activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2923
- PooledSession
 - activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2943
 - activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2927
 - activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2935
 - activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2939
 - activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2931
 - activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2923
- PooledThread
 - activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller, 2943
 - activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller, 2927
 - activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller, 2935
 - activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller, 2939
 - activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller, 2931
 - activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 2923
- pop
 - decaf::util::concurrent::BlockingQueue, 847
 - decaf::util::concurrent::SynchronousQueue, 3722
 - decaf::util::PriorityQueue, 3033
- port
 - decaf::lang::Math, 2511
- PortUnreachableException
 - activemq::commands::ActiveMQDestination, 332
- Pos
 - deflate.h, 4727
- pos
 - gz_state, 1977
- Posf
 - deflate.h, 4727
- position
 - decaf::nio::Buffer, 932
- POSITIVE_INFINITY
 - decaf::lang::Double, 1798
 - decaf::lang::Float, 1914
- pow
 - decaf::lang::Math, 2505
- prefetch
 - activemq::commands::ConsumerControl, 1405
- PrefetchPolicy
 - activemq::core::PrefetchPolicy, 2977
- prefetchSize
 - activemq::commands::ConsumerInfo, 1466
- PRESET_DICT
 - zutil.h, 4745
- prev
 - internal_state, 2120
- prev_length
 - internal_state, 2120
- prev_match
 - internal_state, 2120

- internal_state, 2120
- previous
 - decaf::util::ListIterator, 2345
- previousIndex
 - decaf::util::ListIterator, 2346
- PrimitiveList
 - activemq::util::PrimitiveList, 2982
- PrimitiveMap
 - activemq::util::PrimitiveMap, 2993
- PrimitiveType
 - activemq::util::PrimitiveValueNode, 3015
- PrimitiveTypesMarshaller
 - activemq::wireformat::openwire::marshal::PrimitiveTypesMarshaller, 3003
- PrimitiveValueConverter
 - activemq::util::PrimitiveValueConverter, 3010
- PrimitiveValueNode
 - activemq::util::PrimitiveValueNode, 3016–3018
- printStackTrace
 - cms::CMSException, 1162
 - decaf::lang::Exception, 1836
 - decaf::lang::Throwable, 3786
- priority
 - activemq::commands::ConsumerInfo, 1466
 - activemq::commands::Message, 2532
- PriorityQueue
 - decaf::util::PriorityQueue, 3030, 3031
- PriorityQueueIterator
 - decaf::util::PriorityQueue, 3035
- processBeginTransaction
 - activemq::state::CommandVisitor, 1202
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1394
- processBrokerError
 - activemq::state::CommandVisitor, 1202
 - activemq::state::CommandVisitorAdapter, 1211
- processBrokerInfo
 - activemq::state::CommandVisitor, 1202
 - activemq::state::CommandVisitorAdapter, 1211
- processCommitTransactionOnePhase
 - activemq::state::CommandVisitor, 1202
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1394
- processCommitTransactionTwoPhase
 - activemq::state::CommandVisitor, 1202
- activemq::state::CommandVisitorAdapter, 1211
- activemq::state::ConnectionStateTracker, 1394
- processConnectionControl
 - activemq::state::CommandVisitor, 1202
 - activemq::state::CommandVisitorAdapter, 1211
- processConnectionError
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
- processConnectionInfo
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processConsumerControl
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
- processConsumerInfo
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processControlCommand
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
- processDestinationInfo
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processEndTransaction
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processFlushCommand
 - activemq::state::CommandVisitor, 1203
 - activemq::state::CommandVisitorAdapter, 1211
- processForgetTransaction
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
- processKeepAliveInfo
 - activemq::state::CommandVisitor, 1204

- activemq::state::CommandVisitorAdapter, 1211
- processMessage
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processMessageAck
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processMessageDispatch
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
- processMessageDispatchNotification
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
- processMessagePull
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
- processPrepareTransaction
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1395
- processProducerAck
 - activemq::state::CommandVisitor, 1204
 - activemq::state::CommandVisitorAdapter, 1211
- processProducerInfo
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1396
- processRecoverTransactions
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1211
- processRemoveConnection
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1396
- processRemoveConsumer
 - activemq::state::CommandVisitor, 1205
- activemq::state::CommandVisitorAdapter, 1211
- activemq::state::ConnectionStateTracker, 1396
- processRemoveDestination
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1211
 - activemq::state::ConnectionStateTracker, 1396
- processRemoveInfo
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1211
- processRemoveProducer
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1212
 - activemq::state::ConnectionStateTracker, 1396
- processRemoveSession
 - activemq::state::CommandVisitor, 1205
 - activemq::state::CommandVisitorAdapter, 1212
 - activemq::state::ConnectionStateTracker, 1396
- processRemoveSubscriptionInfo
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
- processReplayCommand
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
- processResponse
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
- processRollbackTransaction
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
 - activemq::state::ConnectionStateTracker, 1396
- processSessionInfo
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
 - activemq::state::ConnectionStateTracker, 1397
- processShutdownInfo
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212

- processTransactionInfo
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1212
- processWireFormat
 - activemq::state::CommandVisitor, 1206
 - activemq::state::CommandVisitorAdapter, 1213
- PRODUCER_ADVISORY_PREFIX
 - activemq::commands::ActiveMQDestination, 332
- ProducerAck
 - activemq::commands::ProducerAck, 3037
- ProducerAckMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerAckMarshaller, 3061
 - activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller, 3041
 - activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller, 3049
 - activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller, 3045
 - activemq::wireformat::openwire::marshal::v5::ProducerAckMarshaller, 3053
 - activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller, 3057
- ProducerExecutor
 - activemq::cmsutil::CmsTemplate, 1182
 - activemq::cmsutil::CmsTemplate::ProducerExecutor, 3065
- ProducerId
 - activemq::commands::ProducerId, 3068
- producerId
 - activemq::commands::Message, 2532
 - activemq::commands::MessageId, 2667
 - activemq::commands::ProducerAck, 3039
 - activemq::commands::ProducerInfo, 3100
- ProducerIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerIdMarshaller, 3093
 - activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller, 3073
 - activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller, 3081
 - activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller, 3077
 - activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller, 3085
 - activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3089
- ProducerInfo
 - activemq::commands::ProducerInfo, 3097
- ProducerInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ProducerInfoMarshaller, 3110
 - activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller, 3106
 - activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller, 3118
 - activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller, 3102
 - activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller, 3114
 - activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller, 3122
- producerSequenceId
 - activemq::commands::MessageId, 2667
- ProducerState
 - activemq::state::ProducerState, 3125
- Properties
 - decaf::util::Properties, 3128
- propertyExists
 - activemq::commands::ActiveMQMessageTemplate, 436
 - cms::Message, 2549
- propertyNames
 - decaf::util::Properties, 3132
- ProtocolException
 - decaf::net::ProtocolException, 3137, 3138
- providerGenerateSeed
 - decaf::internal::security::SecureRandomImpl, 3337
 - decaf::security::SecureRandomSpi, 3339
- providerGetDefaultSSLParameters
 - decaf::net::ssl::SSLContextSpi, 3548
- providerGetServerSocketFactory
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2843
 - decaf::net::ssl::SSLContextSpi, 3549
- providerGetSupportedSSLParameters
 - decaf::net::ssl::SSLContextSpi, 3549
- providerInit
 - decaf::internal::net::ssl::openssl::OpenSSLContextSpi, 2844
- providerNextBytes
 - decaf::internal::security::SecureRandomImpl, 3337, 3338
 - decaf::security::SecureRandomSpi, 3340
- providerSetSeed
 - decaf::internal::security::SecureRandomImpl, 3338
 - decaf::security::SecureRandomSpi, 3340

- publish
 - decaf::util::logging::ConsoleHandler, 1400
 - decaf::util::logging::Handler, 1980
 - decaf::util::logging::StreamHandler, 3651
- purge
 - decaf::util::Timer, 3792
- push
 - decaf::util::StlQueue, 3619
- PushbackInputStream
 - decaf::io::PushbackInputStream, 3143
- put
 - decaf::internal::nio::ByteBuffer, 1013
 - decaf::internal::nio::CharArrayBuffer, 1116
 - decaf::internal::nio::DoubleArrayBuffer, 1806, 1807
 - decaf::internal::nio::FloatArrayBuffer, 1922, 1923
 - decaf::internal::nio::IntArrayBuffer, 2063, 2064
 - decaf::internal::nio::LongArrayBuffer, 2441, 2442
 - decaf::internal::nio::ShortArrayBuffer, 3456, 3457
 - decaf::internal::util::ByteArrayAdapter, 984
 - decaf::nio::ByteBuffer, 1046–1048
 - decaf::nio::CharBuffer, 1128–1131
 - decaf::nio::DoubleBuffer, 1816, 1817
 - decaf::nio::FloatBuffer, 1931–1933
 - decaf::nio::IntBuffer, 2072–2074
 - decaf::nio::LongBuffer, 2450–2452
 - decaf::nio::ShortBuffer, 3465–3467
 - decaf::util::concurrent::BlockingQueue, 848
 - decaf::util::concurrent::ConcurrentStlMap, 1242
 - decaf::util::concurrent::SynchronousQueue, 3723
 - decaf::util::Map, 2467
 - decaf::util::StlMap, 3610
- put_byte
 - deflate.h, 4727
- putAll
 - decaf::util::concurrent::ConcurrentStlMap, 1242
 - decaf::util::Map, 2467
 - decaf::util::StlMap, 3610, 3611
- putChar
 - decaf::internal::nio::ByteBuffer, 1013, 1014
 - decaf::internal::util::ByteArrayAdapter, 984
 - decaf::nio::ByteBuffer, 1049
- putDouble
 - decaf::internal::nio::ByteBuffer, 1014, 1015
 - decaf::internal::util::ByteArrayAdapter, 984
 - decaf::nio::ByteBuffer, 1049, 1050
- putDoubleAt
 - decaf::internal::util::ByteArrayAdapter, 985
- putFloat
 - decaf::internal::nio::ByteBuffer, 1015, 1016
 - decaf::internal::util::ByteArrayAdapter, 985
 - decaf::nio::ByteBuffer, 1050, 1051
- putFloatAt
 - decaf::internal::util::ByteArrayAdapter, 986
- putIfAbsent
 - decaf::util::concurrent::ConcurrentMap, 1229
 - decaf::util::concurrent::ConcurrentStlMap, 1243
- putInt
 - decaf::internal::nio::ByteBuffer, 1016
 - decaf::internal::util::ByteArrayAdapter, 986
 - decaf::nio::ByteBuffer, 1051
- putIntAt
 - decaf::internal::util::ByteArrayAdapter, 986
- putLong
 - decaf::internal::nio::ByteBuffer, 1017
 - decaf::internal::util::ByteArrayAdapter, 987
 - decaf::nio::ByteBuffer, 1052
- putLongAt
 - decaf::internal::util::ByteArrayAdapter, 987
- putShort
 - decaf::internal::nio::ByteBuffer, 1018
 - decaf::internal::util::ByteArrayAdapter, 988
 - decaf::nio::ByteBuffer, 1053
- putShortAt
 - decaf::internal::util::ByteArrayAdapter, 988
- QUEUE
 - cms::Destination, 1723
- QUEUE_PREFIX
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- QUEUE_QUALIFIED_PREFIX

- activemq::commands::ActiveMQDestination, 332
- queueTask
 - decaf::util::concurrent::ThreadPool, 3781
- quoteIllegal
 - decaf::internal::net::URLEncoderDecoder, 3933
- Random
 - decaf::util::Random, 3156
- random
 - decaf::lang::Math, 2505
- randomUUID
 - decaf::util::UUID, 3973
- raw
 - gz_state, 1977
- reached
 - decaf::net::InetAddress, 2022
- read
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2866
 - decaf::internal::net::tcp::TcpSocket, 3744
 - decaf::internal::util::ByteArrayAdapter, 988
 - decaf::io::InputStream, 2047–2049
 - decaf::io::Reader, 3165–3167
 - decaf::lang::Readable, 3160
 - decaf::nio::CharBuffer, 1131
- readAsciiString
 - activemq::wireformat::openwire::marshal::BaseDataStreamAdapter, 819
- readBoolean
 - activemq::commands::ActiveMQBytesMessage, 238
 - activemq::commands::ActiveMQStreamMessage, 541
 - activemq::wireformat::openwire::utils::BooleanStream, 858
 - cms::BytesMessage, 1060
 - cms::StreamMessage, 3655
 - decaf::io::DataInput, 1559
 - decaf::io::DataInputStream, 1568
- readByte
 - activemq::commands::ActiveMQBytesMessage, 238
 - activemq::commands::ActiveMQStreamMessage, 542
 - cms::BytesMessage, 1060
 - cms::StreamMessage, 3655
 - decaf::io::DataInput, 1560
 - decaf::io::DataInputStream, 1568
- readBytes
 - activemq::commands::ActiveMQBytesMessage, 239
- activemq::commands::ActiveMQStreamMessage, 542, 543
- cms::BytesMessage, 1061
- cms::StreamMessage, 3655, 3656
- readChar
 - activemq::commands::ActiveMQBytesMessage, 240
 - activemq::commands::ActiveMQStreamMessage, 543
 - cms::BytesMessage, 1062
 - cms::StreamMessage, 3657
 - decaf::io::DataInput, 1560
 - decaf::io::DataInputStream, 1568
- ReadChecker
 - activemq::transport::inactivity::InactivityMonitor, 2007
 - activemq::transport::inactivity::ReadChecker, 3162
- readConfiguration
 - decaf::util::logging::LogManager, 2410, 2411
- readDouble
 - activemq::commands::ActiveMQBytesMessage, 240
 - activemq::commands::ActiveMQStreamMessage, 544
 - cms::BytesMessage, 1062
 - cms::StreamMessage, 3657
 - decaf::io::DataInput, 1560
 - decaf::io::DataInputStream, 1568
- Reader
 - decaf::io::Reader, 3164
- readFloat
 - activemq::commands::ActiveMQBytesMessage, 241
 - activemq::commands::ActiveMQStreamMessage, 544
 - cms::BytesMessage, 1062
 - cms::StreamMessage, 3657
 - decaf::io::DataInput, 1560
 - decaf::io::DataInputStream, 1569
- readFully
 - decaf::io::DataInput, 1561
 - decaf::io::DataInputStream, 1569, 1570
- readInt
 - activemq::commands::ActiveMQBytesMessage, 241
 - activemq::commands::ActiveMQStreamMessage, 544
 - cms::BytesMessage, 1063
 - cms::StreamMessage, 3658
 - decaf::io::DataInput, 1562
 - decaf::io::DataInputStream, 1570
- readLine

- decaf::io::DataInput, 1562
- decaf::io::DataInputStream, 1570
- readLock
 - decaf::util::concurrent::locks::ReadWriteLock, 3173
- readLong
 - activemq::commands::ActiveMQBytesMessage, 241
 - activemq::commands::ActiveMQStreamMessage, 545
 - cms::BytesMessage, 1063
 - cms::StreamMessage, 3658
 - decaf::io::DataInput, 1563
 - decaf::io::DataInputStream, 1571
- readOnly
 - decaf::internal::nio::CharArrayBuffer, 1118
- readonly
 - decaf::io::FileDescriptor, 1892
- ReadOnlyBufferException
 - decaf::nio::ReadOnlyBufferException, 3169, 3170
- readShort
 - activemq::commands::ActiveMQBytesMessage, 242
 - activemq::commands::ActiveMQStreamMessage, 545
 - cms::BytesMessage, 1063
 - cms::StreamMessage, 3659
 - decaf::io::DataInput, 1563
 - decaf::io::DataInputStream, 1571
- readString
 - activemq::commands::ActiveMQBytesMessage, 242
 - activemq::commands::ActiveMQStreamMessage, 546
 - cms::BytesMessage, 1064
 - cms::StreamMessage, 3659
 - decaf::io::DataInput, 1563
 - decaf::io::DataInputStream, 1572
- readString16
 - activemq::util::MarshallingSupport, 2494
- readString32
 - activemq::util::MarshallingSupport, 2495
- readUnsignedByte
 - decaf::io::DataInput, 1564
 - decaf::io::DataInputStream, 1572
- readUnsignedShort
 - activemq::commands::ActiveMQBytesMessage, 242
 - activemq::commands::ActiveMQStreamMessage, 546
 - cms::BytesMessage, 1064
 - cms::StreamMessage, 3659
 - decaf::io::DataInput, 1564
- decaf::io::DataInputStream, 1572
- readUTF
 - activemq::commands::ActiveMQBytesMessage, 243
 - cms::BytesMessage, 1065
 - decaf::io::DataInput, 1564
 - decaf::io::DataInputStream, 1572
- ready
 - decaf::io::InputStreamReader, 2054
 - decaf::io::Reader, 3167
- rebalanceConnection
 - activemq::commands::ConnectionControl, 1271
- RECEIPT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- receive
 - activemq::cmsutil::CachedConsumer, 1073
 - activemq::cmsutil::CmsTemplate, 1176, 1177
 - activemq::core::ActiveMQConsumer, 316, 317
 - cms::MessageConsumer, 2590, 2591
 - RECEIVE_TIMEOUT_INDEFINITE_WAIT
 - activemq::cmsutil::CmsTemplate, 1182
 - RECEIVE_TIMEOUT_NO_WAIT
 - activemq::cmsutil::CmsTemplate, 1182
 - ReceiveExecutor
 - activemq::cmsutil::CmsTemplate, 1182
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3175
 - receiveNoWait
 - activemq::cmsutil::CachedConsumer, 1073
 - activemq::core::ActiveMQConsumer, 317
 - cms::MessageConsumer, 2591
- receiveSelected
 - activemq::cmsutil::CmsTemplate, 1177, 1178
- recievedByDFBridge
 - activemq::commands::Message, 2532
- reconnect
 - activemq::transport::failover::FailoverTransport, 1880
 - activemq::transport::IOTransport, 2148
 - activemq::transport::mock::MockTransport, 2774
 - activemq::transport::Transport, 3886
 - activemq::transport::TransportFilter, 3896
- reconnectTo
 - activemq::commands::ConnectionControl, 1271
- recover
 - activemq::cmsutil::PooledSession, 2966
 - activemq::core::ActiveMQSession, 529

- cms::Session, 3375
- redeliveryCounter
 - activemq::commands::Message, 2532
 - activemq::commands::MessageDispatch, 2598
- RedeliveryPolicy
 - activemq::core::RedeliveryPolicy, 3178
- redispatch
 - activemq::core::ActiveMQSession, 529
- ReentrantLock
 - decaf::util::concurrent::locks::ReentrantLock, 3183
- ReferenceType
 - decaf::lang::ArrayPointer, 732
 - decaf::lang::Pointer, 2948
- registerFactory
 - activemq::transport::TransportRegistry, 3903
 - activemq::wireformat::WireFormatRegistry, 4018
- rejectedExecution
 - decaf::util::concurrent::RejectedExecutionHandler, 3192
- RejectedExecutionException
 - decaf::util::concurrent::RejectedExecutionException, 3189, 3190
- relativize
 - decaf::net::URI, 3929
- release
 - decaf::lang::ArrayPointer, 735
 - decaf::lang::Pointer, 2951
 - decaf::util::concurrent::atomic::AtomicRefCounter, 747
 - decaf::util::concurrent::Semaphore, 3346
- releaseAll
 - activemq::cmsutil::ResourceLifecycleManager, 3284
- remaining
 - decaf::nio::Buffer, 932
- remainingCapacity
 - decaf::util::concurrent::BlockingQueue, 848
 - decaf::util::concurrent::SynchronousQueue, 3723
- remove
 - activemq::util::ActiveMQProperties, 481
 - cms::CMSProperties, 1167
 - decaf::internal::util::TimerTaskHeap, 3806
 - decaf::util::AbstractCollection, 187
 - decaf::util::AbstractQueue, 196
 - decaf::util::Collection, 1190
 - decaf::util::concurrent::ConcurrentMap, 1229
 - decaf::util::concurrent::ConcurrentStlMap, 1243, 1244
 - decaf::util::concurrent::SynchronousQueue, 3723
 - decaf::util::Iterator, 2155
 - decaf::util::List, 2342
 - decaf::util::Map, 2468
 - decaf::util::PriorityQueue, 3033, 3034
 - decaf::util::Properties, 3132
 - decaf::util::Queue, 3151
 - decaf::util::StlList, 3599, 3600
 - decaf::util::StlMap, 3611
 - decaf::util::StlSet, 3628
- removeAll
 - activemq::core::MessageDispatchChannel, 2603
 - decaf::util::AbstractCollection, 188
 - decaf::util::AbstractSet, 199
 - decaf::util::Collection, 1191
 - decaf::util::concurrent::SynchronousQueue, 3724
- removeConsumer
 - activemq::core::ActiveMQSession, 530
 - activemq::state::SessionState, 3438
- removeDispatcher
 - activemq::core::ActiveMQConnection, 286
- removeHandler
 - decaf::util::logging::Logger, 2395
- RemoveInfo
 - activemq::commands::RemoveInfo, 3195
- RemoveInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaller, 3211
 - activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller, 3199
 - activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller, 3207
 - activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller, 3219
 - activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller, 3215
 - activemq::wireformat::openwire::marshal::v6::RemoveInfoMarshaller, 3203
- removeProducer
 - activemq::core::ActiveMQConnection, 286
 - activemq::core::ActiveMQSession, 530
 - activemq::state::SessionState, 3438
- removeProperty
 - activemq::wireformat::stomp::StompFrame, 3636
- removePropertyChangeListener
 - decaf::util::logging::LogManager, 2411
- removeSession
 - activemq::core::ActiveMQConnection, 286
 - activemq::state::ConnectionState, 1391
- RemoveSubscriptionInfo

- activemq::commands::RemoveSubscriptionInfo, 3223
- RemoveSubscriptionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::RemoveSubscriptionInfoMarshaller, 3228
 - activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionInfoMarshaller, 3236
 - activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionInfoMarshaller, 3232
 - activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaller, 3248
 - activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller, 3244
 - activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller, 3240
- removeSynchronization
 - activemq::core::ActiveMQTransactionContext, 721
- removeTask
 - activemq::threads::CompositeTaskRunner, 1224
- removeTempDestination
 - activemq::state::ConnectionState, 1391
- RemoveTransactionAction
 - activemq::state::ConnectionStateTracker, 1398
- removeTransactionState
 - activemq::state::ConnectionState, 1391
- removeTransportListener
 - activemq::core::ActiveMQConnection, 286
- removeURI
 - activemq::transport::CompositeTransport, 1226
 - activemq::transport::failover::FailoverTransport, 1880
 - activemq::transport::failover::URIPool, 3943
- renegotiateWireFormat
 - activemq::wireformat::openwire::OpenWireFormat, 2894
- replace
 - decaf::util::concurrent::ConcurrentMap, 1230, 1231
 - decaf::util::concurrent::ConcurrentStlMap, 1244, 1245
- ReplayCommand
 - activemq::commands::ReplayCommand, 3252
- ReplayCommandMarshaller
 - activemq::wireformat::openwire::marshal::v1::ReplayCommandMarshaller, 3259
 - activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller, 3263
- activemq::wireformat::openwire::marshal::v3::ReplayCommand, 3267
- activemq::wireformat::openwire::marshal::v4::ReplayCommand, 3255
- activemq::wireformat::openwire::marshal::v5::ReplayCommand, 3275
- activemq::wireformat::openwire::marshal::v6::ReplayCommand, 3271
- replyTo
 - activemq::commands::ReplayCommand, 2532
- reportError
 - decaf::util::logging::Handler, 1980
- request
 - activemq::transport::correlator::ResponseCorrelator, 3293
- activemq::transport::failover::FailoverTransport, 1881
- activemq::transport::IOTransport, 2149
- activemq::transport::logging::LoggingTransport, 2404
- activemq::transport::mock::MockTransport, 2774
- activemq::transport::Transport, 3886, 3887
- activemq::transport::TransportFilter, 3896, 3897
- activemq::wireformat::openwire::OpenWireFormatNegotiator, 2903
- reserve
 - decaf::util::concurrent::ThreadPool, 3781
- reserved
 - z_stream_s, 4062
- reset
 - activemq::commands::ActiveMQBytesMessage, 243
 - activemq::commands::ActiveMQStreamMessage, 546
 - activemq::state::ConnectionState, 1391
 - cms::BytesMessage, 1065
 - decaf::internal::util::TimerTaskHeap, 3806
 - decaf::io::BufferedInputStream, 938
 - decaf::io::ByteArrayInputStream, 1025
 - decaf::io::ByteArrayOutputStream, 1029
 - decaf::io::FilterInputStream, 1898
 - decaf::io::InputStream, 2049
 - decaf::io::PushbackInputStream, 3144
 - decaf::io::Reader, 3168
 - decaf::lang::ArrayPointer, 735
 - decaf::lang::Pointer, 2952
 - decaf::nio::Buffer, 933
 - decaf::util::logging::LogManager, 2411
 - decaf::util::StlMapShrinker, 3670
 - decaf::util::zip::Adler32, 723
 - decaf::util::zip::CRC32, 1143
 - decaf::util::zip::CRC32, 1525

- decaf::util::zip::Deflater, 1711
- decaf::util::zip::Inflater, 2032
- decaf::util::zip::InflaterInputStream, 2040
- resize
 - decaf::internal::util::ByteArrayAdapter, 989
- resolve
 - decaf::net::URI, 3930
- resolveDestinationName
 - activemq::cmsutil::CmsDestinationAccessor, 1159
 - activemq::cmsutil::DestinationResolver, 1757
 - activemq::cmsutil::DynamicDestinationResolver, 1822
- ResolveProducerExecutor
 - activemq::cmsutil::CmsTemplate, 1182
 - activemq::cmsutil::CmsTemplate::ResolveProducerExecutor, 3278
- ResolveReceiveExecutor
 - activemq::cmsutil::CmsTemplate, 1182
 - activemq::cmsutil::CmsTemplate::ResolveReceiveExecutor, 3279
- ResourceLifecycleManager
 - activemq::cmsutil::ResourceLifecycleManager, 3283
 - decaf::internal::util::ResourceLifecycleManager, 3281
- Response
 - activemq::commands::Response, 3286
- ResponseCorrelator
 - activemq::transport::correlator::ResponseCorrelator, 3292
- ResponseMarshaller
 - activemq::wireformat::openwire::marshal::v1::ResponseMarshaller, 3316
 - activemq::wireformat::openwire::marshal::v2::ResponseMarshaller, 3301
 - activemq::wireformat::openwire::marshal::v3::ResponseMarshaller, 3311
 - activemq::wireformat::openwire::marshal::v4::ResponseMarshaller, 3296
 - activemq::wireformat::openwire::marshal::v5::ResponseMarshaller, 3306
 - activemq::wireformat::openwire::marshal::v6::ResponseMarshaller, 3321
- restore
 - activemq::state::ConnectionStateTracker, 1397
- restoreTransport
 - activemq::transport::failover::FailoverTransport, 1882
- result
 - activemq::commands::IntegerResponse, 2093
 - resume
 - activemq::commands::ConnectionControl, 1271
 - retainAll
 - decaf::util::AbstractCollection, 188
 - decaf::util::Collection, 1191
 - decaf::util::concurrent::SynchronousQueue, 3724
 - retroactive
 - activemq::commands::ConsumerInfo, 1466
 - returnInstance
 - decaf::util::logging::LogWriter, 2419
 - returnSession
 - activemq::cmsutil::SessionPool, 3436
 - reverse
 - decaf::lang::Integer, 2086
 - decaf::lang::Long, 2428
 - decaf::util::StlQueue, 3620
 - reverseBytes
 - decaf::lang::Integer, 2086
 - decaf::lang::Long, 2429
 - decaf::lang::Short, 3446
 - rewind
 - decaf::nio::Buffer, 933
 - rollback
 - activemq::cmsutil::PooledSession, 2966
 - activemq::core::ActiveMQConsumer, 317
 - activemq::core::ActiveMQSession, 530
 - activemq::core::ActiveMQTransactionContext, 721
 - rotateLeft
 - decaf::lang::Integer, 2086
 - decaf::lang::Long, 2429
 - rotateRight
 - decaf::lang::Integer, 2086
 - decaf::lang::Long, 2429
 - round
 - decaf::lang::Math, 2506
 - run
 - activemq::threads::CompositeTaskRunner, 1241
 - activemq::threads::DedicatedTaskRunner, 1241
 - run
 - activemq::transport::inactivity::ReadChecker, 3162
 - activemq::transport::inactivity::WriteChecker, 4020
 - activemq::transport::IOTransport, 2149
 - activemq::transport::mock::InternalCommandListener, 2123
 - decaf::lang::Runnable, 3325

- decaf::lang::Thread, 3771
- decaf::util::concurrent::PooledThread, 2969
- RUNNABLE
 - decaf::lang::Thread, 3768
- RuntimeException
 - decaf::lang::exceptions::RuntimeException, 3328, 3329
- sane
 - inflate_state, 2025
- schedule
 - decaf::util::Timer, 3792–3796
- scheduleAtFixedRate
 - decaf::util::Timer, 3797–3799
- scheduledExecutionTime
 - decaf::util::TimerTask, 3802
- SECONDS
 - decaf::util::concurrent::TimeUnit, 3815
- SecureRandom
 - decaf::security::SecureRandom, 3332, 3333
- SecureRandomImpl
 - decaf::internal::security::SecureRandomImpl, 3337
- SecureRandomSpi
 - decaf::security::SecureRandomSpi, 3339
- seek
 - gz_state, 1977
- SEEK_CUR
 - zconf.h, 4738
- SEEK_END
 - zconf.h, 4738
- SEEK_SET
 - zconf.h, 4738
- selector
 - activemq::cmsutil::CmsTemplate::ReceiveExecutor, 3176
 - activemq::commands::ConsumerInfo, 1466
 - activemq::commands::SubscriptionInfo, 3675
- Semaphore
 - decaf::util::concurrent::Semaphore, 3343
- semaphore
 - decaf::util::concurrent::ConditionHandle, 1255
- SEND
 - activemq::wireformat::stomp::StompCommand::SendInfo, 3631
- send
 - activemq::cmsutil::CachedProducer, 1078, 1079
 - activemq::cmsutil::CmsTemplate, 1178, 1179
 - activemq::core::ActiveMQProducer, 474, 475
 - activemq::core::ActiveMQSession, 530
 - cms::MessageProducer, 2728, 2729
- SendExecutor
 - activemq::cmsutil::CmsTemplate, 1182
 - activemq::cmsutil::CmsTemplate::SendExecutor, 3350
- sendPullRequest
 - activemq::core::ActiveMQConnection, 286
- sendUrgentData
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2866
 - decaf::net::Socket, 3514
 - decaf::net::SocketImpl, 3535
- ServerSocket
 - decaf::net::ServerSocket, 3354, 3355
 - decaf::net::Socket, 3518
- ServerSocketFactory
 - decaf::net::ServerSocketFactory, 3362
- serviceName
 - activemq::commands::DiscoveryEvent, 1761
- SESSION_TRANSACTED
 - cms::Session, 3368
- SessionId
 - activemq::commands::SessionId, 3380
- sessionId
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionInfo, 3410
- SessionIdMarshaller
 - activemq::wireformat::openwire::marshal::v1::SessionIdMarshaller, 3404
 - activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller, 3384
 - activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller, 3400
 - activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller, 3388
 - activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller, 3396
 - activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3392
- SessionInfo
 - activemq::commands::SessionInfo, 3408
- SessionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaller, 3420
 - activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller, 3428
 - activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller, 3424
 - activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller, 3432

- activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller, 3781
- 3416
- activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller, 3412
- 3636
- SessionPool
 - activemq::cmsutil::SessionPool, 3435
- SessionState
 - activemq::state::SessionState, 3438
- set
 - decaf::util::concurrent::atomic::AtomicBoolean, 739
 - decaf::util::concurrent::atomic::AtomicInteger, 745
 - decaf::util::concurrent::atomic::AtomicReference, 750
 - decaf::util::List, 2342
 - decaf::util::ListIterator, 2346
 - decaf::util::StlList, 3600
- setAbsolute
 - decaf::internal::net::URIType, 3956
- setAckHandler
 - activemq::commands::Message, 2527
- setAckMode
 - activemq::commands::SessionInfo, 3409
- setAckType
 - activemq::commands::MessageAck, 2562
- setAdditionalPredicate
 - activemq::commands::ConsumerInfo, 1464
- setAdvisory
 - activemq::commands::ActiveMQDestination, 329
- setAlwaysSyncSend
 - activemq::core::ActiveMQConnection, 287
 - activemq::core::ActiveMQConnectionFactory, 299
- setArrival
 - activemq::commands::Message, 2528
- setAuthority
 - decaf::internal::net::URIType, 3956
- setBackOffMultiplier
 - activemq::core::policies::DefaultRedeliveryPolicy, 1679
 - activemq::core::RedeliveryPolicy, 3180
 - activemq::transport::failover::FailoverTransport, 1882
- setBackup
 - activemq::transport::failover::FailoverTransport, 1882
- setBackupPoolSize
 - activemq::transport::failover::BackupTransport, 757
 - activemq::transport::failover::FailoverTransport, 1882
- setBlockSize
 - activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller, 3781
 - 3416
 - activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller, 3412
 - 3636
 - setBody
 - activemq::commands::ActiveMQBytesMessage, 243
 - setBodyBytes
 - activemq::commands::ActiveMQBytesMessage, 243
 - cms::BytesMessage, 1065
 - setBool
 - activemq::util::PrimitiveList, 2986
 - activemq::util::PrimitiveMap, 2997
 - activemq::util::PrimitiveValueNode, 3022
 - setBoolean
 - activemq::commands::ActiveMQMapMessage, 369
 - cms::MapMessage, 2478
 - setBooleanProperty
 - activemq::commands::ActiveMQMessageTemplate, 436
 - activemq::wireformat::openwire::utils::MessagePropertyInterce, 2736
 - cms::Message, 2549
 - setBranchQualifier
 - activemq::commands::XATransactionId, 4034
 - setBrokerId
 - activemq::commands::BrokerInfo, 901
 - setBrokerInTime
 - activemq::commands::Message, 2528
 - setBrokerMasterConnector
 - activemq::commands::ConnectionInfo, 1359
 - setBrokerName
 - activemq::commands::BrokerInfo, 901
 - activemq::commands::DiscoveryEvent, 1760
 - setBrokerOutTime
 - activemq::commands::Message, 2528
 - setBrokerPath
 - activemq::commands::ConnectionInfo, 1359
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::DestinationInfo, 1730
 - activemq::commands::Message, 2528
 - activemq::commands::ProducerInfo, 3098
 - setBrokerSequenceId
 - activemq::commands::MessageId, 2666
 - setBrokerUploadUrl
 - activemq::commands::BrokerInfo, 901
 - setBrokerURL
 - activemq::commands::BrokerInfo, 901
 - activemq::core::ActiveMQConnection, 287

- activemq::core::ActiveMQConnectionFactory, 299
- setBrowser
 - activemq::commands::ConsumerInfo, 1464
- setByte
 - activemq::commands::ActiveMQMapMessage, 369
 - activemq::util::PrimitiveList, 2987
 - activemq::util::PrimitiveMap, 2998
 - activemq::util::PrimitiveValueNode, 3022
 - cms::MapMessage, 2478
- setByteArray
 - activemq::util::PrimitiveList, 2987
 - activemq::util::PrimitiveMap, 2998
 - activemq::util::PrimitiveValueNode, 3022
 - decaf::io::BlockingByteArrayInputStream, 841
 - decaf::io::ByteArrayInputStream, 1025, 1026
- setByteProperty
 - activemq::commands::ActiveMQMessageTemplate, 436
 - activemq::wireformat::openwire::utils::MessageProperty, 2736
 - cms::Message, 2550
- setBytes
 - activemq::commands::ActiveMQMapMessage, 369
 - cms::MapMessage, 2479
- setCacheEnabled
 - activemq::commands::WireFormatInfo, 3989
 - activemq::wireformat::openwire::OpenWireFormat, 2895
- setCacheSize
 - activemq::commands::WireFormatInfo, 3989
 - activemq::wireformat::openwire::OpenWireFormat, 2895
- setCause
 - activemq::commands::BrokerError, 865
- setChar
 - activemq::commands::ActiveMQMapMessage, 370
 - activemq::util::PrimitiveList, 2987
 - activemq::util::PrimitiveMap, 2998
 - activemq::util::PrimitiveValueNode, 3023
 - cms::MapMessage, 2479
- setCipherSuites
 - decaf::net::ssl::SSLParameters, 3552
- setClientID
 - activemq::core::ActiveMQConnection, 287
 - cms::Connection, 1265
- setClientId
 - activemq::core::ActiveMQConnectionFactory, 299
- activemq::commands::ConnectionInfo, 1359
- activemq::commands::JournalTopicAck, 2186
- activemq::commands::RemoveSubscriptionInfo, 3224
- activemq::commands::SubscriptionInfo, 3674
- activemq::core::ActiveMQConnectionFactory, 299
- setClientMaster
 - activemq::commands::ConnectionInfo, 1359
- setClose
 - activemq::commands::ConnectionControl, 1270
 - activemq::commands::ConsumerControl, 1404
- setClosed
 - activemq::transport::failover::BackupTransport, 753
- setCloseTimeout
 - activemq::transport::failover::BackupTransport, 753
- activemq::core::ActiveMQConnection, 288
- activemq::core::ActiveMQConnectionFactory, 299
- setCluster
 - activemq::commands::Message, 2528
- setCMSCorrelationID
 - activemq::commands::ActiveMQMessageTemplate, 437
 - cms::Message, 2550
- setCMSDeliveryMode
 - activemq::commands::ActiveMQMessageTemplate, 437
 - cms::Message, 2551
- setCMSDestination
 - activemq::commands::ActiveMQMessageTemplate, 437
 - cms::Message, 2551
- setCMSExpiration
 - activemq::commands::ActiveMQMessageTemplate, 437
 - cms::Message, 2552
- setCMSMessageID
 - activemq::commands::ActiveMQMessageTemplate, 438
 - cms::Message, 2552
- setCMSPriority
 - activemq::commands::ActiveMQMessageTemplate, 438
 - cms::Message, 2552
- setCMSRedelivered
 - activemq::commands::ActiveMQMessageTemplate, 438

- cms::Message, 2553
- setCMSReplyTo
 - activemq::commands::ActiveMQMessageTemplate, 3849
 - 439
 - cms::Message, 2553
- setCMSTimestamp
 - activemq::commands::ActiveMQMessageTemplate, 1882
 - 439
 - cms::Message, 2554
- setCMSType
 - activemq::commands::ActiveMQMessageTemplate, 439
 - cms::Message, 2554
- setCollisionAvoidancePercent
 - activemq::core::policies::DefaultRedeliveryPolicy, 1680
 - activemq::core::RedeliveryPolicy, 3180
- setCommand
 - activemq::commands::ControlCommand, 1495
 - activemq::wireformat::stomp::StompFrame, 3636
- setCommandId
 - activemq::commands::BaseCommand, 763
 - activemq::commands::Command, 1197
 - activemq::commands::PartialCommand, 2920
- setComponents
 - activemq::util::CompositeData, 1220
- setCompressed
 - activemq::commands::Message, 2528
- setConnectedBrokers
 - activemq::commands::ConnectionControl, 1270
- setConnection
 - activemq::commands::ActiveMQTempDestination, 578
 - activemq::commands::Message, 2528
- setConnectionFactory
 - activemq::cmsutil::CmsAccessor, 1156
- setConnectionId
 - activemq::commands::BrokerInfo, 901
 - activemq::commands::ConnectionError, 1298
 - activemq::commands::ConnectionInfo, 1359
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::DestinationInfo, 1730
 - activemq::commands::LocalTransactionId, 2350
 - activemq::commands::ProducerId, 3070
 - activemq::commands::RemoveSubscriptionInfo, 3225
- activemq::commands::SessionId, 3382
- activemq::commands::TransactionInfo, 3849
- setConnectionInterruptProcessingComplete
 - activemq::state::ConnectionState, 1391
- activemq::transport::failover::FailoverTransport, 1882
- setConsumerId
 - activemq::commands::ConsumerControl, 1404
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::MessageAck, 2563
 - activemq::commands::MessageDispatch, 2596
 - activemq::commands::MessageDispatchNotification, 2632
 - activemq::commands::MessagePull, 2742
- setContent
 - activemq::commands::Message, 2528
- setCorrelationId
 - activemq::commands::Message, 2529
 - activemq::commands::MessagePull, 2742
 - activemq::commands::Response, 3287
- setData
 - activemq::commands::DataArrayResponse, 1530
 - activemq::commands::DataResponse, 1585
 - activemq::commands::PartialCommand, 2920
- setDataStructure
 - activemq::commands::Message, 2529
- setDefault
 - decaf::net::ssl::SSLContext, 3547
- setDefaultClientId
 - activemq::core::ActiveMQConnection, 288
- setDefaultDestination
 - activemq::cmsutil::CmsTemplate, 1179
- setDefaultDestinationName
 - activemq::cmsutil::CmsTemplate, 1179
- setDeletedByBroker
 - activemq::commands::ActiveMQBlobMessage, 207
- setDeliveryMode
 - activemq::cmsutil::CachedProducer, 1080
 - activemq::cmsutil::CmsTemplate, 1180
 - activemq::core::ActiveMQProducer, 476
 - cms::MessageProducer, 2730
- setDeliveryPersistent
 - activemq::cmsutil::CmsTemplate, 1180
- setDeliverySequenceId
 - activemq::commands::MessageDispatchNotification, 2633
- setDestination

- activemq::commands::ConsumerControl, 1404
- activemq::commands::ConsumerInfo, 1464
- activemq::commands::DestinationInfo, 1730
- activemq::commands::JournalQueueAck, 2158
- activemq::commands::JournalTopicAck, 2186
- activemq::commands::Message, 2529
- activemq::commands::MessageAck, 2563
- activemq::commands::MessageDispatch, 2597
- activemq::commands::MessageDispatchNotification, 2633
- activemq::commands::MessagePull, 2742
- activemq::commands::ProducerInfo, 3099
- activemq::commands::SubscriptionInfo, 3674
- setDestinationResolver
 - activemq::cmsutil::CmsDestinationAccessor, 1159
- setDictionary
 - decaf::util::zip::Deflater, 1711, 1712
 - decaf::util::zip::Inflater, 2032, 2033
- setDisableMessageID
 - activemq::cmsutil::CachedProducer, 1080
 - activemq::core::ActiveMQProducer, 476
 - cms::MessageProducer, 2730
- setDisableMessageTimeStamp
 - activemq::cmsutil::CachedProducer, 1080
 - activemq::core::ActiveMQProducer, 476
 - cms::MessageProducer, 2730
- setDispatchAsync
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::ProducerInfo, 3099
 - activemq::core::ActiveMQConnection, 288
 - activemq::core::ActiveMQConnectionFactory, 300
- setDouble
 - activemq::commands::ActiveMQMapMessage, 370
 - activemq::util::PrimitiveList, 2988
 - activemq::util::PrimitiveMap, 2998
 - activemq::util::PrimitiveValueNode, 3023
 - cms::MapMessage, 2479
- setDoubleProperty
 - activemq::commands::ActiveMQMessageTemplate, 439
 - activemq::wireformat::openwire::utils::MessageProperty, 2736
 - cms::Message, 2555
- setDroppable
 - activemq::commands::Message, 2529
- setDuplexConnection
 - activemq::commands::BrokerInfo, 901
- setDurableTopicPrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1675
 - activemq::core::PrefetchPolicy, 2978
- setEnabled
 - activemq::transport::failover::BackupTransportPool, 757
- setEnabledCipherSuites
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2851
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2867
 - decaf::net::ssl::SSLServerSocket, 3558
 - decaf::net::ssl::SSLSocket, 3568
- setEnabledProtocols
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2851
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2867
 - decaf::net::ssl::SSLServerSocket, 3558
 - decaf::net::ssl::SSLSocket, 3568
- setenv
 - decaf::lang::System, 3732
- setErrorManager
 - decaf::util::logging::Handler, 1980
- setException
 - activemq::commands::ConnectionError, 1298
 - activemq::commands::ExceptionResponse, 1841
- setExceptionClass
 - activemq::commands::BrokerError, 866
- setExceptionListener
 - activemq::core::ActiveMQConnection, 288
 - activemq::core::ActiveMQConnectionFactory, 300
 - cms::Connection, 1265
- setExclusive
 - activemq::commands::ActiveMQDestination, 329
 - activemq::commands::ConsumerInfo, 1464
- setExit
 - activemq::commands::ConnectionControl, 1170
- setInterceptor
 - activemq::commands::Message, 2529
- setExpiration
 - activemq::commands::Message, 2529
- setExplicitQosEnabled
 - activemq::cmsutil::CmsTemplate, 1180

- setFailOnClose
 - activemq::transport::mock::MockTransport, 2775
- setFailOnKeepAliveSends
 - activemq::transport::mock::MockTransport, 2776
- setFailOnReceiveMessage
 - activemq::transport::mock::MockTransport, 2776
- setFailOnSendMessage
 - activemq::transport::mock::MockTransport, 2776
- setFailOnStart
 - activemq::transport::mock::MockTransport, 2776
- setFailOnStop
 - activemq::transport::mock::MockTransport, 2776
- setFaultTolerant
 - activemq::commands::ConnectionControl, 1270
 - activemq::commands::ConnectionInfo, 1359
- setFaultTolerantConfiguration
 - activemq::commands::BrokerInfo, 901
- setFilter
 - decaf::util::logging::Handler, 1980
 - decaf::util::logging::Logger, 2395
- setFirstMessageId
 - activemq::commands::MessageAck, 2563
- setFirstNakNumber
 - activemq::commands::ReplayCommand, 3253
- setFloat
 - activemq::commands::ActiveMQMapMessage, 370
 - activemq::util::PrimitiveList, 2988
 - activemq::util::PrimitiveMap, 2999
 - activemq::util::PrimitiveValueNode, 3023
 - cms::MapMessage, 2480
- setFloatProperty
 - activemq::commands::ActiveMQMessageTemplate, 440
 - activemq::wireformat::openwire::utils::MessagePropertyIntercept, 2736
 - cms::Message, 2555
- setFlush
 - activemq::commands::ConsumerControl, 1404
- setFormatId
 - activemq::commands::XATransactionId, 4034
- setFormatter
 - decaf::util::logging::Handler, 1981
- setFragment
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3956
- setGlobalTransactionId
 - activemq::commands::XATransactionId, 4034
- setGroupID
 - activemq::commands::Message, 2529
- setGroupSequence
 - activemq::commands::Message, 2529
- setHost
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3957
- setInitialDelayTime
 - activemq::transport::inactivity::InactivityMonitor, 2006
- setInitialized
 - activemq::transport::failover::FailoverTransport, 1882
- setInitialReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1882
- setInitialRedeliveryDelay
 - activemq::core::policies::DefaultRedeliveryPolicy, 1680
 - activemq::core::RedeliveryPolicy, 3180
- setInput
 - decaf::util::zip::Deflater, 1712, 1713
 - decaf::util::zip::Inflater, 2033, 2034
- setInputStream
 - activemq::transport::IOTransport, 2150
- setInt
 - activemq::commands::ActiveMQMapMessage, 371
 - activemq::util::PrimitiveList, 2988
 - activemq::util::PrimitiveMap, 2999
 - activemq::util::PrimitiveValueNode, 3023
 - cms::MapMessage, 2480
- setIntProperty
 - activemq::commands::ActiveMQMessageTemplate, 440
 - activemq::wireformat::openwire::utils::MessagePropertyIntercept, 2737
- setKeepAlive
 - decaf::net::Socket, 3514
- setKeepAliveResponseRequired
 - activemq::transport::inactivity::InactivityMonitor, 2007
- setLastDeliveredSequenceId
 - activemq::commands::RemoveInfo, 3196
 - activemq::core::ActiveMQConsumer, 318
 - activemq::core::ActiveMQSession, 531
- setLastMessageId
 - activemq::commands::MessageAck, 2563

- activemq::commands::MessageAck, 2563
- setLastNakNumber
 - activemq::commands::ReplayCommand, 3253
- setLevel
 - decaf::util::logging::Handler, 1981
 - decaf::util::logging::Logger, 2395
 - decaf::util::logging::LogRecord, 2416
 - decaf::util::zip::Deflater, 1713
- setLimit
 - activemq::util::MemoryUsage, 2514
- setList
 - activemq::util::PrimitiveValueNode, 3023
- setLoggerName
 - decaf::util::logging::LogRecord, 2416
- setLong
 - activemq::commands::ActiveMQMapMessage, 371
 - activemq::util::PrimitiveList, 2989
 - activemq::util::PrimitiveMap, 2999
 - activemq::util::PrimitiveValueNode, 3024
 - cms::MapMessage, 2480
- setLongProperty
 - activemq::commands::ActiveMQMessageTemplate, 440
 - activemq::wireformat::openwire::utils::MessagePropertyInterceptor, 2737
 - cms::Message, 2556
- setMagic
 - activemq::commands::WireFormatInfo, 3989
- setManageable
 - activemq::commands::ConnectionInfo, 1359
- setManaged
 - decaf::internal::util::GenericResource, 1974
- setMap
 - activemq::util::PrimitiveValueNode, 3024
- setMark
 - cms::CMSException, 1162
 - decaf::lang::Exception, 1836
 - decaf::lang::Throwable, 3786
- setMarshaledForm
 - activemq::commands::BaseDataStructure, 832
 - activemq::wireformat::MarshalAware, 2486
- setMarshaledProperties
 - activemq::commands::Message, 2529
 - activemq::commands::WireFormatInfo, 3989
- setMasterBroker
 - activemq::commands::BrokerInfo, 901
- setMaxCacheSize
 - activemq::state::ConnectionStateTracker, 1398
 - activemq::transport::failover::FailoverTransport, 1883
- setMaximumPendingMessageLimit
 - activemq::commands::ConsumerInfo, 1464
- setMaximumRedeliveries
 - activemq::core::policies::DefaultRedeliveryPolicy, 1680
 - activemq::core::RedeliveryPolicy, 3180
- setMaxInactivityDuration
 - activemq::commands::WireFormatInfo, 3989
 - activemq::wireformat::openwire::OpenWireFormat, 2895
- setMaxInactivityDurationInitialDelay
 - activemq::commands::WireFormatInfo, 3989
 - activemq::wireformat::openwire::OpenWireFormat, 2895
- setMaxReconnectAttempts
 - activemq::transport::failover::FailoverTransport, 1883
- setMaxReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1883
- setMaxThreads
 - decaf::util::concurrent::ThreadPool, 3781
- setMessage
 - activemq::commands::BrokerError, 866
 - activemq::commands::JournalTrace, 2214
 - activemq::commands::MessageDispatch, 2597
 - decaf::lang::Exception, 1836
 - decaf::util::logging::LogRecord, 2416
- setMessageAck
 - activemq::commands::JournalQueueAck, 2158
- setMessageCount
 - activemq::commands::MessageAck, 2563
- setMessageId
 - activemq::commands::JournalTopicAck, 2186
 - activemq::commands::Message, 2529
 - activemq::commands::MessageDispatchNotification, 2633
 - activemq::commands::MessagePull, 2742
- setMessageIdEnabled
 - activemq::cmsutil::CmsTemplate, 1180
- setMessageListener
 - activemq::cmsutil::CachedConsumer, 1073
 - activemq::core::ActiveMQConsumer, 318
 - cms::MessageConsumer, 2591

- setMessageSequenceId
 - activemq::commands::JournalTopicAck, 2186
- setMessageTimestampEnabled
 - activemq::cmsutil::CmsTemplate, 1181
- setMimeType
 - activemq::commands::ActiveMQBlobMessage, 207
- setName
 - activemq::commands::ActiveMQBlobMessage, 207
 - decaf::lang::Thread, 3771
- setNeedClientAuth
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2851
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2867
 - decaf::net::ssl::SSLParameters, 3553
 - decaf::net::ssl::SSLServerSocket, 3558
 - decaf::net::ssl::SSLSocket, 3569
- setNetworkBrokerId
 - activemq::commands::NetworkBridgeFilter, 2795
- setNetworkConnection
 - activemq::commands::BrokerInfo, 901
- setNetworkConsumerPath
 - activemq::commands::ConsumerInfo, 1464
- setNetworkProperties
 - activemq::commands::BrokerInfo, 901
- setNetworkSubscription
 - activemq::commands::ConsumerInfo, 1464
- setNetworkTTL
 - activemq::commands::NetworkBridgeFilter, 2795
- setNoLocal
 - activemq::cmsutil::CmsTemplate, 1181
 - activemq::commands::ConsumerInfo, 1464
- setNoRangeAcks
 - activemq::commands::ConsumerInfo, 1464
- setNumReceivedMessageBeforeFail
 - activemq::transport::mock::MockTransport, 2776
- setNumReceivedMessages
 - activemq::transport::mock::MockTransport, 2776
- setNumSentKeepAlives
 - activemq::transport::mock::MockTransport, 2776
- setNumSentKeepAlivesBeforeFail
 - activemq::transport::mock::MockTransport, 2776
- setNumSentMessageBeforeFail
 - activemq::transport::mock::MockTransport, 2776
- setNumSentMessages
 - activemq::transport::mock::MockTransport, 2776
- setObjectId
 - activemq::commands::RemoveInfo, 3196
- setOOBInline
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2868
 - decaf::net::Socket, 3514
- setOpaque
 - decaf::internal::net::URIType, 3957
- setOperationType
 - activemq::commands::DestinationInfo, 1730
- setOptimizedAcknowledge
 - activemq::commands::ConsumerInfo, 1464
- setOption
 - decaf::internal::net::tcp::TcpSocket, 3745
 - decaf::net::SocketImpl, 3535
- setOrdered
 - activemq::commands::ActiveMQDestination, 330
- setOrderedTarget
 - activemq::commands::ActiveMQDestination, 330
- setOriginalDestination
 - activemq::commands::Message, 2529
- setOriginalTransactionId
 - activemq::commands::Message, 2529
- setOutputStream
 - decaf::util::logging::StreamHandler, 3651
- setOutgoingListener
 - activemq::transport::mock::MockTransport, 2776
- setOutputStream
 - activemq::transport::IOTransport, 2150
- setParameters
 - activemq::util::CompositeData, 1220
- setParent
 - decaf::util::logging::Logger, 2395
- setPassword
 - activemq::commands::ConnectionInfo, 1359
 - activemq::core::ActiveMQConnection, 288
 - activemq::core::ActiveMQConnectionFactory, 300
- setPath
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3957
- setPeerBrokerInfos
 - activemq::commands::BrokerInfo, 901
- setPersistent

- activemq::commands::Message, 2529
- setPhysicalName
 - activemq::commands::ActiveMQDestination, 330
- setPooledThreadListener
 - decaf::util::concurrent::PooledThread, 2969
- setPort
 - decaf::internal::net::URIType, 3957
- setPreferedWireFormatInfo
 - activemq::wireformat::openwire::OpenWireFormat, 2895
- setPrefetch
 - activemq::commands::ConsumerControl, 1404
- setPrefetchPolicy
 - activemq::core::ActiveMQConnection, 288
 - activemq::core::ActiveMQConnectionFactory, 300
- setPrefetchSize
 - activemq::commands::ConsumerInfo, 1464
- setPrepared
 - activemq::state::TransactionState, 3876
- setPreparedResult
 - activemq::state::TransactionState, 3876
- setPriority
 - activemq::cmsutil::CachedProducer, 1080
 - activemq::cmsutil::CmsTemplate, 1181
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::Message, 2529
 - activemq::core::ActiveMQProducer, 476
 - cms::MessageProducer, 2731
 - decaf::lang::Thread, 3771
- setProducerId
 - activemq::commands::Message, 2529
 - activemq::commands::MessageId, 2666
 - activemq::commands::ProducerAck, 3038
 - activemq::commands::ProducerInfo, 3099
- setProducerSequenceId
 - activemq::commands::MessageId, 2666
- setProducerSessionKey
 - activemq::commands::ProducerId, 3070
- setProducerWindowSize
 - activemq::core::ActiveMQConnection, 289
 - activemq::core::ActiveMQConnectionFactory, 300
- setProperties
 - activemq::commands::WireFormatInfo, 3990
 - activemq::util::ActiveMQProperties, 481
 - decaf::util::logging::LogManager, 2411
- setProperty
 - activemq::util::ActiveMQProperties, 481
 - activemq::wireformat::stomp::StompFrame, 3637
- cms::CMSProperties, 1167
- decaf::lang::System, 3732
- decaf::util::Properties, 3132
- setProtocols
 - decaf::net::ssl::SSLParameters, 3553
- setPubSubDomain
 - activemq::cmsutil::CmsDestinationAccessor, 1159
 - activemq::cmsutil::CmsTemplate, 1181
- setQuery
 - decaf::internal::net::URIType, 3957
- setQueueBrowserPrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1675
 - activemq::core::PrefetchPolicy, 2979
- setQueuePrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1675
 - activemq::core::PrefetchPolicy, 2979
- setRandomize
 - activemq::transport::failover::FailoverTransport, 1883
 - activemq::transport::failover::URIPool, 3944
- setReadCheckTime
 - activemq::transport::inactivity::InactivityMonitor, 2007
- setReadOnly
 - decaf::internal::nio::ByteBuffer, 1019
 - decaf::internal::nio::CharArrayBuffer, 1117
 - decaf::internal::nio::DoubleArrayBuffer, 1807
 - decaf::internal::nio::FloatArrayBuffer, 1923
 - decaf::internal::nio::IntArrayBuffer, 2064
 - decaf::internal::nio::LongArrayBuffer, 2442
 - decaf::internal::nio::ShortArrayBuffer, 3457
- setReadOnlyBody
 - activemq::commands::Message, 2529
- setReadOnlyProperties
 - activemq::commands::Message, 2529
- setRebalanceConnection
 - activemq::commands::ConnectionControl, 1270
- setReceiveBufferSize
 - decaf::net::ServerSocket, 3358
 - decaf::net::Socket, 3515
- setReceiveTimeout
 - activemq::cmsutil::CmsTemplate, 1181
- setRecievedByDFBridge
 - activemq::commands::Message, 2530
- setReconnectDelay
 - activemq::transport::failover::FailoverTransport, 1883

- setReconnectTo
 - activemq::commands::ConnectionControl, 1270
- setRedeliveryCounter
 - activemq::commands::Message, 2530
 - activemq::commands::MessageDispatch, 2597
- setRedeliveryPolicy
 - activemq::core::ActiveMQConnection, 289
 - activemq::core::ActiveMQConnectionFactory, 301
 - activemq::core::ActiveMQConsumer, 318
- setRemoteBlobUrl
 - activemq::commands::ActiveMQBlobMessage, 207
- setReplyTo
 - activemq::commands::Message, 2530
- setResponse
 - activemq::transport::correlator::FutureResponse, 1970
- setResponseBuilder
 - activemq::transport::mock::InternalCommandList, 2123
 - activemq::transport::mock::MockTransport, 2776
- setResponseRequired
 - activemq::commands::BaseCommand, 763
 - activemq::commands::Command, 1197
- setRestoreConsumers
 - activemq::state::ConnectionStateTracker, 1398
- setRestoreProducers
 - activemq::state::ConnectionStateTracker, 1398
- setRestoreSessions
 - activemq::state::ConnectionStateTracker, 1398
- setRestoreTransaction
 - activemq::state::ConnectionStateTracker, 1398
- setResult
 - activemq::commands::IntegerResponse, 2093
- setResume
 - activemq::commands::ConnectionControl, 1270
- setRetroactive
 - activemq::commands::ConsumerInfo, 1464
- setReuseAddress
 - decaf::net::ServerSocket, 3359
 - decaf::net::Socket, 3515
- setScheduledTime
 - decaf::util::TimerTask, 3802
- setScheme
 - activemq::util::CompositeData, 1220
 - decaf::internal::net::URIType, 3957
- setSchemeSpecificPart
 - decaf::internal::net::URIType, 3958
- setSeed
 - decaf::security::SecureRandom, 3334, 3335
 - decaf::util::Random, 3159
- setSelector
 - activemq::commands::ConsumerInfo, 1464
 - activemq::commands::SubscriptionInfo, 3674
- setSendBufferSize
 - decaf::net::Socket, 3515
- setSendTimeout
 - activemq::core::ActiveMQConnection, 289
 - activemq::core::ActiveMQConnectionFactory, 301
 - activemq::core::ActiveMQProducer, 477
- setServerAuthority
 - decaf::internal::net::URIType, 3958
- setServiceName
 - activemq::commands::DiscoveryEvent, 1760
- setSessionAcknowledgeMode
 - activemq::cmsutil::CmsAccessor, 1156
- setSessionId
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionInfo, 3409
- setShort
 - activemq::commands::ActiveMQMapMessage, 371
 - activemq::util::PrimitiveList, 2989
 - activemq::util::PrimitiveMap, 2999
 - activemq::util::PrimitiveValueNode, 3024
 - cms::MapMessage, 2481
- setShortProperty
 - activemq::commands::ActiveMQMessageTemplate, 441
 - activemq::wireformat::openwire::utils::MessagePropertyInterface, 2737
 - cms::Message, 2557
- setSize
 - activemq::commands::ProducerAck, 3038
- setSizePrefixDisabled
 - activemq::commands::WireFormatInfo, 3990
 - activemq::wireformat::openwire::OpenWireFormat, 2896
- setSlaveBroker
 - activemq::commands::BrokerInfo, 901
- setSocketImplFactory
 - decaf::net::ServerSocket, 3359
 - decaf::net::Socket, 3516

- setSoLinger
 - decaf::net::Socket, 3516
- setSoTimeout
 - decaf::net::ServerSocket, 3359
 - decaf::net::Socket, 3516
- setSource
 - decaf::internal::net::URIType, 3958
- setSourceFile
 - decaf::util::logging::LogRecord, 2416
- setSourceFunction
 - decaf::util::logging::LogRecord, 2416
- setSourceLine
 - decaf::util::logging::LogRecord, 2416
- setSSLParameters
 - decaf::net::ssl::SSLSocket, 3569
- setStackTrace
 - decaf::lang::Exception, 1837
- setStackTraceElements
 - activemq::commands::BrokerError, 866
- setStackTraceEnabled
 - activemq::commands::WireFormatInfo, 3990
 - activemq::wireformat::openwire::OpenWireFormat, 2896
- setStart
 - activemq::commands::ConsumerControl, 1404
- setStartupMaxReconnectAttempts
 - activemq::transport::failover::FailoverTransport, 1883
- setStop
 - activemq::commands::ConsumerControl, 1404
- setStrategy
 - decaf::util::zip::Deflater, 1714
- setString
 - activemq::commands::ActiveMQMapMessage, 372
 - activemq::util::PrimitiveList, 2989
 - activemq::util::PrimitiveMap, 2999
 - activemq::util::PrimitiveValueNode, 3024
 - cms::MapMessage, 2481
- setStringProperty
 - activemq::commands::ActiveMQMessageTemplate, 441
 - activemq::wireformat::openwire::utils::MessageProperty, 2737
 - cms::Message, 2557
- setSubscriptionName
 - activemq::commands::RemoveSubscriptionInfo, 3225
 - activemq::commands::SubscriptionInfo, 3674
- setSubscribedDestination
 - activemq::commands::SubscriptionInfo, 3674
- setSubscriptionName
 - activemq::commands::ConsumerInfo, 1464
- setSubscriptionName
 - activemq::commands::JournalTopicAck, 2186
- setSuspend
 - activemq::commands::ConnectionControl, 1270
- setSynchronizationRegistered
 - activemq::core::ActiveMQConsumer, 318
- setTargetConsumerId
 - activemq::commands::Message, 2530
- setTcpNoDelay
 - decaf::net::Socket, 3517
- setTcpNoDelayEnabled
 - activemq::commands::WireFormatInfo, 3990
 - activemq::wireformat::openwire::OpenWireFormat, 2896
- setText
 - activemq::commands::ActiveMQTextMessage, 665
 - cms::TextMessage, 3764
- setTextView
 - activemq::commands::MessageId, 2666
- setThrown
 - decaf::util::logging::LogRecord, 2417
- setTightEncodingEnabled
 - activemq::commands::WireFormatInfo, 3990
 - activemq::wireformat::openwire::OpenWireFormat, 2896
- setTime
 - decaf::util::Date, 1668
- setTimeout
 - activemq::commands::DestinationInfo, 1730
 - activemq::commands::MessagePull, 2742
 - activemq::transport::failover::FailoverTransport, 1883
- setTimestamp
 - activemq::commands::Message, 2530
 - decaf::util::logging::LogRecord, 2417
- setTopicPrefetch
 - activemq::core::policies::DefaultPrefetchPolicy, 1676
 - activemq::core::PrefetchPolicy, 2979

- setTrackMessages
 - activemq::state::ConnectionStateTracker, 1398
 - activemq::transport::failover::FailoverTransport, 1883
- setTrackTransactionProducers
 - activemq::state::ConnectionStateTracker, 1398
 - activemq::transport::failover::FailoverTransport, 1883
- setTrackTransactions
 - activemq::state::ConnectionStateTracker, 1398
- setTrafficClass
 - decaf::net::Socket, 3517
- setTransactionId
 - activemq::commands::JournalTopicAck, 2186
 - activemq::commands::JournalTransaction, 2241
 - activemq::commands::Message, 2530
 - activemq::commands::MessageAck, 2563
 - activemq::commands::TransactionInfo, 3849
- setTransactionState
 - activemq::state::ProducerState, 3125
- setTransport
 - activemq::transport::failover::BackupTransport, 753
 - activemq::transport::mock::InternalCommandList, 2123
- setTransportInterruptionProcessingComplete
 - activemq::core::ActiveMQConnection, 289
- setTransportListener
 - activemq::transport::failover::FailoverTransport, 1883
 - activemq::transport::IOTransport, 2150
 - activemq::transport::mock::MockTransport, 2777
 - activemq::transport::Transport, 3887
 - activemq::transport::TransportFilter, 3897
- setTreadId
 - decaf::util::logging::LogRecord, 2417
- setType
 - activemq::commands::JournalTransaction, 2241
 - activemq::commands::Message, 2530
 - activemq::commands::TransactionInfo, 3849
- setUncaughtExceptionHandler
 - decaf::lang::Thread, 3771
- setUpSocketImpl
 - decaf::net::ServerSocket, 3360
- setUri
 - activemq::transport::failover::BackupTransport, 753
 - setUsage
 - activemq::util::MemoryUsage, 2514
 - setUseAsyncSend
 - activemq::core::ActiveMQConnection, 289
 - activemq::core::ActiveMQConnectionFactory, 301
 - setUseClientMode
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 2846
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2868
 - decaf::net::ssl::SSLSocket, 3569
 - setUseCollisionAvoidance
 - activemq::core::policies::DefaultRedeliveryPolicy, 1680
 - activemq::core::RedeliveryPolicy, 3181
 - setUseCompression
 - activemq::core::ActiveMQConnection, 290
 - activemq::core::ActiveMQConnectionFactory, 301
 - setUseExponentialBackOff
 - activemq::core::policies::DefaultRedeliveryPolicy, 1680
 - activemq::core::RedeliveryPolicy, 3181
 - activemq::transport::failover::FailoverTransport, 1883
 - setUseParentHandlers
 - decaf::util::logging::Logger, 2395
 - setUserID
 - activemq::commands::Message, 2530
 - setUserInfo
 - decaf::internal::net::URIType, 3958
 - setUserName
 - activemq::commands::ConnectionInfo, 1359
 - setUsername
 - activemq::core::ActiveMQConnection, 290
 - activemq::core::ActiveMQConnectionFactory, 301
 - setValid
 - decaf::internal::net::URIType, 3958
 - setValue
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1329
 - activemq::commands::ConsumerId, 1433
 - activemq::commands::LocalTransactionId, 2350
 - activemq::commands::MessageId, 2666
 - activemq::commands::ProducerId, 3070
 - activemq::commands::SessionId, 3382
 - activemq::util::PrimitiveValueNode, 3024
 - decaf::util::Map::Entry, 1824

- setVersion
 - activemq::commands::WireFormatInfo, 3990
 - activemq::wireformat::openwire::OpenWireFormat, 2896
 - activemq::wireformat::stomp::StompWireFormat, 3645
 - activemq::wireformat::WireFormat, 3978
- setWantClientAuth
 - decaf::internal::net::ssl::openssl::OpenSSLParameters, 1224
 - decaf::internal::net::ssl::openssl::OpenSSLServerSocket, 2852
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2868
 - decaf::net::ssl::SSLParameters, 3553
 - decaf::net::ssl::SSLServerSocket, 3558
 - decaf::net::ssl::SSLSocket, 3570
- setWasPrepared
 - activemq::commands::JournalTransaction, 2241
- setWindowSize
 - activemq::commands::ProducerInfo, 3099
- setWireFormat
 - activemq::transport::failover::FailoverTransport, 1884
 - activemq::transport::IOTransport, 2150
 - activemq::transport::mock::MockTransport, 2777
 - activemq::transport::Transport, 3888
 - activemq::transport::TransportFilter, 3897
- setWriteCheckTime
 - activemq::transport::inactivity::InactivityMonitor, 2007
- SEVERE
 - decaf::util::logging::Level, 2336
- severe
 - decaf::util::logging::Logger, 2396
- Short
 - decaf::lang::Short, 3441
- SHORT_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- ShortArrayBuffer
 - decaf::internal::nio::ShortArrayBuffer, 3452, 3453
- ShortBuffer
 - decaf::nio::ShortBuffer, 3461
- shortValue
 - activemq::util::PrimitiveValueNode::PrimitiveValueNode, 3009
 - decaf::lang::Byte, 966
 - decaf::lang::Character, 1106
 - decaf::lang::Double, 1796
 - decaf::lang::Float, 1912
 - decaf::lang::Integer, 2087
 - decaf::lang::Long, 2430
 - decaf::lang::Number, 2837
 - decaf::lang::Short, 3446
- shutdown
 - activemq::state::ConnectionState, 1391
 - activemq::state::SessionState, 3438
 - activemq::state::TransactionState, 3876
 - activemq::threads::CompositeTaskRunner, 1671, 1672
 - activemq::threads::DedicatedTaskRunner, 3736
 - activemq::threads::TaskRunner, 3736
 - ShutdownInfo
 - activemq::commands::ShutdownInfo, 3471
 - ShutdownInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaller, 3482
 - activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller, 3478
 - activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller, 3490
 - activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller, 3494
 - activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller, 3486
 - activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3474
 - shutdownInput
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2869
 - decaf::internal::net::tcp::TcpSocket, 3745
 - decaf::net::Socket, 3517
 - decaf::net::SocketImpl, 3535
 - shutdownLibrary
 - activemq::library::ActiveMQCPP, 321
 - shutdownNetworking
 - decaf::internal::net::Network, 2791
 - shutdownOutput
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2869
 - decaf::internal::net::tcp::TcpSocket, 3745
 - decaf::net::Socket, 3517
 - decaf::net::SocketImpl, 3535
 - shutdownRuntime
 - decaf::lang::Runtime, 3327
 - signal
 - decaf::util::concurrent::locks::Condition, 1254
 - signalAll
 - decaf::util::concurrent::locks::Condition, 1254
 - SignatureException

- decaf::security::SignatureException, 3497, 3498
- signum
 - decaf::lang::Integer, 2087
 - decaf::lang::Long, 2430
 - decaf::lang::Math, 2506, 2507
- SimpleFormatter
 - decaf::util::logging::SimpleFormatter, 3500
- SimpleLogger
 - decaf::util::logging::SimpleLogger, 3501
- SIZE
 - decaf::lang::Byte, 968
 - decaf::lang::Character, 1107
 - decaf::lang::Double, 1798
 - decaf::lang::Float, 1914
 - decaf::lang::Integer, 2090
 - decaf::lang::Long, 2433
 - decaf::lang::Short, 3448
- size
 - activemq::commands::ProducerAck, 3039
 - activemq::core::MessageDispatchChannel, 2603
 - activemq::wireformat::openwire::utils::HexTable, 1985
 - decaf::internal::util::TimerTaskHeap, 3806
 - decaf::io::ByteArrayOutputStream, 1029
 - decaf::io::DataOutputStream, 1581
 - decaf::util::Collection, 1191
 - decaf::util::concurrent::ConcurrentStlMap, 1245
 - decaf::util::concurrent::SynchronousQueue, 3724
 - decaf::util::Map, 2469
 - decaf::util::PriorityQueue, 3034
 - decaf::util::Properties, 3132
 - decaf::util::StlList, 3601
 - decaf::util::StlMap, 3611
 - decaf::util::StlQueue, 3620
 - decaf::util::StlSet, 3628
 - gz_state, 1977
- skip
 - decaf::internal::net::ssl::openssl::OpenSSLSocketInputStream, 2884
 - decaf::internal::net::tcp::TcpSocketInputStream, 3749
 - decaf::io::BlockingByteArrayInputStream, 841
 - decaf::io::BufferedInputStream, 938
 - decaf::io::ByteArrayInputStream, 1026
 - decaf::io::FilterInputStream, 1899
 - decaf::io::InputStream, 2050
 - decaf::io::PushbackInputStream, 3145
 - decaf::io::Reader, 3168
 - decaf::util::zip::CheckedInputStream, 1138
 - decaf::util::zip::InflaterInputStream, 2040
 - gz_state, 1977
- skipBytes
 - decaf::io::DataInput, 1565
 - decaf::io::DataInputStream, 1573
- slaveBroker
 - activemq::commands::BrokerInfo, 903
- sleep
 - decaf::lang::Thread, 3772
 - decaf::util::concurrent::TimeUnit, 3811
- SLEEPING
 - decaf::lang::Thread, 3768
- slice
 - decaf::internal::nio::ByteBuffer, 1019
 - decaf::internal::nio::CharArrayBuffer, 1117
 - decaf::internal::nio::DoubleArrayBuffer, 1807
 - decaf::internal::nio::FloatArrayBuffer, 1923
 - decaf::internal::nio::IntArrayBuffer, 2064
 - decaf::internal::nio::LongArrayBuffer, 2442
 - decaf::internal::nio::ShortArrayBuffer, 3457
 - decaf::nio::ByteBuffer, 1053
 - decaf::nio::CharBuffer, 1132
 - decaf::nio::DoubleBuffer, 1818
 - decaf::nio::FloatBuffer, 1933
 - decaf::nio::IntBuffer, 2075
 - decaf::nio::LongBuffer, 2453
 - decaf::nio::ShortBuffer, 3467
- Socket
 - decaf::net::Socket, 3506–3508
- SOCKET_OPTION_BINDADDR
 - decaf::net::SocketOptions, 3539
- SOCKET_OPTION_BROADCAST
 - decaf::net::SocketOptions, 3539
- SOCKET_OPTION_IP_MULTICAST_IF
 - decaf::net::SocketOptions, 3539
- SOCKET_OPTION_IP_MULTICAST_IF2
 - decaf::net::SocketOptions, 3539
- SOCKET_OPTION_IP_MULTICAST_LOOP
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_IP_TOS
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_KEEPAIVE
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_LINGER
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_OOBLINE
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_RCVBUF
 - decaf::net::SocketOptions, 3540
- SOCKET_OPTION_REUSEADDR
 - decaf::net::SocketOptions, 3541

SOCKET_OPTION_SNDBUF	src/main/activemq/commands/ActiveMQMessage.h,
decaf::net::SocketOptions, 3541	4085
SOCKET_OPTION_TCP_NODELAY	src/main/activemq/commands/ActiveMQMessageTemplate.h,
decaf::net::SocketOptions, 3541	4086
SOCKET_OPTION_TIMEOUT	src/main/activemq/commands/ActiveMQObjectMessage.h,
decaf::net::SocketOptions, 3541	4087
SocketException	src/main/activemq/commands/ActiveMQQueue.h,
decaf::net::SocketException, 3521, 3522	4088
SocketFactory	src/main/activemq/commands/ActiveMQStreamMessage.h,
decaf::net::SocketFactory, 3525	4089
SocketFileDescriptor	src/main/activemq/commands/ActiveMQTempDestination.h,
decaf::internal::net::SocketFileDescriptor,	4090
3528	src/main/activemq/commands/ActiveMQTempQueue.h,
SocketImpl	4091
decaf::net::SocketImpl, 3531	src/main/activemq/commands/ActiveMQTempTopic.h,
SocketTimeoutException	4092
decaf::net::SocketTimeoutException, 3542,	src/main/activemq/commands/ActiveMQTextMessage.h,
3543	4093
sqrt	src/main/activemq/commands/ActiveMQTopic.h,
decaf::lang::Math, 2508	4094
src/main/activemq/cmsutil/CachedConsumer.h,	src/main/activemq/commands/BaseCommand.h,
4067	4095
src/main/activemq/cmsutil/CachedProducer.h,	src/main/activemq/commands/BaseDataStructure.h,
4068	4096
src/main/activemq/cmsutil/CmsAccessor.h,	src/main/activemq/commands/BooleanExpression.h,
4069	4097
src/main/activemq/cmsutil/CmsDestinationAccessControl.h,	src/main/activemq/commands/BrokerError.h,
4070	4098
src/main/activemq/cmsutil/CmsTemplate.h,	src/main/activemq/commands/BrokerId.h,
4071	4099
src/main/activemq/cmsutil/DestinationResolver.h,	src/main/activemq/commands/BrokerInfo.h,
4072	4100
src/main/activemq/cmsutil/DynamicDestinationResolver.h,	src/main/activemq/commands/Command.h,
4073	4101
src/main/activemq/cmsutil/MessageCreator.h,	src/main/activemq/commands/ConnectionControl.h,
4074	4102
src/main/activemq/cmsutil/PooledSession.h,	src/main/activemq/commands/ConnectionError.h,
4075	4103
src/main/activemq/cmsutil/ProducerCallback.h,	src/main/activemq/commands/ConnectionId.h,
4076	4104
src/main/activemq/cmsutil/ResourceLifecycleManager.h,	src/main/activemq/commands/ConnectionInfo.h,
4077	4105
src/main/activemq/cmsutil/SessionCallback.h,	src/main/activemq/commands/ConsumerControl.h,
4079	4106
src/main/activemq/cmsutil/SessionPool.h,	src/main/activemq/commands/ConsumerId.h,
4080	4107
src/main/activemq/commands/ActiveMQBlobMessage.h,	src/main/activemq/commands/ConsumerInfo.h,
4081	4108
src/main/activemq/commands/ActiveMQBytesMessage.h,	src/main/activemq/commands/ControlCommand.h,
4082	4109
src/main/activemq/commands/ActiveMQDestination.h,	src/main/activemq/commands/DataArrayResponse.h,
4083	4110
src/main/activemq/commands/ActiveMQMapMessage.h,	src/main/activemq/commands/DataResponse.h,
4084	4111

src/main/activemq/commands/DataStructure.h, src/main/activemq/commands/Response.h,
 4112 4140
 src/main/activemq/commands/DestinationInfo.h,src/main/activemq/commands/SessionId.h,
 4113 4141
 src/main/activemq/commands/DiscoveryEvent.h,src/main/activemq/commands/SessionInfo.h,
 4114 4142
 src/main/activemq/commands/ExceptionResponse.h,src/main/activemq/commands/ShutdownInfo.h,
 4115 4143
 src/main/activemq/commands/FlushCommand.hsrc/main/activemq/commands/SubscriptionInfo.h,
 4116 4144
 src/main/activemq/commands/IntegerResponse.hsrc/main/activemq/commands/TransactionId.h,
 4117 4145
 src/main/activemq/commands/JournalQueueAck.hsrc/main/activemq/commands/TransactionInfo.h,
 4118 4146
 src/main/activemq/commands/JournalTopicAck.hsrc/main/activemq/commands/WireFormatInfo.h,
 4119 4147
 src/main/activemq/commands/JournalTrace.h, src/main/activemq/commands/XATransactionId.h,
 4120 4148
 src/main/activemq/commands/JournalTransaction.h,src/main/activemq/core/ActiveMQAckHandler.h,
 4121 4149
 src/main/activemq/commands/KeepAliveInfo.h, src/main/activemq/core/ActiveMQConnection.h,
 4122 4150
 src/main/activemq/commands/LastPartialCommand.h,src/main/activemq/core/ActiveMQConnectionFactory.h,
 4123 4151
 src/main/activemq/commands/LocalTransactionId.h,src/main/activemq/core/ActiveMQConnectionMetaData.h,
 4124 4152
 src/main/activemq/commands/Message.h, src/main/activemq/core/ActiveMQConstants.h,
 4125 4153
 src/main/activemq/commands/MessageAck.h, src/main/activemq/core/ActiveMQConsumer.h,
 4127 4154
 src/main/activemq/commands/MessageDispatch.hsrc/main/activemq/core/ActiveMQProducer.h,
 4128 4155
 src/main/activemq/commands/MessageDispatchNotification.h,src/main/activemq/core/ActiveMQQueueBrowser.h,
 4129 4156
 src/main/activemq/commands/MessageId.h, src/main/activemq/core/ActiveMQSession.h,
 4130 4157
 src/main/activemq/commands/MessagePull.h, src/main/activemq/core/ActiveMQSessionExecutor.h,
 4131 4158
 src/main/activemq/commands/NetworkBridgeFilter.h,src/main/activemq/core/ActiveMQTransactionContext.h,
 4132 4159
 src/main/activemq/commands/PartialCommand.hsrc/main/activemq/core/DispatchData.h, 4160
 4133 src/main/activemq/core/Dispatcher.h, 4161
 src/main/activemq/commands/ProducerAck.h, src/main/activemq/core/MessageDispatchChannel.h,
 4134 4162
 src/main/activemq/commands/ProducerId.h, src/main/activemq/core/policies/DefaultPrefetchPolicy.h,
 4135 4163
 src/main/activemq/commands/ProducerInfo.h, src/main/activemq/core/policies/DefaultRedeliveryPolicy.h,
 4136 4164
 src/main/activemq/commands/RemoveInfo.h, src/main/activemq/core/PrefetchPolicy.h, 4165
 4137 src/main/activemq/core/RedeliveryPolicy.h,
 src/main/activemq/commands/RemoveSubscriptionInfo.h, 4166
 4138 src/main/activemq/core/Synchronization.h,
 src/main/activemq/commands/ReplayCommand.h, 4167
 4139 src/main/activemq/exceptions/ActiveMQException.h,

- 4168
- src/main/activemq/exceptions/BrokerException.h, 4202
- 4169
- src/main/activemq/exceptions/ExceptionDefines.h, 4203
- 4170
- src/main/activemq/io/LoggingInputStream.h, 4204
- 4175
- src/main/activemq/io/LoggingOutputStream.h, 4205
- 4176
- src/main/activemq/library/ActiveMQCPP.h, 4206
- 4177
- src/main/activemq/state/CommandVisitor.h, 4207
- 4178
- src/main/activemq/state/CommandVisitorAdapter.h, 4208
- 4179
- src/main/activemq/state/ConnectionState.h, 4209
- 4181
- src/main/activemq/state/ConnectionStateTracker.h, 4210
- 4182
- src/main/activemq/state/ConsumerState.h, 4211
- 4183
- src/main/activemq/state/ProducerState.h, 4212
- 4184
- src/main/activemq/state/SessionState.h, 4185
- src/main/activemq/state/Tracked.h, 4186
- src/main/activemq/state/TransactionState.h, 4187
- src/main/activemq/threads/CompositeTask.h, 4188
- src/main/activemq/threads/CompositeTaskRunner.h, 4189
- src/main/activemq/threads/DedicatedTaskRunner.h, 4190
- src/main/activemq/threads/Task.h, 4191
- src/main/activemq/threads/TaskRunner.h, 4192
- src/main/activemq/transport/AbstractTransportFactory.h, 4193
- src/main/activemq/transport/CompositeTransport.h, 4194
- src/main/activemq/transport/correlator/FutureResponse.h, 4195
- src/main/activemq/transport/correlator/ResponseCorrelator.h, 4196
- src/main/activemq/transport/DefaultTransportListener.h, 4197
- src/main/activemq/transport/failover/BackupTransport.h, 4198
- src/main/activemq/transport/failover/BackupTransportPool.h, 4199
- src/main/activemq/transport/failover/CloseTransport.h, 4200
- src/main/activemq/transport/failover/FailoverTransport.h, 4201
- src/main/activemq/transport/failover/FailoverTransportFactory.h, 4202
- src/main/activemq/transport/failover/FailoverTransportListener.h, 4203
- src/main/activemq/transport/failover/URIPool.h, 4204
- src/main/activemq/transport/inactivity/InactivityMonitor.h, 4205
- src/main/activemq/transport/inactivity/ReadChecker.h, 4206
- src/main/activemq/transport/inactivity/WriteChecker.h, 4207
- src/main/activemq/transport/IOTransport.h, 4208
- src/main/activemq/transport/logging/LoggingTransport.h, 4209
- src/main/activemq/transport/mock/InternalCommandListener.h, 4210
- src/main/activemq/transport/mock/MockTransport.h, 4211
- src/main/activemq/transport/mock/MockTransportFactory.h, 4212
- src/main/activemq/transport/mock/ResponseBuilder.h, 4213
- src/main/activemq/transport/tcp/SslTransport.h, 4214
- src/main/activemq/transport/tcp/SslTransportFactory.h, 4215
- src/main/activemq/transport/tcp/TcpTransport.h, 4216
- src/main/activemq/transport/tcp/TcpTransportFactory.h, 4217
- src/main/activemq/transport/Transport.h, 4218
- src/main/activemq/transport/TransportFactory.h, 4219
- src/main/activemq/transport/TransportFilter.h, 4220
- src/main/activemq/transport/TransportListener.h, 4221
- src/main/activemq/transport/TransportRegistry.h, 4222
- src/main/activemq/transport/correlator/ResponseCorrelator.h, 4223
- src/main/activemq/util/ActiveMQProperties.h, 4224
- src/main/activemq/util/CMSExceptionSupport.h, 4225
- src/main/activemq/util/CompositeData.h, 4226
- src/main/activemq/util/Config.h, 4227
- src/main/activemq/util/IdGenerator.h, 4230
- src/main/activemq/util/LongSequenceGenerator.h, 4231
- src/main/activemq/util/MarshallingSupport.h, 4232

- src/main/activemq/util/MemoryUsage.h, 4233
- src/main/activemq/util/PrimitiveList.h, 4234
- src/main/activemq/util/PrimitiveMap.h, 4235
- src/main/activemq/util/PrimitiveValueConverter.h, 4236
- src/main/activemq/util/PrimitiveValueNode.h, 4237
- src/main/activemq/util/URISupport.h, 4238
- src/main/activemq/util/Usage.h, 4239
- src/main/activemq/wireformat/MarshalAware.h, 4240
- src/main/activemq/wireformat/openwire/marshal/BaseDataStreamMarshaller.h, 4241
- src/main/activemq/wireformat/openwire/marshal/DataStreamMarshaller.h, 4242
- src/main/activemq/wireformat/openwire/marshal/PrimitiveTypesMarshaller.h, 4243
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBlobMessageMarshaller.h, 4244
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQBytesMessageMarshaller.h, 4250
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQDestinationMarshaller.h, 4256
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMapMessageMarshaller.h, 4262
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQMessageMarshaller.h, 4268
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQObjectMessageMarshaller.h, 4274
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQQueueMarshaller.h, 4280
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQStreamMessageMarshaller.h, 4286
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempDestinationMarshaller.h, 4292
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempQueueMarshaller.h, 4298
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTempTopicMarshaller.h, 4304
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTextMessageMarshaller.h, 4310
- src/main/activemq/wireformat/openwire/marshal/v1/ActiveMQTopicMarshaller.h, 4316
- src/main/activemq/wireformat/openwire/marshal/v1/BaseCommandMarshaller.h, 4322
- src/main/activemq/wireformat/openwire/marshal/v1/BrokerIdMarshaller.h, 4328
- src/main/activemq/wireformat/openwire/marshal/v1/BrokerInfoMarshaller.h, 4334
- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionControlMarshaller.h, 4340
- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionErrorMarshaller.h, 4346
- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionIdMarshaller.h, 4352
- src/main/activemq/wireformat/openwire/marshal/v1/ConnectionInfoMarshaller.h, 4358
- src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h, 4364
- src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h, 4370
- src/main/activemq/wireformat/openwire/marshal/v1/ConsumerInfoMarshaller.h, 4376
- src/main/activemq/wireformat/openwire/marshal/v1/ControlCommandMarshaller.h, 4382
- src/main/activemq/wireformat/openwire/marshal/v1/DataArrayMarshaller.h, 4388
- src/main/activemq/wireformat/openwire/marshal/v1/DataResponseMarshaller.h, 4394
- src/main/activemq/wireformat/openwire/marshal/v1/DestinationInfoMarshaller.h, 4400
- src/main/activemq/wireformat/openwire/marshal/v1/DiscoveryInfoMarshaller.h, 4406
- src/main/activemq/wireformat/openwire/marshal/v1/ExceptionInfoMarshaller.h, 4412
- src/main/activemq/wireformat/openwire/marshal/v1/FlushCommandMarshaller.h, 4418
- src/main/activemq/wireformat/openwire/marshal/v1/IntegerResponseMarshaller.h, 4424
- src/main/activemq/wireformat/openwire/marshal/v1/JournalQueueMarshaller.h, 4430
- src/main/activemq/wireformat/openwire/marshal/v1/JournalTopicMarshaller.h, 4436
- src/main/activemq/wireformat/openwire/marshal/v1/JournalTraceMarshaller.h, 4442
- src/main/activemq/wireformat/openwire/marshal/v1/JournalTransactionMarshaller.h, 4448
- src/main/activemq/wireformat/openwire/marshal/v1/KeepAliveInfoMarshaller.h, 4454
- src/main/activemq/wireformat/openwire/marshal/v1/LastPartialMessageMarshaller.h, 4460
- src/main/activemq/wireformat/openwire/marshal/v1/LocalTransactionMarshaller.h, 4466
- src/main/activemq/wireformat/openwire/marshal/v1/Marshallable.h, 4472
- src/main/activemq/wireformat/openwire/marshal/v1/MessageAckMarshaller.h, 4478
- src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchMarshaller.h, 4484
- src/main/activemq/wireformat/openwire/marshal/v1/MessageDispatchInfoMarshaller.h, 4490
- src/main/activemq/wireformat/openwire/marshal/v1/MessageIdMarshaller.h, 4496
- src/main/activemq/wireformat/openwire/marshal/v1/MessageMarshaller.h, 4502
- src/main/activemq/wireformat/openwire/marshal/v1/MessagePullMarshaller.h, 4508

src/main/activemq/wireformat/openwire/marshalsrv1/NetworkBridgeFilterMarshaller/openwire/marshal/v2/ActiveMQT	
4514	4305
src/main/activemq/wireformat/openwire/marshalsrv1/PartialCommandMarshaller/openwire/marshal/v2/ActiveMQT	
4520	4311
src/main/activemq/wireformat/openwire/marshalsrv1/ProducerAckMarshaller/openwire/marshal/v2/ActiveMQT	
4526	4317
src/main/activemq/wireformat/openwire/marshalsrv1/ProducerIdMarshaller/openwire/marshal/v2/BaseComm	
4532	4323
src/main/activemq/wireformat/openwire/marshalsrv1/ProducerInfoMarshaller/openwire/marshal/v2/BrokerIdMa	
4538	4329
src/main/activemq/wireformat/openwire/marshalsrv1/ProducerInfoMarshaller/openwire/marshal/v2/BrokerInfoM	
4544	4335
src/main/activemq/wireformat/openwire/marshalsrv1/ProducerSubscriptionInfoMarshaller/openwire/marshal/v2/Connection	
4550	4341
src/main/activemq/wireformat/openwire/marshalsrv1/ReplyCommandMarshaller/openwire/marshal/v2/Connection	
4556	4347
src/main/activemq/wireformat/openwire/marshalsrv1/ResponseMarshaller/openwire/marshal/v2/Connection	
4562	4353
src/main/activemq/wireformat/openwire/marshalsrv1/SessionMarshaller/openwire/marshal/v2/Connection	
4568	4359
src/main/activemq/wireformat/openwire/marshalsrv1/SessionInfoMarshaller/openwire/marshal/v2/ConsumerC	
4574	4365
src/main/activemq/wireformat/openwire/marshalsrv1/SubscriptionInfoMarshaller/openwire/marshal/v2/ConsumerId	
4580	4371
src/main/activemq/wireformat/openwire/marshalsrv1/SubscriptionInfoMarshaller/openwire/marshal/v2/ConsumerIn	
4586	4377
src/main/activemq/wireformat/openwire/marshalsrv1/SubscriptionIdMarshaller/openwire/marshal/v2/ControlCom	
4592	4383
src/main/activemq/wireformat/openwire/marshalsrv1/SubscriptionInfoMarshaller/openwire/marshal/v2/DataArrayF	
4598	4389
src/main/activemq/wireformat/openwire/marshalsrv1/WireFormatInfoMarshaller/openwire/marshal/v2/DataRespor	
4604	4395
src/main/activemq/wireformat/openwire/marshalsrv1/XATransactionIdMarshaller/openwire/marshal/v2/Destination	
4610	4401
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQBlobMessageMarshaller/openwire/marshal/v2/DiscoveryE	
4245	4407
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQBytesMessageMarshaller/openwire/marshal/v2/ExceptionR	
4251	4413
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQDestinationMarshaller/openwire/marshal/v2/FlushComm	
4257	4419
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQMapMessageMarshaller/openwire/marshal/v2/IntegerResp	
4263	4425
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQMessageMarshaller/openwire/marshal/v2/JournalQue	
4269	4431
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQQueueMessageMarshaller/openwire/marshal/v2/JournalTop	
4275	4437
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQQueueMessageMarshaller/openwire/marshal/v2/JournalTrac	
4281	4443
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQQueueMessageMarshaller/openwire/marshal/v2/JournalTran	
4287	4449
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQQueueDestinationMarshaller/openwire/marshal/v2/KeepAliveIn	
4293	4455
src/main/activemq/wireformat/openwire/marshalsrv2/ActiveMQQueueMessageMarshaller/openwire/marshal/v2/LastPartial	
4299	4461

src/main/activemq/wireformat/openwire/marshalsrv2/InboundTransactionWireMarshaller/openwire/marshal/v3/ActiveMQD
4467 4258

src/main/activemq/wireformat/openwire/marshalsrv2/MarshallerFactory/openwire/marshal/v3/ActiveMQM
4473 4264

src/main/activemq/wireformat/openwire/marshalsrv2/MessageMarshaller/openwire/marshal/v3/ActiveMQM
4479 4270

src/main/activemq/wireformat/openwire/marshalsrv2/MessageDispatcherMarshaller/openwire/marshal/v3/ActiveMQC
4485 4276

src/main/activemq/wireformat/openwire/marshalsrv2/MessageDispatcherNotificationMarshaller/openwire/marshal/v3/ActiveMQC
4491 4282

src/main/activemq/wireformat/openwire/marshalsrv2/MessageMarshaller/openwire/marshal/v3/ActiveMQS
4497 4288

src/main/activemq/wireformat/openwire/marshalsrv2/MessageMarshaller/openwire/marshal/v3/ActiveMQT
4503 4294

src/main/activemq/wireformat/openwire/marshalsrv2/MessagePullMarshaller/openwire/marshal/v3/ActiveMQT
4509 4300

src/main/activemq/wireformat/openwire/marshalsrv2/NetworkBridgeFilterMarshaller/openwire/marshal/v3/ActiveMQT
4515 4306

src/main/activemq/wireformat/openwire/marshalsrv2/PartialCommandMarshaller/openwire/marshal/v3/ActiveMQT
4521 4312

src/main/activemq/wireformat/openwire/marshalsrv2/ProducerAckMarshaller/openwire/marshal/v3/ActiveMQT
4527 4318

src/main/activemq/wireformat/openwire/marshalsrv2/ProducerIdMarshaller/openwire/marshal/v3/BaseComm
4533 4324

src/main/activemq/wireformat/openwire/marshalsrv2/ProducerIdMarshaller/openwire/marshal/v3/BrokerIdMa
4539 4330

src/main/activemq/wireformat/openwire/marshalsrv2/ProducerInfoMarshaller/openwire/marshal/v3/BrokerInfo
4545 4336

src/main/activemq/wireformat/openwire/marshalsrv2/ProducerSubscriptionInfoMarshaller/openwire/marshal/v3/Connection
4551 4342

src/main/activemq/wireformat/openwire/marshalsrv2/ReplyCommandMarshaller/openwire/marshal/v3/Connection
4557 4348

src/main/activemq/wireformat/openwire/marshalsrv2/ResponsiveMarshaller/openwire/marshal/v3/Connection
4563 4354

src/main/activemq/wireformat/openwire/marshalsrv2/SessionIdMarshaller/openwire/marshal/v3/Connection
4569 4360

src/main/activemq/wireformat/openwire/marshalsrv2/SessionInfoMarshaller/openwire/marshal/v3/ConsumerC
4575 4366

src/main/activemq/wireformat/openwire/marshalsrv2/ShutdownInfoMarshaller/openwire/marshal/v3/ConsumerId
4581 4372

src/main/activemq/wireformat/openwire/marshalsrv2/SubscriptionInfoMarshaller/openwire/marshal/v3/ConsumerIn
4587 4378

src/main/activemq/wireformat/openwire/marshalsrv2/TransactionIdMarshaller/openwire/marshal/v3/ControlCom
4593 4384

src/main/activemq/wireformat/openwire/marshalsrv2/TransactionInfoMarshaller/openwire/marshal/v3/DataArrayF
4599 4390

src/main/activemq/wireformat/openwire/marshalsrv2/WireFormatInfoMarshaller/openwire/marshal/v3/DataRespon
4605 4396

src/main/activemq/wireformat/openwire/marshalsrv2/XML/activemq/IdMarshaller/openwire/marshal/v3/Destination
4611 4402

src/main/activemq/wireformat/openwire/marshalsrv3/ActiveMQBlockMessageMarshaller/openwire/marshal/v3/DiscoveryE
4246 4408

src/main/activemq/wireformat/openwire/marshalsrv3/ActiveMQBytesMessageMarshaller/openwire/marshal/v3/ExceptionR
4252 4414

src/main/activemq/wireformat/openwire/marshaller/v3/FlushContinuationMarshaller/openwire/marshaller/v3/ShutDownIn	4420	4582
src/main/activemq/wireformat/openwire/marshaller/v3/InflightResponseMarshaller/openwire/marshaller/v3/Subscription	4426	4588
src/main/activemq/wireformat/openwire/marshaller/v3/JainActiveQueueAckMarshaller/openwire/marshaller/v3/Transaction	4432	4594
src/main/activemq/wireformat/openwire/marshaller/v3/JainActiveQueueAckMarshaller/openwire/marshaller/v3/Transaction	4438	4600
src/main/activemq/wireformat/openwire/marshaller/v3/JainActiveQueueMarshaller/openwire/marshaller/v3/WireFormat	4444	4606
src/main/activemq/wireformat/openwire/marshaller/v3/JainActiveQueueMarshaller/openwire/marshaller/v3/XATransact	4450	4612
src/main/activemq/wireformat/openwire/marshaller/v3/KeepActiveInfoMarshaller/openwire/marshaller/v4/ActiveMQB	4456	4247
src/main/activemq/wireformat/openwire/marshaller/v3/LastPartialContinuationMarshaller/openwire/marshaller/v4/ActiveMQB	4462	4253
src/main/activemq/wireformat/openwire/marshaller/v3/LastPartialContinuationMarshaller/openwire/marshaller/v4/ActiveMQD	4468	4259
src/main/activemq/wireformat/openwire/marshaller/v3/MarshallerFactory/openwire/marshaller/v4/ActiveMQM	4474	4265
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQM	4480	4271
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQC	4486	4277
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQC	4492	4283
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQS	4498	4289
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQT	4504	4295
src/main/activemq/wireformat/openwire/marshaller/v3/MisactiveQueueMarshaller/openwire/marshaller/v4/ActiveMQT	4510	4301
src/main/activemq/wireformat/openwire/marshaller/v3/NioBridgeFilterMarshaller/openwire/marshaller/v4/ActiveMQT	4516	4307
src/main/activemq/wireformat/openwire/marshaller/v3/PartialContinuationMarshaller/openwire/marshaller/v4/ActiveMQT	4522	4313
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerAckMarshaller/openwire/marshaller/v4/ActiveMQT	4528	4319
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerIdMarshaller/openwire/marshaller/v4/BaseComm	4534	4325
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerIdMarshaller/openwire/marshaller/v4/BrokerIdMa	4540	4331
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerInfoMarshaller/openwire/marshaller/v4/BrokerInfoM	4546	4337
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerSubscriptionInfoMarshaller/openwire/marshaller/v4/Connection	4552	4343
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerSubscriptionInfoMarshaller/openwire/marshaller/v4/Connection	4558	4349
src/main/activemq/wireformat/openwire/marshaller/v3/ProducerSubscriptionInfoMarshaller/openwire/marshaller/v4/Connection	4564	4355
src/main/activemq/wireformat/openwire/marshaller/v3/SessionIdMarshaller/openwire/marshaller/v4/Connection	4570	4361
src/main/activemq/wireformat/openwire/marshaller/v3/SessionInfoMarshaller/openwire/marshaller/v4/ConsumerC	4576	4367

src/main/activemq/wireformat/openwire/marshaller/v4/ConsumerInfoMarshaller.dat/openwire/marshal/v4/ProducerId
4373 4535

src/main/activemq/wireformat/openwire/marshaller/v4/ConsumerInfoMarshaller.dat/openwire/marshal/v4/ProducerInfo
4379 4541

src/main/activemq/wireformat/openwire/marshaller/v4/ControlCommandMarshaller/openwire/marshal/v4/RemoveInfo
4385 4547

src/main/activemq/wireformat/openwire/marshaller/v4/DataActiveResponseMarshaller/openwire/marshal/v4/RemoveSub
4391 4553

src/main/activemq/wireformat/openwire/marshaller/v4/DataResponseMarshaller.dat/openwire/marshal/v4/ReplayCom
4397 4559

src/main/activemq/wireformat/openwire/marshaller/v4/DeactivateInfoMarshaller/openwire/marshal/v4/ResponseM
4403 4565

src/main/activemq/wireformat/openwire/marshaller/v4/DisconnectWireMarshaller/openwire/marshal/v4/SessionIdM
4409 4571

src/main/activemq/wireformat/openwire/marshaller/v4/ExceptionResponseMarshaller/openwire/marshal/v4/SessionInfo
4415 4577

src/main/activemq/wireformat/openwire/marshaller/v4/FlushActivemqWireMarshaller/openwire/marshal/v4/ShutDownIn
4421 4583

src/main/activemq/wireformat/openwire/marshaller/v4/InegerResponseMarshaller/openwire/marshal/v4/Subscription
4427 4589

src/main/activemq/wireformat/openwire/marshaller/v4/JournalQueueAckMarshaller/openwire/marshal/v4/Transaction
4433 4595

src/main/activemq/wireformat/openwire/marshaller/v4/JournalTopicAckMarshaller/openwire/marshal/v4/Transaction
4439 4601

src/main/activemq/wireformat/openwire/marshaller/v4/JournalTransMarshaller.dat/openwire/marshal/v4/WireFormat
4445 4607

src/main/activemq/wireformat/openwire/marshaller/v4/JournalTransWireMarshaller/openwire/marshal/v4/XATransact
4451 4613

src/main/activemq/wireformat/openwire/marshaller/v4/KickActiveInfoMarshaller.dat/openwire/marshal/v5/ActiveMQB
4457 4248

src/main/activemq/wireformat/openwire/marshaller/v4/LastActiveQueueIdMarshaller/openwire/marshal/v5/ActiveMQB
4463 4254

src/main/activemq/wireformat/openwire/marshaller/v4/LoadQueueWireMarshaller/openwire/marshal/v5/ActiveMQD
4469 4260

src/main/activemq/wireformat/openwire/marshaller/v4/MarshallerFactory.dat/openwire/marshal/v5/ActiveMQM
4475 4266

src/main/activemq/wireformat/openwire/marshaller/v4/MisageAckMarshaller.dat/openwire/marshal/v5/ActiveMQM
4481 4272

src/main/activemq/wireformat/openwire/marshaller/v4/MisageDispatchMarshaller/openwire/marshal/v5/ActiveMQC
4487 4278

src/main/activemq/wireformat/openwire/marshaller/v4/MisageDispatchNotificationMarshaller.dat/openwire/marshal/v5/ActiveMQC
4493 4284

src/main/activemq/wireformat/openwire/marshaller/v4/MisageLiveMsgWireFormat/openwire/marshal/v5/ActiveMQS
4499 4290

src/main/activemq/wireformat/openwire/marshaller/v4/MisageMarshallerFormat/openwire/marshal/v5/ActiveMQT
4505 4296

src/main/activemq/wireformat/openwire/marshaller/v4/MisagePushMarshaller.dat/openwire/marshal/v5/ActiveMQT
4511 4302

src/main/activemq/wireformat/openwire/marshaller/v4/NetworkBridgeFilterMarshaller/openwire/marshal/v5/ActiveMQT
4517 4308

src/main/activemq/wireformat/openwire/marshaller/v4/PartialCommandMarshaller/openwire/marshal/v5/ActiveMQT
4523 4314

src/main/activemq/wireformat/openwire/marshaller/v4/PingActiveMarshaller.dat/openwire/marshal/v5/ActiveMQT
4529 4320

src/main/activemq/wireformat/openwire/marshaller/v5/BaseActiveAndMarshalHeader/openwire/marshaller/v5/MessageDis	4326	4488
src/main/activemq/wireformat/openwire/marshaller/v5/BrokerIdMarshaller/openwire/marshaller/v5/MessageDis	4332	4494
src/main/activemq/wireformat/openwire/marshaller/v5/BrokerInfoMarshaller/openwire/marshaller/v5/MessageDis	4338	4500
src/main/activemq/wireformat/openwire/marshaller/v5/ConnectiveControlMarshaller/openwire/marshaller/v5/MessageMa	4344	4506
src/main/activemq/wireformat/openwire/marshaller/v5/ConnectiveErrorMarshaller/openwire/marshaller/v5/MessagePul	4350	4512
src/main/activemq/wireformat/openwire/marshaller/v5/ConnectiveIdMarshaller/openwire/marshaller/v5/NetworkBri	4356	4518
src/main/activemq/wireformat/openwire/marshaller/v5/ConnectiveInfoMarshaller/openwire/marshaller/v5/PartialCom	4362	4524
src/main/activemq/wireformat/openwire/marshaller/v5/ConsumerGroupWireFormat/openwire/marshaller/v5/ProducerAc	4368	4530
src/main/activemq/wireformat/openwire/marshaller/v5/ConsumerIdMarshaller/openwire/marshaller/v5/ProducerId	4374	4536
src/main/activemq/wireformat/openwire/marshaller/v5/ConsumerInfoMarshaller/openwire/marshaller/v5/ProducerInf	4380	4542
src/main/activemq/wireformat/openwire/marshaller/v5/ControlCommandWireFormat/openwire/marshaller/v5/RemoveInfo	4386	4548
src/main/activemq/wireformat/openwire/marshaller/v5/DataActiveResponseMarshaller/openwire/marshaller/v5/RemoveSub	4392	4554
src/main/activemq/wireformat/openwire/marshaller/v5/DataResponseMarshaller/openwire/marshaller/v5/ReplayCom	4398	4560
src/main/activemq/wireformat/openwire/marshaller/v5/DeactivatedInfoMarshaller/openwire/marshaller/v5/ResponseM	4404	4566
src/main/activemq/wireformat/openwire/marshaller/v5/DiscardEmptyWireFormat/openwire/marshaller/v5/SessionIdM	4410	4572
src/main/activemq/wireformat/openwire/marshaller/v5/ExceptionResponseMarshaller/openwire/marshaller/v5/SessionInfo	4416	4578
src/main/activemq/wireformat/openwire/marshaller/v5/FlushActiveMQWireFormat/openwire/marshaller/v5/ShutDownIn	4422	4584
src/main/activemq/wireformat/openwire/marshaller/v5/InActiveResponseMarshaller/openwire/marshaller/v5/Subscription	4428	4590
src/main/activemq/wireformat/openwire/marshaller/v5/MainActiveQueueAckMarshaller/openwire/marshaller/v5/Transaction	4434	4596
src/main/activemq/wireformat/openwire/marshaller/v5/MainActiveTopicAckMarshaller/openwire/marshaller/v5/Transaction	4440	4602
src/main/activemq/wireformat/openwire/marshaller/v5/MainActiveTransMarshaller/openwire/marshaller/v5/WireFormat	4446	4608
src/main/activemq/wireformat/openwire/marshaller/v5/MainActiveTransWireMarshaller/openwire/marshaller/v5/XATransact	4452	4614
src/main/activemq/wireformat/openwire/marshaller/v5/MainActiveInfoMarshaller/openwire/marshaller/v6/ActiveMQB	4458	4249
src/main/activemq/wireformat/openwire/marshaller/v5/MainPartialQueueWireMarshaller/openwire/marshaller/v6/ActiveMQB	4464	4255
src/main/activemq/wireformat/openwire/marshaller/v5/MainTransQueueIdMarshaller/openwire/marshaller/v6/ActiveMQD	4470	4261
src/main/activemq/wireformat/openwire/marshaller/v5/MarshallerFactory/openwire/marshaller/v6/ActiveMQM	4476	4267
src/main/activemq/wireformat/openwire/marshaller/v5/MessageAckMarshaller/openwire/marshaller/v6/ActiveMQM	4482	4273

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQObjectMessageMarshaller/openwire/marshaller/v6/JournalTopic
4279 4441

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQQueueMessageMarshaller/openwire/marshaller/v6/JournalTopic
4285 4447

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQSimpleMessageMarshaller/openwire/marshaller/v6/JournalTopic
4291 4453

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQTempDestinationMarshaller/openwire/marshaller/v6/KeepAliveIn
4297 4459

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQTempQueueMarshaller/openwire/marshaller/v6/LastPartial
4303 4465

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQTempTopicMarshaller/openwire/marshaller/v6/LocalTrans
4309 4471

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQTextMessageMarshaller/openwire/marshaller/v6/MarshallerF
4315 4477

src/main/activemq/wireformat/openwire/marshaller/v6/ActiveMQTopicMarshaller/openwire/marshaller/v6/MessageAck
4321 4483

src/main/activemq/wireformat/openwire/marshaller/v6/BaseActiveMQMarshaller/openwire/marshaller/v6/MessageDis
4327 4489

src/main/activemq/wireformat/openwire/marshaller/v6/BrokerIdMarshaller/openwire/marshaller/v6/MessageDis
4333 4495

src/main/activemq/wireformat/openwire/marshaller/v6/BrokerIdMessageMarshaller/openwire/marshaller/v6/MessageIdM
4339 4501

src/main/activemq/wireformat/openwire/marshaller/v6/ConnectionControlMarshaller/openwire/marshaller/v6/MessageMa
4345 4507

src/main/activemq/wireformat/openwire/marshaller/v6/ConnectionErrorMarshaller/openwire/marshaller/v6/MessagePul
4351 4513

src/main/activemq/wireformat/openwire/marshaller/v6/ConnectionIdMarshaller/openwire/marshaller/v6/NetworkBri
4357 4519

src/main/activemq/wireformat/openwire/marshaller/v6/ConnectionInfoMarshaller/openwire/marshaller/v6/PartialCom
4363 4525

src/main/activemq/wireformat/openwire/marshaller/v6/ConsumerGroupMarshaller/openwire/marshaller/v6/ProducerAc
4369 4531

src/main/activemq/wireformat/openwire/marshaller/v6/ConsumerIdMarshaller/openwire/marshaller/v6/ProducerId
4375 4537

src/main/activemq/wireformat/openwire/marshaller/v6/ConsumerInfoMarshaller/openwire/marshaller/v6/ProducerInf
4381 4543

src/main/activemq/wireformat/openwire/marshaller/v6/DefaultCommandMarshaller/openwire/marshaller/v6/RemoveInfo
4387 4549

src/main/activemq/wireformat/openwire/marshaller/v6/DataActiveResponseMarshaller/openwire/marshaller/v6/RemoveSub
4393 4555

src/main/activemq/wireformat/openwire/marshaller/v6/DataResponseMarshaller/openwire/marshaller/v6/ReplayCom
4399 4561

src/main/activemq/wireformat/openwire/marshaller/v6/DestinationInfoMarshaller/openwire/marshaller/v6/ResponseM
4405 4567

src/main/activemq/wireformat/openwire/marshaller/v6/DisconnectErrorMarshaller/openwire/marshaller/v6/SessionIdM
4411 4573

src/main/activemq/wireformat/openwire/marshaller/v6/ExceptionResponseMarshaller/openwire/marshaller/v6/SessionInfo
4417 4579

src/main/activemq/wireformat/openwire/marshaller/v6/FlushCommandMarshaller/openwire/marshaller/v6/Shut downIn
4423 4585

src/main/activemq/wireformat/openwire/marshaller/v6/LargeResponseMarshaller/openwire/marshaller/v6/Subscription
4429 4591

src/main/activemq/wireformat/openwire/marshaller/v6/LocalQueueAckMarshaller/openwire/marshaller/v6/Transaction
4435 4597

- src/main/activemq/wireformat/openwire/marshaller/InvalidDestinationException.h, 4603
- src/main/activemq/wireformat/openwire/marshaller/InvalidSelectorException.h, 4609
- src/main/activemq/wireformat/openwire/marshaller/InvalidTransactionIdException.h, 4615
- src/main/activemq/wireformat/openwire/OpenWireFormat.h, 4616
- src/main/activemq/wireformat/openwire/OpenWireFormatFactory.h, 4617
- src/main/activemq/wireformat/openwire/OpenWireFormatNegotiator.h, 4618
- src/main/activemq/wireformat/openwire/OpenWireResponseBuilder.h, 4619
- src/main/activemq/wireformat/openwire/OutputStream.h, 4620
- src/main/activemq/wireformat/openwire/Utils/HexTable.h, 4621
- src/main/activemq/wireformat/openwire/Utils/MessagePropertyInterceptor.h, 4622
- src/main/activemq/wireformat/stomp/StompCommandConstants.h, 4623
- src/main/activemq/wireformat/stomp/StompFrame.h, 4624
- src/main/activemq/wireformat/stomp/StompHelper.h, 4625
- src/main/activemq/wireformat/stomp/StompWireFormat.h, 4626
- src/main/activemq/wireformat/stomp/StompWireFormatFactory.h, 4627
- src/main/activemq/wireformat/WireFormat.h, 4628
- src/main/activemq/wireformat/WireFormatFactory.h, 4629
- src/main/activemq/wireformat/WireFormatNegotiator.h, 4630
- src/main/activemq/wireformat/WireFormatRegistry.h, 4631
- src/main/cms/BytesMessage.h, 4632
- src/main/cms/Closeable.h, 4633
- src/main/cms/CMSException.h, 4635
- src/main/cms/CMSPProperties.h, 4636
- src/main/cms/CMSSecurityException.h, 4637
- src/main/cms/Config.h, 4228
- src/main/cms/Connection.h, 4638
- src/main/cms/ConnectionFactory.h, 4639
- src/main/cms/ConnectionMetaData.h, 4640
- src/main/cms/DeliveryMode.h, 4641
- src/main/cms/Destination.h, 4642
- src/main/cms/ExceptionListener.h, 4643
- src/main/cms/IllegalStateException.h, 4644
- src/main/cms/InvalidClientIdException.h, 4646
- src/main/cms/InvalidDestinationException.h, 4647
- src/main/cms/InvalidSelectorException.h, 4648
- src/main/cms/MapMessage.h, 4649
- src/main/cms/Message.h, 4650
- src/main/cms/MessageConsumer.h, 4650
- src/main/cms/MessageEnumeration.h, 4651
- src/main/cms/MessageEOFException.h, 4652
- src/main/cms/MessageFormatException.h, 4653
- src/main/cms/MessageListener.h, 4654
- src/main/cms/MessageNotReadableException.h, 4655
- src/main/cms/MessageNotWriteableException.h, 4656
- src/main/cms/MessageProducer.h, 4657
- src/main/cms/ObjectMessage.h, 4658
- src/main/cms/Queue.h, 4659
- src/main/cms/QueueBrowser.h, 4661
- src/main/cms/Session.h, 4662
- src/main/cms/Startable.h, 4663
- src/main/cms/Stopable.h, 4664
- src/main/cms/StreamMessage.h, 4665
- src/main/cms/TemporaryQueue.h, 4666
- src/main/cms/TemporaryTopic.h, 4667
- src/main/cms/TextMessage.h, 4668
- src/main/cms/Topic.h, 4669
- src/main/cms/UnsupportedOperationException.h, 4670
- src/main/decaf/internal/AprPool.h, 4672
- src/main/decaf/internal/DecafRuntime.h, 4673
- src/main/decaf/internal/io/StandardErrorOutputStream.h, 4674
- src/main/decaf/internal/io/StandardInputStream.h, 4675
- src/main/decaf/internal/io/StandardOutputStream.h, 4676
- src/main/decaf/internal/net/DefaultServerSocketFactory.h, 4677
- src/main/decaf/internal/net/DefaultSocketFactory.h, 4678
- src/main/decaf/internal/net/Network.h, 4679
- src/main/decaf/internal/net/SocketFileDescriptor.h, 4680
- src/main/decaf/internal/net/ssl/DefaultSSLContext.h, 4681
- src/main/decaf/internal/net/ssl/DefaultSSLServerSocketFactory.h, 4682
- src/main/decaf/internal/net/ssl/DefaultSSLSocketFactory.h, 4683
- src/main/decaf/internal/net/ssl/openssl/OpenSSLContextSpi.h, 4684
- src/main/decaf/internal/net/ssl/openssl/OpenSSLParameters.h, 4685

src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h, 4686
 src/main/decaf/internal/net/ssl/openssl/OpenSSLServerSocketFactory.h, 4687
 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h, 4688
 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h, 4689
 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h, 4690
 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h, 4691
 src/main/decaf/internal/net/ssl/openssl/OpenSSLSocketFactory.h, 4692
 src/main/decaf/internal/net/tcp/TcpSocket.h, 4693
 src/main/decaf/internal/net/tcp/TcpSocketInputStream.h, 4694
 src/main/decaf/internal/net/tcp/TcpSocketOutputStream.h, 4695
 src/main/decaf/internal/net/URIEncoderDecoder.h, 4696
 src/main/decaf/internal/net/URIHelper.h, 4697
 src/main/decaf/internal/net/URIType.h, 4698
 src/main/decaf/internal/nio/BufferFactory.h, 4699
 src/main/decaf/internal/nio/ByteBuffer.h, 4700
 src/main/decaf/internal/nio/CharArrayBuffer.h, 4701
 src/main/decaf/internal/nio/DoubleArrayBuffer.h, 4702
 src/main/decaf/internal/nio/FloatArrayBuffer.h, 4703
 src/main/decaf/internal/nio/IntArrayBuffer.h, 4704
 src/main/decaf/internal/nio/LongArrayBuffer.h, 4705
 src/main/decaf/internal/nio/ShortArrayBuffer.h, 4706
 src/main/decaf/internal/security/unix/SecureRandomImpl.h, 4707
 src/main/decaf/internal/security/windows/SecureRandomImpl.h, 4708
 src/main/decaf/internal/util/ByteArrayAdapter.h, 4709
 src/main/decaf/internal/util/concurrent/ConditionImpl.h, 4710
 src/main/decaf/internal/util/concurrent/MutexImpl.h, 4711
 src/main/decaf/internal/util/concurrent/SynchronousQueueImpl.h, 4712
 src/main/decaf/internal/util/concurrent/TransferQueueImpl.h, 4713
 src/main/decaf/internal/util/concurrent/TransferQueue.h, 4714
 src/main/decaf/internal/util/concurrent/TransferStack.h, 4715
 src/main/decaf/internal/util/concurrent/unix/ConditionHandle.h, 4716
 src/main/decaf/internal/util/concurrent/unix/MutexHandle.h, 4717
 src/main/decaf/internal/util/concurrent/windows/ConditionHandle.h, 4718
 src/main/decaf/internal/util/concurrent/windows/MutexHandle.h, 4719
 src/main/decaf/internal/util/GenericResource.h, 4720
 src/main/decaf/internal/util/HexStringParser.h, 4721
 src/main/decaf/internal/util/Resource.h, 4722
 src/main/decaf/internal/util/ResourceLifecycleManager.h, 4723
 src/main/decaf/internal/util/TimerTaskHeap.h, 4724
 src/main/decaf/internal/util/zip/crc32.h, 4725
 src/main/decaf/internal/util/zip/deflate.h, 4726
 src/main/decaf/internal/util/zip/gzguts.h, 4727
 src/main/decaf/internal/util/zip/infast.h, 4728
 src/main/decaf/internal/util/zip/infix.h, 4729
 src/main/decaf/internal/util/zip/inflate.h, 4730
 src/main/decaf/internal/util/zip/inftrees.h, 4731
 src/main/decaf/internal/util/zip/trees.h, 4732
 src/main/decaf/internal/util/zip/zconf.h, 4733
 src/main/decaf/internal/util/zip/zlib.h, 4734
 src/main/decaf/internal/util/zip/zutil.h, 4735
 src/main/decaf/io/BlockingByteArrayInputStream.h, 4736
 src/main/decaf/io/BufferedInputStream.h, 4737
 src/main/decaf/io/BufferedOutputStream.h, 4738
 src/main/decaf/io/ByteArrayInputStream.h, 4739
 src/main/decaf/io/ByteArrayOutputStream.h, 4740
 src/main/decaf/io/Closeable.h, 4741
 src/main/decaf/io/DataInput.h, 4742
 src/main/decaf/io/DataInputStream.h, 4743
 src/main/decaf/io/DataOutput.h, 4744
 src/main/decaf/io/DataOutputStream.h, 4745

- src/main/decaf/io/EOFException.h, 4755
- src/main/decaf/io/FileDescriptor.h, 4756
- src/main/decaf/io/FilterInputStream.h, 4757
- src/main/decaf/io/FilterOutputStream.h, 4758
- src/main/decaf/io/Flushable.h, 4759
- src/main/decaf/io/InputStream.h, 4760
- src/main/decaf/io/InputStreamReader.h, 4761
- src/main/decaf/io/InterruptedIOException.h, 4762
- src/main/decaf/io/IOException.h, 4763
- src/main/decaf/io/OutputStream.h, 4764
- src/main/decaf/io/OutputStreamWriter.h, 4765
- src/main/decaf/io/PushbackInputStream.h, 4766
- src/main/decaf/io/Reader.h, 4767
- src/main/decaf/io/UnsupportedEncodingException.h, 4768
- src/main/decaf/io/UTFDataFormatException.h, 4769
- src/main/decaf/io/Writer.h, 4770
- src/main/decaf/lang/Appendable.h, 4771
- src/main/decaf/lang/ArrayPointer.h, 4772
- src/main/decaf/lang/Boolean.h, 4774
- src/main/decaf/lang/Byte.h, 4775
- src/main/decaf/lang/Character.h, 4776
- src/main/decaf/lang/CharSequence.h, 4777
- src/main/decaf/lang/Comparable.h, 4778
- src/main/decaf/lang/Double.h, 4779
- src/main/decaf/lang/Exception.h, 4780
- src/main/decaf/lang/exceptions/ClassCastException.h, 4781
- src/main/decaf/lang/exceptions/ExceptionDefines.h, 4782
- src/main/decaf/lang/exceptions/IllegalArgumentExcepion.h, 4783
- src/main/decaf/lang/exceptions/IllegalMonitorStateException.h, 4784
- src/main/decaf/lang/exceptions/IllegalStateException.h, 4785
- src/main/decaf/lang/exceptions/IllegalThreadStateException.h, 4786
- src/main/decaf/lang/exceptions/IndexOutOfBoundsException.h, 4787
- src/main/decaf/lang/exceptions/InterruptedExcepion.h, 4788
- src/main/decaf/lang/exceptions/InvalidStateException.h, 4789
- src/main/decaf/lang/exceptions/NoSuchElementException.h, 4790
- src/main/decaf/lang/exceptions/NullPointerException.h, 4791
- src/main/decaf/lang/exceptions/RuntimeException.h, 4792
- src/main/decaf/lang/exceptions/UnsupportedOperationException.h, 4793
- src/main/decaf/lang/Float.h, 4794
- src/main/decaf/lang/Integer.h, 4795
- src/main/decaf/lang/Iterable.h, 4796
- src/main/decaf/lang/Long.h, 4797
- src/main/decaf/lang/Math.h, 4798
- src/main/decaf/lang/Number.h, 4799
- src/main/decaf/lang/Pointer.h, 4800
- src/main/decaf/lang/Readable.h, 4801
- src/main/decaf/lang/Runnable.h, 4802
- src/main/decaf/lang/Runtime.h, 4803
- src/main/decaf/lang/Short.h, 4804
- src/main/decaf/lang/String.h, 4805
- src/main/decaf/lang/System.h, 4806
- src/main/decaf/lang/Thread.h, 4807
- src/main/decaf/lang/ThreadGroup.h, 4808
- src/main/decaf/lang/Throwable.h, 4809
- src/main/decaf/net/BindException.h, 4810
- src/main/decaf/net/ConnectException.h, 4811
- src/main/decaf/net/HttpRetryException.h, 4812
- src/main/decaf/net/Inet4Address.h, 4813
- src/main/decaf/net/Inet6Address.h, 4814
- src/main/decaf/net/InetAddress.h, 4815
- src/main/decaf/net/InetSocketAddress.h, 4816
- src/main/decaf/net/MalformedURLException.h, 4817
- src/main/decaf/net/NoRouteToHostException.h, 4818
- src/main/decaf/net/PortUnreachableException.h, 4819
- src/main/decaf/net/ProtocolException.h, 4820
- src/main/decaf/net/ServerSocket.h, 4821
- src/main/decaf/net/ServerSocketFactory.h, 4822
- src/main/decaf/net/Socket.h, 4823
- src/main/decaf/net/SocketAddress.h, 4824
- src/main/decaf/net/SocketError.h, 4825
- src/main/decaf/net/SocketException.h, 4826
- src/main/decaf/net/SocketFactory.h, 4827
- src/main/decaf/net/SocketImpl.h, 4828
- src/main/decaf/net/SocketImplFactory.h, 4829
- src/main/decaf/net/SocketOptions.h, 4830
- src/main/decaf/net/SocketTimeoutException.h, 4831
- src/main/decaf/net/ssl/SSLContext.h, 4832
- src/main/decaf/net/ssl/SSLContextSpi.h, 4833
- src/main/decaf/net/ssl/SSLParameters.h, 4834
- src/main/decaf/net/ssl/SSLServerSocket.h, 4835

- src/main/decaf/net/ssl/SSLServerSocketFactory.h, 4834
- src/main/decaf/net/ssl/SSLSocket.h, 4835
- src/main/decaf/net/ssl/SSLSocketFactory.h, 4836
- src/main/decaf/net/UnknownHostException.h, 4837
- src/main/decaf/net/UnknownServiceException.h, 4838
- src/main/decaf/net/URI.h, 4839
- src/main/decaf/net/URISyntaxException.h, 4840
- src/main/decaf/net/URL.h, 4841
- src/main/decaf/net/URLDecoder.h, 4842
- src/main/decaf/net/URLEncoder.h, 4843
- src/main/decaf/nio/Buffer.h, 4844
- src/main/decaf/nio/BufferOverflowException.h, 4845
- src/main/decaf/nio/BufferUnderflowException.h, 4846
- src/main/decaf/nio/ByteBuffer.h, 4847
- src/main/decaf/nio/CharBuffer.h, 4848
- src/main/decaf/nio/DoubleBuffer.h, 4849
- src/main/decaf/nio/FloatBuffer.h, 4850
- src/main/decaf/nio/IntBuffer.h, 4851
- src/main/decaf/nio/InvalidMarkException.h, 4852
- src/main/decaf/nio/LongBuffer.h, 4853
- src/main/decaf/nio/ReadOnlyBufferException.h, 4854
- src/main/decaf/nio/ShortBuffer.h, 4855
- src/main/decaf/security/auth/x500/X500Principal.h, 4856
- src/main/decaf/security/cert/Certificate.h, 4857
- src/main/decaf/security/cert/CertificateEncodingException.h, 4858
- src/main/decaf/security/cert/CertificateException.h, 4859
- src/main/decaf/security/cert/CertificateExpiredException.h, 4860
- src/main/decaf/security/cert/CertificateNotYetValidException.h, 4861
- src/main/decaf/security/cert/CertificateParsingException.h, 4862
- src/main/decaf/security/cert/X509Certificate.h, 4863
- src/main/decaf/security/GeneralSecurityException.h, 4864
- src/main/decaf/security/InvalidKeyException.h, 4865
- src/main/decaf/security/Key.h, 4866
- src/main/decaf/security/KeyException.h, 4867
- src/main/decaf/security/KeyManagementException.h, 4868
- src/main/decaf/security/NoSuchAlgorithmException.h, 4869
- src/main/decaf/security/NoSuchProviderException.h, 4870
- src/main/decaf/security/Principal.h, 4871
- src/main/decaf/security/PublicKey.h, 4872
- src/main/decaf/security/SecureRandom.h, 4873
- src/main/decaf/security/SecureRandomSpi.h, 4874
- src/main/decaf/security/SignatureException.h, 4875
- src/main/decaf/util/AbstractCollection.h, 4876
- src/main/decaf/util/AbstractList.h, 4877
- src/main/decaf/util/AbstractMap.h, 4878
- src/main/decaf/util/AbstractQueue.h, 4879
- src/main/decaf/util/AbstractSequentialList.h, 4880
- src/main/decaf/util/AbstractSet.h, 4881
- src/main/decaf/util/Collection.h, 4882
- src/main/decaf/util/Comparator.h, 4883
- src/main/decaf/util/comparators/Less.h, 4884
- src/main/decaf/util/concurrent/atomic/AtomicBoolean.h, 4885
- src/main/decaf/util/concurrent/atomic/AtomicInteger.h, 4886
- src/main/decaf/util/concurrent/atomic/AtomicRefCounter.h, 4887
- src/main/decaf/util/concurrent/atomic/AtomicReference.h, 4888
- src/main/decaf/util/concurrent/BlockingQueue.h, 4889
- src/main/decaf/util/concurrent/BrokenBarrierException.h, 4890
- src/main/decaf/util/concurrent/Callable.h, 4891
- src/main/decaf/util/concurrent/CancellationException.h, 4892
- src/main/decaf/util/concurrent/Concurrent.h, 4893
- src/main/decaf/util/concurrent/ConcurrentMap.h, 4894
- src/main/decaf/util/concurrent/ConcurrentStlMap.h, 4895
- src/main/decaf/util/concurrent/CountDownLatch.h, 4896
- src/main/decaf/util/concurrent/Delayed.h, 4897
- src/main/decaf/util/concurrent/ExecutionException.h, 4898
- src/main/decaf/util/concurrent/Executor.h, 4899

- src/main/decaf/util/concurrent/ExecutorService.h, 4900
- src/main/decaf/util/concurrent/Future.h, 4901
- src/main/decaf/util/concurrent/Lock.h, 4902
- src/main/decaf/util/concurrent/locks/Condition.h, 4904
- src/main/decaf/util/concurrent/locks/Lock.h, 4903
- src/main/decaf/util/concurrent/locks/LockSupport.h, 4905
- src/main/decaf/util/concurrent/locks/ReadWriteLock.h, 4906
- src/main/decaf/util/concurrent/locks/ReentrantLock.h, 4907
- src/main/decaf/util/concurrent/Mutex.h, 4908
- src/main/decaf/util/concurrent/PooledThread.h, 4909
- src/main/decaf/util/concurrent/PooledThreadListener.h, 4910
- src/main/decaf/util/concurrent/RejectedExecutionException.h, 4911
- src/main/decaf/util/concurrent/RejectedExecutionHandler.h, 4912
- src/main/decaf/util/concurrent/Semaphore.h, 4913
- src/main/decaf/util/concurrent/Synchronizable.h, 4914
- src/main/decaf/util/concurrent/SynchronousQueue.h, 4915
- src/main/decaf/util/concurrent/TaskListener.h, 4916
- src/main/decaf/util/concurrent/ThreadFactory.h, 4917
- src/main/decaf/util/concurrent/ThreadPool.h, 4918
- src/main/decaf/util/concurrent/TimeoutException.h, 4919
- src/main/decaf/util/concurrent/TimeUnit.h, 4920
- src/main/decaf/util/Config.h, 4229
- src/main/decaf/util/Date.h, 4921
- src/main/decaf/util/Iterator.h, 4922
- src/main/decaf/util/List.h, 4923
- src/main/decaf/util/ListIterator.h, 4924
- src/main/decaf/util/logging/ConsoleHandler.h, 4925
- src/main/decaf/util/logging/EventManager.h, 4926
- src/main/decaf/util/logging/Filter.h, 4927
- src/main/decaf/util/logging/Formatter.h, 4928
- src/main/decaf/util/logging/Handler.h, 4929
- src/main/decaf/util/logging/Level.h, 4930
- src/main/decaf/util/logging/Logger.h, 4931
- src/main/decaf/util/logging/LoggerCommon.h, 4932
- src/main/decaf/util/logging/LoggerDefines.h, 4933
- src/main/decaf/util/logging/LoggerHierarchy.h, 4935
- src/main/decaf/util/logging/LogManager.h, 4936
- src/main/decaf/util/logging/LogRecord.h, 4937
- src/main/decaf/util/logging/LogWriter.h, 4938
- src/main/decaf/util/logging/MarkBlockLogger.h, 4939
- src/main/decaf/util/logging/PropertiesChangeListener.h, 4940
- src/main/decaf/util/logging/SimpleFormatter.h, 4941
- src/main/decaf/util/logging/SimpleLogger.h, 4942
- src/main/decaf/util/logging/StreamHandler.h, 4943
- src/main/decaf/util/logging/XMLFormatter.h, 4944
- src/main/decaf/util/Map.h, 4945
- src/main/decaf/util/PriorityQueue.h, 4946
- src/main/decaf/util/Properties.h, 4947
- src/main/decaf/util/Queue.h, 4660
- src/main/decaf/util/Random.h, 4948
- src/main/decaf/util/Set.h, 4949
- src/main/decaf/util/StlList.h, 4950
- src/main/decaf/util/StlMap.h, 4951
- src/main/decaf/util/StlQueue.h, 4952
- src/main/decaf/util/StlSet.h, 4953
- src/main/decaf/util/StringTokenizer.h, 4954
- src/main/decaf/util/Timer.h, 4955
- src/main/decaf/util/TimerTask.h, 4956
- src/main/decaf/util/UUID.h, 4957
- src/main/decaf/util/zip/Adler32.h, 4958
- src/main/decaf/util/zip/CheckedInputStream.h, 4959
- src/main/decaf/util/zip/CheckedOutputStream.h, 4960
- src/main/decaf/util/zip/Checksum.h, 4961
- src/main/decaf/util/zip/CRC32.h, 4962
- src/main/decaf/util/zip/DataFormatException.h, 4963
- src/main/decaf/util/zip/Deflater.h, 4964
- src/main/decaf/util/zip/DeflaterOutputStream.h, 4965
- src/main/decaf/util/zip/Inflater.h, 4966
- src/main/decaf/util/zip/InflaterInputStream.h, 4967
- src/main/decaf/util/zip/ZipException.h, 4968
- SSLContext

- decaf::net::ssl::SSLContext, 3545
- SSLParameters
 - decaf::net::ssl::SSLParameters, 3551, 3552
- SSLServerSocket
 - decaf::net::ssl::SSLServerSocket, 3555, 3556
- SSLServerSocketFactory
 - decaf::net::ssl::SSLServerSocketFactory, 3561
- SSLSocket
 - decaf::net::ssl::SSLSocket, 3564, 3565
- SSLSocketFactory
 - decaf::net::ssl::SSLSocketFactory, 3572
- SslTransport
 - activemq::transport::tcp::SslTransport, 3574
- stackTrace
 - decaf::lang::Exception, 1837
- StandardErrorOutputStream
 - decaf::internal::io::StandardErrorOutputStream, 3580
- StandardInputStream
 - decaf::internal::io::StandardInputStream, 3582
- StandardOutputStream
 - decaf::internal::io::StandardOutputStream, 3584
- start
 - activemq::commands::ConsumerControl, 1405
 - activemq::core::ActiveMQConnection, 290
 - activemq::core::ActiveMQConsumer, 318
 - activemq::core::ActiveMQSession, 531
 - activemq::core::ActiveMQSessionExecutor, 535
 - activemq::core::MessageDispatchChannel, 2603
 - activemq::transport::correlator::ResponseCorrelator, 3294
 - activemq::transport::failover::FailoverTransport, 1884
 - activemq::transport::IOTransport, 2150
 - activemq::transport::mock::MockTransport, 2777
 - activemq::transport::Transport, 3888
 - activemq::transport::TransportFilter, 3897
 - activemq::wireformat::openwire::OpenWireFormat, 2904
 - cms::Startable, 3586
 - decaf::lang::Thread, 3772
 - gz_state, 1977
- startHandshake
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2869
 - decaf::net::ssl::SSLSocket, 3570
- stat_desc
 - tree_desc_s, 3905
- State
 - decaf::lang::Thread, 3768
- state
 - z_stream_s, 4062
- static_dtree
 - trees.h, 4736
- static_len
 - internal_state, 2120
- static_ltree
 - trees.h, 4736
- static_tree_desc
 - deflate.h, 4727
- STATIC_TREES
 - zutil.h, 4745
- staticCast
 - decaf::lang::Pointer, 2952
- StaticInitializer
 - activemq::core::ActiveMQConstants::StaticInitializer, 3588
- status
 - internal_state, 2120
- std, 178
- std::binary_function, 835
- std::less< decaf::lang::ArrayPointer< T > >, 2330
 - operator(), 2330
- std::less< decaf::lang::Pointer< T > >, 2331
 - operator(), 2331
- StlList
 - decaf::util::StlList, 3593, 3594
- StlMap
 - decaf::util::StlMap, 3605, 3606
- StlQueue
 - decaf::util::StlQueue, 3617
- StlSet
 - decaf::util::StlSet, 3625
- StompFrame
 - activemq::wireformat::stomp::StompFrame, 3634
- StompHelper
 - activemq::wireformat::stomp::StompHelper, 3639
- StompWireFormat
 - activemq::wireformat::stomp::StompWireFormat, 3644
- StompWireFormatFactory
 - activemq::wireformat::stomp::StompWireFormatFactory, 3647
- stop
 - activemq::commands::ConsumerControl, 1405
 - activemq::core::ActiveMQConnection, 290

- activemq::core::ActiveMQConsumer, 318
- activemq::core::ActiveMQSession, 531
- activemq::core::ActiveMQSessionExecutor, 535
- activemq::core::MessageDispatchChannel, 2603
- activemq::transport::failover::FailoverTransport, 1884
- activemq::transport::IOTransport, 2151
- activemq::transport::mock::MockTransport, 2777
- activemq::transport::Transport, 3888
- activemq::transport::TransportFilter, 3898
- cms::Stoppable, 3648
- decaf::util::concurrent::PooledThread, 2969
- store
 - decaf::util::Properties, 3132, 3133
- STORED
 - inflate.h, 4733
- STORED_BLOCK
 - zutil.h, 4745
- strategy
 - gz_state, 1977
 - internal_state, 2120
- StreamHandler
 - decaf::util::logging::StreamHandler, 3650
- String
 - decaf::lang::String, 3666
- STRING_TYPE
 - activemq::util::PrimitiveValueNode, 3016
- StringTokenizer
 - decaf::util::StringTokenizer, 3668
- stringValue
 - activemq::util::PrimitiveValueNode::PrimitiveValueNode, 3009
- strm
 - gz_state, 1977
 - internal_state, 2120
- strstart
 - internal_state, 2120
- subscriptionName
 - activemq::commands::RemoveSubscriptionInfo, 3226
 - activemq::commands::SubscriptionInfo, 3675
- SUBSCRIBE
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- subscribedDestination
 - activemq::commands::SubscriptionInfo, 3675
- SubscriptionInfo
 - activemq::commands::SubscriptionInfo, 3672
- SubscriptionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::SubscriptionInfo, 3681
 - activemq::wireformat::openwire::marshal::v2::SubscriptionInfo, 3697
 - activemq::wireformat::openwire::marshal::v3::SubscriptionInfo, 3677
 - activemq::wireformat::openwire::marshal::v4::SubscriptionInfo, 3689
 - activemq::wireformat::openwire::marshal::v5::SubscriptionInfo, 3685
 - activemq::wireformat::openwire::marshal::v6::SubscriptionInfo, 3693
- subscriptionName
 - activemq::commands::ConsumerInfo, 1466
- subscriptionName
 - activemq::commands::JournalTopicAck, 2187
- subSequence
 - decaf::internal::nio::CharArrayBuffer, 1117
 - decaf::lang::CharSequence, 1136
 - decaf::lang::String, 3667
 - decaf::nio::CharBuffer, 1132
- supportsUrgentData
 - decaf::net::SocketImpl, 3536
- suspend
 - activemq::commands::ConnectionControl, 1271
- swap
 - decaf::lang::ArrayPointer, 736
 - decaf::lang::Pointer, 2952
 - decaf::util::concurrent::atomic::AtomicRefCounter, 748
- sync
 - inflate.h, 4733
- sync
 - decaf::io::FileDescriptor, 1892
- SynchronizableImpl
 - decaf::internal::util::concurrent::SynchronizableImpl, 3712
- synchronized
 - Concurrent.h, 4893
- SynchronousQueue
 - decaf::util::concurrent::SynchronousQueue, 3718
- syncRequest
 - activemq::core::ActiveMQConnection, 290
 - activemq::core::ActiveMQSession, 531
- System
 - decaf::lang::System, 3728
- TABLE
 - inflate.h, 4733
- take

- decaf::util::concurrent::BlockingQueue, 848
- decaf::util::concurrent::SynchronousQueue, 3724
- takeSession
 - activemq::cmsutil::SessionPool, 3436
- targetConsumerId
 - activemq::commands::Message, 2532
- Task
 - decaf::util::concurrent::ThreadPool, 3779
- TcpSocket
 - decaf::internal::net::tcp::TcpSocket, 3741
- TcpSocketInputStream
 - decaf::internal::net::tcp::TcpSocketInputStream, 3748
- TcpSocketOutputStream
 - decaf::internal::net::tcp::TcpSocketOutputStream, 3750
- TcpTransport
 - activemq::transport::tcp::TcpTransport, 3753
- TEMP_POSTFIX
 - activemq::commands::ActiveMQDestination, 332
- TEMP_PREFIX
 - activemq::commands::ActiveMQDestination, 332
- TEMP_QUEUE_QUALIFIED_PREFIX
 - activemq::commands::ActiveMQDestination, 332
- TEMP_TOPIC_QUALIFIED_PREFIX
 - activemq::commands::ActiveMQDestination, 332
- TEMPORARY_QUEUE
 - cms::Destination, 1723
- TEMPORARY_TOPIC
 - cms::Destination, 1723
- TEMPQUEUE_PREFIX
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- TEMPTOPIC_PREFIX
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- TERMINATED
 - decaf::lang::Thread, 3768
- TEXT
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- text
 - activemq::commands::ActiveMQTextMessage, 666
 - gz_header_s, 1975
- Thread
 - decaf::lang::Thread, 3768
- ThreadGroup
 - decaf::lang::ThreadGroup, 3776
- ThreadPool
 - decaf::util::concurrent::ThreadPool, 3779
- Throwable
 - decaf::lang::Throwable, 3784
- Throwing
 - decaf::util::logging, 176
- throwing
 - decaf::util::logging::Logger, 2396
- tightMarshal
 - activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 819
 - activemq::wireformat::openwire::marshal::DataStreamMarshaller, 1638
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMarshaller, 215
 - activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMarshaller, 255
 - activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller, 339
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMapMarshaller, 380
 - activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller, 407
 - activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMarshaller, 452
 - activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller, 497
 - activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMarshaller, 558
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller, 586
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller, 615
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller, 648
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTextMarshaller, 677
 - activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller, 705
 - activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller, 782
 - activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller, 882
 - activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller, 914
 - activemq::wireformat::openwire::marshal::v1::ConnectionContainerMarshaller, 1282
 - activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller, 1314
 - activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller, 1345
 - activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller, 1375

activemq::wireformat::openwire::marshal::v2::BaseCommandMarshaller; openwire::marshal::v2::MessageDispatcher
 803 2641
 activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller; openwire::marshal::v2::MessageIdMarshaller
 894 2670
 activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller; openwire::marshal::v2::MessageMarshaller
 926 2705
 activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller; openwire::marshal::v2::MessagePullMarshaller
 1294 2746
 activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller; openwire::marshal::v2::NetworkBridgeFilter
 1302 2798
 activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller; openwire::marshal::v2::PartialCommandMarshaller
 1333 2928
 activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller; openwire::marshal::v2::ProducerAckMarshaller
 1363 3042
 activemq::wireformat::openwire::marshal::v2::ConsumerGroupViewMarshaller; openwire::marshal::v2::ProducerIdMarshaller
 1408 3074
 activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller; openwire::marshal::v2::ProducerInfoMarshaller
 1437 3107
 activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller; openwire::marshal::v2::RemoveInfoMarshaller
 1470 3200
 activemq::wireformat::openwire::marshal::v2::ContactGroupAndIdMarshaller; openwire::marshal::v2::RemoveSubscription
 1499 3237
 activemq::wireformat::openwire::marshal::v2::DataActiveResponseMarshaller; openwire::marshal::v2::ReplayCommandMarshaller
 1533 3264
 activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller; openwire::marshal::v2::ResponseMarshaller
 1596 3302
 activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller; openwire::marshal::v2::SessionIdMarshaller
 1734 3385
 activemq::wireformat::openwire::marshal::v2::DiscoveryInfoMarshaller; openwire::marshal::v2::SessionInfoMarshaller
 1768 3429
 activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller; openwire::marshal::v2::ShutdownInfoMarshaller
 1848 3479
 activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller; openwire::marshal::v2::SubscriptionInfoMarshaller
 1946 3698
 activemq::wireformat::openwire::marshal::v2::IntegrationResponseMarshaller; openwire::marshal::v2::TransactionIdMarshaller
 2100 3833
 activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller; openwire::marshal::v2::TransactionInfoMarshaller
 2165 3873
 activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller; openwire::marshal::v2::WireFormatInfoMarshaller
 2194 4002
 activemq::wireformat::openwire::marshal::v2::JournalTransactionInfoMarshaller; openwire::marshal::v2::XATransactionInfoMarshaller
 2217 4042
 activemq::wireformat::openwire::marshal::v2::JournalTransactionInfoMarshaller; openwire::marshal::v3::ActiveMQBlobMarshaller
 2248 211
 activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller; openwire::marshal::v3::ActiveMQBytesMarshaller
 2275 251
 activemq::wireformat::openwire::marshal::v2::LastPartialCommandMarshaller; openwire::marshal::v3::ActiveMQDestinationMarshaller
 2314 335
 activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller; openwire::marshal::v3::ActiveMQMapMarshaller
 2357 376
 activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller; openwire::marshal::v3::ActiveMQMessageMarshaller
 2571 403
 activemq::wireformat::openwire::marshal::v2::MessageDispatcherMarshaller; openwire::marshal::v3::ActiveMQObjectMarshaller
 2608 448

activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaller	493	activemq::wireformat::openwire::marshal::v3::JournalTraceMarshaller	2221
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMessageMarshaller	554	activemq::wireformat::openwire::marshal::v3::JournalTransactionMarshaller	2252
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueDeflationMarshaller	582	activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller	2279
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueFormatMarshaller	611	activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	2310
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueTopicMarshaller	640	activemq::wireformat::openwire::marshal::v3::LocalTransactionMarshaller	2361
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	669	activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller	2575
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller	697	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2612
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller	768	activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	2645
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	874	activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	2682
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	906	activemq::wireformat::openwire::marshal::v3::MessageMarshaller	2700
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	1274	activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller	2754
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	1306	activemq::wireformat::openwire::marshal::v3::NetworkBridgeFailureMarshaller	2810
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	1337	activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller	2936
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	1367	activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller	3050
activemq::wireformat::openwire::marshal::v3::ConsumerGroupMarshaller	1412	activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller	3082
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	1441	activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller	3119
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	1474	activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller	3208
activemq::wireformat::openwire::marshal::v3::ContentCommandMarshaller	1503	activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionMarshaller	3233
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller	1537	activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller	3268
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller	1600	activemq::wireformat::openwire::marshal::v3::ResponseMarshaller	3312
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	1738	activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller	3401
activemq::wireformat::openwire::marshal::v3::DiscoveryInfoMarshaller	1772	activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller	3425
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	1852	activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller	3491
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	1950	activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller	3678
activemq::wireformat::openwire::marshal::v3::IntegrationResponseMarshaller	2104	activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller	3837
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	2173	activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller	3861
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller	2198	activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	4014

activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	1742
4054	
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobWireMessageMarshaller	1776
219	
activemq::wireformat::openwire::marshal::v4::ActiveMQByteWireMessageMarshaller	1860
259	
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	1954
343	
activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller	2108
384	
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	2177
411	
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectWireMessageMarshaller	2206
456	
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireMessageMarshaller	2229
501	
activemq::wireformat::openwire::marshal::v4::ActiveMQStackWireMessageMarshaller	2260
562	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller	2283
590	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	2322
619	
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller	2369
644	
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	2579
673	
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller	2620
701	
activemq::wireformat::openwire::marshal::v4::BaseCommandWireMarshaller	2649
775	
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	2674
878	
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	2710
910	
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	2758
1278	
activemq::wireformat::openwire::marshal::v4::ConnectionFromMarshaller	2814
1310	
activemq::wireformat::openwire::marshal::v4::ConnectionMarshaller	2940
1341	
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	3046
1371	
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	3078
1416	
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	3103
1445	
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	3220
1478	
activemq::wireformat::openwire::marshal::v4::ContractCommandMarshaller	3249
1507	
activemq::wireformat::openwire::marshal::v4::DataActiveResponseMarshaller	3256
1541	
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller	3297
1604	

activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	3389	activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller	1379
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	3433	activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller	1424
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	3495	activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller	1453
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	3690	activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller	1486
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	3841	activemq::wireformat::openwire::marshal::v5::ControlCommandMarshaller	1515
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	3869	activemq::wireformat::openwire::marshal::v5::DataArrayResponseMarshaller	1549
activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaller	4006	activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller	1588
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller	4046	activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller	1754
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobWireFormatMarshaller	227	activemq::wireformat::openwire::marshal::v5::DiscoveryEventManager	1784
activemq::wireformat::openwire::marshal::v5::ActiveMQByteWireFormatMarshaller	263	activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller	1856
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	347	activemq::wireformat::openwire::marshal::v5::FlushCommandMarshaller	1962
activemq::wireformat::openwire::marshal::v5::ActiveMQMapWireFormatMarshaller	388	activemq::wireformat::openwire::marshal::v5::IntegerResponseMarshaller	2116
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	415	activemq::wireformat::openwire::marshal::v5::JournalQueueAckMarshaller	2169
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectWireFormatMarshaller	460	activemq::wireformat::openwire::marshal::v5::JournalTopicAckMarshaller	2190
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueWireFormatMarshaller	505	activemq::wireformat::openwire::marshal::v5::JournalTraceMarshaller	2237
activemq::wireformat::openwire::marshal::v5::ActiveMQStackingMessageMarshaller	566	activemq::wireformat::openwire::marshal::v5::JournalTransactionMarshaller	2256
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	594	activemq::wireformat::openwire::marshal::v5::KeepAliveInfoMarshaller	2287
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	623	activemq::wireformat::openwire::marshal::v5::LastPartialCommandMarshaller	2318
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	652	activemq::wireformat::openwire::marshal::v5::LocalTransactionMarshaller	2365
activemq::wireformat::openwire::marshal::v5::ActiveMQTextWireFormatMarshaller	681	activemq::wireformat::openwire::marshal::v5::MessageAckMarshaller	2587
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	709	activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller	2616
activemq::wireformat::openwire::marshal::v5::BaseCommandWireFormatMarshaller	789	activemq::wireformat::openwire::marshal::v5::MessageDispatchMarshaller	2657
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	886	activemq::wireformat::openwire::marshal::v5::MessageIdMarshaller	2678
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller	918	activemq::wireformat::openwire::marshal::v5::MessageMarshaller	2695
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller	1286	activemq::wireformat::openwire::marshal::v5::MessagePullMarshaller	2750
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller	1318	activemq::wireformat::openwire::marshal::v5::NetworkBridgeMarshaller	2806
activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller	1349	activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller	2932

activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller,openwire::marshal::v6::ActiveMQTopicC
 3054 713
 activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller,openwire::marshal::v6::BaseCommandM
 3086 796
 activemq::wireformat::openwire::marshal::v5::ProducerInfoMarshaller,openwire::marshal::v6::BrokerIdMarsha
 3115 890
 activemq::wireformat::openwire::marshal::v5::RemoveInfoMarshaller,openwire::marshal::v6::BrokerInfoMarsh
 3216 922
 activemq::wireformat::openwire::marshal::v5::RemoveSubscriptionInfoMarshaller,openwire::marshal::v6::ConnectionCont
 3245 1290
 activemq::wireformat::openwire::marshal::v5::ReplaceCommandMarshaller,openwire::marshal::v6::ConnectionError
 3276 1322
 activemq::wireformat::openwire::marshal::v5::ResponseMarshaller,openwire::marshal::v6::ConnectionIdMa
 3307 1353
 activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller,openwire::marshal::v6::ConnectionInfoM
 3397 1383
 activemq::wireformat::openwire::marshal::v5::SessionInfoMarshaller,openwire::marshal::v6::ConsumerContro
 3417 1428
 activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller,openwire::marshal::v6::ConsumerIdMar
 3487 1457
 activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller,openwire::marshal::v6::ConsumerInfoMa
 3686 1490
 activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller,openwire::marshal::v6::ControlComman
 3825 1519
 activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller,openwire::marshal::v6::DataArrayRespo
 3853 1553
 activemq::wireformat::openwire::marshal::v5::WireFormatMarshaller,openwire::marshal::v6::DataResponseM
 3994 1592
 activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller,openwire::marshal::v6::DestinationInfoM
 4058 1750
 activemq::wireformat::openwire::marshal::v6::ActiveMQBlobWireFormatMarshaller,openwire::marshal::v6::DiscoveryEventM
 231 1764
 activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller,openwire::marshal::v6::ExceptionRespon
 267 1844
 activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller,openwire::marshal::v6::FlushCommandI
 355 1942
 activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller,openwire::marshal::v6::IntegerResponse
 396 2096
 activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller,openwire::marshal::v6::JournalQueueAc
 423 2161
 activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller,openwire::marshal::v6::JournalTopicAck
 468 2202
 activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller,openwire::marshal::v6::JournalTraceMa
 513 2225
 activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceMessageMarshaller,openwire::marshal::v6::JournalTransact
 574 2244
 activemq::wireformat::openwire::marshal::v6::ActiveMQSimpleInformationMarshaller,openwire::marshal::v6::KeepAliveInfoM
 602 2271
 activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller,openwire::marshal::v6::LastPartialComm
 631 2306
 activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller,openwire::marshal::v6::LocalTransaction
 660 2353
 activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller,openwire::marshal::v6::MessageAckMar
 685 2567

activemq::wireformat::openwire::marshal::v6::MessagePatchMarshaller,
 2628
 activemq::wireformat::openwire::marshal::v6::MessagePatchNotificationMarshaller,
 2637
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller,
 2686
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller,
 2720
 activemq::wireformat::openwire::marshal::v6::MessageMarshaller,
 2766
 activemq::wireformat::openwire::marshal::v6::NetworkFilterMarshaller,
 2802
 activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller,
 2924
 activemq::wireformat::openwire::marshal::v6::ProducerAckMarshaller,
 3058
 activemq::wireformat::openwire::marshal::v6::ProducerMarshaller,
 3090
 activemq::wireformat::openwire::marshal::v6::ProducerInfoMarshaller,
 3123
 activemq::wireformat::openwire::marshal::v6::RemoveMarshaller,
 3204
 activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller,
 3241
 activemq::wireformat::openwire::marshal::v6::ReplayCommandMarshaller,
 3272
 activemq::wireformat::openwire::marshal::v6::ResponseMarshaller,
 3322
 activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller,
 3393
 activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller,
 3413
 activemq::wireformat::openwire::marshal::v6::ShutdownMarshaller,
 3475
 activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller,
 3694
 activemq::wireformat::openwire::marshal::v6::TransactionMarshaller,
 3845
 activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller,
 3865
 activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller,
 3998
 activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller,
 4038
 tightMarshal2
 1545
 activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,
 819
 activemq::wireformat::openwire::marshal::DataStreamMarshaller,
 1645
 activemq::wireformat::openwire::marshal::v1::ActiveMQBlockWireFormatMarshaller,
 215
 activemq::wireformat::openwire::marshal::v1::ActiveMQByteMessageMarshaller,
 255
 activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller,
 1864
 activemq::wireformat::openwire::marshal::v1::ActiveMQMapMessageMarshaller,
 1339
 activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller,
 1380
 activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller,
 1407
 activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMarshaller,
 1552
 activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller,
 1977
 activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMarshaller,
 1558
 activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller,
 1586
 activemq::wireformat::openwire::marshal::v1::ActiveMQTemporalityMarshaller,
 1613
 activemq::wireformat::openwire::marshal::v1::ActiveMQTemporalityMarshaller,
 1648
 activemq::wireformat::openwire::marshal::v1::ActiveMQTextMarshaller,
 1677
 activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller,
 1705
 activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller,
 1733
 activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller,
 1882
 activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller,
 1914
 activemq::wireformat::openwire::marshal::v1::ConnectionContainerMarshaller,
 1982
 activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller,
 2014
 activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller,
 2145
 activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller,
 2175
 activemq::wireformat::openwire::marshal::v1::ConsumerControlMarshaller,
 2420
 activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller,
 2449
 activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller,
 2482
 activemq::wireformat::openwire::marshal::v1::ControlCommandMarshaller,
 2510
 activemq::wireformat::openwire::marshal::v1::DataArrayResponseMarshaller,
 2545
 activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller,
 2574
 activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller,
 2603
 activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller,
 2632
 activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller,
 2661
 activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller,
 2690

- 1958
- activemq::wireformat::openwire::marshal::v1::IntegerResponseInfoMarshaleropenwire::marshal::v1::TransactionIdMarshaller
- 2112
- activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaleropenwire::marshal::v1::TransactionInfoMarshaler
- 2181
- activemq::wireformat::openwire::marshal::v1::JournalTopicAckInfoMarshaleropenwire::marshal::v1::WireFormatInfoMarshaler
- 2210
- activemq::wireformat::openwire::marshal::v1::JournalTransactionInfoMarshaleropenwire::marshal::v1::XATransactionInfoMarshaler
- 2233
- activemq::wireformat::openwire::marshal::v1::JournalTransactionInfoMarshaleropenwire::marshal::v2::ActiveMQBlobMarshaler
- 2264
- activemq::wireformat::openwire::marshal::v1::KeepAliveInfoMarshaleropenwire::marshal::v2::ActiveMQBytesMarshaler
- 2291
- activemq::wireformat::openwire::marshal::v1::LastBatchInfoMarshaleropenwire::marshal::v2::ActiveMQDestinationMarshaler
- 2326
- activemq::wireformat::openwire::marshal::v1::LocalTransactionInfoMarshaleropenwire::marshal::v2::ActiveMQMapMarshaler
- 2373
- activemq::wireformat::openwire::marshal::v1::MessageAckInfoMarshaleropenwire::marshal::v2::ActiveMQMessageMarshaler
- 2583
- activemq::wireformat::openwire::marshal::v1::MessageDispatchInfoMarshaleropenwire::marshal::v2::ActiveMQObjectMarshaler
- 2624
- activemq::wireformat::openwire::marshal::v1::MessageDispatchInfoMarshaleropenwire::marshal::v2::ActiveMQQueueMarshaler
- 2653
- activemq::wireformat::openwire::marshal::v1::MessageIdInfoMarshaleropenwire::marshal::v2::ActiveMQStreamMarshaler
- 2690
- activemq::wireformat::openwire::marshal::v1::MessageIdInfoMarshaleropenwire::marshal::v2::ActiveMQTempInfoMarshaler
- 2715
- activemq::wireformat::openwire::marshal::v1::MessageIdInfoMarshaleropenwire::marshal::v2::ActiveMQTempInfoMarshaler
- 2762
- activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaleropenwire::marshal::v2::ActiveMQTempInfoMarshaler
- 2818
- activemq::wireformat::openwire::marshal::v1::PartialCommandInfoMarshaleropenwire::marshal::v2::ActiveMQTextMarshaler
- 2944
- activemq::wireformat::openwire::marshal::v1::ProductInfoMarshaleropenwire::marshal::v2::ActiveMQTopicInfoMarshaler
- 3062
- activemq::wireformat::openwire::marshal::v1::ProductInfoMarshaleropenwire::marshal::v2::BaseCommandMarshaler
- 3094
- activemq::wireformat::openwire::marshal::v1::ProductInfoMarshaleropenwire::marshal::v2::BrokerIdMarshaler
- 3111
- activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaleropenwire::marshal::v2::BrokerInfoMarshaler
- 3212
- activemq::wireformat::openwire::marshal::v1::RemoveInfoMarshaleropenwire::marshal::v2::ConnectionContainerMarshaler
- 3229
- activemq::wireformat::openwire::marshal::v1::ReplaceCommandInfoMarshaleropenwire::marshal::v2::ConnectionErrorMarshaler
- 3260
- activemq::wireformat::openwire::marshal::v1::ResponseInfoMarshaleropenwire::marshal::v2::ConnectionIdMarshaler
- 3318
- activemq::wireformat::openwire::marshal::v1::SessionIdInfoMarshaleropenwire::marshal::v2::ConnectionInfoMarshaler
- 3405
- activemq::wireformat::openwire::marshal::v1::SessionInfoMarshaleropenwire::marshal::v2::ConsumerControllerMarshaler
- 3421
- activemq::wireformat::openwire::marshal::v1::ShutdownInfoMarshaleropenwire::marshal::v2::ConsumerIdMarshaler
- 3483
- activemq::wireformat::openwire::marshal::v1::SubscriptionInfoMarshaleropenwire::marshal::v2::ConsumerInfoMarshaler

1470	3200
activemq::wireformat::openwire::marshal::v2::CommandAndResponseMarshaler	activemq::wireformat::openwire::marshal::v2::RemoveSubscription
1499	3237
activemq::wireformat::openwire::marshal::v2::DataAndResponseMarshaler	activemq::wireformat::openwire::marshal::v2::ReplayCommand
1533	3264
activemq::wireformat::openwire::marshal::v2::DataAndResponseMarshaler	activemq::wireformat::openwire::marshal::v2::ResponseMarshaler
1596	3303
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaler	activemq::wireformat::openwire::marshal::v2::SessionIdMarshaler
1734	3385
activemq::wireformat::openwire::marshal::v2::DiscoveryInfoMarshaler	activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaler
1768	3429
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaler	activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaler
1848	3479
activemq::wireformat::openwire::marshal::v2::FlushCommandAndResponseMarshaler	activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaler
1946	3698
activemq::wireformat::openwire::marshal::v2::IntegerResponseMarshaler	activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaler
2100	3833
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaler	activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaler
2165	3873
activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaler	activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaler
2194	4002
activemq::wireformat::openwire::marshal::v2::JournalTransactionInfoMarshaler	activemq::wireformat::openwire::marshal::v2::XATransactionInfoMarshaler
2217	4042
activemq::wireformat::openwire::marshal::v2::JournalTransactionInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMarshaler
2248	211
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMarshaler
2275	251
activemq::wireformat::openwire::marshal::v2::LastReceivedCommandMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaler
2314	335
activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQMapMarshaler
2357	376
activemq::wireformat::openwire::marshal::v2::MessageAckMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaler
2571	403
activemq::wireformat::openwire::marshal::v2::MessageDispatchInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMarshaler
2608	448
activemq::wireformat::openwire::marshal::v2::MessageDispatchInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMarshaler
2641	493
activemq::wireformat::openwire::marshal::v2::MessageDispatchInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQStreamMarshaler
2670	554
activemq::wireformat::openwire::marshal::v2::MessageDispatchInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQTemplateMarshaler
2705	582
activemq::wireformat::openwire::marshal::v2::MessageDispatchInfoMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQTemplateMarshaler
2746	611
activemq::wireformat::openwire::marshal::v2::NetworkBridgeFilterMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQTemplateMarshaler
2798	640
activemq::wireformat::openwire::marshal::v2::PartialCommandAndResponseMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQTextMarshaler
2928	669
activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaler	activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaler
3042	697
activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaler	activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaler
3074	769
activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaler	activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaler
3107	874
activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaler	activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaler

906	2700
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	activemq::wireformat::openwire::marshal::v3::MessagePullMarshaller
1274	2754
activemq::wireformat::openwire::marshal::v3::ConnectionErrorInfoMarshaller	activemq::wireformat::openwire::marshal::v3::NetworkBridgeFailureInfoMarshaller
1306	2810
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	activemq::wireformat::openwire::marshal::v3::PartialCommandMarshaller
1337	2936
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	activemq::wireformat::openwire::marshal::v3::ProducerAckMarshaller
1367	3050
activemq::wireformat::openwire::marshal::v3::ConsumerGroupViewMarshaller	activemq::wireformat::openwire::marshal::v3::ProducerIdMarshaller
1412	3082
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	activemq::wireformat::openwire::marshal::v3::ProducerInfoMarshaller
1441	3119
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	activemq::wireformat::openwire::marshal::v3::RemoveInfoMarshaller
1474	3208
activemq::wireformat::openwire::marshal::v3::ContainerCommandMarshaller	activemq::wireformat::openwire::marshal::v3::RemoveSubscriptionMarshaller
1503	3233
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller	activemq::wireformat::openwire::marshal::v3::ReplayCommandMarshaller
1537	3268
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller	activemq::wireformat::openwire::marshal::v3::ResponseMarshaller
1600	3313
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	activemq::wireformat::openwire::marshal::v3::SessionIdMarshaller
1738	3401
activemq::wireformat::openwire::marshal::v3::DisconnectInfoMarshaller	activemq::wireformat::openwire::marshal::v3::SessionInfoMarshaller
1772	3425
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	activemq::wireformat::openwire::marshal::v3::ShutdownInfoMarshaller
1852	3491
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	activemq::wireformat::openwire::marshal::v3::SubscriptionInfoMarshaller
1950	3678
activemq::wireformat::openwire::marshal::v3::IntegerResponseMarshaller	activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller
2104	3837
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller
2173	3861
activemq::wireformat::openwire::marshal::v3::JournalTopicAckMarshaller	activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller
2198	4014
activemq::wireformat::openwire::marshal::v3::JournalTransactionIdMarshaller	activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller
2221	4054
activemq::wireformat::openwire::marshal::v3::JournalTransactionInfoMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQBlobMarshaller
2252	219
activemq::wireformat::openwire::marshal::v3::KeepAliveInfoMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQBytesMarshaller
2279	259
activemq::wireformat::openwire::marshal::v3::LastPartialCommandMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller
2310	343
activemq::wireformat::openwire::marshal::v3::LocalTransactionIdMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQMapMarshaller
2361	384
activemq::wireformat::openwire::marshal::v3::MessageAckMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller
2575	411
activemq::wireformat::openwire::marshal::v3::MessageDispatchMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMarshaller
2612	456
activemq::wireformat::openwire::marshal::v3::MessageDispatchNotificationMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQQueueMarshaller
2645	501
activemq::wireformat::openwire::marshal::v3::MessageIdMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQStreamMarshaller
2682	562
activemq::wireformat::openwire::marshal::v3::MessageMarshaller	activemq::wireformat::openwire::marshal::v4::ActiveMQTemplateMarshaller

590	2283
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaler	activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaler
619	2322
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaler	activemq::wireformat::openwire::marshal::v4::LocalTransactionIdMarshaler
644	2369
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaler	activemq::wireformat::openwire::marshal::v4::MessageAckMarshaler
673	2579
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMessageHeader	activemq::wireformat::openwire::marshal::v4::MessageDispatchInfoMarshaler
701	2620
activemq::wireformat::openwire::marshal::v4::BaseCommandMarshaler	activemq::wireformat::openwire::marshal::v4::MessageDispatchInfoMarshaler
776	2649
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaler	activemq::wireformat::openwire::marshal::v4::MessageIdMarshaler
878	2674
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaler	activemq::wireformat::openwire::marshal::v4::MessageMarshaler
910	2710
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaler	activemq::wireformat::openwire::marshal::v4::MessagePullMarshaler
1278	2758
activemq::wireformat::openwire::marshal::v4::ConnectionErrorMarshaler	activemq::wireformat::openwire::marshal::v4::NetworkBridgeFailureMarshaler
1310	2814
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaler	activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaler
1341	2940
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaler	activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaler
1371	3046
activemq::wireformat::openwire::marshal::v4::ConsumerGroupInfoMarshaler	activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaler
1416	3078
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaler	activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaler
1445	3103
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaler	activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaler
1478	3220
activemq::wireformat::openwire::marshal::v4::ContactCommandMarshaler	activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionInfoMarshaler
1507	3249
activemq::wireformat::openwire::marshal::v4::DataActiveResponseMarshaler	activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaler
1541	3256
activemq::wireformat::openwire::marshal::v4::DataResponseMarshaler	activemq::wireformat::openwire::marshal::v4::ResponseMarshaler
1604	3298
activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaler	activemq::wireformat::openwire::marshal::v4::SessionIdMarshaler
1742	3389
activemq::wireformat::openwire::marshal::v4::DiscardInfoMarshaler	activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaler
1776	3433
activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaler	activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaler
1860	3495
activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaler	activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaler
1954	3690
activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaler	activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaler
2108	3841
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaler	activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaler
2177	3869
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaler	activemq::wireformat::openwire::marshal::v4::WireFormatInfoMarshaler
2206	4006
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaler	activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaler
2229	4046
activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaler	activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMarshaler
2260	227
activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaler	activemq::wireformat::openwire::marshal::v5::ActiveMQBytesMarshaler

- 263
- activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller; openwire::marshal::v5::FlushCommand
- 347
- activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller; openwire::marshal::v5::IntegerResponse
- 388
- activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller; openwire::marshal::v5::JournalQueueAc
- 415
- activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller; openwire::marshal::v5::JournalTopicAck
- 460
- activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMarshaller; openwire::marshal::v5::JournalTraceMa
- 505
- activemq::wireformat::openwire::marshal::v5::ActiveMQSequenceMessageMarshaller; openwire::marshal::v5::JournalTransact
- 566
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller; openwire::marshal::v5::KeepAliveInfoM
- 594
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller; openwire::marshal::v5::LastPartialComm
- 623
- activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller; openwire::marshal::v5::LocalTransaction
- 652
- activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller; openwire::marshal::v5::MessageAckMar
- 681
- activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller; openwire::marshal::v5::MessageDispatch
- 709
- activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller; openwire::marshal::v5::MessageDispatch
- 790
- activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller; openwire::marshal::v5::MessageIdMarsh
- 886
- activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller; openwire::marshal::v5::MessageMarsh
- 918
- activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller; openwire::marshal::v5::MessagePullMar
- 1286
- activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller; openwire::marshal::v5::NetworkBridgeF
- 1318
- activemq::wireformat::openwire::marshal::v5::ConnectionIdMarshaller; openwire::marshal::v5::PartialCommand
- 1349
- activemq::wireformat::openwire::marshal::v5::ConnectionInfoMarshaller; openwire::marshal::v5::ProducerAckMar
- 1379
- activemq::wireformat::openwire::marshal::v5::ConsumerControlMarshaller; openwire::marshal::v5::ProducerIdMars
- 1424
- activemq::wireformat::openwire::marshal::v5::ConsumerIdMarshaller; openwire::marshal::v5::ProducerInfoMa
- 1453
- activemq::wireformat::openwire::marshal::v5::ConsumerInfoMarshaller; openwire::marshal::v5::RemoveInfoMars
- 1486
- activemq::wireformat::openwire::marshal::v5::ContractCommandMarshaller; openwire::marshal::v5::RemoveSubscrip
- 1515
- activemq::wireformat::openwire::marshal::v5::DataActiveResponseMarshaller; openwire::marshal::v5::ReplayCommand
- 1549
- activemq::wireformat::openwire::marshal::v5::DataResponseMarshaller; openwire::marshal::v5::ResponseMarsha
- 1588
- activemq::wireformat::openwire::marshal::v5::DestinationInfoMarshaller; openwire::marshal::v5::SessionIdMarsha
- 1754
- activemq::wireformat::openwire::marshal::v5::DiscardRequestMarshaller; openwire::marshal::v5::SessionInfoMars
- 1784
- activemq::wireformat::openwire::marshal::v5::ExceptionResponseMarshaller; openwire::marshal::v5::ShutdownInfoM

3487	1457
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller	openwire::marshal::v6::ConsumerInfoMarshaller
3686	1490
activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller	openwire::marshal::v6::ControlCommandMarshaller
3825	1519
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller	openwire::marshal::v6::DataArrayResponseMarshaller
3853	1553
activemq::wireformat::openwire::marshal::v5::WireFormatInfoMarshaller	openwire::marshal::v6::DataResponseMarshaller
3994	1592
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller	openwire::marshal::v6::DestinationInfoMarshaller
4058	1750
activemq::wireformat::openwire::marshal::v6::ActiveMQBlobWireFormatMarshaller	openwire::marshal::v6::DiscoveryEventManager
231	1764
activemq::wireformat::openwire::marshal::v6::ActiveMQByteWireFormatMarshaller	openwire::marshal::v6::ExceptionResponseMarshaller
267	1844
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller	openwire::marshal::v6::FlushCommandMarshaller
355	1942
activemq::wireformat::openwire::marshal::v6::ActiveMQMapWireFormatMarshaller	openwire::marshal::v6::IntegerResponseMarshaller
396	2096
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	openwire::marshal::v6::JournalQueueAckMarshaller
423	2161
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectWireFormatMarshaller	openwire::marshal::v6::JournalTopicAckMarshaller
468	2202
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueWireFormatMarshaller	openwire::marshal::v6::JournalTraceMarshaller
513	2225
activemq::wireformat::openwire::marshal::v6::ActiveMQSequenceWireFormatMarshaller	openwire::marshal::v6::JournalTransactionMarshaller
574	2244
activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller	openwire::marshal::v6::KeepAliveInfoMarshaller
602	2271
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	openwire::marshal::v6::LastPartialCommandMarshaller
631	2306
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	openwire::marshal::v6::LocalTransactionMarshaller
660	2353
activemq::wireformat::openwire::marshal::v6::ActiveMQTextMessageMarshaller	openwire::marshal::v6::MessageAckMarshaller
685	2567
activemq::wireformat::openwire::marshal::v6::ActiveMQTopicMarshaller	openwire::marshal::v6::MessageDispatchMarshaller
713	2628
activemq::wireformat::openwire::marshal::v6::BaseCommandWireFormatMarshaller	openwire::marshal::v6::MessageDispatchMarshaller
797	2637
activemq::wireformat::openwire::marshal::v6::BrokerIdMarshaller	openwire::marshal::v6::MessageIdMarshaller
890	2686
activemq::wireformat::openwire::marshal::v6::BrokerInfoMarshaller	openwire::marshal::v6::MessageMarshaller
922	2720
activemq::wireformat::openwire::marshal::v6::ConnectionControlMarshaller	openwire::marshal::v6::MessagePullMarshaller
1290	2766
activemq::wireformat::openwire::marshal::v6::ConnectionErrorMarshaller	openwire::marshal::v6::NetworkBridgeMarshaller
1322	2802
activemq::wireformat::openwire::marshal::v6::ConnectionIdMarshaller	openwire::marshal::v6::PartialCommandMarshaller
1353	2924
activemq::wireformat::openwire::marshal::v6::ConnectionInfoMarshaller	openwire::marshal::v6::ProducerAckMarshaller
1383	3058
activemq::wireformat::openwire::marshal::v6::ConsumerControlMarshaller	openwire::marshal::v6::ProducerIdMarshaller
1428	3090
activemq::wireformat::openwire::marshal::v6::ConsumerIdMarshaller	openwire::marshal::v6::ProducerInfoMarshaller

3123	activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,
activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller,	823
3204	tightMarshalObjectArray2
activemq::wireformat::openwire::marshal::v6::RemoveSubscriptionInfoMarshaller,	823
3241	activemq::wireformat::openwire::marshal::v6::ReplyToConsumerIdMarshaller,
3272	activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,
activemq::wireformat::openwire::marshal::v6::ResponseMarshaller,	824
3323	tightMarshalString2
activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller,	824
3393	activemq::wireformat::openwire::marshal::v6::SessionInfoMarshaller,
3413	activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,
activemq::wireformat::openwire::marshal::v6::ShutdownMarshaller,	824
3475	activemq::wireformat::openwire::marshal::DataStreamMarshaller,
activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller,	824
3694	activemq::wireformat::openwire::marshal::v1::ActiveMQBlobMarshaller,
activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller,	824
3845	activemq::wireformat::openwire::marshal::v1::ActiveMQBytesMarshaller,
activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller,	825
3865	activemq::wireformat::openwire::marshal::v1::ActiveMQDestinationMarshaller,
activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller,	840
3998	activemq::wireformat::openwire::marshal::v1::ActiveMQMapMarshaller,
activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller,	881
4038	activemq::wireformat::openwire::marshal::v1::ActiveMQMessageMarshaller,
tightMarshalBrokerError1	408
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	408
820	activemq::wireformat::openwire::marshal::v1::ActiveMQObjectMarshaller,
tightMarshalBrokerError2	453
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	453
820	activemq::wireformat::openwire::marshal::v1::ActiveMQQueueMarshaller,
tightMarshalCachedObject1	498
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	498
820	activemq::wireformat::openwire::marshal::v1::ActiveMQStreamMarshaller,
tightMarshalCachedObject2	559
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	559
820	activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller,
tightMarshalCachedObject2	587
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	587
821	activemq::wireformat::openwire::marshal::v1::ActiveMQTemplateMarshaller,
tightMarshalLong1	649
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	649
821	activemq::wireformat::openwire::marshal::v1::ActiveMQTextMarshaller,
tightMarshalLong2	678
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	678
822	activemq::wireformat::openwire::marshal::v1::ActiveMQTopicMarshaller,
tightMarshalNestedObject1	706
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	706
822	activemq::wireformat::openwire::marshal::v1::BaseCommandMarshaller,
activemq::wireformat::openwire::OpenWireFormat,	784
2897	activemq::wireformat::openwire::marshal::v1::BrokerIdMarshaller,
tightMarshalNestedObject2	883
activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller,	883
822	activemq::wireformat::openwire::marshal::v1::BrokerInfoMarshaller,
activemq::wireformat::openwire::OpenWireFormat,	915
2897	activemq::wireformat::openwire::marshal::v1::ConnectionContainerMarshaller,
tightMarshalObjectArray1	1288
	activemq::wireformat::openwire::marshal::v1::ConnectionErrorMarshaller,
	1315
	activemq::wireformat::openwire::marshal::v1::ConnectionIdMarshaller,
	1346

activemq::wireformat::openwire::marshal::v1::ConnectionInfoMarshaller	3063
1376	
activemq::wireformat::openwire::marshal::v1::ConsumerGroupViewMarshaller	3095
1421	
activemq::wireformat::openwire::marshal::v1::ConsumerIdMarshaller	3112
1450	
activemq::wireformat::openwire::marshal::v1::ConsumerInfoMarshaller	3213
1483	
activemq::wireformat::openwire::marshal::v1::ContainerCommandMarshaller	3230
1512	
activemq::wireformat::openwire::marshal::v1::DataActiveResponseMarshaller	3261
1546	
activemq::wireformat::openwire::marshal::v1::DataResponseMarshaller	3318
1609	
activemq::wireformat::openwire::marshal::v1::DestinationInfoMarshaller	3406
1747	
activemq::wireformat::openwire::marshal::v1::DiscoveryEventMarshaller	3422
1781	
activemq::wireformat::openwire::marshal::v1::ExceptionResponseMarshaller	3484
1865	
activemq::wireformat::openwire::marshal::v1::FlushCommandMarshaller	3683
1959	
activemq::wireformat::openwire::marshal::v1::IntegerResponseMarshaller	3830
2113	
activemq::wireformat::openwire::marshal::v1::JournalQueueAckMarshaller	3858
2182	
activemq::wireformat::openwire::marshal::v1::JournalTopicAckMarshaller	4011
2211	
activemq::wireformat::openwire::marshal::v1::JournalTransactionInfoMarshaller	4051
2234	
activemq::wireformat::openwire::marshal::v1::JournalTransactionMarshaller	224
2265	
activemq::wireformat::openwire::marshal::v1::KeepActiveInfoMarshaller	272
2292	
activemq::wireformat::openwire::marshal::v1::LastBatchCompInfoMarshaller	352
2327	
activemq::wireformat::openwire::marshal::v1::LocalTransactionMarshaller	393
2374	
activemq::wireformat::openwire::marshal::v1::MessageAckMarshaller	420
2584	
activemq::wireformat::openwire::marshal::v1::MessageDispatchMarshaller	465
2625	
activemq::wireformat::openwire::marshal::v1::MessageDispatchNotificationMarshaller	510
2654	
activemq::wireformat::openwire::marshal::v1::MessageIdMarshaller	571
2691	
activemq::wireformat::openwire::marshal::v1::MessageMarshaller	599
2716	
activemq::wireformat::openwire::marshal::v1::MessagePullMarshaller	628
2763	
activemq::wireformat::openwire::marshal::v1::NetworkBridgeFilterMarshaller	657
2819	
activemq::wireformat::openwire::marshal::v1::PartialCommandMarshaller	690
2945	

activemq::wireformat::openwire::marshal::v2::ActiveMQTopicMarshaller	2609
718	
activemq::wireformat::openwire::marshal::v2::BaseCommandWireMarshaller	2642
805	
activemq::wireformat::openwire::marshal::v2::BrokerIdMarshaller	2671
895	
activemq::wireformat::openwire::marshal::v2::BrokerInfoMarshaller	2706
927	
activemq::wireformat::openwire::marshal::v2::ConnectionControlMarshaller	2747
1295	
activemq::wireformat::openwire::marshal::v2::ConnectionErrorMarshaller	2799
1303	
activemq::wireformat::openwire::marshal::v2::ConnectionIdMarshaller	2929
1334	
activemq::wireformat::openwire::marshal::v2::ConnectionInfoMarshaller	3043
1364	
activemq::wireformat::openwire::marshal::v2::ConsumerGroupWireMarshaller	3075
1409	
activemq::wireformat::openwire::marshal::v2::ConsumerIdMarshaller	3108
1438	
activemq::wireformat::openwire::marshal::v2::ConsumerInfoMarshaller	3201
1471	
activemq::wireformat::openwire::marshal::v2::ContactCommandMarshaller	3238
1500	
activemq::wireformat::openwire::marshal::v2::DataActiveResponseMarshaller	3265
1534	
activemq::wireformat::openwire::marshal::v2::DataResponseMarshaller	3303
1597	
activemq::wireformat::openwire::marshal::v2::DestinationInfoMarshaller	3386
1735	
activemq::wireformat::openwire::marshal::v2::DiscardResponseMarshaller	3430
1769	
activemq::wireformat::openwire::marshal::v2::ExceptionResponseMarshaller	3480
1849	
activemq::wireformat::openwire::marshal::v2::FlushCommandMarshaller	3699
1947	
activemq::wireformat::openwire::marshal::v2::IntegrationResponseMarshaller	3834
2101	
activemq::wireformat::openwire::marshal::v2::JournalQueueAckMarshaller	3874
2166	
activemq::wireformat::openwire::marshal::v2::JournalTopicAckMarshaller	4003
2195	
activemq::wireformat::openwire::marshal::v2::JournalTransactionMarshaller	4043
2218	
activemq::wireformat::openwire::marshal::v2::JournalTransactionInfoMarshaller	212
2249	
activemq::wireformat::openwire::marshal::v2::KeepAliveInfoMarshaller	252
2276	
activemq::wireformat::openwire::marshal::v2::LastReceivedCommandMarshaller	336
2315	
activemq::wireformat::openwire::marshal::v2::LocalTransactionIdMarshaller	377
2358	
activemq::wireformat::openwire::marshal::v2::MessageAckMarshaller	404
2572	
activemq::wireformat::openwire::marshal::v2::MessageDispatchMarshaller	
activemq::wireformat::openwire::marshal::v2::MessageIdMarshaller	
activemq::wireformat::openwire::marshal::v2::MessageMarshaller	
activemq::wireformat::openwire::marshal::v2::MessagePullMarshaller	
activemq::wireformat::openwire::marshal::v2::NetworkBridgeMarshaller	
activemq::wireformat::openwire::marshal::v2::PartialCommandMarshaller	
activemq::wireformat::openwire::marshal::v2::ProducerAckMarshaller	
activemq::wireformat::openwire::marshal::v2::ProducerIdMarshaller	
activemq::wireformat::openwire::marshal::v2::ProducerInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::RemoveInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::RemoveSubscriptionMarshaller	
activemq::wireformat::openwire::marshal::v2::ReplayCommandMarshaller	
activemq::wireformat::openwire::marshal::v2::ResponseMarshaller	
activemq::wireformat::openwire::marshal::v2::SessionIdMarshaller	
activemq::wireformat::openwire::marshal::v2::SessionInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::ShutdownInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::SubscriptionInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller	
activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::WireFormatInfoMarshaller	
activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller	
activemq::wireformat::openwire::marshal::v3::ActiveMQBlobMarshaller	
activemq::wireformat::openwire::marshal::v3::ActiveMQBytesMarshaller	
activemq::wireformat::openwire::marshal::v3::ActiveMQDestinationMarshaller	
activemq::wireformat::openwire::marshal::v3::ActiveMQMapMarshaller	
activemq::wireformat::openwire::marshal::v3::ActiveMQMessageMarshaller	

activemq::wireformat::openwire::marshal::v3::ActiveMQObjectMessageMarshaller	2199	activemq::wireformat::openwire::marshal::v3::JournalTopicAck
449		
activemq::wireformat::openwire::marshal::v3::ActiveMQQueueMessageMarshaller	2222	activemq::wireformat::openwire::marshal::v3::JournalTraceMa
494		
activemq::wireformat::openwire::marshal::v3::ActiveMQSequenceMessageMarshaller	2253	activemq::wireformat::openwire::marshal::v3::JournalTransact
555		
activemq::wireformat::openwire::marshal::v3::ActiveMQTempDeflationMarshaller	2280	activemq::wireformat::openwire::marshal::v3::KeepAliveInfoM
583		
activemq::wireformat::openwire::marshal::v3::ActiveMQTempQueueMarshaller	2311	activemq::wireformat::openwire::marshal::v3::LastPartialComm
612		
activemq::wireformat::openwire::marshal::v3::ActiveMQTempTopicMarshaller	2362	activemq::wireformat::openwire::marshal::v3::LocalTransaction
641		
activemq::wireformat::openwire::marshal::v3::ActiveMQTextMessageMarshaller	2576	activemq::wireformat::openwire::marshal::v3::MessageAckMar
670		
activemq::wireformat::openwire::marshal::v3::ActiveMQTopicMarshaller	2613	activemq::wireformat::openwire::marshal::v3::MessageDispat ch
698		
activemq::wireformat::openwire::marshal::v3::BaseCommandMarshaller	2646	activemq::wireformat::openwire::marshal::v3::MessageDispat ch
770		
activemq::wireformat::openwire::marshal::v3::BrokerIdMarshaller	2683	activemq::wireformat::openwire::marshal::v3::MessageIdMarsh
875		
activemq::wireformat::openwire::marshal::v3::BrokerInfoMarshaller	2701	activemq::wireformat::openwire::marshal::v3::MessageMarshal
907		
activemq::wireformat::openwire::marshal::v3::ConnectionControlMarshaller	2755	activemq::wireformat::openwire::marshal::v3::MessagePullMar
1275		
activemq::wireformat::openwire::marshal::v3::ConnectionErrorMarshaller	2811	activemq::wireformat::openwire::marshal::v3::NetworkBridgeF
1307		
activemq::wireformat::openwire::marshal::v3::ConnectionIdMarshaller	2937	activemq::wireformat::openwire::marshal::v3::PartialCommand
1338		
activemq::wireformat::openwire::marshal::v3::ConnectionInfoMarshaller	3051	activemq::wireformat::openwire::marshal::v3::ProducerAckMar
1368		
activemq::wireformat::openwire::marshal::v3::ConsumerGroupMarshaller	3083	activemq::wireformat::openwire::marshal::v3::ProducerIdMars
1413		
activemq::wireformat::openwire::marshal::v3::ConsumerIdMarshaller	3120	activemq::wireformat::openwire::marshal::v3::ProducerInfoMa
1442		
activemq::wireformat::openwire::marshal::v3::ConsumerInfoMarshaller	3209	activemq::wireformat::openwire::marshal::v3::RemoveInfoMars
1475		
activemq::wireformat::openwire::marshal::v3::ContentCommandMarshaller	3234	activemq::wireformat::openwire::marshal::v3::RemoveSubscrip
1504		
activemq::wireformat::openwire::marshal::v3::DataActiveResponseMarshaller	3269	activemq::wireformat::openwire::marshal::v3::ReplayCommand
1538		
activemq::wireformat::openwire::marshal::v3::DataResponseMarshaller	3313	activemq::wireformat::openwire::marshal::v3::ResponseMarshal
1601		
activemq::wireformat::openwire::marshal::v3::DestinationInfoMarshaller	3402	activemq::wireformat::openwire::marshal::v3::SessionIdMarsha
1739		
activemq::wireformat::openwire::marshal::v3::DiscoveryEventMarshaller	3426	activemq::wireformat::openwire::marshal::v3::SessionInfoMars
1773		
activemq::wireformat::openwire::marshal::v3::ExceptionResponseMarshaller	3492	activemq::wireformat::openwire::marshal::v3::ShutdownInfoMa
1853		
activemq::wireformat::openwire::marshal::v3::FlushCommandMarshaller	3679	activemq::wireformat::openwire::marshal::v3::SubscriptionInfo
1951		
activemq::wireformat::openwire::marshal::v3::IntegrationResponseMarshaller	3838	activemq::wireformat::openwire::marshal::v3::TransactionIdMa
2105		
activemq::wireformat::openwire::marshal::v3::JournalQueueAckMarshaller	3862	activemq::wireformat::openwire::marshal::v3::TransactionInfo
2174		

activemq::wireformat::openwire::marshal::v3::WireFormatInfoMarshaller	4015	1605	activemq::wireformat::openwire::marshal::v4::DataResponseMarshaller
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller	4055	1743	activemq::wireformat::openwire::marshal::v4::DestinationInfoMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQBlobWireFormatMarshaller	220	1777	activemq::wireformat::openwire::marshal::v4::DiscoveryEventManager
activemq::wireformat::openwire::marshal::v4::ActiveMQByteWireFormatMarshaller	260	1861	activemq::wireformat::openwire::marshal::v4::ExceptionResponseMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQDestinationMarshaller	344	1955	activemq::wireformat::openwire::marshal::v4::FlushCommandMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQMapMessageMarshaller	385	2109	activemq::wireformat::openwire::marshal::v4::IntegerResponseMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQMessageMarshaller	412	2178	activemq::wireformat::openwire::marshal::v4::JournalQueueAckMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQObjectMessageMarshaller	457	2207	activemq::wireformat::openwire::marshal::v4::JournalTopicAckMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQQueueWireFormatMarshaller	502	2230	activemq::wireformat::openwire::marshal::v4::JournalTraceMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQSequenceMessageMarshaller	563	2261	activemq::wireformat::openwire::marshal::v4::JournalTransactionMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTempDestinationMarshaller	591	2284	activemq::wireformat::openwire::marshal::v4::KeepAliveInfoMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTempQueueMarshaller	620	2323	activemq::wireformat::openwire::marshal::v4::LastPartialCommandMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTempTopicMarshaller	645	2370	activemq::wireformat::openwire::marshal::v4::LocalTransactionMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTextMessageMarshaller	674	2580	activemq::wireformat::openwire::marshal::v4::MessageAckMarshaller
activemq::wireformat::openwire::marshal::v4::ActiveMQTopicMarshaller	702	2621	activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller
activemq::wireformat::openwire::marshal::v4::BaseCommandWireFormatMarshaller	777	2650	activemq::wireformat::openwire::marshal::v4::MessageDispatchMarshaller
activemq::wireformat::openwire::marshal::v4::BrokerIdMarshaller	879	2675	activemq::wireformat::openwire::marshal::v4::MessageIdMarshaller
activemq::wireformat::openwire::marshal::v4::BrokerInfoMarshaller	911	2711	activemq::wireformat::openwire::marshal::v4::MessageMarshaller
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	1279	2759	activemq::wireformat::openwire::marshal::v4::MessagePullMarshaller
activemq::wireformat::openwire::marshal::v4::ConnectionFromMarshaller	1311	2815	activemq::wireformat::openwire::marshal::v4::NetworkBridgeMarshaller
activemq::wireformat::openwire::marshal::v4::ConnectionIdMarshaller	1342	2941	activemq::wireformat::openwire::marshal::v4::PartialCommandMarshaller
activemq::wireformat::openwire::marshal::v4::ConnectionInfoMarshaller	1372	3047	activemq::wireformat::openwire::marshal::v4::ProducerAckMarshaller
activemq::wireformat::openwire::marshal::v4::ConnectionControlMarshaller	1417	3079	activemq::wireformat::openwire::marshal::v4::ProducerIdMarshaller
activemq::wireformat::openwire::marshal::v4::ConsumerIdMarshaller	1446	3104	activemq::wireformat::openwire::marshal::v4::ProducerInfoMarshaller
activemq::wireformat::openwire::marshal::v4::ConsumerInfoMarshaller	1479	3221	activemq::wireformat::openwire::marshal::v4::RemoveInfoMarshaller
activemq::wireformat::openwire::marshal::v4::ContainerCommandMarshaller	1508	3250	activemq::wireformat::openwire::marshal::v4::RemoveSubscriptionMarshaller
activemq::wireformat::openwire::marshal::v4::DataActiveResponseMarshaller	1542	3257	activemq::wireformat::openwire::marshal::v4::ReplayCommandMarshaller

activemq::wireformat::openwire::marshal::v4::ResponseMarshaller	1350
3298	
activemq::wireformat::openwire::marshal::v4::SessionIdMarshaller	1380
3390	
activemq::wireformat::openwire::marshal::v4::SessionInfoMarshaller	1425
3434	
activemq::wireformat::openwire::marshal::v4::ShutdownInfoMarshaller	1454
3496	
activemq::wireformat::openwire::marshal::v4::SubscriptionInfoMarshaller	1487
3691	
activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller	1516
3842	
activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller	1550
3870	
activemq::wireformat::openwire::marshal::v4::WireFormatMarshaller	1589
4007	
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller	1755
4047	
activemq::wireformat::openwire::marshal::v5::ActiveMQBlobMessageMarshaller	1785
228	
activemq::wireformat::openwire::marshal::v5::ActiveMQByteMessageMarshaller	1857
264	
activemq::wireformat::openwire::marshal::v5::ActiveMQDestinationMarshaller	1963
348	
activemq::wireformat::openwire::marshal::v5::ActiveMQMapMessageMarshaller	2117
389	
activemq::wireformat::openwire::marshal::v5::ActiveMQMessageMarshaller	2170
416	
activemq::wireformat::openwire::marshal::v5::ActiveMQObjectMessageMarshaller	2191
461	
activemq::wireformat::openwire::marshal::v5::ActiveMQQueueMessageMarshaller	2238
506	
activemq::wireformat::openwire::marshal::v5::ActiveMQStreamMessageMarshaller	2257
567	
activemq::wireformat::openwire::marshal::v5::ActiveMQTempDestinationMarshaller	2288
595	
activemq::wireformat::openwire::marshal::v5::ActiveMQTempQueueMarshaller	2319
624	
activemq::wireformat::openwire::marshal::v5::ActiveMQTempTopicMarshaller	2366
653	
activemq::wireformat::openwire::marshal::v5::ActiveMQTextMessageMarshaller	2588
682	
activemq::wireformat::openwire::marshal::v5::ActiveMQTopicMarshaller	2617
710	
activemq::wireformat::openwire::marshal::v5::BaseCommandMarshaller	2658
791	
activemq::wireformat::openwire::marshal::v5::BrokerIdMarshaller	2679
887	
activemq::wireformat::openwire::marshal::v5::BrokerInfoMarshaller	2696
919	
activemq::wireformat::openwire::marshal::v5::ConnectionControlMarshaller	2751
1287	
activemq::wireformat::openwire::marshal::v5::ConnectionErrorMarshaller	2807
1319	

activemq::wireformat::openwire::marshal::v5::PartialCommandMarshaller	openwire::marshal::v6::ActiveMQTextM
2933	686
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	openwire::marshal::v6::ActiveMQTopicC
3055	714
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	openwire::marshal::v6::BaseCommandM
3087	798
activemq::wireformat::openwire::marshal::v5::ProducerIdMarshaller	openwire::marshal::v6::BrokerIdMarsh
3116	891
activemq::wireformat::openwire::marshal::v5::RemoteInfoMarshaller	openwire::marshal::v6::BrokerInfoMarsh
3217	923
activemq::wireformat::openwire::marshal::v5::RemoteSubscriptionInfoMarshaller	openwire::marshal::v6::ConnectionCont
3246	1291
activemq::wireformat::openwire::marshal::v5::ReplaceCommandMarshaller	openwire::marshal::v6::ConnectionError
3277	1323
activemq::wireformat::openwire::marshal::v5::ResponseMarshaller	openwire::marshal::v6::ConnectionIdMa
3308	1354
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller	openwire::marshal::v6::ConnectionInfoM
3398	1384
activemq::wireformat::openwire::marshal::v5::SessionIdMarshaller	openwire::marshal::v6::ConsumerContro
3418	1429
activemq::wireformat::openwire::marshal::v5::ShutdownInfoMarshaller	openwire::marshal::v6::ConsumerIdMar
3488	1458
activemq::wireformat::openwire::marshal::v5::SubscriptionInfoMarshaller	openwire::marshal::v6::ConsumerInfoMa
3687	1491
activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller	openwire::marshal::v6::ControlComman
3826	1520
activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller	openwire::marshal::v6::DataArrayRespo
3854	1554
activemq::wireformat::openwire::marshal::v5::WireFormatMarshaller	openwire::marshal::v6::DataResponseM
3995	1593
activemq::wireformat::openwire::marshal::v5::XATransactionMarshaller	openwire::marshal::v6::DestinationInfoM
4059	1751
activemq::wireformat::openwire::marshal::v6::ActiveMQBinaryMessageMarshaller	openwire::marshal::v6::DiscoveryEventM
232	1765
activemq::wireformat::openwire::marshal::v6::ActiveMQBytesMessageMarshaller	openwire::marshal::v6::ExceptionRespor
268	1845
activemq::wireformat::openwire::marshal::v6::ActiveMQDestinationMarshaller	openwire::marshal::v6::FlushCommandL
356	1943
activemq::wireformat::openwire::marshal::v6::ActiveMQMapMessageMarshaller	openwire::marshal::v6::IntegerResponse
397	2097
activemq::wireformat::openwire::marshal::v6::ActiveMQMessageMarshaller	openwire::marshal::v6::JournalQueueAc
424	2162
activemq::wireformat::openwire::marshal::v6::ActiveMQObjectMessageMarshaller	openwire::marshal::v6::JournalTopicAck
469	2203
activemq::wireformat::openwire::marshal::v6::ActiveMQQueueMarshaller	openwire::marshal::v6::JournalTraceMa
514	2226
activemq::wireformat::openwire::marshal::v6::ActiveMQStreamMessageMarshaller	openwire::marshal::v6::JournalTransact
575	2245
activemq::wireformat::openwire::marshal::v6::ActiveMQTempDestinationMarshaller	openwire::marshal::v6::KeepAliveInfoM
603	2272
activemq::wireformat::openwire::marshal::v6::ActiveMQTempQueueMarshaller	openwire::marshal::v6::LastPartialComr
632	2307
activemq::wireformat::openwire::marshal::v6::ActiveMQTempTopicMarshaller	openwire::marshal::v6::LocalTransaction
661	2354

- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 826
- 2568 tightUnmarshalConstByteArray
- activemq::wireformat::openwire::marshal::v6::MessageDispatcherMarshaller, 826
- 2629
- activemq::wireformat::openwire::marshal::v6::MessageDispatcherNotificationMarshaller, 826
- 2638 activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller
- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 826
- 2687 tightUnmarshalNestedObject
- activemq::wireformat::openwire::marshal::v6::MessageMarshaller, 827
- 2721
- activemq::wireformat::openwire::marshal::v6::MessagePullMarshaller, 2897
- 2767
- activemq::wireformat::openwire::marshal::v6::NightOnBridgeStringMarshaller, 2803
- 2803 activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller
- activemq::wireformat::openwire::marshal::v6::PartialCommandMarshaller, 827
- 2925 TIME
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 432
- 3059 time
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 432
- 3091 TIMED_WAITING
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3768
- 3124 timedJoin
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3811
- 3205 timedWait
- activemq::wireformat::openwire::marshal::v6::ProducerIdMarshaller, 3811
- 3242 timeout
- activemq::wireformat::openwire::marshal::v6::ReplyToQueueIdMarshaller, 1731
- 3273
- activemq::wireformat::openwire::marshal::v6::ResponseMarshaller, 2743
- 3323 TimeoutException
- activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3787, 3788
- 3394
- activemq::wireformat::openwire::marshal::v6::SessionIdMarshaller, 3792
- 3414 decaf::util::Timer, 3792
- activemq::wireformat::openwire::marshal::v6::ShutdownInfoMarshaller, 3803
- 3476 TimerImpl
- activemq::wireformat::openwire::marshal::v6::SubscriptionInfoMarshaller, 3803
- 3695 TimerTask
- activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller, 3802
- 3846 TimerTaskHeap
- activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller, 3805
- 3866 timestamp
- activemq::wireformat::openwire::marshal::v6::WireFormatInfoMarshaller, 2532
- 3999 decaf::util::UUID, 3973
- activemq::wireformat::openwire::marshal::v6::XAPIDTransactionIdMarshaller, 3809
- 4039 decaf::util::concurrent::TimeUnit,
- tightUnmarshalBrokerError toArray
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 481
- 825 cms::CMSProperties, 1168
- tightUnmarshalByteArray decaf::util::AbstractCollection, 189
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 1192
- 825 decaf::util::concurrent::SynchronousQueue,
- tightUnmarshalCachedObject 3724
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 3134

- decaf::util::StlQueue, 3620
- decaf::util::StringTokenizer, 3670
- toBinaryString
 - decaf::lang::Integer, 2087
 - decaf::lang::Long, 2430
- toByteArray
 - decaf::io::ByteArrayOutputStream, 1029
- toDays
 - decaf::util::concurrent::TimeUnit, 3812
- toDegrees
 - decaf::lang::Math, 2511
- toDestinationOption
 - activemq::core::ActiveMQConstants, 309
- toHexFromBytes
 - activemq::wireformat::openwire::marshal::BaseDataStructureMarshaller, 828
- toHexString
 - decaf::lang::Double, 1796
 - decaf::lang::Float, 1912
 - decaf::lang::Integer, 2088
 - decaf::lang::Long, 2430
- toHours
 - decaf::util::concurrent::TimeUnit, 3812
- toMicros
 - decaf::util::concurrent::TimeUnit, 3813
- toMillis
 - decaf::util::concurrent::TimeUnit, 3813
- toMinutes
 - decaf::util::concurrent::TimeUnit, 3813
- toNanos
 - decaf::util::concurrent::TimeUnit, 3814
- toOctalString
 - decaf::lang::Integer, 2088
 - decaf::lang::Long, 2431
- TOPIC
 - cms::Destination, 1723
- TOPIC_PREFIX
 - activemq::wireformat::stomp::StompCommandConstants, 3631
- TOPIC_QUALIFIED_PREFIX
 - activemq::commands::ActiveMQDestination, 332
- toRadians
 - decaf::lang::Math, 2511
- toSeconds
 - decaf::util::concurrent::TimeUnit, 3814
- toStream
 - activemq::wireformat::stomp::StompFrame, 3637
- toString
 - activemq::commands::ActiveMQBlobMessage, 207
 - activemq::commands::ActiveMQBytesMessage, 244
- activemq::commands::ActiveMQDestination, 330
- activemq::commands::ActiveMQMapMessage, 372
- activemq::commands::ActiveMQMessage, 399
- activemq::commands::ActiveMQObjectMessage, 445
- activemq::commands::ActiveMQQueue, 486
- activemq::commands::ActiveMQStreamMessage, 547
- activemq::commands::ActiveMQTempDestination, 578
- activemq::commands::ActiveMQTempQueue, 607
- activemq::commands::ActiveMQTempTopic, 636
- activemq::commands::ActiveMQTextMessage, 666
- activemq::commands::ActiveMQTopic, 694
- activemq::commands::BaseCommand, 763
- activemq::commands::BaseDataStructure, 833
- activemq::commands::BooleanExpression, 856
- activemq::commands::BrokerId, 871
- activemq::commands::BrokerInfo, 901
- activemq::commands::Command, 1197
- activemq::commands::ConnectionControl, 1270
- activemq::commands::ConnectionError, 1298
- activemq::commands::ConnectionId, 1329
- activemq::commands::ConnectionInfo, 1359
- activemq::commands::ConsumerControl, 1404
- activemq::commands::ConsumerId, 1433
- activemq::commands::ConsumerInfo, 1464
- activemq::commands::ControlCommand, 1495
- activemq::commands::DataArrayResponse, 1530
- activemq::commands::DataResponse, 1585
- activemq::commands::DataStructure, 1663
- activemq::commands::DestinationInfo, 1730
- activemq::commands::DiscoveryEvent, 1760
- activemq::commands::ExceptionResponse, 1841
- activemq::commands::FlushCommand, 1939

- activemq::commands::IntegerResponse, 2093
- activemq::commands::JournalQueueAck, 2158
- activemq::commands::JournalTopicAck, 2186
- activemq::commands::JournalTrace, 2214
- activemq::commands::JournalTransaction, 2241
- activemq::commands::KeepAliveInfo, 2268
- activemq::commands::LastPartialCommand, 2302
- activemq::commands::LocalTransactionId, 2350
- activemq::commands::Message, 2530
- activemq::commands::MessageAck, 2563
- activemq::commands::MessageDispatch, 2597
- activemq::commands::MessageDispatchNotification, 2633
- activemq::commands::MessageId, 2666
- activemq::commands::MessagePull, 2742
- activemq::commands::NetworkBridgeFilter, 2795
- activemq::commands::PartialCommand, 2920
- activemq::commands::ProducerAck, 3038
- activemq::commands::ProducerId, 3070
- activemq::commands::ProducerInfo, 3099
- activemq::commands::RemoveInfo, 3196
- activemq::commands::RemoveSubscriptionInfo, 3225
- activemq::commands::ReplayCommand, 3253
- activemq::commands::Response, 3287
- activemq::commands::SessionId, 3382
- activemq::commands::SessionInfo, 3409
- activemq::commands::ShutdownInfo, 3472
- activemq::commands::SubscriptionInfo, 3674
- activemq::commands::TransactionId, 3821
- activemq::commands::TransactionInfo, 3849
- activemq::commands::WireFormatInfo, 3991
- activemq::commands::XATransactionId, 4034
- activemq::core::ActiveMQConstants, 309
- activemq::state::ConnectionState, 1391
- activemq::state::ConsumerState, 1492
- activemq::state::ProducerState, 3125
- activemq::state::SessionState, 3438
- activemq::state::TransactionState, 3876
- activemq::util::ActiveMQProperties, 481
- activemq::util::PrimitiveList, 2990
- activemq::util::PrimitiveMap, 3000
- activemq::util::PrimitiveValueNode, 3024
- activemq::wireformat::openwire::marshal::BaseDataStreamMarshaller, 828
- cms::CMSProperties, 1168
- decaf::io::ByteArrayOutputStream, 1030
- decaf::io::FilterOutputStream, 1902
- decaf::io::InputStream, 2050
- decaf::io::OutputStream, 2911
- decaf::lang::Boolean, 853, 854
- decaf::lang::Byte, 966
- decaf::lang::Character, 1106
- decaf::lang::CharSequence, 1136
- decaf::lang::Double, 1797
- decaf::lang::Float, 1912, 1913
- decaf::lang::Integer, 2088, 2089
- decaf::lang::Long, 2431
- decaf::lang::Short, 3446
- decaf::lang::String, 3667
- decaf::lang::Thread, 3773
- decaf::net::InetAddress, 2022
- decaf::net::ServerSocket, 3360
- decaf::net::Socket, 3518
- decaf::net::SocketImpl, 3536
- decaf::net::URI, 3931
- decaf::nio::ByteBuffer, 1054
- decaf::nio::CharBuffer, 1133
- decaf::nio::DoubleBuffer, 1818
- decaf::nio::FloatBuffer, 1934
- decaf::nio::IntBuffer, 2075
- decaf::nio::LongBuffer, 2453
- decaf::nio::ShortBuffer, 3468
- decaf::security::cert::Certificate, 1088
- decaf::util::concurrent::atomic::AtomicBoolean, 739
- decaf::util::concurrent::atomic::AtomicInteger, 745
- decaf::util::concurrent::atomic::AtomicReference, 751
- decaf::util::concurrent::locks::ReentrantLock, 3186
- decaf::util::concurrent::Semaphore, 3347
- decaf::util::concurrent::TimeUnit, 3814
- decaf::util::Date, 1668
- decaf::util::logging::Level, 2335
- decaf::util::Properties, 3134
- decaf::util::UUID, 3974
- total
 - inflate_state, 2025
- total_in
 - z_stream_s, 4062
- total_out
 - z_stream_s, 4062

- toURI
 - activemq::util::CompositeData, 1220
- toURIOption
 - activemq::core::ActiveMQConstants, 309
- toURL
 - decaf::net::URI, 3931
- Trace
 - zutil.h, 4745
- Tracec
 - zutil.h, 4745
- Tracecv
 - zutil.h, 4745
- Tracev
 - zutil.h, 4745
- Tracevv
 - zutil.h, 4745
- track
 - activemq::state::ConnectionStateTracker, 1398
- trackBack
 - activemq::state::ConnectionStateTracker, 1398
- Tracked
 - activemq::state::Tracked, 3818
- TRANSACTION_STATE_BEGIN
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_-COMMITONEPHASE
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_-COMMITTWOPHASE
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_END
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_FORGET
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_PREPARE
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_RECOVER
 - activemq::core::ActiveMQConstants, 309
- TRANSACTION_STATE_ROLLBACK
 - activemq::core::ActiveMQConstants, 309
- TransactionId
 - activemq::commands::TransactionId, 3820
- transactionId
 - activemq::commands::JournalTopicAck, 2187
 - activemq::commands::JournalTransaction, 2241
 - activemq::commands::Message, 2532
 - activemq::commands::MessageAck, 2564
 - activemq::commands::TransactionInfo, 3850
- TransactionIdMarshaller

- activemq::wireformat::openwire::marshal::v1::TransactionIdMarshaller, 3828
- activemq::wireformat::openwire::marshal::v2::TransactionIdMarshaller, 3832
- activemq::wireformat::openwire::marshal::v3::TransactionIdMarshaller, 3836
- activemq::wireformat::openwire::marshal::v4::TransactionIdMarshaller, 3840
- activemq::wireformat::openwire::marshal::v5::TransactionIdMarshaller, 3824
- activemq::wireformat::openwire::marshal::v6::TransactionIdMarshaller, 3844
- TransactionInfo
 - activemq::commands::TransactionInfo, 3848
- TransactionInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::TransactionInfoMarshaller, 3856
 - activemq::wireformat::openwire::marshal::v2::TransactionInfoMarshaller, 3872
 - activemq::wireformat::openwire::marshal::v3::TransactionInfoMarshaller, 3860
 - activemq::wireformat::openwire::marshal::v4::TransactionInfoMarshaller, 3868
 - activemq::wireformat::openwire::marshal::v5::TransactionInfoMarshaller, 3852
 - activemq::wireformat::openwire::marshal::v6::TransactionInfoMarshaller, 3864
- TransactionState
 - activemq::core::ActiveMQConstants, 308
 - activemq::state::TransactionState, 3876
- transfer
 - decaf::internal::util::concurrent::TransferQueue, 3879
 - decaf::internal::util::concurrent::TransferStack, 3881, 3882
- TransferQueue
 - decaf::internal::util::concurrent::TransferQueue, 3878
- TransferStack
 - decaf::internal::util::concurrent::TransferStack, 3881
- TransportFilter
 - activemq::transport::TransportFilter, 3893
- transportInterrupted
 - activemq::core::ActiveMQConnection, 291
 - activemq::state::ConnectionStateTracker, 1398
 - activemq::transport::DefaultTransportListener, 1705
 - activemq::transport::failover::FailoverTransportListener, 1889
 - activemq::transport::TransportFilter, 3898

- activemq::transport::TransportListener, 3901
- transportResumed
 - activemq::core::ActiveMQConnection, 291
 - activemq::transport::DefaultTransportListener, 1705
 - activemq::transport::failover::FailoverTransportListener, 1889
 - activemq::transport::TransportFilter, 3898
 - activemq::transport::TransportListener, 3901
- tree_desc
 - deflate.h, 4727
- tree_desc_s, 3905
 - dyn_tree, 3905
 - max_code, 3905
 - stat_desc, 3905
- trees.h
 - _dist_code, 4735
 - _length_code, 4735
 - base_dist, 4736
 - base_length, 4736
 - static_dtree, 4736
 - static_ltree, 4736
- TRY_FREE
 - zutil.h, 4745
- tryAcquire
 - decaf::util::concurrent::Semaphore, 3347–3349
- tryLock
 - activemq::core::MessageDispatchChannel, 2603
 - decaf::internal::util::concurrent::SynchronizableImpl, 3713
 - decaf::io::InputStream, 2051
 - decaf::io::OutputStream, 2911
 - decaf::util::AbstractCollection, 189
 - decaf::util::concurrent::ConcurrentStlMap, 1246
 - decaf::util::concurrent::locks::Lock, 2380, 2381
 - decaf::util::concurrent::locks::ReentrantLock, 3186, 3187
 - decaf::util::concurrent::Mutex, 2784
 - decaf::util::concurrent::Synchronizable, 3704
 - decaf::util::StlMap, 3612
 - decaf::util::StlQueue, 3620
- trylock
 - decaf::internal::util::concurrent::MutexImpl, 2789
- TYPE
 - inflate.h, 4732
- type
 - activemq::transport::TransportListener, 3901
 - activemq::commands::JournalTransaction, 2241
 - activemq::commands::Message, 2532
 - activemq::commands::TransactionInfo, 3850
 - TYPEDO
 - inflate.h, 4732
 - uch
 - zutil.h, 4745
 - uchf
 - zutil.h, 4745
 - uInt
 - zconf.h, 4738
 - uIntf
 - zconf.h, 4738
 - ulg
 - zutil.h, 4745
 - uLong
 - zconf.h, 4738
 - uLongf
 - zconf.h, 4738
 - uncaughtException
 - decaf::lang::Thread::UncaughtExceptionHandler, 3906
 - UnknownHostException
 - decaf::net::UnknownHostException, 3907, 3908
 - UnknownServiceException
 - decaf::net::UnknownServiceException, 3910, 3911
 - unlock
 - activemq::core::MessageDispatchChannel, 2604
 - decaf::internal::util::concurrent::MutexImpl, 2789
 - decaf::internal::util::concurrent::SynchronizableImpl, 3713
 - decaf::io::InputStream, 2051
 - decaf::io::OutputStream, 2911
 - decaf::util::AbstractCollection, 190
 - decaf::util::concurrent::ConcurrentStlMap, 1246
 - decaf::util::concurrent::Lock, 2376
 - decaf::util::concurrent::locks::Lock, 2381
 - decaf::util::concurrent::locks::ReentrantLock, 3188
 - decaf::util::concurrent::Mutex, 2784
 - decaf::util::concurrent::Synchronizable, 3705
 - decaf::util::StlMap, 3612
 - decaf::util::StlQueue, 3620
 - unmarshal

- validateQuery
 - decaf::internal::net::URIHelper, 3940
- validateScheme
 - decaf::internal::net::URIHelper, 3940
- validateSimple
 - decaf::internal::net::URIEncoderDecoder, 3933
- validateSsp
 - decaf::internal::net::URIHelper, 3940
- validateUserinfo
 - decaf::internal::net::URIHelper, 3941
- value
 - activemq::commands::BrokerId, 871
 - activemq::commands::ConnectionId, 1330
 - activemq::commands::ConsumerId, 1434
 - activemq::commands::LocalTransactionId, 2350
 - activemq::commands::ProducerId, 3071
 - activemq::commands::SessionId, 3382
- valueOf
 - decaf::lang::Boolean, 854
 - decaf::lang::Byte, 966, 967
 - decaf::lang::Character, 1106
 - decaf::lang::Double, 1797
 - decaf::lang::Float, 1913
 - decaf::lang::Integer, 2089, 2090
 - decaf::lang::Long, 2432
 - decaf::lang::Short, 3447
 - decaf::util::concurrent::TimeUnit, 3815
- values
 - decaf::util::concurrent::ConcurrentStlMap, 1246
 - decaf::util::concurrent::TimeUnit, 3816
 - decaf::util::Map, 2470
 - decaf::util::StlMap, 3612
- variant
 - decaf::util::UUID, 3974
- verify
 - decaf::security::cert::Certificate, 1088
- version
 - decaf::util::UUID, 3974
- visit
 - activemq::commands::BrokerError, 866
 - activemq::commands::BrokerInfo, 902
 - activemq::commands::Command, 1198
 - activemq::commands::ConnectionControl, 1271
 - activemq::commands::ConnectionError, 1298
 - activemq::commands::ConnectionInfo, 1359
 - activemq::commands::ConsumerControl, 1404
 - activemq::commands::ConsumerInfo, 1465
 - activemq::commands::ControlCommand, 1495
 - activemq::commands::DestinationInfo, 1730
 - activemq::commands::FlushCommand, 1939
 - activemq::commands::KeepAliveInfo, 2268
 - activemq::commands::Message, 2530
 - activemq::commands::MessageAck, 2563
 - activemq::commands::MessageDispatch, 2597
 - activemq::commands::MessageDispatchNotification, 2633
 - activemq::commands::MessagePull, 2742
 - activemq::commands::ProducerAck, 3038
 - activemq::commands::ProducerInfo, 3099
 - activemq::commands::RemoveInfo, 3196
 - activemq::commands::RemoveSubscriptionInfo, 3225
 - activemq::commands::ReplayCommand, 3253
 - activemq::commands::Response, 3287
 - activemq::commands::SessionInfo, 3409
 - activemq::commands::ShutdownInfo, 3472
 - activemq::commands::TransactionInfo, 3850
 - activemq::commands::WireFormatInfo, 3991
- voidp
 - zconf.h, 4738
- voidpc
 - zconf.h, 4738
- voidpf
 - zconf.h, 4738
- w_bits
 - internal_state, 2120
- w_mask
 - internal_state, 2120
- w_size
 - internal_state, 2120
- wait
 - activemq::core::MessageDispatchChannel, 2604, 2605
 - decaf::internal::util::concurrent::ConditionImpl, 1258
 - decaf::internal::util::concurrent::SynchronizableImpl, 3713, 3714
 - decaf::io::InputStream, 2051, 2052
 - decaf::io::OutputStream, 2911, 2912
 - decaf::util::AbstractCollection, 190, 191
 - decaf::util::concurrent::ConcurrentStlMap, 1246, 1247
 - decaf::util::concurrent::Mutex, 2785, 2786

- decaf::util::concurrent::Synchronizable, 3706, 3708, 3709
- decaf::util::StlMap, 3612, 3613
- decaf::util::StlQueue, 3621, 3622
- WAIT_INFINITE
 - Concurrent.h, 4893
- waitForSpace
 - activemq::util::MemoryUsage, 2514
 - activemq::util::Usage, 3965
- WAITING
 - decaf::lang::Thread, 3768
- wakeup
 - activemq::core::ActiveMQSession, 532
 - activemq::core::ActiveMQSessionExecutor, 536
 - activemq::threads::CompositeTaskRunner, 1225
 - activemq::threads::DedicatedTaskRunner, 1672
 - activemq::threads::TaskRunner, 3736
- want
 - gz_state, 1977
- Warn
 - decaf::util::logging, 176
- warn
 - decaf::util::logging::SimpleLogger, 3502
- WARNING
 - decaf::util::logging::Level, 2336
- warning
 - decaf::util::logging::Logger, 2396
- was
 - inflate_state, 2025
- wasPrepared
 - activemq::commands::JournalTransaction, 2241
- wbits
 - inflate_state, 2025
- what
 - cms::CMSException, 1162
 - decaf::lang::Exception, 1837
- whave
 - inflate_state, 2025
- WIN_INIT
 - deflate.h, 4727
- window
 - inflate_state, 2025
 - internal_state, 2120
- window_size
 - internal_state, 2120
- windowSize
 - activemq::commands::ProducerInfo, 3100
- WireFormatInfo
 - activemq::commands::WireFormatInfo, 3984
- WireFormatInfoMarshaller
 - activemq::wireformat::openwire::marshal::v1::WireFormatInfo, 4009
 - activemq::wireformat::openwire::marshal::v2::WireFormatInfo, 4001
 - activemq::wireformat::openwire::marshal::v3::WireFormatInfo, 4013
 - activemq::wireformat::openwire::marshal::v4::WireFormatInfo, 4005
 - activemq::wireformat::openwire::marshal::v5::WireFormatInfo, 3993
 - activemq::wireformat::openwire::marshal::v6::WireFormatInfo, 3997
- WireFormatNegotiator
 - activemq::wireformat::WireFormatNegotiator, 4016
- wnext
 - inflate_state, 2025
- work
 - inflate_state, 2025
- wrap
 - decaf::nio::ByteBuffer, 1054
 - decaf::nio::CharBuffer, 1133
 - decaf::nio::DoubleBuffer, 1818, 1819
 - decaf::nio::FloatBuffer, 1934
 - decaf::nio::IntBuffer, 2075
 - decaf::nio::LongBuffer, 2453
 - decaf::nio::ShortBuffer, 3468
 - inflate_state, 2025
 - internal_state, 2120
- write
 - decaf::internal::net::ssl::openssl::OpenSSLSocket, 2869
 - decaf::internal::net::tcp::TcpSocket, 3746
 - decaf::internal::util::ByteArrayAdapter, 989
 - decaf::io::OutputStream, 2913, 2914
 - decaf::io::Writer, 4024–4026
- WRITE_FAILURE
 - decaf::util::logging::ErrorManager, 1829
- writeBoolean
 - activemq::commands::ActiveMQBytesMessage, 244
 - activemq::commands::ActiveMQStreamMessage, 547
 - activemq::wireformat::openwire::utils::BooleanStream, 859
 - cms::BytesMessage, 1065
 - cms::StreamMessage, 3660
 - decaf::io::DataOutput, 1575
 - decaf::io::DataOutputStream, 1581
- writeByte
 - activemq::commands::ActiveMQBytesMessage, 244

- activemq::commands::ActiveMQStreamMessage, 547
- cms::BytesMessage, 1066
- cms::StreamMessage, 3660
- decaf::io::DataOutput, 1575
- decaf::io::DataOutputStream, 1582
- writeBytes
 - activemq::commands::ActiveMQBytesMessage, 245
 - activemq::commands::ActiveMQStreamMessage, 548
 - cms::BytesMessage, 1066
 - cms::StreamMessage, 3661
 - decaf::io::DataOutput, 1575
 - decaf::io::DataOutputStream, 1582
- writeChar
 - activemq::commands::ActiveMQBytesMessage, 245
 - activemq::commands::ActiveMQStreamMessage, 548
 - cms::BytesMessage, 1067
 - cms::StreamMessage, 3661
 - decaf::io::DataOutput, 1576
 - decaf::io::DataOutputStream, 1582
- writeChars
 - decaf::io::DataOutput, 1576
 - decaf::io::DataOutputStream, 1582
- WriteChecker
 - activemq::transport::inactivity::InactivityMonitor, 2007
 - activemq::transport::inactivity::WriteChecker, 4020
- writeDouble
 - activemq::commands::ActiveMQBytesMessage, 246
 - activemq::commands::ActiveMQStreamMessage, 549
 - cms::BytesMessage, 1067
 - cms::StreamMessage, 3662
 - decaf::io::DataOutput, 1576
 - decaf::io::DataOutputStream, 1582
- writeFloat
 - activemq::commands::ActiveMQBytesMessage, 246
 - activemq::commands::ActiveMQStreamMessage, 549
 - cms::BytesMessage, 1067
 - cms::StreamMessage, 3662
 - decaf::io::DataOutput, 1577
 - decaf::io::DataOutputStream, 1582
- writeInt
 - activemq::commands::ActiveMQBytesMessage, 246
- activemq::commands::ActiveMQStreamMessage, 549
- cms::BytesMessage, 1068
- cms::StreamMessage, 3662
- decaf::io::DataOutput, 1577
- decaf::io::DataOutputStream, 1582
- writeLock
 - decaf::util::concurrent::locks::ReadWriteLock, 3173
- writeLong
 - activemq::commands::ActiveMQBytesMessage, 247
 - activemq::commands::ActiveMQStreamMessage, 549
 - cms::BytesMessage, 1068
 - cms::StreamMessage, 3663
 - decaf::io::DataOutput, 1577
 - decaf::io::DataOutputStream, 1582
- Writer
 - decaf::io::Writer, 4022
- writeShort
 - activemq::commands::ActiveMQBytesMessage, 247
 - activemq::commands::ActiveMQStreamMessage, 550
 - cms::BytesMessage, 1068
 - cms::StreamMessage, 3663
 - decaf::io::DataOutput, 1577
 - decaf::io::DataOutputStream, 1582
- writeString
 - activemq::commands::ActiveMQBytesMessage, 247
 - activemq::commands::ActiveMQStreamMessage, 550
 - activemq::util::MarshallingSupport, 2495
 - cms::BytesMessage, 1069
 - cms::StreamMessage, 3663
- writeString16
 - activemq::util::MarshallingSupport, 2496
- writeString32
 - activemq::util::MarshallingSupport, 2496
- writeTo
 - decaf::io::ByteArrayOutputStream, 1030
- writeUnsignedShort
 - activemq::commands::ActiveMQBytesMessage, 247
 - activemq::commands::ActiveMQStreamMessage, 550
 - cms::BytesMessage, 1069
 - cms::StreamMessage, 3664
 - decaf::io::DataOutput, 1578
 - decaf::io::DataOutputStream, 1582
- writeUTF

activemq::commands::ActiveMQBytesMessage,	z_errmsg
248	zutil.h, 4745
cms::BytesMessage, 1069	Z_ERRNO
decaf::io::DataOutput, 1578	zlib.h, 4742
decaf::io::DataOutputStream, 1582	Z_FILTERED
written	zlib.h, 4742
decaf::io::DataOutputStream, 1582	Z_FINISH
wsiz	zlib.h, 4742
inflate_state, 2025	Z_FIXED
	zlib.h, 4742
XATransactionId	Z_FULL_FLUSH
activemq::commands::XATransactionId,	zlib.h, 4742
4032	Z_HUFFMAN_ONLY
XATransactionIdMarshaller	zlib.h, 4742
activemq::wireformat::openwire::marshal::v1::XATransactionIdMarshaller,	Z_INFLATE_BLOCK
4049	zlib.h, 4742
activemq::wireformat::openwire::marshal::v2::XATransactionIdMarshaller,	Z_INFLATE_DICT
4041	zlib.h, 4742
activemq::wireformat::openwire::marshal::v3::XATransactionIdMarshaller,	Z_INFLATE_COMPRESSION
4053	zlib.h, 4742
activemq::wireformat::openwire::marshal::v4::XATransactionIdMarshaller,	Z_INFLATE_FLUSH
4045	zlib.h, 4742
activemq::wireformat::openwire::marshal::v5::XATransactionIdMarshaller,	Z_INFLATE_TRANSACTION
4057	zlib.h, 4742
activemq::wireformat::openwire::marshal::v6::XATransactionIdMarshaller,	Z_INFLATE_TRANSACTION
4037	zconf.h, 4738
xflags	z_off_t
gz_header_s, 1975	zconf.h, 4738
XMLFormatter	Z_OK
decaf::util::logging::XMLFormatter, 4060	zlib.h, 4742
	Z_PARTIAL_FLUSH
yield	zlib.h, 4742
decaf::lang::Thread, 3773	Z_RLE
	zlib.h, 4742
Z_ASCII	z_stream
zlib.h, 4742	zlib.h, 4742
Z_BEST_COMPRESSION	Z_STREAM_END
zlib.h, 4742	zlib.h, 4742
Z_BEST_SPEED	Z_STREAM_ERROR
zlib.h, 4742	zlib.h, 4742
Z_BINARY	z_stream_s, 4062
zlib.h, 4742	adler, 4062
Z_BLOCK	avail_in, 4062
zlib.h, 4742	avail_out, 4062
Z_BUF_ERROR	data_type, 4062
zlib.h, 4742	msg, 4062
Z_DATA_ERROR	next_in, 4062
zlib.h, 4742	next_out, 4062
Z_DEFAULT_COMPRESSION	opaque, 4062
zlib.h, 4742	reserved, 4062
Z_DEFAULT_STRATEGY	state, 4062
zlib.h, 4742	total_in, 4062
Z_DEFLATED	total_out, 4062
zlib.h, 4742	zalloc, 4062

- zfree, 4062
- z_streamp
 - zlib.h, 4742
- Z_SYNC_FLUSH
 - zlib.h, 4742
- Z_TEXT
 - zlib.h, 4742
- Z_TREES
 - zlib.h, 4742
- Z_UNKNOWN
 - zlib.h, 4742
- Z_VERSION_ERROR
 - zlib.h, 4742
- ZALLOC
 - zutil.h, 4745
- zalloc
 - z_stream_s, 4062
- zconf.h
 - Byte, 4738
 - Bytef, 4738
 - charf, 4738
 - const, 4738
 - intf, 4738
 - MAX_MEM_LEVEL, 4738
 - MAX_WBITS, 4738
 - OF, 4738
 - SEEK_CUR, 4738
 - SEEK_END, 4738
 - SEEK_SET, 4738
 - uInt, 4738
 - uIntf, 4738
 - uLong, 4738
 - uLongf, 4738
 - voidp, 4738
 - voidpc, 4738
 - voidpf, 4738
 - z_off64_t, 4738
 - z_off_t, 4738
 - ZEXTERN, 4738
- ZEXTERN
 - zconf.h, 4738
- ZFREE
 - zutil.h, 4745
- zfree
 - z_stream_s, 4062
- ZipException
 - decaf::util::zip::ZipException, 4064, 4065
- zlib.h
 - deflateInit, 4741
 - deflateInit2, 4741
 - gz_header, 4742
 - gz_headerp, 4742
 - gzFile, 4742
 - inflateBackInit, 4741
 - inflateInit, 4741
 - inflateInit2, 4742
 - OF, 4742
 - Z_ASCII, 4742
 - Z_BEST_COMPRESSION, 4742
 - Z_BEST_SPEED, 4742
 - Z_BINARY, 4742
 - Z_BLOCK, 4742
 - Z_BUF_ERROR, 4742
 - Z_DATA_ERROR, 4742
 - Z_DEFAULT_COMPRESSION, 4742
 - Z_DEFAULT_STRATEGY, 4742
 - Z_DEFLATED, 4742
 - Z_ERRNO, 4742
 - Z_FILTERED, 4742
 - Z_FINISH, 4742
 - Z_FIXED, 4742
 - Z_FULL_FLUSH, 4742
 - Z_HUFFMAN_ONLY, 4742
 - Z_MEM_ERROR, 4742
 - Z_NEED_DICT, 4742
 - Z_NO_COMPRESSION, 4742
 - Z_NO_FLUSH, 4742
 - Z_NULL, 4742
 - Z_OK, 4742
 - Z_PARTIAL_FLUSH, 4742
 - Z_RLE, 4742
 - z_stream, 4742
 - Z_STREAM_END, 4742
 - Z_STREAM_ERROR, 4742
 - z_streamp, 4742
 - Z_SYNC_FLUSH, 4742
 - Z_TEXT, 4742
 - Z_TREES, 4742
 - Z_UNKNOWN, 4742
 - Z_VERSION_ERROR, 4742
 - ZLIB_VER_MAJOR, 4742
 - ZLIB_VER_MINOR, 4742
 - ZLIB_VER_REVISION, 4742
 - ZLIB_VER_SUBREVISION, 4742
 - ZLIB_VERNUM, 4742
 - ZLIB_VERSION, 4742
 - zlib_version, 4742
- ZLIB_INTERNAL
 - gzguts.h, 4729
 - zutil.h, 4745
- ZLIB_VER_MAJOR
 - zlib.h, 4742
- ZLIB_VER_MINOR
 - zlib.h, 4742
- ZLIB_VER_REVISION
 - zlib.h, 4742
- ZLIB_VER_SUBREVISION
 - zlib.h, 4742

ZLIB_VERNUM
 zlib.h, 4742
ZLIB_VERSION
 zlib.h, 4742
zlib_version
 zlib.h, 4742
zstrerror
 gzguts.h, 4729
zutil.h
 Assert, 4745
 DEF_MEM_LEVEL, 4745
 DEF_WBITS, 4745
 DYN_TREES, 4745
 ERR_MSG, 4745
 ERR_RETURN, 4745
 F_OPEN, 4745
 MAX_MATCH, 4745
 MIN_MATCH, 4745
 OF, 4745
 OS_CODE, 4745
 PRESET_DICT, 4745
 STATIC_TREES, 4745
 STORED_BLOCK, 4745
 Trace, 4745
 Tracec, 4745
 Tracecv, 4745
 Tracev, 4745
 Tracevv, 4745
 TRY_FREE, 4745
 uch, 4745
 uchf, 4745
 ulg, 4745
 ush, 4745
 ushf, 4745
 z_errmsg, 4745
 ZALLOC, 4745
 ZFREE, 4745
 ZLIB_INTERNAL, 4745