

globus gram job manager callout error Reference Manual

2.1

Generated by Doxygen 1.4.7

Thu Jan 26 15:39:53 2012

Contents

1	globus gram job manager callout error Module Index	1
2	globus gram job manager callout error Module Documentation	1

1 globus gram job manager callout error Module Index

1.1 globus gram job manager callout error Modules

Here is a list of all modules:

Activation	1
Datatypes	2

2 globus gram job manager callout error Module Documentation

2.1 Activation

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation.

Defines

- `#define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE`

2.1.1 Detailed Description

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation.

Before any Globus GRAM Jobmanager Callout Error API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function returns `GLOBUS_SUCCESS` if the Globus GRAM Jobmanager Callout Error API was successfully initialized, and you are therefore allowed to subsequently call Globus GRAM Jobmanager Callout Error API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GRAM Jobmanager Callout Error API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function should be called once for each time Globus GRAM Jobmanager Callout Error API was activated.

2.1.2 Define Documentation

2.1.2.1 `#define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE`

Module descriptor.

2.2 Datatypes

Enumerations

- enum globus_gram_jobmanager_callout_error_t {
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS = 0,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR = 1,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED = 2,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB = 3,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE = 4,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST = 5 }

2.2.1 Enumeration Type Documentation

2.2.1.1 enum globus_gram_jobmanager_callout_error_t

GRAM Jobmanager Callout Error codes.

Enumerator:

- GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS*** Credentials not accepted.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR*** Authorization system mis-configured.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED*** Authorization denied.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB*** Authorization denied - invalid job id.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE***
Authorization denied - executable not allowed.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST*** Last marker - never used.

Index

Activation, 1

Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
AUTHZ_DENIED

globus_gram_jobmanager_callout_error_-
datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
AUTHZ_DENIED_BAD_EXECUTABLE

globus_gram_jobmanager_callout_error_-
datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
AUTHZ_DENIED_INVALID_JOB

globus_gram_jobmanager_callout_error_-
datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
AUTHZ_SYSTEM_ERROR

globus_gram_jobmanager_callout_error_-
datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
BAD_CREDS

globus_gram_jobmanager_callout_error_-
datatypes, 2

globus_gram_jobmanager_callout_error_activation

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_ERROR_MODULE, 1

globus_gram_jobmanager_callout_error_datatypes

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_AUTHZ_DENIED, 2

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_AUTHZ_DENIED_BAD_-
EXECUTABLE, 2

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_AUTHZ_DENIED_INVALID_-
JOB, 2

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_AUTHZ_SYSTEM_ERROR,
2

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_BAD_CREDS, 2

GLOBUS_GRAM_JOBMANAGER_-
CALLOUT_ERROR_LAST, 2

globus_gram_jobmanager_callout_error_t, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
ERROR_LAST

globus_gram_jobmanager_callout_error_-
datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_-
ERROR_MODULE

globus_gram_jobmanager_callout_error_-
activation, 1

globus_gram_jobmanager_callout_error_t

globus_gram_jobmanager_callout_error_-
datatypes, 2