

globus gridmap callout error

1.2

Generated by Doxygen 1.6.1

Thu Jan 26 15:51:10 2012

Contents

1	Module Index	1
1.1	Modules	1
2	Module Documentation	1
2.1	Activation	1
2.1.1	Detailed Description	1
2.1.2	Define Documentation	2
2.2	Datatypes	2
2.2.1	Enumeration Type Documentation	2

1 Module Index

1.1 Modules

Here is a list of all modules:

Activation	1
Datatypes	2

2 Module Documentation

2.1 Activation

The Globus Gridmap Callout Error API uses standard Globus module activation and deactivation.

Defines

- `#define GLOBUS_GRIDMAP_CALLOUT_ERROR_MODULE`

2.1.1 Detailed Description

The Globus Gridmap Callout Error API uses standard Globus module activation and deactivation. Before any Globus Gridmap Callout Error API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GRIDMAP_CALLOUT_ERROR_MODULE)
```

This function returns `GLOBUS_SUCCESS` if the Globus Gridmap Callout Error API was successfully initialized, and you are therefore allowed to subsequently call Globus Gridmap Callout Error API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus Gridmap Callout Error API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GRIDMAP_CALLOUT_ERROR_MODULE)
```

This function should be called once for each time Globus Gridmap Callout Error API was activated.

2.1.2 Define Documentation

2.1.2.1 #define GLOBUS_GRIDMAP_CALLOUT_ERROR_MODULE

Module descriptor.

2.2 Datatypes

Enumerations

- enum globus_gridmap_callout_error_t {
 GLOBUS_GRIDMAP_CALLOUT_LOOKUP_FAILED = 0,
 GLOBUS_GRIDMAP_CALLOUT_GSSAPI_ERROR = 1,
 GLOBUS_GRIDMAP_CALLOUT_BUFFER_TOO_SMALL = 2,
 GLOBUS_GRIDMAP_CALLOUT_ERROR_LAST = 3 }

2.2.1 Enumeration Type Documentation

2.2.1.1 enum globus_gridmap_callout_error_t

Gridmap Callout Error codes.

Enumerator:

- GLOBUS_GRIDMAP_CALLOUT_LOOKUP_FAILED** Gridmap lookup failed.
- GLOBUS_GRIDMAP_CALLOUT_GSSAPI_ERROR** GSSAPI error.
- GLOBUS_GRIDMAP_CALLOUT_BUFFER_TOO_SMALL** Buffer too small.
- GLOBUS_GRIDMAP_CALLOUT_ERROR_LAST** Last marker - never used.

Index

Activation, 1

Datatypes, 2

GLOBUS_GRIDMAP_CALLOUT_BUFFER_TOO_-
SMALL

globus_gridmap_callout_error_datatypes, 2

globus_gridmap_callout_error_activation

GLOBUS_GRIDMAP_CALLOUT_ERROR_-
MODULE, 1

globus_gridmap_callout_error_datatypes

GLOBUS_GRIDMAP_CALLOUT_BUFFER_-
TOO_SMALL, 2

GLOBUS_GRIDMAP_CALLOUT_ERROR_-
LAST, 2

globus_gridmap_callout_error_t, 2

GLOBUS_GRIDMAP_CALLOUT_GSSAPI_-
ERROR, 2

GLOBUS_GRIDMAP_CALLOUT_LOOKUP_-
FAILED, 2

GLOBUS_GRIDMAP_CALLOUT_ERROR_LAST

globus_gridmap_callout_error_datatypes, 2

GLOBUS_GRIDMAP_CALLOUT_ERROR_-
MODULE

globus_gridmap_callout_error_activation, 1

globus_gridmap_callout_error_t

globus_gridmap_callout_error_datatypes, 2

GLOBUS_GRIDMAP_CALLOUT_GSSAPI_ERROR

globus_gridmap_callout_error_datatypes, 2

GLOBUS_GRIDMAP_CALLOUT_LOOKUP_-
FAILED

globus_gridmap_callout_error_datatypes, 2